PingAuthorize

July 1, 2025



PINGAUTHORIZE Version: 9.3

Copyright

All product technical documentation is Ping Identity Corporation 1001 17th Street, Suite 100 Denver, CO 80202 U.S.A.

Refer to https://docs.pingidentity.com for the most current product documentation.

Trademark

Ping Identity, the Ping Identity logo, PingAccess, PingFederate, PingID, PingDirectory, PingDataGovernance, PingIntelligence, and PingOne are registered trademarks of Ping Identity Corporation ("Ping Identity"). All other trademarks or registered trademarks are the property of their respective owners.

Disclaimer

The information provided in Ping Identity product documentation is provided "as is" without warranty of any kind. Ping Identity disclaims all warranties, either express or implied, including the warranties of merchantability and fitness for a particular purpose. In no event shall Ping Identity or its suppliers be liable for any damages whatsoever including direct, indirect, incidental, consequential, loss of business profits or special damages, even if Ping Identity or its suppliers have been advised of the possibility of such damages. Some states do not allow the exclusion or limitation of liability for consequential or incidental damages so the foregoing limitation may not apply.

Table of Contents

PingAuthorize	11
Release Notes	14
Introduction to PingAuthorize	44
PingAuthorize architectural overview	
Getting started with PingAuthorize (tutorials)	
Using the tutorials	
Importing default policies.	
Configuring fine-grained access control for an API	
Configuring attribute-based access control for API resources	
Tutorial (optional): Creating SCIM policies	101
Installing PingAuthorize.	121
Docker deployment	123
Deployment requirements when using Docker	123
Deploying PingAuthorize Server and Policy Editor using Docker.	124
Post-setup steps (Docker deployment)	127
Next steps	128
Manual installation	128
Before you install manually	128
System requirements	129
About license keys	130
Creating a Java installation dedicated to PingAuthorize	131
Preparing a Linux environment	132
Obtaining the installation packages	136
Setting up a PostgreSQL database	136
Installing the server and the Policy Editor manually	137
Installing the server manually	138
Installing the Policy Editor manually	142
Installing the Policy Editor interactively	142
Installing the Policy Editor noninteractively	147
Clustering and scaling	157
Post-setup steps (manual installation)	157
Next steps	158
Signing on to the administrative console	158
Signing on to the Policy Editor	160
Changing the Policy Editor authentication mode	160
Configuring an OIDC provider for single sign-on requests from PingAuthorize	162
Uninstalling PingAuthorize	180
Upgrading PingAuthorize	181
Upgrade considerations	183
Upgrade considerations introduced in PingAuthorize 8.x	184

Docker upgrades	188
Manual upgrades	189
Policy-related upgrades	192
Backing up policies	192
Upgrading the Trust Framework and policies	193
Upgrading a PostgreSQL policy database	194
PingAuthorize Integrations	195
Apigee API gateway integration	198
Setting up PingAuthorize	198
Configuring Apigee	199
Troubleshooting the Apigee integration	208
Kong API gateway integration	211
Preparing PingAuthorize for Kong Gateway integration.	211
Setting up Kong Gateway	212
Troubleshooting the Kong Gateway integration	218
MuleSoft API gateway integration	220
Deploying the custom MuleSoft policy for PingAuthorize	221
Applying the custom MuleSoft policy for PingAuthorize	222
PingAuthorize Server Administration Guide	227
Running PingAuthorize Server	229
Starting PingAuthorize Server	229
Running PingAuthorize Server as a foreground process	229
Starting PingAuthorize Server at boot time (Unix/Linux)	229
Starting PingAuthorize Server at boot time (Windows)	231
Registering PingAuthorize Server as a Windows service	
Running multiple service instances	231
Deregistering and uninstalling services	232
Log files for Windows services.	232
Starting PingAuthorize Policy Editor	232
Stopping PingAuthorize Server	236
Stopping PingAuthorize Policy Editor	236
Restarting PingAuthorize Server	237
About the API security gateway	237
API gateway request and response flow	237
Gateway configuration basics	238
API security gateway authentication	239
API security gateway policy requests	241
API gateway policy request attributes	242
Endpoint configuration properties that affect policy requests	246
Path parameters	247
API security gateway HTTP 1.1 support	248
Gateway error templates	249
About the Sideband API	252
API gateway integration	252

Sideband API configuration basics	255
Authenticating to the Sideband API	256
API server request authentication	258
Sideband API policy requests	260
Sideband API policy request attributes	260
Sideband API Endpoint configuration properties	264
Path parameters	265
Request context configuration	266
Sideband access token validation	267
Sideband error templates	268
About the SCIM service	270
SCIM API request and response flow	270
SCIM configuration basics	271
SCIM endpoints	275
SCIM authentication	275
SCIM policy requests	276
Policy request attributes	276
About SCIM searches	280
SCIM search policy processing	280
Using paged SCIM searches	282
Lookthrough limit for SCIM searches	285
Disabling the SCIM REST API	286
About the SCIM user store	286
Defining the LDAP user store	288
Defining the LDAP user store with create-initial-config	288
Defining the LDAP user store manually	289
Location management for load balancing	291
Automatic backend LDAP server discovery	292
Joining a PingAuthorize Server to an existing PingDirectory Server topology	293
Joining a topology at setup	293
Joining a topology with manage-topology	294
Configuring a load-balancing algorithm with an LDAP external template	295
Configuring automatic backend LDAP server discovery	296
LDAP health checks	298
Configuring a health check using dsconfig	299
Connecting non-LDAP data stores	302
Managing Server SDK Extensions	302
About the Authorization Policy Decision APIs	304
JSON PDP API request and response flow	305
Authenticating to the JSON PDP API	312
XACML-JSON PDP API request and response flow	314
Policy Editor configuration	327
Specifying custom configuration with an options file	328
Configuring a key store for a policy information provider	329

Example: Configuring a trust store for a policy information provider	330
Configuring the Policy Editor with runtime environment variables	332
Changing the default JWT claim for the OIDC user ID	335
Configuring the JWKS endpoint cache	337
Configuring Trust Framework attribute caching for development	339
Configuring Policy Editor security headers	341
Manage policy database credentials	342
Setting database credentials at initial setup	343
Changing database credentials	344
Specifying database credentials when you start the GUI	345
Docker: Setting the initial database credentials.	346
Docker: Changing database credentials	346
Configuring SpEL java classes for value processing	347
Setting the request list length for Decision Visualizer	350
HTTP caching	351
Policy administration	352
About the Trust Framework	352
Environment-specific Trust Framework attributes	353
Creating policies in a development environment	359
Configuring external PDP mode	360
Changing the active policy branch	362
Default and example policies	363
Importing and exporting policies	363
Exporting a policy deployment package	366
Using the Deployment Manager	367
Setting up an Amazon S3 deployment package store	369
Configuring the Policy Editor to publish to a deployment package store	371
Publishing to a deployment package store	374
Adding a filesystem deployment package store	376
Adding an Amazon S3 deployment package store to PingAuthorize	378
Adding an Azure deployment package store	381
Prepare policies for production	383
Using policies in a production environment	386
Policy database backups	389
Restoring a policy database from a backup	390
Policy application management with signed deployment packages	392
Configuring Trust Framework attribute caching for production	397
User profile availability in policies	401
Access token validators	403
Access token validator types	405
Handling signed JWTs	412
Handling signed and encrypted JWTs	414
Token resource lookup methods	416

Server configuration	418
Administration accounts	418
About the dsconfig tool	418
PingAuthorize administrative console	419
About the configuration audit log	420
About the config-diff tool	420
Certificates	421
Replacing the server certificate	422
Preparing a new keystore with the replacement key pair	422
Importing earlier trusted certificates into the new keystore	424
Updating the server configuration to use the new certificate	425
Replacing the key store and trust store files	426
Retiring the previous certificate	426
Listener certificates.	426
Replacing listener certificates	427
X.509 certificates	430
Certificate subject DNs	431
Certificate key pairs	432
Certificate extensions	433
Certificate chains	435
About representing certificates, private keys, and certificate signi	וg
requests.	436
Certificate trust	436
Keystores and truststores	438
Transport Layer Security (TLS).	439
TLS handshakes	440
Key agreement	442
LDAP StartTLS extended operation	442
About the manage-certificates tool.	443
Available manage-certificates subcommands	443
Using manage-certificates as a simple certification authority	444
Common manage-certificates arguments	447
Listing the certificates in a keystore	448
Generating self-signed certificates	451
Generating certificate signing requests	456
Importing signed and trusted certificates	459
Exporting certificates	461
Enabling TLS support during server setup	464
Enabling TLS support after setup	466
Configuring key and trust manager providers	466
Configuring TLS connection handlers	467
Updating the topology registry	468
Troubleshooting TLS-related issues	469
	409
	-70

About manage-certificates check-certificate-usability	471
Idapsearch for TLS-related arguments	474
Using low-level TLS debugging	479
Policy Decision Service configuration	480
Configuring the Decision Response View	480
Configuring a user store	482
Configuring Access Token Validation	483
Configure PingOne to use SSO for the administrative console	484
Configuring traffic through a load balancer.	486
Configuring logging.	488
Enable detailed logging	489
Example: PingAuthorize Server configuration with dsconfig	492
Configuring the PingAuthorize User Store	492
Configuring the PingAuthorize OAuth subject search	493
Deployment automation and server profiles	494
Variable substitution	495
Layout of a server profile	496
About the manage-profile tool	498
Common manage-profile workflows	500
Server profiles in a pets service model	504
Server status	504
Server availability	505
User Store Availability gauge	506
Endpoint Average Response Time (Milliseconds) gauge	507
HTTP Processing (Percent) gauge	508
Policy Decision Service Availability gauge	509
Example: auto-healing for unavailable servers	509
Available gauges	510
Common alarms	513
Manage monitoring	515
Profiling server performance using the Stats Logger	516
Logging HTTP performance statistics using a Periodic Stats Logger	518
StatsD monitoring endpoint	518
Sending metrics to Splunk	520
Managing HTTP correlation IDs	520
About HTTP correlation IDs	520
Enabling or disabling correlation ID support	521
Configuring the correlation ID response header	522
How the server manages correlation IDs	522
Command-line tools	524
Saving command options in a file	527
Creating a tools properties file	528
Evaluation priority of command-line options	529
Sample dsconfig batch files	530

Running task-based tools	531
About the layout of the PingAuthorize Server folders	532
About the layout of the Policy Editor folders	534
PingAuthorize Policy Administration Guide	534
	536
Version control (Branch Manager)	537
Creating a new top-level branch	537
Creating a subbranch from a commit	538
	538
Deleting a branch	539
Merging branches	539
Reverting branch changes	540
Commiting changes	541
Generating snapshots	541
Partial snapshot export and merging	542
Creating a partial snapshot export	542
Merging a partial snapshot	542
Creating a deployment package	543
Deleting a deployment package	544
	544
Self-governance use cases	545
Self-governance Trust Framework	547
Importing a self-governance policy snapshot.	553
Trust Framework	554
Domains (Authorization Policy Decision APIs only)	554
Services	554
Connecting a service	555
Common settings	557
HTTP services	558
LDAP services	561
	562
Attributes	565
Creating an attribute	565
Attribute name, description, and location	565
Resolvers	566
Attribute caching	570
Value settings	571
Attribute interpolation	574
Conditions	574
Adding a named condition	579
-	580
Identity classifications and IdP support	581
	581
Copying Policy Editor entities	586


Trust Framework testing	588
Viewing dependents	589
Policy management	590
Policy sets, policies, and rules	591
Creating policies and policy sets	591
Adding targets to a policy	592
Conditional targets (Applies to)	594
Statements	595
Provided statements	597
Custom statements	609
Rules and combining algorithms	609
Rule structure	611
Policy testing	614
Visualizing a policy decision response	616
Repeating policies and attributes	618
Policy solutions	620
Use case: Using consent to determine access to a resource	620
Getting a path component from the request URL	621
Getting the requestor identifier from the access token	626
Searching for consent granted by resource owner to requestor	626
Getting consent status from the consent record	631
Creating a policy to check consent and then permit or deny access	632
Use case: Using consent to change a response	636
Creating a policy to check consent and then change the server response .	637
Use case: Using a SCIM resource type or a policy request action to control behavior.	643
Getting the SCIM resource type and the action being executed	644
Creating a policy to permit or deny the creation of resources	646
Creating a policy to control the set of actions for a specific resource	648
Creating a policy to restrict the ability to delete based on resource type .	651
Creating a policy to dynamically modify a resource based on the SCIM resou	irce
type	653
Restricting the modification of attributes	656
Allowing attributes to be modified by administrators	657
Adding attributes to an allow list	657
Test Suite	658
Management REST API documentation	661
Troubleshooting PingAuthorize Server	661
Working with the collect-support-data tool	663
PingAuthorize Server logs for troubleshooting and monitoring	668
Troubleshooting resources for Java applications	672
Java troubleshooting tools	672
	675
Troubleshooting resources in the operating system.	675
	678
	070

PingAuthorize

PingAuthorize

PingIdentity.

PingAuthorize software provides fine-grained, attribute-based access control and dynamic authorization management, enabling you to protect resources and filter data for databases, applications, and APIs.





- Introduction to PingAuthorize
- Installing PingAuthorize
- PingAuthorize Tutorials



- Use cases
- Server admin guide
- Policy admin guide
- Policy development and promotion
- API gateway integrations

6

Troubleshoot PingAuthorize

- Enable detailed logging
- Capture debugging data
- Monitor server availability
- Troubleshoot TLS-related issues
- Configure LDAP health checks
- Visualize a policy decision response

Learn More

- API reference guide □
- PingAuthorize Server Docker image^[2]
- PingAuthorize Policy Editor Docker image □
- PingAuthorize Community^[]
- Ping Identity Support Portal □
- PingAuthorize customer training (existing customers only)
- Partner Portal (partners)

Release Notes



PingIdentity.

New features and improvements in PingAuthorize. Updated November 25, 2024.

PingAuthorize 9.3.0.7 (November 2024)

Fixed an issue with deployment package store requests



We fixed an issue that caused logs and monitors to make requests to deployment package stores more frequently than the configured polling interval, creating performance issues.

Fixed a Policy Editor sign-off issue



We fixed an issue that could prevent complete sign-off from the Policy Editor when using the Authorization Code with PKCE grant type.

Fixed a config-diff error

Fixed DS-49071

We fixed an issue where **config-diff** would result in an **Unknown property** error when comparing configuration objects of different types.

Fixed an alert types issue



We fixed an issue where alert types that were disabled would still produce suppression messages.

PingAuthorize 9.3.0.6 (August 2024)

Added support for a new signature algorithm



We added support for Elliptic Curve Digital Signature Algorithm (ECDSA)-encoded signatures for JWT tokens when using the **Has** Valid Signature For JWKS and Has Invalid Signature For JWKS attribute comparators. Learn more in Conditions.

Fixed a Policy Editor UI issue



We fixed an issue where, in some cases, when selecting a scenario in entity testing or in the **Test Suite** with a large number of scenarios already defined, the Policy Editor UI would repeatedly flicker.

Fixed a PingAuthorize Server performance issue



We fixed an issue where, when using PingAuthorize Server's API security gateway in embedded PDP mode, policy decision logging could cause a memory leak and negatively impact the performance of long-running server instances.

Fixed an issue with PIP keystore service calls



We fixed an issue where, when making a service call with a policy information provider key store for MTLS configured and the **Server (TLS)** option set to **None** or **Default**, the service would incorrectly return a **Client TLS certificate is required** error.

Fixed an issue with HTTP service log messages



We fixed an issue where the status field of an HTTP service log message would include a status message, such as **OK**, rather than a status code.

Fixed error response handling in APP WARN



We fixed an issue where the HTTP Service Executor was not properly capturing error messages in the APP WARN logs for the policy information provider (PIP) endpoint.

Fixed an issue with HTTP service requests



We fixed an issue where, when making HTTP service calls, the policy decision point would incorrectly assign default values to the request body and content-type header.

PingAuthorize 9.3.0.5 (March 2024)

Fixed a NullPointerException caused by an unconfigured alert handler



Fixed an issue where a NullPointerException was thrown when an alert or alarm was raised and one or more of the alert handlers weren't configured. This most commonly happened when the server was being stopped.

Now, instead of throwing a NullPointerException, the server logs this message: Alert notification '<notification>' will not be processed by alert handler '<alert_handler>' since that alert handler does not have configuration.

Fixed SCIM case-sensitivity error



We fixed an issue where requests to create SCIM entries were not always observing the **case-exact=false** property, leading to incorrect case-sensitivity errors. Now, requests featuring this property will not be case-sensitive.

PingAuthorize 9.3.0.4 (January 2024)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.3.0.3 (November 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.3.0.2 (October 2023)

Fixed handling of empty array values for SCIM patch operations



SCIM **replace** operations with a value of [] now unassign the corresponding attribute. SCIM **add** operations with a value of [] are now ignored and no longer return an error.

Added enforcement of the maximum policy branch limit



We fixed an issue where the Policy Editor did not enforce the maximum branch limit of 100.

Added a service performance fix

Fixed PAZ-9858

We fixed an issue where HTTP services configured with dynamic settings could produce memory leaks and leave the PDP unresponsive.

PingAuthorize 9.3.0.1 (August 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.3.0.0 (June 2023)

Exercise fine-grained control over Policy Editor changes using self-governance

New

Build self-governance policies to manage access to your Policy Editor entities and operations. This allows you to protect against unauthorized or accidental application policy changes. For more information, see Self-governance.

Simpler OAuth token handling for PIPs using HTTP services

New

To reduce configuration complexity and time to production when connecting to HTTP services that require OAuth authentication, configure the Client Credentials flow to handle tokens directly from a token endpoint. For more information, see HTTP services.

Copy Policy Editor entities for faster configuration

New

To build your authorization logic more quickly and accurately, you can make editable copies of many of your Policy Editor entities, including items in the Trust Framework, Policy Manager, and Library. For more information, see Copying Policy Editor entities.

New authorization comparators for IP subnet ranges

New

With the new **In CIDR Block** and **Not In CIDR Block** comparators, you can check whether a user's IP address is in, or not in, a defined subnet range. These comparators make it easier to add network information checks to your zero trust policies. IPv4 and IPv6 addresses are supported. For more information, see **Conditions**.

Added a property that lets you control servlet information

New

Added the **include-servlet-information-in-error-pages** configuration property to give you control over whether servlet information gets printed on HTTP error pages or remains hidden (by default).

Apache Camel services have been removed



To enhance overall security for PingAuthorize, Camel services have been removed from the default configuration. If your policies depend upon Camel, see Apache Camel availability for more information.

Validate token signatures and claims in policy

Improved

You can now validate JWT signatures and claims in the authorization layer, adding defense in depth and allowing you to build policy and rule logic around genuine tokens. Enhances support for PDP API use cases. For more information, see **Conditions**.

Better control over statements in decision outcomes

Improved

You now have more control over whether statements are included in decision outcomes and the way statements propagate through decision evaluations. This makes it easier to provide information in decision responses, such as reasons for both **permit** and **deny** decisions and risk evaluation feedback. For more information, see **Statements**.

Add parent resolvers to attributes more quickly

Improved

To reduce the number of clicks needed to add a parent resolver to a Trust Framework attribute, we added the **+** Add Parent **Resolver** button.

Better targeting for regex-replace-attributes

Improved

We added the ability to target individual attributes using the **regex-replace-attributes** statement for a more precise modification of the payload. For more information, see **Regex Replace Attributes**.

Clarified WARN logs by migrating slow methods



We made WARN logging easier to interpret by changing the logging level for slow methods from WARN to DEBUG.

More resilient audit logging in the Policy Editor

Improved

We updated the default configuration for the decision-audit log to make audit logging more resilient.

Timeouts improved for replication enable and remove defunct server operations

Improved

Improved various timeouts for replication enable and remove defunct server operations to scale with the size of the topology. Smaller sized topologies should not be impacted by these changes.

Improved how a backup of the config backend is handled

Improved

If during a backup of the config backend, a file is deleted from the **config/archived-configs** directory, that deleted file will now be ignored instead of causing the backup to fail.

Added a missing field value in Policy Editor audit logging



We fixed an audit logging issue where ADMIN_POINT_AUDIT was not logging the operation field.

Fixed the Add Statement list display



We fixed a display issue where the Add Statement drop-down list was running off of the page and couldn't be fully accessed.

Corrected the linking behavior for Identity Properties



We fixed an issue where clicking the linked **Identity Properties** in **Identity Classes** or **Identity Providers** didn't open the **Identity Properties** editor.

Fixed a NullPointerException for URIs without hosts



We fixed an issue where JSON response bodies containing URIs without hosts would produce a NullPointerException when PingAuthorize was configured in gateway mode.

PingAuthorize 9.2.0.5 (March 2024)

Fixed SCIM case-sensitivity error



We fixed an issue where requests to create SCIM entries were not always observing the **case-exact=false** property, leading to incorrect case-sensitivity errors. Now, requests featuring this property will not be case-sensitive.

Fixed a NullPointerException caused by an unconfigured alert handler



We fixed an issue where a **NullPointerException** was thrown when an alert or alarm was raised, and one or more of the alert handlers were not configured. This most commonly happened when the server was being stopped.

Now, instead of throwing a NullPointerException, the server logs this message: Alert notification '<notification>' will not be processed by alert handler '<alert handler>' since that alert handler does not have configuration.

PingAuthorize 9.2.0.4 (November 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.2.0.3 (September 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.2.0.2 (August 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.2.0.1 (May 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.2.0.0 (December 2022)

Added the ability to define external Trust Framework attribute caches for development and production

New

Added support and configuration controls for Redis external caching of Trust Framework attribute values. See Configuring Trust Framework attribute caching for production and Configuring Trust Framework attribute caching for development.

Added the ability to configure custom OIDC scopes for the Policy Editor

New

You can now use the --scope option during Policy Editor setup to persistently override the default OpenID Connect (OIDC) scopes. For a one-time override, use the **PING_SCOPE** environment variable during Policy Editor startup. See the **OIDC mode** (custom scope) tab of Installing the PingAuthorize Policy Editor non-interactively for more details.

Added an HTTP servlet extension to support Prometheus monitoring

New

Added an HTTP servlet extension that allows the values of numeric monitor attributes to be published as metrics in a form that can be consumed by a Prometheus monitoring server. See Monitoring server metrics with Prometheus \square .

Setting up and upgrading PostgreSQL policy databases has changed



In an early access release of the Policy Editor, we provided a tool called the **db-cli** for PostgreSQL policy databases. This tool is now deprecated and will be removed in a later release. You should now use the **policy-db** tool to **create** and **upgrade** PostgreSQL databases.

Docker support update for PingAuthorize PAP using PostgreSQL



PingAuthorize policy administration point (PAP) Docker images based on product version 9.2.0.0 EA do not support PostgreSQL as a policy database backend due to schema changes. We have reintroduced PostgreSQL support for images based on version 9.2.0.0 GA or later. See Deploying PingAuthorize Policy Editor using Docker.

Updated Groovy version support



Updated Groovy support from version 2.x to 3.x. This change might introduce some minor incompatibilities in Groovy script support. For example, import statements can no longer be split into multiple lines. Deployments making use of Groovy-scripted extensions should carefully test these extensions in a temporary standalone instance to verify compatibility and make any necessary changes before updating an existing instance.

Deprecated the OIDC implicit flow for the Policy Editor

Info

The OIDC Implicit flow implementation in the Policy Editor has been deprecated, because the OAuth Working Group no longer recommends its use. Implicit flow will be removed from a future version of PingAuthorize. You should transition to the Authorization Code with PKCE flow.

Qualified the Apigee OAuth flow

Info

You can use OAuth standard authentication as part of your Apigee integration with PingAuthorize. See Configuring Apigee for PingAuthorize integration for more information.

Deprecated the Swagger documentation for the Policy Editor REST APIs



The Swagger pages documenting the REST APIs that manage the Policy Editor have been deprecated and will be removed from the product in a future release. We plan to re-implement the REST API documentation outside of the Policy Editor and make it available at a future date.

Introduced a character limit for Policy Editor entities



Set a limit of 255 characters for the following names: branches, deployment packages, Trust Framework entities, and Policy Manager entities.

Improved the performance of the Policy Editor and PDP APIs



You should see performance improvements when using the Policy Editor or the various PingAuthorize PDP modes and APIs.

Made the JWKS endpoint response cacheable in the Policy Editor

Improved

You can now use the Authentication.oidcJwksCacheExpirySeconds setting in the options.yml file to control whether the server caches the JWKS endpoint response and for how long when using the Policy Editor in OIDC mode. See Configuring the JWKS endpoint cache.

Made the Policy Editor user data configurable

Improved

You can now change the claim that controls the user data displayed in the upper right of the Policy Editor. See Changing the default JWT claim for the OIDC user ID for more information.

Added support for generating digital signatures

Improved

Added support for generating digital signatures with a key obtained from an encryption settings definition. By default, the server's preferred encryption settings definition is used to obtain the signing key, but you can use the **signing-encryption-settings property** in the crypto manager configuration to choose an alternative definition.

Previously, signatures were generated using a legacy key shared among servers in the topology, which could make it difficult to validate signatures outside of the topology. The legacy key will continue to be used in environments without any encryption settings definitions.

The replace-certificate tool re-prompts you for the path to a valid file containing certificates

Improved

Previously in an interactive PingAuthorize Server setup, when **replace-certificate** prompted you for the path to a file containing one or more certificates to be imported, it would exit with an error if the provided path represented a file that did not contain valid certificate information. It now re-prompts you for the path to a valid file after displaying the error message.

Fixed an issue with batch JSON PDP API requests



You should now be able to make batch JSON PDP API requests that contain only one decision request.

Fixed an issue with SpEL allow lists



Fixed an issue where SpEL allow lists in the configuration file were being ignored.

Fixed an issue with policy database value migration during an upgrade



Fixed a database upgrade issue where attributes with default values of null were not migrating and test assertion values became empty. This issue only affected customers that were running a pre-9.2-EA Policy Editor and upgraded to 9.2-EA.

Fixed an issue that prevented the Policy Editor from starting after upgrading the policy database schema



Fixed a rare issue where the tools missed applying some upgrade operations for the policy database, preventing the Policy Editor from starting. The **setup** and **policy-db** tools now validate the system time when performing schema element upgrades.

Fixed an issue with the Policy Editor UI when trying to drag multiple components onto a rule condition



The Policy Editor UI no longer prevents you from dragging more than one Trust Framework component onto a policy rule when creating conditions.

Fixed an issue with missing Policy Editor entity changes



Fixed an issue where the Policy Editor could drop entity changes when performed concurrently with commits on the same branch.

Fixed an issue with policy creation using Applies To targets



Fixed an issue that stopped you from creating policies or policy sets with targets in the Applies To section.

Fixed an issue with replacing deleted deployment packages



Fixed an issue where the Deployment Manager wouldn't let you replace the deployment package after deleting that deployment package from the Policy Editor.

Fixed an issue with Policy Editor logging



Fixed a regression from 9.2-EA where the lowered log level of HTTP PIP service call failures prevented them from appearing when using the default Policy Editor logging configuration.

Fixed a pagination issue with Test Suite entities in the Policy Editor



Fixed an issue where a large number of saved Test Suite entities were not being paged correctly by the Policy Editor backend, resulting in an HTTP 400 response.

Fixed an issue with portability of the configuration.yml file for the Policy Editor



Fixed an issue with the Policy Editor **setup** tool using an absolute file reference to the default H2 policy database when writing **configuration.yml**, which caused issues if the server instance root was moved to a different file system location. Now, the **setup** tool generates a file reference relative to the server instance root. You can still provide your own value through -- dbConnectionString, or by modifying configuration.yml after it is generated.

Fixed a Policy Editor OIDC sign-on error



Fixed the following error in the OIDC implicit grant flow: Unable to complete background login with reason: invalid state parameter.

Fixed a Policy Editor issue with propagating the OIDC base URL to the configuration file



Fixed a Policy Editor issue for the **bin/setup oidc** command with the **--oidcBaseUrl** argument. Previously, when you provided a path without an ending forward slash, the command didn't propagate your path value to **configuration.yml**.

Updated the dsconfig tool for applying authentication settings to a server group

Fixed	DS-46313
-------	----------

Updated the **dsconfig** tool to ensure that it uses the correct authentication type when applying changes to all servers in a server group. Previously, it would always attempt to use simple authentication, even if the connection to the initial server was authenticated using a different mechanism.

Fixed a Kong-related issue when using set-headers with an array of strings



Fixed an issue where, when using the **ping-auth** plugin with Kong Gateway, sending the **set-headers** statement with an array of strings in the payload produced an error.

Fixed a Kong-related issue where using exclude-attributes or regex-replace-attributes produced invalid JSON



Fixed an issue where, when using the ping-auth plugin with Kong Gateway, sending either the exclude-attributes or regexreplace-attributes statements returned invalid JSON in the response.

Fixed a Kong-related issue where using set-attributes produced an upstream server timeout error



Fixed an issue where, when using the ping-auth plugin with Kong Gateway, sending the set-attributes statement returned the following message: An invalid response was received from the upstream server. The Kong error log also listed an upstream timed out error for the same response.

Fixed Kong-related modify-query statement failures



Fixed an issue where, when using the ping-auth plugin with Kong Gateway, sending the modify-query statement with a query in the payload but no set query parameters returned the following response: An unexpected error occurred. The Kong error log also listed a thread aborted runtime error.

PingAuthorize 9.1.0.5 (May 2024)

Fixed SCIM case-sensitivity error



We fixed an issue where requests to create SCIM entries were not always observing the **case-exact=false** property, leading to incorrect case-sensitivity errors. Now, requests featuring this property will not be case-sensitive.

Fixed a NullPointerException caused by an unconfigured alert handler

Fixed DS-47455

We fixed an issue where a **NullPointerException** was thrown when an alert or alarm was raised, and one or more of the alert handlers were not configured. This most commonly happened when the server was being stopped.

Now, instead of throwing a NullPointerException, the server logs this message: Alert notification '<notification>' will not be processed by alert handler '<alert handler>' since that alert handler does not have configuration.

PingAuthorize 9.1.0.4 (November 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.1.0.3 (August 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.1.0.2 (March 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.1.0.1 (December 2022)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.1.0.0 (June 2022)

Updated commons-codec to address a security issue



Updated the **commons-codec** library to version 1.13 to address a security issue.

Updated Jackson Databind to address a security vulnerability



Updated Jackson Databind to 2.13.3 to address the CVE-2020-36518^[] security vulnerability.

Updated Google Guava to address a security vulnerability



Updated the Google Guava dependency in common libraries to address the CVE-2020-8908 ^C security vulnerability.

Added conditional effects for policy rules



Rules now include **conditional effects**, allowing policy builders to write one rule with two possible effects. The effect produced depends on whether the effect condition evaluates to **true** or **false**.

Description	
Effect	
Effect	Permit if condition holds, otherwise deny
- When	Permit
ALL ANY	Deny
Is Usin	g Permit if condition holds, otherwise deny
AM	Deny if condition holds, otherwise permit
+ Comp	arison Amed Condition Group

γ Νote

Previous rule conditions are now set as targeting conditions in the **Applies To** section.

Added the ability to configure attribute logging for the Policy Decision Service

New

Added the option to **configure logging for Trust Framework attributes**. The Policy Decision Service logs the designated attributes when they are evaluated as part of a request. This option is only available in embedded mode.

Added the ability to sanitize error logging to protect sensitive data

New

Added the ability to sanitize error log messages as they are generated. This can help prevent sensitive information from being leaked through log messages, although the resulting log messages can potentially be less useful for troubleshooting purposes. See Log Sanitization \square for more information.

Updated the administrative console browser support

Info

The administrative console now supports Microsoft Edge. Administrative console support for Microsoft Internet Explorer 11 has been deprecated.

Deprecated Apache Camel for PIP connections



Using Apache Camel to connect policy information points (PIPs) to PingAuthorize has been deprecated, and the feature will be removed in a future release of the product. We recommend using HTTP services instead, where applicable.

Made it easier to present a custom SSL certificate to the Policy Editor

Improved

We added a new **environment variable** named **KEYSTORE_PIN_FILE** to the Policy Editor **setup** and **start-server** tools. This variable takes precedence over **PING_KEYSTORE_PASSWORD** when validating and presenting the server certificate.

Improved UI performance in the Policy Editor

Improved

The Policy Editor now supports API HTTP caching, which is enabled by default to improve UI performance. Disable this feature and restore the legacy behavior by providing the --disableApiHttpCache option to the setup tool. Alternatively, set the environment variable PING_ENABLE_API_HTTP_CACHE to false when running start-server to disable it for a particular server runtime instance.

Added a command-line configuration tool for PingAuthorize Docker containers

Improved

Added a **docker-pre-start-config** command-line tool for PingAuthorize Docker containers. Use the tool before the server is started to make configuration changes to the server that depend on the running container's environment.

Added and updated PingAuthorize Server profile command-line tools

Improved

Added a **--skipValidation** argument for the **manage-profile replace-profile** command. This argument allows skipping the final server validation step when running on an offline server.

Added an --excludeSetupArguments argument for the manage-profile generate-profile command. This argument allows generating a server profile that does not include a setup-arguments.txt file.

Updated the **setup** and **replace-profile** subcommands to fail when a server profile includes an **encryption-settings-db** file in the profile's **server-root/pre-setup**/ directory.

Enhanced advice logging

Improved

During advice processing, the File Based Error Log Publisher publishes additional helpful messages to the configured output file.

Removed the OIDC offline_access scope requirement for the Policy Editor



The Policy Editor no longer requires the offline_access scope when configured in OpenID Connect mode using the Authorizat ion Code with PKCE grant type.

Fixed the Policy Editor issue rejecting bearer tokens with array-type aud claims



Fixed an issue that prevented the Policy Editor REST APIs from accepting a bearer token when the **aud** claim was an array of strings.

Enabled the Policy Editor to decode JWTs with underscores



The Policy Editor is now able to decode JWTs that contain underscore characters.

Enhanced HTTP performance

Fixed PAZ-3238, PAZ-2291

This release includes general HTTP performance improvements and bug fixes.

Fixed alert consistency for cleared alarms



Fixed issues where gauges could raise an alarm and create an alert, but not create an alert when that same alarm was later cleared, making it unclear when the reported condition had abated.

Updated the API gateway behavior for handling trailing zeros



When operating as an API gateway, PingAuthorize will no longer remove trailing zeros from numbers in non-SCIM response bodies and advice payloads.

Fixed the Policy Editor UI tab switching error



Fixed an issue where the Policy Editor threw an error when rapidly switching between Trust Framework tabs under slow network conditions.

Fixed the Policy Editor error that occurs when updating entities concurrently



Fixed an issue where concurrent updates to the same entities in the Policy Editor could sometimes produce an error.

Fixed an issue resolving JSONPath expressions that contain the keys() function



Fixed an issue where calling keys() in a JSONPath expression did not return the object's keys.

Fixed the PIN retrieval issues with third-party passphrase providers



Fixed issues that prevented obtaining key and trust store PINs with the Amazon Secrets Manager, CyberArk Conjur, and HashiCorp Vault passphrase providers.

Fixed erroneous certificate expiration warnings



Fixed an issue that prevented the server from refreshing the monitor data used to detect and warn about an upcoming certificate expiration. This could cause the server to continue to warn about an expiring certificate even after that certificate had been replaced.

Fixed the PingAuthorize name and version in collect-support-data



The collect-support-data (CSD) tool now correctly displays the name and version of PingAuthorize.

Updated the incorrect version information for collect-support-data



The status tool now shows the current collect-support-data version.

Updated to LDAP SDK version 6.0.5



Updated to LDAP SDK for Java version 6.0.5 for bug fixes and new functionality.

Recovering from a failed setup on Windows

Issue DS-45941

The **setup** command might fail on Windows operating systems due to the presence of Bouncy Castle JAR files that begin with **bc** in the **lib** directory. The JAR files are mentioned in an error message similar to the following:

```
An unexpected error occurred while attempting to copy the non-FIPS Bouncy Castle jar file into the server's
classpath:
FileSystemException:
lib\bcprov-jdk15to18-1.71.jar:
The process cannot access the file because it is being used by another process.
```

A temporary workaround is to delete the JAR files that begin with **bc** from the **lib** directory before attempting to run **setup** again.

PingAuthorize 9.0.0.6 (August 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.0.0.5 (April 2023)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.0.0.4 (January 2023)

Fixed erroneous certificate expiration warnings



Fixed an issue that prevented the server from refreshing the monitor data used to detect and warn about an upcoming certificate expiration. This could cause the server to continue to warn about an expiring certificate even after that certificate had been replaced.

PingAuthorize 9.0.0.2 (July 2022)

Updated to LDAP SDK version 6.0.5



Updated to LDAP SDK for Java version 6.0.5 for bug fixes and new functionality.

Fixed an incorrect SCIM POST error response



Fixed an issue where SCIM **POST** requests that violated a unique attribute constraint received an internal error instead of the expected SCIM error response.

Fixed an incorrect SCIM POST error code



Fixed an issue where SCIM **POST** requests that violated a unique attribute constraint received an error response with status **400 Bad Request** instead of **409 Conflict**.

Fixed the PingAuthorize name and version in collect-support-data



The collect-support-data (CSD) tool now correctly displays the name and version of PingAuthorize.

PingAuthorize 9.0.0.1 (February 2022)

Version incremented for administrative purposes



The PingAuthorize version number was incremented due to changes released for PingDirectory. There are no release notes for this version of PingAuthorize.

PingAuthorize 9.0.0.0 (December 2021)

Added support for policy deployment from Microsoft Azure blob storage

New

The PingAuthorize Server can now consume deployment packages published to Microsoft Azure blob storage. This enables policy writers to deploy new policies to a central Azure deployment package store read by the PingAuthorize Server running in embedded mode. For more information, see Adding an Azure deployment package store, Configuring the Policy Editor to publish to a deployment package store, and Using the Deployment Manager.

Enabled configuration of the SpEL allow list in PDP mode

New

Now you can configure the SpEL allow list when the Policy Decision Service is running in embedded policy decision point (PDP) mode. An out-of-the-box PingAuthorize installation adds the following classes to the default allow list: String, Date, Random, UUID, Integer, Long, Double, Byte, Math, Boolean, LocalDate, DayOfWeek, Instant, ChronoUnit, and SimpleDateForma t. When configuring a policy deployment package containing SpEL expressions that reference additional Java classes, administrators must use dsconfig or the administrative console to add spel-allowlisted-class attributes to the Policy Decision Service. The class must also be available on the server classpath at server start. For non-standard Java classes, place the .jar file in the server lib folder.

Expanded Policy Editor database support to include PostgreSQL

New

The PingAuthorize Policy Editor can now persist its policies, Trust Framework, and versioning data in a PostgreSQL policy database instead of the default H2 file-based database. To initialize the database, use the instructions at https://github.com/pingidentity/pingauthorize-contrib/tree/main/sql/postgresql^C. To configure the Policy Editor for PostgreSQL, use the following setup options:

--dbConnectionString

- The JDBC connection string (for example, "jdbc:postgresql://localhost:5432/policy_db")
- --dbAppUsername
 - The PostgreSQL user
- --dbAppPassword
 - The user's password

Added support for the MuleSoft API Gateway in a sideband architecture

New

Now you can deploy PingAuthorize in a sideband configuration with the MuleSoft API Gateway. With a sideband deployment, your organization can quickly set up an environment for fine-grained, dynamic authorization that integrates with existing identity management infrastructure and requires minimal changes to your network configuration. For more information about our custom MuleSoft policy, see MuleSoft API gateway integration.

OpenID Connect (OIDC) Authorization Code with Proof Key for Code Exchange (PKCE)

New

Policy Editor setup in OpenID Connect (OIDC) authentication mode now uses the Authorization Code with Proof Key for Code Exchange (PKCE) grant type by default, instead of the implicit grant type. For information about configuring the Policy Editor in OIDC authentication mode, see Installing the PingAuthorize Policy Editor non-interactively.

Upgrading from early access to general availability

Info

If you are upgrading from PingAuthorize 9.0.0.0 Early Access to 9.0.0.0 General Availability, you must upgrade both the PingAuthorize Server and the Policy Editor before you use the Policy Decision Service in external mode. Upgrading only one component results in this error: Please upgrade to PingAuthorize Policy Editor version '9.0.0.0'.

Server profiles replace peer setup



Peer server setup and clustered configuration have been removed from **setup**. To manage server configuration, use server profiles instead of peer setup. Server profiles support deployment best practices such as automation and Infrastructure-as-Code (IaC). For more information about server profiles, see Deployment automation and server profiles.

Upgrading from earlier versions of PingAuthorize



For more considerations, see Upgrade considerations.

Added support for password storage schemes

Improved

Added support for password storage schemes that allow users to authenticate with passwords stored in the Amazon AWS Secrets Manager service, the Microsoft Azure Key Vault service, a CyberArk Conjur instance, or a HashiCorp Vault instance.

Added redaction capability for dsconfig

Improved

Added a global configuration property that can be used to indicate that the values of sensitive configuration properties should be redacted when constructing the **dsconfig** representation for a configuration change, given that these values might be included in the server's configuration audit log or administrative alerts whenever a configuration change is applied. By default, the values of configuration properties that are defined as sensitive get obscured rather than redacted, which allows the change to be replayed without revealing the actual value of the property. However, it is now possible to redact such values rather than obscuring them, which provides stronger protection against exposing those values but might interfere with the ability to replay the configuration audit log if it contains changes involving sensitive properties.

Mirrored configuration change logging

Improved

Updated the server to record the original requester's DN and IP address in access log and configuration audit log messages for mirrored configuration changes.

Added support for obtaining secrets from CyberArk Conjur

Improved

The Conjur cipher stream provider can use a retrieved secret to generate the encryption key used to protect the contents of the encryption settings database. The Conjur passphrase provider can be used in other cases where the server might need a clear-text secret, including PINs for accessing certificate key stores or credentials for authenticating to external services. The server can authenticate to Conjur with a username and password or an API key.

Added support for obtaining secrets from Azure Key Vault

Improved

The Azure Key Vault cipher stream provider can use a retrieved secret to generate the encryption key used to protect the contents of the encryption settings database. The Azure Key Vault passphrase provider can be used in other cases where the server might need a clear-text secret, including PINs for accessing certificate key stores or credentials for authenticating to external services.

Added a PKCS #11 cipher stream provider

Improved

Added a PKCS #11 cipher stream provider that can require access to a certificate in a PKCS #11 token to unlock the server's encryption settings database. Only certificates with RSA key pairs can be used because JVMs do not currently provide adequate key wrapping support for elliptic curve key pairs.

Runtime server problem-status handling

Improved

When the Policy Decision Service is unable to handle requests due to misconfiguration or problems with the runtime environment, the PingAuthorize Server status is now DEGRADED instead of UNAVAILABLE. Orchestration systems like Kubernetes now remove such servers from pools instead of restarting them, allowing server administrators to investigate and correct the issue.

Added administrative console PIN support

Improved

The administrative console can now be configured to supply PINs to its trust stores through the **oidc-trust-store-pinpassphrase-provider** and **trust-store-pin-passphrase-provider** settings. This means trust store types that require passphrases (for example, PKCS12 or BCFKS) are now properly supported.

Administrative console file retrieval with SSO

Improved

The administrative console can now retrieve files created from **collect-support-data** or **server-profile** tasks when using single sign-on (SSO) to authenticate with the managed server.

Added file servlet support for OIDC and OAuth 2.0

Improved

Updated the file servlet to add support for token-based authentication using an OAuth 2.0 access token or an OpenID Connect ID token. The servlet previously only supported basic authentication.

manage-profile generate-profile argument validation

Improved

Improved **includePath** argument validation performed by the **manage-profile generate-profile** tool. The tool will only use relative paths that exist below the server root, and it previously silently ignored absolute paths or relative paths that referenced files outside of the server root. It will now exit with an error if the **includePath** argument is used to provide an absolute path or a path outside the server root. It will accept—but warn about—paths that reference files that do not exist.

Expanded 1dap-diff capabilities

Improved

Made several improvements to the ldap-diff tool:

- Added the ability to perform a byte-for-byte comparison of attribute values rather than using schema-based logical equivalence.
- Added the ability to use a properties file to obtain default values for command-line arguments.
- Improved the ability to use different TLS-related settings for the source and target servers.
- Improved support for SASL authentication.

Added TLS protocol configuration to the crypto manager

Improved

Updated the crypto manager configuration to add properties for controlling the set of TLS protocols and cipher suites that will be used for outbound connections, as well as properties for controlling whether to enable TLS cipher suites that rely on the SHA-1 digest algorithm or the RSA key exchange algorithm.

Added JDK support

Improved

Added support for the use of JDKs obtained through Eclipse Foundation and BellSoft.

Added certificate management support

Improved

Added support for new extended operations that can be used to help manage the server's **listener** and inter-server certificates. Updated the **replace-certificate** tool to add support for replacing and purging certificates in a remote instance, and to allow skipping validation for the new certificate chain.

Secret key loss when removing a server from the topology

Fixed DS-4	14591
------------	-------

Fixed an issue introduced in version 7.0.0.0 where secret keys under cn=Topology, cn=config could be lost when removing a server from the topology. When a server is removed via the dsreplication disable or remove-defunct-server tools, its secret keys will now be distributed among the remaining members of the topology. The keys from the rest of the topology will also be copied to the server being removed.

The cipher secret keys in the topology that are affected by this change are used by reversible password storage schemes (except for AES256, which uses the encryption settings database). If you are using a reversible password storage scheme other than AES256, prior to this fix, you could lose access to keys that had been used for reversible password encryption when removing servers from the topology.

Λοτε

Since this change only applies to the most recent version of **remove-defunct-server** and **dsreplication disable**, if you are removing a server from a multi-version topology, you should run that tool from the most recent version. In the past, **dsreplication disable** and **remove-defunct-server** could only be run from an older version. Now, when removing a server from the topology, they should be run from the most recent version in the topology. If you run the tool from an older server, it will not include this fix, and you might lose access to secret keys from servers that are removed from the topology.

Shutting down PingAuthorize Server with an invalid package store



An invalid deployment package store no longer prevents the PingAuthorize Server from shutting down.

remove-defunct-server attribute removal



Fixed an issue in which **remove-defunct-server** would remove attributes from **config.ldif** if they were identical apart from case.

Policy Editor batch scripts refer to non-existent Java files



The PingAuthorize Policy Editor **start-server.bat** and **stop-server.bat** scripts no longer output messages referring to nonexistent java.properties or dsjavaproperties files.

JVM segmentation faults during start-server



Removed -XX:RefDiscoveryPolicy=1 from the default **start-server** Java arguments. In rare cases, this argument was related to segmentation faults in the Java virtual machine, especially when used with the G1 garbage collector.

Configuration keys and values in the Policy Editor Test Suite



The Policy Editor now uses policy configuration keys and values correctly in Test Suite tests. For details about configuring policy configuration keys, see Environment-specific Trust Framework attributes.

OIDC authentication to the Policy Editor for PingOne users with TLS 1.3 might limit functionality



When PingOne users authenticate with OIDC to the Policy Editor, environments using OpenJDK versions older than 11.0.3 might run into an intermittent TLS 1.3 issue preventing them from loading test scenarios. The issue appears in the logs as com.symphonicsoft.authentication.OidcAuthenticator: Could not retrieve jwks information from '<ping-one-url>/ as/jwks' and includes the following message: javax.net.ssl.SSLException: No PSK available. Unable to resume. This is an OpenJDK bug^[2] that has been fixed in version 11.0.3. To circumvent this issue, you can upgrade to OpenJDK 11.0.3 or newer. Disabling TLS 1.3 also prevents this issue.

Deployment package store detection



If the configured deployment package store is not available when the PingAuthorize Server starts, it will not be able to detect when the store becomes available again. To ensure that the PingAuthorize Server begins using the deployment package store when the store is available again, you must restart the server or change the Policy Decision Service configuration.

Can't use an existing persistent database with Docker volumes



The pingdatagovernancepap and pingauthorizepap Docker images now run as unprivileged (non-root) users by default. If you have existing pingdatagovernancepap policy databases, configure the containers to run as **root**. For more information, see Deploying PingAuthorize Policy Editor using Docker.

Can't persist the database in /opt/db with Docker volumes



To persist a policy database in a Docker volume, create a new Docker volume with a mount target of /opt/out instead of /opt/ db . For more information, see Deploying PingAuthorize Policy Editor using Docker.

Reconfiguring the Policy Editor in a Docker volume



When you use the Policy Editor in a Docker volume, changing the configuration using an **options.yml** file also requires that you create an empty file such as **/opt/out/instance/delete-after-setup** before you restart **pingauthorizepap**. Consider this example:

1. You start the container with a command like the following:

```
$ docker run --network=<network_name> --name pap -p 8443:1443 \
    --env-file ~/.pingidentity/config \
    --volume /home/developer/pap/server-profile:/opt/in/ \
    --env PING_OPTIONS_FILE=custom-options.yml \
    --volume /home/developer/pap/Symphonic.mv.db:/opt/out/Symphonic.mv.db \
    --env PING_H2_FILE=/opt/out/Symphonic \
    pingidentity/pingauthorizepap:<TAG>
```

(j) Note

This example command bind mounts a customized options.yml file named custom-options.yml to the server root using the server profile capability. The host system server-profile folder must contain instance /custom-options.yml for this example to work correctly. The Docker image <TAG> is only a placeholder. See https://devops.pingidentity.com/reference/config/^[].

- 2. You decide to change the configuration, so you edit the **custom-options.yml** file.
- 3. You create the empty file with a command like this:

docker exec -it pap /bin/sh -c "touch /opt/out/instance/delete-after-setup"

4. With that file in place, you can now restart the Policy Editor with the following commands:

```
$ docker stop pap
$ docker start --attach pap
```

Upgrading multi-server topologies from earlier versions



Upgrading multi-server topologies that contain PingDataGovernance 6.x or 7.x to PingAuthorize is not supported.

Using the Periodic Stats Logger



Published throughput and latency stats for SCIM, sideband, and gateway requests for the Periodic Stats Logger are not recorded until the requests are made and the logger is reset.

Policy Editor snapshot import error



The Policy Editor produces an error when a user attempts to import an exported snapshot that contains references to named value processors.

Using the administrative console with Tomcat 9.0.31



Several known issues can occur when you use the administrative console with Tomcat 9.0.31. You can resolve these issues by upgrading to Tomcat 9.0.33 or later.

Harmless failure message when stopping the PingAuthorize service



If you use the **create-systemd-script** tool to create a forking **systemd** service, the service is stopped by the **systemctl stop ping-authorize.service** command. At that time, you can see the status using the

systemctl status ping-authorize.service command. That status might contain an indication of failure: Active: failed
(Result: exit-code). This error has to do with the way the service exits. It is harmless.

Previous Releases

For information about enhancements and issues resolved in previous major and minor releases of PingAuthorize, follow these links to their release notes:

• PingAuthorize 8.3 (June 2021)^[2]

Introduction to PingAuthorize

Ping Identity.

PingAuthorize is a solution for fine-grained, attribute-based access control and dynamic authorization management.

Digital transactions worldwide are increasing at exponential rates. At the heart of every transaction are questions of authorization:

- · Can a given user perform this action or access this resource?
- How much data can a given partner access?

With more sophisticated use cases and more regulations for sensitive data, the rules that guide these questions of authorization get more complex. For example, a user can only transfer funds if their account is in good standing and they've agreed to the terms of service, or a partner can only access user data for those users who have given explicit consent.

Using traditional, static authorization solutions, like role-based access control (RBAC), to address complex authorization requirements lacks the full transaction context available only with dynamic, runtime authorization. PingAuthorize dynamic authorization can evaluate any identity attributes, consents, entitlements, resources, or contexts to make attribute-based access control (ABAC) decisions in real time. PingAuthorize gives you centralized control over your digital transactions and application-level access to your protected resource.

The following components provide the main capabilities for PingAuthorize.

PingAuthorize Policy Editor

Policy Administration and Delegation

PingAuthorize Policy Editor enables nontechnical stakeholders to collaborate with IT and application developers to build and test authorization policies with a drag-and-drop UI. The editor supports fine-grained permissions and workflows to enable the right operational processes and delegated administration scenarios.

Attribute Resolution and Orchestration

Authorization policies depend on any combination of attribute expressions that are evaluated at runtime by PingAuthorize Server. These attribute values might be present in the transaction itself, like an identifier of the authenticated user.

PingAuthorize Policy Editor enables additional attribute values to be determined at runtime by configuring attribute source and attribute processing without writing any code.

PingAuthorize Server

PingAuthorize Server includes the runtime policy decision service and multiple integration capabilities:

Authorization Policy Decision APIs

Applications or services obtain policy decisions at runtime using a policy decision point (PDP) application programming interface (API). Applications then enforce these decisions in their own application or service code. This integration configuration is the most flexible, supporting any application or service use case.

API Security Gateway and Sideband API

For fine-grained access control and data protection within application, platform, or microservice APIs, customers can integrate the API Security Gateway or Sideband API into their API architecture.

In this configuration, PingAuthorize Server inspects API requests and responses, and then enforces policy by blocking, filtering, obfuscating, or otherwise modifying request and response data and attributes. This approach requires little or no code changes by the API developer.

SCIM Service

For fine-grained data access control and protection for structured datastore like Lightweight Directory Access Protocol (LDAP) and RDBMS, customers can deploy the System for Cross-domain Identity Management (SCIM) service in front of their datastores.

In this configuration, PingAuthorize Server provides SCIM-based APIs through which clients create, read, update, and delete (CRUD) data. The SCIM service enforces policy by blocking, filtering, obfuscating, or otherwise modifying data and attributes.

> Important

The available enforcement features described above vary depending on your license. For more information, check your PingAuthorize license key or contact your Ping Identity account representative.

Learn more about PingAuthorize architecture and policy decision environments in PingAuthorize architectural overview.

Get started

Learn how to quickly spin up a PingAuthorize solution and walk through some simple use cases in Getting started with PingAuthorize (tutorials).

PingAuthorize architectural overview

When planning your PingAuthorize dynamic authorization software deployment, you should review the components to install as well as the potential deployment methods, architectures, and environments.

Components

Policy Editor

The Policy Editor gives policy administrators the ability to develop and test data-access policies.

PingAuthorize Server

The PingAuthorize Server enforces policies to control fine-grained access to data.

When you configure a REST API to access data through the PingAuthorize Server, the server applies data-access policies that allow, block, filter, or modify protected resource and data attributes.

Implementation architectures


PingAuthorize Server supports the following implementation and data flow architectures for enforcing fine-grained access to data:

- SCIM API to datastores
- API security gateway as reverse proxy
- API security gateway in sideband configuration
- PDP APIs for non-API use cases

The following sections describe these architectures in more detail.


SCIM API to datastores

The PingAuthorize Server System for Cross-domain Identity Management (SCIM) service provides a REST API for data that is stored in one or more external datastores, based on the SCIM 2.0 standard^[]. Authorization policies are enforced by the SCIM service. Learn more in SCIM API request and response flow.




API security gateway as reverse proxy

You can configure PingAuthorize Server's API security gateway as a reverse proxy to an existing JSON REST API. In this architecture, PingAuthorize Server acts as an intermediary between clients and existing API services. Authorization policies are enforced by the API security gateway. Learn more in API gateway request and response flow.




API security gateway in sideband configuration

You can configure the PingAuthorize Server's API security gateway as an extension to an existing API lifecycle management gateway, commonly known as a sideband configuration. In this architecture, the API lifecycle management gateway functions as the intermediary between clients and existing API services and enforces policy decisions made by the PingAuthorize Server. Learn more in API gateway integration.



PDP APIs for non-API use cases

You can implement either of the PingAuthorize Server's PDP APIs to support policy decisions in cases where you don't need to protect an API resource. Learn more about Authorization Policy Decision APIs.



Policy decision environments

You can configure PingAuthorize for either of the following policy decision environments:

Development environment (external PDP)


Policies are developed in the Policy Editor. The Policy Editor serves as the external policy decision point (PDP), and the PingAuthorize Server serves as the policy enforcement point (PEP).

This configuration accelerates policy deployment by putting the decision point closer to your policy updates, making it ideal for development or testing environments.

🆒 Important

External PDP mode is not intended for use in production environments.

The following image shows PingAuthorize Server configured in a reverse proxy architecture. The **development environment** supports all PingAuthorize implementation and data flow architectures.



Learn more about configuring PingAuthorize for development environments in Configuring external PDP mode.

Pre-production and production environments (embedded PDP)


Policies are developed in the Policy Editor and deployed to the PingAuthorize Server, which serves as both the PEP and the PDP. This configuration supports policy testing in pre-production environments and live policy decisions in production environments.

In these environments, the policy administrator **bundles policies into a deployment package** and then publishes them to the PingAuthorize Server. Embedding the policies in the PingAuthorize Server reduces latency in the decision request-response flow.

The Policy Editor can deploy policy deployment packages to the PingAuthorize Server using one of the following methods:

- Export the deployment package as a static file.
- Publish to a cloud package store (AWS S3, Azure) with the Deployment Manager.
- Publish to a file system package store with the Deployment Manager.

The following image shows PingAuthorize Server configured in the reverse proxy architecture. Pre-production and production environments support all PingAuthorize implementation and data flow architectures.



Learn more about configuring PingAuthorize for production environments in Configuring embedded PDP mode.


Getting started with PingAuthorize (tutorials)

. .



This section provides tutorials for installing and configuring PingAuthorize Server with different fine-grained access control policies.

As you complete these tutorials, you will quickly get up and running with PingAuthorize Server and its Policy Editor. You will also learn how to implement data access policies for a REST application programming interface (API) and System for Cross-domain Identity Management (SCIM) resources.



- Setting up your environment
- Starting PingAuthorize
- Verifying proper startup
- Accessing the GUIs
- Stopping PingAuthorize



- Importing default policies
- Configuring fine-grained access control for an API
- Configuring attribute-based access control for API resources
- Creating SCIM policies

Using the tutorials

Use the tutorials to familiarize yourself with the capabilities of PingAuthorize dynamic authorization management by walking through the provided configuration exercises.

Before you begin

To complete these tutorials, you must:

- Complete the instructions at https://devops.pingidentity.com/get-started/introduction/ 2.
- Have access to Git.

· Increase your Docker memory limit to at least 4 GB.

To change this setting, go to **Docker Dashboard** \rightarrow **Settings** \rightarrow **Resources** \rightarrow **Advanced**.

The tutorials provide sample requests that use **curl**. However, you can use any program that can send HTTP request, such as **wget** or Postman.

Setting up your environment

About this task

To help you get started quickly with PingAuthorize, we provide Docker containers that have everything you need. Deploy these containers using Docker commands and then start using PingAuthorize.

Steps

1. Clone the GitHub repository that contains the supporting source files.

Replace the variable *<X.X>* with the first two digits of the PingAuthorize release you want to clone.

```
git clone --branch <X.X> https://github.com/pingidentity/pingauthorize-tutorials && cd
pingauthorize-tutorials
```

This command places the files in the **pingauthorize-tutorials** directory and changes to that directory. The directory contains a **docker-compose.yml** file that defines the containers used in the tutorial.

You shouldn't need to modify this file or understand its contents to follow the tutorial steps. However, you might need to change some configuration values that the Docker Compose environment uses. The env-template.txt file contains various configuration values, including the default port definitions used by the Docker Compose containers.

2. Copy the template to a new .env file at the root of the cloned repository and edit its contents using any text editor.

```
cp env-template.txt .env
vi .env
```

You might not need to modify any values if all the default ports are available.

(i) Note You must still have an .env file in place for the environment to start.

Starting PingAuthorize

About this task

To start the Docker Compose environment:

Steps

- 1. Go to the pingauthorize-tutorials directory you cloned in Setting up your environment.
- 2. Run the following command.

docker-compose up --detach

Verifying proper startup

About this task

The command shows the status of the containers started by the **docker-compose** command. Each of the four containers should initially have a status of **starting**. All four containers should reach an equilibrium state of **healthy**.

Steps

• To verify that both PingAuthorize Server and Policy Editor started properly and are running, run the following command.

```
docker container ls --format '{{ .Names }}: {{ .Status }}'
```

(i) Note

It could take up to 15 minutes for all four containers to reach this equilibrium state.

• If you have any issues, check the log files using the docker-compose logs command.

Accessing the GUIs

About this task

PingAuthorize has two GUIs:

- Administrative console
- Policy Editor

O Tip

If you have problems connecting because of self-signed certificates, click **Advanced** or try a different browser.

Steps

• Access either the administrative console or the Policy Editor.

Choose from:

• To make configuration changes to PingAuthorize Server, access the administrative console.

Description	Details
URL	https://localhost:5443/console/login ^亿

Description	Details	
Details to enter at sign-on	 Server: pingauthorize :1636 Username: administrator Password: 2FederateM0re 1 Note If submitting the form results in a Server unavailable error, wait longer for the containers to reach an equilibrium healthy state, as described in Verifying proper startup. 	

 $\,\circ\,$ To make and test policy changes, access the Policy Editor.

This GUI calculates decision responses when you configure PingAuthorize to use the GUI as an external policy decision point.

Description	Details
URL	https://localhost:8443 ^亿
Details to enter at sign-on	 User ID: admin Password: password123

Stopping PingAuthorize

About this task

If you have completed the tutorials and no longer need the containers, run the following commands to stop and remove the containers.



To simplify the prerequisites for using Docker with this tutorial, all of the changes you make are lost when you destroy your Docker Compose environment. For standard installations, use persistent volumes to maintain data across container deployments.

Steps

- 1. Go to the pingauthorize-tutorials directory you cloned in Setting up your environment.
- 2. Run the following command.

docker-compose down

About the tutorial configuration

We provide the following pre-configured Docker containers through the Docker Compose environment, so that you can develop policies immediately.

Container	Description
pingauthorize	<i>PingAuthorize Server</i> The server enforces the policies you define.
pingauthorizepap	<i>PingAuthorize Policy Editor</i> Use this GUI to define the policies that determine access control and protect your data.
pingdirectory	<i>PingDirectory</i> A directory of user information.
	Note PingAuthorize doesn't require PingDirectory. However, some of the tutorials do use PingDirectory as an attribute provider. You can reference the attributes in your policies.
pingdataconsole	<i>administrative console</i> Use this GUI to configure PingAuthorize.

Tutorial 1: Importing default policies

This tutorial describes how to use the PingAuthorize Policy Editor to import default attribute-based access control policies. It also introduces the Trust Framework and describes the default policies.

About this task

Before you can begin writing policies, you must import the default policies from a snapshot file. This file contains a minimal set of policies and the default Trust Framework. The Trust Framework defines the foundational elements that you use to build policies, such as application programming interface (API) services, HTTP methods, and HTTP requests.

The default policies and Trust Framework are stored in a snapshot file named **defaultPolicies.SNAPSHOT**, which is bundled with both PingAuthorize Server and the Policy Editor. You must base all policies that you create for use with PingAuthorize on the policies and Trust Framework entities defined in this file.

To use the default policies that are distributed with PingAuthorize Server:

Steps

1. Copy defaultPolicies.SNAPSHOT from the PingAuthorize Policy Editor container to the current directory on your computer using the following command.

Note Be sure to include the trailing . character.
<pre>docker cp {PAP_CONTAINER_NAME}:/opt/out/instance/resource/policies/defaultPolicies.SNAPSHOT .</pre>

- 2. Sign on to the Policy Editor using the URL and credentials from Accessing the GUIs.
- 3. In the Import a Branch from a Snapshot section, click Snapshot and select the file that you just copied to your computer.
- 4. In the Name field, enter PingAuthorize Tutorials.

	Or	
Import a Snapshot	Branch from a Snapshot defaultPolicies.SNAPSHOT	×
Name	PingAuthorize Tutorials	Import

5. Click Import.

Result:

The Policy Editor displays the **Version Control** page. From this page, you can manage policy changes similar to how you would in a software source control system.

6. To select the policy branch that you just created, click **PingAuthorize Tutorials**.

Result:

A **Commits** table opens. This table provides a log of all changes made to a policy branch.

7. Click the expand arrow at the left of the top line for **Uncommitted Changes**.

Result:

This opens a list of all changes to the policy branch that are yet to be committed. In this case, the list includes all of the contents of the snapshot that you just imported.

Options	Commit Message		Commite	d on	Creator	Approvals
i≡	Uncommitted Changes		N/A		N/A	
Changes						
Entity Type	Name	Operation	Changed on	Creator	Entity Details	Revert
PolicySet	Global Decision Point	CREATE	3/22/2021, 11:14:59 AM	admin	0	S
PolicySet	PDP API Endpoint Policies	CREATE	3/22/2021, 11:14:59 AM	admin	0	Э
Policy	Token Validation	CREATE	3/22/2021, 11:14:59 AM	admin	0	I
Policy	Token Authorization	CREATE	3/22/2021, 11:14:59 AM	admin	0	C
Rule	Access token is inactive	CREATE	3/22/2021, 11:14:59 AM	admin	0	E
Rule	Permitted SCIM scope for user	CREATE	3/22/2021, 11:14:59 AM	admin	0	Ð
Rule	Token does not contain PDP scope	CREATE	3/22/2021, 11:14:59 AM	admin	0	Э
Rule	Permitted OAuth client	CREATE	3/22/2021, 11:14:59 AM	admin	0	C
Target	Inline target	CREATE	3/22/2021, 11:14:59 AM	admin	0	C
Target	Inline target	CREATE	3/22/2021, 11:14:59 AM	admin	0	C
95 items					<	Page 1 of 10 >

8. Click Commit New Changes.

9. In the Commit Message field, enter Initial commit. Click Commit.

-	2 items	
Commit New Change	es ×	
Commit Message	Initial commit	
	Commit	1
		١
	licies, you can use the Policy Editor's version control feature to manage yo es by committing your changes every time you achieve a satisfactory wor	

Introduction to the Trust Framework and default policies

You can now use the Policy Editor with PingAuthorize Server. First though, explore the interface, paying particular attention to the **Trust Framework** and **Policies** sections in the left pane.

Trust Framework

state.

In the **Trust Framework** section, shown below, you define the foundational elements that you use to build policies and make access control decisions.

		Definitions Target Search	
>\$	Branch Manager	Domains Services Attributes Identity	Classes Identity Providers Identity Properties Actions Conditions Processors
•4	Trust Framework	+	Details History Test
	Policies	→ 🚫 Gateway	AccessToken
	Test Suite	→ Sutering → SHttpRequest	
	> API Reference Control Contro		JSON object representing the decoded access token that was passed from fields of the access token are consistent with those defined by RFC 7519, JS
		S audience	Parent HttpRequest
		Client_id	 Resolvers (1 total)
		<pre>issued_at issuer issuer issuer</pre>	• 🛊 Request
		Scope	+ Add Resolver

The Trust Framework provides several types of entities. The following table describes the ones you will use most.

Entity	Description	
Services	Services perform two functions. Most often, they represent a specific API service or API resource type to be protected by your policies. They can also define <i>policy information points</i> , external data sources (such as APIs or LDAP directory servers) that PingAuthorize can use to make policy decisions.	
Attributes	Attributes provide the context that informs fine-grained policy decisions. Attributes often correspond to elements of an HTTP request, such as an access token subject. However, you can obtain their values from a variety of sources.	
Actions	Actions label the type of a request and generally correspond to HTTP methods (GET, POST, and so on) or CRUD actions (create, delete, and so on).	


Look at the Trust Framework's default attributes and consider how you could use them in your own policies. Some important Trust Framework attributes include those in the following table.

Attribute	Description
HttpRequest.AccessToken	This is the introspected or deserialized access token from the HTTP request.
HttpRequest.RequestBody	This is the HTTP request body, typically present for POST, PUT, and PATCH operations.
HttpRequest.ResponseBody	This is the upstream API server's HTTP response body.

Attribute	Description
SCIM.resource	For SCIM operations, this is the SCIM resource being retrieved or modified.
TokenOwner	For requests authorized using an access token, this is the user who granted the access token.

Policies

In the **Policies** section, shown below, you define your organization's access control policies.



You define your policies within a hierarchical tree that consists of two types of items.

Policy Set

A container for one or more policies.

Policy

A policy, which defines a set of rules that yield a policy decision when evaluated.

When the policy engine receives a policy request from PingAuthorize Server in response to an API call, it starts at the Global Decision Point and walks down the policy tree, first checking if each policy set or policy is applicable to the current policy request, and then evaluating the rules defined by each policy. Each rule returns a policy decision, typically PERMIT or DENY. Likewise, each policy might return a different policy decision. The policy engine evaluates an overall decision using *combining algorithms*.

The default policy tree contains the following policy sets and policies:

Global Decision Point

This is the root of the policy tree. Place all other policy sets or policies under this point. This node's combining algorithm is set to **A single deny will override any permit**. This algorithm requires no denies and at least one policy to permit the API call.

Token Validation

For most cases, this is the only default policy. It checks for a valid access token. In combination with the Global Decision Point combining algorithm, this is rather permissive. Any API caller can succeed with a valid access token.

PDP API Endpoint Policies

The PingAuthorize Server XACML-JSON PDP API uses these policies. They are not discussed further in this tutorial.

You will use the following items in the UI in a tutorial.

Library

The default policy library contains example statements and rules.

Decision Visualiser

You will use this tool to examine policy decisions in detail.

Tutorial 2: Configuring fine-grained access control for an API

This tutorial shows you how to set up PingAuthorize for attribute-based access control of a JavaScript Object Notation (JSON) REST application programming interface (API).

API access control is often categorized in terms of granularity.

Access control granularity type	Description
Coarse-grained	Users or clients have access to all of or none of an application or API.
Medium-grained	Users or clients have access to some pages or resources within an application or API.
Fine-grained	Users or clients can take specific actions on an application page or an API resource when <i>action-specific conditions</i> are met. For example, a request to transfer bank funds might be denied if the amount exceeds the average of recent transfers by 20% or more.

Scenario

For this tutorial, you are the producer of an online game in which players compete with friends to create the funniest meme. When starting a new game, the first player optionally invites other players using their email addresses. To prevent email spam, you must create a policy that blocks a user from starting a new game with other players if the user's email address comes from a generic mail domain. Game activities are represented using an example Meme Game API

) Νote

The above link directs you to the Meme Game API Git project, where you can build and run the API. You can access the API server with specific API paths, such as meme-game.com/api/v1/answers.

Tasks

This tutorial teaches you how to configure two fine-grained API access control rules by walking you through the following tasks:

- 1. Configure a reverse proxy for the Meme Game API.
- 2. Test the reverse proxy.
- 3. Add a policy for the Meme Game API's Create Game endpoint.
- 4. Test the policy from the Policy Editor.
- 5. Test the reverse proxy by making an HTTP request.
- 6. Modify the rule for the Meme Game API's Create Game endpoint.

The following sections provide the details for completing these tasks.

Configuring a reverse proxy for the Meme Game API

Configure a reverse proxy by configuring an API External Server and a Gateway API Endpoint. The API reverse proxy acts as an intermediary between your HTTP client and the HTTP API, providing fine-grained access control for the API.

Steps

- 1. Configure an API External Server for the Meme Game API. An API External Server controls how PingAuthorize Server handles connections to an HTTPS API server, including configuration related to TLS. In this case, we simply need to provide a base URL.
 - 1. Sign on to the administrative console using the URL and credentials from Accessing the GUIs.
 - 2. Click External Servers.
 - 3. Click New External Server and choose API External Server.
 - 4. For Name, specify Meme Game API.
 - 5. For **Base URL**, specify https://meme-game.com^[2].

The following image shows this configuration.

		View dsconfig Save	Cance
Name *	Meme Game API	0	
Description			0
Base URL *	https://meme-game.com	0	
Hostname Verification Method	strict 🗙 🗸 📀		
Key Manager Provider	The Java Runtime Environment's default key mana	0	
Trust Manager Provider	The Java Runtime Environment's default trust man	0	
SSL Cert Nickname	A certificate will be chosen from the key manager arbitrarily.	0	
Connect Timeout	30 s	0	

6. Click Save.

- 2. Configure a Gateway API Endpoint. A Gateway API Endpoint controls how PingAuthorize Server proxies incoming HTTP client requests to an upstream API server.
 - 1. In the administrative console, click Configuration and then Gateway API Endpoints.
 - 2. Click New Gateway API Endpoint.
 - 3. For Name, specify Meme Game Games.
 - 4. For Inbound Base Path, specify /meme-game/api/v1/games.

The inbound base path defines the base request path for requests to be received by PingAuthorize Server.

5. For Outbound Base Path, specify /api/v1/games.

The outbound base path defines the base request path for requests that PingAuthorize Server forwards to an API server.

6. For API Server, specify Meme Game API. This is the API External Server you defined previously.

-	API Endpoint	uthorize Server Gateway, w	hich acts as a facade and policy enforceme	ent point
		View API commands	Save To PingAuthorize Server Cluster	Cancel
General Configura	tion			
Name *	Meme Game - Games	0		
Description			0	
Error Template	If no error template is specified, then a default error	0	2	
Correlation ID Header	The correlation-id-response-header property of the HTTP Connect	0		
Inbound Base Path *	/meme-game/api/v1/games	0		
Outbound Base Path *	/api/v1/games	0		
API Server *	Meme Game API X - Y	0		

7. Save your changes.

Testing the reverse proxy

PingAuthorize Server is now configured to accept HTTP requests beginning with the path /meme-games/api/v1/games and forward them to the Meme Game API. Before proceeding, we will confirm that this configuration is working by making a request to the Meme Game API through the PingAuthorize Server.

About this task

These tutorials use **curl** to make HTTP requests.

The Meme Game API provides an API to create a new game, which looks like this:

```
POST /api/v1/games
{
    "data": {
        "type": "game",
        "attributes": {
            "invitees": ["friend@example.com"]
        }
    }
}
```

We configured a Gateway API Endpoint to forward any requests to /meme-game/api/v1/games to the Meme Game API endpoint.

Steps

• Send a request using curl.

```
curl --insecure --location --request POST 'https://localhost:7443/meme-game/api/v1/games' \
--header 'Authorization: Bearer { "active": true, "sub": "user.99@example.com" }' \
--header 'Content-Type: application/json' \
--data-raw '{
    "data": {
        "type": "game",
        "attributes": {
            "invitees": {
               "invitees": [
               "user.99@example.com"
            ]
            }
        }
    }
}'
```

This example uses *Bearer token authorization* with a *mock access token*. For an explanation of this authorization, see For further consideration: The PingAuthorize API security gateway, part 1.

Result:

If the PingAuthorize Server is configured correctly, then the response status should be **201 Created** with a response body like the following.

```
{
    "data": {
        "id": "130",
        "type": "games"
    },
    "meta": {}
}
```

For further consideration: The PingAuthorize API security gateway, part 1

Additional concepts to consider include request routing and Bearer token authorization.

Request routing

You configure request routing by defining a Gateway API Endpoint in the PingAuthorize Server configuration. Each Gateway API Endpoint determines which incoming HTTP requests are proxied to an API server and how PingAuthorize Server translates the HTTP request into a policy decision request.

Bearer token authorization

The testing in Testing the reverse proxy uses this authorization. The token itself is a *mock access token*, which is a special kind of Bearer token that a PingAuthorize Server in test environments can accept. A mock Bearer token is formatted as a single line of JSON, with the same fields used in standard JWT access tokens, plus a boolean "active" field, which indicates whether the token should be considered valid. When you use mock access tokens, you do not need to obtain an access token from an actual OAuth 2 auth server, which saves you time during testing.

Adding a policy for the Create Game endpoint

Now that we have confirmed that PingAuthorize Server is correctly configured to act as a reverse proxy to the Meme Game API, we can define a policy to try out its access control capabilities. This policy will accept or deny a request to create a game based on the identity making the request.

About this task

First, we define a *service* in the **Trust Framework**. Services have various uses, but at their most basic level, you use them to define a specific API that can be governed by your policies. By defining different services in your Trust Framework, you can **target each** policy specifically to their applicable APIs.

Then, we define a policy. This policy will reject any requests to start a new meme game if the user's identifier ends with @example.com. We will identify users using the subject of the request's access token.

Steps

- 1. Define the service.
 - 1. Sign on to the Policy Editor using the URL and credentials from Accessing the GUIs.
 - 2. Go to Trust Framework and click Services.
 - 3. From the + menu, select Add new Service.
 - 4. For the name, replace Untitled with Meme Game Games.

The service name must match the endpoint name. To understand why, see For further consideration: The PingAuthorize API security gateway, part 2.

5. Verify that in the Parent field, no parent is selected.

To remove a parent, click the delete icon to the right of the **Parent** field.

🗱 Meme Game - Gan	nes	•
Description		
		8
Parent	no parent selected	•
 Service Settings 		
Service Type	None	•

6. Click Save changes.

2. Define the policy.

- 1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.
- 2. Select Global Decision Point.
- 3. From the + menu, select Add Policy.
- 4. For the name, replace **Untitled** with Users starting a new game.
- 5. Click + next to Applies to.
- 6. In the upper-right corner of the left pane, click **Components**. This reveals a tree of items to target the policy and restrict the types of requests to which the policy applies.
- 7. From the Actions list, drag inbound-POST to the Add definitions and targets, or drag from Components box.
- 8. From the Services list, drag Meme Games Games to the Add definitions and targets, or drag from Components box.

Using these components restricts the policy to incoming POST requests and the Meme Games - Games service.

- 9. Set the Combining Algorithm to Unless one decision is deny, the decision will be permit.
- 10. Click **+** Add Rule. This reveals an interface to define a condition. Define the rule as follows.
 - 1. For the name, replace **Untitled** with **Deny if token subject ends with @example.com**.
 - 2. For Effect, select Deny.
 - 3. Specify the condition.
 - 1. Click + Comparison.
 - 2. From the Select an Attribute list, select HttpRequest.AccessToken.subject.
 - 3. In the second field, select **Ends With**.
 - 4. In the third field, type @example.com.

The following screen shows the rule.

escription		
Applies to		
🕞 Add defi	itions and targets, or drag from Components O All Requests	
- When ALL ANY A HttpR + Compariso	NONE CLEAR ALL quest.AccessToken.subject Ends With + Named Condition + Group	
Effect		
Effect	Jeny	

11. Click Save changes.

For more information about API security gateway processing, see For further consideration: The PingAuthorize API security gateway, part 2.

For further consideration: The PingAuthorize API security gateway, part 2

Additional concepts to consider include the phases of API security gateway processing and the need for the service name to match the Gateway API Endpoint name.

API security gateway processing occurs in two phases

The inbound phase

When the API security gateway receives an HTTP request, it generates a policy request with an action label including the phase and the HTTP method, such as **inbound-POST** or **inbound-GET**. Based on the result returned by the policy engine, the request might be rejected immediately or it might be forwarded to the API server, potentially with modifications.

The following diagram illustrates the inbound request processing.

Inbound request processing HTTP client

PingAuthorize^{**}



2. Policy request

3. Policy decision



API Security Gateway

Policy Engine


4. Forwarded HTTP request

The outbound phase

When the API server returns an HTTP response to the API security gateway, another policy request is generated, again with an action label including the phase and HTTP method, such as **outbound-POST** or **outbound-GET**. Based on the result returned by the policy engine, the response might be modified, and then it is forwarded back to the HTTP client.

The following diagram illustrates the outbound request processing.

Outbound request processing



PingAuthorize[™] 2. Policy request 3. Policy decision **API** Security Gateway Policy Engine 4. Final HTTP response



Service name must match Gateway API Endpoint name

In Adding a policy for the Create Game endpoint, we named the service to match the name of the Gateway API Endpoint in the PingAuthorize configuration. This is important. When PingAuthorize receives an HTTP request, it generates a *policy request* that represents the HTTP request and sends it to its policy engine for processing. The policy request will include a service field, and its name will be the name of the Gateway API Endpoint that handled the HTTP request.

Testing the policy from the Policy Editor

We can now test the policy and make sure that it works as we intend. First, we test the policy directly from the Policy Editor's test interface.

Steps

- 1. In the Policy Editor, click the **Test** tab at the top of the main pane to display the test interface.
- 2. Fill out the **Request** section. The test uses this information to simulate the policy request that PingAuthorize Server makes when it receives an HTTP request.

Description	Details
Service	Meme Games - Games
Action	inbound-POST
Attributes	<pre>HttpRequest.AccessToken { "active": true, "sub": "user.99@example.com" }</pre>

The following image shows the test.

ng Scenario Tests				
Request				
Domain	Select to add Domain to the testing scenario	•		
Service	Meme Game - Games -	Ŵ		
Identity Provider	Select to add Identity Provider to the testing scenario	•		
Action	inbound-POST -			
Attributes	Sector {"active": true, "sub": "user.99@example.com"}			
	Select an attribute to add it to the testing scenario	•		
Overrides				
Attributes	Select an attribute to add it to the testing scenario	•		
Services	Select a service to add it to the testing scenario	•		

3. Click Execute.

Result:

The policy test result displays. If the policy worked as expected, the leftmost result is red, indicating a **DENY** result.

Details History Test			
Users starting a new game			
Testing Scenario Tests Test Results \times Test Results \times	Test Results ×		
Visualisation Request Response Output Attributes	Services		
Users starting a new game		 Deny if token subject ends with @example.com 	
8	°8		
PermitUnlessDeny	′		
<1	ns		<1 ms

4. Optional: Experiment with testing.

Click the **Testing Scenario** tab and try different inputs to see how the policy result changes. For example, change the **HttpRequest.AccessToken** attribute value to { "active": true, "sub": "user.99@my-company.com" }. The policy result is now **PERMIT**, as shown in the following image.

Details History Test		
🖹 Users starting a new gam	ne	
Testing Scenario Tests Test Res	sults × Test Results ×	
Visualisation Request Respons	se Output Attributes Services	
Users starting a new	<i>w</i> game	 Deny if token subject ends with @example.com
\bigcirc	PermitUnlessDeny	N/A
	<1 ms	<1 ms

Testing the policy by making an HTTP request

Having tested the policy from the Policy Editor to prove the policy works as intended, we can confirm that policy enforcement from end-to-end by sending an HTTP request through the PingAuthorize Server reverse proxy.

Steps

1. Send a request using curl.

```
curl --insecure --location --request POST 'https://localhost:7443/meme-game/api/v1/games' \
--header 'Authorization: Bearer { "active": true, "sub": "user.99@example.com" }' \
--header 'Content-Type: application/json' \
--data-raw '{
    "data": {
        "type": "game",
        "attributes": {
            "invitees": [
            "user.99@example.com"
        ]
        }
    }
}'
```

Result:

You should receive an error response with a response status of 403 Forbidden.

The request has an access token value of { "active": true, "sub": "user.99@example.com" }. The sub field of the access token corresponds to the HttpRequest.AccessToken.subject Trust Framework attribute that your policy uses to make its decision.

2. As an experiment, edit the access token value in **curl** to change the **sub** value to an email address for a different domain. What should happen with this new request?

Send a request using **curl**.

```
curl --insecure --location --request POST 'https://localhost:7443/meme-game/api/v1/games' \
--header 'Authorization: Bearer { "active": true, "sub": "user.99@my-company.com" }' \
--header 'Content-Type: application/json' \
--data-raw '{
    "data": {
        "type": "game",
        "attributes": {
            "invitees": [
            "user.99@example.com"
        ]
        }
    }
}'
```

Result:

The HTTP response status should now be 201 Created.

To better understand how policy decisions work, see For further consideration: Decision Visualiser.

For further consideration: Decision Visualiser

Returning to the Policy Editor, we can view a log of how the policy engine handled the HTTP request.

Steps

- 1. In the Policy Editor, go to Policies and click Decision Visualiser.
- 2. Click the **Recent Decisions** tab. The two most recent items listed correspond to your last HTTP request and response. The first item should correspond to the HTTP response, while the second item should correspond to the HTTP request.
- 3. Click the second decision. Its visualization appears.
- 4. Click the **Request** tab. This displays a JSON representation of the policy request that PingAuthorize generated to represent your HTTP request.

The following image shows a request example:

PingAuthorize

S Recent Decisions Paste Logs		Visualisation Request Response Output Attributes Services
PERMIT 2020-09-10 19:29:06	G	{ "domain": "", "service": "Meme Game - Games",
PERMIT 2020-09-10 19:29:06		"identityProvider": "Mock Access Token Validator", "action": "inbound-POST", "attributes": {
OENY 2020-09-10 19:28:28		"HttpRequest.RequestBody": "{\"data\":{\"type\":\"game\",\"attributes\":{\"invited" "HttpRequest.CorrelationId": "72b49636-f86e-405a-beec-3d9c4e2c16db", "HttpRequest.RequestURI": "https://calamity.local:7443/meme-game/api/v1/games",
PERMIT 2020-09-10 19:27:15		"HttpRequest.IPAddress": "172.29.0.1", "Gateway": "{\"_BasePath\":\"/meme-game/api/v1/games\"}", "HttpRequest.RequestHeaders": "{\"Authorization\":[\"Bearer { \\\"active\\\": true "HttpRequest.ResponseHeaders": "{}",
PERMIT 2020-09-10 19:27:14		<pre>"HttpRequest.AccessToken": "{\"access_token\":\"{ \\\"active\\\": true, \\\"sub\\\ } }</pre>
PERMIT 2020-09-10 19:23:16		
PERMIT 2020-09-10 19:23:04		

5. Click the **Response** tab. This displays a JSON representation of the policy response that the policy engine returned after evaluating your policy.

Here is a response example.

Policies Library Target S	Search Decision Visualiser
③ Recent Decisions Paste Logs	Visualisation Request Response Output Attributes Services
 PERMIT 2020-09-10 19:29:06 	<pre>{</pre>
 PERMIT 2020-09-10 19:29:06 	"timestamp": "2020-09-11T00:29:06.338726Z", "elapsedTime": 5578, "request": {
OENY 2020-09-10 19:28:28	"domain": "", "service": "Meme Game – Games", "identityProvider": "Mock Access Token Validator", "action": "inbound-POST".
 PERMIT 2020-09-10 19:27:15 	"action : "Inbound-POSI", "attributes": { "HttpRequest.RequestBody": "{\"data\":{\"type\":\"game\",\"attributes\":{\"inv "HttpRequest.CorrelationId": "72b49636-f86e-405a-beec-3d9c4e2c16db",
PERMIT 2020-09-10 19:27:14	"HttpRequest.RequestURI": "https://calamity.local:7443/meme-game/api/v1/games" "HttpRequest.IPAddress": "172.29.0.1", "Gateway": "{\"_BasePath\":\"/meme-game/api/v1/games\"}",
PERMIT 2020-09-10 19:23:16	"HttpRequest.RequestHeaders": "{\"Authorization\":[\"Bearer { \\\"active\\\": "HttpRequest.ResponseHeaders": "{}", "HttpRequest.AccessToken": "{\"access_token\":\"{ \\\"active\\\": true, \\\"su
PERMIT 2020-09-10 19:23:04	} }, "decision": "PERMIT", "authorised": true

Both the policy request and the policy response might be hard to understand at the moment, but as you become familiar with PingAuthorize and its policy engine, you'll find that the Decision Visualiser is indispensable for troubleshooting and understanding your policies.

Modifying the rule for the Create Game endpoint

Now that we have defined a policy that permits or denies the ability to create a game based on the email address of the person creating the game, we will modify the rule so that any user can create a game, but only those with real email addresses can create games with invitees. This section demonstrates how a policy can take an action based on data in the request body.

About this task

To review, the Meme Game API offers a game creation endpoint that looks like this:

```
POST /api/v1/games
{
    "data": {
        "type": "game",
        "attributes": {
            "invitees": ["friend@example.com"]
        }
    }
}
```

The requester specifies one or more invitees using the data.attributes.invitees field. We will update our policy with a second rule that disallows a new game if anybody else is invited to it.

Steps

- 1. Define a Trust Framework attribute to represent the data.attributes.invitees field.
 - 1. In the Policy Editor, go to Trust Framework and click Attributes.
 - 2. From the + menu, select Add new Attribute.
 - 3. For the name, replace Untitled with Meme Game invitees.
 - 4. Verify that in the **Parent** field, no parent is selected.

To remove a parent, click the delete icon to the right of the **Parent** field.

- 5. Click the + next to **Resolvers** and click + Add Resolver.
- 6. Set Resolver type to Attribute.
- 7. Select the attribute HttpRequest.RequestBody.
- 8. Click the + next to Value Processors and click + Add Processor.
- 9. Set Processor to JSON Path.
- 10. Set the value to \$.data.attributes.invitees.
- 11. Set Value type to Collection.
- 12. For Value Settings, select Default value and specify square brackets ([]) to indicate an empty collection.
- 13. Set Type to Collection.

14. Click Save changes.

The following image shows the new attribute.

Details History Test			
🚫 Meme Game invitees			=
Description			
Parent	no parent selected		
 Resolvers (1 total) 	no parent selected		-
- Attribute - Reques	tBody		=
 Resolve attribute using 	7		
Resolver type Att	ribute	✓ HttpRequest.RequestBody	•
+ Add Resolver			
 Value Processors (1 total)		
Untitled JSON Pat	h Processor		
Processor	JSON Path 🗸	\$.data.attributes.invitees	\bigtriangledown
Value type	Collection -		
+ Add Processor			
 Value Settings 			
Default value			li.
Туре	Collection	✓ Secret	

This Trust Framework attribute introduces resolvers and value processors, which are two important components. To better understand these components, see For further consideration: Resolvers and value processors.

- 2. Modify a rule to use the Meme Game invitees attribute we just created.
 - 1. In the Policy Editor, go to Policies.
 - 2. Select the Users starting a new game policy.
 - 3. Rename the **Deny if token subject ends with @example.com** rule to Deny if token subject ends with @example.com AND request contains invitees.
 - 4. Expand the rule by clicking its + icon.
 - 5. For Effect, select Deny.
 - 6. Specify a second comparison.
 - 1. Click + Comparison.
 - 2. From the Select an Attribute list, select Meme Game invitees.

3. In the second field, select **Does Not Equal**.

4. In the third field, type [].

7. Click Save changes.

The following image shows the rule.

Applies to					
🔒 Add	efinitions and targets, or drag from Com	ponents O All Requests			
- When					
ALL A	Y NONE CLEAR ALL				
E A	HttpRequest.AccessToken.subject	- Ends With	- C	@example.com	t
1 A	Meme Game invitees	- Does Not Equal	• - C	0	1
+ Con	parison + Named Condition	+ Group			
Effect					
LINCOL					

3. Test the policy.

As before, you can test your policy by sending an HTTP request or using the Policy Editor test interface. Try testing using the following combinations of inputs:

- An access token with the subject <code>user.0@example.com</code> and with invitees.
 - This should be denied.
- An access token with the subject user.0@my-company.com and with invitees.

This should be permitted.

• An access token with the subject user.0@example.com and no invitee list.

This should be permitted.

• An access token with the subject user.0@my-company.com and no invitee list.

This should be permitted.

For further consideration: Resolvers and value processors

Resolvers and value processors are key components in defining policies.

Modifying the rule for the Create Game endpoint introduces their use. Here is more about how you use them in your policies.

Resolvers

A resolver defines the source of an attribute's value. In this case, the source is the **HttpRequest.RequestBody** policy request attribute, which is set automatically by PingAuthorize Server. Many other types of sources are available; for example, a resolver might define an attribute value using a constant, or a resolver might call out to an external API to obtain the attribute value.

Value Processors

Value processors extract and transform values from the source value provided by the resolver. In this case, a value processor uses a JSONPath expression to extract the value of a specific field from the HTTP request body provided by the resolver.

Conclusion

In this tutorial about fine-grained access control, you added anti-spam protections to the Meme Game API by blocking requests using certain email addresses. In doing so, you learned how to configure PingAuthorize Server to act as a reverse proxy to a JSON API. You then learned how to use the PingAuthorize Policy Editor to create a fine-grained access control policy with rules that take effect based on the access token and body of an HTTP request. You also learned how to test policies and inspect policy requests using the Policy Editor.

You also learned:

- Gateway API Endpoint names in the PingAuthorize Server configuration must match Trust Framework Service names in the Policy Editor.
- Policies can pinpoint different API services and HTTP verbs.
- Policies can PERMIT or DENY transactions based on any combination of attributes.
- Mock access tokens make testing very easy.
- Trust Framework attributes obtain their values using resolvers and transform their values using processors.
- PingAuthorize Server supplies Attributes for HTTP metadata, request data, and OAuth 2 access token attributes.
- You can test policies directly from the Policy Editor.
- The Policy Editor's Decision Visualiser gives you a detailed view of recent policy decisions.

Tutorial 3: Configuring attribute-based access control for API resources

This tutorial describes how to build and test fine-grained access control (FGAC) policies that restrict access to a protected resource based on attributes of both the resource and the caller.

Scenario

In some data use cases, it is necessary to know both the resource being requested and the requesting user. For example, a counselor can only view the records of students in their department. In the scenario of the meme game, users are allowed to invite their friends or family to like or critique their memes. Because some memes are inappropriate for younger audiences, the city of Youngstown, Ohio passes an ordinance that does not allow you to serve its citizens memes rated for ages 13 and older. You must create a policy to enforce this by checking the city of the user's profile and the age rating of the shared meme.

γ Νote

Obviously, not all Youngstown residents are young. In a more realistic scenario, we might compare the age of the requesting user to the age rating of the meme. However, computing the user's age from their date of birth adds unnecessary complexity.

Tasks

This tutorial teaches you how to configure attribute-based application programming interface (API) access control rules by walking you through the following tasks:

- 1. Configure a proxy for the Meme Game API.
- 2. Create a policy blocking all users from viewing shared memes.
- 3. Add policy condition logic to allow users not from Youngstown to view shared memes.
- 4. Add policy condition logic to allow users from Youngstown to view shared memes rated for ages under 13.
- 5. Add a statement to set the API error response when a policy blocks access.

The following sections provide the details for completing these tasks.

Configuring the API security gateway

This tutorial describes how to use the API security gateway to allow requests to a parameterized endpoint.

You will configure https://localhost:7443/meme-game/api/v1/users/{user}/answers to proxy to https://meme-game.com/ api/v1/users/{user}/answers, where user can be any username.

Creating the gateway API endpoint

Configure a reverse proxy by configuring an API External Server and a Gateway API Endpoint.

Steps

1. **Optional:** Configure an API External Server for the Meme Game API. An API External Server controls how PingAuthorize Server handles connections to an HTTPS API server, including configuration related to TLS. In this case, we simply need to provide a base URL.

(i) Note

If you completed Tutorial 2: Configuring fine-grained access control for an API, then you already set up this API External Server.

- 1. Sign on to the administrative console using the URL and credentials from Accessing the GUIs.
- 2. Click External Servers.

- 3. Click New External Server and choose API External Server.
- 4. For Name, specify Meme Game API.
- 5. For **Base URL**, specify https://meme-game.com^[].

The following image shows this configuration.

New API External Server API External Servers are used by Gateway API Endpoints to specify connections to external API servers using HTTP or HTTPS.				
		View dsconfig Save Canc	el	
Name *	Meme Game API	Ø		
Description		6	>	
Base URL *	https://meme-game.com	0		
Hostname Verification Method	strict 🗙 🗸 📀			
Key Manager Provider	The Java Runtime Environment's default key mana	• @		
Trust Manager Provider	The Java Runtime Environment's default trust man	• @		
SSL Cert Nickname	A certificate will be chosen from the key manager arbitrarily.	Ø		
Connect Timeout	30 s	Ø		
Response Timeout	30 s	Ø		

6. Click Save.

- 2. Configure a Gateway API Endpoint. A Gateway API Endpoint controls how PingAuthorize Server proxies incoming HTTP client requests to an upstream API server.
 - 1. In the administrative console, click **Configuration** and then **Gateway API Endpoints**.

2. Click New Gateway API Endpoint.

- 3. For Name, specify Meme Game Shared Answers.
- 4. For Inbound Base Path, specify /meme-game/api/v1/users/{user}/answers.

The inbound base path defines the base request path for requests to be received by PingAuthorize Server.

By surrounding a value in curly braces, you can add a parameter to a gateway API endpoint's **inbound-base-path** and use it to fill in a parameter of the same name in the outbound path. You can also use this parameter to inform other elements of the policy request, such as the service.

5. For Outbound Base Path, specify /api/v1/users/{user}/answers.

The outbound base path defines the base request path for requests that PingAuthorize Server forwards to an API server.

6. For **API Server**, specify Meme Game API. This is the API External Server you defined in **Configuring a reverse proxy** for the Meme Game API.

Your screen should look like the following one.

New Gateway API Endpoint A Gateway API Endpoint represents an endpoint at an API service that is protected by the PingAuthorize Server Gateway, which acts as a facade and policy enforcement point (PEP) for the API service.				
	View API commands Save To PingAuthorize Server Cluster Cancel			
General Configura	tion			
Name *	Meme Game - Shared Answers			
Description				
Error Template	If no error template is specified, then a default error			
Correlation ID Header	The correlation-id-response-header property of the HTTP Connecti			
Inbound Base Path *	/meme-game/api/v1/users/{user}/answers			
Outbound Base Path *	/api/v1/users/{user}/answers			
API Server *	Meme Game API X - C			

7. Save your changes.

Testing the gateway

You can test the newly created Gateway API Endpoint with cURL or Postman.

Steps

• Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers ^[2]. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers \
    -H 'Authorization: Bearer {"active": true, "sub": "user.0"}'
```

Result:

You should get a 200 OK response with a JSON response body that contains a series of answers in an array titled data.

Creating a policy based on user credentials

This tutorial describes how to create a policy that acts on information about the user.

Creating a service for the Shared Answers endpoint

Create a service in the Trust Framework to ensure that our policy only affects requests to our new endpoint.

About this task

This task passes the name of the Gateway API Endpoint configured in PingAuthorize Server as the service to the PingAuthorize policy decision point (PDP).

Steps

- 1. From the PingAuthorize Policy Editor, go to Trust Framework and click Services.
- 2. From the + menu, select Add new service.
- 3. For the name, replace **Untitled** with Meme Game Shared Answers.
- 4. Verify that, in the **Parent** field, no parent is selected.

To remove a parent, click the delete icon to the right of the Parent field.

Your service should look like the example in the following image:

Details History Test		
🗱 Meme Game - Share	ed Answers	≡
Description		
Parent	no parent selected	•
 Service Settings 		
Service Type	None	•

5. Click Save changes.

Creating a policy for the Shared Answers endpoint

Create a policy to prevent users from accessing the Shared Answers endpoint.

Steps

- 1. In the PingAuthorize Policy Editor, go to the **Policies** tab.
- 2. Select Global Decision Point.
- 3. From the + menu, select Add Policy.
- 4. For the name, replace **Untitled** with **Users viewing shared memes**.
- 5. Click + next to Applies to.
- 6. In the upper-right corner of the left pane, click **Components**.
- 7. From the Actions list, drag outbound-GET to the Add definitions and targets, or drag from Components box.
- 8. From the Services list, drag Meme Game Shared Answers to the Add definitions and targets, or drag from Components box.
- 9. For the combining algorithm, select Unless one decision is permit, the decision will be deny.

10. Click Save changes.

Your policy should look like the example in the following image:

Details History Test	
Users viewing shared memes	
Description	
	/
- Applies to	
Add definitions and targets, or drag from Components Add definitions and targets, or drag from Components 🔅 Meme Game - Shared Answers 🗵 🖗 outbound-GET 🗵	
+ Comparison + Named Condition	
- Rules (0 total)	
Combining Algorithm Unless one decision is permit, the decision will be deny	•

Testing the policy

You can test the new policy with cURL or Postman.

Steps

• Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1^[2]. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.0"}'
```

Result:

You should get a 403 Forbidden response with the following body.

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

Creating an attribute from user data

Create an attribute to represent the city the user lives in.

Steps

- 1. In the PingAuthorize Policy Editor, go to Trust Framework and click Attributes.
- 2. From the + menu, select Add new Attribute.
- 3. For the name, replace **Untitled** with city.
- 4. For Parent, select TokenOwner.
- 5. Click the + next to **Resolvers** and click + Add Resolver.
- 6. For Resolver type, select Attribute and specify a value of TokenOwner.
- 7. Click the + next to Value Processors and click + Add Processor.
- 8. For Processor, select JSON Path and specify a value of \$.1[0]. (The LDAP attribute 1 represents locality.)
- 9. For the processor's Value type, select String.
- 10. For Value Settings, set the Type to String.
- 11. Click Save changes.

Result:

You have an attribute for the user's city, as shown in the following image.

Details History Test			
🟷 city			=
Description			
Parent	TokenOwner		-
 Resolvers (1 total) 			
 Attribute - Token Resolve attribute usir 			Ξ
Resolver type A	ttribute	▼ TokenOwner	•
+ Add Resolver Value Processors (1 tota	al)		
- Untitled JSON Pa			
Processor	JSON Path	▼ \$.1[0]	\bigtriangledown
Value type	String	•	
+ Add Processor			
 Value Settings 			
Default value			
Туре	String	✓ Secret	

Adding logic to allow non-Youngstown users

Add a rule to the Users viewing shared memes API policy to allow users who are not from Youngstown to view answers.

Steps

- 1. From the PingAuthorize Policy Editor, go to the **Policies** tab.
- 2. Select Users viewing shared memes.
- 3. Click + Add Rule.
- 4. For the name, replace Untitled with Allow people outside of Youngstown.
- 5. For Effect, select Permit.
- 6. To specify a **Condition**, perform the following steps:
 - 1. Click **+ Comparison**.
 - 2. From the Select an Attribute list, select TokenOwner.city.
 - 3. In the second field, select **Does Not Equal**.
 - 4. In the third field, type Youngstown .

7. Click Save changes.

Result:

You have a rule that allows users from outside Youngstown.

escription	
Applies to	
Add definitions and targets, or drag from Components	
- When ALL ANY NONE CLEAR ALL A TokenOwner.city - Does Not Equal - C Youngstown + Comparison + Named Condition + Group	1
Effect	
Effect Permit	-

Testing that the policy blocks Youngstown users

You can test the new rule with cURL or Postman.

Steps

1. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1^[] as user.0. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.0"}'
```

Result:



```
{
    "data": {
    "id": "1",
    "type": "answers",
    "attributes": {
    "url": "https://i.imgflip.com/2fm6x.jpg",
    "captions": [
        "Still waiting for the bus to Jennie's"
    ],
    "rating": null,
    "created_at": "2020-05-06T22:25:06+00:00"
    }
    },
    "meta": {}
}
```

2. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1^C as user.660. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.660"}'
```

Result:

The user is from Youngstown, so the result is a 403 Forbidden response with the following body.

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

Creating a policy based on the API response

This tutorial describes how to create a policy that acts on information about the response received from the API server.

Creating an attribute from response data

Create an attribute to represent the age rating of the meme being requested.

Steps

- 1. From the PingAuthorize Policy Editor, go to Trust Framework and click Attributes.
- 2. From the + menu, select Add new Attribute.
- 3. For the name, replace Untitled with Meme game answer rating.
- 4. Verify that in the **Parent** field, no parent is selected.

To remove a parent, click the delete icon to the right of the Parent field.

- 5. Click the + next to **Resolvers** and click + Add Resolver.
- 6. For **Resolver type**, select **Attribute** and specify a value of **HttpRequest.ResponseBody**.
- 7. Click the + next to Value Processors and click + Add Processor.
- 8. For **Processor**, select **JSON Path** and specify a value of **\$.data.attributes.rating**.
- 9. For the processor's Value type, select Number.
- 10. For Value Settings, set the Type to Number.
- 11. Click Save changes.

Result:

You have a new attribute for the answer's age rating.

\$	Meme game answer ratin	g				•
Pa	rent no					///. •
-	Resolvers (1 total)					
	Attribute - Response	Body			=	∎
	 Resolve attribute using 					_
	Resolver type Attribu	ute	•	HttpRequest.ResponseB	3ody	
-	Add Resolver Value Processors (1 total)					
	Processor	JSON Path 👻	\$.data.attributes.rating		ę	\diamond
	Value type	Number 🔺				
+	Add Processor					
-	Value Settings					
	Default value					
	Туре	Number	•	Secret		
+	Caching					

Adding logic to allow family-friendly memes

Add a rule to the Users viewing shared memes API policy to allow users to view answers that are rated for ages under 13.

Steps

- 1. From the PingAuthorize Policy Editor, go to the **Policies** tab.
- 2. Select Users viewing shared memes.
- 3. Click + Add Rule.

- 4. For the name, replace **Untitled** with Anyone can view family-friendly answers.
- 5. For Effect, select Permit.
- 6. Specify a **Condition**.
 - 1. Click **+ Comparison**.
 - 2. From the Select an Attribute list, select Meme game answer rating.
 - 3. In the second field, select Less Than.
 - 4. In the third field, type 13.

7. Click Save changes.

Result:

Your new rule to allow family-friendly memes should look like the following image.

scription	
Applies to	
Add definitions and targets, or drag from Components	O All Requests
- When	
ALL ANY NONE CLEAR ALL	
A Meme game answer rating	- C 13
+ Comparison + Named Condition + Group	
Effect	
Effect Permit	

Testing that the policy blocks Youngstown users from viewing age 13+ memes

You can test the newly created rule with cURL or Postman.

Steps

1. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/2^[] as user.0. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/2 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.0"}'
```

Result:

When requesting answer 2 as user.0, expect a 200 OK response with the following body.

```
{
        "data": {
        "id": "2",
        "type": "answers",
        "attributes": {
        "url": "https://i.imgflip.com/23ls.jpg",
        "captions": [
               "There was a spider",
               "it's gone now"
        ],
        "rating": 13,
        "created_at": "2020-05-06T22:25:06+00:00"
        }
        },
        "meta": {}
}
```

2. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/2^[] as user.660. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/2 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.660"}'
```

Result:

When requesting answer 2, which is rated age 13, as **user.660**, who is from Youngstown, OH, expect a **403** Forbidden response with the following body.

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

3. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1^[] as user.0. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.0"}'
```

Result:

When requesting answer 1 as user.0, expect a 200 OK response with the following body.

```
{
    "data": {
    "id": "1",
    "type": "answers",
    "attributes": {
    "url": "https://i.imgflip.com/2fm6x.jpg",
    "captions": [
        "Still waiting for the bus to Jennie's"
    ],
    "rating": null,
    "created_at": "2020-05-06T22:25:06+00:00"
    }
    },
    "meta": {}
}
```

4. Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1[□] as user.660. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.660"}'
```

Result:

When requesting answer 1, which is unrated, as **user.660**, who is from Youngstown, OH, expect a **403** Forbidden response with the following body. Be aware that this is not the correct behavior; however, to resolve it, we would need to change our attribute definitions.

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

Allowing unrated memes

Answer 1 is not being served to **user.660**, even though it has not been rated as 13+. In this scenario, an unrated answer should be considered friendly to all users. Consider why an unrated meme is being blocked for this user. To resolve this, you can add a default value to the age rating.

Steps

- 1. In the PingAuthorize Policy Editor, go to Trust Framework and click Attributes.
- 2. Select Meme game answer rating.
- 3. For Value Settings, select the Default Value checkbox, and specify a value of 0.
- 4. Click Save changes.

Result:

Your attribute for answer age ratings has a default value of 0, as shown in the following image.

Details History Test		
🚫 Meme game answer ra	ting	Ξ
Description		1.
Parent	no parent selected	•
 Resolvers (1 total) 		
+ 🕴 Attribute - Respon	seBody	Ξ
+ Add Resolver		
 Value Processors (1 total 		
+ 🚦 Untitled JSON Pat	h Processor	Ŵ
+ Add Processor		
 Value Settings 		
Default value	0	
Туре	Number - Secret	

Testing the default value

You can test that the policy now works correctly with cURL or Postman.

Steps

• Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/1^[] as user.660. The following cURL command makes such a request.

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/1 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.660"}'
```

Result:

You should get a 200 OK response with the following body.

```
{
    "data": {
    "id": "1",
    "type": "answers",
    "attributes": {
    "url": "https://i.imgflip.com/2fm6x.jpg",
    "captions": [
                     "Still waiting for the bus to Jennie's"
    ],
    "rating": null,
    "created_at": "2020-05-06T22:25:06+00:00"
    }
    },
    "meta": {}
}
```

Creating a statement to provide a more useful error message

Add a command, known as a statement, that instructs PingAuthorize to set the HTTP response code and provide a more useful error message when rejecting the outbound response.

About this task

Because the reason for denial is a user attribute (the user's location), use a 4xx response code to indicate a user issue. The **451** status code is commonly used when content is unavailable because of legal restrictions.

Steps

- 1. In the Policy Editor, click **Policies**.
- 2. Select Users viewing shared memes.
- 3. Click + Statements.
- 4. Click + Add Statement and select Denied Reason.
- 5. For the name, replace **Untitled** with **Send** "not permitted" error.
- 6. In the **Applies to** list, select **Deny**.
- 7. In the Payload field, enter

{"status": 451, "message": "Restricted", "detail": "Not permitted per regulation"}.

8. Click Save changes.

Result:

You have a new statement that looks like the following image:

Send "no	t permitted" error		Obligatory	
Statement th	at allows a policy writer to provide	an error message containing	he reason that a request has been denied	1.
Code	denied-reason			
Applies To	Deny	✓ Applies If	All decisions in path match	•
Payload	{"status": 451, "message": "Restr	ricted", "detail": "Not permittee	d per regulation"}	C

Testing the statement

You can test that the statement works correctly with cURL or Postman.

Steps

```
• Issue a GET request to https://localhost:7443/meme-game/api/v1/users/user.0/answers/2<sup>[]</sup> as user.660. The following cURL command makes such a request.
```

```
curl --insecure -X GET \
    https://localhost:7443/meme-game/api/v1/users/user.0/answers/2 \
    -H 'Authorization: Bearer {"active": true, "sub": "user.660"}'
```

Result:

Expect a 451 Unavailable For Legal Reasons response with the following body.

```
{
    "errorMessage": "Restricted: Not permitted per regulation",
    "status": 451
}
```

Conclusion

In this tutorial, you allowed users to access the meme game's shared answers functionality through PingAuthorize. Following a request from government authorities, you blocked users from the town of Youngstown, Ohio from viewing memes intended for audiences aged 13 or older. In doing so, you learned about the PingAuthorize ability to control access to resources based on attributes of both the requesting user and the resource being requested. You also learned how to use statements to modify response bodies.

You also learned:

• Policies can apply to outbound upstream server API responses before they are sent to the API client.

- HttpRequest.ResponseBody is the upstream server API response body before it is sent to the client.
- Attributes that cannot be resolved because of any reason, including processing errors, might impact policy outcomes.
- PingAuthorize supplies the user profile of the access token subject as the Trust Framework attribute Token0wner .
- You must populate the child attributes of the Token0wner that you want to use in a policy.
- Many attributes in LDAP are multivalued.
- Statements are used to modify the API response in some way.
- In this case, **denied-reason** was used to set the HTTP status code and message body.

Tutorial (optional): Creating SCIM policies

This tutorial demonstrates how to develop fine-grained access control (FGAC) policies for the System for Cross-domain Identity Management (SCIM) REST application programming interface (API) built into PingAuthorize Server.

In the previous section, you used PingAuthorize Server to filter data that an external REST API returned.

While PingAuthorize Server's API security gateway protects existing REST APIs, PingAuthorize Server's built-in SCIM service provides a REST API for accessing and protecting identity data that might be contained in datastore like Lightweight Directory Access Protocol (LDAP) and relational databases.

PingAuthorize Server uses SCIM in the following ways:

- Internally, user identities are represented as SCIM identities by way of one or more SCIM resource types and schemas. This approach includes access token subject (SAML), which are always mapped to a SCIM identity.
- A SCIM REST API service provides access to user identities through HTTP.

You will now design a set of policies to control access to the SCIM REST API by using OAuth 2 access token rules.

Before proceeding, make a test request to generate a SCIM REST API response using only the default policies. As in the previous section, send a mock access token in the request.

curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub": "user.1", "scope": "nonexistent.scope", "client_id": "nonexistent.client"}'

Although the precise attributes values might vary, the response returns the SCIM resource that corresponds to user.1.

{"mail":["user.1@example.com"],"initials":["RJV"],"homePhone":["+1 091 438 1890"],
"pager":["+1 472 824 8704"],"givenName":["Romina"],"employeeNumber":1","telephoneNumber":["+1 319 624 9982"],
"mobile":["+1 650 622 7719"],"sn":["Valerio"],"cn":["Romina Valerio"],
"description":["This is the description for Romina Valerio."],"street":["84095 Maple Street"],
"st":["NE"],"postalAddress":["Romina Valerio\$84095 Maple Street\$Alexandria, NE 39160"],
"uid":["user.1"],"l":["Alexandria"],"postalCode":["39160"],"entryUUID":"355a133d-58ea-3827-8e8d-b39cf74ddb3e",
"objectClass":["top","person","organizationalPerson","inetOrgPerson"],"entryDN":"uid=user.1,ou=people,o=yeah",
"meta":{"resourceType":"Users",
"location":"https://localhost:7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},
"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","schemas":["urn:pingidentity:schemas:store:2.0:UserStoreAdapter"]}

This response is a success response, although it is preferred that it not be one, because it shows that any active access token referencing a valid user can be used to access any data.

Scenario

In this tutorial, you limit the requester's access to profile data, returning only specific attributes of the profile that granted the access token. This is achieved using the OIDC-like scope email and profile.

Also, you create a scope scimAdmin that has full access to SCIM-based User resources.

Tasks

This tutorial walks you through these tasks.

- 1. Create a basic policy structure for scope-based access to SCIM resources.
- 2. Create a policy for the email scope that only allows access to the subject's mail attributes.
- 3. Create a policy for the profile scope that only allows access to a few other profile attributes.
- 4. Create a policy for the scimAdmin scope that allows access to all attributes.

The following sections provide the details for completing these tasks.

Tutorial: Creating the policy tree

This tutorial describes how to create a tree structure and ensure that your policies apply only to SCIM requests.

About this task

The default policies include the policy named **Token Validation**. In the PingAuthorize Policy Editor, you can find this policy under **Global Decision Point**. This policy denies any request using an access token if the token's **active** flag is set to **false**. This policy is augmented with a set of scope-based access control policies.

Steps

- 1. To create the tree structure, perform the following steps:
 - 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
 - 2. Click Policies.
 - 3. Select Global Decision Point.
 - 4. From the + menu, select Add Policy Set.
 - 5. For the name, replace Untitled with SCIM Policy Set.
 - 6. In the Policies section, set the Combining algorithm to A single deny will override any permit decisions.

A combining algorithm determines the manner in which the policy set resolves potentially contending decisions from child policies.

- 7. Click + Applies to.
- 8. Click Components.

9. From the Services list, drag SCIM2 to the Add definitions and targets, or drag from Components box.

This step ensures that policies in the SCIM policy set apply only to SCIM requests.

10. Click Save changes.

Result:

You should have a screen like the following.

Policies Compo	Details History Test	
	DI SCIM Policy Set	Disabled 🗌 🗮
Library	Description	
▶ 🗹 Rules		
 Targets E Statements 	Applies to	
Trust Framework	🕒 Add definitions and targets, or drag from Components 🛛 🔅 SCIM2 📉	
 Domains Services 	+ Comparison + Named Condition	
 OpenBanking Account and Transaction API PDP 	- Policies (0)	
SCIM2	Combining Algorithm A single deny will override any permit decisions	•
 	+ Statements (0 total)	
▶ K ^A Conditions	+ Properties	

2. To add a branch under the SCIM policy set to hold SCIM-specific access token policies, go from **Components** to **Policies** and perform the following steps:

1. Select SCIM Policy Set.

- 2. From the + menu, select Add Policy Set.
- 3. For the name, replace Untitled with Token Policies.
- 4. In the Policies section, set the Combining algorithm to A single deny will override any permit decisions.

5. Click Save changes.

3. To add another branch that holds a policy specific to access token scopes, perform the following steps:

1. Select Token Policies.

- 2. From the + menu, select Add Policy Set.
- 3. For the name, replace Untitled with Scope Policies.
- 4. In the Policies section, set the Combining algorithm to Unless one decision is permit, the decision will be deny.
- 5. Click Save changes.

Result:

After creating the new branches, they should look like the following.

Policies Library Target	: Search De	ecision Visualiser	
Policies	Components	Details History Test	
+		Scope Policies	Disabled 🗌 🚍
 Global Decision Point Token Validation PDP API Endpoint Policies 		Description	
Random jokes API policy SCIM Policy Set		Applies to	
Token Policies		- Policies (0)	
Discope Policies		Combining Algorithm Unless one decision is permit, the decision will be deny	•

Tutorial: Creating SCIM access token policies

This tutorial describes how to define access token policies after you define a structure.

In this section, you will define three policies that use a requester's access token to limit data access.

Creating a policy for permitted access token scopes

The first policy defines the access token scopes that PingAuthorize Server accepts for SCIM requests.

About this task

The following table defines these scopes.

Scope	Allowed actions	Applies to
scimAdmin	search, retrieve, create/modify, delete	Any data
email	retrieve	Requester's email attributes
profile	retrieve	Requester's profile attributes

To create the policy and add rules to define the scopes, perform the following steps:

Steps

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Expand Global Decision Point, SCIM Policy Set, and Token Policies.
- 4. Select Scope Policies.
- 5. Next to **Statements**, click +.
- 6. Click Components.
- 7. From the **Statements** list, drag **Insufficient Scope** to the area immediately following the **Statements** section. A box appears for you to drop the item into.

8. Click Save changes.

9. Click Policies to the left of Components.

10. Select Scope Policies.

- 11. From the + menu, select Add Policy.
- 12. For the name, replace **Untitled** with **Permitted Scopes**.
- 13. Change the combining algorithm to A single deny will override any permit decisions.

14. Click Save changes.

Testing the policy with cURL

Test the newly created policy with cURL.

About this task

If you attempt the same HTTP request that you issued previously, it is now denied.

Steps

• Run the HTTP request to perform the test.

Example:

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "nonexistent.scope", "client_id": "nonexistent.client"}'
{"schemas":["urn:ietf:params:scim:api:messages:2.0:Error"],"status":"403",
"scimType":"insufficient_scope", "detail":"Requested operation not allowed by the granted OAuth scopes."}
```

Defining the email scope

Define a permitted access token scope to retrieve email attributes.

Steps

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Expand Global Decision Point, SCIM Policy Set, Token Policies, and Scope Policies.
- 4. Select Permitted Scopes.
 - 1. Click Components.
- 5. From the Rules list, drag Permitted SCIM scope for user to the Rules section.

6. To the right of the copied rule, click the hamburger menu.

7. Click Replace with clone.

8. Change the name to Scope: email.

- 9. To expand the rule, click +.
- 10. Change the description to Rule that permits a SCIM user to access its own mail attribute if the access token contains the email scope.
- 11. In the HttpRequest.AccessToken.scope row of the Condition section, type email in the CHANGEME field.
- 12. Within the rule, click **Show "Applies to"**.
- 13. From the Actions section, drag retrieve to the Add definitions and targets, or drag from Components box.

i Note

This task uses different actions from the previous gateway example.

- 14. Within the rule, click **Show Statements**.
- 15. Click + next to **Statements**.
- 16. From the Statements list, drag Include email attributes to the Statements section of the rule.

(i) Note

This predefined statement includes a payload. If the condition for this rule is satisfied, the response includes the **mail** attribute.

17. Click Save changes.

Result

You now have a new email scope, which should look like the following.

	nits a SCIM user to access its own mail attribute i		-		
Applies to					
🕞 A	d definitions and targets, or drag from Cor	mponents 🦻 🖗 retrieve	3		
- When	ANY NONE CLEAR ALL				
- I A	HttpRequest.AccessToken.scope	- Contains	• C	email	Î
- : A	HttpRequest.AccessToken.token_owner	- Equals	• A	HttpRequest.ResourcePath	•
+	omparison + Named Condition	+ Group			
Effect					

Testing the email scope with cURL

You can test a newly created email scope with cURL.

About this task

If you make the same request as earlier, a 403 is returned because the provided scope is not allowed.

curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub": "user.1", "scope": "nonexistent.scope", "client_id": "nonexistent.client"}'

Steps

• Adjust the request to use the email scope.

Example:

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "email", "client_id": "nonexistent.client"}'
```

{"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","meta":{"resourceType":"Users","location":"https://localhost: 7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},"schemas":["urn:pingidentity:schemas:store: 2.0:UserStoreAdapter"],"mail":["user.1@example.com"]}

Result:

The request succeeds, and only the mail attribute is returned.

Defining the profile scope

Define a permitted access token scope to retrieve profile attributes.

Steps

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Expand Global Decision Point, SCIM Policy Set, Token Policies, and Scope Policies.
- 4. Select Permitted Scopes.
- 5. Click Components.
- 6. From the Rules list, drag Permitted SCIM scope for user to the Rules section.
- 7. To the right of the copied rule, click the hamburger menu.
- 8. Click Replace with clone.
- 9. Change the name to Scope: profile.
- 10. To expand the rule, click +.
- 11. Change the description to Rule that permits a SCIM user to access a subset of its own profile attributes if the access token contains the profile scope.
- 12. In the HttpRequest.AccessToken.scope row of the Condition section, type profile in the CHANGEME field.
- 13. Within the rule, click Show "Applies to".
- 14. From the Actions section, drag retrieve to the Add definitions and targets, or drag from Components box.
- 15. Within the rule, click **Show Statements**.
- 16. Next to **Statements**, click **+**.
- 17. From the **Statements** list, drag **Include profile attributes** to the **Statements** section of the rule.

(i) Note

This predefined statement includes a payload. If the condition for this rule is satisfied, the response includes the uid, sn, givenName, and description attributes.

18. Click Save changes.

Result

You now have a new profile scope, which should look like the following.

Rule that permits a SCIM user to access a subset of its own profile attributes if the acc	ess token contains the prome scope.	
Applies to		
Add definitions and targets, or drag from Components	trieve ×	
- When		
ALL ANY NONE CLEAR ALL		
A HttpRequest.AccessToken.scope - Contains	- C profile	1
A HttpRequest.AccessToken.token_owner - Equals	- A HttpRequest.ResourcePath	- 1
+ Comparison + Named Condition + Group		
Effect		
Effect Permit		
		•

Testing the profile scope with cURL

Test your new profile scope with cURL.

Steps

• Make the same request as earlier, but change the email scope that the access token uses to profile.

Example:

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "profile", "client_id": "nonexistent.client"}'
```

{"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","meta":{"resourceType":"Users","location":"https://localhost: 7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},"schemas":["urn:pingidentity:schemas:store: 2.0:UserStoreAdapter"],"uid":["user.1"],"givenName":["Romina"],"description":["This is the description for Romina Valerio."],"sn":["Valerio"]}

Result:

The attributes defined by the new rule's statement are returned.

• Because an access token might contain multiple scopes, confirm that an access token with the email and profile scopes returns the union of the attributes that both scopes grant.

Result:

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "email profile", "client_id": "nonexistent.client"}'
```

```
{"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","meta":{"resourceType":"Users","location":"https://localhost:
7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},"schemas":["urn:pingidentity:schemas:store:
2.0:UserStoreAdapter"],"uid":["user.1"],"mail":["user.1@example.com"],"givenName":["Romina"],"description":
["This is the description for Romina Valerio."],"sn":["Valerio"]}
```

Defining the scimAdmin scope

For the scimAdmin scope, you will define different behaviors that depend on the action of the request.

As a result, the scope definition will be split into multiple rules.

Adding the scimAdmin retrieve rule

Add the scimAdmin retrieve rule to the Permitted Scopes policy.

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Select Permitted Scopes.
- 4. Click + Add Rule.
- 5. For the name, replace Untitled with Scope: scimAdmin (retrieve).
- 6. From the Effect list, select Permit.
- 7. In the **Condition** section, perform the following steps:
 - 1. Click + Comparison.
 - 2. In the first field, select HttpRequest.AccessToken.scope.
 - 3. From the comparator list, select Contains.
 - 4. In the final field, type scimAdmin.
- 8. Within the rule, click Show "Applies to".
- 9. Click Components.
- 10. From the Actions section, drag retrieve to the Add definitions and targets, or drag from Components box.
- 11. Within the rule, click Show Statements.
- 12. Click + next to Statements.

- 13. From the Statements list, drag Include all attributes to the Statements section of the rule.
- 14. Click Save changes.

Result

You now have a new scope for the scimAdmin retrieve rule, which should look like the following.

Scope: scimAdmin (retrieve)	Disabled 🗌 📮 💿 🚍
Description	
- Applies to	
Add definitions and targets, or drag from Components	
When ALL ANY NONE CLEAR ALL A Http:Request.AccessToken.scope Contains C scimAdmin	÷
+ Comparison - + Named Condition - + Group	
- Effect	
Effect Permit	•
- Statements (1 total)	
Include all attributes	Sobligatory 🖌 📕
+ Add Statement	
Hide "Applies to" Hide Statements Show Properties	

Adding the scimAdmin create/modify rule

Add the scimAdmin create/modify rule to the Permitted Scopes policy.

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Select Permitted Scopes.
- 4. Click + Add Rule.
- 5. For the name, replace Untitled with Scope: scimAdmin (create/modify).
- 6. From the Effect list, select Permit.
- 7. In the **Condition** section, perform the following steps:
 - 1. Click **+ Comparison**.

- 2. In the first field, select HttpRequest.AccessToken.scope.
- 3. From the comparator list, select Contains.
- 4. In the final field, type **scimAdmin**.
- 8. Within the rule, click **Show "Applies to"**.
- 9. Click Components.
- 10. From the Actions section, drag create to the Add definitions and targets, or drag from Components box.
- 11. From the Actions sections, drag modify to the Add definitions and targets, or drag from Components box.
- 12. Click Save changes.

Adding the scimAdmin search rule

Add the scimAdmin search rule to the Permitted Scopes policy.

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Select Permitted Scopes.
- 4. Click + Add Rule.
- 5. For the name, replace Untitled with Scope: scimAdmin (search).
- 6. From the Effect list, select Permit.
- 7. In the **Condition** section, perform the following steps:
 - 1. Click + Comparison.
 - 2. In the first field, select HttpRequest.AccessToken.scope.
 - 3. From the comparator list, select Contains.
 - 4. In the final field, type scimAdmin.
- 8. Within the rule, click Show "Applies to".
- 9. Click Components.
- 10. From the Actions section, drag search to the Add definitions and targets, or drag from Components box.
- 11. Click Save changes.

Adding the scimAdmin delete rule

Add the scimAdmin delete rule to the Permitted Scopes policy.

Steps

- 1. Sign on to the PingAuthorize Policy Editor using the URL and credentials from Accessing the GUIs.
- 2. Click Policies.
- 3. Select Permitted Scopes.
- 4. Click + Add Rule.
- 5. For the name, replace Untitled with Scope: scimAdmin (delete).
- 6. From the Effect list, select Permit.
- 7. In the **Condition** section, perform the following steps:
 - 1. Click + Comparison.
 - 2. In the first field, type HttpRequest.AccessToken.scope .
 - 3. From the comparator list, select Contains.
 - 4. In the final field, type scimAdmin.
- 8. Within the rule, click Show "Applies to".
- 9. Click Components.
- 10. From the Actions section, drag delete to the Add definitions and targets, or drag from Components box.
- 11. Click Save changes.

Creating a policy for permitted OAuth2 clients

This tutorial describes how to configure a policy to allow specific OAuth2 clients for a REST service. A REST service typically allows only requests from an allow list of OAuth2 clients.

About this task

In the PingAuthorize Policy Editor, define a policy in which each rule specifies an allowed client.

- 1. Go to Policies \rightarrow Policies.
- 2. Expand Global Decision Point and SCIM Policy Set.
- 3. Highlight Token Policies and click + and then Add Policy.
- 4. For the name, replace Untitled with Permitted Clients.
- 5. From the Combining Algorithm list, select Unless one decision is permit, the decision will be deny.

6. Click + Add Rule.

- 7. For the name, replace **Untitled** with Client: client1.
- 8. From the Effect list, select Permit.
- 9. In the **Condition** section:
 - 1. Click + Comparison.
 - 2. From the Select an Attribute list, select HttpRequest.AccessToken.client_id.
 - 3. From the middle, comparison-type list, select Equals.
 - 4. In the final field, enter client1.
- 10. Click + Add Rule.
- 11. For the name, replace **Untitled** with **Client: client2**.
- 12. From the Effect list, select Permit.
- 13. In the **Condition** section:
 - 1. Click + Comparison.
 - 2. From the Select an Attribute list, select HttpRequest.AccessToken.client_id.
 - 3. From the middle, comparison-type list, select Equals .
 - 4. In the final field, enter client2.

14. Expand **+** Statements.

(i) Note

Do not click Show Statements within the client1 or client2 rules.

- 15. Click Components.
- 16. From the **Statements** list, drag **Unauthorized Client** to the **Statements** box.
- 17. Click Save changes.

Result

The completed configuration should resemble the following image.

Client: client1	Disabled
Client: client2	Disabled
Description	
Applies to	
Add definitions and targets, or drag from Components O All Requests	
- When	
ALL ANY NONE CLEAR ALL	
A HttpRequest.AccessToken.client_id - Equals - C client2	Û
+ Comparison + Named Condition + Group	
Effect	
Effect Permit	•

Testing the client policy with cURL

To confirm that you successfully completed the tasks from the previous section, test the client policy with cURL.

About this task

After completing the tasks in the previous sections, test the responses you receive for access tokens for any client other than client1 or client2.

Steps

• To test that an access token for any client other than client1 or client2 is rejected, run the following.

curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub": "user.1", "scope": "email", "client_id": "nonexistent.client"}'

Result:

Successful completion of the tasks in the previous sections will result in the following response.

{"schemas":["urn:ietf:params:scim:api:messages:2.0:Error"],"status":"401","scimType":"The client is not authorized to request this resource.","detail":"unauthorized_client"}

• To test that an access token for client1 is accepted, run the following.

curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub": "user.1", "scope": "email", "client_id": "client1"}'

Result:

Successful completion of the tasks in the previous sections will result in the following response.

```
{"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","meta":{"resourceType":"Users","location":"https://localhost:
7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},"schemas":["urn:pingidentity:schemas:store:
2.0:UserStoreAdapter"],"mail":["user.1@example.com"]}
```

Creating a policy for permitted audiences

This tutorial describes how to create a policy for a REST service to control access based on an acceptable audience value.

About this task

An authorization server like PingFederate might set an **audience** field on the access tokens that it issues, naming one or more services that are allowed to accept the access token. A REST service can use the **audience** field to ensure that it does not accept access tokens that are intended for use with a different service.

As with the Permitted Clients policy, each rule in the Permitted Audiences policy defines an acceptable audience value.

Steps

- 1. Go to Policies \rightarrow Policies.
- 2. Expand Global Decision Point and SCIM Policy Set.
- 3. Highlight Token Policies and click + and then Add Policy.
- 4. For the name, replace Untitled with Permitted Audiences.
- 5. From the Combining Algorithm list, select Unless one decision is permit, the decision will be deny.
- 6. Click + Add Rule.
- 7. For the name, replace **Untitled** with Audience: https://example.com
- 8. From the Effect list, select Permit .
- 9. In the **Condition** section:
 - 1. Click **+ Comparison**.
 - 2. From the Select an Attribute list, select HttpRequest.AccessToken.audience.
 - 3. From the middle, comparison-type list, select Equals.
 - 4. In the final field, enter https://example.com^[].

10. Expand **+** Statements.

11. Click the **Components** tab, expand **Statements**, and drag **Unauthorized Audience** to the **Statements** box.

Note
 Do not click Show Statements within the "Audience: https://example.com"^[] rule.

12. Click Save changes.

Result

The final configuration should resemble the following image.

escription	
Applies to	
Add definitions and targets, or drag from Components	
When ALL ANY NONE CLEAR ALL A HttpRequest.AccessToken.audience - Equals - C https://example.com + Comparison + Named Condition + Group	
+ Comparison + Named Condition + Group Effect	
Effect Permit	-

Testing the audience policy with cURL

To confirm that you successfully completed the previous task, test the audience policy with cURL.

Steps

1. To test that an access token without a specific audience value is rejected, run the following.

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "email", "client_id": "client1"}'
```

Result:

Successful creation of the audience policy will result in the following.

```
{"schemas":["urn:ietf:params:scim:api:messages:2.0:Error"],"status":"403","scimType":
"invalid_token","detail":"The access token was issued for a different audience."}
```

2. To test that an access token with an audience value of https://example.com^C is accepted, run the following.

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":
"user.1", "scope": "email", "client_id": "client1", "aud": "https://example.com"}'
```

Result:

Successful creation of the audience policy will result in the following.

```
{"id":"355a133d-58ea-3827-8e8d-b39cf74ddb3e","meta":{"resourceType":"Users",
"location":"https://localhost:7443/scim/v2/Users/355a133d-58ea-3827-8e8d-b39cf74ddb3e"},
"schemas":["urn:pingidentity:schemas:store:2.0:UserStoreAdapter"],"mail":["user.1@example.com"]}
```

Tutorial: Creating a policy for role-based access control

This tutorial describes how to create the final policy, which is an access-control rule that can base its authorization decision on an attribute of the requesting identity, rather than on an access token claim.

About this task

When PingAuthorize Server authorizes a request, an access token validator resolves the subject of the access token to a SCIM user and populates a policy request attribute called **TokenOwner** with the SCIM user's attributes. In this scenario, build a policy around the **employeeType** attribute, which must be defined in the Trust Framework.

Steps

- 1. Go to Trust Framework and click the Attributes tab. Click TokenOwner.
- 2. Click + and then Add new Attribute.
- 3. For the name, replace Untitled with employeeType.
- 4. From the Parent list, select TokenOwner.

5. In the Resolvers section:

- 1. Click + Add Resolver.
- 2. From the Resolver type list, select Attribute and in the Select an Attribute list, specify a value of Token0wner.
- 6. Click + next to Value Processors and then + Add Processor.
- 7. From the Processor list, select JSON Path and enter the value employeeType .
- 8. Set the Value type to Collection.
- 9. In the Value Settings section:
 - 1. Select the **Default Value** check box and in the **Enter a default value** field, enter the value [].



2. From the Type list, select Collection.

10. Click Save changes.

Result

The final attribute configuration should resemble the following image.

> employeeType			
Parent	TokenOwner		•
Resolvers (1 total)			
Attribute - Toke	enOwner		Ξ
Add Resolver			
Value Processors (1	1 total)		
Untitled JSON	Path Processor		
Processor	JSON Path	✓ employeeType	\bigtriangledown
Processor Value type	JSON Path Collection	 employeeType 	0
Value type			0
Value type			
Value type Add Processor			
Value type • Add Processor Value Settings	Collection		
Value type • Add Processor Value Settings Default value	Collection	•	

Next steps

Add a policy that uses the employeeType attribute.

- 1. Go to **Policies** \rightarrow **Policies**.
- 2. Select SCIM Policy Set and click + and then Add Policy.
- 3. For the name, replace **Untitled** with **Restrict Intern Access**.
- 4. From the Combining Algorithm list, select Unless one decision is deny, the decision will be permit.
- 5. Click + Add Rule.

- 6. For the name, replace **Untitled** with **Restrict access for interns**.
- 7. From the **Effect** list, select **Permit**.
- 8. In the **Condition** section:
 - 1. Click + Comparison.
 - 2. In the Select an Attribute list, select TokenOwner.employeeType.
 - 3. From the middle, comparison-type list, select Contains.
 - 4. In the Type in constant value field, enter intern.
- 9. Within the rule, click **Show Statements**, and then click the **+** next to **Statements**.
- 10. Click + Add Statement → Custom Advice.
- 11. For the name, replace Untitled with Restrict attributes visible to interns.
- 12. Select the **Obligatory** check box.
- 13. In the **Code** field, enter exclude-attributes.
- 14. From the Applies To list, select Permit.
- 15. In the **Payload** field, enter ["description"].
- 16. Click Save changes.

Restrict access for interns	Disabled 🔲 🚍
Description	
Applies to	
Add definitions and targets, or drag from Components O All Requests	
- When	
ALL ANY NONE CLEAR ALL	
A TokenOwner.employeeType - Contains - C intern	8
+ Comparison + Named Condition + Group	
Effect	
EHELA	
Effect Permit	•
Statements (1 total)	
Restrict attributes visible to interns	Obligatory 🔽 🗮
+ Add Statement	
de "Applies to" Hide Statements Show Properties	

Testing the policy with cURL

Test the policy for role-based access control using cURL.

About this task

The PingAuthorize sample user data allows an employeeType attribute but does not populate it with values for any users.

Confirm that **user.2** cannot read the **description** attribute, even though the **profile** scope allows it, by running the following command.

```
curl --insecure -X GET https://localhost:7443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub": "user.2",
"scope": "profile", "client_id": "client1", "aud": "https://example.com"}'
```

The response should be similar to the following response.

```
{"id":"c9cbfb8c-d915-3de3-8a2c-a01c0ccc6d09","meta":{"resourceType":"Users","location":"https://localhost:7443/scim/
v2/Users/c9cbfb8c-d915-3de3-8a2c-a01c0ccc6d09"},"schemas":["urn:pingidentity:schemas:store:
2.0:UserStoreAdapter"],"uid":["user.2"],"givenName":["Billy"],"sn":["Zaleski"]}
```

Example files

The compressed PingAuthorize Server file at **PingAuthorize/resource/policies** includes a policy snapshot and deployment package that both contain an example Trust Framework and example policies.

Conclusion

In this tutorial, you set scope-based access to SCIM resources.

You also learned:

- Like exclude-attributes used in this tutorial, include-attributes filters which attributes can be returned to the caller. include-attributes works more like opt-in, while exclude-attributes works more like opt-out.
- Multiple attributes can apply from multiple rules or even policies. They are combined by PingAuthorize to **include** before **exclude**.

Installing PingAuthorize

. .

PingIdentity.

You can install PingAuthorize manually or deploy it with Docker.

Installation method	Recommended for	
Docker	Server administrators familiar with Docker who want to use orchestration to manage their environments. Learn more in Docker deployment.	
Manual	Server administrators familiar with their operating systems who want to tweak and maintain their environments themselves. Learn more in Manual installation.	

Learn more about the available implementation architectures and development environments for your PingAuthorize installation in PingAuthorize architectural overview.

Docker deployment

Running PingAuthorize Docker containers standardizes your deployments and helps support DevOps principles.

Learn more about installation and deployment methods in Installing PingAuthorize.

Deployment requirements when using Docker

For a PingAuthorize software deployment using Docker DevOps, you need a supported version of Docker, the Docker images, and a compatible browser.

Docker

This following version of Docker is supported:

• Docker 20.10.9

🆒 Important

Increase your Docker memory limit to at least 4 GB. To change this setting, go to **Docker Dashboard** \rightarrow **Settings** \rightarrow **Resources** \rightarrow **Advanced**.

Containers

Docker images for Ping Identity's on-premise server products are available on Ping Identity Docker Hub \square . For information about Docker deployments, visit the Ping Identity DevOps \square documentation. To start deploying images, see Get Started \square .

The following Docker containers are available.

Container	Description	Image
pingdataconsole	administrative console Use the administrative console to configure PingAuthorize.	DockerHub: PingDataConsole ^{[2}
pingauthorize	PingAuthorize Server The server enforces the policies you define.	DockerHub: PingAuthorize ^{[2}
pingauthorizepap	PingAuthorize Policy Editor Use the Policy Editor to define the policies that determine access control and data protection.	DockerHub: PingAuthorizePAP ^亿
pingdirectory	PingDirectory A directory of user information.	DockerHub: PingDirectory ^亿
	Note PingAuthorize does not require PingDirectory.	

(i) Note

Only the PingDataConsole, PingAuthorize, PingAuthorize PAP, and PingDirectory software is licensed under Ping Identity's end user license agreement. Any other software components contained in the image are licensed solely under the terms of the applicable open source/third party license.

Ping Identity accepts no responsibility for the performance of any specific virtualization software and in no way guarantees the performance or interoperability of any virtualization software with its products.

Browsers

The PingAuthorize administrative console is compatible with several different web browsers, including:

- Google Chrome
- Mozilla Firefox
- Microsoft Edge

Deploying PingAuthorize Server and Policy Editor using Docker

Instead of manual software installation, you can run Docker images of the PingAuthorize Server and Policy Editor.

About this task

To start the setup process after you obtain the Docker images:

- 1. Run the PingAuthorize Server container, pingauthorize .
- 2. Run the PingAuthorize Policy Editor container, pingauthorizepap .

- 3. **Optional:** To configure PingAuthorize with a GUI, run the PingAuthorize administrative console container, **pingdataconsol** e.
- 4. Optional: If you need user-level control of the data, set up a user store.

If you use PingDirectory, run the pingdirectory container.

Next steps

- Perform Post-setup steps (Docker deployment).
- Perform Next steps as needed.

Deploying PingAuthorize Server using Docker

Perform a PingAuthorize Server deployment by running a Docker image.

About this task

The following command uses the ~/.pingidentity/config environment file to configure common environment variables. See Get Started ^[2].

Steps

• Run the following command.

```
docker run --network=<network_name> \
    --env-file ~/.pingidentity/config \
    --name {SERVER_CONTAINER_NAME} \
    --publish 1389:1389 \
    --publish 8443:1443 \
    --detach \
    --env SERVER_PROFILE_URL=https://github.com/pingidentity/pingidentity-server-profiles.git \
    --env SERVER_PROFILE_PATH=getting-started/{SERVER_CONTAINER_NAME} \
    --tmpfs /run/secrets \
    pingidentity/{SERVER_CONTAINER_NAME}:<TAG>
```

The Docker image *<TAG* - used in the example is only a placeholder. For actual tag values, see Docker Hub^{C/}.

Λοτε

- For proper communication between containers, create a Docker network using a command, such as do cker network create --driver <network_type> <network_name>, and then connect to that network with the --network=<network_name> option.
- You can use server profiles to automate deployment of PingAuthorize Server. For more information, see Deployment automation and server profiles.

Deploying PingAuthorize Policy Editor using Docker

Deploy PingAuthorize Policy Editor by running its Docker image. Using Docker DevOps enables the automated policy database update feature with mounted volumes.

About this task

When running the Ping Identity DevOps **pingauthorizepap** Docker container, you can use the following commands to ensure that the policy database is on the mounted volume in preparation for future versions of the image. The commands:

- Run a pingauthorizepap Docker container named pap on host port 8443.
- Use the ~/.pingidentity/config environment file to configure common environment variables. See Get Started 2.
- Bind mount a customized options.yml file named custom-options.yml to the server root using the server profile capability. The host system server-profile folder must contain instance/custom-options.yml for this example to work correctly. See https://devops.pingidentity.com/reference/config/^C.
- Set the Ping_Options_File environment variable to tell setup to use custom-options.yml.

For an H2 database, the command:

- Bind-mounts a volume that maps a policy database to /opt/out/Symphonic.mv.db.
- Sets the PING_H2_FILE environment variable to tell **setup** to use /opt/out/Symphonic.mv.db for the policy database. The environment variable must exclude the .mv.db extension.

To use a PostgreSQL policy database, make sure you have met the following prerequisites:

- The PostgreSQL instance must be reachable on the network from the Policy Editor host and listening for connections.
- The Policy Editor uses both a PostgreSQL administration user and a server runtime user. Have a database administrator create both users before providing their credentials to the **policy-db** tool. The administration user must be able to create new databases. When new releases of the Policy Editor become available, continue using the same administration user to prevent database object ownership issues.

Learn more about creating new database users and configuring PostgreSQL to listen for remote connections securely in the PostgreSQL documentation \square .

The Policy Editor uses Java Database Connectivity (JDBC) to connect to PostgreSQL. Be prepared to provide the JDBC connection string in the following format: jdbc:postgresql://<host>:<port>/<name>. For example: jdbc:postgresql://example.com:5432/pap_db

i) Note

- The Ping Identity DevOps Docker image documentation is frequently updated as new features are released. For the most recent instructions about running the Docker images, see https://devops.pingidentity.com/^[].
- For proper communication between containers, create a Docker network using a command such as docker network create --driver <network_type> <network_name>, and then connect to that network with the -network=<network_name> option.
- The Docker image <*TAG*> used in the example is only a placeholder. For actual tag values, see Docker Hub \square .

Steps

• Run the pingauthorizepap Docker container.

Choose from:

• If you are using an H2 database, run the following command.

```
$ docker run --network=<network_name> --name pap -p 8443:1443 \
    --env-file ~/.pingidentity/config \
    --volume /home/developer/pap/server-profile:/opt/in/ \
    --env PING_0PTIONS_FILE=custom-options.yml \
    --volume /home/developer/pap/Symphonic.mv.db:/opt/out/Symphonic.mv.db \
    --env PING_H2_FILE=/opt/out/Symphonic \
    pingidentity/{PAP_CONTAINER_NAME}:<TAG>
```

• If you are using a PostgreSQL database, run the following command.

The official **pingauthorizepap** Docker image detects whether a PostgreSQL database needs to be created or upgraded when you provide the **PING_POLICY_DB_SYNC=true** environment variable along with the database connection string, database administration credentials, and server runtime credentials.

```
$ docker run --network=<network_name> --name pap -p 8443:1443 \
    --env PING_POLICY_DB_SYNC=true \
    --env PING_DB_CONNECTION_STRING="jdbc:postgresql://<host>:<port>/<database>" \
    --env PING_DB_ADMIN_USERNAME="<admin-username>" \
    --env PING_DB_ADMIN_PASSWORD="<admin-password>" \
    --env PING_DB_APP_USERNAME="<username>" \
    --env PING_DB_APP_USERNAME="<username>" \
    --env PING_DB_APP_DSSWORD="<password>" \
    --env FING_DB_APP_PASSWORD="<password>" \
    --env FING_OPTIONS_FILE=custom-options.yml \
    --detach \
    --tmpfs /run/secrets \
    pingidentity/pingauthorizepap:<tag>
```

Λοτε

The **PING_DB_APP_PASSWORD** and **PING_DB_ADMIN_PASSWORD** can instead be provided as Vault secrets or through a secrets volume. See **Using Hashicorp Vault** ^C.

Post-setup steps (Docker deployment)

After you successfully set up the PingAuthorize Policy Editor, you must start the server and then configure PingAuthorize Server to use the Policy Editor as its policy decision point (PDP).

(j) Note

The containers must be on the same Docker network to communicate properly.

Sign on to the Policy Editor and import a policy snapshot. You can find a set of default policies in the resource/policies/ defaultPolicies.SNAPSHOT file. For more information, see Signing on to the PingAuthorize Policy Editor.

To configure PingAuthorize Server to use the Policy Editor, use **dsconfig** or the administrative console to create a Policy External Server to represent the Policy Editor, then assign the Policy External Server to the Policy Decision Service and configure it to use external PDP mode. Also, set the Trust Framework Version to the current version, v2.

Consider the following example. Assume a container named pingauthorize and that no files are needed from the file system. The following commands run **dsconfig** from within the container.

```
docker exec {SERVER_CONTAINER_NAME} /opt/out/instance/bin/dsconfig create-external-server \
    --server-name "{PAP_Name}" \
    --type policy \
    --set "base-url:https://<pap-hostname>:<pap-port>" \
    --set "shared-secret:2FederateM0re" \
    --set "branch:Default Policies"

docker exec {SERVER_CONTAINER_NAME} /opt/out/instance/bin/dsconfig set-policy-decision-service-prop \
    --set pdp-mode:external \
    --set "policy-server:{PAP_Name}" \
    --set trust-framework-version:{TRUST_FRAMEWORK_VERSION}
```

In the example, the base URL consists of the host name and port chosen for the Policy Editor during setup. The shared secret value is **2FederateM0re** by default. The branch name corresponds to the branch name that you chose when importing your policy snapshot.

Next steps

After installed, complete some configuration steps and then start developing policies to enforce fine-grained access to data.

Consider performing the following next steps:

- Configure access token validation.
- Configure a user store.
- Sign on to the administrative console to configure endpoints for existing JSON APIs.

For more information, see About the API security gateway.

• Sign on to the administrative console to define SCIM APIs for data in databases.

For more information, see About the SCIM service.

· Sign on to the PingAuthorize Policy Editor to create policies.

For more information, see the PingAuthorize Policy Administration Guide.

Manual installation

Instead of running Docker images, you can install PingAuthorize manually using .zip archives.

Learn more about installation and deployment methods in Installing PingAuthorize.

Before you install manually

You must prepare your computing environment by installing certain system requirements before a manual PingAuthorize software installation.

The following components are required to install PingAuthorize:

- Supported Linux or Windows platform
- Valid license key
- Java

The following sections describe these prerequisites in more detail.

System requirements

Ensure that your computing environment meets the system requirements for the PingAuthorize dynamic authorization management software.

Ping Identity has qualified the configurations in this section and has certified that they are compatible with the product. PingAuthorize supports differences in operating system versions, service packs, and other platform variations until the platform or other required software is suspected of causing issues.

Platforms

You can run PingAuthorize on a variety of different platforms and operating systems, including:

- Amazon Linux 2022
- Canonical Ubuntu 18.04 LTS and 20.04 LTS
- CentOS Linux 7.7 and 8.1
- Microsoft Windows Server 2016 and 2019 (Policy Editor not supported)
- Oracle Linux 7.9 and 8.6
- Red Hat Enterprise Linux ES 7.7, 7.9, 8.5, 8.6, and 9.0
- SUSE Linux Enterprise 12 SP5 and 15 SP1

γ Note

This product was tested with the default configurations of all operating system components. Customized implementations or third-party plugins could affect the deployment of this product.

Java Runtime Environment

Make sure your Java Runtime Environment (JRE) meets the system requirements for PingAuthorize:

- Oracle JDK 8 64-bit
- Oracle JDK 11 LTS 64-bit
- OpenJDK 8 64-bit
- OpenJDK 11
- Amazon Corretto 8

• Amazon Corretto 11

🕥 Note

Due to the number of supported JDK variants, we do not explicitly list all of them here. The criteria for supported JDKs are:

- They must be built from the OpenJDK codebase.
- They must use the HotSpot JIT compiler. They cannot use OpenJ9 or other JIT implementations.

The Ping Identity Java Support Policy[□] applies to your JRE.

Browsers

The PingAuthorize administrative console is compatible with several different web browsers, including:

- Google Chrome 107.0.5304.107 (64-bit)
- Mozilla Firefox 107.0 (64-bit)
- Microsoft Edge 107.0.1418.42

Databases

The Policy Editor persists its policies, trust framework, and versioning data in a policy database. By default, this is an embedded H2 file-based database. Optionally, you can configure the Policy Editor to use a PostgreSQL database.

For more information, see Setting up a PostgreSQL database.

Supported databases:

- H2
- PostgreSQL 15.1

About license keys

License keys are required to install, update, and renew all Ping products.

How to obtain a license

To obtain a license key, contact your account representative or use the Ping Identity licensing portal

When do you need a license

A license is required for setting up a new single server instance and can be used site-wide for all servers in an environment. Additionally, you must obtain a new license when updating a server to a new major version, such as when upgrading from 7.3 to 8.0. When cloning a server instance with a valid license, you do not need a new license.

🕥 Note

The update process displays a prompt for a new license.

How to specify a license

• Specify a license at setup

You have these options:

- Use the --licenseKeyFile cpath-to-license> option with setup.
- Copy the license file to the PingAuthorize Server root directory and then run the **setup** tool. The tool discovers the license file.
- Specify a license after setup

Use the administrative console or **dsconfig** (in the Topology section, select License).

(i) Note

Placing the new license file in the PingAuthorize Server root directory does not work in this case.

For information about how to specify the license with the Policy Editor, see Installing the PingAuthorize Policy Editor noninteractively.

How to view the license status

To view the details of a license, including its expiration, you have these options:

- The server's **status** tool
- The administrative console's Status page (On the Monitors tab, search for License.)

License expiration

The server provides a notification as the expiration date approaches.

Before a license expires, obtain a new one and install it by using **dsconfig** or the administrative console.

i Νote

An expiring license causes alerts and alarms but does not affect the functionality of PingAuthorize Server. However, PingAuthorize Policy Editor fails to start if the license has expired.

Creating a Java installation dedicated to PingAuthorize

Create a Java installation for PingAuthorize Server using the Java Development Kit (JDK).

About this task

PingAuthorize Server requires Java for 64-bit architectures. Even if Java is already installed on your system, you should create a separate Java installation for PingAuthorize Server. This setup ensures that updates to the system-wide Java installation do not inadvertently impact PingAuthorize Server.

) Note

This setup requires that you install the JDK, rather than the Java Runtime Environment (JRE).

Steps

- 1. Download and install a JDK.
- 2. Set the JAVA_HOME environment variable to the Java installation directory path.
- 3. Add the bin directory to the PATH environment variable.

Preparing a Linux environment

For Linux computing environments, complete the required tasks described in this section before initiating a PingAuthorize Server installation.

About this task

Complete the following tasks before you install PingAuthorize Server in a Linux environment:

Steps

- 1. Set the file descriptor limit.
- 2. Set the maximum user processes.
- 3. Disable file system swapping.
- 4. Manage system entropy.
- 5. Enable the server to listen on privileged ports.

Setting the file descriptor limit

PingAuthorize Server allows for an unlimited number of connections. The following steps describe how to manually increase the file descriptor limit on the operating system.

About this task

i) Νote

If the operating system relies on **systemd**, see the Linux operating system documentation for instructions on setting the file descriptor limit.

Steps

1. Display the current fs.file-max limit of the system.

sysctl fs.file-max

The fs.file-max limit is the maximum server-wide file limit you can set without tuning the kernel parameters in the proc file system.

2. Edit the /etc/sysctl.conf file.

If there is a line that sets the value of the **fs.file-max** property, make sure that its value is set to at least 1.5 times the per-process limit. If there is no line that sets a value for this property, add the following to the end of the file (100000 is just an example here; specify a value of at least 1.5 times the per-process limit).

fs.file-max = 100000

3. Display the current hard limit of the system.

ulimit -aH

The open files (-n) value is the maximum number of open files per process limit.

Verify that its value is set to at least 65535.

4. Edit the /etc/security/limits.conf file.

If the file contains lines that set the soft and hard limits for the number of file descriptors, verify that the values are set to 65535. If the properties are absent, add the following lines to the end of the file, before **#End** of file, inserting a tab between the columns.

* soft nofile 65535

* hard nofile 65535

(j) Note

The number of open file descriptors is limited by the physical memory available to the host. You can determine this limit with the following command.

cat /proc/sys/fs/file-max

If the file-max value is significantly higher than the 65535 limit, consider increasing the file descriptor limit to between 10% and 15% of the system-wide file descriptor limit. For example, if the file-max value is 810752, you could set the file descriptor limit to 100000. If the file-max value is lower than 65535, the host is likely not sized appropriately.

5. Reboot the server.

6. Verify that the file descriptor limit is set to 65535.

```
ulimit -n
```

7. For RedHat 7 or later, modify the /etc/security/limits.d/20-nproc.conf file to set limits for the open files and max user processes.

Add or edit the following lines if they do not already exist.

* soft nproc 65536 * soft nofile 65536 * hard nproc 65536 * hard nofile 65536 root soft nproc unlimited

Next steps

After the operating system limit is set, use one of the following methods to configure the number of file descriptors that the server uses:

- Use a NUM_FILE_DESCRIPTORS environment variable.
- Create a config/num-file-descriptors file with a single line, such as NUM_FILE_DESCRIPTORS=12345.

If these values are not set, the default value of 65535 is used.

(i) Note

This optional step ensures that the server shuts down safely before it reaches the file descriptor limit.

Setting the maximum user processes

Set the maximum user processes higher than the default to improve memory when running multiple servers on a machine.

About this task

On some Linux distributions, such as RedHat Enterprise Linux (RHEL) Server/CentOS 6.0 or later, the default maximum number of user processes is set to 1024, which is considerably lower than the same parameter on earlier distributions, such as RHEL/ CentOS 5.x. The default value of 1024 leads to some Java virtual machine (JVM) memory errors when running multiple servers on a machine, due to each Linux thread being counted as a user process.

At startup, PingAuthorize Server attempts to raise this limit to 16383 if the value reported by **ulimit** is less than that number. If the value cannot be set, an error message is displayed. In such a scenario, you must explicitly set the limit in /etc/security/limit.conf, as the following example shows.

* soft nproc 100000

* hard nproc 100000

Steps

- Set the 1683 value in the NUM_USER_PROCESSES environment variable.
- Set the 1683 value in config/num-user-processes.

Disabling file system swapping

To disable the file system swapping in PingAuthorize, use vm.swappiness.

About this task

Disable all performance-tuning services, like **tuned**. If performance tuning is required, perform the following steps to set vm.swappiness:

Steps

- 1. Clone the existing performance profile.
- 2. Add vm.swappiness = 0 to the new profile's tuned.conf file in /usr/lib/tuned/profilename/tuned.conf.
- 3. Select the updated profile by running tuned-adm profile customized_profile.

Managing system entropy

Entropy is used to calculate random data that the system uses in cryptographic operations.

About this task

Some environments with low entropy might experience intermittent performance issues with SSL-based communication, such as certificate generation. This scenario is more typical on virtual machines but can also occur in physical instances. For best results, monitor the value of kernel.random.entropy_avail in the configuration file /etc/sysctl.conf.

(i) Note

To increase system entropy on a Windows system, move the mouse pointer in circles or type characters randomly into an empty text document.

Steps

• On a UNIX or Linux system, ensure that **rng-tools** is installed and run the following command.

sudo rngd -r /dev/urandom -o /dev/random

• To check the level of a system entropy on a UNIX or Linux system, run the following command.

cat /proc/sys/kernel/random/entropy_avail

(i) Note

Values smaller than 3200 are considered too low to generate a certificate and might cause the system to hang indefinitely.

Enabling the server to listen on privileged ports

To enable PingAuthorize Server to listen on privileged ports as a non-root user, grant capabilities to specific commands.

About this task

Linux systems provide capabilities that grant specific commands the ability to complete tasks that are normally permitted only by a root account. Instead of granting an ability to a specific user, capabilities are granted to a specific command. For convenience, you might enable the server to listen on privileged ports while running as a non-root user.

Steps

• To assign capabilities to an application, run the **setcap** command.

For example, the **cap_net_bind_service** capability enables a service to bind a socket to privileged ports, which are defined as ports with numbers less than 1024. If Java is installed in **/ds/java**, and if the Java command to run the server is **/ds/java/bin/java**, then you can grant the Java binary the **cap_net_bind_service** capability by running the following command.

\$ sudo setcap cap_net_bind_service=+eip /ds/java/bin/java

The Java binary requires an additional shared library, libjli.so, as part of the Java installation.

Because additional limitations are imposed on where the operating system looks for shared libraries to load for commands with assigned capabilities, you must create the file /etc/ld.so.conf.d/libjli.conf with the path to the directory that contains the libjli.so file.

Example:

For example, if the Java installation is located in /ds/java, the contents must be as shown in this example.

```
/ds/java/lib/amd64/jli
```

Run the following command for the change to take effect.

\$ sudo ldconfig -v

Obtaining the installation packages

To begin the software installation process for PingAuthorize, obtain the server component's .zip installation packages.

About this task

The PingAuthorize distribution consists of two compressed files, one for each of the following server components:

- PingAuthorize Server
- PingAuthorize Policy Editor

To start the installation process, complete the following steps:

Steps

- 1. Obtain the latest compressed release bundles ^[2] from Ping Identity.
- 2. Expand the release bundles into the folders of your choice.

Setting up a PostgreSQL database

To set up a PostgreSQL database for your attribute-based access control policies, create the policy database using the **policy-db** tool.

Before you begin

- The PostgreSQL instance must be reachable on the network from the Policy Editor host and listening for connections.
- The Policy Editor uses both a PostgreSQL administration user and a server runtime user. Have a database administrator create both users before providing their credentials to the **policy-db** tool. The administration user must be able to create new databases. When new releases of the Policy Editor become available, continue using the same administration user to prevent database object ownership issues.

Learn more about creating new database users and configuring PostgreSQL to listen for remote connections securely in the PostgreSQL documentation \square .

The Policy Editor uses Java Database Connectivity (JDBC) to connect to PostgreSQL. Be prepared to provide the JDBC connection string in the following format: jdbc:postgresql://<host>:<port>/<name>. For example: jdbc:postgresql://example.com:5432/pap_db

About this task

Follow these instructions to create a PostgreSQL database for a manual installation of the Policy Editor. See Deploying PingAuthorize Policy Editor using Docker for containerized deployments.

Steps

1. Run the following command:

```
$ bin/policy-db \
```

```
--dbConnectionString "jdbc:postgresql://<host>:<port>/<name>" \
```

- --dbAppUsername <server-runtime-username> \
- --dbAppPassword <server-runtime-password>

) Νote

Alternatively, you can provide the server runtime password through the **PING_DB_APP_PASSWORD** environment variable.

2. Provide the database administration credentials when prompted.

Result

The **policy-db** tool connects to PostgreSQL, creates the database and its objects, and grants access to the server runtime username.

Next steps

Configure the Policy Editor to use the PostgreSQL database. See Installing the PingAuthorize Policy Editor non-interactively.

🔿 Important

Provide the Policy Editor with the same --dbConnectionString, --dbAppUsername, and server runtime password you used to create the PostgreSQL database.

Installing the server and the Policy Editor manually

Use manual install mode for the PingAuthorize Policy Editor and PingAuthorize Server installations.

About this task

After you obtain the installation files, start the setup process.

Steps

- 1. Install PingAuthorize Server.
- 2. Install PingAuthorize Policy Editor.
- 3. Perform additional configuration steps.

The following sections describe these installation and configuration steps.

Installing the server manually

Choose your manual install mode for PingAuthorize Server and then perform the server installation.

Steps

- 1. Read about the server installation modes and decide which mode you want to use.
- 2. Complete the steps for your chosen mode, interactive or noninteractive.

About the server installation modes

There are several different installation modes for PingAuthorize Server.

PingAuthorize Server provides the following tools to help install and configure the system:

- The **setup** tool performs the initial tasks needed to start PingAuthorize Server, including configuring Java virtual machine (JVM) runtime settings and assigning listener ports for the PingAuthorize Server's HTTP services.
- The **create-initial-config** tool configures connectivity between a System for Cross-domain Identity Management (SCIM) 2 user store and PingAuthorize Server. During the process, the **prepare-external-store** tool prepares each PingDirectory Server to serve as a user store by PingAuthorize Server. Configuration can be written to a file to use for additional installations.

(i) Note

Using **create-initial-config** is optional. However, if you do not use it, you do not get the user's profile (the requester's attributes). For more information, see **User profile availability in policies**.

• After the initial setup is finished, you can use the **dsconfig** tool and the administrative console to perform additional configuration.

) Тір

You can use server profiles to automate deployment of PingAuthorize Server. For more information, see **Deployment** automation and server profiles.

To install a server instance, run the **setup** tool in one of the following modes:

Interactive command-line mode

Prompts for information during the installation process. To run the installation in this mode, use the **setup --cli** command.

Noninteractive command-line mode

Designed for setup scripts to automate installations or for command-line usage. To run the installation in this mode, setup must be run with the **--no-prompt** option as well as the other arguments required to define the appropriate initial configuration.

You can perform all installation and configuration steps while signed on to the system as the user or the role under which PingAuthorize Server will run.

Interactive

Installing the server interactively

Run the **setup** tool, which prompts you interactively for the information that it needs to install PingAuthorize Server.

Before you begin

Be prepared to provide the following information:

- The location of a valid license file
- The name and password for an administrative account, which is also called the root user distinguished name (DN)
- An available port for PingAuthorize Server to accept HTTPS requests
- An available LDAPS port for PingAuthorize Server to accept administrative requests
- Information related to the server's connection security, including the location of a **keystore** that contains the server certificate, the nickname of that server certificate, and the location of a truststore
- The amount of memory to reserve for usage by the Java virtual machine (JVM)
- A unique instance name for the server

Steps

1. Run the **setup** command.

Example:

\$./setup

2. To start and stop PingAuthorize Server, use the **start-server** and **stop-server** commands, respectively.

For additional options, see Starting PingAuthorize Server.

Noninteractive

Installing the server noninteractively

For an automated installation, run the **setup** tool in noninteractive, command-line mode.

Before you begin

Be prepared to provide the following settings using command-line arguments:

- The location of a valid license file
- The name and password for an administrative account, which is also called the root user distinguished name (DN).
- An available port for PingAuthorize Server to accept HTTPS requests
- An available LDAPS port for PingAuthorize Server to accept administrative requests
- Information related to the server's connection security, including the location of a keystore that contains the server certificate, the nickname of that server certificate, and the location of a truststore
- The amount of memory to reserve for usage by the Java virtual machine (JVM)
- A unique instance name for the server

Steps

- Run the **setup** tool to install the server noninteractively.
- For more information about the available setup options, run **setup** with the **--help** argument, which displays a complete list of setup options, along with examples.

\$./setup --help

Example

The following example sets up PingAuthorize with these settings:

• LDAP port 8389

- LDAPS port 8636
- HTTPS port 8443
- An automatically generated self-signed server certificate
- 1 GB of memory reserved for the server's JVM
- A unique server instance name of pingauthorize1

• A server location of Austin

\$./setup \	
clino-promptacceptLicense \	
licenseKeyFile <path-to-license></path-to-license>	,
rootUserDN "cn=directory manager" \	(
rootUserPassword <your-password></your-password>	
ldapPort 8389ldapsPort 8636 \	
httpsPort 8443 \	
generateSelfSignedCertificate \	
maxHeapSize 1g \	
instanceName pingauthorize1 \	
location Austin	

Installing the PingAuthorize Policy Editor manually

Choose the database for your fine-grained access control use case, protected resource, and computing environment and install the PingAuthorize Policy Editor.

About this task

You can install the PingAuthorize Policy Editor in one of two ways: interactively or noninteractively.

Steps

1. Choose the database to use:

Choose from:

- H2: The default embedded database.
- PostgreSQL: This is optional and requires additional configuration.
- 2. **Optional:** If you are using a PostgreSQL database, set up the database.

For more information, see Setting up a PostgreSQL database.

3. Install the PingAuthorize Policy Editor:

Choose from:

• Interactive: The setup tool prompts you for information during the installation process.

For more information, see Installing the PingAuthorize Policy Editor interactively.

• Noninteractive: Automated installation allows more control over configuration. If you are using a PostgreSQL database, you must use this mode.

For more information, see Installing the PingAuthorize Policy Editor non-interactively.

Installing the PingAuthorize Policy Editor interactively

You can run the PingAuthorize Policy Editor **setup** command interactively in command-line interface (CLI) install mode.

Before you begin

You must have the following information:

- The location of a valid license file
- An available port for the PingAuthorize Policy Editor to accept HTTPS requests

About this task

The setup tool prompts you interactively for the information that it needs.

(i) Note

You cannot configure some setup options when installing the PingAuthorize Policy Editor interactively, such as PostgreSQL database configuration. For more information, see Installing the PingAuthorize Policy Editor non-interactively.

Steps

1. Choose the authentication mode for the PingAuthorize Policy Editor:

Choose from:

- Demo mode: Configures the PingAuthorize Policy Editor to use form-based authentication with a fixed set of credentials. Unlike OpenID Connect (OIDC) mode, this mode doesn't require an external authentication server. However, it is inherently insecure and should only be used for demonstration purposes.
- OIDC mode: Configures the PingAuthorize Policy Editor to delegate authentication and sign-on services to a PingFederate OIDC provider.

In OIDC mode, you must provide the following additional information:

- $^{\circ}\,$ The host name and port of an OIDC provider
- Information related to the server's connection security, including the location of a keystore that contains the server certificate, the nickname of that server certificate, and the location of a trust store

i) Note

To use PingAuthorize Policy Editor with other OIDC providers, such as PingOne, see Installing the PingAuthorize Policy Editor non-interactively.

2. Run the **setup** command.

i) Note

If you don't want to use the default database credential, see Setting database credentials at initial setup.

3. Copy and record any generated values needed to configure external servers.

The Shared Secret is used in PingAuthorize, under External Servers \rightarrow Policy External Server \rightarrow Shared Secret.

4. To start the Policy Editor, or policy administration point (PAP), run bin/start-server.

The Policy Editor runs in the background, so you can close the terminal window in which it was started without interrupting it.

Example

See Example: Installing and configuring the Policy Editor interactively for a more detailed walkthrough of the previous steps.

Next steps

- 1. Complete the steps in Post-setup steps (manual installation).
- 2. Consider additional configuration options in Specifying custom configuration with an options file.

Example: Installing and configuring the Policy Editor interactively

This tutorial describes how to install an instance of the PingAuthorize Policy Editor interactively.

About this task

(i) Note

These installation instructions are for tutorial purposes. They will only provide a limited install.

Steps

- 1. Extract the contents of the compressed PingAuthorize-PAP distribution file.
- 2. Change the directory to PingAuthorize-PAP.
- 3. To configure the application, run the ./bin/setup script.
- 4. Answer the on-screen questions.

For the following questions, use the recommended answers provided.

Question	Answer
How would you like to configure the Policy Editor?	Use Quickstart to set up a demo server with credentials admin / password123 and to use a self-signed certificate for SSL
On which port should the Policy Editor listen for HTTPS communications?	You can use any unused port here, but most of the examples in this guide assume that port 9443 is used for the PingAuthorize Policy Editor.
Enter the fully qualified host name or IP address that users' browsers will use to connect to this GUI	Unless you are testing on localhost , ensure that the provided API URL uses the public DNS name of the PingAuthorize Policy Editor server. For example, pap.example.com.

5. Copy and record any generated values needed to configure external servers.

The Shared Secret is used in PingAuthorize, under **External Servers** → **Policy External Server** → **Shared Secret**.

6. To start the Policy Editor, or policy administration point (PAP), run bin/start-server.

The Policy Editor runs in the background, so you can close the terminal window in which it was started without interrupting it.

Result

Your demo configuration should resemble the following example.

[/opt/{pingauthorize}-PAP]\$ bin/setup Please enter the location of a valid {pingauthorize} with Symphonic license file [/opt/{pingauthorize}-PAP/{pingauthorize}.lic]: /opt/{pingauthorize}/{pingauthorize}.lic {pingauthorize} Policy Editor _____ How would you like to configure the Policy Editor? 1) Quickstart (DEMO PURPOSES ONLY): This option configures the server with a form based authentication and generates a self-signed server certificate 2) OpenID Connect: This option configures the server to use an OpenID Connect provider such as {pingfed} 3) Cancel the setup Enter option [1]: 1 On which port should the Policy Editor listen for application HTTPS communications? [9443]: 9443 Enter the fully qualified host name or IP address that users' browsers will use to connect to this GUI [centos.localdomain]: pap.examplecom On which port should the Policy Editor listen for administrative HTTPS communications? [9444]: 9444 Would you like to enable periodic policy database backups? (yes / no) [yes]: yes Enter the backup schedule as a cron expression (defaults to daily at midnight): [0 0 0 * * ?]: 0 0 0 * * ? Setup Summary -----Host Name: pap.example.com Server Port: 9443 Secure Access: Self-signed certificate Admin Port: 9444 Periodic Backups: Enabled Backup Schedule: 0 0 0 * * ? Command-line arguments that would set up this server non-interactively: setup demo --hostname pap.example.com --adminPort 9444 --port 9443 --certNickname server-cert \ --licenseKeyFile /opt/{pingauthorize}/{pingauthorize}.lic \ --backupSchedule '0 0 0 * * ?' --pkcs12KeyStorePath config/keystore.p12 \ --generateSelfSignedCertificate What would you like to do? 1) Set up the server with the parameters above 2) Provide the setup parameters again 3) Cancel the setup Enter option [1]: Setup completed successfully

Please configure the following values {pingauthorize} Server - Policy External Server Base URL: Shared Secret: Trust Manager Provider: Please start the server by running bin/start-server

In this example, the PingAuthorize Policy Editor is now running and listening on port 9443.

Next steps

To sign on to the interface, go to https://<host>:9443^[]. The default credentials are admin and password123.

(i) Note

Use the default user name and password sign on credentials for demo and testing purposes only, such as this initial walk-through. To configure the PingAuthorize Policy Editor for PingFederate OpenID Connect (OIDC) single sign-on (SSO), see Installing the PingAuthorize Policy Editor non-interactively.

Installing the PingAuthorize Policy Editor non-interactively

For an automated software installation, run PingAuthorize Policy Editor **setup** in the non-interactive command-line interface (CLI) install mode.

About this task

γ Νote

You must run **setup** in non-interactive command-line mode instead of interactive mode if you need to do any of the following:

- Configure the Policy Editor with a policy configuration key.
- Configure a key store for a policy information provider.
- · Configure a trust store for a policy information provider.
- Customize the Policy Editor's logging behavior.
- Configure the Policy Editor for a PostgreSQL database.
- Configure the Policy Editor to present an existing Secure Sockets Layer (SSL) certificate instead of generating a self-signed certificate.
- Enable self-governance.

For more information, see Specifying custom configuration with an options file.

Steps

1. **Optional:** If you choose to use a PostgreSQL policy database, you must **set up the database** before you install the Policy Editor.

After you set up your PostgreSQL policy database, be prepared to provide the following information when installing the Policy Editor:

• PostgreSQL Java database connectivity (JDBC) connection string, with the host, port, and database name

- The server runtime credential provided through the **policy-db** tool
- 2. Choose the authentication mode for the PingAuthorize Policy Editor:

Choose from:

- Demo mode: Configures the PingAuthorize Policy Editor to use form-based authentication with a fixed set of credentials. Unlike OpenID Connect (OIDC) mode, this mode doesn't require an external authentication server. However, it's inherently insecure and should only be used for demonstration purposes.
- OIDC mode: Configures the PingAuthorize Policy Editor to delegate authentication and sign-on services to an OIDC provider, such as PingFederate.

If you choose OIDC mode, you must provide the host name and port of an OIDC provider or its base URL.

i) Note

If you don't use the **setup** tool to generate a self-signed certificate, you must also provide information related to the PingAuthorize Policy Editor's connection security, including the location of a key store that contains the server certificate and the nickname of that server certificate.

If the OIDC provider presents a certificate that is not trusted by the Policy Editor's Java Runtime Environment (JRE), do one of the following:

- Add the certificate to the JRE trust store. For details, see Configuring an OIDC provider for single sign-on requests from PingAuthorize.
- Disable certificate validation by starting the Policy Editor with the PING_OIDC_TLS_VALIDATION environment variable set to NONE. See the following tabs for examples.

O Tip

The **setup** tool's --help option displays the options available for a non-interactive installation.

3. Run the **setup** command with the appropriate authentication mode, as illustrated in Authentication mode examples.

- 1. **Optional:** If you're using a PostgreSQL policy database, provide the server runtime user value you used to create the database to --dbAppUsername as part of the **setup** command.
- 2. **Optional:** Explore the CLI help documentation for the **setup** command.

Option	Command
View the general options for running setup .	<pre>\$ bin/setuphelp</pre>
View the options for running setup in demo mode.	<pre>\$ bin/setup demohelp</pre>
View the options for running setup in OIDC mode.	<pre>\$ bin/setup oidchelp</pre>

γ Note

If you don't want to use the default database credentials for your H2 policy database, see Setting database credentials at initial setup.

4. Copy and record any generated values needed to configure external servers.

The shared secret is used in PingAuthorize, under External Servers → Policy External Server → Shared Secret.

5. To start the Policy Editor, or policy administration point (PAP), run bin/start-server.

The Policy Editor runs in the background, so you can close the terminal window in which it was started without interrupting it.

1. **Optional:** If you're using a PostgreSQL policy database, provide the server runtime password value you used to create the database to the **PING_DB_APP_PASSWORD** environment variable before server start.

Authentication mode examples

Click the following tabs for examples of the **setup** command in different authentication modes.

- 1. After you complete setup, see Post-setup steps (manual installation).
- 2. Consider additional configuration options in Specifying custom configuration with an options file.

OIDC mode (PingFederate)

Example: Set up the PingAuthorize Policy Editor in OIDC mode (PingFederate)

Use this example as a reference to set up the PingAuthorize Policy Editor for sign-ons using a PingFederate OIDC provider:

```
$ bin/setup oidc \
    --oidcHostname <ping-federate-hostname> \
    --oidcPort <ping-federate-port> \
    --clientId pingauthorizepolicyeditor \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

The Policy Editor uses the provided OIDC host name and OIDC to query the PingFederate server's autodiscovery endpoint for the information it needs to make OIDC requests. The provided client ID represents the Policy Editor and must be configured in PingFederate.

The Policy Editor can skip host name verification and accept self-signed SSL certificates from the OIDC provider.

The following example uses the **PING_OIDC_TLS_VALIDATION** environment variable to set up the Policy Editor to handle sign-ons for a provider using a self-signed certificate:

```
$ env PING_OIDC_TLS_VALIDATION=NONE bin/setup oidc \
    --oidcHostname <ping-federate-hostname> \
    --oidcPort <ping-federate-port> \
    --clientId pingauthorizepolicyeditor \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

For more information about configuring PingFederate, see Configuring an OIDC provider for single sign-on requests from PingAuthorize.

OIDC mode (generic)

Example: Set up the PingAuthorize Policy Editor in OIDC mode (generic OIDC provider)

This example sets up the PingAuthorize Policy Editor for sign-ons using an arbitrary OIDC provider.

This example departs from the PingFederate example by specifying the OIDC provider's base URL, rather than a host name and port. This can be useful if the OIDC provider's autodiscovery and authorization endpoints include an arbitrary prefix, such as a customer-specific environment identifier.

```
$ bin/setup oidc \
    --oidcBaseUrl https://auth.example.com/9595f417-a117-3f24-a255-5736ab01f543/auth/ \
    --clientId 7cb9f2c9-c366-57e0-9560-db2132b2d813 \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

The Policy Editor uses the provided OIDC base URL to query the OIDC provider's autodiscovery endpoint for the information it needs to make OIDC requests. The provided client ID represents the Policy Editor and must be configured in the OIDC provider as well.

The Policy Editor can skip host name verification and accept self-signed SSL certificates from the OIDC provider.

The following example uses the **PING_OIDC_TLS_VALIDATION** environment variable to set up the Policy Editor to handle sign-ons for a provider using a self-signed certificate:

```
$ env PING_OIDC_TLS_VALIDATION=NONE bin/setup oidc \
    --oidcBaseUrl https://auth.example.com/9595f417-a117-3f24-a255-5736ab01f543/auth/ \
    --clientId 7cb9f2c9-c366-57e0-9560-db2132b2d813 \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
```

```
--licenseKeyFile <path-to-license>
```

For more information about configuring an OIDC provider, see Configuring an OIDC provider for single sign-on requests from PingAuthorize.

OIDC mode (custom scope)

Example: Set up the PingAuthorize Policy Editor in OIDC mode (custom scope)

This example sets up the PingAuthorize Policy Editor for sign-ons using OIDC with one or more custom scopes.

In OIDC mode, the Policy Editor UI requests an access token with the following default scopes: **openid email profile**. You can change the default requested scopes persistently, during server setup, or on a one-time basis, at server startup.

Add OIDC scopes during setup

To add requested OIDC scopes persistently, use the **--scope** option to provide a space-separated list of scopes to the **setup** command.

```
$ bin/setup oidc \
    --oidcBaseUrl https://auth.example.com/02fa3993-a851-4eb5-96c7-f0c561be23c6/auth/ \
    --clientId 21a74125-85db-4fca-8a56-e5d45d4d8163 \
    --scope "openid email profile <additional_scope>" \
    --generateSelfSignedCertificate \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

The Policy Editor uses the provided OIDC base URL to query the OIDC provider's autodiscovery endpoint for the information it needs to make OIDC requests. The provided client ID represents the Policy Editor and must be configured in the OIDC provider as well.

The Policy Editor can skip host name verification and accept self-signed SSL certificates from the OIDC provider. The following example uses the **PING_OIDC_TLS_VALIDATION** environment variable to set up the Policy Editor to handle signons for a provider using a self-signed certificate:

```
$ env PING_OIDC_TLS_VALIDATION=NONE bin/setup oidc \
    --oidcBaseUrl https://auth.example.com/02fa3993-a851-4eb5-96c7-f0c561be23c6/auth/ \
    --clientId 21a74125-85db-4fca-8a56-e5d45d4d8163 \
    --scope "openid email profile <additional_scope>" \
    --generateSelfSignedCertificate \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

Add OIDC scopes at startup

To override persistently requested OIDC scopes for a single runtime instance of the Policy Editor, use the **PING_SCOPE** environment variable to provide a space-separated list of scopes to the **start-server** command:

```
$ env PING_SCOPE="openid email profile <different_scope>" bin/start-server
```

For more information about configuring an OIDC provider, see Configuring an OIDC provider for single sign-on requests from PingAuthorize.

OIDC mode (self-governance)

Example: Set up the PingAuthorize Policy Editor in OIDC mode (self-governance)

This example sets up the PingAuthorize Policy Editor with self-governance and OIDC authentication.

For more information about configuring OIDC authentication, see the OIDC mode (generic) tab on this page.

j Note

Self-governance is not supported in clustered Policy Editor configurations.

To enable self-governance with OIDC authentication, use the following arguments:

--enableSelfGovernance (required)

Turns on the self-governance functionality.

--selfGovernanceSystemUser (required)

Sets the self-governance administrator username for OIDC authentication.

--apiHttpCacheTtl (optional)

Sets the time-to-live value (in seconds) for the HTTP cache, after which the cache is refreshed and a new selfgovernance check is performed. This value must be 1 or greater.

) Note

If you don't specify a value, the Policy Editor uses the default time-to-live of 60 seconds.

The following example sets up the Policy Editor to use PingOne for OIDC authentication, enables self-governance, and specifies an OIDC username for the self-governance administrator:

```
$ bin/setup oidc \
--hostname localhost \
--port 9443 \
--adminPort <admin-port> \
--oidcBaseUrl https://auth.pingone.com/<my-environment-id>/as \
--clientId <my-client-id> \
--generateSelfSignedCertificate \
--enableSelfGovernance \
--selfGovernanceSystemUsername <oidc-authenticated-user>
```

Demo mode

Example: Set up the PingAuthorize Policy Editor in demo mode

This example sets up the PingAuthorize Policy Editor in demo mode with an automatically-generated self-signed server certificate.

After completing setup, the Policy Editor will accept sign-ons using the username admin and the password password123.

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license>
```

The decision point shared secret is a credential that the PingAuthorize Server uses to authenticate to the Policy Editor when it uses the Policy Editor as an external policy decision point (PDP).

For information about how to configure PingAuthorize Server to use the decision point shared secret, see Post-setup steps (manual installation).[discrete]

Demo mode (PostgreSQL)

Example: Set up the PingAuthorize Policy Editor with a PostgreSQL policy database

This example sets up the PingAuthorize Policy Editor in demo mode with the following options:

- · Automatically generated self-signed server certificate
- PostgreSQL policy database with server runtime credentials (see the following caution about --dbAppPassword)

\$ bin/setup demo \

- --dbConnectionString "jdbc:postgresql://<host>:<port>/<database>" \
- --dbAppUsername "<db-user>" \
- --dbAppPassword "<db-password>" $\$
- --generateSelfSignedCertificate \
- --decisionPointSharedSecret pingauthorize \
- --hostname <pap-hostname> $\$
- --port <pap-port> \
- --adminPort <admin-port> \
- --licenseKeyFile <path-to-license>

() Caution

Using the --dbAppPassword option to provide the PostgreSQL database password to the **setup** tool persists the password to a configuration file.

Instead, omit --dbAppPassword entirely to persist the default password, and set the PING_DB_APP_PASSWORD environment variable before server start. For example:

\$ env PING_DB_APP_PASSWORD=<db-password> bin/start-server

Demo mode (custom SSL certificate)

Example: Set up the PingAuthorize Policy Editor to use a custom SSL certificate

This example sets up the PingAuthorize Policy Editor in demo mode with a provided SSL server certificate in PKCS12 format:

```
$ env KEYSTORE_PIN_FILE=<path-to-keystore.pin> bin/setup demo
--adminUsername admin \
--pkcs12KeyStorePath <path-to-keystore.p12> \
--certNickname <certificate-nickname> \
--decisionPointSharedSecret <shared-secret> \
--hostname <pap-hostname> \
--port <pap-port> \
--adminPort <admin-port> \
--licenseKeyFile <path-to-license>
```

(i) Note

If you don't use the KEYSTORE_PIN_FILE during setup, you can supply the --keystorePassword option.

The following information describes the previous example code block:

- The KEYSTORE_PIN_FILE environment variable, along with the --pkcs12KeyStorePath and --certNickname command-line options, affect the server's SSL certificate configuration.
- KEYSTORE_PIN_FILE contains the path to a file containing a valid key store PIN value.
- The --pkcs12KeyStorePath value is a path to a valid PKCS12 key store file.
- The --certNickname value is the certificate nickname or alias.

n Warning

- The PingAuthorize Policy Editor only supports lowercase certificate nicknames.
- Because the KEYSTORE_PIN_FILE is not persisted, it must also be available in the environment of start-server.

Demo mode (self-governance)

Example: Set up the PingAuthorize Policy Editor in demo mode (self-governance)

This example sets up the PingAuthorize Policy Editor in demo mode with self-governance enabled.

For more information about setting up the Policy Editor in demo mode, click the **Demo mode** tab on this page.

To enable self-governance in demo mode, use the --enableSelfGovernance argument. The following values are set by default:

- The time-to-live value for the HTTP cache is set to 60 seconds, after which the cache is refreshed and a new selfgovernance check is performed.
- The self-governance administrator username is set to selfgovernanceadmin.
- The self-governance administrator password is set to password123.

The following example sets up the Policy Editor in demo mode with self-governance enabled:

```
$ bin/setup demo \
--adminUsername admin \
--enableSelfGovernance \
--generateSelfSignedCertificate \
--licenseKeyFile /opt/PingAuthorize/PingAuthorize.lic \
--decisionPointSharedSecret pingauthorize \
--hostname localhost \
--port 9443 \
--adminPort <admin-port>
```

Clustering and scaling

PingAuthorize Servers are stateless. They do not require intra-cluster communication to scale. Instead, similarly configured independent server instances can be added behind the same network load balancer to achieve higher throughput while maintaining low latency.

Automated environments

To maintain identically configured PingAuthorize Server instances behind your load balancer, use DevOps principles of Infrastructure-as-Code (IaC) and Automation. For more information about using server profiles to scale upward by installing a new, identically configured instance of PingAuthorize Server, see Deployment automation and server profiles.

Post-setup steps (manual installation)

After you set up the PingAuthorize Policy Editor, you must start the server from the CLI and then change the PingAuthorize Server configuration to use the Policy Editor as its policy decision point (PDP).

To start the Policy Editor, run the following command.

\$ bin/start-server

Then, sign on to the Policy Editor and import a policy snapshot. You can find a set of default policies in the resource/policies/ defaultPolicies.SNAPSHOT file. For more information, see Signing on to the PingAuthorize Policy Editor.

To configure PingAuthorize Server to use the Policy Editor, use **dsconfig** or the administrative console to create a Policy External Server to represent the Policy Editor, then assign the Policy External Server to the Policy Decision Service and configure it to use external PDP mode. Also, set the Trust Framework Version to the current version, v2. Consider the following example.

```
dsconfig create-external-server \
    --server-name "{PAP_Name}" \
    --type policy \
    --set "base-url:https://<pap-hostname>:<pap-port>" \
    --set "shared-secret:pingauthorize" \
    --set "branch:Default Policies" \

dsconfig set-policy-decision-service-prop \
    --set pdp-mode:external \
    --set "policy-server:{PAP_Name}"
    --set trust-framework-version:{TRUST_FRAMEWORK_VERSION}
```

In the example, the base URL consists of the host name and port chosen for the Policy Editor during setup. Similarly, the shared secret value was chosen during setup. The branch name corresponds to the branch name that you chose when importing your policy snapshot. The decision node is the ID of the root node in your policy tree. If you are using the default policies, then use the ID shown in the example.

Next steps

After installed, complete some configuration steps and then start developing policies to enforce fine-grained access to data.

Consider performing the following next steps:

- · Configure access token validation.
- Configure a user store.
- Sign on to the administrative console to configure endpoints for existing JSON APIs.

For more information, see About the API security gateway.

• Sign on to the administrative console to define SCIM APIs for data in databases.

For more information, see About the SCIM service.

• Sign on to the PingAuthorize Policy Editor to create policies.

For more information, see the PingAuthorize Policy Administration Guide.

Signing on to the administrative console

After deploying or installing the server, access the administrative console to verify the server configuration and manage the server settings.

Docker deployment

Signing on to the administrative console (Docker deployment) About this task

When using Docker containers, the containers must be on the same Docker network to communicate properly.

Steps

1. Start the PingDataConsole.

The following command uses the ~/.pingidentity/config environment file to configure common environment variables. See Get Started ^[2].

```
docker run \
    --env-file ~/.pingidentity/config \
    --name pingdataconsole \
    --detach \
    --publish 5443:8443 \
    --tmpfs /run/secrets \
    pingidentity/pingdataconsole:<TAG>
```

The Docker image *<TAG>* used in the example is only a placeholder. For actual tag values, see Docker Hub (https://hub.docker.com/r/pingidentity/pingdataconsole^[2]).

2. Sign on using the information in the following table.

Description	Details
URL	https://localhost:\${HTTPS_PORT}/console/login□
Details to enter at login	Server: pingauthorize:1636 Username: administrator Password: 2FederateM0re
	O Note If submitting the form results in a "Server unavailable" error, wait longer for the containers to reach an equilibrium "healthy" state, as described in Verifying proper startup.

Manual installation

Signing on to the administrative console (manual installation) Steps

1. To access the administrative console, go to https://<host>:<port>/console/login .

The default port is 8443.

2. To sign on to the administrative console, use the initial root user distinguished name (DN) and root user password specified during setup.

The default DN is cn=Directory Manager.

Signing on to the PingAuthorize Policy Editor

You can sign on to the PingAuthorize Policy Editor by entering your username and password credentials in the appropriate web browser URL.

Steps

 After completing setup for demo mode, sign on to the PingAuthorize Policy Editor by going to the following URL in a web browser: \https://<host>:<port>.

Substitute the host name and port that you specified during setup.

- 2. Use the following demo credentials to sign on to the PingAuthorize Policy Editor:
 - User name: admin
 - Password: password123
- 3. **Optional:** If you set up the PingAuthorize Policy Editor to use OpenID Connect (OIDC) mode, you must also configure an OIDC provider. For more information, see **Configuring an OIDC provider for single sign-on requests from PingAuthorize**.

Then, when you sign on using the URL mentioned previously, the GUI prompts you to proceed to the OIDC provider to sign on. After OIDC authentication is complete, the GUI redirects you back to the PingAuthorize Policy Editor.

Changing the PingAuthorize Policy Editor authentication mode

You can change the authentication mode after the initial setup.

Steps

- For a manually installed Policy Editor, see Changing the Policy Editor authentication mode for manual installs.
- For a Policy Editor Docker deployment, see Changing the Policy Editor authentication mode for Docker deployments.

Changing the Policy Editor authentication mode for manual installs

About this task

To change the authentication mode that a manually installed PingAuthorize Policy Editor uses, re-run the **setup** tool and choose a different authentication mode. This action overwrites the PingAuthorize Policy Editor's existing configuration.

Steps

1. Stop the Policy Editor.

Example:

\$ bin/stop-server

2. Run the **setup** command and select a different authentication mode.

The modes are:

• Demo mode

Configures the PingAuthorize Policy Editor to use form-based authentication with a fixed set of credentials. Unlike OIDC mode, this mode does not require an external authentication server. However, it is inherently insecure and is recommended only for demonstration purposes.

OpenID Connect (OIDC) mode

Configures the PingAuthorize Policy Editor to delegate authentication and sign-on services to an OpenID Connect provider, such as PingFederate.

Example:

\$ bin/setup

3. Start the Policy Editor.

Example:

\$ bin/start-server

Changing the Policy Editor authentication mode for Docker deployments

About this task

To switch to OIDC authentication for a Docker deployment of the PingAuthorize Policy Editor, re-run the **docker run** command using the OIDC environment variables.

Steps

- 1. Stop the Policy Editor Docker container.
- 2. Run the Policy Editor Docker container in OIDC mode by using the PING_OIDC_CONFIGURATION_ENDPOINT and PING_CLIENT_ID environment variables in your docker run command, as shown in the following example.

Example:

γ Νote

For proper communication between containers, create a Docker network using a command like docker network create --driver <network_type> <network_name>, and then connect to that network with the -- network=<network_name> option.

docker run --network=<network_name> -p 8443:1443 -d \
--env-file ~/.pingidentity/config \
--env PING_EXTERNAL_BASE_URL=localhost:8443 \
--env PING_CLIENT_ID=c2f081c0-6a2e-4249-b07d-d60234bb5b21 \
--env PING_OIDC_CONFIGURATION_ENDPOINT=https://auth.pingone.com/3e665735-23da-40a9-a2bb-7ccddc171aaa/as/.wellknown/openid-configuration \
pingidentity/{PAP_CONTAINER_NAME}:<TAG>

(i) Note

The Docker image < TAG > used in the example is only a placeholder. For actual tag values, see the **PingAuthorize PAP Docker Image** \square on Docker Hub.

Configuring an OIDC provider for single sign-on requests from PingAuthorize

When you install the PingAuthorize software with OpenID Connect (OIDC) authentication, configure an OIDC provider to accept single sign-on (SSO) requests from PingAuthorize.

About this task

If you chose OIDC mode when you set up the PingAuthorize Policy Editor, you must configure an OIDC provider, such as PingFederate or PingOne, to accept sign-on requests from the PingAuthorize Policy Editor. Refer to the following tabs for the configuration steps for PingOne and PingFederate.

If you're using another OIDC provider, refer to the provider's documentation for specific client configuration steps. The following steps show the general procedure:

Steps

1. Use the following configuration values to create an OAuth 2 client that represents the PingAuthorize Policy Editor.

OAuth 2 client configuration	Configuration value
Client ID	pingauthorizepolicyeditor
Redirect URI	https:// <host>:<port>/idp-callback</port></host>
Grant type	Authorization Code with PKCE
Response type	code
Scopes	
Refresh tokens	Enable

OAuth 2 client configuration	Configuration value
Client authentication on the token endpoint	Disable The Policy Editor doesn't have access to the client secret and doesn't send the credential to the token endpoint.
Return ID token on refresh grant	true
Always re-roll refresh tokens	true

S Important

When an authentication token expires, the Policy Editor performs a silent renewal, triggering a background process to retrieve a new token from the OIDC provider. For this process to work, you must configure your OIDC provider to issue the refresh token in the following manner:

• Issue an id_token as part of the refresh grant.

• Re-roll the refresh token after each use. The Policy Editor will not use refresh tokens more than once. Because these constraints apply to silent renewal, a misconfiguration of the previous items will still allow you to sign on. After your token expires, though, the application will eject you from your session and redirect you to the sign-on screen. This could cause you to lose unsaved changes in the Policy Editor.

- 2. Configure the access tokens and ID tokens issued for the OAuth 2 client with the following claims:
 - ° sub
 - ° name
 - ° email
- 3. Configure the OIDC provider to accept a cross-origin resource sharing (CORS) origin that matches the PingAuthorize Policy Editor's scheme, public host, and port, such as https://<host>:<port>.
- 4. Configure the OIDC provider to issue tokens to the PingAuthorize Policy Editor only when the authenticated user is authorized to administer policies according to your organization's access rules.

i Note

Sign the tokens with a signing algorithm of RSA using SHA-256.

For PingFederate, this level of authorization is controlled with issuance criteria. Learn more in the PingFederate documentation.

Configuring PingOne

Configuring PingOne as an OIDC provider for PingAuthorize

To improve security and ensure a consistent authentication experience across all enterprise applications, enable single sign-on (SSO) for the PingAuthorize Policy Editor using PingOne as an OIDC provider.

Components

- PingOne
- PingAuthorize 9.0 or later

Instructions and screenshots might differ slightly from other product versions. You can find the latest documentation in the PingOne^[] documentation.

Before you begin

- Confirm that PingOne is accessible from the subnet on which the Policy Editor is running.
- Extract the Policy Editor distribution to your specified install location, with appropriate permissions set for write access, for example /opt/PingAuthorize-PAP.

Configuring PingOne for PingAuthorize policy administration About this task

Configure PingOne to authorize external access to the Policy Editor.


Steps

1. Sign on to PingOne and click your environment.

Choose from:

- If you have an account, go to the URL for your environment. Each environment has a unique URL for signing on that follows the https://console.pingone.com/?env=<environmentID> format.
- \circ If you don't already have a PingOne account, create one at Try Ping^[].
- 2. To create an application in PingOne to represent the Policy Editor, go to **Connections > Applications** and click the + icon.
- 3. Enter a name for the application, such as **PingAuthorize Policy Editor**.
- 4. (Optional) Enter a description and add an icon.
- 5. Click OIDC Web App, and then click Save.
- 6. On the **Configuration** tab, click the **Pencil** icon to edit the settings.
- 7. In the PKCE Enforcement list in the Grant Type section, select S256_REQUIRED.
- 8. In the Redirect URIs field, enter a redirect URL that follows the format https://<pap.hostname:port>/idpcallback.
- 9. In the Token Endpoint Authentication Method section, click None.
- 10. Click Save.

- 11. On the **Resources** tab, click the **Pencil** icon to edit the settings.
- 12. In the Scopes list, click the + icon to add the email and profile scopes to the Allowed Scopes list.
- 13. Click Save.
- 14. Click the toggle to enable the application.



15. Copy the following IDs:

- Client ID: To find the client ID, go to the application's Profile tab.
- Environment ID: To find the environment ID, click Environment in the left navigation pane.

Note You'll need the client ID and the environment ID to configure the Policy Editor to use PingOne.

Configuring PingAuthorize policy administration to use PingOne About this task

The following configuration enables the Policy Editor to use PingOne for authentication.

Steps

- 1. Run the <PingAuthorize-PAP> /bin/stop-server command to stop the Policy Editor.
- 2. Using the client ID and environment ID from Configuring PingOne for PingAuthorize policy administration, run the following command to configure the Policy Editor:

```
bin/setup oidc \
    --licenseKeyFile <path to PingAuthorize.lic> \
    --generateSelfSignedCertificate \
    --hostname <pap-hostname> --port <pap-port> \
    --adminPort <admin-port> \
    --oidcBaseUrl https://auth.pingone.<regional domain>/<environment id>/as \
    --clientId <client-id>
```

3. Run the **bin/start-server** command to start the Policy Editor.

- 4. Verify that you can sign on to the Policy Editor using the application you created in PingOne:
 - 1. Go to the Policy Editor.
 - 2. Click Click to Sign in.

Result:

Your browser redirects to the URL you set in Configuring PingOne for PingAuthorize policy administration.



By default, the signed-on username uses the **sub** JSON Web Token (JWT) claim for the OIDC user ID. You can find details on using a non-default claim in **Changing the default JWT claim for the OIDC user ID**.

Configuring PingFederate

Configuring PingFederate as an OIDC provider for PingAuthorize

To improve security and ensure a consistent authentication experience across all enterprise applications, enable single sign-on (SSO) for the PingAuthorize Policy Editor using PingFederate as an OIDC provider.

This topic describes one way to configure PingFederate as an OpenID Connect provider for the PingAuthorize Policy Editor. In this example, PingFederate also acts as the identity provider and uses a PingDirectory LDAP server with sample data as the backing store.

Components

- PingFederate 10.3 or later
- PingDirectory 9.0 or later
- PingAuthorize 9.0 or later

Instructions and screenshots might differ slightly from other product versions. For the latest documentation, see the PingFederate documentation \square and PingDirectory documentation \square .

Before you begin

Make sure of the following:

- PingFederate is running and accessible from the subnet on which the Policy Editor is running.
- PingDirectory is running and accessible from the subnet on which PingFederate is running.
- PingDirectory is loaded with the identities to be used. This example uses the sample data provided when running the PingDirectory setup command line tool with option --sampleData 1000.
- You have extracted the Policy Editor distribution to your specified install location, with appropriate permissions set for write access. This document uses an installation directory of /opt/PingAuthorize-PAP.
- If using SSL, the certificate chain is available as a PKCS12 keystore to upload as the server certificate chain for PingFederate.
- The signing certificate for JWT tokens is available for upload to PingFederate.

(i) Note

If the PingFederate certificate chain contains certificates that aren't trusted by the default Java truststore on the system on which the Policy Editor is running, you'll need to add them. An example of how to do this is provided in the "Add Certificate to Java Trust Store" subsection.

Configuring PingFederate for PingAuthorize

Configure PingFederate to authorize external access through tokens to the PingAuthorize Policy Editor.

About this task

You can also use PingAccess to authorize external access through rules. Learn more in Rule Creation in PingAccess \square in the PingAccess documentation.

The following example configuration assumes that any authenticated user can access the PingAuthorize Policy Editor. You can find more informarion about limiting access to members of a specific group in Configuring PingFederate group access for PingAuthorize.

Steps

- 1. In the PingFederate administrative console, go to System > Data & Credential Stores > Data Stores.
- 2. Click Add New Data Store.
- 3. On the **Data Store Type** tab, in the **Name** field, enter a name for the datastore.
- 4. In the Type list, select Directory (LDAP), and then click Next.
- 5. On the **LDAP Configuration** tab, enter the address and authentication information for PingFederate to use when accessing PingDirectory, and then click **Next**.
- 6. On the **Summary** tab, review your configuration. Click **Save**.

Ping	Federate	AUTHENTIC	ATION APPLICATIONS	SECURITY SECURITY	YSTEM	С	
03	 ✓ Data & Credential Stores Data Stores 	Data Stores Data Store	mmary				
Ξ±	Password Credential Validators	Click a heading link to edit a configuration setting.	_				
\$		Data Store					
x	Active Directory Domains/Kerberos	Data Store Type					
	Realms	Type of Data Store		LDAP			
À	Identity Store	LDAP Configuration					
<>	Provisioners	Data Store Name		PingDirectory D	Data Store		
		Hostname(s)		Hostname(s): da Default	ls.example.com:1636		
		LDAP Type		PingDirectory			
		LDAPS		true			
		Username		cn=Directory M	lanager,cn=Root DNs,cn=config		
		Mask Values in Log		false			
		Test Connection on Borrow		false			
		Test Connection on Return		false			
		Create New Connections if Necessary		true			
		Verify LDAPS Hostname		true			
		Minimum Connections		10			
		Maximum Connections		100			
		Maximum Wait (ms)		-1			
		Time Between Eviction (ms)		60000			
		Read Timeout (ms)		3000			
		Connection Timeout (ms)		3000			
		DNS TTL (ms)		60000			
		LDAP DNS SRV Record prefix		_ldaptcp			
		LDAPs DNS SRV Record prefix		_ldapstcp			
https://lo	calhost:9999/render/pingfederate	app?service=direct/1/Home/Holder/summaryCard.\$Summary.direct	&sp=1		Cano	cel Previous	Save

7. Go to **Authentication > Policies > Sessions** and enable authentication sessions. The following example enables authentication sessions for all sources. Make the appropriate change for your environment, and then click **Save**.

Ping	Federate	AUTHENTICATION APPLICATIONS SECURITY SYSTEM			
	< Policies	Sessions			
۲	Policies	Sessions define how frequently users are challenged to authenticate. Application sessions apply to PingFederate user facing endpoints, such as the profile management endpoint. Authentication			
14	Fragments	sessions wrap authentication sources (IdP adapters and IdP connections) to control when they are invoked. Additional tracking options for logout are available to control if all adapters should be involved in the logout process, and if the user's revoked session should be published. Publishing revoked sessions is recommended in order to provide a secure single logout (SLO) experience with PingAccess deployments.			
0	Selectors	TRACK ADAPTER SESSIONS FOR LOGOUT			
A.A.	Policy Contracts	✓ TRACK REVOKED SESSIONS ON LOGOUT			
~~	Sessions	SESSION REVOCATION LIFETIME (MINUTES) 490			
	Local Identity Profiles	APPLICATION SESSIONS			
		IDLE TIMEOUT (MINUTES) 60			
		MAX TIMEOUT (MINUTES) 480			
		AUTHENTICATION SESSIONS			
		ENABLE AUTHENTICATION SESSIONS FOR ALL SOURCES			
MAKE AUTHENTICATION SESSIONS PERSISTENT					
		HASH UNIQUE USER KEY VALUE			

8. Go to Security > Certificate & Key Management > SSL Client Keys & Certificates and import your JWT signing certificate. Click Save.

í	Not	te			
		_			

PingFederate expects the certificate chain and keys to be encoded in PKCS12 format.

- 9. Configure your OAuth server using the OpenID Connect protocol.
 - 1. Go to **System > OAuth Settings > Scope Management** and create scopes.
 - 2. In the Scope Value field, enter the email, openid, and profile scopes and click Add after each entry. Click Save.

Ping	Federate		AUTHENTICATION	APPLICATIONS	SECURITY	SYSTEM				Q	?	
0)JJ	 OAuth Settings Authorization Server Settings 	Scope Management	ve Scopes Default Scope									
킢	Scope Management	Common scopes are available to request scopes where a compone		dividual clients are co	nfigured to restrict	t common scopes. Sc	opes can be d	leclared as dyna	mic, whic	ch allows OAu	th clients to	D
۵	Virtual Issuers	Scope Value	Scope Description				Dynamic	Action				
x	011	email	OpenId Connect Profile Email	Access				Edit Delete				
	Client Settings	openid	OpenID Connect Enablement					Edit Delete				
Ą	Client Registrations Policies	profile	OpenID User Profile Access					Edit Delete				
<>	Policies							Add				
		Scope Group Value	Scope Group Description	n			Sub Scope	es Ad	tion			
							email openi profile	d	Add			
								Ca	ncel	Next	Save	

- 3. Go to Applications > OAuth > Access Token Management and click Create New Instance.
- 4. On the **Type** tab, in the **Type** list, select **JSON Web Tokens**. In the **Parent Instance** list, select **None**. Click **Next**.

- 5. On the **Instance Configuration** tab, click **Add a new row to 'Certificates'** and add the previously imported signing certificate. Select the desired signing algorithm and token timeout, and then click **Next**.
- 6. On the Session Validation tab, enable the session validation options.

Ping	Federate		AUTHENTICATION	APPLICATIONS	SECURITY	SYSTEM	
	< OAuth	Access Token Manageme	ent Create Acc	ess Token Ma	nagement	Instance	
Z	Clients	Type Instance Configuration	Session Validation	Access Token Attrib	ute Contract	Resource URIs	
Ł	Access Token Management	On this page, a policy can be defined to bind together the validity of access tokens with the user's session. A session id query session status and tailor the application flow. You can require that the session has not been revoked through a log					
V .	Access Token	session that has not timed out. Activity	on associated authentica	ation sessions can also	be updated to	slide idle timeouts	
	Mappings	✓ INCLUDE SESSION IDENTIFIER	IN ACCESS TOKEN				
	0	✓ CHECK FOR VALID AUTHENTIC	ATION SESSION				
	OpenID Connect Policy Management	CHECK SESSION REVOCATION	STATUS				
	CIBA Request Policies	✓ UPDATE AUTHENTICATION SES	SION ACTIVITY				

7. On the Access Token Attribute Contract tab, add the attributes to be included in the OAuth access token. This example extends the contract with cn, email, scope, sub, and uid attributes.

Ping	Federate	AUTHENTICATION APPLICATIONS SECURITY SYSTEM	
	< OAuth	Access Token Management Create Access Token Management Instance	
2	Clients	Type Instance Configuration Session Validation Access Token Attribute Contract Resource URIs Access Control 5	Summary
Ł	Access Token Management	Provide the names of the attributes that will be carried in (or referenced by) the OAuth access token. For auditing purposes, an attribute may be cho	osen as the subject.
1		Extend the Contract	Action
***	Access Token Mappings	cn	Edit Delete
		email	Edit Delete
	OpenID Connect Policy Management	scope	Edit Delete
		sub	Edit Delete
	CIBA Request Policies	uid	Edit Delete
	Policies		Add

- 8. Click **Next** until you reach the **Summary** tab. Click **Save**. Accept the default values for the **Resources URIs** and **Access Control** settings.
- 9. Go to Applications > OAuth > Access Token Mappings to create an Access Token Mapping in the Default context for the Access Token Manager you just created. Click Add Mapping, and then click Add Attribute Source.
- 10. In the Active Data Store list, select the PingDirectory datastore that you created in step 2. Click Next.

Ping	Federate		AUTHENTICATION		SECURITY	SYSTEM
	< OAuth	Access Token Mappi	ngs Access Token	Mapping At	tribute Sour	ces & User Lookup
Ð	Clients	Data Store LDAP Directo	ry Search LDAP Filter	Summary		
Ł	Access Token Management	Data stores are used to retrieve s	upplemental attributes. Specify	the attribute store's	details to use it in y	your configuration.
Υ.Ψ	Access Token	ATTRIBUTE SOURCE ID	PingDirectory			
	Mappings	ATTRIBUTE SOURCE DESCRIPTION	Policy Token Mapping			
	OpenID Connect Policy Management	ACTIVE DATA STORE	PingDirectory Data Store	~		
	CIBA Request Policies	DATA STORE TYPE	LDAP			
		Manage Data Stores				

- 11. On the **LDAP Directory Search** tab, in the **Base DN** field, enter the base DN for the PingDirectory data that provides your identities.
- 12. In the **Attributes to return from search** section, click **Add Attribute** and enter the attributes to be retrieved.

The sample data uses ou=People, dc=example, dc=com, and the configuration shown in the following image retrieves the cn, mail, and uid attributes.

Access Token Attribute Mapping Access Token Mapping Attribute Sources & User Lookup				
Data Store LDAP Dire	tory Search LDAP Filter Summary			
Please configure your directory contract.	search. This information, along with the attribut	tes supplied in the contract,	will be used to fulfill the	
BASE DN	ou=People,dc=example,dc=com			
SEARCH SCOPE	One Level 🗸 🗸			
Attributes to return from search	h			
ROOT OBJECT CLASS	ATTRIBUTE		Action	
	Subject DN			
	cn		Remove	
	mail		Remove	
	uid		Remove	
<show all="" attributes=""></show>	ou	~	Add Attribute	
View Attribute Contract				
	Cancel	Previous Next	Done Save	

13. On the LDAP Filter tab, in the Filter field, enter uid=\${USER_KEY} to match the PingDirectory sample data with the authenticating user information.

Access Token Attribute Map User Lookup	ping Acces	s Token N	1apping Attr	ribute Sour	ces &
Data Store LDAP Directory Search	LDAP Filter	Summary			
Rease enter a Filter for extracting data from	your directory.				
FILTER uid=\${USER_KEY}					
Values					
\$[EXPIRES_AT]					
\$[USER_KEY]					
View List of Available LDAP Attributes					
			Cancel	Previous	Nex

- 14. On the **Summary** tab, click **Next** and **Save**.
- 15. On the **Contract Fulfillment** tab, fulfill the contract with the LDAP attributes from the PingDirectory datastore. Leave the remaining settings as their defaults and click **Save**.

The scope attribute is fulfilled from the OAuth context.

Access Token	Attribute Mapping Access	s Token Mappin	g	
Attribute Sources &	User Lookup Contract Fulfilment	Issuance Criteria	Summary	
Select a Source and Vi	alue to map into each item in the Contract	ist.		
Contract	Source	Value	Ac	tions
cn	LDAP (PingDirectory)	cn .	~ No	ine available
email	LDAP (PingDirectory)	v mai	~ No	ine available
scope	Context	Scope	~ No	ine available
sub	LDAP (PingDirectory)	uid	~ No	ine available
uid	LDAP (PingDirectory)	uid	~ No	ine available
	c	Previous	Next Don	Save

- 16. Go to Applications > OAuth > OpenID Connect Policy Management and click Add Policy.
- 17. On the **Manage Policy** tab, from the **Access Token Manager** list, select the access token manager you created previously.
- 18. Ensure that the Include User Info in ID Token checkbox is selected. Click Next.

- 19. On the Attribute Contract tab, extend the policy contract with the email and name attributes. Click Next.
- 20. On the Attribute Scopes tab, map the previously defined email and profile scopes to the email and name ID token attributes. Click Next.

Manage Policy	Attribute Contract	Attribute Scopes	Attribute Sources & User Loo	kup
Contract Fulfilme	nt Issuance Criteri	a Summary		
	OpenID Connect to contr n scopes and attributes I		e released to OAuth clients. On th I in the specification.	is page you may add
Scope			Attributes	Action
liams			email	Edit I Deleti
rofile			name	Edit I Delet
- SELECT -	~			Add

21. On the **Contract Fulfillment** tab, fulfill the contract with the values in the access token. Click **Next** until you reach the **Summary** tab, and then click **Save**.

Ping	Federate		AUTHENTICATION	APPLICATIONS SECURITY	SYSTEM	$\bigcirc @$
	< OAuth	OpenID Connect	Policy Management P	olicy		
Ð	Clients	Manage Policy Attr	ibute Contract Attribute Scopes	Attribute Sources & User Lookup	Contract Fulfillment	Issuance Criteria Summary
٨	Access Token Management	Fulfill the Attribute Contrac	t with values from the Access Token	or from other sources listed.		
1 ,1		Attribute Contract	Source	Value		Actions
	Access Token Mappings	email	Access Token 🗸	email	~	None available
	OpenID Connect Policy Management	name	Access Token 🗸	cn	~	None available
	CIBA Request Policies	sub	Access Token 🗸	sub	~	None available
						Cancel Previous Next Save

- 22. Click Set as Default to set the newly created policy as the default policy.
- 23. Go to Applications > OAuth > Clients and click Add Client.

To provide the Policy Editor with appropriate defaults, configure PingFederate with a **Client ID** of **pingauthorize-pap** and select the **Authorization Code** checkbox in the **Allowed Grant Types** section. In the **Default Access Token Manager** list, select the JWT Manager created earlier, and in the **Redirection URIs** field, add the correct callback URL for the Policy Editor, such as https://pap.example.com:9443/idp-callback.

Click Save.

24. Go to Authentication > OAuth > IdP Adapter Grant Mapping and create a new Form Adapter Mapping, fulfilling the contracts for USER_NAME and USER_KEY with the username form field. Click Next and Save on the Summary tab.

Ping	Federate		AUTHENTICATION	APPLICATIONS	SECURITY S	YSTEM		$\bigcirc @ ($
	< OAuth	IdP Adapter Grant	Mapping IdP Adapte	er Mapping				
۲	Policy Contract Grant Mapping	Attribute Sources & User Lo	ookup Contract Fulfillment	Issuance Criteria	Summary			
•1	IdP Adapter Grant	Select a Source and Value to	map into each item in the Contrac	t list.				
0	Mapping	Contract	Source		Value		Actions	
Â.	Resource Owner Credentials Grant Mapping	USER_KEY	Adapter V		username	~	None available	
	CIBA Authenticators	USER_NAME	Adapter 🗸		username	~	None available	
							Cancel Previous	Next

25. Because this PingFederate instance uses a different domain from the Policy Editor, you must modify the PingFederate CORS settings. Go to System > OAuth Settings > Authorization Server Settings. In the Cross-Origin Resource Sharing Settings section, enter the domain for the Policy Editor in the Allowed Origin field. Click Add and then Save.

Allowed Origin	Action	
https://pap.example.com:8080	Edit I Delete	
	Add	
Device Authorization Grant Settings		

Result

PingFederate is configured to handle OpenID Connect (OIDC) requests.

Next steps

Configuring PingAuthorize Policy Editor to use PingFederate

Configuring PingAuthorize Policy Editor to use PingFederate

Configure the PingAuthorize Policy Editor to use PingFederate for authentication.

Before you begin

Configure PingFederate to handle OpenID Connect requests as described in Configuring PingFederate for PingAuthorize.

About this task

Reconfigure a manually installed PingAuthorize Policy Editor to use PingFederate for authentication.

Steps

1. Add the certificate to the Java Trust Store.

If the certificate chain added to PingFederate uses an intermediate certificate authority that is not trusted by the default Java trust store, you must add the certificate. Use the following command (root permissions are usually required). **\$JAVA_HOME** must be defined as the installation location of the JVM on which the Policy Editor will run.

```
keytool -import \
-file /path/to/IntermediateCA.cer \
-keystore $JAVA_HOME/jre/lib/security/cacerts \
-storepass changeit
```

- 2. Reconfigure PingAuthorize to point unauthenticated users to PingFederate.
 - 1. Stop the application.

\$ bin/stop-server
The server was successfully stopped.

- 2. Re-run **bin/setup** to reconfigure the application.
- 3. Select OpenID Connect to configure the Policy Editor.

```
[/opt/{pingauthorize}-PAP]$ bin/setup
```

```
There is an existing configuration file at /config/configuration.yml. Overwrite? (yes / no) [no]: yes
```

Detected valid license file in server root {pingauthorize}.lic

{pingauthorize} Policy Editor

How would you like to configure the Policy Editor?

1) Quickstart (DEMO PURPOSES ONLY): This option configures the server with a form based authentication and

generates a self-signed server certificate

2) OpenID Connect: This option configures the server to use an OpenID Connect provider such as ${\tt PingFederate}$

3) Cancel the setup

Enter option [1]: 2

On which port should the Policy Editor listen for HTTPS communications? [9443]:

Enter the fully qualified host name or IP address that users' browsers will use to connect to this GUI [pap.example.com]: pap.example.com

4. Ensure that the PingFederate discovery endpoint uses the public DNS name of the PingFederate server. In this example, the Policy Editor uses a self-signed SSL certificate.

Enter the port of the OpenID Connect provider [9031]: Enter the fully qualified host name or IP address of the OpenID Connect provider [pap.example.com]: pf.example.com Certificate server options: 1) Generate self-signed certificate (recommended for testing purposes only) 2) Use an existing certificate located on a Java Keystore (JKS) 3) Use an existing certificate located on a PKCS12 keystore

Enter option [1]:

There already exists a keystore at /config/keystore.p12. Do you want to delete it? (yes / no) [no]: yes

5. Follow the remaining prompts.

```
Setup Summary
-----
            pap.example.com
Host Name:
Server Port:
              9443
Secure Access: Self-signed certificate
              9444
Admin Port:
Periodic Backups: Enabled
Backup Schedule: 0 0 0 * * ?
Command-line arguments that would set up this server non-interactively:
   setup oidc --pkcs12KeyStorePath config/keystore.p12 --licenseKeyFile
{pingauthorize}.lic \
        --oidcHostname pf.example.com --oidcPort 9031 --certNickname server-cert --
backupSchedule '0 0 0 * * ?' \
        --hostname pap.example.com --port 9443 --generateSelfSignedCertificate --
adminPort 9444
What would you like to do?
   1) Set up the server with the parameters above
   2) Provide the setup parameters again
   3) Cancel the setup
Enter option [1]:
Setup completed successfully
Please configure the following values
_____
{pingauthorize} Server - Policy External Server
 Base URL:
                                              https://pap.example.com:9443
 Shared Secret:
                                              2222142a754f4838ad1e3dccb6e93940
 Trust Manager Provider:
                                              Blind Trust
PingFederate - OAuth Client Config
                                              pingauthorizepolicyeditor
 Client ID:
 CORS Allowed Origin:
                                              https://pap.example.com:9443
 Redirect URL:
                                              https://pap.example.com:9443/idp-
callback
Please start the server by running bin/start-server
```

6. Restart the application by running **bin/start-server**.

3. Verify that you can log into the Policy Editor using OpenID Connect provided by PingFederate.

- 1. Go to the Policy Editor, for example, https://pap.example.com:9443. Your browser should be redirected into the OAuth flow.
- 2. Click Click to Sign In.

3. Sign on with your user name and password.

The sample configuration in this document creates an identity with the user name **user.20** and password password .

4. Once authenticated, PingFederate will prompt the user with the scopes associated with the OAuth client. Check all of them to continue.

Request for Ap	oproval
	Logged in as user.20
Policy Administration GUI is requesting permission for the following:	
ACCESS TO YOUR USERNAME	F
✓ OPENID CONNECT ENABLEMENT	
✓ OPENID CONNECT PROFILE EMAIL ACCESS	Client : Policy Administration GUI
✓ OPENID USER PROFILE ACCESS	
Allow	
Don't Allow	

Result:

You are now authenticated and authorized to view the Policy Editor.

Configuring PingFederate group access for PingAuthorize

Configure PingFederate so that only members of a specific LDAP group are authorized to access the application.

About this task

Configuring PingFederate for PingAuthorize and **Configuring PingAuthorize Policy Editor to use PingFederate** explain how to configure the PingAuthorize Policy Editor and PingFederate so that any authenticated user can access the PingAuthorize Policy Editor. This task describes how to configure PingFederate to limit access to a specific LDAP group.

Steps 1. Create an LDAP group in PingDirectory and add the desired user (user.20) to the group. 1. Create a file named create-policy-writer-group.ldif and add the following. dn: ou=groups,dc=example,dc=com objectclass: top objectclass: organizationalunit ou: groups dn: cn=PolicyWriter,ou=groups,dc=example,dc=com objectclass: top

objectclass: groupOfUniqueNames cn: PolicyWriter ou: groups uniquemember: uid=user.20,ou=People,dc=example,dc=com

2. Use the PingDirectory **ldapmodify** tool to load the newly created **ldif** file.

/opt/PingDirectory/bin/ldapmodify -a -f create-policy-writer-group.ldif

- 2. Add the group membership claim requirement in PingFederate.
 - 1. In PingFederate, go to Applications > OAuth > Access Token Mappings.
 - 2. Select the PingDirectory mapping from the list, and then on the **Attribute Sources & User Lookup** tab, select the PingDirectory source.
 - 3. Click the LDAP Directory Search tab, and in the Root Object Class list, select Show All Attributes.
 - 4. Add the isMemberOf attribute, and then click Done to return to Access Token Attribute Mapping.

Data Store LDAP Direc	tory Search LDAP Filter Summary	
Please configure your directory	r search. This information, along with the attributes supplied in the contract, will be used to fulfill the contract.	
BASE DN	ou=People,dc=example,dc=com	
SEARCH SCOPE	One Level 🗸	
Attributes to return from searc	ĥ	
ROOT OBJECT CLASS	ATTRIBUTE	Action
	Subject DN	
	cn	Remove
	mail	Remove
	uid	Remove
<show all="" attributes=""></show>	IsMemberOf V	Add Attribu
View Attribute Contract		

5. Go to the **Issuance Criteria** tab and add a new row with the following values:

Column	Value
Source	LDAP (pingdir)
Attribute Name	isMemberOf
Condition	multi-value contains (case sensitive)
Value	cn=PolicyWriter,ou=groups,dc=example,dc=com

gFederate can evaluate vario	ous criteria to determine whethe	er to issue an access token. Use this optional screen to c	onfigure the criteria for use with this toker	authorization.	
urce	Attribute Name	Condition	Value	Error Result	Action
AP (pingdir)	isMemberOf	multi-value contains (case insensitive)	cn=PolicyWriter,ou=groups,dc	=example,dc=com	Edit I Dele
SELECT - 🗸 🗸	- SELECT -	- SELECT -	~		Add

6. Click Save.

Result:

Only user.20 can access the PingAuthorize Policy Editor.

3. Verify that only specified users can access the PingAuthorize Policy Editor.

(i) Note Clear any active SSO sessions before you sign on as each user.
Clear any active 550 sessions before you sign on as each user.
1. Sign on as user.0.
Result:
Access is denied.
2. Sign on as user.20.
Result:
Access is granted.

Uninstalling PingAuthorize

For manual installations, PingAuthorize Server provides an uninstall tool to remove its components from the system.

Steps

- 1. Go to the PingAuthorize Server root directory.
- 2. Run the **uninstall** command.
 - \$./uninstall
- 3. Select the option to remove all components or select the components you want to remove.

Example:

To remove selected components, enter yes when prompted.

Remove Server Libraries and Administrative Tools? (yes / no) [yes]: yes
Remove Log Files? (yes / no) [yes]: no
Remove Configuration and Schema Files? (yes / no) [yes]: yes
Remove Backup Files Contained in bak Directory? (yes / no) [yes]: no
Remove LDIF Export Files Contained in ldif Directory? (yes / no) [yes]: no
The files will be permanently deleted, are you sure you want to continue? (yes / no) [yes]:

4. Manually delete any remaining files or directories.

Next steps

To remove PingAuthorize Policy Editor, run **stop-server** and remove its installation directory.

Upgrading PingAuthorize

PingIdentity.

PingAuthorize includes two server applications you must upgrade in tandem—the main PingAuthorize Server and the Policy Editor.

Ping Identity issues software release builds periodically with new features, enhancements, and fixes for improved server performance.

κ) Νote

PingAuthorize Server used in external PDP mode requires a Policy Editor with the same version. When upgrading PingAuthorize Server, you must also upgrade the Policy Editor.

Upgrade considerations

When upgrading, you must consider factors such as the scope of the update, the PingAuthorize or PingDataGovernance version from which you are upgrading, and if you are not using Docker, your installed version of Java.

γ Νote

The 8.3.0.0 release is the first release of PingAuthorize. Previously, the product was known as PingDataGovernance.

General considerations

For Docker deployments, the upgrade process involves downloading and deploying the latest containers.

For manual installations, the upgrade process involves downloading and extracting a new version of the PingAuthorize Server .zip file on the server and running the update utility with the --serverRoot or -R option value from the new root server pointing to the installation.

Consider the following when upgrading:

• If you are upgrading from a PingAuthorize Early Access release to a PingAuthorize General Availability release, you must upgrade both the PingAuthorize Server and the Policy Editor before you use the Policy Decision Service in external mode. Upgrading only one component results in this error:

Please upgrade to PingAuthorize Policy Editor version <X.X.X.X>.

- The update affects only the server being upgraded. The process does not alter the configuration of other servers, so you must update those servers separately.
- The update tool verifies that the installed version of Java meets the new server requirements. To simplify the process, install the version of Java that is supported by the new server before running the tool.
- Upgrades for PingDataGovernance Server are only supported from versions 7.0.0.0 or later. If upgrading from a version of PingDataGovernance prior to 7.3.0.0, configuration loss will occur. The update tool has a warning message about this.

🔿 Тір

For additional considerations, see Planning your upgrade \square .

(j) Note

For information about important fixes made over several releases, see Critical Fixes^[2].

Considerations introduced in PingAuthorize 9.3.0.0

PingAuthorize no longer supports policy deployment packages with Apache Camel policy information point (PIP) services. If you're running PingAuthorize in embedded policy decision point (PDP) mode using deployment packages containing Camel PIPs, you can't upgrade to PingAuthorize 9.3 without additional action. See Enabling Camel service connections for more information.

Considerations introduced in PingAuthorize 9.0.0.0

Keep in mind the following important upgrade considerations introduced in this version of PingAuthorize Server.

General

Peer server setup has been removed. To manage server configuration, use server profiles instead of peer setup. Server profiles support deployment best practices such as automation and Infrastructure-as-Code (IaC). For more information about server profiles, see Deployment automation and server profiles.

Spring compatibility

Spring configuration properties in PingAuthorize administrative console configuration files prior to version 9.0.0.0 are not compatible with the administrative console bundled with PingAuthorize 9.0.0.0 and later. This incompatibility is caused by major updates to Spring dependencies. Attempting to use these older configuration files will result in the administrative console failing to start.

If you are using older PingAuthorize administrative console configuration files, these should be updated. Replace the following excerpt in the old application.yml file:

```
spring:
    profiles.active: default
    main.show-banner: false
    thymeleaf.cache: true
    thymeleaf.prefix: classpath:/public/app/
```

with the following:

```
spring:
  profiles.active: default
  web.resources:
    # 1 year. Update the corresponding value in MvcConfig if this changes.
    cache.period: 31536000
    add-mappings: false # use our custom mappings instead of the defaults
  main:
    banner-mode: "OFF"
  thymeleaf:
    prefix: classpath:/public/app/
```

Upgrade considerations introduced in PingAuthorize 8.x

Considerations introduced in PingAuthorize 8.3.0.0

Keep in mind the following important considerations introduced in this version of PingAuthorize Server.

General

- If you are upgrading to PingAuthorize 8.3.0.0, you must also upgrade to PingAuthorize Policy Editor 8.3.0.0.
- The policy decision service configuration has changed. When using embedded policy decision point (PDP) mode, you must specify a deployment-package-source-type for the policy decision service in your configuration. You might need to update the dsconfig files in your server profile when upgrading to version 8.3 to set a deployment-package-source-type. If you want to maintain the existing behavior from previous releases, use "static-file" as your deployment-package-source-type.

Deployments with multi-server topologies

• Upgrading from PingDataGovernance 6.x or 7.x

Upgrading multi-server topologies that contain PingDataGovernance 6.x or 7.x is not supported.

• Upgrading from PingDataGovernance 8.0.0.0 or later

You can upgrade multi-server topology deployments that contain PingDataGovernance 8.0.0.0 or later to PingAuthorize. When updating a PingDataGovernance multi-server topology to PingAuthorize, you must remove all servers from the topology, update each server individually, then add all the servers back to the topology, as explained below.

i) Note

The known issues and workarounds in this section apply only to deployments with multi-server PingDataGovernance topologies. Deployments with single-server topologies can upgrade without these issues.

For each server to be upgraded:

1. Remove the server from the topology by running a command like this one:

manage-topology remove-server <connection args>

2. Update the server.

After you have successfully upgraded every server, you can then join each server to the topology by running a command like this one:

manage-topology add-server <connection args> <remote server connection args>

If you do not follow these steps, adding a PingAuthorize server to a PingDataGovernance topology could result in the following error message:

Entry cn=License,cn=Topology,cn=config cannot be modified because one of the configuration change listeners registered for that entry rejected the change: The provided license key was generated for PingAuthorize but this is PingDataGovernance with Symphonic

Another consequence of not following these steps is that restarting any server in the topology that is not updated fails. To use the server again, you must remove the server from the topology and reset its license to a PingDataGovernance license.

Upgrading from a version earlier than 7.3.0.0

If you are upgrading from a PingDataGovernance version earlier than 7.3.0.0, PingAuthorize creates the **deleted-oauth2**scopes.txt file to capture data that can simplify the upgrade. For information about what to do with this file, contact your Ping Identity account representative.

Considerations introduced in PingDataGovernance 8.2.0.0

Keep in mind the following important considerations introduced in this version of PingDataGovernance Server.

General

- If you are upgrading to PingDataGovernance 8.2.0.0, you must also upgrade to Policy Administration GUI 8.2.0.0.
- Changes to SpEL expressions using collection projection might cause policy errors with the following form:

EL1004E: Method call: Method <Symphonic Value method>() cannot be found on type <native Java type>

If your policies rely on SpEL collection projection and methods like intValue(), stringValue(), jsonRepresentation(), or pojoRepresentation(), you must update these expressions. It is recommended that you update the policies to use collection transforms instead of SpEL collection projection. For information about collection transforms, see the *PingDataGovernance Policy Administration Guide*.

• This upgrade moves to Jetty 9.4. As a result, the HTTPS connection handler will no longer support TLS_RSA ciphers by default. If you use any legacy HTTPS clients that still require TLS_RSA ciphers, modify the **ssl-cipher-suite** property of the HTTPS Connection Handler to include them.

Gateway API Endpoint and Sideband API Endpoint configurations

 PingDataGovernance now strictly validates path parameters used in gateway application programming interface (API) endpoint and sideband API endpoint configurations. The inbound-base-path value (for gateway API endpoints) and the base-path value (for sideband API endpoints) no longer allow duplicate path parameters. For example, /Users/{userId}/Manager/{userId} defines the userId path parameter twice and is invalid. In addition, other configuration properties cannot refer to a path parameter that is not defined by inbound-basepath or base-path.

Previously, the server would allow such invalid configuration changes to be saved, but now the server rejects them. Upgrades or server profile deployments including invalid configuration of this kind will now fail. If this happens, correct the invalid configuration values.

Considerations introduced in PingDataGovernance 8.1.0.0

General

• PingDataGovernance 8.1.0.0 uses a new policy request format that requires changes to the Trust Framework.

If you are using policies intended for a previous release, you can continue to use your existing policies by setting the trust-framework-version property of the Policy Decision Service to v1. If you upgrade your server using the update tool, this property is set for you automatically.

The v1 format is deprecated, however, and you are strongly encouraged to update your Trust Framework as soon as possible. To do this, load your existing policies in the Policy Administration GUI and apply the Trust Framework changes by going to **Branch Manager** \rightarrow **Merge Snapshot** and selecting the **resource/policies/upgrade**snapshots/8.0.0.0-to-8.1.0.0.SNAPSHOT file included with the server. Then, configure PingDataGovernance Server to issue policy requests using the new Trust Framework by setting the **trust-framework-version** property of the Policy Decision Service to v2.

- If you are upgrading to PingDataGovernance 8.1.0.0, an updated version of the Policy Administration GUI is required.
- The PingDataGovernance Policy Administration GUI no longer uses the UNIX environment variable **PING_HOSTNAME**. Instead, server administrators should use **PING_EXTERNAL_BASE_URL** to specify both the domain and the port. For more information, see the *PingDataGovernance Server Administration Guide*.

Policy processing and advice

- The Allow Attributes advice and the Prohibit Attributes advice have been removed and can no longer be used. Requests involving policies that refer to these advice types will fail.
- The HttpRequest.Headers policy request attributes is not available starting with Trust Framework version v2. It has been replaced by the HttpRequest.RequestHeaders and HttpRequest.ResponseHeaders policy request attributes. Update existing policies or Trust Framework entities that refer to HttpRequest.Headers to refer to HttpRequest.RequestHeaders.
- SCIM 2 requests now include the resource type in the service value during policy processing. For example, for a glossary:gSCIM[2 request that affects the "Users" resource type, the service value will now be "SCIM2.Users" instead of "SCIM2". Existing policy rules or targets that rely on an exact equality match for "SCIM2" must be updated. For example, a condition of "Service Equals SCIM2" would need to be updated to "Service Matches SCIM2".
- For security, by default, the policy engine's SpEL processor now invokes Java classes only in the allow-list presented in the *PingDataGovernance Server Administration Guide*. To use other classes, add a key to the core section of the Policy Administration GUI's configuration called AttributeProcessing.SpEL.AllowedClasses with a list of the classes to include. If you are using embedded PDP mode, add a policy configuration key of the same name to the PingDataGovernance Server configuration.

PDP API

• The XACML-JSON PDP API now requires a different request format. With this new format, you can make multiple decisions using a single HTTP request. In addition, the response format is now compliant with the XACML-JSON specification. The 8.0 PDP API request format is no longer supported. For more information, see the *PingDataGovernance Server Administration Guide*.

Peer setup and clustered configuration

- Peer setup and clustered configuration are deprecated and will be removed in PingAuthorize 9.0. We encourage deployers to manage server configuration using server profiles, which support deployment best practices such as automation and Infrastructure-as-Code (IaC). For more information about server profiles, see the *PingAuthorize Server Administration Guide*.
- If you have upgraded a server that is in a cluster (that is, has a cluster name set in the Server Instance configuration object) to version 8.1, you will not be able to make cluster configuration changes until all servers with the same cluster name have been upgraded to version 8.1. If needed, you could create temporary clusters based on server versions and modify each server's cluster name appropriately to minimize the impact while you are upgrading.

Docker upgrades

Upgrading PingAuthorize Server using Docker

When using Docker, instead of upgrading PingAuthorize Server, you deploy a container with the new PingAuthorize version and use the same server profile.

About this task

If you deployed a container using a server profile, when you want to deploy a newer PingAuthorize Server version, you deploy a container with that version using the same server profile.

Steps

• For more information, see https://devops.pingidentity.com/reference/config/^[].

(The server profiles for Docker deployments differ from those discussed in Deployment automation and server profiles.)

Upgrading the PingAuthorize Policy Editor using Docker

If you originally installed the Policy Editor with Docker per Deploying PingAuthorize Policy Editor using Docker, use this procedure to upgrade the PingAuthorize Policy Editor when a new version is released.

Steps

- 1. In your current Policy Editor, complete the steps in Backing up policies.
- 2. Stop the old Docker container and start the new one.

When a new Docker image for the PingAuthorize Policy Editor is available, you stop the existing Docker container and start the new container from the new image while mounting the same volumes.

A Warning

If you use a shared volume, you should always stop the Docker container running the older version of the Policy Editor before you start the new container.

The following commands stop the running container and run a new image named *<pap_new*>. This image uses the volumes from *<pap_old>* to house the policy database. Also, the command uses the same **PING_H2_FILE** location from pingauthorize_server_administration_guide:paz_start_pe.adoc#section_mv2_1kv_5lb.

(i) Note

- The Ping Identity DevOps Docker images use the PingAuthorize **setup** tool to update the H2 policy database on the mounted volume. If you store your policies in a PostgreSQL database, follow the instructions in Deploying PingAuthorize Policy Editor using Docker to update your policy database.
- For proper communication between containers, create a Docker network using a command such as docker network create --driver <network_type> <network_name>, and then connect to that network with the --network=<network_name> option.

```
$ docker container stop <pap_old>
$ docker run --network=<network_name> --name <pap_new> \
    -p 443:1443 -d --env-file ~/.pingidentity/config \
    --volumes-from <pap_old> \
    --env PING_H2_FILE=/opt/out/Symphonic \
    pingidentity/{PAP_CONTAINER_NAME}:<TAG>
```

The Docker image *<TAG>* used in the example is only a placeholder. For actual tag values, see Docker Hub (https://hub.docker.com/r/pingidentity/pingauthorizepap^[2]).

Warning

The **setup** tool uses the default credentials to upgrade the policy database. If the credentials no longer match the default values, the server administrator should pass the correct credentials to the **setup** tool using the PI NG_DB_ADMIN_USERNAME, PING_DB_ADMIN_PASSWORD, PING_DB_APP_USERNAME, and PING_DB_APP_PASSWORD UNIX environment variables.

For example, if the old policy database admin credentials have been previously set to admin/Passw0rd, and the application credentials have been set to app/S3cret, the docker **run** command should include those environment variables as shown in this example.

```
$ docker container stop <pap_old>
$ docker run --network=<network_name> --name <pap_new> \
-p 443:1443 -d --env-file ~/.pingidentity/config \
--env PING_H2_FILE=/opt/out/Symphonic \
--env PING_DB_ADMIN_USERNAME=admin \
--env PING_DB_ADMIN_PASSWORD=Passw0rd \
--env PING_DB_APP_USERNAME=app \
--env PING_DB_APP_PASSWORD=S3cret \
pingidentity/{PAP_CONTAINER_NAME}:<TAG>
```

The Docker image <TAG> used in the example is only a placeholder. For actual tag values, see Docker Hub (https://hub.docker.com/r/pingidentity/pingauthorizepap^[2]).

This command ensures that the **setup** tool has the correct credentials to access the policy database, and that it does not reset credentials to their defaults.

3. In the new Policy Editor, complete the steps in Upgrading the Trust Framework and policies.

Manual upgrades

Upgrading PingAuthorize Server manually

Perform the following steps to upgrade a PingAuthorize server.

Steps

1. Download and unzip the new version of PingAuthorize Server in a location outside the existing server's installation.

For these steps, assume the existing server installation is in /opt/pingauthorize/PingAuthorize and the new server version is extracted into /home/stage/PingAuthorize.

- 2. Provide a copy of the PingAuthorize license file for the version to which you are upgrading in the /home/stage/ PingAuthorize directory, or give the location of the license file to the tool using the --licenseKeyFile option.
- 3. Run the update tool provided with the new server package to update the existing PingAuthorize Server.

The update tool might prompt for confirmation on server configuration changes if it detects customization.

Example:

/home/stage/{pingauthorize}/update --serverRoot /opt/pingauthorize/{pingauthorize}

Reverting an update

After you've updated PingAuthorize Server, you can revert to the previous version (one level back) using the revert-update tool.

About this task

The **revert-update** tool accesses a log of file actions taken by the updater to put the file system back to its previous state. If you have run multiple updates, you can run the **revert-update** tool multiple times to sequentially revert to each prior update. You can only revert back one level at a time with the **revert-update** tool. For example, if you had to run the update twice since first installing PingAuthorize Server, you can run the **revert-update** tool to revert to its previous state, then run the **revert-update** tool again to return to its original state.

When starting the server for the first time after running a revert, the server displays warnings about "offline configuration changes," but these are not critical and will not appear during subsequent start-ups.

Steps

• Run revert-update in the server root directory to revert back to the most recent previous version of the server, as shown in the following example:

/opt/pingauthorize/{pingauthorize}/revert-update

Upgrading the PingAuthorize Policy Editor manually

If you originally installed the PingAuthorize Policy Editor using .zip files, use this procedure to upgrade the Policy Editor when a new version is released.

Steps

- 1. In your current Policy Editor, complete the steps in Backing up policies.
- 2. Stop the Policy Editor.

\$ bin/stop-server

- 3. Obtain the new version of the PingAuthorize Policy Editor and extract it to a location outside the existing Policy Editor's installation.
- 4. Prepare the existing policy database.



The new server installation might require changes to the policy database structure.

Choose from:

• If you store your policies in the H2 policy database, copy the existing database. The server **setup** tool performs these upgrades and generates a new **configuration.xml** file.

This example assumes the old installation is in /opt/pingauthorize/PingAuthorize-PAP-previous, and the new installation is in /opt/pingauthorize/PingAuthorize-PAP. Run the following commands to upgrade from each version:

Step 8.1 and later

\$ cp /opt/pingauthorize/{pingauthorize}-PAP-previous/Symphonic.mv.db opt/pingauthorize/ {pingauthorize}-PAP

Step 8.0 earlier

\$ cp /opt/pingauthorize/{pingauthorize}-PAP-previous/admin-point-application/db/Symphonic.mv.db
opt/pingauthorize/{pingauthorize}-PAP

• If you store your policies in a PostgreSQL database, follow the instructions for Upgrading a PostgreSQL policy database.

5. Run the **setup** tool.



Updating PingAuthorize Server uses an **update** tool. However, PingAuthorize Policy Editor does not have this tool. Instead of updating the Policy Editor in-place, you must install the new Policy Editor.

🔨 Warning

The **setup** tool uses the default credentials to upgrade the database. If the credentials no longer match the default values, provide the correct credentials to the **setup** tool using the appropriate command-line options:

- If you are using the default H2 policy database implementation, provide the non-default values using the --dbAdminUsername, --dbAdminPassword, --dbAppUsername, and --dbAppPassword commandline options. Otherwise, setup fails when it cannot access the H2 policy database, or it might reset credentials to their default values. For more information, see Manage policy database credentials.
- If you are using a PostgreSQL policy database implementation, provide the server runtime user value through the --dbAppUsername command-line option. For the server runtime password, provide this value to the PING_DB_APP_PASSWORD environment variable before server start.

Follow the instructions in either of the following topics:

- Installing the PingAuthorize Policy Editor interactively
- Installing the PingAuthorize Policy Editor non-interactively
- 6. Start the new Policy Editor.

Follow the instructions in Post-setup steps (manual installation).

7. In the new Policy Editor, complete the steps in Upgrading the Trust Framework and policies.

Policy-related upgrades

As part of the PingAuthorize upgrade process, you must upgrade specific Policy Editor components and dependencies, including policies, policy databases, and the Trust Framework.

See the following topics for instructions on upgrading Policy Editor components and dependencies:

- Backing up policies
- Upgrading the Trust Framework and policies
- Upgrading a PostgreSQL policy database

Backing up policies

Back up existing policies before upgrading the Policy Editor. Do this by exporting policy snapshots.

About this task

Back up policies manually as described below or rely on the automatic backups covered in Policy database backups.

Steps

- 1. Sign on to the Policy Editor and choose any existing branch to go to the main landing page.
- 2. To display your current branches, select **Branch Manager** → **Version Control**.
- 3. From the **Branches** list, click a branch that you want to export.

Result:

You should see a list of the commits for that branch, and the most recent version of the branch is named **Uncommitted Changes**.

- 4. Identify the commit that represents the snapshot that you want to export and click the hamburger menu in the **Options** column.
- 5. Choose Export Snapshot.

Result:

Your browser downloads the file.

6. Repeat for any additional branches that you want to back up.

Upgrading the Trust Framework and policies

PingAuthorize ships with a default Trust Framework and policy snapshot that policy writers should use as a starting point when developing their policies. Occasionally, a server upgrade results in changes to the default Trust Framework and policies, and policy writers must upgrade any policies based on defaultPolicies.SNAPSHOT.

Steps

- 1. Sign on to the Policy Editor and choose any branch to go to the main landing page.
- 2. Select Branch Manager from the navigation bar on the left, and open the Merge Snapshot tab.
- Click the file selection option, and go to the resource/policies/upgrade-snapshots folder of the new Policy Editor deployment.
- 4. Select the correct **SNAPSHOT** file based on the version you are upgrading from and the version to which you are upgrading.

🔿 Important

If you are upgrading from 7.3.0.*x*, use the 7.3.0.x-to-8.0.0.0-SNAPSHOT and merge that (per the next step) before you select and merge 8.0.0.0-to-8.1.0.0.SNAPSHOT.

Example:

When upgrading from version 8.0.0.0 to version 8.1.0.0, use resource/policies/upgrade-snapshots/8.0.0.0-to-8.1.0.0.SNAPSHOT.

5. Merge the partial snapshot.

(i) Note

Merge conflicts might occur where objects have been updated. If you have not modified the objects in conflict, you can safely select **Keep Snapshots**.

- 6. Return to your PingAuthorize Server installation.
- 7. Run the following dsconfig command to configure PingAuthorize Server to use the latest Trust Framework version:

```
dsconfig set-policy-decision-service-prop \
    --set trust-framework-version:{TRUST_FRAMEWORK_VERSION}
```

Upgrading a PostgreSQL policy database

To upgrade an existing PostgreSQL policy database, use the **policy-db** tool.

Before you begin

- The PostgreSQL instance must be reachable on the network from the Policy Editor host and listening for connections.
- The Policy Editor uses both a PostgreSQL administration user and a server runtime user. Have a database administrator create both users before providing their credentials to the **policy-db** tool. The administration user must be able to create new databases. When new releases of the Policy Editor become available, continue using the same administration user to prevent database object ownership issues.

Learn more about creating new database users and configuring PostgreSQL to listen for remote connections securely in the PostgreSQL documentation \square .

The Policy Editor uses Java Database Connectivity (JDBC) to connect to PostgreSQL. Be prepared to provide the JDBC connection string in the following format: jdbc:postgresql://<host>:<port>/<name>. For example: jdbc:postgresql://example.com:5432/pap_db

About this task

When a newer version of the Policy Editor is released, it will fail to start when pointing to a PostgreSQL database with older database objects. Running **start-server** will print a message like the following to the console:

```
The policy database at 'jdbc:postgresql://example.com:5432/pap_db' is older than this version of PingAuthorize Policy Editor (9.2.0.0). Please use the policy-db tool to upgrade the database before running start-server again.
```

This message indicates that you must run the **policy-db** tool for this newer version of the Policy Editor to upgrade the database objects.

Follow these instructions to upgrade a PostgreSQL database for a manual upgrade of the Policy Editor. Be prepared to provide the database administration credentials and server runtime credentials you used to create the PostgreSQL database.

γ Νote

See Deploying PingAuthorize Policy Editor using Docker for containerized deployments.

Steps

- 1. Complete steps 1-3 of Upgrading the PingAuthorize Policy Editor manually.
- 2. Run the following command:

\$ bin/policy-db \ --dbConnectionString "jdbc:postgresql://<host>:<port>/<name>" \ --dbAppUsername <server-runtime-username> \ --dbAppPassword <server-runtime-password>

(i) Note

Alternatively, you can provide the server runtime password through the **PING_DB_APP_PASSWORD** environment variable.

3. Provide the database administration credentials when prompted.

Result

The **policy-db** tool connects to PostgreSQL and applies the upgrades.


Next steps

Complete steps 5-7 of Upgrading the PingAuthorize Policy Editor manually.

Important


Provide the Policy Editor with the same --dbConnectionString, --dbAppUsername, and server runtime password you used to create the PostgreSQL database.

PingAuthorize Integrations



API gateway integrations enable you to use PingAuthorize for attribute-based access control and policy decisions with your API gateway.

The following diagram outlines how API requests flow through your API gateway and PingAuthorize.



- 1. The client sends a request to the API gateway.
- 2. The API gateway-specific integration kit processes the client's request and sends it to the PingAuthorize Server for policy processing.
- 3. The PingAuthorize Server determines whether to permit or deny the API request based on policies defined in the PingAuthorize Policy Editor.
- 4. The API gateway analyzes the response from the PingAuthorize Server to determine whether the request should be forwarded to the upstream API and, if so, whether any modifications should be made to the request.
- 5. The API gateway passes the original or modified request to the API target.
- 6. The API resource server sends a response to the gateway with the requested resources.
- 7. The API gateway integration kit processes the resource server's response and forwards it to the PingAuthorize Server for policy processing.
- 8. The PingAuthorize Server determines whether to forward the API response to the client based on policies defined in the PingAuthorize Policy Editor.
- 9. The PingAuthorize Server sends a final response to the API gateway.

10. The API gateway processes the response and forwards the requested API resource to the client.

PingAuthorize provides the following API gateway integrations:

- Kong API gateway integration
- MuleSoft API gateway integration
- Apigee API gateway integration

Apigee API gateway integration

Ping Identity's shared flow for Apigee extends Apigee's authorization capabilities through an external policy evaluation service.

Integration with Apigee allows centralized management of API access control and application protection in PingAuthorize while delegating enforcement to Apigee. Learn more about how this integration kit interacts with PingAuthorize in API gateway integration.

Install and configure the integration kit in Apigee to enable management of access control rules in PingAuthorize.

To configure the integration kit:

- 1. Set up PingAuthorize for Apigee integration.
- 2. Configure Apigee for PingAuthorize integration.

Setting up PingAuthorize for Apigee integration

To allow Apigee to use PingAuthorize as an external runtime authorization service, set up PingAuthorize to receive authorization requests from Apigee.

Before you begin

Install PingAuthorize.

Steps

- 1. On the **Configuration** page of the PingAuthorize administrative console, in the **Web Services and Applications** section, go to **HTTP Servlet Extensions > Sideband API**.
- 2. In the Request Context Method list, select state.

Sc Austin PingAuthorize Server 1	/ Configuration / HTTP Servlet Extens	ons /	Configuration Guide
Edit Sideband API H	ITTP Servlet Extensior	ı	
The Sideband API HTTP Servlet Exte	ension is used by a third-party API Gatew	ay to authorize JSON-based HTTP reque	est and response data.
			View API commands Save Cancel
Name *	Sideband API		
Description			ø
Cross Origin Policy	No cross-origin policy is defined and n	o CORS hear 💉 🕇 📀	
Response Header	Enter a value to add		+ 0
			×
Correlation ID Response Header	The correlation-id-response-header pro	perty of the HTTP Connect	
Request Limit	No size limit will be enforced on reques	ts.	
Request Context Method	state	0 C - x	
Shared Secret Header Name *	CLIENT-TOKEN	0 C	
Shared Secrets	Available	Selected	0
	Search Q	Search	Q
		 The Sideband API HTTP Service Extension will treat all request authenticated regardless of the shared secret header value. 	s as

- 3. In the Shared Secret Header Name field, enter CLIENT-TOKEN.
- 4. To create a new shared secret, in the **Shared Secrets** section, click the + icon to the right of the **Selected** table.
- 5. In the New Sideband API Shared Secret modal, enter a shared secret name and value, and then click Save To PingAuthorize Server Cluster.
- 6. Click Save.

Configuring Apigee for PingAuthorize integration

Install the PingAuth shared flow bundle in Apigee and configure it to integrate with PingAuthorize.

Before you begin

Ensure you have:

- A supported Apigee environment. The Ping Identity shared flow for Apigee supports Apigee Edge, Apigee Private Cloud, and Apigee X.
- The PingAuth shared flow bundle .zip archive. Download the integration kit for Apigee from the Ping Identity Integration Directory

Adding the PingAuthorize shared flow to Apigee

Steps

- 1. Upload the shared flow bundle:
 - 1. In Apigee, go to **Develop > Shared Flows** and do one of the following:
 - In Apigee X, click Upload Bundle.
 - In Apigee Edge or Apigee Private Cloud, click +Shared Flow, and then click Upload Bundle.
 - 2. For the shared flow name, enter PingAuth.
 - 3. In File Picker, select the PingAuth shared flow bundle .zip archive.
 - 4. Click Create.
- 2. In Apigee X, configure the connection to PingAuthorize.

γ Νote

Skip this step if you're using Apigee Edge or Apigee Private Cloud. Apigee X doesn't support managing the configuration values stored in key-value maps through the Apigee UI. You must add these configuration values to the key-value map policy. The key-value map is created and the configuration values are added the first time the PingAuth shared flow executes at runtime.

- 1. To access the PingAuth shared flow, go to Develop > Shared Flows > PingAuth.
- 2. Click the **Develop** tab and examine **Revisions** to make sure you're on the latest revision.
- 3. In the Policies panel on the left, click the Load KVM Config policy.
- 4. In the Code panel, remove the comment lines above and below the InitialEntries element.
- 5. Edit the value for service_host_port to match the host name of your PingAuthorize server instance and the port of the HTTPS connection handler.


For example, pingauthorize:8443.

🔿 Тір

You can find the HTTPS connection handler port from the **Configuration** page of the PingAuthorize administrative console by going to **System > Connection Handlers**.

- 6. Edit the value of shared_secret to match the shared secret that you created in PingAuthorize.
- 7. Click Save.

Your flow configuration should look like this:



3. In Apigee Edge or Apigee Private Cloud, configure the connection to PingAuthorize.

Apigee Edge stores environment-specific configuration values in key-value maps so that the same policies can be used across multiple deployment environments without any changes to the policies.

- 1. Go to Environment > Key Value Maps and click +Key Value Map.
- 2. Edit the key-value map and click Add Entry.
- 3. Add a **service_host_port** key and set the value to the host name of your PingAuthorize Server instance and the port of the HTTPS connection handler.

For example, pingauthorize:8443.

- 4. Add a shared_secret key and set the value to the shared secret that you created in PingAuthorize.
- 5. Click Save.

Your key-value map configuration should look like this:

apigee	Dashboard	APIs	Publish	Analytics Admin	Help				
Dashboard /	Environments /	prod						Organiz	ation pingidentity -
Enviror	nment Co	onfig	guratio	n prod -					
Caches	Flow Hooks	Key	Value Maps	References	Target Servers	TLS Keystores	Virtual Hosts		
									+ Key Value Map
Name								Action	
 PingAuth 	ı							Delete	
Key		<u>,</u> v	alue					,	Action
service	host_port	p	oingauthoriz	e:8443					× Delete
shared	secret								× Delete
									/ Edit

4. (Optional) Configure HTTPS trust for PingAuthorize.

By default, the PingAuth shared flow only trusts the PingAuthorize HTTPS connection handler certificate if the certificate is issued from a well-known certificate authority. To enable Apigee to trust specific HTTPS certificates from PingAuthorize Server:

- 1. Go to Environment > TLS Keystores and click +Keystore.
- 2. Give the key store a name that helps you identify your PingAuthorize environment.

For example, PingAuthorize-dev-truststore.

- 3. Click the + button to add a certificate.
- 4. Enter a certificate alias and upload the certificate configured for the HTTPS connection handler in PingAuthorize.

8	Apigee babbitt-ping-testing Eval -			P 🤉 🍥
<>	Environments \geq TLS keystores			+ Keystore
Դ Ու	eval 🗸 All 🗸	All Expired		1 - 1 of 1 < >
(3)	NAME 4	COMMON NAME	EXPIRATION	
	Keystore PingAuthTrust			
	O ₩ server	localhost	✓ in 7 months	

- 5. Click Save.
- 6. Go to **Environment > References** and click **+Reference**.
- 7. Name the new reference PingAuthTrust.
- 8. Select the key store that you created previously and click Save.

88	Apigee babbitt-ping-testing Eval -		P 🤊 🍥
<>	$Environments \mathrel{\scriptstyle{\scriptstyle{>}}} \mathbf{References}$		+ Reference
Դ Ու	eval 🗸 All 🗸		1-1 of 1 < >
(3)	NAME *	REFERENCE	
	PingAuthTrust	PingAuthTrust	

- 9. Go to **Develop > Shared Flows > PingAuth**.
- 10. On the **Develop** tab, examine **Revisions** to make sure you're on the latest revision.
- 11. In the **Policies** panel on the left, click the **Sideband Call** policy.
- 12. In the **Code** panel, remove the comment characters surrounding the **TrustStore** element.

8	Apigee babbitt-ping-testing	Eva	l 👻		۵.	?	
$\langle \rangle$	Shared Flows > PingA	\u1	th $>$ Overview	> 54			:
Т III	Revision 54 Vpdated Apr 14th, 2022				OVERVIEV Deploy to: eval		DEVELOP Save
1	Navigator		Policy: Sideband Call		Help for Selected Service Callout	t Poli	cy î∧ ⊐
	Search	<<	Туре	ServiceCallout			cy cy
		-	Diaglas, Nama	Sideband Call			spe
	Policies Error Response Init Handle Sideband Response Load KVM Config Raise Error Response Remove Unsupported Headers	+	Display Name	Sideband-Call HTTP O Proxy Chaining O Path Chaining			ctor
	Sideband Call						
	Sideband Call Init Sideband Call Prepare		HTTP Target	https://{PingAuth.serviceHostPort}			
	 Shared Flows 		Attached to	default Shared Flow			
	default		Code Sideband Call				×
	Verault	+	1 xml version-</td 2 < <5erviceCallo	<pre>!learPayload="true" variable="pingAuth.calloutRequest"> verything is set in init policy or in javascript> 'PingAuth.calloutResponse> ttConnections rrties:/ Rishttps://PingAuth.serviceHostPort}{PingAuth.serviceBasePath}-/URL>> ttps://PingAuth.serviceHostPort}-/URL> foo inabled>true-/Enabled> rrustSpone>ref://PingAuthTrust-/[rustStore]> infoo economic additionErrors>> infoo economic additionErrors>> infoo economic additionErrors>> infoo</pre>			

13. Click Save.

5. Go to **Develop > Shared Flows > PingAuth** and deploy the most recent revision to your environment.

Adding an API proxy in Apigee

Configure the API proxy in Apigee to point to the target endpoint that you want to reach.

Steps


1. Go to API Proxies > Create Proxy and click the Reverse proxy tile.

	safely expose backend services to API cons nplate to create your API proxy.	umers.	
¥.	Reverse proxy (most common) Route inbound traffic to a backend service. or Use OpenAPI Spec	<u> </u>	No target Create a simple API proxy that does not route to any backend target. or Use OpenAPI Spec
×,	Upload proxy bundle Import an existing proxy from a zip archive.	¥	Integration target Route inbound traffic to an integration target.


2. On the Proxy details page, enter the Name, Base path, and Target (Existing API).

API Proxies > Crea	ate Proxy
	1 Proxy details 2 Policies 3
	Proxy details
	Name <u>httpbin</u>
	Alphanumeric characters, dash (-) or underscore (_) Base path
	/httpbin This proxy will handle requests on hostname/base-path Learn more
	Description
	(Optional)
	Target (Existing API)
	https://httpbin.org/get
	The URL of the backend service that this proxy invokes

3. On the Common policies page, click Pass through (no authorization).



4. Select the checkbox for your deployment environment.



5. Click Create and Deploy.

Attaching the PingAuthorize shared flow to API proxies

Attach the PingAuth shared flow to the API proxies where you want to use PingAuthorize as the external authorization policy runtime service.

Steps

- 1. Add a Flow Callout policy:
 - 1. Go to one of your APIs in **Develop > API Proxies** and click the **Develop** tab.

S Important

Ensure you are on the latest revision of the proxy.

- 2. In the **Policies** panel on the left, click the **+** icon.
- 3. In the Add Policy modal, in the Extension panel on the left, click Flow Callout.
- 4. Enter a Name for the policy.

8	Apigee babbitt-ping-testing	Eval 👻					P	0 🌍
<>	API Proxies > httpbi	in → Develop → 2						:
î T		Add Policy			×	DEVELO		PERFORMANCE
~	Revision 2 Updated 12 hours ago					Dep	loy to: eval	 Save
()	Navigator	EXTENSION	Policy Type	Flow Callout		operty Inspect	or PreFlow	>>
	Search	Java Callout		_		low		
	httpbin	new Python	Display Name	PingAuth		e guest	PreFlow	
	 Policies 	JavaScript	Name	PingAuth		sponse		
	 Proxy Endpoints 	Service Callout						
	▼ default	Flow Callout	Shared Flow	PingAuth	*			
	All PreFlow	Message Logging						
	All PostFlow	Pata Capture	Flow Callouts I	et you execute shared flows. Learn	more			
		External Callout						
	✓ default	Trace Capture						
	All PreFlow	Publish Message						
	All PostFlow	DIALOGFLOW						
	• Hesources	SParse Dialogflow Request						
		Set Dialogflow Response						
					Cancel Add			
		10 <response></response>						
		11 12 - <http: ection="" www.angle.com=""></http:>						

- 5. In the Shared Flow list, select PingAuth, and then click Add.
- 2. Attach the Flow Callout policy to flows.

О Тір

Because PingAuthorize provides fine-grained authorization, you should integrate PingAuthorize late in the PreFlow of the request to the proxy endpoint, after coarse-grained authentication and authorization functions. Learn more about other ways to integrate PingAuthorize in Controlling API proxies with flows \square in the Apigee documentation.

- 1. In the **Proxy Endpoints** panel on the left, click **PreFlow**.
- 2. In the **Request** section, click +Step to add a flow step to the request.

		Develop > 2		RVIEW DEVELOP DEBUG PERF
Revision 2 Updated 12 hor	urs ago		Currently on eval: Revis	
lavigator	F	Flow: PreFlow	Help for Selected Flow	Property Inspector PreFlow
Search				PreFlow
			+	name PreFlow
httpbin			Step	Request
 Policies 	+			Response
🖉 🔼 PingAuth				
Proxy Endpoints	+	REQUEST		
✓ default	+	RESPONSE		
All PreFlow		RESPONSE		
All PostFlow	Í	+		
Target Endpoints	+	Step		
 ✓ default 	() ()			
All PreFlow	-			
All PostFlow	_			
Resources	+	Code default	×	
100001000		<pre>1 <?xml version="1.0" encoding="UTF-8" standalone="yes"?> 2 - <proxyendpoint name="default"></proxyendpoint></pre>		
		3 - <preflow name="PreFlow"></preflow>		
		4 <request></request>		
		5 <response></response> 6		
		7 <flows></flows>		
		<pre>8 - <postflow name="PostFlow"></postflow></pre>		
		9 <request></request> 10 <response></response>		
		11		
		12 - <http: <="" sections="" td="" www.sections.com=""><td></td><td></td></http:>		
		13 <basepath>/httpbin</basepath>		

3. In the Add Step modal, click the Existing tab, and then select the Flow Callout policy you created previously.

88	Apigee babbitt-ping-testing	g Eval 👻						P	?	
<>	API Proxies > httpb	in > Develop	> 2							:
Դ Ու		Add Step				×	DEVEL	.OP DEBUG	PERFC	RMANCE
6	Revision 2 Updated 12 hours ago Navigator	Policy Instance	New Existing					eploy to: eval	•	Save 🔹
	Search	C n. PingAuth					low			
	httpbin			Policy Type	PingAuth		e	PreFlow		
	■ httpbin ▼ Policies			Display Name	PingAuth		quest iponse			
	PingAuth			News	Dischuth					
	 Proxy Endpoints 			Name	PingAuth					
	✓ default			Attached to Flows	none					
	All PreFlow All PostFlow									
	✓ Target Endpoints									
	▼ default									
	All PreFlow									
	All PostFlow ▼ Resources									
-	• Nesources									
						Cancel Add				
			<response></response> PostFlow> TTPProxyConnection> <basepath>/httpbin</basepath>							

4. Click Add.

- 5. In the Target Endpoints panel on the left, select PreFlow.
- 6. In the **Response** section, click **+Step** to add a flow step to the response.

(i) Note

This allows PingAuthorize to process the API response from the target API before it's processed by Apigee.

- 7. In the Add Step modal, click the Existing tab, and then select the Flow Callout policy you created previously.
- 3. Save and deploy the updated proxy.

API Proxies > h	ttpbin > De	evelop > 3	OVE	RVIEW DEVEL	OP DEBUG	PERFC
Revision 3 Updated 3 hou	urs ago		Currently on eval: Revi		ploy to: eval	-
Navigator	Flow	r: PreFlow	Help for Selected Flow	Property Inspec	ctor PreFlow	
Search Search	+ Enc + 1 2	dpoint default Policy PingAuth k?xml version="1.0" encoding="UTF-8" standalone="yes"?> <flowcallout continueonerror="false" enabled="true" name="]</td><td>+
Step
FingAut
h
PingAuth"></flowcallout>	PreFlow name Request Response Step Name	PreFlow PingAuth		
	3 4 5 6 7	<faultrules></faultrules> <properties></properties> <sharedflowbundle> PingAuth</sharedflowbundle>				

Next steps

Configure fine-grained authorization policies in the PingAuthorize Policy Editor. You can find information on how to target specific API requests and extract other HTTP metadata to use in your policies in Sideband API policy requests.

Troubleshooting the Apigee integration

Troubleshoot the most common issues with the Apigee gateway integration with PingAuthorize.

Troubleshooting API client HTTP 5xx errors

About this task

Apigee might return HTTP 502 when there is misconfiguration or miscommunication between the PingAuth Shared Flow for Apigee and PingAuthorize Server.

To address 5xx errors, make adjustments to the **Load KVM Config** policy assigned to **PingAuth** in Apigee X or the key value map that you created for the PingAuth Shared Flow in Apigee Edge or Apigee Private Cloud.

The PingAuth Shared Flow for Apigee logs warning messages to the Apigee error log when it encounters problems communicating with PingAuthorize. For more information, see Enable logging in Apigee.

Steps

• Check the PingAuth Shared Flow service_host_port value.

If the Apigee **service_host_port** value does not match your PingAuthorize server environment, the Apigee error log message might indicate that the plugin received an invalid response from the server.

1. Confirm that the value entered for **service_host_port** matches the host name of your PingAuthorize server and the port of the HTTPS connection handler.

You can find this port number on the **Configuration** page of the PingAuthorize administration console by going to **System** \rightarrow **Connection Handlers**.

- 2. If necessary, update the service_host_port value to match your PingAuthorize server.
- Check the PingAuth Shared Flow shared secret.

If the shared secret doesn't match the API gateway credential in PingAuthorize, the Apigee error log message might indicate that the plugin received an HTTP 401 error from PingAuthorize, which gets translated to a 5xx error and then sent to the API client.

- 1. Confirm that the value of the **shared_secret** key that you created in Apigee matches the shared secret value that you created for PingAuthorize.
- 2. If necessary, on the **Configuration** page of the PingAuthorize administration console, go to **Web Services and Applications** → **HTTP Servlet Extensions** → **Sideband API** and update the value of the shared secret.
- 3. Copy the new value of the shared secret and update the value of the Apigee shared_secret key.

Troubleshooting API client HTTP 4xx errors

The Apigee API gateway might return a 4xx error to the API client if the API client's request can't be authenticated by the PingAuthorize sideband API endpoint.

To troubleshoot 4xx errors caused by authentication issues against the PingAuthorize sideband API, see Diagnostic and decision data.

Setting up error response handling in the target server

About this task

You should have an Apigee policy that handles errors returned by the target server.

If you don't configure error handling using a policy, the API proxy goes into an error state in the **<TargetEndpoint>** response, and the normal API proxy flow won't continue to the **<ProxyEndpoint>**.

Steps

1. Go to API Proxies → httpbin_bad_response → Develop and create a new ReturnGenericError policy of type AssignMessage. Configure the policy as desired.

Apigee darina-apige	ex Eval 👻		
A Your Apigee evaluation will expire	re in 10 days.		
<> Develop	API Proxies > httpbin	bad_response > Develop > 22	
API Proxies			
Shared Flows	Revision 22 Vpdated Jun 7th, 2022		OVE Currently on eval: Revis
Offline Debug	Updated Jun /th, 2022		Currentiy on eval: Hevis
T Publish	A new version of the Develop tab is availa	le for preview Try now Learn more	
II. Analyze	Navigator	Policy: ReturnGenericError	Help for Selected Assign Message Policy
Admin Admin	Search ■ httpbin_bad_response ▼ Policies ■ pingauth 2 ReturnGenericError	Type AssignMessage Display Name ReturnGenericError Name ReturnGenericError	
	 Proxy Endpoints 	+ Code ReturnGenericError	÷
	default All PreFlow All PostFlow Target Endpoints default All PreFlow All PreFlow All PostFlow	<pre>+ 1 k?xml version="1.0" encoding="UTF-8" standalone="yes"?> 2 < -AssignMessage name="ReturnGenericErron"> 3 < <set> 4 <</set></pre>	BLE. PLEASE CONTACT SUPPORT.
	 Resources 	+	

2. Select the **PreFlow** option in the **Target Endpoints** for your API proxy. Add the error policy you just created as a <**Step>** in the <**DefaultFaultRule>**.

(i) Note There are mul	tiple methods for adding	error handling policy.	
Apigee darina-ap Vour Apigee evaluation will a	expire in 10 days.		
Develop	Navigator	Flow: PreFlow	
API Proxies	Search		
	httpbin_bad_response		
Shared Flows	 Policies 	+	
	🕂 pingauth		
Offline Debug	ReturnGenericError	REQU	EST
Publish	 Proxy Endpoints 	+ Code default	
	✓ default All PreFlow	+ 1 xml version="1.0" encoding="UTF-8" standalone="y<br 2 ~ <targetendpoint name="default"> 3 ~ <preflow name="PreFlow"></preflow></targetendpoint>	es" <i>!></i>
•••	All PostFlow	4 <request></request>	
😥 Admin	 Target Endpoints 	+ 5 · <response> 6 · <step></step></response>	
	▼ default	+ 7 <a>Name>pingauth	
	All PreFlow	8 9	
	All PostFlow	10 /PreFlow	
	 Resources 	+ 11 <flows></flows> 12 < <postflow name="PostFlow"></postflow>	
		13	
		14 <response></response>	
		<pre>15 16 < </pre> <pre>coefaultFaultRule name="fault-rule"></pre>	
		17 • <step></step>	
		18 Name>ReturnGenericError 19 	
		20	
		<pre>21 - <httptargetconnection> 22 <url>https://httpbin.org/status/400</url></httptargetconnection></pre>	
		23	
		24	

Enable logging in Apigee

To view error log messages, configure Apigee error logging. For more information, see the Apigee Trace documentation².

Apigee also provides debug logging for further troubleshooting. For more information, see Enabling debug logging \square in the Apigee documentation.

Kong API gateway integration

Ping Identity provides the **ping-auth** Kong Gateway integration plugin, which enables PingAuthorize to be used for attributebased access control and policy decisions.

Integration with Kong Gateway allows PingAuthorize to handle the complexities of attribute-based access control and dynamic authorization, making it easier for you to control access to your API resources. Instead of configuring policies multiple times, deploy the Kong Gateway integration once and manage your policy rules in PingAuthorize.

The following are important to consider when using the ping-auth Kong Gateway integration plugin for PingAuthorize:

Mutual TLS (mTLS)

This plugin supports client certificate authentication using mTLS. However, this feature requires using the mtls-auth plugin, only available in the enterprise edition of Kong, in conjunction with ping-auth. For more information, see the Kong mTLS documentation ^[]. When configured, mtls-auth uses the mTLS process to retrieve the client certificate, which allows ping-auth to provide the certificate in the client_certificate field of the sideband requests.

Transfer-encoding

Because of an outstanding defect in Kong, **ping-auth** is unable to support the Transfer-Encoding header, regardless of the value.

Logging limit

Because of OpenResty's log level limit, log messages are limited to 2048 bytes by default, which is less than the size of many requests and responses. For more information, see the OpenResty reference documentation \square .

Preparing PingAuthorize for Kong Gateway integration

For Kong Gateway to use PingAuthorize as an external authorization policy runtime service, you must prepare PingAuthorize to receive authorization requests from Kong Gateway.

Before you begin

- Install and start Kong Gateway. Learn more in the Kong Gateway 🖸 documentation.
- Install and start PingAuthorize. Learn more in Installing PingAuthorize.

Steps

- 1. In the PingAuthorize administrative console, go to Configuration > HTTP Servlet Extensions > Sideband API.
- 2. In the Request Context Method list, select State.

- 3. In the Shared Secret Header Name field, enter CLIENT-TOKEN.
- 4. Next to the **Selected** table for **Shared Secrets**, click the + icon to create a new shared secret.

∧ Important

The shared secret authenticates the **ping-auth** plugin to PingAuthorize. Version 1.2.0 of the plugin supports referenceable secrets. For security reasons, store the shared secret in a vault supported by Kong. Learn more in Secrets Management \square and Environment Variables Vault \square in the Kong documentation.

- 5. In the modal dialog, create a suitably long shared secret value, and then click Save To PingAuthorize Server Cluster.
- 6. At the top of the Edit Sideband API HTTP Servlet Extension page, click Save.

Ping Identity.	PingData Administrative Co	onsole		E Servers	🕶 👤 administrator 🕶 🛛 🕶
Configuration	d38098802088 / Configuration	h / HTTP Servlet Extensions /			Configuration Guide
Status		ITTP Servlet Extension ension is used by a third-party API Gateway t	o authorize JSON-based H	HTTP request an	d response data.
				View API com	mands Save Cancel
	Name *	Sideband API 🕜			
	Description				Ø
	Cross Origin Policy	No cross-origin policy is defined and no C	CORS hea	0	
	Response Header	Enter a value to add		•	F & 0
				1	ĸ
	Correlation ID Response Header	The correlation-id-response-header prope	rty of the HTTP Connect	0	
	Request Limit	No size limit will be enforced on requests.		AO	
	Request Context Method	state	0 C - X		
	Shared Secret Header Name *	CLIENT-TOKEN		9 C'	
	Shared Secrets	Available	Selected		0 C
		Search Q	Search Kong Gateway		۹ ۲
			Kong Galeway		-
			•		
			*		-

Setting up Kong Gateway

Download, install, and configure the ping-auth plugin to set up Kong Gateway with PingAuthorize.

Steps

1. Install the plugin by running the luarocks install kong-plugin-ping-auth command.

Learn more in the Kong Gateway plugin installation guide \square .

- 2. After installation, load the plugin into Kong by editing the plugins = bundled, ping-auth property in the kong.conf file.
- 3. Restart Kong Gateway.
- 4. To confirm the plugin loads successfully, look for the debug-level Loading plugin: ping-auth message in Kong's error. log file.
- 5. Use the Kong Gateway UI or API to complete the configuration.

Kong Gateway UI • In Kong Manager, select the default workspace, and then click Plugins. Kong Manager Change Workspace Plugins New Plugin default Plugins allow you to extend Kong's capabilities with features like rate limiting, authentication, and logging. Learn more 🖾 Dashboard Search by id **API** Gateway Name Enabled Id Applied To Services 3e70ec9a... 🖸 😑 ping-auth false Global View Edit 屳 Routes Consumers Plugins Upstreams Certificates +* I wish this page would ... SNIs

• Next to the ping-auth plugin, click Edit, and then click the toggle to enable the plugin.

Â	Kong Manager	Workspaces Dev Portals Vitals Teams	Docs / Support	(j)
88	Change Workspace			
DE	default	Plugins > Update ping-auth plugin		
(∑)	Dashboard	This plugin is Enabled		
	API Gateway Services Routes	Global All services, routes, and consumers Scoped		
	Consumers	Specific consumers, services, and/or routes		
	Upstreams	Tags ③ Enter list of tags		
	SNIs	e.g. tag1, tag2, tag3		

- (Optional) To enable the plugin for specific consumers, services, or routes, click Scoped, and then enter Service, Route, and Consumer information as needed.
- Connect Kong Gateway to PingAuthorize.
 - 1. Make sure the **Config.Secret Header Name** value in Kong Manager matches the secret header name configured for the Sideband API Servlet Extension in PingAuthorize.

CLIENT-TOKEN	
Config.Service Url	
https://pingauthorize:8443	
Config.Shared Secret xxxxxxxxxxxx Config.Verify Service Certificate	
Update Cancel	Delete Plug

2. In the **Config.Service URL** field in Kong Manager, enter the hostname of your PingAuthorize Server instance and the port of the HTTPS Connection Handler.

For example, https://pingauthorize:8443.

Q Tip

To find the HTTPS Connection Handler port number in the PingAuthorize administrative console, go to **Configuration > System > Connection Handlers**.

3. In the Config.Shared Secret field, enter the sideband client's shared secret you created in Preparing PingAuthorize for Kong Gateway integration.

is Important

The shared secret authenticates the ping-auth plugin to PingAuthorize. Version 1.2.0 of the plugin supports referenceable secrets. For security reasons, store the shared secret in a vault supported by Kong. Learn more in Secrets Management \square and Environment Variables Vault \square in the Kong documentation.

• (Optional) Configure the rest of the optional fields in Kong Manager or the API.

Option	API Field Name	Description
Config.Connection KeepAlive Ms	connection_keepAlive_ms	The duration to keep the connection alive for reuse. The default is 60000.

Option	API Field Name	Description
Config.Connection Timeout Ms	connection_timeout_ms	The duration to wait before the connection times out. The default is 1 0000 .
Config.Enable Debug Logging	enable_debug_logging	Controls if requests and responses are logged at the debug level. The default is false. For log messages to show in error.log, you must set log_level = debug in kong.conf.
Config.Verify Service Certificate	verify_service_certificate	Controls whether the service certificate is verified. This is intended for testing purposes and the default is true.

• Click Update, and then click Update Plugin.

Kong Gateway API

• Include the following JSON object in a POST request to https://<KONG_URL>/plugins:

```
{
    "name": "ping-auth",
    "enabled": true,
    "config": {
        "service_url": "https://<PingAuthorize Server hostname>:<HTTPS Connection Handler port>/",
        "shared_secret": "<shared secret>",
        "secret_header_name": "<shared secret header name>"
    }
}
```

• service_url: The hostname of your PingAuthorize Server instance and the port of the HTTPS Connection Handler. This URL shouldn't contain /sideband in the path.

For example, https://pingauthorize:8443.

• shared_secret : The shared secret value you created in the PingAuthorize administrative console.

i Important

The shared secret authenticates the ping-auth plugin to PingAuthorize. Version 1.2.0 of the plugin supports referenceable secrets. For security reasons, store the shared secret in a vault supported by Kong. Learn more in Secrets Management \square and Environment Variables Vault \square in the Kong documentation.

secret_header_name : The name of the header in which the shared secret is provided.

Learn more in the Kong Gateway Admin API documentation.

• (Optional) Configure additional options.

Option	API Field Name	Description
Config.Connection KeepAlive Ms	connection_keepAlive_ms	The duration to keep the connection alive for reuse. The default is 60000.
Config.Connection Timeout Ms	connection_timeout_ms	The duration to wait before the connection times out. The default is 1 0000 .
Config.Enable Debug Logging	enable_debug_logging	Controls if requests and responses are logged at the debug level. The default is false. For log messages to show in error.log, you must set log_level = debug in kong.conf.

Option	API Field Name	Description
Config.Verify Service Certificate	verify_service_certificate	Controls whether the service certificate is verified. This is intended for testing purposes and the default is true.

Result

Kong Gateway is now configured to work with PingAuthorize.

Troubleshooting the Kong Gateway integration

Consult the following sections to troubleshoot issues with the Kong Gateway integration with PingAuthorize:

- Troubleshooting API client HTTP 5xx errors
- API client HTTP 4xx errors
- Enabling error logging in Kong Gateway
- Enabling debug logging for the Kong Gateway plugin

Troubleshooting API client HTTP 5xx errors

About this task

Kong Gateway might return HTTP 502 when there is misconfiguration or miscommunication between the Ping Identity plugin for Kong Gateway and PingAuthorize Server.

Note (i)

The plugin for Kong Gateway logs warning messages to the Kong Gateway error log when it encounters problems communicating with PingAuthorize.

For more information, see Enabling error logging in Kong Gateway.

Steps

1. Check the ping-auth shared secret value in Kong Gateway to confirm it matches your PingAuthorize environment.

Example:

If the ping-auth Config.Shared Secret value doesn't match the PingAuthorize sideband client's shared secret value, the Kong error log message might indicate that the plugin received an HTTP 401 error from PingAuthorize, which gets translated to a 5xx error sent to the API client. For example:

2022/03/28 16:19:49 [warn] 78#0: *85187 [lua] network_handler.lua:145: is_failed_request(): [ping-auth] Sideband request denied with status code 401: The Gateway Token is invalid

- 1. If there is a shared secret mismatch, go to **Configuration** → **Web Services and Applications** → **Sideband API Shared Secrets** in the PingAuthorize administrative console.
- 2. Update the shared secret value for PingAuthorize.
- 3. Copy the value to the **Config.Shared Secret** field in the Kong Gateway ping-auth plugin configuration.
- 2. Check the **ping-auth Config.Service URL** value in Kong Gateway to confirm that it matches your PingAuthorize environment.

Example:

If the **Config.Service URL** value doesn't contain the hostname and HTTPS Connection Handler port configured for your PingAuthorize server, the Kong error log message might indicate that the plugin received an invalid response from the server. For example:

2022/03/28 16:19:49 [error] 78#0: *90929 [lua] access.lua:114: handle_response(): [ping-auth] Unable to parse JSON body returned from policy provider. Error: Expected value but found T_END at character 1

1. If necessary, confirm that the values entered in the **Config.Service Url** field of the **ping-auth** plugin in Kong Gateway correspond to the hostname and HTTPS Connection Handler port of your PingAuthorize server.

You can find this port number in the PingAuthorize administrative console by going to **Configuration** \rightarrow **System** \rightarrow **Connection Handlers**.

2. Update any mismatched values in **Config.Service Url**.

API client HTTP 4xx errors

The API gateway could return 4xx errors to API clients in these situations:

- PingAuthorize cannot match an API client's request to any of the base paths configured for a sideband API endpoint.
- The API client's request cannot be authenticated for a sideband API endpoint.

🔿 Тір

For more information, see **Diagnostic and decision data**.

Enabling error logging in Kong Gateway

Steps

1. To view error log messages, configure Kong Gateway error logging.

For more information on log levels, see the Kong Gateway Logging Reference documentation.

Example:

For example, in a Docker environment, you can set the environment variable KONG_PROXY_ERROR_LOG to /dev/stderr to send the error log to the container console.

2. View the Kong Gateway error log.

Example:

For example, in a Docker deployment, you can use the docker-compose logs kong --follow command.

Enabling debug logging for the Kong Gateway plugin

About this task

Ping Identity Support might ask you to enable debug logging for the Kong Gateway integration kit. Changing these settings logs the full authorization request and response between the ping-auth plugin in Kong Gateway and PingAuthorize.

() Caution

This could log sensitive and personally identifiable information (PII). Enable debug logging only when troubleshooting and disable it afterward.

Steps

- 1. Enable error logging in Kong Gateway.
- 2. To view debug messages, configure Kong error log verbosity.

For more information, see the Kong Gateway Logging Reference C documentation.

Example:

For example, in a Docker environment, you can set the environment variable KONG_LOG_LEVEL to debug to set the verbosity.

- 3. To enable debug logging, edit settings for the ping-auth plugin and select the Config.Enable Debug Logging check box.
- 4. View the Kong Gateway error log.

Example:

For example, when depoloying Docker, you can use the docker-compose logs kong --follow command.

5. Look for messages containing ping-auth.

Example:

A typical log message looks like: [ping-auth] Sending sideband request to policy provider.

MuleSoft API gateway integration

Learn how to enable fine-grained access control through the MuleSoft API gateway by deploying the PingAuthorize API adapter and connecting to the sideband API.

Ping Identity provides a custom MuleSoft policy to enable this configuration.

To integrate PingAuthorize with the MuleSoft gateway, see the following:

- 1. Deploying the custom MuleSoft policy for PingAuthorize
- 2. Applying the custom MuleSoft policy for PingAuthorize

Deploying the custom MuleSoft policy for PingAuthorize

You must deploy the custom MuleSoft policy to make it available to your integrated APIs.

Before you begin

You must:

• Have the correct MuleSoft version.

The custom policy supports MuleSoft 4.3.0. If you are using any other version, contact Ping Identity support.

• Install and configure PingAuthorize software.

See the PingAuthorize installation information for your environment.

- Download the MuleSoft Integration Kit for PingAuthorize^[2], which contains the custom MuleSoft policy.
- Create a sideband adapter shared secret.

Sideband adapters like the custom MuleSoft policy use a shared secret header to authorize against PingAuthorize. For information, see Creating a shared secret.

(i) Note

Make sure you record the shared secret value. You need it to configure the MuleSoft policy.

· Configure the sideband adapter request context.

For more information, see **Request context configuration**. Complete the section titled Request context using the state field.

• Install Apache Maven.

About this task

To begin integrating PingAuthorize with MuleSoft 4.3.0, deploy the custom MuleSoft policy. The MuleSoft policy package has a .zip archive that contains the policy files.

Steps

- 1. Extract the policy files to create a project folder.
- 2. Edit the pom.xml file to enter your organization's groupID.

Example:

```
<?xml version="1.0" encoding="UTF-8"?>
cyroject xmlns="http://maven.apache.org/POM/4.0.0"
    xmlns:xsi="http://www.w3.org/2001/XMLSchemainstance"
    xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://maven.apache.org/xsd/maven-4.0.0.xsd">

cmodelVersion>4.0.0

cmodelVersion>4.0.0
```

```
<artifactId>PingAuthorize</artifactId>
    <version>0.4.0</version>
    <name>PingAuthorize</name>
    <description>PingAuthorize sideband policy for Mule 4.X APIs deployed on Mule Cloudhub from Ping
Identity</description>
```

3. From the command line in your project folder, run the following command to package the PingAuthorize policy and create a deployable .jar file. > mvn clean install

(i) Note

You must have a MuleSoft Enterprise Repository license to compile the policy. For more information, see *Configure Maven to Access MuleSoft Enterprise Repository* in Maven Reference^[].

4. Upload the PingAuthorize policy to Exchange

For more information, see Deploying a Policy Created Using the Maven Archetype^[].

Result

The custom MuleSoft policy is now available to your APIs. For more information, see Applying the custom MuleSoft policy for PingAuthorize.

Applying the custom MuleSoft policy for PingAuthorize

You must apply the deployed custom MuleSoft policy to use MuleSoft as an API gateway with PingAuthorize.

About this task

The PingAuthorize policy supports HTTP APIs configured with the Endpoint with proxy or Basic Endpoint options.

Steps

- 1. Sign on to your MuleSoft Anypoint account.
- 2. Go to the API manager, expand the API to which you want to attach the PingAuthorize policy, and click Version.

🚍 🕦 API Ma	anager					
API Administration (S	andbox)					
SANDBOX	Manage API V Prom	ote from environment	Q PingAuthorizeAPI		\times	1-1 of 1 v < >
API Administration					All Favorites Active	
API Groups New					[P Environment Information
Automated Policies						
Client Applications	API Name	Version	Status	Client Applications	Creat	ion Date
Analytics	 PingAuthorizeAPI 				1 vers	ion
Analytics		☆ <u>v1</u>	Unregistered	0	06-15	-2021 13:51

3. In the left navigation pane, click **Policies**.

The **Policies** page supports applying the PingAuthorize policy to the API.

🚍 🝿 API Manager		
API Administration (Sandbox) PingAuthorizeAPI (v1) - Settings		
SANDBOX	PingAuthorizeAPI v1	
- API Administration	API Status: O Unregistered Asset Version: 1.0.0 Latest ()	Туре: НТТР
	Add consumer endpoint	
Alerts		
Contracts	API Instance 🛈	Autodiscovery 🛈
Policies	ID: 16971110	API ID: 16971110
SLA Tiers	Label: 🕀 Add a label	
Settings		

4. Click Apply New Policy.

😑 🕦 API Ma	Ξ 🕦 API Manager			
API Administration (Sandbox) PingAuthorizeAPI (v1) - Policies				
SANDBOX	PingAuthorizeAPI v1			
← API Administration	API Status: Unregistered Asset Version: 1.0.0 Latest () Type: HTTP			
Alerts				
Contracts				
Policies	API level policies			
SLA Tiers	Apply New Policy			
Settings	Apply new roncy			
	There are no applied policies.			

Result:

The Select Policy window opens.

5. In the Select Policy window, select the PingAuthorize policy and current version. Click Configure Policy.

All Categories	✓ All Mule Versions ✓	
Policies	Min Mule Version	
> Message Logging		
> Rate limiting		
> Rate limiting - SLA based		
> Spike Control		
> Tokenization	You need permission to apply this p	olicy. Learn more
	You need permission to apply this p	oolicy. Learn more
> XML threat protection	You need permission to apply this p	oolicy. Learn more
 XML threat protection Add Attribute Custom 	You need permission to apply this p	oolicy. Learn more
> XML threat protection> Add Attribute Custom	You need permission to apply this p 4.1.1	oolicy. Learn more

- 6. On the Apply Policy page, enter the following values:
 - 1. In the **PAZ Token** field, enter the sideband adapter shared secret generated as part of the prerequisites in **Deploying the custom MuleSoft policy for PingAuthorize**.
 - 2. In the PAZ Host field, enter the PingAuthorize host and port.

(i) Note

Do not include the connection scheme (http:// or https://).

- 3. Select the **Enable SSL** check box for a secure HTTPS connection between MuleSoft and PingAuthorize.
- 4. Select the **Allow self-signed certificate** check box to enable MuleSoft to accept a self-signed certificate from PingAuthorize.

For information about configuring PingAuthorize to use trusted certificates, see **Importing signed and trusted** certificates.

5. Select an access token type:

Choose from:

Use Authorization Header: Indicates that the authorization header of an incoming request should be passed to PingAuthorize and used to authorize the client.

- Use hard-coded parsed access token: Allows configuration of an access token that will be used for every request. Use this only for testing purposes.
- Use parsed access token: Allows configuration of a DataWeave expression for retrieving a parsed access token from the Mule message. When you use MuleSoft's OAuth 2.0 Token Enforcement policies to obtain a parsed access token, use the expression #[authentication.properties.userProperties]. For more information, see DataWeave Language ^[].

6. Optional: Configure the Connection Timeout and Read Timeout.

Timeouts govern the behavior of the API gateway when it cannot connect to PingAuthorize or the response from PingAuthorize is delayed.

Timeout parameter	Description
Connection Timeout	Governs the time the API gateway waits to establish a connection with PingAuthorize, following which it sends the client request to the backend server.
Read Timeout	Governs the time the API Gateway waits for PingAuthorize's response before sending the request to the backend server.

(i) Note

The default value is 5000 milliseconds (5 seconds). It's good practice to configure a small value to limit the delay in case PingAuthorize isn't reachable or is unresponsive.

7. **Optional:** Select the **Enable debug logging** check box to see requests sent to PingAuthorize Server along with responses.

8. Optional: Configure Methods & Resource Conditions.

See **Resource-Level Policies** for more information.

Apply PingAuthorize policy
PingAuthorize sideband policy for Mule 4.X APIs deployed on Mule Cloudhub from Ping Identity
PAZ TOKEN PingAuthorize sideband shared secret
PAZ Host * Hostname or IP:Port
18.081 081-00100
Enable SSL If enabled, Mulesoft will connect to PingAuthorize over HTTPS
Allow self-signed certificate If enabled, Mulesoft will accept self-signed certificates from PingAuthorize
Access token type * How the adapter should handle access tokens
O Use Authorization header
Use hard-coded parsed access token (for testing purposes only) Use parsed access token
Connection Timeout *
Connection Timeout * Connection timeout in milliseconds
5000
Read Timeout * Read timeout in milliseconds
5000
Enable debug logging If enabled, logs requests to and responses from the PingAuthorize server.
Method & Resource conditions
Apply configurations to all API methods & resources
Apply configurations to specific methods & resources
Cancel Apply

Next steps

If there are any changes to PingAuthorize endpoints, repeat the process explained in step 6 and re-deploy the configuration.

PingAuthorize Server Administration Guide

.

PingIdentity.

PingAuthorize Server includes the runtime policy decision service and multiple integration capabilities:

- Authorization policy decision APIs
- API security gateway and sideband API
- SCIM service

Running PingAuthorize

For manual software installations of PingAuthorize Server and the PingAuthorize Policy Editor, you can launch the applications from the command-line interface (CLI).

Starting PingAuthorize Server

To start PingAuthorize Server in a Unix/Linux computing environment, use the **bin/start-server** command-line interface (CLI) command. On Windows, use the **bat/start-server.bat** command.

Steps

1. In a terminal window, go to the directory where you have installed PingAuthorize Server.

2. Run the command for your operating system.

Operating System	Command
Unix/Linux	bin/start-server
Windows	bat/start-server.bat

Running PingAuthorize Server as a foreground process

Run or stop PingAuthorize Server as a foreground process in Unix/Linux computing environments through the CLI.

Steps

- To launch PingAuthorize Server as a foreground process, run \$ bin/start-server --nodetach.
- To stop a running PingAuthorize Server, do one of the following:

Choose from:

- In the terminal window running the server, press and hold CTRL+C.
- In a new terminal window, run bin/stop-server.

Starting PingAuthorize Server at boot time (Unix/Linux)

Create a script to run PingAuthorize Server when the system boots.

About this task

PingAuthorize Server does not start automatically when the system is booted. By default, you must use the **bin/start-server** command to start it manually.

Steps

• To configure PingAuthorize Server to start automatically when the system boots, complete one of the following tasks:

Choose from:

- Use the create-systemd-script utility to create a script.
 - 1. Create the service unit configuration file in a temporary location, as in the following example:

```
$ bin/create-systemd-script \
  --outputFile /tmp/ping-authorize.service \
  --userName pingauthorize
```

In this example, **pingauthorize** represents the username assigned to PingAuthorize Server.

- 2. Switch to root user. The command for doing this will vary depending on your distribution.
- 3. As a root user, copy the ping-authorize.service configuration file to the /etc/systemd/ system directory.

cp ping-authorize.service /etc/systemd/

4. Reload systemd to read the new configuration file.

\$ systemctl daemon-reload

5. To start PingAuthorize Server, use the **start** command.

\$ systemctl start ping-authorize.service

6. To configure PingAuthorize Server to start automatically when the system boots, use the **enable** command, as in the following example:

\$ systemctl enable ping-authorize.service

7. Sign off from the system as the root user.

- Create a Run Control (RC) script manually.
 - 1. Run **bin/create-rc-script** to create the startup script.
 - 2. Move the script to the /etc/init.d directory.
 - 3. Create symlinks to the script from the /etc/rc3.d directory.

To ensure that the server is started, begin the symlinks with an **S**.

4. Create symlinks to the script from the /etc/rc0.d directory.

To ensure that the server is stopped, begin the symlinks with a κ .

Starting PingAuthorize Server at boot time (Windows)

On Windows Server systems you can register PingAuthorize Server as a service to start it up when booting.

About this task

PingAuthorize Server can run as a service on Windows Server operating systems. This approach allows the server to start at boot time, and allows the administrator to log off from the system without stopping the server.

Registering PingAuthorize Server as a Windows service

Registering PingAuthorize Server as a service allows you to automate startup when booting.

About this task

🕥 Note

The following options are not supported when PingAuthorize Server is registered to run as a Windows service:

- · Command-line arguments for the start-server.bat and stop-server.bat scripts
- Using a task to stop the server

Steps

1. Run **bin/stop-server** to stop PingAuthorize Server.

i) Note

You cannot register a server while it is running.

- 2. From a Windows command prompt, run **bat/register-windows-service.bat** to register the server as a service.
- 3. Use one of the following methods to start PingAuthorize Server:

Choose from:

- The Windows Services Control Panel
- The bat/ start-server.bat command

Running multiple service instances

You can run multiple instances of PingAuthorize Server as Windows services by altering the wrapper-product.conf file.

About this task

Only one instance of a particular service can run at a time. Services are distinguished by the wrapper.name property in the <serv er-root>/config/wrapper-product.conf file.

To run additional service instances, change the wrapper.name property on each additional instance. You can also add or change service descriptions in the wrapper-product.conf file.

Steps

- 1. Open the <server-root>/config/wrapper-product.conf file.
- 2. Change the wrapper.name property to a unique string, such as pingauthorize1.
- 3. Save the wrapper-product.conf file.
- 4. Register PingAuthorize Server as a service. For more information, see Registering PingAuthorize Server as a Windows service.
- 5. Repeat these steps for each service instance you want to create.

Deregistering and uninstalling services

When a server is registered as a service, it cannot run as a non-service process or be uninstalled.

About this task

Steps

- 1. To remove the service from the Windows registry, run the bat/deregister-windows-service.bat script.
- 2. To uninstall PingAuthorize Server, run the PingAuthorize/uninstall.bat script. For more information, see Uninstalling PingAuthorize.

Log files for Windows services

You can configure the log files generated by PingAuthorize Server running as a Windows service.

Log files are stored in <server-root>/logs, and file names begin with windows-service-wrapper.

You can edit the log file configurations in the <server-root>/config/wrapper.conf file.

Log files are configured to rotate each time the wrapper starts due to file size. You can edit the allowed file size using the wrapper .logfile.maxsize parameter. The default size is 50 Mb.

By default, only the two most recent log files are retained. You can change how many log files to retain by editing the wrapper.logfile.maxfiles parameter.

(i)

Starting PingAuthorize Policy Editor

For a manual software installation, use the start-server command-line interface (CLI) command to start the Policy Editor. Also, you can use environment variables to override configuration variables at startup.

```
To start PingAuthorize Policy Editor, use the bin/start-server command.
```

```
$ bin/start-server
     Note
```

You can run bin/start-server manually from the command line or within a script.

Overriding the configuration at startup

You can override a number of Policy Editor settings by defining specific environment variables before starting the server. By overriding some of the configuration, you can redefine certain aspects of the configuration without re-running the **setup** tool.

To override the configuration, stop the Policy Editor, define one or more of the environment variables, and restart the Policy Editor.

Environment variables you can use to override configuration variables

The following table lists the environment variables that you can define, sorted based on expected frequency of use with related variables grouped together.

Environment variable	Example value	Description
PING_EXTERNAL_BASE_URL	pap.example.com:9443	The Policy Editor hostname and port. PingAuthorize uses this value to construct AJAX requests. The port value must match the value of PING_PORT for web browsers to pass cross-origin resource sharing (CORS) checks.
PING_PORT	443	The Policy Editor HTTPS port. The server binds to this listen port.
PING_KEYSTORE_TYPE	JKS	The Policy Editor's key store type. Valid values include \ensuremath{JKS} and $\ensuremath{PKCS12}$.
PING_KEYSTORE_PATH	/path/to/keystore.jks	The path to the Policy Editor's key store.

Environment variable	Example value	Description
KEYSTORE_PIN_FILE	/path/to/keystore.pin	The path to the Policy Editor's key store PIN file. When present, this environment variable takes precedence over PING_KEYSTORE_PASSWORD when validating and presenting the server certificate. The key store PIN value itself does not persist to the configuration.yml file and is not visible on the command-line. For a more complete example, see the Demo mode (custom SSL certificate) tab of Installing the PingAuthorize Policy Editor non-interactively .
PING_KEYSTORE_PASSWORD	password1234	The Policy Editor's key store password.
PING_CERT_ALIAS	server-cert	The alias for the Policy Editor's server certificate.
PING_SHARED_SECRET	pingauthorize	The Policy Editor's shared secret, which PingAuthorize Server needs to make policy requests to the Policy Editor.
PING_OIDC_ CONFIGURATION_ENDPOINT	https://oidc.example.com: 9031/.well-known/openid- configuration ^[2]	The OpenID Connect (OIDC) provider's discovery Uniform Resource Locator (URL). Used when the Policy Editor is set up in OIDC mode.
PING_SCOPE	openid email profile additional_scope	Space-separated OIDC scope that the Policy Editor requests during authorization and validates during token verification. Used to override the requested OIDC scopes configured during server setup.
PING_OIDC_TLS_VALIDATION	NONE	The OIDC Transport Layer Security (TLS) validation setting. Set to NONE to configure the Policy Editor to accept self-signed Secure Sockets Layer (SSL) certificates from the OIDC provider and skip hostname verification. Used when the Policy Editor is set up in OIDC mode. For non- production use only.
PING_CLIENT_ID	8cb9f2c9-c366-47e0-9560- db2132b2d813	The Policy Editor's client ID with the OIDC provider. Used when the Policy Editor is set up in OIDC mode.
PING_USERNAMES	admin, user1, user2	Used in demo mode. A comma-separated list of usernames accepted by the Policy Editor for sign on.
PING_H2_FILE		The path to the policy database H2 file. Leave off the .mv.db extension.
PING_DB_APP_USERNAME	db_user	The username the application uses to access the server database.
PING_DB_APP_PASSWORD	Pa\$\$w0rd!23	The password the application uses to access the server database.

Environment variable	Example value	Description
PING_DB_ADMIN_USERNAME	db_admin	The username the setup tool uses when upgrading the policy database (H2 only).
PING_DB_ADMIN_PASSWORD	\$3cr3T	The password the setup tool uses when upgrading the policy database (H2 only).
PING_OPTIONS_FILE	/path/to/options.yml	The path to an options.yml file to use with the Policy Editor's setup tool.
PING_ADMIN_PORT	9444	The admin port where the H2 database backup endpoint is available. The policy administration point (PAP) uses this endpoint to back up the H2 database, which stores your Trust Framework, policies, commit history, and other data. Related environment variables: PING_BACKUP_SCHEDULE , PING_H2_BACKUP_DIR
PING_BACKUP_SCHEDULE	000**?	The periodic database backup schedule for the Policy Editor (also known as the PAP) in the form of a cron expression.
		Note The PAP evaluates the expression against the system timezone. For the PingAuthorize Docker images, the default timezone is UTC.
		The default is 0 0 0 * * ? , which is midnight every day. For more information, see .quartz-scheduler.org/ documentation/quartz-2.3.0/tutorials/crontrigger.html// [Quartz 2.3.0 cron format]. Related environment variables: PING_ADMIN_PORT , PING_H2_BACKUP_DIR
PING_H2_BACKUP_DIR	/opt/out/backup	The directory in which to place the H2 database backup files. The default is [.parmname] SERVER_ROOT /policy-backup. Related environment variables: PING_ADMIN_PORT, PING_BACKUP_SCHEDULE
PING_ENABLE_API_HTTP_CACH E	false	Controls the API HTTP caching feature for the run-time instance of the server. APIs are cached by default. Provide this environment variable at run time and set it to false to disable API HTTP caching for that server instance.

Example: Use an existing SSL certificate for HTTPS connections

This example shows how to provide the environment variables necessary for the Policy Editor to present a different SSL certificate than the one configured during **setup**:

```
env PING_CERT_ALIAS=<certificate-nickname> \
PING_KEYSTORE_PATH=<path-to-keystore-file> \
PING_KEYSTORE_TYPE=<PKCS12-or-JKS> \
KEYSTORE_PIN_FILE=<path-to-keystore-pin-file> \
bin/start-server
```

Example: Override the configured HTTPS port

In this example, the Policy Editor is started using an HTTPS port that differs from the value configured during installation. The override requires two environment variables: **PING_PORT** and **PING_EXTERNAL_BASE_URL**.

```
$ bin/stop-server
$ export PING_PORT=9443 PING_EXTERNAL_BASE_URL=pap.example.com:9443; bin/start-server
```

Example: Override the configured policy database location

This example changes the policy database location. The new value must be a policy server Java database connectivity (JDBC) connection string for an H2 embedded database. To use a file located at /opt/shared/Symphonic.mv.db, use the following commands:

\$ bin/stop-server

- \$ export PING_H2_FILE=/opt/shared/Symphonic
- \$ bin/setup demo {ADDITIONAL_ARGUMENTS} && bin/start-server

(i) Note

Even though the actual filename of the policy database includes the extension .mv.db, the JDBC connection string excludes the extension.

If /opt/shared/Symphonic.mv.db does not exist, **setup** creates a new one. If the file does exist and is from an older PingAuthorize server, **setup** updates the file to the latest version.

Troubleshooting startup errors

The **bin/start-server** command prints an error message if it detects that an error has occurred during startup. For more information about the error, see the logs/authorize-pe.log and logs/start-server.log files.

Stopping PingAuthorize Server

PingAuthorize Server provides a simple shutdown script to stop the server.

Steps

• To stop the PingAuthorize Server, run the **\$ bin/stop-server** command.

(i) Note

You can run **bin/stop-server** manually from the command line or within a script.

Stopping PingAuthorize Policy Editor

PingAuthorize Policy Editor provides a simple shutdown script to stop the system.

Steps

• To stop the PingAuthorize Policy Editor, run the **bin/stop-server** command.

(i) Note

You can run **bin/stop-server** manually from the command line or within a script.

Restarting PingAuthorize Server

You can stop and restart PingAuthorize Server with a single command.

About this task

Running this command is equivalent to shutting down PingAuthorize Server, exiting the Java virtual machine (JVM) session, and starting the server again.

Steps

- 1. Go to the PingAuthorize Server root directory.
- 2. Run **bin/stop-server** with the **--restart** or **-R** option.

Example:

```
$ bin/stop-server --restart
```

About the API security gateway

When you configure PingAuthorize Server for the application programming interface (API) gateway pattern, the server and gateway provide dynamic authorization management between a client and a REST API.

See the following topics for specific details about the functionality of the API security gateway.


- API gateway request and response flow
- Gateway configuration basics
- API security gateway authentication
- API security gateway policy requests
- API security gateway HTTP 1.1 support
- Gateway error templates

API gateway request and response flow

Using the application programming interface (API) gateway pattern, PingAuthorize processes JavaScript Object Notation (JSON) requests and responses in two distinct phases according to a defined sequence.

The gateway handles proxied requests in the following phases:

- Inbound phase When a client submits an API request to PingAuthorize Server, the gateway forms a policy request based on the API request and submits it to the policy decision point (PDP) for evaluation. If the policy result allows it, PingAuthorize Server forwards the inbound request to the API server.
- Outbound phase After PingAuthorize Server receives the upstream API server's response, the gateway again forms a policy request, this time based on the API server response, and submits it to the PDP. If the policy result is positive, PingAuthorize Server forwards the outbound response to the client.



The API gateway supports only JSON requests and responses.

Gateway configuration basics

You can configure the application programming interface (API) gateway architecture by creating and modifying its components.

The API security gateway consists of the following components:

- · One or more gateway HTTP servlet extensions
- · One or more gateway API endpoint
- One or more API external servers

An API external server represents the upstream API server and contains the configuration for the server's protocol scheme, host name, port, and connection security. You can create the server in the PingAuthorize administrative console, or with the following example command.

```
{pingauthorize}/bin/dsconfig create-external-server \
    --server-name "API Server" \
    --type api \
    --set base-url:https://api-service.example.com:1443
```

A gateway API endpoint represents a public path prefix that PingAuthorize Server accepts for handling proxied requests. A gateway API endpoint configuration defines the base path for receiving requests (inbound-base-path) as well as the base path for forwarding the request to the API server (outbound-base-path). It also defines the associated API external server and other properties that relate to policy processing, such as service, which targets the policy requests generated for the gateway API endpoint to specific policies.

The following example commands use the API external server from the previous example to create a pair of gateway API endpoints.

```
{pingauthorize}/bin/dsconfig create-gateway-api-endpoint \
    --endpoint-name "Consent Definitions" \
    --set inbound-base-path:/c/definitions \
    --set outbound-base-path:/consent/v1/definitions \
    --set "api-server:API Server" \
    --set service:Consent
{pingauthorize}/bin/dsconfig create-gateway-api-endpoint \
    --endpoint-name "Consent Records" \
    --set inbound-base-path:/c/consents \
    --set outbound-base-path:/consent/v1/consents \
    --set outbound-base-path:/consents \
    --set service:API Server" \
    --set service:Consent
```

The gateway HTTP servlet extension is the server component that represents the API security gateway itself. In most cases, you do not need to configure this component.

Changes to these components do not typically require a server restart to take effect. For more information about configuration options, see the *Configuration Reference*, located in the server's **docs/config-guide** directory.

API security gateway authentication

The API security gateway authenticates requests through bearer tokens by default, and you can configure it to handle authentication according to your preferences.

Although the gateway doesn't require the authentication of requests, the default policy set requires bearer token authentication.

To support this, the gateway uses the configured access token validators to evaluate bearer tokens that are included in incoming requests. The validation result is supplied to the policy request in the HttpRequest.AccessToken attribute, and the user identity associated with the token is provided in the TokenOwner attribute.

Policies use this authentication information to affect the processing of requests and responses. For example, a policy in the default policy set requires that all requests are made with an active access token.

```
Rule: Deny if HttpRequest.AccessToken.active Equals false
Statement:
   Code: denied-reason
   Applies To: Deny
   Payload: {"status":401, "message": "invalid_token", "detail":"Access token is expired or otherwise
invalid"}
```

Gateway API Endpoints include the following configuration properties to specify how client authentication is handled:

http-auth-evaluation-behavior

Determines whether the Gateway API Endpoint evaluates or modifies the HTTP authentication scheme and whether this scheme is forwarded to the API server.

This property accepts the following values:

do-not-evaluate

The Gateway API Endpoint doesn't evaluate or modify the HTTP authentication scheme. This can be useful when implementing an authentication scheme that doesn't evaluate bearer tokens, such as MTLS.

If the client request includes an **Authorization** header, the PingAuthorize Server forwards the unmodified header to the external API server.

) Note

If you specify this value, policies protecting this endpoint should not enforce constraints on request authentication, such as the validity of the access token. The default policy snapshot enforces such a constraint in the **Token Validation** policy.

evaluate-and-forward

The Gateway API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server forwards the unmodified header to the external API server unless a policy decision directs otherwise.

This value is set by default.

evaluate-and-discard

The Gateway API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server removes this header before forwarding the request to the external API server.

evaluate-and-replace

The Gateway API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server replaces this header with one containing the basic authentication credentials defined for the external API server.

🕥 Note

If you specify this value, make sure your authorization policies enforce an appropriate level of authorization for the client.

Example

```
bin/dsconfig set-gateway-api-endpoint-prop \
    --endpoint-name <your-endpoint-name> \
    --set http-auth-evaluation-behavior:evaluate-and-replace
```

In this example, the http-auth-evaluation-behavior property is set to evaluate-and-replace .

access-token-validator

Sets the access token validators that the Gateway API Endpoint uses. By default, this property has no value, and the Gateway API Endpoint can evaluate every bearer token by using each access token validator that is configured on the server. To constrain the set of access token validators that a Gateway API Endpoint uses, set this property to use one or more specific values.

If http-auth-evaluation-behavior is set to do-not-evaluate, this setting is ignored.

Example

```
bin/dsconfig set-gateway-api-endpoint-prop \
    --endpoint-name <your-endpoint-name> \
    --set access-token-validator:example-token-validator
```

In this example, the access-token-validator property is set to example-token-validator.

API security gateway policy requests

The API security gateway creates policy requests for incoming requests and API responses, and you can observe how it creates them.

Before accepting an incoming request and forwarding it to the API server, the gateway creates a policy request based on the incoming request and sends it to the policy decision point (PDP) for authorization. Before accepting an API server response and forwarding it back to the client, the gateway creates a policy request based on the incoming request and response and sends it to the PDP for authorization. An understanding of the manner in which the gateway formulates policy requests can help you create and troubleshoot policies more effectively.

You can selectively disable response policy processing on a per-API-Endpoint basis. This ability is useful if the Gateway authorizes requests but does not filter responses. Disabling this processing can improve performance for frequent requests or requests that return very large responses. To disable processing, set the Gateway API Endpoint's **disable-response-processing** property to **t rue**.

To better understand how the gateway formulates policy requests, enable detailed decision logging to view policy request attributes in action, particularly when first developing API security gateway policies. For more information, see Policy Decision Logger.

API gateway policy request attributes

There are many policy request attributes generated by the security gateway, including attributes nested within the attributes, HttpRequest.AccessToken, HttpRequest.ClientCertificate, and Gateway fields.

The following table identifies the attributes of a policy request that the gateway generates.

Policy request attributes	Description	Туре
action	Identifies the gateway request processing phase and the HTTP method, such as GET or POST. The value is formatted as <phase>- <method>. Example values include inbound-GET, inbound-POST, outbound-GET, and outbound-POST.</method></phase>	String
attributes	Identifies additional attributes that do not correspond to a specific entity type in the PingAuthorize Trust Framework. For more information about these attributes, see the following table.	Object
domain	Unused.	String
identityProvider	Identifies the access token validator that evaluates the bearer token used in an incoming request.	String

Policy request attributes	Description	Туре
service	Identifies the API service. By default, this attribute is set to the name of the Gateway API Endpoint, which can be overridden by setting the Gateway API Endpoint's service property. Multiple Gateway API Endpoints can use the same service value.	String

The following table identifies the additional attributes that are included in **attributes**.

Attribute	Description	Туре
Gateway	Provides additional gateway-specific information about the request not provided by the following attributes.	Object
HttpRequest.AccessToken	Parsed access token. For more information, see the following table.	Object
HttpRequest.ClientCertificate	Properties of the client certificate, if one was used.	Object
HttpRequest.CorrelationId	A unique value that identifies the request and response, if available.	String
HttpRequest.IPAddress	The client IP address.	String
HttpRequest.QueryParameters	Request URI query parameters.	Object
HttpRequest.RequestBody	The request body, if available	Object
HttpRequest.RequestHeaders	The HTTP request headers.	Object
HttpRequest.RequestURI	The request URI.	String
HttpRequest.ResourcePath	Portion of the request URI path following the inbound base path that the Gateway API Endpoint defines.	String
HttpRequest.ResponseBody	The response body, if available. This attribute is provided only for outbound policy requests.	Object
HttpRequest.ResponseHeaders	The HTTP response headers, if available.	Object
HttpRequest.ResponseStatus	The HTTP response status code, if available.	Number
Token0wner	The access token subject as a SCIM resource, as obtained by the access token validator.	Object

The access token validator populates the HttpRequest.AccessToken attribute, which contains the fields in the following table. These fields correspond approximately to the fields that the IETF Token Introspection specification (RFC 7662 ^C) defines.

Attribute	Description	Туре
access_token	The actual access token from the client request.	String
active	Indicates whether this access token is currently active, as determined by the access token validator.	Boolean
audience	Identifies the recipients for whom the access token is intended. Typically, the authorization server sets this field to indicate the resource servers that might accept the token.	Array
client_id	The client ID of the application that was granted the access token.	String
expiration	Date and time at which the access token expires.	DateTime
issued_at	Date and time at which the access token was issued.	DateTime
issuer	Token issuer. This attribute is usually a URI that identifies the authorization server.	String
not_before	Date and time before which a resource server does not accept the access token.	DateTime
scope	Identifies the list of scopes granted to this token.	Collection
subject	Token subject. This attribute is a user identifier that the authorization server sets.	String
token_owner	User identifier that was resolved by the access token validator's token resource lookup method. This attribute is always a SCIM ID of the form <resource type="">/<resource id="">.</resource></resource>	String

Attribute	Description	Туре
token_type	The token type, as set by the authorization server. This value is typically set to bearer .	String
user_token	Flag that the access token validator sets to indicate that the token was issued originally to a subject. If this flag is fals e , the token does not have a subject and was issued directly to a client.	Boolean
username	Subject's user name. This attribute is a user identifier that the authorization server sets.	String

The following table identifies the fields that the HttpRequest.ClientCertificate attribute contains.

Attribute	Description	Туре
algorithm	Name of the certificate signature algorithm, such as SHA256withRSA .	String
algorithmOID	Signature algorithm OID.	String
issuer	Distinguished name (DN) of the certificate issuer.	String
notAfter	Expiration date and time of the certificate.	DateTime
notBefore	Earliest date on which the certificate is considered valid.	DateTime
subject	DN of the certificate subject.	String
subjectRegex	Regular expression that must be matched by the subject field of the certificate to ensure that the certificate belongs to the requesting client.	String
valid	Indicates whether the certificate is valid.	Boolean

The following table identifies the fields that the Gateway attribute contains.

Attribute	Description	Туре
_BasePath	Portion of the HTTP request URI that matches the Gateway API Endpoint's in bound-base-path value.	String
_TrailingPath	Portion of the HTTP request URI that follows the _BasePath .	String
base path parameters	Parameters used in a Gateway API Endpoint's inbound-base-path configuration property are included as fields of the Gateway attribute.	String
custom attribute	The Gateway attribute might contain multiple arbitrary custom attributes that are defined by the policy-request-attribute of the Gateway API Endpoint configuration.	String

Gateway API Endpoint configuration properties that affect policy requests

The following table identifies Gateway API Endpoint properties that might force the inclusion of additional attributes in a policy request.

Gateway API Endpoint property	Description
inbound-base-path	Defines the URI path prefix that the gateway uses to determine whether the Gateway API Endpoint handles a request. The inbound-base-path property value can include parameters. If parameters are found and matched, they are included as attributes to policy requests. The following configuration properties reference parameters that the inbound-base-path introduces: • outbound-base-path • service • resource-path • policy-request-attribute
service	Identifies the API service to the PDP. The service value appears in the policy request as the servic e attribute. If undefined, the service value defaults to the name of the Gateway API Endpoint.

Gateway API Endpoint property	Description
resource-path	Identifies the REST resource to the PDP. The resource path value appears in the policy request as the HttpRequest.ResourcePath attribute. If undefined, the resource path value defaults to the portion of the request that follows the base path defined by inbound-base-path.
policy-request-attribute	Defines zero or more static, arbitrary key-value pairs. If specified, key-value pairs are always added as attributes to policy requests. These custom attributes appear in the policy request as fields of the Gateway attribute. For example, if a value of policy- request-attribute is foo=bar, the attribute Gateway.foo is added to the policy request with a value of bar.

API gateway path parameters

The **inbound-base-path** property value can include parameters. If parameters are found and matched, they are included in policy requests as fields of the **Gateway** policy request attribute.

xref:paz_gw_api_endpoint_config_parms.adoc[] identifies additional configuration properties that can use these
parameters.

You must introduce parameters by the **inbound-base-path** property. Other configuration properties cannot introduce new parameters.

Basic example

The following example configuration demonstrates how request URIs are mapped to the outbound path to alter policy requests.

Gateway API Endpoint property	Example value
inbound-base-path	/accounts/{accountId}/transactions
outbound-base-path	/api/v1/accounts/{accountId}/transactions
policy-request-attribute	foo=bar

A request URI with the path /accounts/XYZ/transactions/1234 matches the inbound base path and is mapped to the outbound path /api/v1/accounts/XYZ/transactions/1234.

The following properties are added to the policy request:

- HttpRequest.ResourcePath : 1234
- Gateway.accountId : XYZ

• Gateway.foo : bar

Advanced example

Request URIs are mapped to the outbound path to alter policy requests.

Consider the following example configuration.

Gateway API Endpoint property	Example value
inbound-base-path	<pre>/health/{tenant}/{resourceType}</pre>
outbound-base-path	/api/v1/health/{tenant}/{resourceType}
service	HealthAPI.{resourceType}
resource-path	<pre>{resourceType}/{_TrailingPath}</pre>

A request URI with the path /health/OmniCorp/patients/1234 matches the inbound base path and is mapped to the outbound path /api/v1/health/OmniCorp/patients/1234.

The following properties are added to the policy request:

- service : HealthAPI.patients
- HttpRequest.ResourcePath : patients/1234
- Gateway.tenant : OmniCorp
- Gateway.resourceType : patients

API security gateway HTTP 1.1 support

In its capacity as a reverse proxy, the API security gateway must modify HTTP requests and responses in addition to the changes required by policy processing.

Forwarded HTTP request headers

HTTP requests often pass through a chain of intermediaries before reaching a destination server. The HTTP 1.1 specifications define two categories of headers that are pertinent to this context.

End-to-end headers

Headers requiring transmission to all recipients on the chain, such as Content-Type .

Hop-by-hop headers

Headers that are only relevant to the next recipient on the chain, such as Connection and Keep-Alive.

The API security gateway never forwards hop-by-hop headers. It generally forwards all end-to-end headers, with the following exceptions:

- Headers related to HTTP resource versioning and conditional requests, such as If-None-Match and If-Modified-Since, are never forwarded.
- Headers related to CORS, such as Origin or Access-Control-Request-Method, are never forwarded.
- Headers that you exclude by using the **allowed-headers** configuration property of an API External Server to define an allow list of forwarded headers.
- Headers that you remove by using a custom statement extension.

The API security gateway always adds the Host, Accept-Encoding, Via, X-Forwarded-For, X-Forwarded-Host, X-Forwarded-Port, and X-Forwarded-Proto headers to forwarded requests. If the HTTP Connection Handler is configured to use or generate correlation IDs, then a correlation ID header is also added to the forwarded request.

You can use the http-auth-evaluation-behavior property of a Gateway API Endpoint to alter the Authorization header of a forwarded request.

Forwarded HTTP response headers

The API security gateway forwards most HTTP response headers, with the following exceptions:

- The Date header is replaced with a value generated by the API security gateway.
- The **Content-Length** header is replaced with a value generated by the API security gateway.
- The Location header is replaced with a value generated by the API security gateway.
- If the HTTP Connection Handler is configured to use or generate correlation IDs, then a correlation ID header is added to the response.
- Headers related to HTTP resource versioning and conditional requests, such as ETag and Last-Modified, are never forwarded.
- Headers related to CORS, such as Access-Control-Allow-Origin or Access-Control-Allow-Headers, are never forwarded.

Unsupported HTTP request header

The API security gateway does not support the Upgrade header.

Unsupported statement changes

The API security gateway does not support using statements to add, modify, or delete the following headers:

- Hop-by-hop headers that the gateway always removes, such as Connection and Keep-Alive
- · Conditional request headers that the gateway always removes, such as If-None-Match and ETag
- Proxy-specific headers that the gateway always adds, such as Via and X-Forwarded-For

The gateway overrides any changes to these headers.

Gateway error templates

REST API clients are often written with the expectation that the API produces a custom error format. Some clients might fail unexpectedly if they encounter an error response that uses an unexpected format.

When a REST API is proxied by PingAuthorize Server, errors that the REST API returns are forwarded to the client as is, unless a policy dictates a modification of the response. In the following scenarios, PingAuthorize Server returns a gateway-generated error:

- When the policy evaluation results in a deny response. This scenario typically results in a 403 error.
- When an internal error occurs in the gateway, or when the gateway cannot contact the REST API service. This scenario typically results in a 500, 502, or 504 error.

By default, these responses use a simple error format, as in the following example:

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

The following table describes this default error format.

Field	Туре	Description
errorMessage	String	Error message
status	Number	HTTP status code

Because some REST API clients expect a specific error response format, PingAuthorize Server provides a facility for responding with custom errors, called error templates. An error template is written in Velocity Template Language and defines the manner in which a Gateway API Endpoint produces error responses.

Error templates feature the following context parameters.

Parameter	Туре	Description
status	Integer	HTTP status
message	String	Exception message
requestURI	String	Original Request URI
requestQueryParams	Object	Query parameters as JSON object
headers	Object	Request headers as JSON object
correlationID	String	Request correlation ID

For more information, see Sideband error templates.

Configuring error templates example

The example in this section demonstrates the configuration of a custom error template for a Gateway API Endpoint named **Test** API.

About this task

Error responses that use this error template feature the following fields:

- code
- message

Steps

1. Create a file named error-template.vtl with the following contents:

```
#set ($code = "UNEXPECTED_ERROR")
#if($status == 403)
#set ($code = "ACCESS_FAILED")
#end
{
    "code":"$code",
    "message":"$message"
}
```

2. Add the error template to the configuration, as follows:

```
dsconfig create-error-template \
    --template-name "Custom Error Template" \
    --set "velocity-template<error-template.vtl"</pre>
```

3. Assign the error template to the Gateway API Endpoint, as follows:

```
dsconfig set-gateway-api-endpoint-prop \
    --endpoint-name "Test API" \
    --set "error-template:Custom Error Template"
```

(i) Note

The error template is used whenever the gateway generates an error in response to a request.

Example:

A policy **deny** results in a response like the following example:

About the Sideband API

The sideband application programming interface (API) provides dynamic authorization management for requests and responses and returns them in a potentially modified form, which the API gateway forwards to the backend REST API or the client.

As a gateway, PingAuthorize Server functions as a reverse proxy that performs the following steps:


- Intercepts client traffic to a backend REST API service
- Authorizes the traffic to a policy decision point (PDP) that operates either within the PingAuthorize process, called embedded PDP mode, or outside the PingAuthorize process, called external PDP mode

Using the sideband API, you can configure the PingAuthorize Server instead as an adapter to an external API gateway. In sideband mode, an API gateway integration point intercepts client traffic to a backend REST API service and passes intercepted traffic to the PingAuthorize sideband API.

API gateway integration

Enable attribute-based access control (ABAC) through your application programming interface (API) gateway by installing the PingAuthorize API integration adapter (where supported) and connecting to the Sideband API.

For more information on specific API gateway integrations, see **PingAuthorize Integrations**.



Copyright © 2025 Ping Identity Corporation

Processing steps

- 1. When the API gateway receives a request from an API gateway adapter, it makes a call to the Sideband API to process the request.
- 2. The Sideband API returns a response that contains a modified version of the HTTP client's request.

The API gateway forwards the response to the REST API.

3. If the Sideband API returns a response that indicates the request is unauthorized or not to be forwarded, the response includes the response to be returned to the client.

The API gateway returns the response to the client without forwarding the request to the REST API.

- 4. When the API gateway receives a response from the REST API, it makes a call to the Sideband API to process the response.
- 5. The Sideband API returns a response that contains a modified version of the REST API's response.

The API gateway forwards the response to the client.

Sideband API configuration basics

The sideband application programming interface (API) provides fine-grained access control to supported third-party API gateways through an API integration.

The sideband API consists of the following components.

Sideband API Shared Secrets

Defines the authentication credential that the sideband API might require an API gateway adapter to present. For more information, see Authenticating to the Sideband API.

Sideband API HTTP Servlet Extension

Represents the sideband API itself. If you require shared secrets, you might need to configure this component. For more information, see Authenticating to the Sideband API.

Sideband API Endpoints

Represents a public path prefix that the sideband API accepts for handling proxied requests. A sideband API endpoint configuration defines the following items:

- The base path (base-path) for requests that the sideband API accepts
- Properties that relate to policy processing, such as **service**, which targets the policy requests that are generated for the sideband API endpoint to specific policies

PingAuthorize Server's default configuration includes a default sideband API endpoint that accepts all API requests and generates policy requests for the service **Default**. To customize policy requests further, an administrator can create additional sideband API endpoints. For more information about using the sideband API endpoint configuration to customize policy requests, see **Sideband API policy requests**.

(i) Note

Changes to these components do not typically require a server restart to take effect. For more information, see the *Configuration Reference*, located in the server's **docs/config-guide** directory.

Example

The following example commands create a pair of sideband API endpoints that target specific requests to a consent service.

```
{pingauthorize}/bin/dsconfig create-sideband-api-endpoint \
    --endpoint-name "Consent Definitions" \
    --set base-path:/c/definitions \
    --set service:Consent

{pingauthorize}/bin/dsconfig create-sideband-api-endpoint \
    --endpoint-name "Consent Records" \
    --set base-path:/c/consents \
    --set service:Consent
```

Authenticating to the Sideband API

The Sideband API can require an API gateway plugin to authenticate to it by using a shared secret.

To define shared secrets, use Sideband API Shared Secret configuration objects. To manage shared secrets, use the Sideband API HTTP Servlet Extension.

Creating a shared secret

Define the authentication credentials that the Sideband API might require an API gateway plugin to present.

Steps

1. To create a shared secret, run the following example dsconfig command, substituting values of your choosing.

Example:

```
{pingauthorize}/bin/dsconfig create-sideband-api-shared-secret \
    --secret-name "Shared Secret A" \
    --set "shared-secret:secret123"
```

(i) Note

- The **shared-secret** property sets the value that the Sideband API requires the API gateway plugin to present. After you set this value, it is no longer visible.
 - The secret-name property is a label that allows an administrator to distinguish one Sideband API Shared Secret from another.
- 2. To update the shared-secrets property, run the following example dsconfig command.

Example:

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "Sideband API" \
    --add "shared-secrets:Shared Secret A"
```

A new Sideband API Shared Secret is not used until the **shared-secrets** property of the Sideband API HTTP Servlet Extension is updated.

Deleting a shared secret

You can remove a shared secret from use or delete it entirely.

Steps

• To remove a Sideband API Shared Secret from use, run the following example **dsconfig** command, substituting values of your choosing.

Example:

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "Sideband API" \
    --remove "shared-secrets:Shared Secret A"
```

• To delete a Sideband API Shared Secret, run the following example dsconfig command.

Example:

```
{pingauthorize}/bin/dsconfig delete-sideband-api-shared-secret \
    --secret-name "Shared Secret A"
```

Rotating shared secrets

To avoid service interruptions, the Sideband API allows multiple, distinct shared secrets to be accepted at the same time.

About this task

You can configure a new shared secret that the Sideband API accepts alongside an existing shared secret. This allows time to update the API gateway plugin to use the new shared secret.

Steps

- 1. Create a new Sideband API Shared Secret and assign it to the Sideband API HTTP Servlet Extension. For more information, see Creating a shared secret.
- 2. Update the API gateway plugin to use the new shared secret.
- 3. Remove the previous Sideband API Shared Secret. For more information, see Deleting a shared secret.

Customizing the shared secret header

By default, the Sideband API accepts a shared secret from an API gateway plugin through the CLIENT-TOKEN header.

Steps

• To customize a shared secret header, change the value of the Sideband API HTTP Servlet Extension's shared-secretheader property.

Example:

The following command changes the shared secret header to x-shared-secret :

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "Sideband API" \
    --set shared-secret-header-name:x-shared-secret
```

The following command resets the shared secret header to its default value:

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "Sideband API" \
    --reset shared-secret-header-name
```

API server request authentication

As with the API security gateway, API server requests authorized by the Sideband API don't require authentication. However, the default policy set requires bearer token authentication.

The Sideband API uses configured Access Token Validators to evaluate bearer tokens that are included in incoming requests. The HttpRequest.AccessToken attribute supplies the validation result to the policy request, and the TokenOwner attribute provides the user identity that is associated with the token.

Policies use this authentication information to affect the processing requests and responses. For example, the following policy in the default policy set requires all requests to be made with an active access token:

```
Rule: Deny if HttpRequest.AccessToken.active Equals false
Statement:
   Code: denied-reason
   Applies To: Deny
   Payload: {"status":401, "message": "invalid_token", "detail":"Access token is expired or otherwise
invalid"}
```

Sideband API Endpoints include the following configuration properties to specify how client authentication is handled:

http-auth-evaluation-behavior

Determines whether the Sideband API Endpoint evaluates or modifies the HTTP authentication scheme and whether this scheme is forwarded to the API server through the API gateway.

This property accepts the following values:

do-not-evaluate

The Sideband API Endpoint doesn't evaluate or modify the HTTP authentication scheme. This can be useful when implementing an authentication scheme that doesn't evaluate bearer tokens, such as MTLS.

If the client request includes an **Authorization** header, the PingAuthorize Server forwards the unmodified header to the external API server through the API gateway.

🕥 Note

If you specify this value, policies protecting this endpoint should not enforce constraints on request authentication, such as the validity of the access token. The default policy snapshot enforces such a constraint in the **Token Validation** policy.

evaluate-and-forward

The Sideband API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server forwards the unmodified header to the external API server through the API gateway unless a policy decision directs otherwise.

This value is set by default.

evaluate-and-discard

The Sideband API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server removes this header before forwarding the request to the external API server through the API gateway.

evaluate-and-replace

The Sideband API Endpoint evaluates the provided authentication credentials and makes authentication information available for policy evaluation. If the client request includes an **Authorization** header, the PingAuthorize Server replaces this header with one containing the basic authentication credentials defined for the external API server.

i) Note

If you specify this value, make sure your authorization policies enforce an appropriate level of authorization for the client.

Example

```
bin/dsconfig set-sideband-api-endpoint-prop \
    --endpoint-name <your-endpoint-name> \
    --set http-auth-evaluation-behavior:evaluate-and-replace
```

In this example, the http-auth-evaluation-behavior property is set to evaluate-and-replace .

access-token-validator

Sets the access token validators that the Sideband API Endpoint uses. By default, this property has no value, and the Sideband API Endpoint can evaluate every bearer token by using each access token validator that is configured on the server. To constrain the set of access token validators that a Sideband API Endpoint uses, set this property to use one or more specific values.

If http-auth-evaluation-behavior is set to do-not-evaluate, this setting is ignored.

```
Example
bin/dsconfig set-sideband-api-endpoint-prop \
    --endpoint-name <your-endpoint-name> \
    --set access-token-validator:example-token-validator
```

In this example, the access-token-validator property is set to example-token-validator.

Sideband API policy requests

Understanding how the Sideband API formulates policy requests can help you create and troubleshoot policies more effectively.

To authorize an incoming request, the Sideband API performs the following steps:

- · Creates a policy request that is based on the incoming request
- Sends the policy request to the Policy Decision Point (PDP) for evaluation

Sideband API policy request attributes

The following tables provide an overview of policy request attributes.

Policy request attributes are associated with a policy request that the Sideband API generates.

Attribute	Description	Туре
action	Identifies the request-processing phase and the HTTP method, such as GET or POST . The value is formatted as <phase>- <method> . Example values include inbo und-GET , inbound-POST , outbound- GET , and outbound-POST .</method></phase>	String
attributes	Additional attributes that do not correspond to a specific entity type in the Trust Framework. For more information, see the next table.	Object

Attribute	Description	Туре
domain	Unused.	String
identityProvider	Name of the Access Token Validator that evaluates the bearer token in an incoming request.	String
service	Identifies the API service. By default, this value is set to the name of the Sideband API Endpoint. To override the default value, set the Sideband API Endpoint's service property. Multiple Sideband API Endpoints can use the same service value.	String

The following table identifies the additional attributes that are included in **attributes**.

Attribute	Description	Туре
Gateway	Additional gateway-specific information about the request not provided by the following attributes.	Object
HttpRequest.AccessToken	Parsed access token. For more information, see the following table.	Object
HttpRequest.ClientCertificate	Properties of the client certificate, if one was used.	Object
HttpRequest.CorrelationId	A unique value that identifies the request and response, if available.	String
HttpRequest.IPAddress	The client IP address.	String
HttpRequest.QueryParameters	Request URI query parameters.	Object
HttpRequest.RequestBody	The request body, if available.	Object
HttpRequest.RequestHeaders	The HTTP request headers.	Object
HttpRequest.RequestURI	The request URI.	String
HttpRequest.ResourcePath	Portion of the request URI path that follows the inbound base path that the Sideband API Endpoint defines.	String
HttpRequest.ResponseBody	The response body, if available. This attribute is provided only for outbound policy requests.	Object

Attribute	Description	Туре
HttpRequest.ResponseHeaders	The HTTP response headers, if available.	Object
HttpRequest.ResponseStatus	The HTTP response status code, if available.	Number
Token0wner	The access token subject as a SCIM resource, as obtained by the access token validator.	Object

(i) Note

When handling an outbound response, HTTP request data is only available if specifically provided by the API gateway plugin.

The following table identifies the fields that are associated with the HttpRequest.AccessToken attribute, which is populated by the access token validator.

(i) Note

These fields correspond approximately to the fields that are defined by the IETF Token Introspection specification, RFC 7662^[2].

Attribute	Description	Туре
access_token	The actual access token from the client request.	String
active	Indicates whether this access token is currently active, as determined by the access token validator.	Boolean
audience	Identifies the recipients for whom the access token is intended. Typically, the authorization server sets this field to identify the resource servers that can accept the token.	Array
client_id	Client ID of the application that was granted the access token.	String
expiration	Date and time at which the access token expired.	DateTime
issued_at	Date and time at which the access token was issued.	DateTime
issuer	Token issuer. Typically, this value is a URI that identifies the authorization server.	String

Attribute	Description	Туре
not_before	Date and time before which a resource server does not accept an access token.	DateTime
scope	Identifies the list of scopes granted to this token.	Collection
subject	Token subject. This value represents a user identifier that the authorization server sets.	String
token_owner	User identifier that was resolved by the access token validator's token resource lookup method. This value is always a SCIM ID of the form <resource type="">/ <resource id="">.</resource></resource>	String
token_type	Token type, as set by the authorization server. Typically, this value is bearer .	String
user_token	Flag that the access token validator sets to indicate the token was originally issued to a subject. If the flag is false, the token contains no subject and was issued directly to a client.	Boolean
username	Subject's user name. This value represents a user identifier that the authorization server sets.	String

The following table identifies the fields that the HttpRequest.ClientCertificate attribute can contain.

Attribute	Description	Туре
algorithm	Name of the certificate signature algorithm, such as SHA256withRSA .	String
algorithmOID	Signature algorithm OID.	String
issuer	Distinguished name (DN) of the certificate issuer.	String
notAfter	Expiration date and time of the certificate.	DateTime
notBefore	Earliest date on which the certificate is considered valid.	DateTime

Attribute	Description	Туре
subject	DN of the certificate subject.	String
subjectRegex	Regular expression that must be matched by the subject field of the certificate to ensure that the certificate belongs to the requesting client.	String
valid	Indicates whether the SSL client certificate is valid.	Boolean

The following table identifies the fields that the **Gateway** attribute can contain.

Attribute	Description	Туре
_BasePath	Portion of the HTTP request URI that matches the Sideband API Endpoint's base-path value.	String
_TrailingPath	Portion of the HTTP request URI that follows the _BasePath .	String
base path parameters	Parameters in a Sideband API Endpoint's base-path configuration property are included as fields of the Gateway attribute.	String
base path parameters	The Gateway attribute can contain multiple, arbitrary custom attributes that are defined by the policy-request-attribute of the Sideband API Endpoint configuration.	String

Sideband API Endpoint configuration properties

The following table identifies Sideband API Endpoint properties that might force the inclusion of additional attributes with the policy request.

Property	Description
base-path	Defines the URI path prefix that the Sideband API uses to determine whether the Sideband API Endpoint handles a request. The base-path property value can include parameters. If parameters are found and matched, they are included as attributes to policy requests. The following configuration properties can reference parameters that base-path introduces: • service • resource-path • policy-request-attribute
service	Identifies the API service to the PDP. A policy can use this value to target requests. The service value appears in the policy request as the service attribute. If undefined, the service value defaults to the name of the Sideband API Endpoint.
resource-path	Identifies the REST resource to the PDP. The resource path value appears in the policy request as the HttpRequest.ResourcePath attribute. If undefined, the reso urce-path value defaults to the portion of the request that follows the base path, as defined by base-path.
policy-request-attribute	Defines zero or more static, arbitrary key-value pairs. If specified, the pairs are always added as attributes to policy requests. These custom attributes appear in the policy request as fields of the Gateway attribute. For example, if a value of policy- request-attribute is foo=bar, the attribute Gateway.foo is added to the policy request with the value bar.

Sideband API path parameters

If parameters are found and matched for the base-path property, they are included in policy requests as fields of the Gateway policy request attribute.

Other configuration properties can use these parameters. For more information, see Sideband API Endpoint configuration properties.

The **base-path** property must introduce parameters. Other configuration properties cannot introduce new parameters.

Basic example

The following table demonstrates a basic configuration of path parameters.

API Endpoint property	Example value
base-path	/accounts/{accountId}/transactions
policy-request-attribute	foo=bar

A request URI with the path /accounts/XYZ/transactions/1234 matches the example base-path value.

The following properties are added to the policy request:

- HttpRequest.ResourcePath : 1234
- Gateway.accountId : XYZ
- Gateway.foo : bar

Advanced example

The following table demonstrates an advanced configuration of path parameters.

API Endpoint property	Example value
base-path	<pre>/health/{tenant}/{resourceType}</pre>
service	HealthAPI.{resourceType}
resource-path	<pre>{resourceType}/{_TrailingPath}</pre>

A request URI with the path /health/OmniCorp/patients/1234 matches the example base-path value.

The following properties are added to the policy request:

- service : HealthAPI.patients
- HttpRequest.ResourcePath : patients/1234
- Gateway.tenant : OmniCorp
- Gateway.resourceType : patients

Request context configuration

The API gateway plugin provides data and metadata to the Sideband API about HTTP requests received from a client and HTTP responses received from an API server.

When the Sideband API handles an API server's HTTP response, you can enable the API gateway plugin to also provide data and metadata for the original HTTP request, which can be used to make policy decisions. For example, data about access token claims and the token owner are request data, but they might be useful when authorizing an HTTP response.

The Sideband API provides two methods to supply HTTP request data during HTTP response processing. Select a method according to the API gateway plugin's capabilities. By default, both methods are disabled. You can enable them by configuring the request-context-method property of the Sideband API HTTP Servlet Extension.

Request context using the state field

When enabled, the Sideband API adds a **state** field to its responses for inbound HTTP requests. This field contains an encoded form of the request data, including preprocessed authentication data, such as access token claims and token owner attributes. The API gateway plugin is expected to provide this state data when it next makes a request corresponding to the outbound HTTP response. The Sideband API can then pass this data about the HTTP request in its policy request.

As the state data includes preprocessed authentication information, this information can be made available for policy processing without the overhead of re-invoking an access token validator. However, the size of the state data is proportional to the size of the original HTTP request.

To enable this option, use the following command:

```
{pingauthorize}/bin/dsconfig \
   set-http-servlet-extension-prop \
   --extension-name "Sideband API" \
   --set request-context-method:state
```

Request context using the request field

When enabled, an API gateway plugin making a request to handle an outbound HTTP response provides all data about the original HTTP request in the **request** field. If this data includes an **Authorization** header with a bearer token, the Sideband API invokes its access token validators to produce a set of access token claims and token owner attributes, which are then made available in the policy request.

To enable this option, use the following command:

```
{pingauthorize}/bin/dsconfig \
   set-http-servlet-extension-prop \
   --extension-name "Sideband API" \
   --set request-context-method:request
```

Disabling request context handling

The request context feature is disabled by default. If you have enabled it, you can disable it with the following command:

```
{pingauthorize}/bin/dsconfig \
   set-http-servlet-extension-prop \
   --extension-name "Sideband API" \
   --reset request-context-method
```

Sideband access token validation

HTTP requests often include an access token with an Authorization header using the bearer token scheme, as described by RFC 6750^[2].

By default, if a Sideband API request contains an Authorization header, the Sideband API processes the access token as follows:

- An access token validator parses and validates the access token, and the Sideband API adds the access token parsed claims to the policy request's HttpRequest.AccessToken field.
- If the access token has a subject, a token resource lookup method retrieves the subject's attributes, and the Sideband API adds them to the policy request's TokenOwner field.

In some cases, the parsing and validation performed by the access token validator might duplicate processing already performed by the API gateway itself. To eliminate redundant processing, you can configure a Sideband API endpoint to use an external API gateway access token validator, which is a unique access token validator that performs no parsing or validation of its own. The API gateway plugin might then pass the parsed access token claims directly to the Sideband API, which would ignore the **Authorization** header and accept the parsed access token claims as-is.

Example configuration

The following example shows how to configure an external API gateway access token validator with a token resource lookup method and assign it to an existing Sideband API endpoint:

```
dsconfig create-access-token-validator \
    --validator-name "API Gateway Access Token Validator" \
    --type external-api-gateway \
    --set enabled:true \
    --set evaluation-order-index:0
dsconfig create-token-resource-lookup-method \
    --validator-name "API Gateway Access Token Validator" \
    --method-name "Users by uid" \
    --type scim \
    --set scim-resource-type:Users \
    --set 'match-filter:uid eq "%sub%"' \
    --set evaluation-order-index:0
dsconfig set-sideband-api-endpoint-prop \
    --endpoint-name "My API" \
    --set "access-token-validator:API Gateway-Provided Access Token Validator"
```

Sideband error templates

REST API clients often expect a custom error format that the API produces. Some clients might fail unexpectedly if they encounter an error response that uses an unexpected format.

When PingAuthorize Server proxies a REST API, it forwards errors that the API returns to the client as they are, unless a policy dictates modifications to the response. In the following scenarios, PingAuthorize Server returns an error that the Sideband API generates:

- The policy evaluation results in a deny response. This typically results in a 403 error.
- An internal error occurs in the Sideband API. This typically results in a 500 error.

By default, these responses use a simple error format, as shown in the following example:

```
{
    "errorMessage": "Access Denied",
    "status": 403
}
```

The following table describes the default error format.

Field	Туре	Description
errorMessage	String	Error message
status	Number	HTTP status code

Because some REST API clients expect a specific error-response format, PingAuthorize Server provides error templates to respond with custom errors. Error templates, which are written in Velocity Template Language^[2], define the manner in which a Sideband API Endpoint produces error responses.

The following table identifies the context parameters that are provided with error templates.

Parameter	Туре	Description
status	Integer	HTTP status
message	String	Exception message

Example: Configure error templates

This example demonstrates the configuration of a custom error template for a Sideband API Endpoint called Test API.

The following fields are associated with the error responses that use this error template:

- code
- message

To create the error template, perform the following steps:

1. Create a file named error-template.vtl with the following contents:

```
#set ($code = "UNEXPECTED_ERROR")
#if($status == 403)
#set ($code = "ACCESS_FAILED")
#end
{
    "code":"$code",
    "message":"$message"
}
```

2. Add the error template to the configuration.

```
dsconfig create-error-template \
    --template-name "Custom Error Template" \
    --set "velocity-template<error-template.vtl"</pre>
```

3. Assign the error template to the Sideband API Endpoint.

```
dsconfig set-sideband-api-endpoint-prop \
    --endpoint-name "Test API" \
    --set "error-template:Custom Error Template"
```

The error template is used whenever the Sideband API generates an error in response to a request.

About the SCIM service

PingAuthorize Server's built-in System for Cross-domain Identity Management (SCIM) service provides a REST API for data that is stored in one or more external datastores, based on the SCIM 2.0 standard \square .

For information about the SCIM service, see the following topics:


- SCIM API request and response flow
- SCIM configuration basics
- SCIM endpoints
- SCIM authentication
- SCIM policy requests
- Lookthrough limit for SCIM searches
- Disabling the SCIM REST API

SCIM API request and response flow

The System for Cross-domain Identity Management (SCIM) REST API provides an HTTP API for data contained in a user store.

Although user stores typically consist of a single datastore, such as PingDirectory Server, they can also consist of multiple datastores.

When a SCIM request is received, it is translated into one or more requests to the user store, and the resulting user store response is translated into a SCIM response. The SCIM response is authorized by sending a policy request to the policy decision point (PDP). Depending on the policy result, including the statements that are returned in the result, the SCIM response might be filtered or rejected.



SCIM configuration basics

PingAuthorize Server's System for Cross-domain Identity Management (SCIM) subsystem consists of the following components.

SCIM resource types

SCIM resource types define a class of resources, such as users or devices. Every SCIM resource type features at least one SCIM schema, which defines the attributes and subattributes that are available to each resource, and at least one store adapter, which handles datastore interactions.

The following SCIM resource types differ according to the definitions of the SCIM schema:

• Mapping SCIM resource type – Requires an explicitly defined SCIM schema, with explicitly defined mappings of SCIM attributes to store adapter attributes. Use a mapping SCIM resource type to exercise detailed control over the SCIM schema, its attributes, and its mappings.

• Pass-through SCIM resource type – Does not use an explicitly defined SCIM schema. Instead, an implicit schema is generated dynamically, based on the schema that is reported by the store adapter. Use a pass-through SCIM resource type when you need to get started quickly.

SCIM schemas

SCIM schemas define a collection of SCIM attributes, grouped under an identifier called a schema URN. Each SCIM resource type possesses a single core schema and can feature schema extensions, which act as secondary attribute groupings that the schema URN namespaces. SCIM schemas are defined independently of SCIM resource types, and multiple SCIM resource types can use a single SCIM schema as a core schema or schema extension.

(i) Note

A SCIM attribute defines an attribute that is available under a SCIM schema. The configuration for a SCIM attribute defines its data type, regardless of whether it is required, single-valued, or multi-valued. Because it consists of SCIM subattributes, a SCIM attribute can be defined as a complex attribute.

Store adapters

Store adapters act as a bridge between PingAuthorize Server's SCIM system and an external datastore. PingAuthorize Server provides a built-in LDAP store adapter to support LDAP datastores, including PingDirectory Server and PingDirectoryProxy Server. The LDAP store adapter uses a configurable load-balancing algorithm to spread the load among multiple directory servers. Use the Server SDK to create store adapters for arbitrary datastore types.

Each SCIM resource type features a primary store adapter and can also define multiple secondary store adapters. Secondary store adapters allow a single SCIM resource to consist of attributes retrieved from multiple datastores.

Store adapter mappings define the manner in which a SCIM resource type maps the attributes in its SCIM schemas to native attributes of the datastore.

About the create-initial-config tool

The create-initial-config tool helps to quickly configure PingAuthorize Server for the System for Cross-domain Identity Management (SCIM).

Run this tool after completing setup to configure a SCIM resource type named **Users**, along with a related configuration.

For an example of using create-initial-config to create a pass-through SCIM resource type, see Configuring the PingAuthorize user store.

Example: Mapped SCIM resource type for devices

This example demonstrates the addition of a simple mapped SCIM resource type, backed by the standard **device** object class of a PingDirectory Server.

To add data to PingDirectory Server, create a file named devices.ldif with the following contents:

```
dn: ou=Devices,dc=example,dc=com
objectClass: top
objectClass: organizationalUnit
ou: Devices
dn: cn=device.0,ou=Devices,dc=example,dc=com
objectClass: top
objectClass: device
cn: device.0
description: Description for device.0
dn: cn=device.1,ou=Devices,dc=example,dc=com
objectClass: top
objectClass: top
objectClass: device
cn: device.1
```

Use the ldapmodify tool to load the data file.

description: Description for device.1

```
{pingdir}/bin/ldapmodify --defaultAdd --filename devices.ldif
```

Start configuring PingAuthorize Server by adding a store adapter.

```
dsconfig create-store-adapter \
    --adapter-name DeviceStoreAdapter \
    --type ldap \
    --set enabled:true \
    --set "load-balancing-algorithm:User Store LBA" \
    --set structural-ldap-objectclass:device \
    --set include-base-dn:ou=devices,dc=example,dc=com \
    --set include-operational-attribute:createTimestamp \
    --set include-operational-attribute:modifyTimestamp \
    --set create-dn-pattern:entryUUID=server-generated,ou=devices,dc=example,dc=com
```

The previous command creates a store adapter that handles LDAP entries found under the base DN ou=devices, dc=example, dc=com with the object class device. This example uses the user store load-balancing algorithm that is created when you use the create-initial-config tool to set up a users SCIM resource type.

The following command creates a SCIM schema for devices with the schema URN urn:pingidentity:schemas:Device:1.0:

```
dsconfig create-scim-schema \
    --schema-name urn:pingidentity:schemas:Device:1.0 \
    --set display-name:Device
```

Under this schema, add the string attributes name and description.

```
dsconfig create-scim-attribute \
    --schema-name urn:pingidentity:schemas:Device:1.0 \
    --attribute-name name \
    --set required:true
dsconfig create-scim-attribute \
    --schema-name urn:pingidentity:schemas:Device:1.0 \
    --attribute-name description
```

After you create a store adapter and schema, create the SCIM resource type.

```
dsconfig create-scim-resource-type \
    --type-name Devices \
    --type mapping \
    --set enabled:true \
    --set endpoint:Devices \
    --set primary-store-adapter:DeviceStoreAdapter \
    --set lookthrough-limit:500 \
    --set core-schema:urn:pingidentity:schemas:Device:1.0
```

Map the two SCIM attributes to the corresponding LDAP attributes. The following commands map the SCIM name attribute to the LDAP cn attribute, and map the SCIM description attribute to the LDAP description attribute:

```
dsconfig create-store-adapter-mapping \
    --type-name Devices \
    --mapping-name name \
    --set scim-resource-type-attribute:name \
    --set store-adapter-attribute:cn \
    --set searchable:true

dsconfig create-store-adapter-mapping \
    --type-name Devices \
    --mapping-name description \
    --set scim-resource-type-attribute:description \
    --set store-adapter-attribute:description \
```

To confirm that the new resource type has been added, send the following request to the SCIM resource types endpoint:

curl -k https://localhost:8443/scim/v2/ResourceTypes/Devices

The response is:

```
{"schemas":["urn:ietf:params:scim:schemas:core:2.0:ResourceType"],"id":"Devices","name":
"Devices","endpoint":"Devices","schema":"urn:pingidentity:schemas:Device:1.0",
"meta":{"resourceType":"ResourceType","location":"https://localhost:8443/scim/v2/ResourceTypes/Devices"}}
```

For a more advanced example of a mapped SCIM resource type, see the example User schema in PingAuthorize/resource/ starter-schemas.

SCIM endpoints

The following table identifies the endpoints that the System for Cross-domain Identity Management (SCIM) 2.0 REST API provides.

Endpoint	Description	Supported HTTP methods
/ServiceProviderConfig	Provides metadata that indicates the PingAuthorize Server authentication scheme, which is always OAuth 2.0, and its support for features that the SCIM standard considers optional. This endpoint is a metadata endpoint and is not subject to policy processing.	GET
/Schemas	Lists the SCIM schemas that are configured for use on PingAuthorize Server and that define the various attributes available to resource types. This endpoint is a metadata endpoint and is not subject to policy processing.	GET
/Schemas/ <schema></schema>	Retrieves a specific SCIM schema, as specified by its ID. This endpoint is a metadata endpoint and is not subject to policy processing.	GET
/ResourceTypes	Lists all of the SCIM resource types that are configured for use on PingAuthorize Server. Clients can use this information to determine the endpoint, core schema, and extension schemas of any resource types that the server supports. This endpoint is a metadata endpoint and is not subject to policy processing.	GET
/ResourceTypes/ <resourcetype></resourcetype>	Retrieves a specific SCIM resource type, as specified by its ID. This endpoint is a metadata endpoint and is not subject to policy processing.	GET
/ <resourcetype></resourcetype>	Creates a new resource (POST), or lists and filters resources (GET).	GET, POST
/ <resourcetype>/.search</resourcetype>	Lists and filters resources.	POST
<pre>/<resourcetype>/<resourceid></resourceid></resourcetype></pre>	Retrieves a single resource (GET), modifies a single resource (PUT, PATCH), or deletes a single resource (DELETE).	GET, PUT, PATCH, DELETE
/Me	Alias for the resource that the subject of the access token identifies. Retrieves the resource (GET), modifies the resource (PUT, PATCH), or deletes the (DELETE).	GET, PUT, PATCH, DELETE

SCIM authentication

You must authenticate all System for Cross-domain Identity Management (SCIM) requests using OAuth 2.0 bearer token authentication.

Bearer tokens are evaluated using access token validators. The HttpRequest.AccessToken attribute supplies the validation result to the policy request, and the TokenOwner attribute provides the user identity associated with the token. Policies use this authentication information to affect the processing of requests and responses.

SCIM policy requests

For every System for Cross-domain Identity Management (SCIM) request or response, one or more policy requests are sent to the policy decision point (PDP) for authorization.

Policies can use a policy request's **action** value to determine the processing phase and to act accordingly. Understanding how the SCIM service formulates policy requests will help you to create and troubleshoot policies more effectively.

Most SCIM operations are authorized in the following phases:

- 1. The operation itself is authorized.
- 2. The outgoing response is authorized with the **retrieve** action.

In most cases, you can reuse policies that target the **retrieve** action to specify read-access control rules. You can disable this **retrieve** action for a SCIM Resource Type if policies are only used for authorization before the operation. To do so, set the SCIM Resource Type's **disable-response-processing** property to **true**. The resource is then returned as-is after the operation completes. This property also affects SCIM searches.

Operation	Actions
POST /scim/v2/ <resourcetype></resourcetype>	create, retrieve
<pre>GET /scim/v2/<resourcetype>/<resourceid></resourceid></resourcetype></pre>	retrieve
<pre>PUT /scim/v2/<resourcetype>/<resourceid> PATCH /scim/v2/<resourcetype>/<resourceid></resourceid></resourcetype></resourceid></resourcetype></pre>	modify, retrieve
<pre>DELETE /scim/v2/<resourcetype>/<resourceid></resourceid></resourcetype></pre>	delete
GET /scim/v2/ <resourcetype> POST /scim/v2/<resourcetype>/.search</resourcetype></resourcetype>	<pre>search , retrieve -OR- search , search-results For more information about authorizing searches, see About SCIM searches.</pre>

Enable detailed decision logging and view all policy request attributes in action, particularly when learning how to develop SCIM policies. For more information, see **Policy Decision Logger**.

SCIM policy request attributes

The following tables describe policy request attributes and their functions.

The following table identifies the attributes associated with a policy request that the System for Cross-domain Identity Management (SCIM) service generates.

Policy request attribute	Description	Туре
action	<pre>Identifies the SCIM request as one of the following types:</pre>	String
attributes	Additional attributes that do not correspond to a specific entity type in the PingAuthorize Trust Framework. For more information, see the following table.	Object
domain	Unused.	String
identityProvider	Name of the access token validator that evaluates the bearer token used in an incoming request.	String
service	Identifies the SCIM service and resource type using a value of the form SCIM2. <resource type="">. For example, for a request using the "Users" resource type, the service value would be SCIM2.Users.</resource>	String

The following table identifies the additional attributes that are included in attributes.

Attribute	Description	Туре
HttpRequest.AccessToken	Parsed access token. For more information, see the following table.	Object
HttpRequest.ClientCertificate	Properties of the client certificate, if one is used.	Object
HttpRequest.CorrelationId	A unique value that identifies the request and response, if available.	String
HttpRequest.IPAddress	The client IP address.	String
HttpRequest.QueryParameters	Request URI query parameters.	Object

Attribute	Description	Туре
HttpRequest.RequestBody	The request body, if available. This attribute is available for POST, PUT, and PATCH requests.	Object
HttpRequest.RequestHeaders	The HTTP request headers.	Object
HttpRequest.RequestURI	The request URI.	String
HttpRequest.ResourcePath	Uniquely identifies the SCIM resource that is being requested, in the format <resource type="">/<scim id="">, as the following example shows: Users/0450b8db-f055-35d8-8e2f-0f203a291cd1</scim></resource>	String
HttpRequest.ResponseBody	The response body, if available. This attribute is provided only for outbound policy requests.	Object
HttpRequest.ResponseHeaders	The HTTP response headers, if available.	Object
HttpRequest.ResponseStatus	The HTTP response status code, if available.	Number
impactedAttributes	Provides the set of attributes that the request modifies.	Collection
SCIM2	Provides additional, SCIM2-specific information about the request.	Object
Token0wner	Access token subject as a SCIM resource, as obtained by the access token validator.	Object

The access token validator populates the HttpRequest.AccessToken attribute, which contains the fields in the following table. These fields correspond approximately to the fields that the IETF Token Introspection specification (RFC 7662^[]) defines.

Attribute	Description	Туре
access_token	The actual access token from the client request.	String
active	Indicates whether this access token is currently active, as determined by the access token validator.	Boolean
audience	Identifies the recipients for whom the access token is intended. Typically, the authorization server sets this field to indicate the resource servers that might accept the token.	Array
client_id	The client ID of the application that was granted the access token.	String
expiration	Date and time at which the access token expires.	DateTime
issued_at	Date and time at which the access token was issued.	DateTime

Attribute	Description	Туре
issuer	Token issuer. This attribute is usually a URI that identifies the authorization server.	String
not_before	Date and time before which a resource server does not accept the access token.	DateTime
scope	Identifies the list of scopes granted to this token.	Collection
subject	Token subject. This attribute is a user identifier that the authorization server sets.	String
token_owner	User identifier that was resolved by the access token validator's token resource lookup method. This attribute is always a SCIM ID of the form <resource type="">/<resource id=""></resource></resource> .	String
token_type	The token type, as set by the authorization server. This value is typically set to bearer .	String
user_token	Flag that the access token validator sets to indicate that the token was issued originally to a subject. If this flag is <code>false</code> , the token does not have a subject and was issued directly to a client.	Boolean
username	Subject's user name. This attribute is a user identifier that the authorization server sets.	String

The following table identifies the fields that the HttpRequest.ClientCertificate attribute contains.

Attribute	Description	Туре
algorithm	Name of the certificate signature algorithm, such as SHA256withRSA.	String
algorithmOID	Signature algorithm OID.	String
issuer	Distinguished name (DN) of the certificate issuer.	String
notAfter	Expiration date and time of the certificate.	DateTime
notBefore	Earliest date on which the certificate is considered valid.	DateTime
subject	DN of the certificate subject.	String
subjectRegex	Regular expression that must be matched by the subject field of the certificate to ensure that the certificate belongs to the requesting client.	String
valid	Indicates whether the certificate is valid.	Boolean

The following table identifies the fields that the **SCIM2** attribute contains.

Attribute	Description	Туре
modifications	Contains a normalized SCIM 2 PATCH request object that represents all of the changes to apply. This attribute is available for PUT and PATCH requests.	Object
resource	Complete SCIM resource that the request targets. This attribute is available for GET, PUT, PATCH, and DELETE requests. The resource attribute is also available in the policy requests that are performed for each matching SCIM resource in a search result. For more information, see About SCIM searches.	Object

About SCIM searches

Search requests are used to return System for Cross-domain Identity Management (SCIM) resources. You can constrain search requests using filters.

A request that potentially causes the return of multiple SCIM resources is considered a search request. Perform such requests in one of the following manners:

- Make a GET request to /scim/v2/<resourceType>.
- Make a POST request to /scim/v2/<resourceType>/.search.

To constrain the search results, clients should supply a search filter through the filter parameter. For example, a GET request to /scim/v2/Users?filter=st+eq+"TX" returns all SCIM resources of the Users resource type in which the st attribute possesses a value of "TX". Additionally, the Add Filter policy can add a filter automatically to search requests.

SCIM search policy processing

SCIM policy processing involves denying or modifying a search request and then filtering the results.

Policy processing for System for Cross-domain Identity Management (SCIM) searches occurs in the following phases:

- 1. Policies deny or modify a search request. For more information, see Search request authorization.
- 2. Policies filter the search result set. For more information, see Search response authorization.

Search request authorization

In the first phase, a policy request is issued for the search itself, using the **search** action. If the policy result is **deny**, the search is not performed. Otherwise, statements in the policy result are applied to the search filter, giving statements a chance to alter the filter.

i Νote

You can only use statement types that are written specifically for the **search** action. For example, you can use the Add Filter statement type to constrain the scope of a search.

You can also use the Combine SCIM Search Authorizations statement type at this point. If you use this statement, search results are authorized by using a special mode, described in Search response authorization.

Search response authorization

After a search is performed, the resulting **search** response is authorized in one of three ways: default authorization, optimized search response authorization, and no authorization.

Default authorization

The default authorization mode simplifies policy design but can generate a large number of policy requests. For every System for Cross-domain Identity Management (SCIM) resource that the search returns, a policy request is issued by using the **retrieve** action. If the policy result is **deny**, the SCIM resource is removed from the search response. Otherwise, statements in the policy result are applied to the SCIM resource, which gives statements a chance to alter the resource. Because the **retrieve** action is used, policies that are already written for single-resource **GET** operations are reused and applied to the search response.

Optimized search response authorization

If the search request policy result includes the Combine SCIM Search Authorizations statement type, an optimized authorization mode is used instead. This mode reduces the number of overall policy requests but might require a careful policy design. Instead of generating a policy request for each SCIM resource that the search returns, a single policy request is generated for the entire result set. To distinguish the policy requests that this authorization mode generates, the action **search-results** is used.

Write policies that target these policy requests to accept an object that contains a Resources array with all matching results. Statements that the policy result returns are applied iteratively to each member of the result set. The input object that is provided to statements also contains a Resources array, but it contains only the single result currently under consideration.

The following JSON provides an example input object:

```
{
    "Resources": [{
        "name": "Henry Flowers",
        "id": "40424a7d-901e-45ef-a95a-7dd31e4474b0",
        "meta": {
            "location": "https://example.com/scim/v2/Users/40424a7d-901e-45ef-a95a-7dd31e4474b0",
            "resourceType": "Users"
        },
        "schemas": [
            "urn:pingidentity:schemas:store:2.0:UserStoreAdapter"
        ]
      }
    }
}
```

The optimized search response authorization mode checks policies efficiently and is typically faster than the default authorization mode. However, the optimized search response authorization mode might be less memory-efficient because the entire result set, as returned by the datastore, is loaded into memory and processed by the policy decision point (PDP).

No authorization

If you do not need policy processing for the search results on a SCIM Resource Type, such as if policies are only used for authorization before the search and not filtering the results, set that SCIM Resource Type's **disable-response-processing** property to **true**. The search results will be returned as they were received from the external server. This behavior can improve performance for requests that return large numbers of search results. This property also affects other SCIM operations.

Using paged SCIM searches

When searching large data sets, the results can be numerous and produce errors about a request matching too many results relative to the lookthrough limit. Paged searches avoid these errors and also reduce memory utilization.

Before you begin

The paged SCIM searches feature is not available for entry-balanced data sets.

To use paged SCIM searches, your SCIM service's backend servers must be LDAP directory servers and you must use the LDAP store adapter.

Complete the following one-time operations. For either command, you only need to run the command one time per backend server. If you are not sure whether you have run the command, you can run it again safely.

• Set the service account's permissions by running the **prepare-external-store** command on the PingAuthorize server for each backend server.

(i) Note

If you have run this command with PingDataGovernance 8.1.0.0 or earlier, run it again using the command from a PingDataGovernance 8.2.0.0 or a PingAuthorize 8.3.0.0 or later release.

For example:

```
$ prepare-external-store --hostname server.example.com --port 1389 \
--bindDN "cn=Directory Manager" --bindPassword <password1> \
--governanceBindDN "cn=Authorize User,cn=Root DNs,cn=config" \
--governanceBindPassword <password2> \
--userStoreBaseDN ou=people,dc=example,dc=com
```

• If your LDAP store adapter points to a PingDirectoryProxy server, run the following command on that server:

```
$ dsconfig set-request-processor-prop \
--processor-name <proxying-request-processor> \
--set supported-control-oid:2.16.840.1.113730.3.4.9 \
--set supported-control-oid:1.2.840.113556.1.4.473
```

<proxying-request-processor> is the request processor handling the entries targeted by the search.

About this task

PingAuthorize performs SCIM searches using LDAP requests. After you complete the steps below, PingAuthorize creates LDAP requests that include request controls asking the backend servers to sort and page the search results before returning the results. These request controls are marked noncritical, meaning that if the backend server cannot page the results, the backend server still returns the results. In this case, PingAuthorize handles the sorting and paging itself.

If your SCIM searches result in an error because the request matched too many results, as discussed in Lookthrough limit for SCIM searches, you can avoid the error by using paged searches.

Complete the following steps for each search:

Steps

1. Decide your SCIM search.

(i) Note

To get paged results, your search must include at least one of these parameters: startIndex, count, or sortBy.

For example, your search might look like the following:

```
https://<pingauthorize-hostname>:<pingauthorize-port>/scim/v2/Users/?filter=st eq
"TX"&sortBy=sn&sortOrder=ascending
```

Here is the corresponding encoded version:

```
https://<pingauthorize-hostname>:<pingauthorize-port>/scim/v2/Users/?
filter=st%20eq%20%22TX%22&sortBy=sn&sortOrder=ascending
```

On your PingAuthorize Server, collect some information to use later.

- 1. Given a SCIM resource type that you want to search for, find the primary LDAP store adapter that the SCIM resource type uses by looking at its **primary-store-adapter** property.
- 2. Find the corresponding adapter by running the following command:

```
$ dsconfig list-store-adapters
```

3. Find the structural-ldap-objectclass, include-base-dn, and include-filter values for the adapter by running the following command:

```
$ dsconfig get-store-adapter-prop --adapter-name <name-of-store-adapter> \
--property structural-ldap-objectclass \
--property include-base-dn \
--property include-filter
```

- 2. On each backend server, complete the following steps:
 - 1. Create a Virtual List View (VLV) index for your search.

Each SCIM search that you want to produce paged results must have its own VLV index.

Create this index using dsconfig create-local-db-vlv-index with the following options.

Option	Description
index-name	Names the index.
backend-name	Specifies the name of the local database backend in which to place the index. The default database backend for PingDirectory is userRoot.
set base-dn	Specifies the desired base dn. This value must match the value of the inc lude-base-dn property that you found in the previous step.
set scope	ls always whole-subtree.
set filter	<pre>Specifies the filter. Specify "(objectclass=<name-of-store-adapter-objectclass>)" where <name-of-store-adapter-objectclass> is the name of the objectclass used by the adapter, which you found in the previous step. If the primary LDAP store adapter has the include-filter property set, also specify that property value in the filter. For example, if the filter for the adapter objectclass is (objectclass=inetorgperson) and the inclu de-filter value is (st=CA), specify theset filter argument as "(&(objectclass=inetorgperson)(st=CA))". Specify the LDAP attributes for all the components of your SCIM search filter. For example, if a mapping SCIM resource type maps the LDAP attribute s t to the SCIM attribute address.region and the SCIM search filter requires that address.region eq TX, then this filter must include (st = TX) instead of (address.region = TX).</name-of-store-adapter-objectclass></name-of-store-adapter-objectclass></pre>
set sort-order	Specifies whether to sort ascending (+) or descending (-) and the LDAP attribute to sort by.If the SCIM search does not specify the sortBy parameter, specify the sort order as +entryUUID.

Recall the original, decoded SCIM search, shown here:

https://<pingauthorize-hostname>:<pingauthorize-port>/scim/v2/Users/?filter=st eq
"TX"&sortBy=sn&sortOrder=ascending

For example, to create a VLV index for that search, run the following command:

\$ dsconfig create-local-db-vlv-index --index-name sn \
--backend-name userRoot --set base-dn:ou=people,dc=example,dc=com \
--set scope:whole-subtree \
--set filter:"(&(objectclass=inetorgperson)(st=TX))" --set sort-order:+sn

2. Stop the server. Rebuild the index. Start the server. Run the **rebuild-index** command specifying the baseDN and the name of the index.

\$ rebuild-index --baseDN <baseDN-value> --index <name-of-index>

For example, run these commands:

```
$ stop-server
$ rebuild-index --baseDN dc=example,dc=com --index vlv.sn
$ start-server
```

3. Run your SCIM search filter.

γ Νote

The search can include only the filter you specified with **--set filter** in the earlier step without the [.codeph] (objectclass=<name-of-store-adapter-objectclass>)"`` portion.

In addition to the Virtual List View request control, PingAuthorize adds a Server Side request control to the LDAP request. These request controls require certain parameters be set. To satisfy this requirement, PingAuthorize uses the following parameters. If the client does not provide values for one of the parameters, the search uses the corresponding default value shown in the following table.

Parameter	Default
startIndex	1
count	The value of the lookthrough-limit property of the SCIM resource type being searched. That default is 500.
sortBy	entryUUID With this default, the results appear unsorted.
sortOrder	Ascending

Lookthrough limit for SCIM searches

Because a policy evaluates every System for Cross-domain Identity Management (SCIM) resource in a search result, some searches might exhaust server resources. To avoid this scenario, cap the total number of resources that a search matches.

The configuration for each SCIM resource type contains a **lookthrough-limit** property that defines this limit, with a default value of **500**. If a search request exceeds the lookthrough limit, the client receives a 400 response with an error message that resembles the following example:

```
{
   "detail": "The search request matched too many results",
   "schemas": [
        "urn:ietf:params:scim:api:messages:2.0:Error"
],
   "scimType": "tooMany",
   "status": "400"
}
```

To avoid this error, you have these options:

- The client must refine its search filter to return fewer matches.
- Configure paged searches as explained in Using paged SCIM searches.

Disabling the SCIM REST API

Disable the System for Cross-domain Identity Management (SCIM) REST API.

About this task

If you have no need to expose data through the SCIM REST API, disable it by removing the SCIM2 HTTP servlet extension from the HTTPS connection handler, or from any other HTTP connection handler, and restart the handler.

Steps

• Use the following command to remove the extension from the HTTP connection handler and restart it:

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --remove http-servlet-extension:SCIM2 \
    --set enabled:false
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set enabled:true
```

(i) Note


When the SCIM REST API is disabled, access token validators still use PingAuthorize Server's SCIM system to look up token owners.

About the SCIM user store

This topic focuses on the relationship between the PingAuthorize Server SCIM subsystem and its backend data stores, particularly LDAP directory servers.

For general information about SCIM configuration, see SCIM configuration basics.

The PingAuthorize Server SCIM 2.0 REST API and SCIM token resource lookup methods rely on external data stores, collectively called a *user store*, to locate user records. Typically, a user store is composed of a set of PingDirectory Servers, optionally fronted by a set of PingDirectoryProxy Servers. The SCIM subsystem manages communication with the user store through a *store adapter*, which translates SCIM requests into requests native to the data stores. The following diagram shows an example setup.



PingAuthorize Server includes a store adapter type for use with LDAP data stores, the *LDAP store adapter*. The LDAP store adapter manages communications to a pool of LDAP servers using a *load-balancing algorithm*. PingAuthorize Server supports two types of load-balancing algorithms.

Load-balancing algorithm type	Description
Failover load-balancing algorithm	Attempts to always send requests to the same backend LDAP server. If the preferred server is not available, then it fails over to alternate servers.
Fewest operations load-balancing algorithm	Forwards requests to the backend LDAP server with the fewest operations currently in progress. You should only use this load-balancing algorithm when all backend servers are Directory Proxy Servers.

Typically, you connect a load-balancing algorithm to its backend LDAP servers by defining *LDAP external servers* in the configuration and attaching them to the load-balancing algorithm configuration. An LDAP external server configuration manages the actual LDAP connections to a backend LDAP server, such as PingDirectory Server.

(i) Note

Alternatively, if all backend LDAP servers are PingDirectory Servers (version 8.0.0.0 and later), you can configure a load-balancing algorithm to automatically discover the backend servers. See Automatic backend LDAP server discovery.

LDAP external servers monitor and report the availability of backend LDAP servers using LDAP health checks. See LDAP health checks.

Defining the LDAP user store

You can define your user store with the external data servers using **create-initial-config**. If you need more flexibility though, you can define the LDAP store manually.

For information about these options, see:

- Defining the LDAP user store with create-initial-config
- Defining the LDAP user store manually

Defining the LDAP user store with create-initial-config

The **create-initial-config** tool provides limited support for configuring SCIM and the user store configuration needed to connect the SCIM subsystem to a set of LDAP directory servers.

This tool creates the following configuration:

- An LDAP store adapter named UserStoreAdapter
- A load-balancing algorithm named User Store LBA
- One or more LDAP external servers
- (Optional) A SCIM resource type named Users
- (Optional) SCIM schema, attributes, and attribute mappings for the Users resource type

If run interactively, **create-initial-config** walks you through the configuration process. You should be prepared to provide connection information for your directory servers.

You can also run **create-initial-config** noninteractively, which is useful when performing a scripted deployment. For an example, see **Configuring the PingAuthorize user store**.

The following table describes a key subset of the tool's command-line options.

Option	Description
governanceBindDN	The bind DN for a user account that PingAuthorize Server will use to access backend LDAP servers. Create this account using the prepare-external-store tool.
governanceBindPassword	The password for the above account.
userStore	The host, LDAP / LDAPS port, and optional location of a backend LDAP server. You can specify this option once per each backend server.
userStoreBaseDN	The base DN under which entries are stored.
userObjectClass	The structural LDAP object class of entries for the SCIM subsystem to handle if initialSchema has the none or pass-through value.
initialSchema	The SCIM schema and resource type configuration to use. Supports the following values: • pass-through Creates a pass-through SCIM resource type called Users for the LDAP object class specified by theuserObjectClass option. * user Creates a mapping SCIM resource type called Users with an example schema. For more information about this schema, see <server-root>/resource/starter-schemas/README.txt.* none Does not create a SCIM resource type.</server-root>

For more information about running create-initial-config, see its help by running the following command:

create-initial-config --help

When using **create-initial-config** noninteractively, you should also run **prepare-external-store** for each backend LDAP server. This tool creates a privileged user account on the LDAP server for use by PingAuthorize Server and configures a set of global access control instructions (ACIs) needed by this account.

Defining the LDAP user store manually

If you require more flexibility than **create-initial-config** provides, you can manually configure the SCIM subsystem and its connectivity to the LDAP user store. However, if you have not done this before, first use **create-initial-config** to generate an example configuration and then customize that configuration.

About this task

This task shows how to define two backend LDAP servers and a failover load-balancing algorithm. Also, it shows how to connect the load-balancing algorithm to an existing LDAP store adapter named UserStoreAdapter.

(i) Note

The example is simplified and does not discuss SSL connection management. When using SSL to connect to an LDAP external server, you must configure PingAuthorize Server to trust the server certificate presented by the LDAP external server using a trust manager provider.

Steps

1. Run prepare-external-store for each backend LDAP server. This tool creates a service account with the access rights needed by PingAuthorize Server.

Example:

For example:

```
prepare-external-store \
    --hostname ds1.example.com \
    --port 636 \
    --useSSL \
    --trustAll \
    --bindDN "cn=directory manager" \
    --bindPassword password \
    --governanceBindDN 'cn=Authorize User,cn=Root DNs,cn=config' \
    --governanceBindPassword password \
    --userStoreBaseDN 'ou=People,dc=example,dc=com'
```

2. Create an LDAP external server entry for each backend LDAP server. This configures how PingAuthorize Server connects to each LDAP server.

Example:

For example:

```
dsconfig create-external-server \
  --server-name DS1 \
 --type ping-identity-ds \
  --set server-host-name:ds1.example.com \
  --set server-port:636 \
  --set location:Minneapolis \
  --set 'bind-dn:cn=Authorize User, cn=Root DNs,cn=config' \
  --set password:password \
  --set connection-security:ssl \
  --set key-manager-provider:Null \
  --set trust-manager-provider:JKS
dsconfig create-external-server \
  --server-name DS2 \
 --type ping-identity-ds \
  --set server-host-name:ds2.example.com \
  --set server-port:636 \
  --set location:Minneapolis \
  --set 'bind-dn:cn=Authorize User, cn=Root DNs,cn=config' \
  --set password:password \
  --set connection-security:ssl \
  --set key-manager-provider:Null \
  --set trust-manager-provider:JKS
```

3. Create a failover load-balancing algorithm that uses the two LDAP external servers.

Example:

For example:

```
dsconfig create-load-balancing-algorithm \
    --algorithm-name 'User Store LBA' \
    --type failover \
    --set enabled:true \
    --set backend-server:DS1 \
    --set backend-server:DS2
```

4. Assign the load-balancing algorithm to an LDAP store adapter. This example assumes that the store adapter UserStoreAdapter already exists.

Example:

For example:

```
dsconfig set-store-adapter-prop \
    --adapter-name UserStoreAdapter \
    --set 'load-balancing-algorithm:User Store LBA'
```

Location management for load balancing

All PingDirectory and PingAuthorize servers have a location, which is a label that defines a group of servers with similar response time characteristics. Each location consists of a name and an optional list of preferred failover locations.

The failover and fewest operations load-balancing algorithms, discussed in About the SCIM user store, take server location into account when routing requests. By default, they always prefer LDAP backend servers in the same location as the PingAuthorize Server. If no servers are available in the same location, they will fall back to any defined failover locations.

You assign a server a location using the --location option when you run setup.

You can manage configuration-level and server-level location settings after setup as explained in the following table.

Task	Corresponding command example
Define a new location.	dsconfig create-location \ location-name Minneapolis
Define a new location with a failover location. The failover location must already exist.	dsconfig create-location \ location-name Louisville \ set preferred-failover-location:Minneapolis
Add a failover location to an existing location. The failover location must already exist.	dsconfig set-location-prop \ location-name Minneapolis \ set preferred-failover-location:Louisville
Change PingAuthorize Server's existing location by modifying the global configuration.	dsconfig set-global-configuration-prop \ set location:Minneapolis
Change a backend LDAP server's location by modifying its LDAP external server entry.	dsconfig set-external-server-prop \ server-name DS1 \ set location:Minneapolis
Configure a load-balancing algorithm to ignore backend LDAP servers' locations when deciding how to route requests.	dsconfig set-load-balancing-algorithm-prop \ algorithm-name "User Store LBA" \ set use-location:false

Automatic backend LDAP server discovery

Instead of explicitly specifying all backend LDAP servers in the configuration as LDAP external servers, you can configure PingAuthorize Server to automatically discover its backend servers.

î Important

This feature requires that all backend LDAP servers be PingDirectory Servers running version 8.0.0.0 or later. Automatic backend discovery is not supported for PingDirectoryProxy Server or third-party LDAP servers.

To configure automatic backend discovery, you must complete these tasks:

- Join the PingAuthorize Server to the same topology as the PingDirectory Servers.
- Configure the PingAuthorize Server's load-balancing algorithm with an LDAP external server template. This template provides the connection and health check settings that PingAuthorize Server uses for all PingDirectory Servers.
- Configure the topology registry entry for each PingDirectory Server to indicate the name of the PingAuthorize Server loadbalancing algorithm.

Joining a PingAuthorize Server to an existing PingDirectory Server topology

To use automatic backend discovery, the PingAuthorize Server must be a member of the same topology of each backend PingDirectory Server.

You can join a PingAuthorize Server to a PingDirectory Server topology at the time that you set it up or after setup using the manage-topology command.

For information about these options, see:

- Joining a topology at setup
- · Joining a topology with manage-topology

Joining a topology at setup

To join a new PingAuthorize Server to an existing PingDirectory Server topology during setup, provide connection information for one of the PingDirectory Servers to the **setup** tool using its --existingDSTopology* options. This PingDirectory Server must be running when you execute the **setup** tool.

The following table lists some common setup options for joining a PingDirectory Server topology. For a complete list of options, run **setup** --help.

Option	Description
existingDSTopologyHostName	The address of a PingDirectory Server instance in the topology to be joined.
existingDSTopologyPort	The LDAP / LDAPS port for communication with the PingDirectory Server to retrieve information about the topology.

Option	Description
existingDSTopologyUseSSL	Indication that the communication with the PingDirectory Server to retrieve information about the topology should be encrypted with SSL.
existingDSTopologyUseJavaTruststore	The path to a JKS trust store that has the information needed to trust the certificate presented by the PingDirectory Server when using SSL or StartTLS.
existingDSTopologyUsePkcs12Truststore	The path to a PKCS #12 trust store that has the information needed to trust the certificate presented by the PingDirectory Server when using SSL or StartTLS.
existingDSTopologyTrustStorePassword	The password needed to access the contents of the JKS or PKCS #12 trust store. A password is typically required when using a PKCS #12 trust store but is optional when using a JKS trust store.
existingDSTopologyBindDN	The DN of the account to use to authenticate to the PingDirectory Server, such as cn=Directory Manager . This account must have full read and write access to the configuration and to manage the topology.
existingDSTopologyBindPassword	The password for the account to use to authenticate to the PingDirectory Server.

Joining a topology with manage-topology

To join an existing PingAuthorize Server to an existing PingDirectory Server topology, you can use the **manage-topology addserver** command to provide connection information for one of the PingDirectory Servers. This PingDirectory Server must be running when you execute the **setup** tool.

The following table lists the options that specify connection information for a PingDirectory Server. To see this command's complete set of options, run **manage-topology add-server** --help.

Option	Description
remoteServerHostname	The address of a PingDirectory Server in the topology to be joined.
remoteServerPort	The LDAP / LDAPS port for communication with the PingDirectory Server.

Option	Description		
remoteServerConnectionSecurity	 The type of security to use when communicating with the remote server. This value can be: useSSL Indicates that the communication should be encrypted with SSL useStartTLS Indicates that the communication should be encrypted with the StartTLS extended operation noSecurity Indicates that the communication should not be encrypted 		
remoteServerBindDN	The DN of the account to use to authenticate to the PingDirectory Server, such as cn=Directory Manager . This account must be able to modify the configuration of the target server.		
remoteServerBindPassword	The password for the account to use to authenticate to the PingDirectory Server.		
remoteServerBindPasswordFile	The path to a file containing the password for the account to use to authenticate to the PingDirectory Server.		
adminUID	User ID of the topology-wide administrator. This is typically the account used to enable replication for the PingDirectory Servers.		
adminPassword	The password of the topology-wide administrator.		

Configuring a load-balancing algorithm with an LDAP external template

When using automatic backend discovery, you configure a load-balancing algorithm with a single LDAP external template instead of one or more LDAP external servers that refer to specific backend LDAP servers.

An LDAP external server template provides a load-balancing algorithm with many of the settings that it should use when communicating with a backend server that has been discovered from the topology registry. An LDAP external server template configuration object has most of the same properties as an LDAP external server configuration object but omits those related to information that it obtains from the topology registry. The omitted properties include:

- server-host-name
- server-port
- location
- connection-security

In addition, the **health-check-state** property is also not available for LDAP external server templates because it primarily applies to individual servers rather than all of the servers associated with a load-balancing algorithm.

Because the only LDAP servers that can be in the topology registry are PingDirectory Servers, most of the remaining properties in LDAP external server templates have the same default values as the corresponding properties in the Ping Identity DS External Server type. However, there are some exceptions, including the following:

- The authentication-method property has a default value of inter-server in LDAP external server templates, while it has a default value of simple in Ping Identity DS external servers. The inter-server authentication type indicates that the PingAuthorize Server should authenticate to the PingDirectory Server with a proprietary authentication method that uses inter-server certificates stored in the topology registry.
- The key-manager-provider property has a default value of Null in LDAP external server templates, while it has no default value in Ping Identity DS external servers. When using the inter-server authentication type, the topology registry is used to obtain the inter-server certificates, so no additional key manager provider is required.
- The trust-manager-provider property has a default value of JVM-Default in LDAP external server templates, while it has no default value in Ping Identity DS external servers. When using the inter-server authentication type, the topology registry is used to obtain information about the listener certificates that the servers are expected to present.

i) Note

When using automatic backend discovery, it is not necessary to run **prepare-external-store** to create a service account on each PingDirectory Server.

The following example shows how to create an LDAP external template and assign it to a new load-balancing algorithm:

```
dsconfig create-ldap-external-server-template \
    --template-name 'User Store'

dsconfig create-load-balancing-algorithm \
    --algorithm-name 'User Store LBA' \
    --type failover \
    --set enabled:true \
    --set 'ldap-external-server-template:User Store'
```

Configuring automatic backend LDAP server discovery

The following example shows how to configure a load-balancing algorithm to automatically discover backend LDAP servers. Also, it shows how to connect the load-balancing algorithm to an existing LDAP store adapter called UserStoreAdapter.

About this task

This example assumes that you have already created a topology of PingDirectory Servers and that the servers are currently available.

Steps

1. Create an LDAP external server template. This template configures how PingAuthorize Server connects to each LDAP server that it discovers. Typically, the default settings are sufficient, so this example only specifies the template name.

Example:

For example:

```
dsconfig create-ldap-external-server-template \
    --template-name 'User Store'
```

2. Create a failover load-balancing algorithm that uses the LDAP external server template.

Example:

For example:

```
dsconfig create-load-balancing-algorithm \
    --algorithm-name 'User Store LBA' \
    --type failover \
    --set enabled:true \
    --set 'ldap-external-server-template:User Store'
```

3. Assign the load-balancing algorithm to an LDAP store adapter. This example command assumes that the store adapter UserStoreAdapter already exists.

Example:

For example:

```
dsconfig set-store-adapter-prop \
    --adapter-name UserStoreAdapter \
    --set 'load-balancing-algorithm:User Store LBA'
```

4. Run manage-topology add-server to connect the PingAuthorize Server to a running PingDirectory Server.

Example:

For example:

```
manage-topology add-server \
    --remoteServerHostname ds1.example.com \
    --remoteServerPort 636 \
    --remoteServerConnectionSecurity useSSL \
    --remoteServerBindDN "cn=Directory Manager" \
    --remoteServerBindPassword password \
    --adminUID admin \
    --adminPassword password
```

5. Configure each PingDirectory Server in the topology to use PingAuthorize Server's load-balancing algorithm. You should be able to run this command from any server in the topology. The following commands configure two PingDirectory Servers with the instance names ds1 and ds2.

Example:

For example:

```
dsconfig set-server-instance-prop \
    --instance-name ds1 \
    --set 'load-balancing-algorithm-name:User Store LBA'
dsconfig set-server-instance-prop \
    --instance-name ds2 \
    --set 'load-balancing-algorithm-name:User Store LBA'
```

LDAP health checks

LDAP health checks provide information about the health and availability of the LDAP directory servers, which has a direct effect on services, such as the PingAuthorize Server System for Cross-domain Identity Management (SCIM) 2 service and the SCIM Token Resource Lookup method.

Overview

The LDAP health check component provides information about the availability of LDAP external servers. The health check result includes one of the following server states:

AVAILABLE

Completely accessible for use.

DEGRADED

The server is ready for use if necessary, but it has a condition that might make it less desirable than other servers (for example, it is slow to respond or has fallen behind in replication).

UNAVAILABLE

Completely unsuitable for use (for example, the server is offline or is missing critical data).

Health check results also include a numeric score, which has a value between 1 and 10, that can help rank servers with the same state. For example, if two servers are available, you can configure PingAuthorize Server to prefer the server with the higher score.

PingAuthorize Server periodically invokes health checks to monitor each LDAP external server. It might also initiate health checks in response to failed operations. It checks the health of the LDAP external servers at intervals configured in the LDAP server's health-check-frequency property.

The results of health checks performed by PingAuthorize Server are made available to the load-balancing algorithms to take into account when determining where to send requests. PingAuthorize Server attempts to use servers with a state of AVAILABLE before trying servers with a state of DEGRADED. It never attempts to use servers with a state of UNAVAILABLE. Some load-balancing algorithms might also take the health check score into account, such as the health-weighted load-balancing algorithm, which prefers servers with higher scores over those with lower scores. You must configure the algorithms that work best for your environment.

In some cases, an LDAP health check might define different sets of criteria for promoting and demoting the state of a server. A DEGRADED server might need to meet more stringent requirements to meet the criteria for AVAILABLE than it originally took to meet the criteria for DEGRADED. For example, if response time is used to determine the health of a server, then PingAuthorize Server might have a faster response time threshold for transitioning a server from DEGRADED.

back to AVAILABLE than the threshold used to consider it DEGRADED in the first place. This threshold difference can help avoid cases in which a server repeatedly transitions between the two states because it is operating near the threshold. For information about how to configure health checks, see **Configuring a health check using dsconfig**. To associate a health check with an LDAP external server and set the health check frequency, you must configure the **health-check** and **health-check-frequency** properties of the LDAP external server.

(i) Note

The default Consume Admin Alerts and Get Root DSE LDAP health checks apply to all LDAP external servers, even if you did not explicitly configure and add them to an LDAP external server's health-check property. To disable this behavior, reset the use-for-all-servers property for each LDAP health check. For example:

```
dsconfig set-ldap-health-check-prop \
    --check-name 'Consume Admin Alerts' \
    --reset use-for-all-servers
```

Available health checks

PingAuthorize Server provides the following LDAP health checks.

Health check	Description
Measure the response time for searches and examine the entry contents	The health check might retrieve a monitoring entry from a server and base the health check result on whether the entry was returned, how long it took to be returned, and whether the value of the returned entry matches what was expected.
Monitor the replication backlog	If a server falls too far behind in replication, then a PingAuthorize Server can stop sending requests to it. A server is classified as DEGRADED or UNAVAILABLE if the threshold is reached for the number of missing changes, the age of the oldest missing change, or both.
Consume PingAuthorize Server administrative alerts	If a PingDirectory Server indicates there is a problem, it flags itself as DEGRADED or UNAVAILABLE. When a PingAuthorize Server detects this, it stops sending requests to the server. You can configure a PingAuthorize Server to detect administrative alerts as soon as they are issued by maintaining an LDAP persistent search for changes within the cn=alerts branch of a PingDirectory Server. When PingAuthorize Server is notified by the PingDirectory Server of a new alert, it can immediately retrieve the base cn=monitor entry of the PingDirectory Server. If the cn=monitor entry has a value for the unavailable-alert-type attribute, PingAuthorize will consider the PingDirectory server UNAVAILABLE. If the cn=monitor entry has a value for the degraded-alert-type attribute, PingAuthorize will consider the PingDirectory server DEGRADED.
Monitor the busyness of the server	If a server becomes too busy, the health check might mark it as DEGRADED or UNAVAILABLE so that less heavily loaded servers are preferred.

Configuring a health check using dsconfig

Create any health check according to the following instructions.

Steps

1. Use the **dsconfig** tool to configure the LDAP external server locations.

Example:

\$ bin/dsconfig

2. Type the host name or IP address for your PingAuthorize Server, or press Enter to accept the default, localhost.

Example:

PingAuthorize Server host name or IP address [localhost]:

3. Type the number corresponding to how you want to connect to PingAuthorize, or press Enter to accept the default, LDAP.

Example:

```
How do you want to connect?

1) LDAP

2) LDAP with SSL

3) LDAP with StartTLS
```

4. Type the port number for your PingAuthorize Server, or press Enter to accept the default, 389.

Example:

```
PingAuthorize Server port number [389]:
```

5. Type the administrator's bind distinguished name (DN) or press **Enter** to accept the default (cn=Directory Manager), and then type the password.

Example:

```
Administrator user bind DN [cn=Directory Manager]:
Password for user 'cn=Directory Manager':
```

- 6. Enter the number corresponding to LDAP health checks.
 - 1. Enter the number to create a new LDAP health check, then press n to create a new health check from scratch.
- 7. Select the type of health check you want to create.

Example:

This example demonstrates the creation of a new search LDAP health check.

>>> Select the type of LDAP Health Check that you want to create:
 1) Admin Alert LDAP Health Check
 2) Custom LDAP Health Check
 3) Groovy Scripted LDAP Health Check
 4) Replication Backlog LDAP Health Check
 5) Search LDAP Health Check
 6) Third Party LDAP Health Check
 7) Work Queue Busyness LDAP Health Check
 ?) help
 c) cancel
 q) quit

8. Specify a name for the new health check.

Enter choice [c]: 5

Example:

In this example, the health check is named Get example.com.

>>>> Enter a name for the search LDAP Health Check that you want to create: Get example.com

9. Enable the new health check.

Example:

```
>>> Configuring the 'enabled' property
Indicates whether this LDAP health check is enabled for use in the server.
Select a value for the 'enabled' property:
    1) true
    2) false
    ?) help
    c) cancel
    q) quit
Enter choice [c]: 1
```

10. Configure the properties of the health check.

You might need to modify the **base-dn** property, as well as one or more response time thresholds for non-local external servers, accommodating WAN latency.

Example:

The following example is a search LDAP health check for the single entry dc=example,dc=com, which considers non-local responses of up to two seconds healthy.

>>>> Configure the properties of the Search LDAP Health Check Property Value(s) _____ 1) description _ 2) enabled true 3) use-for-all-servers false 4) base-dn "dc=example,dc=com" 5) scope base-object 6) filter (objectClass=*) 7) maximum-local-available-response-time 1 s 8) maximum-nonlocal-available-response-time 2 s 9) minimum-local-degraded-response-time 500 ms 10) minimum-nonlocal-degraded-response-time 1 s 11) maximum-local-degraded-response-time 10 s 12) maximum-nonlocal-degraded-response-time 10 s 13) minimum-local-unavailable-response-time 5 s 14) minimum-nonlocal-unavailable-response-time 5 s 15) allow-no-entries-returned true 16) allow-multiple-entries-returned true 17) available-filter 18) degraded-filter 19) unavailable-filter ?) help f) finish - create the new Search LDAP Health Check d) display the equivalent dsconfig arguments to create this object b) back q) quit

Connecting non-LDAP data stores

The PingAuthorize Server SCIM subsystem supports non-LDAP data stores using custom store adapter extensions. For more information, see the Server SDK.

Managing Server SDK Extensions

You can create extensions that use the Server SDK to add new functionality to your PingAuthorize Server.

To download the PingAuthorize Server SDK, go to the PingAuthorize downloads \square page and click the Add-ons tab.

About the Server SDK

Extension bundles are installed from a .zip archive or a file system directory. You can use the manage-extension tool to install or update any extension that is packaged using the extension bundle format. It opens and loads the extension bundle, confirms the correct extension to install, stops the server if necessary, copies the bundle to the server install root, and then restarts the server.

(i) Note

You can only use the **manage-extension** tool with Java extensions packaged using the extension bundle format. Groovy extensions do not use the extension bundle format. For more information, see the **docs/getting-started/ java-extensions.html** directory in your Server SDK download, which describes the extension bundle format and how to build an extension.

Available types of extensions

See the extension-types.html page in the docs/getting-started directory of your Server SDK build to learn more about specific extension types.

The Server SDK supports the following extensions:

Extensions	Description
Access Loggers	Record information about operations processed by the server. This includes information about connections that are established and closed, as well as whenever requests are received from clients or responses are returned to clients.
Access Token Validators	Validate access tokens submitted by client applications for access to protected HTTP resources.
Alert Handlers	Convey alert notifications generated within the server to administrators so they can take appropriate action. Alert notifications report significant errors, warnings, or events that may warrant immediate attention.
Error Loggers	Record information about events occurring in the server, including warning and error conditions, informational messages, and some limited debugging information (although most debugging information is made available through debug loggers rather than error loggers).
HTTP Operation Loggers	Record information about communication performed by HTTP clients, including requests received and responses written.
HTTP Servlet Extensions	Create servlets that perform custom processing in response to requests received from HTTP clients. HTTP Servlet Extensions can customize the paths for which they should be invoked, the set of initialization parameters, the initialization order, and an optional set of filters that may be used in conjunction with the servlet.
Key Manager Providers	Provide access to Java key managers, which you use to obtain access to a certificate that you might need to present to another system. This includes cases where the server is configured to accept connections from secure clients using SSL or StartTLS, and also when it needs to establish secure connections to other systems with a certificate for client authentication.

Extensions	Description
Manage Extensions Plugins	 Introduce custom processing at various points in the extension bundle installation process while using the manage-extension tool. You can invoke Manage Extension Plugins in the following contexts: Before any files are copied during a first-time install of the extension bundle After files are copied during a first-time install of the extension bundle Before any files are updated during the update of an installed extension bundle After all files are updated during the update of an installed extension bundle
Monitor Providers	Report information about the state of components within the server, and can be used for health-checking purposes, real-time and historical monitoring, and debugging and troubleshooting. You can use each Monitor Provider instance to generate a single monitor entity, generally with information about a single component of the server.
OAuth Token Handlers	Validate incoming SCIM requests using OAuth 2.0 bearer tokens for authentication. Implementations of this API are responsible for decoding the bearer token and checking it for authenticity and validity.
Plugins	Introduce custom processing at various points in the server life cycle or in interaction with clients. You can use Plugins to alter some content before the server performs other processing on it. For example, you can use pre-parsing Plugins to alter the content of a request read from a client or reject that request with an error.
Trust Manager Providers	Provide access to Java trust managers, which the server uses to determine whether to trust a certificate presented to it. This includes cases where a client using SSL or StartTLS presents its own certificate to the server, and also when the client needs to establish secure connections with other systems.
Advices	Carry out custom processing directives included in a policy decision result. For example, you can use an advice to add or remove response content.
Store Adapters	Serve as a native interface to a backend data store. Store Adapters are aggregated into a SCIM Resource Type in the PingAuthorize Server, which supports a SCIM front-end which can be backed by any number and type of native data stores.
Store Adapter Plugins	Perform processing on Store Adapter operations before and after those operations are processed by a Store Adapter.
Token Resource Lookup Methods	Look up the attributes of an access token owner. Using the result of Access Token Validator processing as input, a Token Resource Lookup Method can query a data store to obtain the token owner's attributes. These attributes are then made available to policies for making access control decisions.

About the Authorization Policy Decision APIs

The PingAuthorize Server provides Authorization Policy Decision APIs to support non-API use cases needing attribute-based access control (ABAC).

î Important

The Authorization Policy Decision APIs feature requires PingAuthorize Premier. For more information, contact your Ping Identity account representative.

The PingAuthorize Server's main functionality is to enforce fine-grained policies for data accessed through an application programming interface (API). However, organizations might need to use the core Policy Decision Service for non-API use cases. For example, an application server might use it to request policy decisions when generating dynamic web content. In this configuration, PingAuthorize Server becomes the policy decision point (PDP), and the application server becomes the policy enforcement point (PEP).

The Authorization Policy Decision APIs consist of the following PDP APIs:

• XACML-JSON PDP API

This API provides a standards-based interface.

Standards-based policy enforcement points request policy decisions based on a subset of the XACML-JSON standard. Learn more information in XACML 3.0 JSON Profile 1.1 ^[2].

• JSON PDP API

This API provides a simpler interface.

🕥 Note

The Authorization Policy Decision APIs can indicate when a request or response triggers statements, but the application server must implement the statement.

To make a PDP API available, you must:

- Configure the PingAuthorize Server with a feature-enabled license during setup.
- Configure the Policy Decision Point Service. Learn more in Use policies in a production environment.
- For the XACML-JSON PDP API, configure an access token validator or use token validation within your rules and policies. Learn more in Access token validators or Policy conditions.

JSON PDP API request and response flow

The JSON policy decision point (PDP) API provides an HTTP REST API for attribute-based access control based on policies configured in the PingAuthorize Server Policy Decision Service.

The JSON PDP API is implemented with an individual decision request and a batch request endpoint that consuming application servers can access using POST requests to the /governance-engine or /governance-engine/batch endpoints, respectively.

The HTTP request must include the appropriate **Content-Type** and **Accept** headers, and request bodies must be valid JSON in the expected request format.

The endpoint paths and headers are listed in the following table.


JSON PDP API Endpoint path	Action	Content-Type/Accept	Request data
/governance-engine	POST	application/json	JSON
/governance-engine/batch	POST	application/json	JSON

A successful JSON PDP API request goes through the following flow:

- 1. The client makes the JSON request, which is received by the JSON PDP API. The API forwards the request to the Policy Decision Service.
- 2. When the Policy Decision Service returns a response, the API sends the response to the client.

(i) Note

The Policy Enforcement Point (PEP) must apply any obligations or statements. Learn more about making JSON PDP API requests in the JSON PDP API Reference .



JSON PDP API request format

Individual requests

A valid JSON PDP API request is a simple JSON object that can be forwarded to the Policy Decision Service. Policies can match a decision request by Service, Domain, Action, or other attributes.

The following table describes the values contained in a valid JSON PDP API request.

Field	Туре	Required	PingAuthorize Trust Framework type	Example value
domain	string	no	Domain	Sales.Asia Pacific
action	string	no	Action	Retrieve
service	string	no	Service	Mobile.Landing page

Field	Туре	Required	PingAuthorize Trust Framework type	Example value
identityProvider	string	no	Identity Provider	Social Networks. Spacebook
attributes	map <string, string=""></string,>	yes	Other Attributes	<pre>\{"Prospect name": "B. Vo"}</pre>

<u>О</u> Тір

While the attributes value is required, you can leave it empty.

The following example shows the correct format of a JSON individual decision request.

The following image shows how **Prospect name** is defined in the Policy Administration GUI. In this example, the **Prospect name** attribute has a **Request** resolver and a **Value Settings** type of string.

		Definitions Target Se	arch										
>\$	Branch Manager	Domains Services Attribu	tes Identity Classes	Identity Providers	Identity Properties	Actions	Conditions	Processors					
•4	Trust Framework	Details											
	Policies	🏷 Prospect name											
	Test Suite												
	API Reference	Description											
		Parent	no parent select	red									
		- Resolvers (1 total)											
		• Request											
		+ Add Resolver											
		+ Value Processors (0 total)											
		 Value Settings 											
		Default value											
		Туре	String			•	Secret						
		- Caching											
		Cache Strategy	No Caching	ļ		•							
		-											

(i) Note

The Trust Framework attribute name must match with the key of the attributes map. For example, if you have an attribute named "UserID", an example value for the "attributes" object would be {"UserID":13848}.

Batch requests

Batch requests consist of an array named "requests" of JSON objects, each of which is a standard JSON PDP API single decision request.

The following example shows the correct format of a JSON batch decision request.

```
{
   "requests": [
          {
              "domain": "Sales.Asia Pacific",
              "action": "Retrieve",
              "service": "Mobile.Landing page",
              "identityProvider": "Social Networks.Spacebook",
              "attributes": {
                    "Prospect name": "B. Vo"
               }
          },
          {
              "domain": "Sales.EMEA",
              "action": "Search",
              "service": "Mobile.Users search",
              "identityProvider": "Social Networks.Chirper",
              "attributes": {
                   "Prospect name": "A. Mann"
           }
       }
   ]
}
```

JSON PDP API response format

After the Policy Decision Service determines a decision response, it hands the response back to the JSON PDP API to provide to the client. JSON PDP API responses include decisions, such as **Permit** or **Deny**, and any obligations or statements that matched during policy processing.

Individual response

The following example shows the correct JSON individual response format.

```
{
        "id": "12345678-90ab-cdef-1234-567890abcdef",
        "deploymentPackageId": "12345678-90ab-cdef-1234-567890abcdef",
        "timestamp": "2021-06-11T03:12:19.720485Z",
        "elapsedTime": 184024,
        "decision": "PERMIT",
        "authorized": true,
        "statements": [
                {
        "id": "12345678-90ab-cdef-1234-567890abcdef",
        "name": "Statement Name",
        "code": "statement-code",
        "payload": "{\"data\": \"some data\"}",
        "obligatory": true,
        "fulfilled": false,
        "attributes": { }
        }
],
        "status": {
                 "code": "OKAY",
                 "messages": [ ],
                "errors": [ ],
        }
}
```

(i) Note

The decision and authorized values identify whether the policies authorize the request, and the "statements" array contains statements to be applied by the Policy Enforcement Point.

Batch response

Batch decision responses consist of an array, named "responses", of JSON objects, each of which is a standard JSON PDP API single decision response. The decision responses are guaranteed to be returned in the same order as the received responses. For example, the first response in the batch responses corresponds to a decision on the first request in the batch requests.

The following example shows the correct JSON batch decision response format.

```
{
    "responses": [
          {
              "id": "12345678-90ab-cdef-1234-567890abcdef",
              "deploymentPackageId": "12345678-90ab-cdef-1234-567890abcdef",
              "timestamp": "2021-06-11T04:18:32.820482Z",
              "elapsedTime": 830492,
              "decision": "PERMIT",
              "authorized": true,
              "statements": [
                  {
              "id": "12345678-90ab-cdef-1234-567890abcdef",
              "name": "Advice Name",
              "code": "advice-code",
              "payload": "{\"data\": \"some data\"}",
              "obligatory": true,
              "fulfilled": false,
              "attributes": {}
                  }
              ],
              "status": {
                      "code": "OKAY",
                      "messages": [ ],
                       "errors": [ ],
                  }
         },
         {
              "id": "fedcba09-8765-4321-fedcba098765",
              "deploymentPackageId": "fedcba09-8765-4321-fedcba098765",
              "timestamp": "2021-06-11T04:18:33.650974Z",
              "elapsedTime": 492048,
              "decision": "PERMIT",
              "authorized": true,
              "statements": [
                   {
              "id": "fedcba09-8765-4321-fedcba098765",
              "name": "Different Advice",
              "code": "advice-code",
              "payload": "{\"data\": \"other data\"}",
              "obligatory": false,
              "fulfilled": false,
              "attributes": { }
                    }
        ],
        "status": {
                 "code": "OKAY",
                 "messages": [ ],
                "errors": [ ],
          }
      }
    ]
}
```

Authenticating to the JSON PDP API

The JSON PDP API can require a client to authenticate to it by using a shared secret.

To define shared secrets, use JSON PDP API Shared Secret configuration objects. To manage shared secrets, use the JSON PDP API HTTP Servlet Extension.

Creating a shared secret

Define the authentication credentials that the JSON PDP API might require a client to present.

Steps

1. To create a shared secret, run the following example **dsconfig** command, substituting values of your choosing.

Example:

```
{pingauthorize}/bin/dsconfig create-authorization-policy-decision-shared-secret \
    --secret-name "Shared Secret A" \
    --set "shared-secret:secret123"
```

(i) Note

- The **shared-secret** property sets the value that the JSON PDP API requires the client to present. After you set this value, it is no longer visible.
- The secret-name property is a label that allows an administrator to distinguish one JSON PDP API Shared Secret from another.
- 2. To update the shared-secrets property, run the following example dsconfig command.

```
Example:
```

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "JSON PDP API" \
    --add "shared-secrets:Shared Secret A"
```

A new JSON PDP API Shared Secret is not used until the **shared-secrets** property of the JSON PDP API HTTP Servlet Extension is updated.

Deleting a shared secret

You can remove a shared secret from use or delete it entirely.

Steps

• To remove a JSON PDP API Shared Secret from use, run the following example **dsconfig** command, substituting values of your choosing.

Example:

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "JSON PDP API" \
    --remove "shared-secrets:Shared Secret A"
```

• To delete a JSON PDP API Shared Secret, run the following example dsconfig command.

Example:

```
{pingauthorize}/bin/dsconfig delete-authorization-policy-decision-shared-secret \
    --secret-name "Shared Secret A"
```

Rotating shared secrets

To avoid service interruptions, the JSON PDP API allows multiple, distinct shared secrets to be accepted at the same time.

About this task

You can configure a new shared secret that the JSON PDP API accepts alongside an existing shared secret. This allows time to update the client to use the new shared secret.

Steps

- 1. Create a new JSON PDP API Shared Secret and assign it to the JSON PDP API HTTP Servlet Extension. For more information, see Creating a shared secret.
- 2. Update the client to use the new shared secret.
- 3. Remove the previous JSON PDP API Shared Secret. For more information, see Deleting a shared secret.

Customizing the shared secret header

By default, the JSON PDP API accepts a shared secret from a client through the CLIENT-TOKEN header.

Steps

• To customize a shared secret header, change the value of the JSON PDP API HTTP Servlet Extension's shared-secretheader property.

Example:

The following command changes the shared secret header to x-shared-secret.

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "JSON PDP API" \
    --set shared-secret-header-name:x-shared-secret
```

The following command resets the shared secret header to its default value.

```
{pingauthorize}/bin/dsconfig set-http-servlet-extension-prop \
    --extension-name "JSON PDP API" \
    --reset shared-secret-header-name
```

XACML-JSON PDP API request and response flow

The XACML-JSON policy decision point (PDP) API is a standards-based HTTP API used to make authorization decisions based on policies configured in the PingAuthorize Server Policy Decision Service.

The XACML-JSON PDP API is implemented as a single endpoint, which consuming application servers can access using POST requests to the **/pdp** path. The HTTP requests must include the appropriate **Content-Type** and **Accept** headers, and request bodies must adhere to the XACML-JSON standard. Learn more in **Requests**.

XACML-JSON PDP API Endpoint path	Action	Content-Type/Accept	Request data
/pdp	POST	application/xacml+json	XACML-JSON


The XACML-JSON PDP API supports the MultiRequests JSON object^[2], which allows a client to make multiple decision requests in a single HTTP request.

(i) Note

Because this object also supports single decision requests, it's the only supported XACML-JSON request format. Learn more about making XACML-JSON PDP API requests in the XACML-JSON PDP API Reference ^[2].

A successful XACML-JSON PDP API request goes through the following two-phase flow:

- 1. The client makes the XACML-JSON request, which is received by the XACML-JSON PDP API. The API converts the request to a PingAuthorize Server batch decision request and attempts to authorize the client.
- 2. When the client is successfully authorized, the request is handed off to the Policy Decision Service to process decisions in batch for the XACML-JSON PDP API. The API then converts the batch decision responses to a XACML-JSON response and writes the response to the client.



The following sections describe these stages in more detail.

Requests

The XACML-JSON PDP API first converts the XACML-JSON request to a batch decision request for the policy decision point to be consumed by the Policy Decision Service. Policies can match a decision request by **Service**, **Domain**, **Action**, or other attributes.

The following example XACML-JSON request body illustrates the conversion to a batch decision request. For an example with more than one decision request, see Example.

```
{
  "Request": {
   "MultiRequests": {
     "RequestReference": [{
       "ReferenceId": [
         "dom",
          "act",
          "srv",
          "idp",
         "att"
       ]
     }]
    },
    "AccessSubject": [{
     "Id": "dom",
     "Attribute": [{
       "AttributeId": "domain",
       "Value": "Sales.Asia Pacific"
     }]
    }],
    "Action": [{
     "Id": "act",
      "Attribute": [{
       "AttributeId": "action",
        "Value": "Retrieve"
     }]
   }],
    "Resource": [{
     "Id": "srv",
     "Attribute": [{
       "AttributeId": "service",
       "Value": "Mobile.Landing page"
     }]
    }],
    "Environment": [{
     "Id": "idp",
     "Attribute": [{
       "AttributeId": "symphonic-idp",
       "Value": "Social networks.Spacebook"
     }]
   }],
    "Category": [{
     "Id": "att",
     "Attribute": [{
       "AttributeId": "attribute:Prospect name",
       "Value": "B. Vo"
     }]
    }]
 }
}
```

The previous example shows a single decision request with the following attributes:

• A domain of Sales.Asia Pacific

- An action of Retrieve
- A service of Mobile.Landing page
- An identity provider of Social networks.Spacebook
- A single attribute named Prospect name, with a value of B. Vo

The following table shows how these values map from the Trust Framework entities to the XACML-JSON request.

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
\$.Request	<pre>\$.AccessSubject[*].Attribute[?(@.AttributeId == "domain")].Value</pre>	Domain	Sales.Asia Pacific
	<pre>\$.Action[*].Attribute[?(@.AttributeId == "action")].Value</pre>	Action	Retrieve
	<pre>\$.Resource[*].Attribute[?(@.AttributeId == "service")].Value</pre>	Service	Mobile. Landing page
	<pre>\$.Environment[*].Attribute[?(@.AttributeId == "symphonic-idp")].Value</pre>	Identity Provider	Social Networks. Spacebook
	<pre>\$.Category[*].Attribute[?(@.AttributeId == "attribute:Prospect name")].Value</pre>	Other Attribute (Prospect name in this case)	B. Vo

To illustrate how you can match rules against the **Prospect name** Trust Framework attribute, the following image shows how **Prospect name** is defined in the Policy Editor. In this example, the **Prospect name** attribute has a Request resolver and a **Value Settings Type** of String.

Branch Manager Image: Conclusion Services Attributes Identity Classes Identity Providers Identity Properties Actions Conditions Processors Policies Image: Policies Image: Test Suite Image: Policies Ima								Def	finiti	ion	s	Та	arget S	earc	ch										
Policies Test Suite API Reference Parent no parent selected Resolvers (1 total) • Request • Value Processors (0 total) • Value Settings Default value Type String • Secret • Caching	Bran	Branch Manager	ranch Ma	anager	ger		L	Don	nains	5	Servic	ces	Attrib	utes	Id	entity Clas	ses	Identity Providers	Identity Properties	Acti	ons	Conditions	F	rocessors	
Test Suite API Reference Description Parent no parent selected - Resolvers (1 total) • Request • Value Processors (0 total) • Value Settings Default value Type String Secret	Trust	rust Framewor	rust Fram	nework	ork			De	tails																
API Reference Description Parent no parent selected - Resolvers (1 total) • Request • Add Resolver • Value Processors (0 total) • Value Settings Default value Type String • Caching	Polic	Policies	olicies					5	> P	ros	pect	nar	me												
Parent no parent selected - Resolvers (1 total) • Request • Value Processors (0 total) - Value Settings Default value Type String • Caching	Test	lest Suite	est Suite																						
 Resolvers (1 total) Request Add Resolver Value Processors (0 total) Value Settings Default value Type String Secret 	API R	PI Reference	PI Referer	ence	-			Γ	Desc	cript	ion														
 Resolvers (1 total) Request Add Resolver Value Processors (0 total) Value Settings Default value Type String Secret 								ł	Pare	nt					no	parent se	ecte	d							
 Request Add Resolver Value Processors (0 total) Value Settings Default value Type String Secret 															110										
Add Resolver Value Processors (0 total) Value Settings Default value Type String Secret Caching								-	R	eso	lvers	(1 to	otal)												
 Value Processors (0 total) Value Settings Default value Type String Secret 								٠	:	F	łequ	est													
 Value Settings Default value Type String Secret 									⊢ Ad	id R	esol	ver													
Default value Type String Secret Caching								+	v	alue	e Proc	cess	ors (0 t	otal)										
Type String - Secret								-	v	alue	e Sett	tings	5												
- Caching							1			Def	ault v	alue	5												
										Тур	e					String						Secret			
Casha Stratery No Cashing								-	с	ach	ing														
Cache Strategy No Caching -										Cac	he St	trate	gy			No Cach	ing					,			

γ Νote

The Trust Framework attribute name must be a case-sensitive match with the decision request AttributeId after the attribute: prefix is removed.

Authorization

Before calculating a decision, the XACML-JSON PDP API attempts to authorize the client making the XACML-JSON PDP API request by invoking the Policy Decision Service.

A PDP authorization request can be targeted in policy as having service PDP with action authorize. The default policies included with PingAuthorize Server perform this authorization by only permitting requests with active access tokens that contain the urn:pingauthorize:pdp scope. You can see this policy in Global Decision Point \rightarrow PDP API Endpoint Policies \rightarrow Token Authorization.

(i) Note

The parent of the Token Authorization policy, PDP API Endpoint Policies, constrains the Token Authorization policy to apply to the PDP service only.

For example, under the default policies, the following request would result in an authorized client when the PDP is configured with a mock access token validator.

```
curl --insecure -X POST \
    -H 'Authorization: Bearer {"active":true,"scope":"urn:pingauthorize:pdp", "sub":"<valid-subject>"}' \
    -H 'Content-Type: application/xacml+json' \
    -d '{"Request":{}}' "https://<your-pingauthorize-host>:<your-pingauthorize-port>/pdp"
```

The default policies are intended to provide a foundation. You can modify these policies if additional authorization logic is required.

Decision processing

On successful client authorization, the XACML-JSON PDP API invokes the Policy Decision Service with the batch decision requests converted from the XACML-JSON request.

When writing policy for the XACML-JSON PDP API endpoint, you should note the mapping between the XACML-JSON schema and the PingAuthorize Server decision request. For more information, see **Requests**. After the Policy Decision Service determines a decision response, it hands the response back to the XACML-JSON PDP API to provide to the client.

Responses

The XACML-JSON PDP API converts batch decision responses to a XACML-JSON response.

XACML-JSON responses include decisions, such as **Permit** or **Deny**, and any obligations or advice that matched during policy processing.

(i) Note

The Policy Enforcement Point (PEP) must apply any obligations or advice.

The following table shows the mapping from a decision response to a XACML-JSON response.

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type
<pre>\$.Response[*]</pre>	\$.Decision	Decision
\$.Response[].		Advice (obligatory)
Obligations[]	\$.Id	Advice code
	<pre>\$.AttributeAssigments[?(@.AttributeId == "payload")].Value</pre>	Advice payload
\$.Response[].		Advice (non-obligatory)
AssociatedAdvice[]	\$.Id	Advice code
	<pre>\$.AttributeAssigments[?(@.AttributeId == "payload")].Value</pre>	Advice payload

The following example is an appropriate response based on the request in Requests.

```
{
 "Response": [{
   "Decision": "Permit",
    "Obligations": [{
     "Id": "obligation-id",
      "AttributeAssignments": [{
        "AttributeId": "payload",
        "Value": "payload-value"
     }]
   }],
    "AssociatedAdvice": [{
     "Id": "advice-id",
     "AttributeAssignments": [{
       "AttributeId": "payload",
       "Value": "payload-value"
     }]
    }]
 }]
}
```

In this example, it is up to the application server to handle the obligations and advice in the response.

Example

This example shows how to use the XACML-JSON PDP API in the context of a peer recognition program.

The example company, AnyCompany, has an internal peer recognition program. The peer recognition program allows employees to recognize each other by awarding each other points. The points can be spent in different categories. Each category requires a minimum number of points for the category to become available. When an employee spends enough points in a category, a related product becomes unlocked in an online catalog that the employee can purchase. AnyCompany has implemented a web application where employees spend their points, view their available catalog, and purchase products.

In this example, the web application that implements the online catalog can make the following XACML-JSON request when an employee spends their points. The request includes three decision requests.

```
{
   "Request":{
      "MultiRequests":{
         "RequestReference":[
            {
               "ReferenceId":[
                  "domain-1",
                  "action-1",
                  "service-1",
                  "idp-1",
                  "attributes-1"
               ]
            },
            {
               "ReferenceId":[
                  "domain-1",
                  "action-2",
                  "service-2",
                  "idp-1",
                  "attributes-2"
               ]
            },
            {
               "ReferenceId":[
                  "domain-1",
                  "action-1",
                  "service-3",
                  "idp-1",
                  "attributes-1"
               ]
            }
         ]
      },
      "AccessSubject":[
         {
            "Id":"domain-1",
            "Attribute":[
               {
                  "AttributeId":"domain",
                  "Value":"AnyCompany.Management"
               }
            1
         }
      ],
      "Action":[
         {
            "Id":"action-1",
            "Attribute":[
               {
                  "AttributeId":"action",
                  "Value":"Update"
               }
            ]
         },
         {
            "Id":"action-2",
            "Attribute":[
               {
                  "AttributeId":"action",
                  "Value":"Retrieve"
```

```
]
  }
],
"Resource":[
  {
      "Id":"service-1",
      "Attribute":[
         {
            "AttributeId":"service",
            "Value":"Peer Recognition.Point allocation"
         }
      1
   },
   {
      "Id":"service-2",
      "Attribute":[
         {
            "AttributeId":"service",
            "Value":"Peer Recognition.Points unspent"
         }
      ]
   },
   {
      "Id":"service-3",
      "Attribute":[
         {
            "AttributeId":"service",
            "Value": "Peer Recognition.Products"
         }
      1
   }
],
"Category":[
  {
      "Id":"attributes-1",
      "Attribute":[
         {
            "AttributeId":"attribute:User input.User Id",
            "Value":"self"
         },
         {
            "AttributeId":"attribute:User input.Entertainment",
            "Value":8
         },
         {
            "AttributeId":"attribute:User input.Travel",
            "Value":5
         },
         {
            "AttributeId":"attribute:User input.Academics",
            "Value":6
         },
         {
            "AttributeId":"attribute:User input.Electronics",
            "Value":5
         },
         {
            "AttributeId":"attribute:User input.Sports",
            "Value":5
         },
         {
```

```
"AttributeId":"attribute:User input.Food",
                   "Value":7
               },
                {
                   "AttributeId":"attribute:User input.Music",
                   "Value":4
               }
            ]
         },
         {
            "Id":"attributes-2",
            "Attribute":[
               {
                   "AttributeId":"attribute:User input.User Id",
                   "Value":"self"
               }
             1
         }
      ],
      "Environment":[
         {
             "Id":"idp-1",
             "Attribute":[
                {
                   "AttributeId":"symphonic-idp",
                   "Value":"AnyCompany SSO"
               }
            1
         }
      ]
   }
}
```

The three decision requests are summarized in the **RequestReference** JSON array. Each JSON object in the array contains a single field, **ReferenceId**. Each **ReferenceId** field contains an array of **Id** references that represent the content of the decision request. The following tables highlight the key components of each decision request.

(j) Note

For brevity, only one Trust Framework attribute is listed in each decision request.

First decision request

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
\$.Request. AccessSubject[*]	<pre>\$.Attribute[?(@.AttributeId == "domain")].Value</pre>	Domain	AnyCompany.Management
<pre>\$.Request.Action[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "action")].Value</pre>	Action	Update
\$.Request.Resource[*]	<pre>\$.Attribute[?(@.AttributeId == "service")].Value</pre>	Service	Peer Recognition.Point allocation

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
\$.Request. Environment[*]	<pre>\$.Attribute[?(@.AttributeId == "symphonic-idp")].Value</pre>	Identity Provider	AnyCompany SSO
\$.Request.Category[*]	<pre>\$.Attribute[?(@.AttributeId == "attribute:User input.Entertainment")]</pre>	Attribute	8

Second decision request

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
\$.Request. AccessSubject[*]	<pre>\$.Attribute[?(@.AttributeId == "domain")].Value</pre>	Domain	AnyCompany.Management
<pre>\$.Request.Action[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "action")].Value</pre>	Action	Retrieve
<pre>\$.Request.Resource[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "service")].Value</pre>	Service	Peer Recognition.Points unspent
\$.Request. Environment[*]	<pre>\$.Attribute[?(@.AttributeId == "symphonic-idp")].Value</pre>	Identity Provider	AnyCompany SSO
<pre>\$.Request.Category[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "attribute:User input.User Id")]</pre>	Attribute	self

Third decision request

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
<pre>\$.Request. AccessSubject[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "domain")].Value</pre>	Domain	AnyCompany.Management
<pre>\$.Request.Action[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "action")].Value</pre>	Action	Retrieve
<pre>\$.Request.Resource[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "service")].Value</pre>	Service	Peer Recognition.Products
<pre>\$.Request. Environment[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "symphonic-idp")].Value</pre>	Identity Provider	AnyCompany SSO

Parent (JSON Path)	Field (JSON Path)	PingAuthorize Trust Framework type	Example value
<pre>\$.Request.Category[*]</pre>	<pre>\$.Attribute[?(@.AttributeId == "attribute:User input.Travel")]</pre>	Attribute	5

The following is an example response to the previous example request.

The XACML-JSON response contains the decision responses for each of the three decision requests. The order of the decision responses corresponds to the order of the decision requests. In the first decision response, the system policy does not detect any problems and permits the employee to change her point allocation. In the second decision response, the system policy allows the employee to view her own unspent points and indicates that the value is now 0. In the third decision response, the system permits the retrieval of the employee's own product catalog and indicates which of the products should be unlocked for purchase.

Given the response, the web application can now render the content for the three decision requests. It renders the 0 unspent points and all catalog products, with purchase buttons disabled where appropriate.

```
{
 "Response": [
    {
     "Decision": "Permit",
      "Obligations": [],
      "AssociatedAdvice": []
    }, {
      "Decision": "Permit",
     "Obligations": [],
     "AssociatedAdvice": [{
       "Id": "remaining-points",
       "AttributeAssignments": [{
          "AttributeId": "payload",
          "Value": "0"
       }]
      }]
    }, {
      "Decision": "Permit",
      "Obligations": [],
      "AssociatedAdvice": [{
        "Id": "catalog",
        "AttributeAssignments": [{
          "AttributeId": "attribute:Derived.Product availability.Trip to exotic country",
          "Value": "false"
        }, {
          "AttributeId": "attribute:Derived.Product availability.Super Bowl tickets",
          "Value": "false"
        }, {
          "AttributeId": "attribute:Derived.Product availability.Movie theater gift card",
          "Value": "true"
        }, {
          "AttributeId": "attribute:Derived.Product availability.Encyclopedia subscription",
          "Value": "false"
        }, {
          "AttributeId": "attribute:Derived.Product availability.Dinner at 5-star restaurant",
          "Value": "true"
        }, {
          "AttributeId": "attribute:Derived.Product availability.Expensive laptop",
          "Value": "false"
        }, {
          "AttributeId": "payload",
          "Value": "2020-03-17T16:21:20.175132-05:00"
        }]
      }]
   }]
}
```

Policy Editor configuration

You can configure the PingAuthorize Policy Editor in several ways.

With an options file, for example, you can define policy configuration keys, a key store, or a trust store.

Also, you can set:

· Database credentials at setup or later

- SpEL Java classes to use for value processing
- The number of requests that appear in the Decision Visualizer
- HTTP caching status

Specifying custom configuration with an options file

You can configure the Policy Editor by editing and implementing the options file.

About this task

You must run **setup** in non-interactive command-line mode instead of interactive mode if you need to do any of the following:

- Configure the Policy Editor with a policy configuration key. A policy configuration key is an arbitrary key-value pair that can be referenced by name in the policy Trust Framework. This allows the policy trust store to be defined without hard-coding environment-specific data, such as host names and credentials in the trust store.
- Configure a key store for a policy information provider. This defines a client certificate that the policy engine can use for MTLS connections to a policy information provider.
- Configure a trust store for a policy information provider. This defines the set of certificates or root certificates that the policy engine uses to determine whether it trusts the server certificate presented by a policy information provider.
- Customize the Policy Editor's logging behavior.
- Configure private JSON Web Token (JWT) claims. This allows an organization to convey specific claims about an identity.

(i) Note

If the server detects existing configuration files when running the **setup** tool, the setup process terminates. To reconfigure the server, you must either:

- Delete the existing configuration files and run **setup** again.
- Use the --ignoreWarnings option with the setup tool to overwrite the existing configuration.yml file, delete the administrator key store, and, if you also use the --generateSelfSignedCertificate option, overwrite the server certificate file.

To reconfigure the server while preserving the values in configuration.yml or any certificate key stores, back up the configuration.yml and key stores before re-running setup.

Steps

1. Make a copy of the default options file provided at **config/options.yml** and customize the copy to suit your needs.

The **setup** tool supports configuring these options through the use of a YAML options file.

(i) Note

When you customize your options file, do not remove or alter the logging section. For guidance about customizing logging behavior, contact **Ping Identity Support**

- 2. Configure the Policy Editor with an options file:
 - 1. Stop the Policy Editor:

\$ bin/stop-server

- 2. Run the **setup** tool.
- 3. Provide the options file using the --optionsFile argument.

For example, the following **setup** command configures a Policy Editor in demo mode using an options file named **my-options.yml**:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

3. Start the Policy Editor:

\$ bin/start-server

Key store configuration for policy information providers

The policy engine supports the use of policy information providers (PIPs) to dynamically retrieve data from external services at runtime. You can configure a key store for a PIP in PingAuthorize.

Some policy information providers might use MTLS, in which a client presents a client certificate to establish TLS communications with a server. In such cases, the policy engine can use a client certificate contained in a Java KeyStore (JKS) or PKCS12 key store. The key store details are then configured in an options file in the **keystores** section. A JKS key store file should use the extension .jks, while a PKCS12 key store file should use the extension .p12.

Example

Given a JKS key store named my-client-cert-keystore.jks with the password password123 and a client certificate with the alias my-cert, create an options file with details about the key store.

To set up this key store, complete the following steps.

1. Make a copy of the default options file.

\$ cp config/options.yml my-options.yml

2. Edit the new options file and define the key store details by adding an item under the keystores section.

3. Stop the Policy Editor.

```
$ bin/stop-server
```

4. Run setup using the --optionsFile argument. Customize all other options as appropriate for your needs.

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor.

```
$ bin/start-server
```

After you define the policy information provider in the Trust Framework, you can refer to the key store that you configured using the name MyClientCertKeystore.

Certificate Validation				
Server (TLS)	Default 🗸			
Client (M-TLS)	v			
Keystore name	MyClientCertKeystore 🏷			
Alias	my-cert 🚫	Alias password	password123	\bigtriangledown

Example: Configure a trust store for a policy information provider

The policy engine supports the use of policy information providers (PIPs) to dynamically retrieve data from external services at runtime. You can configure a trust store for a PIP in PingAuthorize.

By default, the policy engine determines whether it should accept a PIP's server certificate using the Java Runtime Environment's (JRE's) default trust store, which contains public root certificates for common certificate authorities. If your PIP uses a server certificate issued by some other certificate authority, such as a private certificate authority operated by your organization, then you can provide a custom Java KeyStore (JKS) or PKCS12 trust store. Configure details about the trust store in an options file in the **truststores** section. A JKS trust store file should use the extension .jks , while a PKCS12 trust store file should use the extension .p12 .

Example

Given a JKS trust store named my-ca-truststore.jks with the password password123 and a trusted root certificate with the alias my-ca, create an options file with details about the trust store.

To set up this trust store, complete the following steps.

1. Make a copy of the default options file.

```
$ cp config/options.yml my-options.yml
```

2. Edit the new options file to define the key store details by adding an item under the truststores section.

```
truststores:
    - name: MyCATruststore
    resource: /path/to/my-ca-truststore.jks
    password: password123
# Other options omitted for brevity...
```

3. Run setup using the --optionsFile argument. Customize all other options as needed.

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

After you define the policy information provider in the Trust Framework, you can see the trust store that you configured using the name MyCATruststore.

Certificate Validation					
Server (TLS)	Custom	•			
Truststore name	MyCATruststore	\bigcirc			
Alias	my-ca	\bigcirc	Alias password	password123	\$
Client (M-TLS)					

Policy Editor configuration with runtime environment variables

You do not have to hard-code values for policy configuration keys in an options file in the Policy Editor configuration. You can specify values for policy configuration keys at runtime using environment variables.

To use environment variables, specify a policy configuration key value in the options file using the *\${variableName}* notation, and then define the environment variable before starting the Policy Editor.

Example: Set policy information provider URI using an environment variable

This example takes the scenario in **Define policy configuration keys in a development environment** and modifies it to specify the Consent API base URI at runtime using an environment variable.

To specify the base URI using an environment variable:

1. Make a copy of the default options file.

```
$ cp config/options.yml my-options.yml
```

2. Edit the new options file and define a policy configuration key in the core section called ConsentBaseUri. Instead of hardcoding its value, specify a variable called CONSENT_BASEURI.

```
core:
   ConsentBaseUri: ${CONSENT_BASEURI}
# Other options omitted for brevity...
```

3. Stop the GUI server.

\$ bin/stop-server

4. Run setup using the --optionsFile argument. Customize all other options as appropriate for your needs.

\$ bin/setup demo \
 --adminUsername admin \
 --generateSelfSignedCertificate \
 -decisionPointSharedSecret pingauthorize \
 -hostname <pap-hostname> \
 -port <pap-port> \
 -adminPort <admin-port> \
 -licenseKeyFile <path-to-license> \
 -optionsFile my-options.yml

5. Set the value of the CONSENT_BASEURI environment variable and then start the server.

\$ export CONSENT_BASEURI=https://consent-us-east.example.com/consent/v1; bin/start-server

To set a different host name, redefine the CONSENT_BASEURI environment variable and restart the server.

```
$ bin/stop-server
$ export CONSENT_BASEURI=https://consent-us-west.example.com/consent/v1; bin/start-server
```

Example: Set trust store details using an environment variable

This example takes the scenario in **Example: Configure a trust store for a policy information provider** and modifies it to specify the trust store password at runtime using an environment variable.

Given a Java KeyStore (JKS) trust store named my-ca-truststore.jks with the password password123 and a trusted root certificate with the alias my-ca, create an options file with details about the trust store. Instead of hard-coding the trust store password, specify it as an environment variable.

To specify the password as an environment variable:

1. Make a copy of the default options file.

\$ cp config/options.yml my-options.yml

2. To edit the new options file and define the key store details, add an item in the truststores section. Specify the password value using the \${ENVIRONMENT_VARIABLE} notation. Also, assign the password to a policy configuration key so it can be used in the Trust Framework.

```
core:
  TrustStorePassword: ${TRUST_STORE_PASSWORD}
truststores:
  - name: MyCATrustStore
    resource: /path/to/my-ca-truststore.jks
    # TRUST_STORE_PASSWORD is an environment variable
    password: ${TRUST_STORE_PASSWORD}
# Other options omitted for brevity...
```

3. Stop the Policy Editor.

```
$ bin/stop-server
```

4. Run setup using the --optionsFile argument. Customize all other options as appropriate for your needs.

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Set the value of the TRUST_STORE_PASSWORD environment variable and start the server.

\$ export TRUST_STORE_PASSWORD=password123; bin/start-server

The policy configuration key that you defined can be used in the Trust Framework. You must first create an attribute to hold the policy configuration key value. Add an attribute with the following settings.

Property	Value
Name	TrustStorePassword
Resolver Type	Configuration Key
Resolver Value	TrustStorePassword

The following image shows the attribute in the Policy Editor.

STrustStorePassword	=
Description	
Parent	no parent selected
 Resolvers (1 total) 	
 Configuration Ke Resolve attribute usin 	ry - TrustStorePassword
Resolver type C	Configuration Key

After you define the policy information provider in the Trust Framework, you can refer to the trust store password using the TrustStorePassword attribute.

Certificate Validation				
Server (TLS)	Custom	•		
Truststore name	MyCATruststore	\bigtriangledown		
Alias	my-ca	\bigtriangledown	Alias password	{{TrustStorePassword}}
Client (M-TLS)				

If you later use a trust store with a different password, you can redefine the **TRUST_STORE_PASSWORD** environment variable and restart the server.

\$ bin/stop-server	
\$ <pre>export TRUST_STORE_PASSWORD=new-password;</pre>	bin/start-server

Changing the default JWT claim for the OIDC user ID

Change the sub JSON Web Token (JWT) claim for the OpenID Connect (OIDC) user ID under the options.yml file's core section.

By default, when a user signs on to the Policy Editor with OIDC, the Policy Editor uses the sub JWT claim to:

- Extract the **sub** claim value from the ID token and:
 - Record the sub claim value in the Creator column of the Commits table when the user makes commits (see Branch Manager > Version Control).

- Make a request to the UserInfo C endpoint and:
 - Use the **sub** claim value from the response as the user data.
 - Display the user data in the upper-right corner of the Policy Editor.

If your organization wants to use a non-default claim for the OIDC user ID, such as **email**, define this claim by completing the following steps.

S Important

You must configure your OIDC provider to include the claim in both the UserInfo endpoint and the ID token for the name to display. Refer to your OIDC provider's documentation for instructions.

Steps

1. Make a copy of the default options file:

\$ cp config/options.yml my-options.yml

2. In the core section of the new options file, uncomment the example Authentication.oidcUserIdField field that uses the email claim:

```
core:
    # Use a JWT claim other than "sub" for the OIDC User ID.
    #
    # Authentication.oidcUserIdField: jwt_claim
    #
    Authentication.oidcUserIdField: "email"
```

1. (Optional): Update the email claim to your organization's preferred claim.

3. Stop the Policy Editor:



4. Run setup using the --optionsFile argument and customize all other options to meet your needs:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor:

\$ bin/start-server

- 6. In the Policy Editor, go to Branch Manager > Version Control and commit a policy change.
- 7. Verify that your claim is being used:
 - 1. Select any branch and verify that the new claim value appears in the upper-right corner of the Policy Editor.
 - 2. Verify that the new claim value appears in the **Creator** column of the **Commits** table for the commit you made in step 6.

Configuring the JWKS endpoint cache

Configure the JSON Web Key Set (JWKS) endpoint cache to manage the key set caching behavior for the Policy Editor in OIDC mode.

About this task

To improve performance, the Policy Editor is configured to cache the JWKS endpoint response indefinitely (when key set caching is enabled). Whenever the Policy Editor encounters a key ID not present in the cache, it makes a request to the JWKS endpoint, regardless of the caching configuration.

You can choose from the following configuration values. This configuration option only affects server-side behavior:

Value	Behavior
Any negative integer	Caches the key set indefinitely (default configuration)
0	Disables key set caching
Positive integer	Sets the key set cache expiry time in seconds

i) Note

In general, using the options.yml file to modify the behavior and output of setup requires restarting the Policy Editor. If you have already run setup once, provide the --ignoreWarnings option to overwrite any existing configuration files.

Doing so, however, overwrites the admin keystore and decision point shared secrets. Additionally, providing -generateSelfSignedCertificate overwrites the server keystore. Be sure to back up the admin and server keystores and your original configuration.yml file if you intend to reuse them.

Steps

1. Make a copy of the default options file:

Example:

\$ cp config/options.yml my-options.yml

Example:

- 2. In the core section of the new options file, uncomment the Authentication.oidcJwksCacheExpirySeconds field.
 - 1. Optional: Change the default value to set a cache expiry limit or disable key set caching:

This option only affects server-side behavior.
#
Authentication.oidcJwksCacheExpirySeconds: 3600

3. If necessary, stop the Policy Editor:

Example:

\$ bin/stop-server

4. Run **setup** using the **--optionsFile** argument and customize all other options as appropriate for your needs:

Example:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    -hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor and provide the OIDC well known configuration URL to the **PING_OIDC_CONFIGURATION_ENDPOINT** environment variable at startup:

Example:

```
$ env PING_OIDC_CONFIGURATION_ENDPOINT=<well-known-url> \
bin/start-server
```

(i)	Note Instead of using the OIDC well known configuration URL to provide the value for the JWKS endpoint, you can specify different values in the ui section of the new options file. Uncomment the fields as specified in the following example and set the URL values for authorizationEndpoint and jwksUri: +
	ui: authClientConfig: authWellKnownEndpoints: authorizationEndpoint: https:// <oidc-host>:<oidc-port>/as/authorize jwksUri: https://<oidc-host>:<oidc-port>/JWKS</oidc-port></oidc-host></oidc-port></oidc-host>
	If you provide a custom value for jwksUri in options.yml, omit the PING_OIDC_CONFIGURATION_ENDPOINT environment variable in this step.


Configuring Trust Framework attribute caching for development

While building and testing policies in a development environment, you can define an external attribute cache for the Trust Framework.

About this task

When you set the Policy Decision Service to external policy decision point (PDP) mode, the Policy Editor is configured by default to cache attribute values in memory on the PingAuthorize Server (for any attributes with a **defined caching strategy**). Alternatively, you can define an external attribute cache using Redis by configuring the **options.yml** file. The available Redis modes include:

- Single Redis instance
- Single Redis instance using TLS
- Replicated Redis
- Redis Sentinel
- Amazon Web Services (AWS) ElastiCache Redis



Steps

1. Make a copy of the default options file:

Example:

\$ cp config/options.yml my-options.yml

2. In the cache section of the new options file, uncomment the line provider: redis to enable the Redis caching options.

3. Uncomment the desired Redis cacheConfig block and modify it to reflect your Redis instance settings.

Example:

```
cache:
    provider:redis
    cacheConfig:
    mode: single_instance
    nodeAddresses: redis://localhost:6379
# username: <optional>
# password: <optional>
```

1. Optional: Uncomment username and password and add the appropriate values.

4. Stop the Policy Editor:

Example:

\$ bin/stop-server

5. Run **setup** using the --optionsFile argument and customize all other options as appropriate for your needs:

Example:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

6. Start the Policy Editor:

Example:

\$ bin/start-server

Configuring Policy Editor security headers

Use an options file to configure the Policy Editor.

About this task

You can configure the Policy Editor to add certain security headers to responses for calls to the UI resources in the options file's **s ecurityHeaders** section. Supported headers include X-Frame-Options, Content-Security-Policy, and Access-Control-Allow-Origin. By default, X-Frame-Options will be set to **deny** and the other headers will remain unset.

Steps

1. Make a copy of the default options file.

\$ cp config/options.yml my-options.yml

2. To configure Policy Editor security headers, edit the securityHeaders section of the new options file.

The file contains commented out examples of different security headers.

1. Duplicate the desired security header, uncomment, and modify its value according to your deployment.

(j) Note

The use of indentation in the **options.yml** file is important. When removing comment hashes, ensure that you retain valid YAML file indentation structure.

The following example illustrates the X-Frame-Options header duplicated and modified.

```
securityHeaders:
    # Configure the values that the Policy Editor will set in its
    # responses for the X-Frame-Options, Content-Security-Policy, and/or
    # Access-Control-Allow-Origin HTTP security headers here.
    #
    # X-Frame-Options: "deny"
    # Content-Security-Policy: "default-src https:"
    # Access-Control-Allow-Origin: "*"
    X-Frame-Options: "sameorigin"
```

3. Stop the Policy Editor.

```
$ bin/stop-server
```

4. Run setup using the --optionsFile argument.

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor.

\$ bin/start-server

Manage policy database credentials

By default, the PingAuthorize Policy Editor stores policies in an H2 database file on the server. You can set the initial credentials and change them later.

(i) Note

These instructions don't apply if you are using a managed RDBMS, such as PostgreSQL, instead of the default H2 database.

This embedded H2 file, stored in the server root by default, contains two user accounts:

- An admin user: Setup uses the admin user to perform database upgrades.
- An application user: The server uses the application user to access the database at runtime.

Each user has its own credentials.

🔨 Warning

If you change either of the default policy database credentials, you must pass the new credentials to **setup** when upgrading the server. Otherwise, the **setup** tool either cannot upgrade the policy database and fails (if neither default credentials work) or resets the changed credentials back to their defaults (if one of the credential pairs works). For more information about upgrades, see Upgrading PingAuthorize.

Setting database credentials at initial setup

The **setup** tool applies credentials to the policy database. Also, this tool generates the **configuration.yml** file that configures the PingAuthorize Policy Editor.

About this task

Using **setup** or environment variables, you can set credentials for both the admin user and the application user.

Because this setup is an initial setup, the Policy Editor is not running.

Steps

• Set credentials for both the admin user and the application user.

Choose from:

• Setting credentials with the **setup** tool.

Include the following options and the credential values with setup :

- --dbAdminUsername
- --dbAdminPassword
- --dbAppUsername
- --dbAppPassword

For example, the following command sets the policy database admin credentials to adminuser / Passw0rd and the policy database application credentials to appuser / S3cret.

```
bin/setup --dbAdminUsername adminuser \
    --dbAdminPassword Passw0rd \
    --dbAppUsername appuser \
    --dbAppPassword S3cret \
    --interactive
```

• Setting credentials with environment variables.

Using environment variables, you can avoid credentials showing up in process lists and command-line history.

The following example sets the policy database admin credentials to adminuser / Passw0rd and the application user credentials to app / S3cret.

```
env PING_DB_ADMIN_USERNAME=adminuser \
   PING_DB_ADMIN_PASSWORD=Passw0rd \
   PING_DB_APP_USERNAME=app \
   PING_DB_APP_PASSWORD=S3cret \
   bin/setup
```

Using environment variables at initial setup generates the configuration.yml file with the adminuser / Passw0rd credentials and the app / S3cret credentials instead of the default credentials.

For more information about these and other UNIX environment variables you can use to override configuration settings, see **Starting PingAuthorize Policy Editor**.

Changing database credentials

To change the policy database credentials after the initial setup, run the **setup** tool again.

About this task

γ Νote

Running the **setup** tool regenerates the **configuration.yml** file and regenerates any self-signed certificate keystore.

Steps

1. Stop the Policy Editor.

bin/stop-server

Run setup with the options desired from the following set and specify the new credentials. To change from the default credentials, run setup one time. To change from nondefault credentials, run setup combined by double ampersands (& &) with a second setup; in the first command, specify the current credentials for the admin user and the new credentials for the application user, and then in the second command, specify the new credentials for the admin user and the now-current credentials for the application user. See the examples.

- --dbAdminUsername
- --dbAdminPassword
- --dbAppUsername
- --dbAppPassword

The first example changes the credentials for the admin and application accounts from their defaults to admin / Passw0rd and app / S3cret, respectively.

```
setup --dbAdminUsername admin \
    --dbAdminPassword Passw0rd \
    --dbAppUsername app \
    --dbAppPassword S3cret \
    --interactive
```

--interactiv

With the credentials no longer the defaults, to change the credentials, you need two **setup** commands. The first command uses the current admin credentials (**admin / Passw0rd**) and sets new application credentials (**app** and **F0cu5**). The second command then uses the newly set application credentials (**app** and **F0cu5**) to set new admin credentials (**adm** in and **S3cure**).

```
setup --dbAdminUsername admin \
    --dbAdminPassword Passw0rd \
    --dbAppUsername app \
    --dbAppPassword F0cu5 \
    --interactive \
    && setup --dbAdminUsername admin \
    --dbAdminPassword S3cure \
    --dbAppUsername app \
    --dbAppPassword F0cu5 \
    --interactive
```

3. Start the Policy Editor.

bin/start-server

Specifying database credentials when you start the GUI

You can override database credentials for the admin account and application account in the configuration.yml file when you start the GUI by using the UNIX environment variables PING_DB_ADMIN_USER, PING_DB_ADMIN_PASSWORD, PING_DB_APP_USER, and PING_DB_APP_PASSWORD.

About this task

For more information about these and other UNIX environment variables you can use to override configuration settings, see **Starting PingAuthorize Policy Editor**.

Steps

1. Stop the Policy Editor.

bin/stop-server

2. Set the environment variables and start the Policy Editor.

Example

The following example starts the server with the overridden policy database admin credentials adminuser / Passw0rd and the overridden policy database application credentials app / S3cret. These environment variables override any values in configuration.yml.

```
env PING_DB_ADMIN_USERNAME=adminuser \
   PING_DB_ADMIN_PASSWORD=Passw0rd \
   PING_DB_APP_USER=app \
   PING_DB_APP_PASSWORD=S3cret \
   bin/start-server
```

Docker: Setting the initial database credentials

When using a Docker image, set the database credentials using UNIX environment variables. Specify the environment variables as command-line options in the **docker run** command.

Steps

- In the docker run command, specify the desired following environment variables using the --env command-line option:
 - --dbAdminUsername
 - --dbAdminPassword
 - o --dbAppUsername
 - o --dbAppPassword

Example

This example initializes the policy database with the admin credentials admin / Passw0rd and the application credentials app / S3cret . Also, it uses the Ping DevOps image.

(j) Note

Specify a separate volume to store the policy database to perform future upgrades. See Deploying PingAuthorize Policy Editor using Docker.

(i) Note

For proper communication between containers, create a Docker network using a command such as docker network create --driver <network_type> <network_name>, and then connect to that network with the --network=<network _name> option.

```
$ docker run --network=<network_name> \
```

```
--env PING_DB_ADMIN_USERNAME=admin \
```

- --env PING_DB_ADMIN_PASSWORD=Passw0rd \
- --env PING_DB_APP_USERNAME=app \
- --env PING_DB_APP_PASSWORD=S3cret \
- pingidentity/{PAP_CONTAINER_NAME}

Docker: Changing database credentials

When your Docker container uses **/opt** to store the policy database on a separate volume, you can change the database credentials.

About this task

Given that you are changing the credentials, you already have a Docker container running with a mounted volume.

Steps

- 1. Stop the Docker container.
- 2. Start the Docker container. In the **docker run** command, specify the desired following environment variables using the **--env** command-line option:
 - o --dbAdminUsername
 - --dbAdminPassword
 - o --dbAppUsername
 - o --dbAppPassword

Also specify -p, -d, --env-file, --volumes-from, and --env PING_H2_FILE.

Example

For example, if you have a container named pap with a mounted volume as shown in the example in Deploying PingAuthorize Policy Editor using Docker, the following command changes the credentials for the admin and application accounts from their default values to admin / Passw0rd and app / S3cret, respectively.

(j) Note

For proper communication between containers, create a Docker network using a command such as docker network create --driver <network_type> <network_name>, and then connect to that network with the --network=<network _name> option.

```
docker run --network=<network_name> -p 443:1443 -d \
    --env-file ~/.pingidentity/config \
    --volumes-from pap \
    --env PING_DB_ADMIN_USERNAME=admin \
    --env PING_DB_ADP_DASSWORD=Passw0rd \
    --env PING_DB_APP_USERNAME=app \
    --env PING_DB_APP_PASSWORD=S3cret \
    --env PING_BL2_FILE=/opt/out/Symphonic \
    pingidentity/{PAP_CONTAINER_NAME}:<TAG>
```

The Docker image *<TAG>* used in the example is only a placeholder. For actual tag values, see Docker Hub (https://hub.docker.com/r/pingidentity/pingauthorize^[2]).

Configuring SpEL Java classes for value processing

When you develop policies, you can use value processing to manipulate data that comes from attributes and services. One value processing option is to use the Spring Expression Language (SpEL). Because SpEL is so powerful, you might want to configure the Java classes available through SpEL to limit what users can do with it.

About this task

Use the optional AttributeProcessing.SpEL.AllowedClasses parameter in the core section of the options file to limit the Java classes available through SpEL.

γ Νote

These instructions are for configuring SpEL Java classes for use in the Policy Editor. When using embedded PDP mode, you must add Java classes to the **SpEL Allowed Class** list to use them in deployment packages. See Adding SpEL Java classes to the allowed list.

Steps

1. Make a copy of the default options file.

Example:

\$ cp config/options.yml my-options.yml

2. Edit the new options file and define AttributeProcessing.SpEL.AllowedClasses in the core section.

By default, the AttributeProcessing.SpEL.AllowedClasses parameter is not in the options file.

If AttributeProcessing.SpEL.AllowedClasses is not in the options file, all classes except those in the fixed deny-list are available. The deny-list consists of classes in these packages:

```
java.lang.*
org.springframework.expression.spel.*
```

(i) Note

The java.lang.* classes in deny-list exclude those in the allow-list defined next.

If AttributeProcessing.SpEL.AllowedClasses is in the options file without a value, only classes in the fixed allow-list are available. The allow-list consists of these classes:

java.lang.String java.util.Date java.util.UUID java.lang.Integer java.lang.Long java.lang.Double java.lang.Byte java.lang.Math java.lang.Boolean java.time.LocalDate java.time.LocalTime java.time.LocalDateTime java.time.ZonedDateTime java.time.DayOfWeek java.time.Instant java.time.temporal.ChronoUnit java.text.SimpleDateFormat java.util.Collections com.symphonicsoft.spelfunctions.RequestUtilsKt

If AttributeProcessing.SpEL.AllowedClasses is in the options file with a value, all classes in allow-list and in the value are available. Consider the following example.

```
...
core:
   AttributeProcessing.SpEL.AllowedClasses: "java.time.format.DateTimeFormatter,java.net.URLEncoder"
...
```

That setting makes the classes in allow-list available in addition to making the DataTimeFormatter and URLEncoder classes available.

3. Stop the Policy Editor.

\$ bin/stop-server

4. Run setup using the --optionsFile argument, and then customize all other options as appropriate for your needs.

Example:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret <shared-secret> \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor.

Example:

\$ bin/start-server

Setting the request list length for Decision Visualizer

In the PingAuthorize Policy Editor, you can select **Policies**, **Decision Visualizer**, and then **Recent Decisions** to view graphs of recent decisions, the times the requests were made, and the decision outcomes. The requests do not include test requests.

About this task

The **RecentRequest.buffer.size** parameter in the configuration file determines the number of recent decisions to choose from. To configure the Policy Editor to use a different value for this parameter, re-run the **setup** tool using an options file to generate a new configuration, as shown in the following steps.

Steps

1. Make a copy of the default options file.

Example:

\$ cp config/options.yml my-options.yml

2. Edit the new options file and define RecentRequest.buffer.size in the core section.

By default, the number of recent decisions is 20.

Warning

Setting a buffer size greater than 20 can cause serious performance degradation.

To disable the feature, set the value to 0.

Example:

```
core:
   RecentRequest.buffer.size: 10
# Other options omitted for brevity...
```

3. Stop the Policy Editor.

\$ bin/stop-server

4. Run setup using the --optionsFile argument, and then customize all other options as appropriate for your needs.

Example:

\$ bin/setup demo \
 --adminUsername admin \
 --generateSelfSignedCertificate \
 --decisionPointSharedSecret <shared-secret> \
 --hostname <pap-hostname> \
 --port <pap-port> \
 --adminPort <admin-port> \
 --licenseKeyFile <path-to-license> \
 --optionsFile my-options.yml

5. Start the Policy Editor.

Example:

\$ bin/start-server

HTTP caching

The Policy Editor transfers data through HTTP APIs.

To improve page loading speeds, the Policy Editor uses HTTP headers to cache the API responses for the following URLs:

- /app/trust-framework/*
- /app/policy-manager/*
- /app/test-suite/*

HTTP caching is enabled by default.

i Νote

When hosting the Policy Editor using a self-signed SSL certificate, browsers like Google Chrome and Microsoft Edge don't include the caching HTTP headers. Customers with such deployments can use a different browser, such as Mozilla Firefox, to observe the performance benefits.

You can disable HTTP caching persistently by providing the --disableApiHttpCache option when running **setup**. Caching remains disabled for future server starts and stops. The following example illustrates this option:

```
bin/setup demo \
--disableApiHttpCache \
--adminUsername admin \
--generateSelfSignedCertificate \
--decisionPointSharedSecret 2FederateM0re \
--hostname example.com \
--port 9443 \
```

--adminPort 9444

To disable HTTP caching for a single server start, provide the **PING_ENABLE_API_HTTP_CACHE= false** environment variable when running **start-server**, as illustrated in the following example:

env PING_ENABLE_API_HTTP_CACHE=false bin/start-server

í) Note

To temporarily re-enable HTTP caching after using the --disableApiHttpCache option, provide the PING_ENABLE_API _HTTP_CACHE= true environment variable when running start-server.

To persistently re-enable HTTP caching after using the --disableApiHttpCache option, delete the **setup** output (the configuration.yml file and key stores generated during **setup**). Then, reconfigure the server by running **setup**.

Policy administration

You define policies for access-control using the PingAuthorize Policy Editor.

This section covers strategies for policy development and techniques to create environment-specific Trust Framework attributes to use in your policies.

About the Trust Framework

The Trust Framework defines all the entities that your organization can use to build policies. These entities include, for example, the HTTP request attributes that describe API requests protected by PingAuthorize Server and the services that identify the REST APIs themselves.

To understand how PingAuthorize Server uses the Trust Framework, you must understand how PingAuthorize Server interacts with its policy engine, also called the policy decision point (PDP). In general, the flow is:

- 1. PingAuthorize Server receives a SCIM 2.0 or API request and translates it to a *policy request*.
- 2. PingAuthorize Server submits the policy request to the PDP for evaluation.
- 3. The PDP applies any matching policies to the policy request and then issues a policy decision.
- 4. PingAuthorize Server uses the policy decision to determine how to proceed with the request, depending on the decision result (typically PERMIT or DENY) and any statements included with the decision.

Consider these simple examples.

- A policy decision with a DENY result could cause PingAuthorize Server to reject a request because it originates from an untrusted IP address.
- A policy decision with the Exclude Attributes statement could cause PingAuthorize Server to remove specific attributes from an API response because the requesting user lacks a necessary entitlement.

Each policy request that PingAuthorize Server generates includes a specific set of attributes. These attributes vary based on the service being used. For more information, see the following topics:

- API security gateway policy requests
- Sideband API policy requests
- SCIM policy requests

Policy request structure is tightly coupled to the Trust Framework. If the Trust Framework entity definitions do not match the policy requests generated by PingAuthorize Server, then PingAuthorize Server does not function as expected. For this reason, your Trust Framework should always be based on the default policies included with the server installation package in the file resource/policies/defaultPolicies.SNAPSHOT.

For information about working with the Trust Framework to customize your organization's policies, see Trust Framework.

Trust Framework versions

The policy request structure used by PingAuthorize Server is versioned so that it can evolve across releases of the server. You configure the version in the Policy Decision Service using the trust-framework-version property. PingAuthorize Server always supports a minimum of two Trust Framework versions, the current (and preferred) Trust Framework version and the previous Trust Framework version.

When an instance of PingAuthorize Server is first installed, the Trust Framework version is undefined. The server raises an alarm to indicate this condition and to provide instructions about how to set the preferred version.

You should explicitly set the version to the preferred version. For example, the following **dsconfig** command configures the Policy Decision Service to form policy requests using Trust Framework version v2.

```
dsconfig set-policy-decision-service-prop \
    --set trust-framework-version:{TRUST_FRAMEWORK_VERSION}
```

🔿 Тір

When the Trust Framework version is set, add the configuration to the server profile that you use to deploy new server instances.

New releases of PingAuthorize Server might introduce changes to the way that the server generates policy requests, potentially in ways that are not backward-compatible with the Trust Framework and policies used in a previous release. In these cases, PingAuthorize Server will prefer the new Trust Framework version and raises an alarm with instructions to move to the new Trust Framework version. Existing policies will continue to work with the older Trust Framework version. However, the older Trust Framework version will be deprecated, so transitioning to the new Trust Framework version is imperative.

For more information about upgrading the Trust Framework version, see Upgrading the Trust Framework and policies.

Environment-specific Trust Framework attributes

With dynamic authorization, policies must be able to retrieve attributes frequently from policy information providers (PIPs) at runtime.

The services and datastores from which additional policy information is retrieved range from development and testing environments to preproduction and production environments.

For example, you might use a Trust Framework service to retrieve a user's consent from the PingDirectory Consent API. This service depends on the URL of the Consent API, the username and password that are used for authentication, and other items that vary between development, preproduction, and production environments.

About policy configuration keys

To avoid hard-coding values such as URLs, usernames, or passwords, Trust Framework attributes can refer to policy configuration keys, which are key/value pairs defined outside of the Trust Framework and provided to the policy engine at runtime.

To define a Trust Framework attribute that uses a policy configuration key, configure the attribute with a **Configuration Key** resolver and the name of the policy configuration key.

For example, in the following image, an attribute called ConsentServiceBaseUri is configured to use a policy configuration key called ConsentBaseUri.

ConsentServiceBaseUri				
The base URI of the PingDire	ectory Consent API			
Parent	no parent selected			
 Resolvers (1 total) 				
Configuration Key Resolve attribute using	- ConsentBaseURI			
Resolver type Co	onfiguration Key ConsentBaseUri			

The means by which policy configuration keys are provided to the policy engine differ based on whether the PingAuthorize Server is configured to use external PDP mode or embedded PDP mode, as shown in the following table.

Mode	Where to define policy configuration keys		
External PDP mode	An options file and run the Policy Editor's setup tool. See Define policy configuration keys in a development environment.		
Embedded PDP mode	The PingAuthorize Server configuration. See Define policy configuration keys in a preproduction environment.		

Example

In this example, you define a policy information provider (PIP) in the Trust Framework so that various properties needed to connect to the PIP can be changed from those needed for a development environment to those needed for a preproduction environment.

You can complete the PIP definition without needing to update the Trust Framework.

Define a policy information provider for the PingDirectory Consent API that uses the following policy configuration keys:

ConsentBaseUri

The base URL to use when making requests to the Consent API.

ConsentUsername

The username for a privileged Consent API account.

ConsentPassword

The password for a privileged Consent API account.

Define the policy information provider in the Trust Framework

Complete the following steps to define the policy information provider (PIP).

Steps

- 1. Define an attribute in the Trust Framework for the Consent API's base HTTPS URL.
 - 1. Go to Trust Framework and then clickAttributes.
 - 2. Add a new attribute.
 - 1. Name the attribute ConsentServiceBaseUri.
 - 2. Add a resolver.
 - 3. Set the **Resolver type** to **Configuration Key**.
 - 4. Set the Resolver value to ConsentBaseUri.
 - 5. Save the attribute.

The following image shows the attribute configuration.

ConsentServiceBaseUri

The base URI of the PingDirectory Consent API

Parent

no parent sele

 Resolvers 	(1	total)
-------------------------------	----	--------

Configuration Resolve attribute of	Key - ConsentBaseURI using		=
Resolver type	Configuration Key 🗸	ConsentBaseUri	

=

•

2. Repeat the previous steps for ConsentUsername and ConsentPassword.

Result:

When complete, you should have defined the following attributes.

Attribute name	Policy configuration key name	
ConsentServiceBaseUri	ConsentBaseUri	
ConsentServiceUsername	ConsentUsername	
ConsentServicePassword	ConsentPassword	

(j) Note

Both the attribute names and the policy configuration key names that you use are arbitrary, and you can use any names that you like. For the sake of this example, attribute names do not match configuration key names, but they do not need to differ.

3. Define the policy information provider using the attributes that you just defined.

1. Go to Trust Framework and then Services.

- 2. Add a new service.
 - 1. Name the service Consent API.
 - 2. Leave the **Parent** value blank. If a value is already present, clear it.
 - 3. Set Service Type to HTTP.
 - 4. Set the URL to \{{ConsentServiceBaseUri}}/consents?subject=\{\{HttpRequest.AccessToken.subject}}.
 - 5. Set Authentication to Basic.
 - 6. For Username, select the attribute ConsentServiceUsername.
 - 7. For **Password**, select the attribute **ConsentServicePassword**.
- 3. Save the new service.

The following image shows the attributes being used.

🛆 Consent API	≡
Description	
Parent	no parent selected -

Service Settings

Service Type	HTTP				•
HTTP Settings					
URL	{{ConsentServiceBase	Uri}}/consen	ts?subject={{HttpRequ	est.AccessToken.subject}}	\bigtriangledown
HTTP Method	GET	•	Content Type	application/json	•
Body					\bigtriangledown
Authentication	Basic				•
Username	ConsentServiceUse	er •	Password	ConsentServicePass	•

Result:

You can use the new Consent API policy information provider to build policies.

Define policy configuration keys in a development environment

Before you can use any policies that you developed with the Consent API policy information provider (PIP), you must configure the Policy Editor to provide values for the PIP's base URL, username, and password.

About this task

To configure the Policy Editor to provide these values, re-run the **setup** tool using an options file to generate a new configuration, as shown in the following steps.

🕥 Note

See Policy Editor configuration with runtime environment variables for an example of defining policy configuration keys at runtime.

Steps

1. Make a copy of the default options file.

Example:

\$ cp config/options.yml my-options.yml

2. Edit the new options file and define the policy configuration keys in the **core** section.

Example:

```
core:
  ConsentBaseUri: https://consent-us-east.example.com/consent/v1
  ConsentUsername: cn=consent admin
  ConsentPassword: Passw0rd123
# Other options omitted for brevity...
```

3. Stop the Policy Editor.

```
$ bin/stop-server
```

4. Run setup using the --optionsFile argument, and then customize all other options as appropriate for your needs.

Example:

```
$ bin/setup demo \
    --adminUsername admin \
    --generateSelfSignedCertificate \
    --decisionPointSharedSecret pingauthorize \
    --hostname <pap-hostname> \
    --port <pap-port> \
    --adminPort <admin-port> \
    --licenseKeyFile <path-to-license> \
    --optionsFile my-options.yml
```

5. Start the Policy Editor.

Example:

\$ bin/start-server

Define policy configuration keys in a preproduction environment

Do not use the Policy Editor in a pre-production or production environment. Define policy configuration keys in the PingAuthorize Server configuration.

About this task

When using embedded PDP mode, policy configuration keys are stored in the PingAuthorize Server configuration, and the server provides the policy configuration key values to the policy engine at runtime. You can use either the administrative console or **dsconfig** to define policy configuration keys.

(j) Note

Policy configuration key values are stored in encrypted form in the PingAuthorize Server configuration, so they are suitable for storing sensitive values such as server credentials.

Define policy configuration keys using the administrative console by following these steps:

Steps

- 1. In the administrative console, under Authorization and Policies, click Policy Decision Service.
- 2. Click New Policy Configuration Key.
 - 1. For Name, enter ConsentBaseUri.
 - 2. For **Policy Configuration Value**, type the base URI. For example, https://consent-us-east.example.com/consent/v1

Example:					
New Policy Configu	ration Key 🖓				Х
			View dsconfig	Save To cluster_example Cluster	Cancel
Name *	ConsentBaseUri	0			
Description			0		
Policy Configuration Value *	https://consent-us-east.example.com/consent/v1	Ø	2		

- 3. Save the policy configuration key.
- 4. Repeat the previous steps for the policy configuration keys ConsentUsername and ConsentPassword.

Example

The following example shows how to use **dsconfig** to create a policy configuration key named **ConsentServiceBaseUri** with the value https://example.com/consent/v1

```
dsconfig create-policy-configuration-key \
    --key-name ConsentServiceBaseUri \
    --set policy-configuration-value:https://example.com/consent/v1
```

Create policies in a development environment

Develop policies using the PingAuthorize Policy Editor as the policy decision point (PDP), which causes all saved policy changes to take effect immediately.

To take advantage of rapid deployment and advanced testing capabilities during policy development, configure PingAuthorize Server in external PDP mode. In this mode, PingAuthorize Server forwards all policy requests to the Policy Editor, which acts as PingAuthorize Server's PDP.

To get started with policy development, see Getting started with PingAuthorize (tutorials) or Loading a policy snapshot.

i) Note

PingAuthorize Server does not function as expected without many of the Trust Framework entities defined by the **def aultPolicies.SNAPSHOT** file bundled with PingAuthorize Server. When developing new policies, begin by importing this snapshot and using it as the basis for your own customizations.

After developing your policies, deploy them using one of the following methods:

- Exporting a policy deployment package
- Using the Deployment Manager

Configuring external PDP mode

To configure PingAuthorize Server to use external PDP mode, use the administrative console or **dsconfig** to create a Policy External Server to represent the Policy Editor, then assign the Policy External Server to the Policy Decision Service and set the PDP mode.

Before you begin

You need the following values to configure PingAuthorize Server to use external PDP mode:

- The shared secret, which is chosen or generated when you install the Policy Editor.
- The branch name, which corresponds to the policy branch you want to evaluate requests against in the Policy Editor.
- The decision node, which is the ID of a node in the policy tree that will be considered first during policy processing. To find the decision node value:
 - 1. In the Policy Editor, go to **Policies**.
 - 2. Select the node that you want to use as the root node.

This is typically the top-level node of your policy tree.

3. Click the hamburger menu and select **Copy ID to clipboard**.

Policies Library Ta	arget Search De	cision Visualiser		
Policies	Components	Details History Test		
+		追 Global Decision Point	Disabled	
 Global Decision Point Token Validation PDP API Endpoint Policies Token Authorization 		Description	 Copy ID to clipboard Get link to here Expand top level containers 	
		+ Applies to	 Collapse top level containers 	
		 Policies (2) 	Se View Dependents	

Using the administrative console

Configuring external PDP mode using the administrative console Steps

- 1. In the PingAuthorize administrative console, go to **Configuration** \rightarrow **Data Sources** \rightarrow **External Servers**.
- 2. Click **New External Server** and select **Policy External Server** from the drop-down menu.
- 3. In the **New Policy External Server** window, specify the following information:
 - Name
 - Base URL
 - Shared Secret
 - Decision Node
 - Branch

New Policy External Policy External Servers are used to requests.	al Server o specify connections to external policy decision point servers and to s	elect the policies that will b	e used to a	authorize
		View API commands	Save	Cancel
Name *	Policy Editor	0		
Description			0	
Base URL *	https:// <pap-hostname>:<pap-port></pap-port></pap-hostname>	0		
Hostname Verification Method	strict 🗙 🗸 🕝			
Key Manager Provider	The Java Runtime Environment's default key mana	0		
Trust Manager Provider	The Java Runtime Environment's default trust man	Ø		
SSL Cert Nickname	A certificate will be chosen from the key manager arbitrarily.	0		
Connect Timeout	30 s	0		
Response Timeout	30 s	0		
User ID *	admin	0		
Shared Secret *	Set Value 📀			
Decision Node	e51688ff-1dc9-4b6c-bb36-8af64d02e9d1	0		
Branch	Default Policies	9 C		
Snapshot	If no value is defined, the snapshot query parameter is not populat	0		

4. Click Save.

- 5. Go to Authorization and Policies \rightarrow Policy Decision Service.
- 6. In the **PDP Mode** list, select **external**.

7. In the **Policy Server** list, select the name you gave to the policy external server in step 3.

	View API commands	Save To PingAuthorize Server Cluster	Cance
General Configuration			
PDP Mode	external	© C' ▼ X	
Policy Server	Policy Editor	× - 🖌 + 0	

Using dsconfig

Configuring external PDP mode using dsconfig Steps

• Use the **dsconfig** commands in the following code block to configure external PDP mode:

```
dsconfig create-external-server \
    --server-name "{PAP_Name}" \
    --type policy \
    --set "base-url:https://<pap-hostname>:<pap-port>" \
    --set "shared-secret:pingauthorize" \
    --set "branch:Default Policies" \
    --set "decision-node:<your decision node ID value>"

dsconfig set-policy-decision-service-prop \
    --set pdp-mode:external \
    --set "policy-server:{PAP_Name}"
```

Changing the active policy branch

The PingAuthorize Policy Editor can manage multiple sets of Trust Framework attributes and policies by storing data sets in different branches.

About this task

In a development environment, you might need to quickly reconfigure PingAuthorize Server between policy branches.

Steps

- 1. To set up branch changes, you must first define a Policy External Server configuration for each branch.
- 2. Change the Policy Decision Service's **policy-server** property as needed.

Example:

Assume that you have two policy branches in the Policy Editor: **Stable Policies** and **Experimental Policies**. Each branch is represented in the PingAuthorize Server configuration as a Policy External Server. During testing, you can switch back and forth between branches by updating the Policy Decision Service's **policy-server** property. To change to the **Experimental Policies** branch, run this command:

dsconfig set-policy-decision-service-prop \
 --set "policy-server:Experimental Policies"

To change back to the Stable Policies branch, run this command:

```
dsconfig set-policy-decision-service-prop \
    --set "policy-server:Stable Policies"
```

Default and example policies

A policy snapshot is a file that contains a complete Trust Framework and policy set.

A policy snapshot is also the data import format for a PingAuthorize Policy Editor. PingAuthorize includes a number of default and example policy snapshot files in the **resource/policies** directory. The following table describes the available snapshot files.

Snapshot filename	Description
defaultPolicies.SNAPSHOT	The default Trust Framework for PingAuthorize Server and a minimal set of policies. Always use this snapshot as the starting point for policy development.
gatewayPolicyExample.SNAPSHOT	An example policy set that demonstrates how to apply policies to an external REST API using PingAuthorize Server as an API security gateway. Based on Getting started with PingAuthorize (tutorials).
scimPolicyExample.SNAPSHOT	An example policy set that demonstrates how to implement access token-based access control using the SCIM 2 REST API. Based on Getting started with PingAuthorize (tutorials).

Importing and exporting policies

PingAuthorize supports two import and export file formats for Trust Framework and policy data.

About this task

The following table describes the snapshot and deployment package formats.

Format	Description
Snapshot	Contains all Trust Framework and policy data for a policy branch in the Policy Editor. Use a snapshot to load data into the Policy Editor for policy development using external policy decision point (PDP) mode.
Deployment package	An optimized data format that contains all policies under a specified root policy node and all Trust Framework entities used by those policies. Use a deployment package to load data into the PingAuthorize Server for policy deployment using embedded PDP mode.

The following sections describe how to import and export policy snapshots using the Policy Editor. See Exporting a policy deployment package and Using the Deployment Manager for more information on deployment packages.

Loading a policy snapshot


To import a policy snapshot into the Policy Editor for policy development, complete the following steps.

About this task

To create a new policy branch with the Trust Framework and policies of the provided snapshot:

Steps

- 1. Go to the Branch Manager section.
- 2. Click the Version Control tab.
- 3. In the + menu, select Import Snapshot.



4. Select a snapshot file and provide a name for your policy branch.

mport Sna	pshot	×
Snapshot	defaultPolicies.SNAPSHOT	×
Name	My Policies	Import

5. Optional: Click Commit New Changes to commit the initial state of the policy branch.

Exporting a policy snapshot

About this task

To import a policy snapshot into a different Policy Editor or use it as the basis to create a deployment package to be loaded in the PingAuthorize Server:

Steps

- 1. Go to the Branch Manager section.
- 2. Select the Version Control tab.
- 3. Choose the commit message corresponding to the version of the branch that you want to export and click the icon in the **Options** column to the left of the commit message.
- 4. Select Export Snapshot.

Commits		Set branch as Merge	e Source Set l	oranch as Merge Target
Options Commit Message	Co	ommited on	Creator	Approvals
📰 Uncommitted Changes	N/	/A	N/A	
📰 Initial commit	3/.	24/2020, 2:32:27 AM	admin	<u>උ</u> 0
🛱 Copy ID to Clipboard	3/	17/2020, 2:03:54 PM	SYSTEM	
Biten Export Snapshot				
د Select source commit to compare				
↑ Select target commit to compare				
♀ Create new branch from commit				
Approve Snapshot				

5. Provide a snapshot filename and click **Export**.

Result

The snapshot file is downloaded to your computer.

Exporting a policy deployment package

When you have completed development and testing of your policies, you can export your Trust Framework and policies to a deployment package for use in embedded PDP mode.

Before you begin

If you want to configure your policy deployment packages to be signed upon export, see Example: Configure signed deployment packages for healthcare.

Steps

1. Export a snapshot.

See Exporting a policy snapshot.

- 2. Go to the Branch Manager section.
- 3. Click the Deployment Packages tab.
- 4. Click the + icon.
- 5. Enter a meaningful name for your deployment package.
- 6. In the **Branch** list, select a policy branch.
- 7. In the **Commit** list, select a commit.

8. In the **Policy Node** list, select a policy node.

Ping Identity.	Ping Authorize					Welcome admin (PingAuthorize Tutorials)
		Version Control	Deployment Packages	Deployment Mana	ger Export Partial Snapshot	Merge Snapshot
>\$	Branch Manager	Packages		Details		
4	Trust Framework	+		NamedDeplo	oymentPackage	
Ð	Policies	_		Branch F	PingAuthorize Tutorials	
	Test Suite			Commit i	nitial commit (by admin at 2022-06-14	T20:29:33.464574Z)
	API Reference				Global Decision Point 👻	,

- 9. Click Create Package.
- 10. Click Export Package.

Result

The deployment package is downloaded to your computer.

Using the Deployment Manager

The Deployment Manager simplifies policy updates by enabling policy writers to deploy new policies to a central deployment package store to be read by the PingAuthorize server running in embedded mode.

About this task

This process is two-fold:

- Policy writers use the Policy Editor to publish policies in a deployment package to a deployment package store.
- Updated deployment packages are picked up by the PingAuthorize Policy Decision Service from the deployment package store.

(i) Note


You configure the interval that the server checks for updates in the store during setup.

This allows a policy writer to deploy new policies without the manual process of exporting a deployment package that is then uploaded into the server through the administrative console.

The Deployment Manager can use deployment package stores that are based on:

- A directory in the filesystem
- An Amazon Simple Storage Service (Amazon S3) bucket
- Azure Blob storage

Package stores hold deployment packages in a central location that the Policy Editor publishes to and the PingAuthorize server reads from, as illustrated in the following diagram:



To use the Deployment Manager:

Steps

1. Define a deployment package store.

Note
 For a filesystem store, you must have a directory on the filesystem that the Policy Editor has read-write access to.
 Amazon S3 buckets must be configured with a secret key and an access key for use. See Setting up an Amazon S3 deployment package store for more information.
 For Azure storage, you must set up an Azure storage account and a container. For later use, record the Connection string value found in your account's Access key settings.

- 2. Use an options file to configure the Policy Editor to publish policies to a store.
- 3. Create and deploy deployment packages to the deployment package store.
- 4. Add the deployment package store for read access to the PingAuthorize Server:
 - 1. Add a filesystem deployment package store.
 - 2. Add an Amazon S3 deployment package store.
 - 3. Add an Azure deployment package store,

5. Configure the Policy Decision Service to read from your deployment package store.

Setting up an Amazon S3 deployment package store

Follow these procedures to create and configure an Amazon Simple Storage Service (S3) bucket that you can publish deployment packages to from the Policy Editor for consumption by PingAuthorize Server.

i) Important

See Using the Deployment Manager for the steps you need to complete for an end-to-end deployment package store configuration in embedded policy decision point (PDP) mode.

Creating an S3 bucket

About this task

To store your deployment packages, create a new S3 bucket in the S3 dashboard of Amazon Web Services (AWS) Management Console.

Steps

1. In the AWS Management Console, on the S3 dashboard ^[2], go to **Buckets** and click **Create bucket**.

Amazon S3 ×	Amazon S3 > Buckets
Buckets Access Grants	Account snapshot (All AWS Regions) Last updated: Apr 28, 2024 by Storage Lens. Metrics are generated every 24 hours. Metrics don't include directory buckets. Learn more [2]
Access Points Object Lambda Access Points Multi-Region Access Points Batch Operations IAM Access Analyzer for S3	Total storage Object count Average object size 2.8 TB 91.4 M 32.3 KB You can enable advanced metrics in the "default-account-dashboard" configuration.
Block Public Access settings for this account	General purpose buckets Directory buckets
Storage Lens Dashboards Storage Lens groups AWS Organizations settings	General purpose buckets (381) Info (All AWS Regions) C C C copy ARN Empty Delete Create bucket Buckets are containers for data stored in S3. Q. Find buckets by name < 1 2 3 4 >

2. Configure the bucket.

Learn more in Creating a bucket^C in the Amazon documentation.

Configuring the IAM user policy

About this task

To manage your deployment package store, configure a new identity and access management (IAM) policy in the IAM dashboard of AWS Management Console.

Steps

1. In the AWS Management Console, on the IAM dashboard \Box , go to Access Management \rightarrow Policies and click Create policy.

Identity and Access Management (IAM)	×		Policies			
Q Search IAM			cies (1/1822) Info cy is an object in AWS that defines permissions.		C Actions	Delete Create policy
				Filter by Type	_	
Dashboard		Q S	Search	AWS managed 🔻	1180 matches < 1 2	2 3 4 5 6 7 59 > 🕥
 Access management 			Policy name	Type 🗢	Used as \bigtriangledown	Description
User groups		0	AccessAnalyzerServic	AWS managed	Permissions policy (1)	Allow Access Analyzer to analyze resou
Users		0	AdministratorAccess	AWS managed	None	Grants account administrative permiss
Roles		-				·
Policies		0	AdministratorAccess	AWS managed	None	Grants account administrative permiss
Identity providers		0	AlexaForBusinessDevi	AWS managed	None	Provide device setup access to AlexaFo
Account settings		0	AlexaForBusinessFull	AWS managed	None	Grants full access to AlexaForBusiness

2. In the Policy editor wizard, select the JSON tab and enter these permissions:

(i) Note

You can manage S3 bucket access in multiple ways, including IAM policies, S3 policies, or S3 access control lists (ACLs). We provide a working IAM policy example, but you should be aware of current AWS best practices, industry best practices, and your organization's conventions when configuring S3 bucket access.

Replace the asterisk wildcard character to restrict the access scope of the previous policy.

- 3. Complete the Create policy wizard according to your organization's specifications.
- 4. On the **Review and create** confirmation page, review your configurations and click **Create policy** to create the IAM user policy.

Configuring the IAM user

About this task

To publish to your AWS deployment package store from the Policy Editor, configure a new IAM user to access the S3 bucket in accordance with the policy that you created in **Configuring the IAM user policy**.

Steps

1. In the AWS Management Console, on to the IAM dashboard \square , go to Access Management \rightarrow Users and click Create user.

Identity and Access $ imes$ Management (IAM)	IAM > Users	
Q Search IAM	Users (50) Info An IAM user is an identity with long-term credentials that is used to interact with AWS in an account.	C Delete Create user
Dashboard	Q Search	< 1 2 3 > 🕲
 Access management 	□ User name ▼ Path ∇ Group: ∇ Last activity	

- 2. Define a username and click Next.
- 3. On the **Set permissions** page, select **Attach policies directly**, and then select the policy you created in **Configuring the IAM** user policy.
 - 1. **Optional:** Select **Create policy** to configure a different user policy.
- 4. On the **Review and create** confirmation page, review your configurations and click **Create user** to create the IAM user.
- 5. Optional: Attach user attribute tags.
- 6. On the Users page, search for and click on the newly created user.
- 7. On the Security credentials tab, in the Access keys section, click Create access key.
- 8. Click Application running outside AWS. Click Next.
- 9. Optional: In the Description tag value field, enter a description for the access key and click Create access key.
- 10. Copy both the Access key ID and Secret access key values to a secure location. Click Done.

These values will be used when configuring connections to the Policy Editor and PingAuthorize server.

介 Important

You cannot recover these credentials at a later time.

Configuring the Policy Editor to publish to a deployment package store

Use an options file to configure the Policy Editor.

Before you begin

If you want to configure your policy deployment packages to be signed upon publication to a store, see Example: Configure signed deployment packages for healthcare.

About this task

To use the Deployment Manager feature, you must configure the Policy Editor to publish policies to a deployment package store in the options file's deploymentPackageStores section.

For more information, see Using the Deployment Manager.

Steps

1. Make a copy of the default options file.

\$ cp config/options.yml my-options.yml

2. To define a deployment package store or stores for the Policy Editor to publish policies to, edit the deploymentPackageSto res section of the new options file.

The file contains commented out examples of different deployment package store types.

1. Duplicate the desired deployment package store type, uncomment, and modify its values according to your deployment.

Important

- The use of indentation in the **options.yml** file is important. When removing comment hashes, ensure that you retain valid YAML file indentation structure.
- For an Azure deployment package store, record the prefix you define for the deployment package store. You will need the prefix for PingAuthorize Server configuration.
- For an Amazon Web Services (AWS) deployment package store, review your existing Simple Storage Service (S3) bucket configurations on the S3 dashboard of AWS Management Console.
- Each deployment package store has its own signing key configuration under deploymentPackageStores. See the Signed filesystem store block for an example. The signing key configuration under deploymentPackageData applies only to exported deployment packages—not deployment package stores.

```
deploymentPackageStores:
 # Define deployment package store publishing targets here.
 #
 # - name: Filesystem store
 # description: File system directory store
 # type: filesystem
    path: /path/to/deployment-package-store/
 #
 # - name: Signed filesystem store
 # description: Signed file system directory store
    type: filesystem
 #
 # path: /path/to/signed-deployment-package-store/
 # securityLevel: signed
 # keystore:
      resource: /path/to/deployment-package-signing-keystore.jks
 #
      password: keystore-password
 #
 #
   signingKey:
 #
      alias: signing-cert-alias
 #
      password: private-key-password
 # - name: S3 bucket store
    description: AWS S3 bucket store
 #
 #
    type: s3bucket
 # securityLevel: unsigned or signed
 #
    keystore:
      resource: /path/to/deployment-package-signing-keystore.jks
 #
 #
      password: keystore-password
 #
    signingKey:
 #
      alias: signing-cert-alias
      password: private-key-password
 #
 #
    config:
 #
      bucket: store-bucket-name
 #
      prefix: store-prefix
 #
      endpoint: https://s3-bucket-endpoint.aws-region.amazonaws.com
 #
      region: aws-s3-bucket-region
 #
       accessKey: aws-access-key
 #
       secretKey: aws-secret-key
 # Other deployment package store types omitted for brevity...
```

(i) Note

For information on properly formatting an S3 endpoint or Azure connection string, see S3 endpoints \square or Storage connection strings \square , respectively.

```
3. Stop the Policy Editor.
```

```
$ bin/stop-server
```

4. Run setup using the --optionsFile argument.

- \$ bin/setup demo \
 --adminUsername admin \
 --generateSelfSignedCertificate \
 -decisionPointSharedSecret pingauthorize \
 -hostname <pap-hostname> \
 --port <pap-port> \
 --adminPort <admin-port> \
 -licenseKeyFile <path-to-license> \
 -optionsFile my-options.yml
- 5. Start the Policy Editor.

\$ bin/start-server

6. To verify that your deployment package store or stores are available in the Policy Editor, go to **Branch Manager** → **Deployment Manager**.

Publishing to a deployment package store

To use the Deployment Manager feature, create a deployment package and publish it to a deployment package store.

Before you begin

You must configure the Policy Editor to publish policies to your deployment package store using an options file.

For more information, see Configuring the Policy Editor to publish to a deployment package store.

About this task

To publish deployment packages to a deployment package store:

Steps

1. Export a snapshot.

For more information, see **Exporting a policy snapshot**.

2. Go to Branch Manager \rightarrow Deployment Packages.

- 3. Click the + icon.
- 4. Enter a meaningful name for your deployment package.
- 5. In the **Branch** list, select a policy branch.
- 6. In the **Commit** list, select a commit.
- 7. In the **Policy Node** list, select a policy node.

Example:

Ping	Ping Authorize					Welcome admin (PingAuthorize Tutorials)
		Version Control	Deployment Packages	Deployment Manager	Export Partial Snapshot	Merge Snapshot
>\$	Branch Manager	Packages		Details		
4	Trust Framework	•		NamedDeployme Name	entPackage	
B	Policies	_		Branch PingA	uthorize Tutorials	•
	Test Suite			Commit initial	commit (by admin at 2022-06-14	T20:29:33.464574Z) -
	API Reference				I Decision Point 👻	,

8. Click Create Package.

9. Click the **Deployment Manager** tab.

- 10. In the **Deployments** pane, select the deployment package store you want to publish the policies to.
- 11. In the Available Packages list, select the deployment package you want to publish to the deployment package store.

12. Click Deploy.

Result

Your deployment package is visible in your configured deployment package store.

Example

If you configured an Amazon Simple Storage Service (S3) bucket for your deployment package store, your published deployment package objects should be visible on the **Objects** tab of your bucket in Amazon Web Services (AWS) Management Console.

(i) Note

Depending on your configured prefix, AWS may have produced an object hierarchy. If so, drill into the hierarchy to locate your published deployment package.

aws Services Q Search fo	r services, features, blogs, docs, and more [Option+S]	
Amazon S3 ×	We're continuing to improve the S3 console to make it faster and easier to use. If you have feedback on the updated experience, choose Provide feedback.	Provide feedback
Buckets Access Points Object Lambda Access Points Multi-Region Access Points Batch Operations	Amazon S3 > Buckets > s3permissionstestbucket > default-deployments/ default-deployments/ Objects Properties	D Copy S3 URI
A		
Access analyzer for S3 Block Public Access settings for	Objects (3) Objects are the fundamental entities stored in Amazon 53. You can use Amazon 53 inventory [2] to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more	Ľ
Access analyzer for 53 Block Public Access settings for this account		ß
Block Public Access settings for this account	Objects are the fundamental entities stored in Amazon S3. You can use Amazon S3 inventory 🖄 to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more	[⁷ < 1 > ⊚
Block Public Access settings for this account Storage Lens Dashboards	Objects are the fundamental entities stored in Amazon 53. You can use Amazon 53 inventory 🔮 to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more C C copy S3 URI C copy URL Download Open Delete Actions Create folder Upload Q. Find objects by prefix Show versions	
Block Public Access settings for this account Storage Lens Dashboards	Objects are the fundamental entities stored in Amazon S3. You can use Amazon S3 inventory [2] to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more and the component of the comp	< 1 > ©
Block Public Access settings for this account Storage Lens	Objects are the fundamental entities stored in Amazon 53. You can use Amazon 53 inventory [2] to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. Learn more C C copy 53 URI C copy URL Download Open [2] Delete Actions ▼ Create folder ① Upload Q. Find objects by prefix Image: C solution of the	< 1 > ③

Next steps

Add the deployment package store to the PingAuthorize Server for read access. Based on your deployment package store configuration, add one of the following:

- Add a filesystem deployment package store.
- Add an Amazon S3 deployment package store.
- Add an Azure deployment package store.

Adding a filesystem deployment package store

To use the Deployment Manager, add a deployment package store for read access to the PingAuthorize server.

About this task

Use the administrative console or **dsconfig** to add the deployment package store.

Administrative console

Adding a new filesystem deployment package store using the administrative console Steps

- 1. In the administrative console, go to **Configuration** → **Authorization** and **Policies** → **Deployment Package Stores**.
- 2. Click New Deployment Package Store.
- 3. In the New Deployment Package Store list, select Filesystem Deployment Package Store.
- 4. Complete the General Configuration fields:
 - 1. In the **Name** field, enter a name for the deployment package store.
 - 2. In the **Poll Interval** field, enter a value in seconds for how often the directory should be polled for changes.

A value of **0** only updates on start-up.

3. In the **Poll Directory** field, enter the directory where the deployment package is stored locally.

5. Optional: Complete the Policy Security fields.

i Νote

(i

If you select **signed** in the **Deployment Package Security Level** field, you must complete the **Deployment Package Trust Store** field.

6. Click Save To PingAuthorize Server Cluster.

Result:

Your filesystem deployment package store is displayed on the **Deployment Package Stores** page.

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Dsconfig

Steps

Adding a new filesystem deployment package store using dsconfig • Run dsconfig with the create-deployment-package-store option: Choose from: • Create a store with an unsigned deployment package. dsconfig create-deployment-package-store \ --store-name "<store-name>" \ --type filesystem \ --set "poll-interval:<poll-interval>" \ --set "poll-directory:<filesystem-directory>"

• Create a store with deployment-package-security-level set to signed.

```
dsconfig create-deployment-package-store \
 --store-name "<store-name>" \
  --type filesystem \
 --set "poll-interval:<poll-interval>" \
 --set deployment-package-security-level:signed \
  --set "deployment-package-trust-store:<trust-store-provider-name>" \
  --set "deployment-package-verification-key-nickname:<key-nickname>" \
  --set "poll-directory:<filesystem-directory>"
```

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Adding an Amazon S3 deployment package store to PingAuthorize

To use Amazon Simple Storage Service (S3) as your deployment package store, add read access for your S3 bucket to the PingAuthorize server.

Before you begin

You must create an access key and accompanying secret key for your S3 bucket. See Setting up an Amazon S3 deployment package store for more information.

About this task

Use the administrative console or **dsconfig** to add the Amazon S3 deployment package store. If needed, review your existing S3 bucket configurations on the S3 dashboard of Amazon Web Services (AWS) Management Console.

Administrative console

Adding an Amazon S3 deployment package store using the administrative console Steps

- 1. In the administrative console, go to Configuration \rightarrow Authorization and Policies \rightarrow Deployment Package Stores.
- 2. Click New Deployment Package Store.
- 3. In the New Deployment Package Store menu, select S3 Deployment Package Store.
- 4. Complete the General Configuration fields:
 - 1. In the **Name** field, enter a name for the deployment package store.
 - 2. In the **Poll Interval** field, enter a value in seconds for how often the Amazon S3 bucket should be polled for changes.

Λοτε

A value of 0 only updates on restart.

- 3. In the **S3 Bucket Name** field, enter the name of your Amazon S3 bucket as shown on your AWS services page.
- 4. In the S3 Bucket Prefix field, enter your Amazon S3 bucket prefix.
- 5. In the S3 Server Endpoint field, enter your Amazon S3 bucket AWS endpoint.
- 6. In the S3 Region Name field, enter the AWS region for your S3 bucket.
- 7. Next to the S3 Access Key ID field, click Set Value and enter the S3 Access Key ID for your S3 bucket.
- 8. Enter the S3 Access Key ID value again to confirm and click **OK**.

i) Note

Your access key value is not displayed after you enter it. The page still displays **Set Value**.

- 9. Next to the S3 Secret Key field, click Set Value and enter the S3 Secret Key for your S3 bucket.
- 10. Enter the value again to confirm and click **OK**.

i) Note

Your secret key value is not displayed after you enter it. The page still displays Set Value.

5. Optional: Complete the Policy Security fields.

) Note

If you select **signed** in the **Deployment Package Security Level** field, you must complete the **Deployment Package Trust Store** field.

6. Click Save To PingAuthorize Server Cluster.

Result:

Your Amazon S3 deployment package store is displayed on the Deployment Package Stores page.

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Dsconfig

```
Adding an Amazon S3 deployment package store using dsconfig
Steps
```

• Run dsconfig with the create-deployment-package-store option:

Choose from:

• Create a store with an unsigned deployment package.

```
dsconfig create-deployment-package-store \
    --store-name "<store-name>" \
    --type s3 \
    --set "poll-interval: <poll-interval>" \
    --set "s3-bucket-name:<bucket-name>" \
    --set "s3-bucket-prefix:<bucket-prefix>" \
    --set "s3-server-endpoint:<server-endpoint>" \
    --set "s3-region-name:<region-name>" \
    --set "s3-access-key-id:<access-key-id>" \
    --set "s3-secret-key:<secret-key>"
```

• Create a store with deployment-package-security-level set to signed.

```
dsconfig create-deployment-package-store \
    --store-name "<store-name>" \
    --type s3 \
    --set "poll-interval: <poll-interval>" \
    --set deployment-package-security-level:signed \
    --set "deployment-package-trust-store:<trust-store-provider-name>" \
    --set "deployment-package-verification-key-nickname:<key-nickname>" \
    --set "s3-bucket-name:<bucket-name>" \
    --set "s3-server-endpoint:<server-endpoint>" \
    --set "s3-access-key-id:<access-key-id>" \
    --set "s3-secret-key:
```

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Adding an Azure deployment package store

To use the Deployment Manager, add a deployment package store for read access to the PingAuthorize server.

About this task

Use the administrative console or **dsconfig** to add the deployment package store.

Administrative console

Adding an Azure deployment package store using the administrative console Before you begin

Set up your Azure storage account:

- If you don't already have an Azure storage account, create one.
- Add a container to your storage account.
- Record the Connection string value found in your account's Access key settings.

For information on setting up an Azure storage account, see your Azure Blob Storage documentation.

Steps

- 1. In the administrative console, go to **Configuration → Authorization and Policies → Deployment Package Stores**.
- 2. Click New Deployment Package Store.
- 3. In the New Deployment Package Store menu, select Azure Deployment Package Store.
- 4. Complete the **General Configuration** fields.
 - 1. In the **Name** field, enter a name for the deployment package store.
 - 2. In the **Poll Interval** field, enter a value in seconds for how often the Azure store should be polled for changes.

(i) Note

A value of 0 only updates on restart.

3. In the **Azure Blob Connection String** field, enter the connection string shown in your Azure storage account's Access key settings.

(i) Note

Your connection string value is not displayed after you enter it. The page still displays **Set Value**.

- 4. In the Azure Blob Container field, enter the name of your container.
- 5. In the **Azure Blob Prefix** field, enter the **prefix you defined** for the deployment package store.
- 5. Optional: Complete the Policy Security fields.

) Note

If you select **signed** in the **Deployment Package Security Level** field, you must complete the **Deployment Package Trust Store** field.

6. Click Save To PingAuthorize Server Cluster.

Result:

Your Azure deployment package store is displayed on the Deployment Package Stores page.

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Dsconfig

```
Adding an Azure deployment package store using dsconfig
Steps
```

• Run dsconfig with the create-deployment-package-store option:

Choose from:

• Create a store with an unsigned deployment package.

```
dsconfig create-deployment-package-store \
    --store-name "<store-name>" \
    --type azure \
    --set "poll-interval:<poll-interval>" \
    --set "azure-blob-connection-string:<blob-connection-string>" \
    --set "azure-blob-container:<blob-container>" \
    --set "azure-blob-prefix:<blob-prefix>"
```

• Create a store with deployment-package-security-level set to signed.

```
dsconfig create-deployment-package-store \
    --store-name "<store-name>" \
    --type azure \
    --set "poll-interval:<poll-interval>" \
    --set "azure-blob-connection-string:<blob-connection-string>" \
    --set "azure-blob-container:<blob-container>" \
    --set "azure-blob-prefix:<blob-prefix>"
    --set deployment-package-security-level:signed \
    --set "deployment-package-trust-store:<trust-store-provider-name>" \
    --set "deployment-package-verification-key-nickname:<key-nickname>"
```

Next steps

Configure the PingAuthorize server to use embedded PDP mode with your deployment package store.

Prepare policies for production

If you configured any of the following features during policy development and testing using the Policy Editor as your decision point, you need to reconfigure these features before putting your policies into a production environment using PingAuthorize Server as your decision point:

- Policy configuration keys
- Policy information provider key store
- Policy information provider trust store
- Non-standard SpEL Java classes

Example: Define a policy information provider key store for MTLS

The policy engine supports the use of PIPs to dynamically retrieve data from external services at runtime. In these cases, the policy engine can use a client certificate contained in a Java KeyStore (JKS) or PKCS12 key store.

When using embedded PDP mode, the key store containing the client certificate is represented in the PingAuthorize Server configuration as a Key Manager Provider, which is then assigned to the Policy Decision Service.

The following example creates a Key Manager Provider named MyClientCertKeystore and makes it available to the policy engine.

```
dsconfig create-key-manager-provider \
    --provider-name MyClientCertKeystore \
    --type file-based \
    --set enabled:true \
    --set key-store-file:<full path to a key store> \
    --set key-store-type:JKS \
    --set key-store-pin:<key store password>
dsconfig set-policy-decision-service-prop \
    --set service-key-store:MyClientCertKeystore
```

When you define the PIP in the Trust Framework, you can refer to the key store that you configured, using the name MyClientCer tKeystore.

	Certificate Validation				
	Server (TLS)	Default -			
L	Client (M-TLS)				
	Keystore name				
	Alias	my-cert 🚫	Alias password	password123	\bigtriangledown

_

Example: Define a policy information provider trust store

For a policy information provider (PIP), you can use the Java Runtime Environment (JRE)'s default trust store or you can provide a custom Java KeyStore (JKS) or PKCS12 trust store.

The policy engine supports the use of PIPs to dynamically retrieve data from external services at runtime. By default, the policy engine determines whether it should accept a PIP's server certificate using the Java Runtime Environment (JRE)'s default trust store, which contains public root certificates for common certificate authorities. However, if your PIP uses a server certificate issued by some other certificate authority, for example, a private certificate authority operated by your organization, then you can provide a custom Java KeyStore (JKS) or PKCS12 trust store.

When using embedded PDP mode, the trust store containing the client certificate is represented in the PingAuthorize Server configuration as a Trust Manager Provider, which is then assigned to the Policy Decision Service.

The following example creates a Trust Manager Provider named MyCATruststore and makes it available to the policy engine.

```
dsconfig create-trust-manager-provider \
    --provider-name MyCATruststore \
    --type file-based \
    --set enabled:true \
    --set trust-store-file:<full path to a trust store> \
    --set trust-store-type:JKS
dsconfig set-policy-decision-service-prop \
    --set service-trust-store:MyCATruststore
```

When you define the policy information provider in the Trust Framework, you can refer to the trust store that you configured using the name MyCATruststore.

Certificate Validation				
Server (TLS) Custom	•			
Truststore name MyCATrus	ststore 🏷			
Alias my-ca	\bigtriangledown	Alias password	password123	\$
Client (M-TLS)				

Example: Add SpEL Java classes to the allowed list

When you develop policies, you can use SpEL expressions in your deployment packages. Configure the Java classes used during SpEL expression evaluation by adding classes to the allowed list.

When using embedded PDP mode, the policy engine allows use of the following classes by default.

java.lang.String java.util.Date java.util.UUID java.lang.Integer java.lang.Long java.lang.Double java.lang.Byte java.lang.Math java.lang.Boolean java.time.LocalDate java.time.LocalTime java.time.LocalDateTime java.time.ZonedDateTime java.time.DayOfWeek java.time.Instant java.time.temporal.ChronoUnit java.text.SimpleDateFormat java.util.Collections

Use **dsconfig** or the administrative console to add non-standard classes to the allowed list. In the administrative console, you can find SpEL allowed classes in the Policy Decision Service configuration.

Example

The following example shows how to add the java.time.format.DateTimeFormatter and java.util.Base64 classes to the allowed list. Run dsconfig with the set-policy-decision-service-prop option.

```
dsconfig set-policy-decision-service-prop \
    --set spel-allowed-class:java.time.format.DateTimeFormatter \
    --set spel-allowed-class:java.util.Base64
```

Important

After you add non-standard classes to the allowed list, you must make them available on the server classpath at server start.

The following example shows how to add .jar files containing the classes to the lib folder and restart the server.

```
cd <paz-instance-root>
cp <jar-file-dir>/addl-spel-classes.jar lib
bin/stop-server -R
```

Use policies in a production environment

After developing and testing policies in external policy decision point (PDP) mode, you can configure PingAuthorize Server for embedded PDP mode for higher environments.

You should use embedded PDP mode for production environments because it is considerably more performant for authorization decisions. This performance boost happens because in embedded PDP mode, PingAuthorize Server doesn't need to call out to the Policy Editor.

When configured to use embedded PDP mode, a policy file called a deployment package is used in PingAuthorize Server's internal policy engine, which then handles all policy requests. The deployment package can be loaded into the server in two ways:

- The deployment package is exported from the Policy Editor and loaded into the internal policy engine by an administrator.
- The deployment package is deployed to a deployment package store, which is read by the internal policy engine for updates at a configurable interval.

(i) Note

If you still anticipate some policy changes in production, consider using this method instead of the exported deployment package method.

Configuring embedded PDP mode

See the following tabs to configure PingAuthorize Server to use embedded PDP mode and assign to the Policy Decision Service either:

- A deployment package store using the Deployment Manager functionality
- An exported deployment package

Deployment package store

Configuring embedded PDP mode with a deployment package store About this task

Follow these steps to assign a deployment package store to the Policy Decision Service and set the policy decision point (PDP) mode to embedded.

(j) Note

For more information on the deployment package store option and the requirements for the Deployment Manager feature, see Using the Deployment Manager.

Steps

• Use **dsconfig** or the administrative console:

Choose from:

• Run dsconfig with the set-policy-decision-service-prop option.

```
dsconfig set-policy-decision-service-prop \
--set pdp-mode:embedded \
--set deployment-package-source-type:store \
--set deployment-package-store:<name of the store>
```

• Use the administrative console.

- 1. In the administrative console, go to Configuration → Authorization and Policies → Policy Decision Service.
- 2. On the Edit Policy Decision Service page, complete the General Configuration fields.

Storig 8d0f3c80ec35 / Configuration /		Configuration Guide		
ervice 🖆				
The Policy Decision Service contains the properties that affect the overall operation of the PingAuthorize Server policy service.				
		View API commands Save To PingAuthorize Server Cluster Cancel		
embedded	0 C - x			
	+ 0			
	properties that affect the overall operation	embedded		

- 3. In the **Deployment Package Store Configuration**section, in the **Deployment Package Store**field, select your deployment package store.
- 4. In the Policy Request Configuration section, select a Trust Framework Version.
- 5. Click Save To PingAuthorize Server Cluster.

Exported deployment package			
Configuring embedded PDP mode with an exported deployment package About this task			
To assign an exported deployment package to the Policy Decision Service and set the PDP mode:			
Steps			
• Run dsconfig with the set-policy-decision-service-prop option.			
Example:			
In this example, the deployment-package value is the full path to a deployment package file. To create a deployment package for export, see Exporting a policy deployment package.			
<pre>dsconfig set-policy-decision-service-prop \ set pdp-mode:embedded \ set "deployment-package</pre>			

Policy database backups

The Policy Editor uses a policy database to store its Trust Framework, policies, commit history, and other data needed for proper operation.

By default, the Policy Editor backs up the policy database to a compressed file once a day by making an HTTP request to an admin connector. The Policy Editor retains up to five policy database backups at a time. Older backups are automatically deleted after this limit is reached.

To customize the handling of policy database backups, configure the admin port, backup schedule, and output location.

(j) Note

If you are using a managed RDBMS, such as PostgreSQL, instead of the default H2 database, make sure you implement backup strategies in line with your organization's best practices.

Configure or disable policy database backups

Do one of the following to change the backup configuration:

- Set the relevant environment variables and restart the Policy Editor.
- Run the Policy Editor **setup** tool with the relevant command-line options.

The following table describes the relevant environment variables and command-line options. Learn more about using the environment variables in Starting PingAuthorize Policy Editor.

Environment variable	Command-line option	Description
PING_ADMIN_PORT	adminPort <port></port>	Specifies the admin port, where administrative task endpoints like periodic policy database backups are handled.
PING_BACKUP_SCHEDULE	backupSchedule <cron-expression></cron-expression>	 Specifies a cron expression to indicate when to perform backups. The default is 0 0 0 * * ?, which is midnight every day. Learn more in Quartz 2.3.0 cron format C. Onote The PAP evaluates the expression against the system timezone. For PingAuthorize Docker images, the default timezone is UTC.
PING_H2_BACKUP_DIR	N/A	Specifies the directory in which to place the policy H2 database backup files. The default is SERVER_ROOT /policy- backup . Note If you are using a Docker image, set this value to a directory on a volume that you mount when you start the Docker container.
N/A	disablePeriodicBackups	Turns off periodic policy database backups.

Learn more about using a backup in Restoring a policy database from a backup.

Restoring a policy database from a backup

The policy database stores Policy Editor items such as the Trust Framework, policies, and commit history. If someone accidentally deletes or changes those items or the database gets corrupted, restore the database from a backup.

For information about how to configure backups, see Policy database backups.

(i) Note

If you are using a managed RDBMS, such as PostgreSQL, instead of the default H2 database, make sure you implement backup strategies in line with your organization's best practices.

Not Using Docker

Restoring a database when not using Docker About this task

To restore a policy database when not in a Docker environment:

Steps

- 1. Ensure the Policy Editor server is no longer running by either using **bin/stop-server** or killing the process.
- 2. Locate the backup .zip file that you want to restore.

The default location is [.parmname] SERVER_ROOT /policy-backup. However, the location might have been changed using the PING_H2_BACKUP_DIR environment variable.

3. Extract the .zip file to the configured database location overwriting the previous policy database file, if present.

The default location is the root of the Policy Editor server installation directory. If it's not there, check the location specified by the **PING_H2_FILE** environment variable.

4. Start the Policy Editor server.

\$ bin/start-server

Using Docker

Restoring a database when using Docker About this task

To restore a policy database in a Docker environment:

Steps

1. Locate the backup .zip file that you want to restore.

The location should be a directory specified using the **PING_H2_BACKUP_DIR** environment variable, as mentioned in **Policy database backups**.

- 2. Extract the .zip file to the database location that you will specify using the PING_H2_FILE environment variable when you start the Docker container.
- 3. Start the Policy Editor Docker container with a mounted volume that has the extracted backup file and use **PING_H** 2_FILE to specify that backup file in the container file system.

For example, the following command assumes the uncompressed database file is named **Symphonic.mv.db** in the host file system. The **PING_H2_FILE** environment variable specifies the file name without the .mv.db extension.

```
$ docker run --network=<network_name> --env-file ~/.pingidentity/config \
    --env PING_H2_FILE=/opt/out/Symphonic \
    --volume <HOST_BACKUP_DIR>:/opt/out pingidentity/{PAP_CONTAINER_NAME}:<TAG>
```

О Тір

For proper communication between containers, create a Docker network using a command such as do cker network create --driver <network_type> <network_name>, and then connect to that network with the --network=<network_name> option.

(i) Note

The Docker image < TAG > used in the example is only a placeholder. For actual tag values, see **Docker** Hub \square .

Policy application management with signed deployment packages

Signed deployment packages ensure a PingAuthorize Server uses only deployment packages from a certain PingAuthorize Policy Editor, allowing you to avoid the use of packages intended for a different context or to use packages from only a designated source.

Use case: Distinct PingAuthorize deployments

Consider an organization with two distinct PingAuthorize deployments: healthcare and banking. Each deployment has a unique set of policies. Using the healthcare policies for the banking deployment, or vice versa, would make the deployment ineffective. Signed deployment packages avoid this issue. To set up signed deployment packages for these two deployments:

- 1. Set up the healthcare configuration.
 - 1. Create a signing key pair with a private key and a public key for healthcare.
 - 2. Set up a Policy Editor to create all healthcare policies. Configure that GUI to sign its deployment packages with the healthcare private key.
 - 3. Configure the healthcare PingAuthorize Server to use the healthcare public key to verify deployment packages. Now the healthcare deployment only accepts healthcare policies and does not accept banking policies.
- 2. Set up the banking configuration.
 - 1. Create a signing key pair with a private key and a public key for banking.
 - 2. Set up a Policy Editor to create all banking policies. Configure that GUI to sign its deployment packages with the banking private key.
 - 3. Configure the banking PingAuthorize Server to use the banking public key to verify deployment packages. Now the banking deployment only accepts banking policies and does not accept healthcare policies.

Use case: Designated source for deployment packages

An organization has several people who write policies. Each policy writer has their own Policy Editor to develop and test policies. However, to ensure the organization fully verifies each deployment package before it goes into preproduction or production, only one Policy Editor can actually sign deployment packages with the key accepted by the PingAuthorize Server.

Example: Configure signed deployment packages for healthcare

In this example, you configure a PingAuthorize Policy Editor to sign its deployment packages for a PingAuthorize Server dedicated to healthcare policies.

About this task

This example uses the **manage-certificates** tool that comes with PingAuthorize. The tool provides many of the same features as the Java **keytool** utility. If you prefer to use **keytool**, running **manage-certificates** --display-keytool-command shows a command that you can use to obtain a similar result.

Steps

- 1. Generate a signing key pair for the Policy Editor:
 - 1. Create a key pair consisting of a private key and the corresponding public key and put the key pair in a key store so that the Policy Editor can use it.

Example:

The following command performs both of these actions by generating a key store with a self-signed certificate:

```
$ manage-certificates generate-self-signed-certificate \
    --keystore "healthcare-pap-signing.jks" \
    --keystore-type jks \
    --keystore-password "<keystore-password>" \
    --private-key-password "<private-key-password>" \
    --alias "healthcare-pap" \
    --subject-dn "cn=Healthcare PAP,dc=example,dc=com" \
    --days-valid 90
```

- This command creates a key store with the name healthcare-pap-signing.jks, containing the Policy Editor's private signing key and the corresponding public key.
- The Policy Editor uses this key store to sign deployment packages.
- The key store itself and the private key each have passwords.
- The signing key pair has the alias healthcare-pap.
- The subject DN is arbitrary.
- The keys are valid for 90 days.
- 2. Export a public certificate from the Policy Editor's key store.

Example:

```
$ manage-certificates export-certificate \
    --keystore "healthcare-pap-signing.jks" \
    --keystore-password "<keystore-password>" \
    --alias "healthcare-pap" \
    --export-certificate-chain \
    --output-format pem \
    --output-file "healthcare-pap.pem"
```

This command creates a public certificate file with the name healthcare-pap.pem. This file becomes an input during the next step, and it is not used directly by either the Policy Editor or PingAuthorize. The public certificate specified by the -- alias argument represents the public key created in the previous step.

3. Create a trust store for PingAuthorize Server for the public certificate from the previous step.

Example:

```
$ manage-certificates import-certificate \
    --keystore "healthcare-pap-verification.jks" \
    --keystore-password "<keystore-password>" \
    --keystore-type jks \
    --alias "healthcare-pap" \
    --certificate-file "healthcare-pap.pem" \
    --no-prompt
```

This command creates a trust store with the name **healthcare-pap-verification.jks**, containing the Policy Editor's public certificate. PingAuthorize Server uses this trust store to verify that deployment packages created by the Policy Editor were actually created by that GUI.

4. Configure the Policy Editor to use the key store to sign the deployment packages it creates:

1. Make a copy of the default options file.

\$ cp config/options.yml my-options.yml

2. Edit the new options file for your policy deployment method, uncommenting the appropriate block and substituting your passwords and other values.

(j) Note

Using deploymentPackageData to define the signing key configuration only affects exported deployment packages. Deployment packages published to a store only use their store-specific configurations defined in the deploymentPackageStores block to apply a signing key.

3. Use the deploymentPackageData block to configure signing for exported deployment packages.

```
deploymentPackageData:
    # contentType: json
    # keystore:
    resource: /path/to/healthcare-pap-signing.jks
    # password: keystore-password
    # securityLevel: signed
    # signingKey:
    # alias: healthcare-pap
    # password: private-key-password
```

4. Under the deploymentPackageStores block, use the appropriate store type to configure signing for deployment packages published to a deployment package store.

```
deploymentPackageStores:
 # Define deployment package store publishing targets here.
 #
 # - name: Signed filesystem store
 # description: Signed file system directory store
 # type: filesystem
 # path: /path/to/signed-deployment-package-store/
 # securityLevel: signed
 # keystore:
 # resource: /path/to/healthcare-pap-signing.jks
 # password: keystore-password
 # signingKey:
 # alias: healthcare-pap
 #
      password: private-key-password
 # Other deployment package store types omitted for brevity...
```

^{5.} Stop the Policy Editor.

\$ bin/stop-server

6. Run **setup** using the --optionsFile my-options.yml argument.

Customize all other options as appropriate for your needs.

7. Start the Policy Editor.

\$ bin/start-server

- 5. Configure the PingAuthorize Server to use the trust store for verification so that it accepts only deployment packages created by this Policy Editor:
 - 1. Create a trust manager provider and include the path to the trust store file and the trust store's password.

The trust manager provider is how the PingAuthorize Server configuration refers to a trust store file.

```
$ dsconfig create-trust-manager-provider \
    --provider-name "Healthcare PAP Verification Store" \
    --type file-based \
    --set enabled:true \
    --set "trust-store-file:/path/to/healthcare-pap-verification.jks" \
    --set trust-store-type:JKS \
    --set "trust-store-pin:<truststore-password>"
```

2. Configure the policy decision service.

```
$ dsconfig set-policy-decision-service-prop \
    --set pdp-mode:embedded \
    --set "deployment-package</path/to/deployment-package.deploymentpackage" \
    --set deployment-package-security-level:signed \
    --set "deployment-package-trust-store:Healthcare PAP Verification Store" \
    --set "deployment-package-verification-key-nickname:healthcare-pap"</pre>
```

Deployment packages are only for the embedded PDP mode, so this command sets the **pdp-mode** property accordingly. The other properties are described in the following table.

Property	Description	
deployment-package- security-level	 Determines whether PingAuthorize Server require a deployment package to be signed. Valid values are: unsigned PingAuthorize Server does not check a deployment package for a trusted signature. This value is set by default. Signed PingAuthorize Server checks a deployment package for a trusted signature and rejects a deployment package that fails that check. Whenever a deployment package fails a check, PingAuthorize Server continues to use the last accepted deployment package. 	
deployment-package- trust-store	Specifies a trust manager provider, which specifies in turn a trust store containing a Policy Editor's public certificate. This property is required if the value of deployment-package-security-level is signed.	
deployment-package- verification-key- nickname	Specifies the alias of the Policy Editor's public certificate. This property is required if the value of deployment-package-security-level is signed.	

(j) Note

For more information about the properties, see the *Configuration Reference* located in the server's **docs/config-guide** directory.

Configuring Trust Framework attribute caching for production

For higher environments, including testing and production, you can define an external attribute cache for the Trust Framework.

With the Policy Decision Service set to embedded policy decision point (PDP) mode, the PingAuthorize Server is configured by default to cache attribute values in memory (for any attributes with a defined caching strategy). Alternatively, you can define an external attribute cache using the following Redis modes:

- Single Redis instance
- Single Redis instance using TLS
- Replicated Redis
- Redis Sentinel
- Amazon Web Services (AWS) ElastiCache Redis

Using the GUI

Setting up Redis external attribute caching in the UI Before you begin

To successfully assign an external Redis attribute cache to the Policy Decision Service, you must set **PDP Mode** to **embedded**.

Steps

- 1. On the **Configuration** page of the PingAuthorize Administration Console, go to **Authorization and Policies** → **External Attribute Caches**.
- 2. Select your desired Redis mode from the New External Attribute Cache list.

Example:

•	
local PingAuthorize Server 1 / Configuration / External Attribute Caches ?? External Attribute Caches represent locations where the PingAuthorize Server can connect to an External Attribute Cache.	Configuration Guide
A The Console is not configured with a trust store so it will automatically trust the certificate associated with local PingAuthorize Server 1.	×
New External Attribute Cache •	Search Q
Redis Elasticache External Attribute Cache Redis Elasticache External Attribute Caches represent locations where the PingAuthorize Server can connect to an external Redis ElastiCache deployment.	Actions
Redis Replicated External Attribute Cache Redis Replicated External Attribute Caches represent locations where the PingAuthorize Server can connect to a Redis Cluster.	Actions 🗸
Redis Sentinel External Attribute Cache Redis Sentinel External Attribute Caches represent locations where the PingAuthorize Server can connect to external Redis caches deployed in a sentinel configuration.	
Redis Single Instance External Attribute Cache Redis Single Instance External Attribute Caches represent locations where the PingAuthorize Server can connect to a single external Resis cache	◀

3. At minimum, enter the required values, as indicated by a red asterisk, and click **Save To PingAuthorize Server Cluster**.

Note
For more information on a field, click the question mark icon.

Example:

i

💰 local PingAuthorize Server 1 / Configuration / External Attribute Caches /					
New Redis Single Instance External Attribute Cache 🖉					
A The Console is not a	A The Console is not configured with a trust store so it will automatically trust the certificate associated with local PingAuthorize Server 1.				
			View API commands Save To PingAuthorize Server Cluster Cancel		
Name *	Redis Single Instance External Attribute Cache	0	↑		
Redis Node Addresses *	redis://example.com:6479	0 0			
Username		0			
Password	Set Value 🕜				

- 4. Go to Authorization and Policies \rightarrow Policy Decision Service.
- 5. Select your Redis cache name from the External Attribute Cache list in the Trust Framework Attribute Cache Configuration section and click Save To PingAuthorize Server Cluster.

Example:

Edit Policy Decision Se	
he Policy Decision Service contains the p	roperties that affect the overall operation of the PingAuthorize Server policy service.
A The Console is not configured wit	h a trust store so it will automatically trust the certificate associated with local PingAuthorize Server 1.
	View API commands Save To PingAuthorize Server Cluster Cancel
General Configuration	
DP Mode	embedded x - 🖸 💿
olicy Server	- / + 0
eployment Package Source Type	store x - 🔿 💿
Deployment Package Store (Configuration
	ployment store X - V + O
Trust Framework Attribute Ca	iche Configuration
External Attribute Cache Single Inst	ance Cache #2 X - X + 0
Deployment Package Static-	ile Configuration
Deployment Package	No data available
	Load From File
eployment Package Security Level	unsigned X -
Deployment Package Trust Store - 🖌 + 💿	
Deployment Package Verification Key	
lickname	
Policy Request Configuration	
ana a la c	
ample:	
💮 Note	
(i) Note	
Alternat	ively, you can use the controls next to the External Attribute Cache list to create, edit, or
	external Redis caches:
° (Click the Plus icon to create a new external attribute cache.

- $^\circ\,$ Click the Pencil icon to edit the configuration of the selected attribute cache.
- Click X to remove the attribute cache from the Policy Decision Service and revert the PDP to an in-memory attribute cache.

Using dsconfig

Setting up Redis external attribute caching with dsconfig Before you begin

When using the **dsconfig set-policy-decision-service-prop** command, the new configuration must still be compliant with the following:

- The pdp-mode property must be set to embedded.
- The deployment-package-source-type property must be set to store or static-file.
 - If the deployment-package-source-type property is set to store, the deployment-package-store property must resolve to a valid deployment package store.
 - If the deployment-package-source-type property is set to static-file, the deployment-package-store property must resolve to a valid deployment package.

About this task

Here are the configuration options available for creating Redis external caches using the **dsconfig** tool. When using the **dsconfig create-external-attribute-cache** command, the new configuration must still be compliant with the required attributes associated with the specified cache type:

Option	Description	
mode	Required. Specifies Redis mode. Accepted values: <pre>single_instance</pre> , <pre>replicated</pre> , <pre>elasticache</pre> , or <pre>sentinel</pre> .	
nodeAddresses	Required, only when mode is single_instance , replicated , or sentinel . Defines node addresses. A comma-separated list of Redis nodes.	
replicationGroupId	Required, only when mode is elasticache. Replication group ID.	
masterName	Required, only when mode is sentinel. Specifies name of the master node.	
database	Optional, only when mode is sentinel. Database index used for Redis connection. Default value is 0.	
scanInterval	Optional, only when mode is sentinel . Redis cluster scan interval in milliseconds. Default value is 1000 .	
checkSentinelList	Optional, only when mode is sentinel . Enables Sentinels list check during startup. Default value is false .	
username	Optional, only when AUTH token authentication is enabled in the Redis provider.	
password	Optional, only when AUTH token authentication is enabled in the Redis provider.	

Steps

1. Create the external attribute cache using the **dsconfig create-external-attribute-cache** command. For example:

Example:

```
$ dsconfig create-external-attribute-cache \
    --cache-name 'Single Instance' \
    --type redis-single-instance \
    --set redis-node-addresses:redis://localhost:6379
```

2. Assign the defined external attribute cache to the Policy Decision Service. For example:

Example:

```
$ dsconfig set-policy-decision-service-prop \
    --set 'external-attribute-cache:Single Instance'
```

Result

Your external attribute cache has been defined and attached to the Policy Decision Service. There is no need to restart the server.

User profile availability in policies

In a policy, you might need to make a decision based on something about the requesting identity, meaning the access token subject or token owner. PingAuthorize can automatically look up the token owner's attributes and provide them in the policy request using a token resource lookup method.

Token resource lookup methods

PingAuthorize provides built-in support for retrieving token owner data using

paz_token_resource_lookup.adoc#section_jbj_xnk_1mb. Using a SCIM token resource lookup method requires a SCIM resource type to be configured, along with its prerequisite configuration objects. For information about SCIM configuration, such as SCIM resource types, store adapters, load-balancing algorithms, and LDAP external servers, see SCIM configuration basics.

For examples that show how to set up a token resource lookup method, see:

- Configuring the PingAuthorize OAuth subject search
- Sideband access token validation
- paz_token_resource_lookup.adoc#section_jbj_xnk_1mb

User profile data from access tokens

When processing an incoming HTTP request, PingAuthorize Server invokes any applicable access token validators to parse the request's access token. If an access token validator successfully validates the access token, it then invokes any related token resource lookup methods. If a token resource lookup method succeeds in retrieving the attributes for the token owner, then PingAuthorize Server includes a **TokenOwner** attribute with the policy request. The contents of the **TokenOwner** attribute are a JSON object containing the user profile.

The exact structure of the **TokenOwner** attribute varies from deployment to deployment. When using a SCIM token resource lookup method, the contents of the **TokenOwner** attribute are a SCIM resource using the schema of the SCIM resource type configured for the token resource lookup method, exactly as if the resource had been retrieved via an HTTP GET without policy restrictions. For example, for a **pass-through** SCIM resource type for the LDAP inetOrgPerson object class, a **TokenOwner** value might look like the following.

```
{
    "cn": [
      "Mark E. Smith"
   ],
    "employeeNumber": "1",
   "entryDN": "uid=mark.e.smith,ou=people,dc=example,dc=com",
   "entryUUID": "8ac3d8b5-4f17-33fa-a4b4-854599ed9a89",
    "givenName": [
       "Mark"
    ],
    "id": "8ac3d8b5-4f17-33fa-a4b4-854599ed9a89",
    "initials": [
      "MES"
    ],
    "1": [
       "Manchester"
    ],
    "mail": [
       "mark.e.smith@example.com"
    ],
    "meta": {
       "location": "https://example.com/scim/v2/Users/8ac3d8b5-4f17-33fa-a4b4-854599ed9a89",
"resourceType": "Users"
   },
    "mobile": [
        "+44 161 872 37676"
    ],
    "modifyTimestamp": "2020-06-03T03:56:54.168Z",
    "objectClass": [
       "top",
       "person",
       "organizationalPerson",
       "inetOrgPerson"
   ],
    "schemas": [
        "urn:pingidentity:schemas:store:2.0:UserStoreAdapter"
    ],
    "sn": [
       "Smith"
    ],
    "uid": [
       "mark.e.smith"
    ]
}
```

The default Trust Framework includes a **TokenOwner** attribute as an empty JSON object. If you need to use a user profile attribute from a policy, add the attribute as a child of **TokenOwner** in the Trust Framework.

For example, the SCIM user profile shown above uses the mail attribute to store a user's email addresses. To make policy decisions involving the token owner's email address, you can add an Emails attribute under TokenOwner in the PingAuthorize Policy Editor, as shown in the following Trust Framework image.

Definitions Target Search				
Domains Services Attributes Identity Classes	Identity Providers Identity Prop	erties Actions Conditions Proces	sors	
+	Details History Test			
 Gateway HttpRequest impactedAttributes SCIM2 	Semails			=
 SCIM2 TokenOwner 				
S Emails	Parent	TokenOwner		-
	 Resolvers (1 total) 			
	Attribute - Toke Resolve attribute us			≡
	Resolver type	Attribute	✓ TokenOwner	•
	+ Add Resolver Value Processors (1 to	otal)		
	Untitled JSON F	Path Processor		Ŵ
	Processor	JSON Path 👻	mail	0
	Value type	Collection -		
	+ Add Processor Value Settings			
	Default value			
	Туре	Collection	✓ Secret	

Access token validators

access token validators verify the tokens that client applications submit when they request access to protected resource.

Specifically, access token validators translate an access token into a data structure that constitutes part of the input for policy processing.

To authenticate to PingAuthorize Server's HTTP services, clients use OAuth 2 bearer token authentication \square to present an access token in the HTTP Authorization request header:

```
"Authorization": "Bearer <access-token>"
```

(i) Note

PingAuthorize does not support the use of query parameters for token validation.

To process the incoming access tokens, PingAuthorize Server uses access token validators, which determine whether to accept an access token and translate it into a set of properties, called claims.

Most access tokens identify a user, also called the token owner, as its subject (SAML). Access token validators can retrieve the token owner's attributes from the datastore using a related component called a token resource lookup method. The user data obtained by a token resource lookup method is sent to the policy decision point (PDP) so that policies can determine whether to authorize the request.


For more information about the types of access tokens PingAuthorize can validate, see Access token validator types.

For information about validating a JSON Web Token (JWT) in policy instead of using a validator, see Conditions.

About access token validator processing

Each access token validator possesses an evaluation order index, an integer that determines its processing priority. Lower values are processed before higher values.

The following image shows the validation process when using an access token validator with the System for Cross-domain Identity Management (SCIM) token resource lookup method.



- 1. If an inbound HTTP request contains an access token, PingAuthorize sends the token to the access token validator with the lowest evaluation order index.
- 2. The access token validator validates the access token.

Validation logic varies by access token validator type, but the validator generally verifies the following information:

- A trusted source issued the token.
- The token is not expired.

If the token is valid, its active flag is set to true. The flag and other access token claims are added to the HttpRequest.AccessToken attribute of the policy request.

3. If the access token contains a subject, the access token validator sets the user_token flag to true and uses a token resource lookup method to fetch the token owner through SCIM.

A token resource lookup defines a SCIM filter that locates the token owner. If the lookup succeeds, the resulting SCIM object is added to the policy request as the **TokenOwner** attribute.

(i) Note

For deployments that don't use SCIM, token owner attributes can be retrieved from other user store types by writing a token resource lookup method extension with the Server SDK. For more information, see User profile availability in policies.

- 4. If the access token validator is unable to validate the access token, it passes the token to the access token validator with the next lowest evaluation order index, and the previous two steps are repeated.
- 5. HTTP request processing continues, and the policy request is sent to the PDP.
- 6. Policies inspect the HttpRequest.AccessToken and TokenOwner attributes to make access control decisions.

Access tokens issued using the OAuth 2 client credentials grant type are issued directly to a client and do not contain a subject. An access token validator always sets the HttpRequest.AccessToken.user_token flag to false for such tokens, which are called application tokens, in contrast to tokens with subjects, which are called user tokens. Because authorization policies often grant a broad level of access for application tokens, you should configure such policies to always check the HttpRequest.AccessToken.user_token flag.

Access token validators determine whether PingAuthorize Server accepts an access token and uses it to provide key information for access-control decisions, but they are neither the sole nor the primary means of managing access. The responsibility for request authorization falls upon the PDP and its policies. This approach allows an organization to tailor access-control logic to its specific needs.

Access token validator types

PingAuthorize Server works with many different types of access token validators.

Click the tabs to learn more about the following types of access token validators:

- PingFederate
- JSON Web Token (JWT)
- Mock access token
- Third-party
- External application programming interface (API) gateway

PingFederate

PingFederate access token validator

To verify the access tokens that a PingFederate authorization server issues, the PingFederate access token validator uses HTTP to submit the tokens to PingFederate Server's token introspection endpoint.

This step allows the authorization server to determine whether a token is valid.

i Note

If you are using PingFederate 10.0 or earlier, ensure that PingFederate is configured to respond to OAuth and OpenID Connect (OIDC) requests by selecting the Enable OAuth 2.0 Authorization Server (AS) role and OpenID Connect check boxes, as explained in Enabling the OAuth AS role ^C. Starting with PingFederate 10.1, these items are always enabled.

Because this step requires an outgoing HTTP request to the authorization server, the PingFederate access token validator might perform slower than other access token validator types. The validation result is guaranteed to be current, which is an important consideration if the authorization server permits the revocation of access tokens.

Before attempting to use a PingFederate access token validator, create a client \square that represents the access token validator in the PingFederate configuration. This client must use the Access Token Validation grant type.

Example PingFederate access token validator configuration

In PingFederate, create a client with the following properties:

- Client ID: PingAuthorize
- Client authentication: Client Secret
- Allowed grant types: Access Token Validation

Take note of the client secret that is generated for the client, and use PingAuthorize Server's **dsconfig** command to create an access token validator:

```
# Change the host name and port below, as needed
dsconfig create-external-server \
 --server-name "{pingfed} External Server" \
  --type http \
  --set base-url:https://example.com:9031
# Create the Access Token Validator
dsconfig create-access-token-validator \
  --validator-name "{pingfed} Access Token Validator" \
 --type ping-federate \
 --set enabled:true \
 --set "authorization-server:{pingfed} External Server" \
 --set client-id:{pingauthorize} \
 --set "client-secret:<client secret>"
 --set evaluation-order-index:2000
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
  --validator-name "{pingfed} Access Token Validator" \
 --method-name "User by uid" \
 --type scim \
  --set scim-resource-type:Users \
 --set 'match-filter:uid eq "%sub%"' \
  --set evaluation-order-index:1000
```

Replace <*client secret*> with the client secret value generated by the PingFederate client.

JWT

JWT access token validator

The JWT access token validator verifies access tokens that are encoded in JWT format, which can be signed in JSON web signature (JWS) format or signed and encrypted in JSON web encryption (JWE) format.

The JWT access token validator inspects the JWT token without presenting it to an authorization server for validation. Because the JWT access token validator doesn't make a token introspection request for every access token that it processes, it performs faster than the PingFederate access token validator. The access token is self-validated however, so the JWT access token validator cannot determine whether the token has been revoked.

Supported JWS/JWE features

For signed tokens, the JWT access token validator supports the following JWT web algorithm (JWA) types:

- RS256
- RS384
- RS512
- ES256
- ES384
- ES512

For encrypted tokens, the JWT access token validator supports the following key-encryption algorithms:

- RSA-OAEP
- ECDH-ES
- ECDH-ES+A128KW
- ECDH-ES+A192KW
- ECDH-ES+A256KW

For encrypted tokens, the JWT access token validator supports the following content-encryption algorithms:

- A128CBC-HS256
- A192CBC-HS384
- A256CBC-HS512

The JWT access token validator configuration defines three allow lists for the JWS/JWE signing and encryption algorithms that it will accept. You should customize these allow lists to reflect only the signing and encryption algorithms used by your access token issuer and no others. Doing so minimizes the access token validator's security threat surface.

Configure these allow lists using the following configuration properties.

Property	Description
allowed-signing-algorithm	Specifies the signing algorithms that the access token validator accepts.
allowed-key-encryption-algorithm	Specifies the key-encryption algorithms that the access token validator accepts.
allowed-content-encryption-algorithm	Specifies the content-encryption algorithms that the access token validator accepts.

Mock access token

Mock access token validator

A mock access token validator is a special access token validator type used for development or testing purposes. It accepts arbitrary tokens without validating whether a trusted source issued them. This approach allows a developer or tester to make bearer token-authenticated requests without first setting up an authorization server.

Mock access tokens are formatted as plain-text JSON objects using standard JWT claims.

Always provide the Boolean active claim when creating a mock token. If this value is true, the token is accepted. If this value is false, the token is rejected.

If the **sub** claim is provided, a token owner lookup populates the **TokenOwner** policy request attribute, as with the other access token validator types.

The following example cURL command provides a mock access token in an HTTP request:

```
curl -k -X GET https://localhost:8443/scim/v2/Me -H 'Authorization: Bearer {"active": true, "sub":"user.3",
"scope":"email profile", "client":"client1"}'
```

🆒 Important

Never use mock access token validators in a production environment because they do not verify whether a trusted source issued an access token.

Example

Example mock access token validator configuration

The configuration for a mock access token validator resembles the configuration for a JWT access token validator. However, the JSON web signature (JWS) signatures require no configuration because mock tokens are not authenticated.

```
# Create the Access Token Validator
dsconfig create-access-token-validator \
   --validator-name "Mock Access Token Validator" \
   --type mock --set enabled:true \
   --set evaluation-order-index:9999
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
   --validator-name "Mock Access Token Validator" \
   --wethod-name "User by uid" \
   --type scim \
   --set 'match-filter:uid eq "%sub%"' \
   --set evaluation-order-index:1000
```

Third-party

Third-party access token validator

To create custom access token validators, use the Server SDK.

External API gateway

External API gateway access token validator

An external API gateway access token validator is a special access token validator that the Sideband API can use when the API gateway itself can validate and parse access tokens. This type of access token validator accepts a set of parsed access token claims from a trusted gateway and performs no further parsing or validation of its own. For information about how the tokens are processed, see Sideband access token validation.

i) Note

External API gateway access token validators are exclusively for use by Sideband API endpoints. If you assign an external API gateway access token validator to any other server component, either explicitly or implicitly, it is ignored.

Example configuration

The following example shows how to configure an external API gateway access token validator with a token resource lookup method and assign it to an existing Sideband API endpoint:

```
dsconfig create-access-token-validator \
    --validator-name "API Gateway Access Token Validator" \
    --type external-api-gateway \
    --set enabled:true \
    --set evaluation-order-index:0
dsconfig create-token-resource-lookup-method \
    --validator-name "API Gateway Access Token Validator" \
    --method-name "Users by uid" \
    --type scim \
    --set scim-resource-type:Users \
    --set 'match-filter:uid eq "%sub%"' \
    --set evaluation-order-index:0
dsconfig set-sideband-api-endpoint-prop \
    --endpoint-name "My API" \
    --set "access-token-validator:API Gateway-Provided Access Token Validator"
```

Handling signed JWTs

All access tokens the JSON web token (JWT) access token validator handles must be cryptographically signed by the token issuer. The JWT access token validator validates a token's signature using a public signing key provided by the issuer.

Steps

• Configure the JWT access token validator with the issuer's public signing key in one of the following ways:

Choose from:

 Store the public key as a trusted certificate in PingAuthorize Server's local configuration using the signingcertificate property.

The following example configures a JWT access token validator to use a locally stored public signing certificate to validate access token signatures. The signing certificate is assumed to have been obtained out of band and must be a PEM-encoded X.509v3 certificate.

```
# Add the public signing certificate to the server configuration
dsconfig create-trusted-certificate \
  --certificate-name "JWT Signing Certificate" \
  --set "certificate</path/to/signing-certificate.pem"
# Create the Access Token Validator
dsconfig create-access-token-validator \
  --validator-name "JWT Access Token Validator" \
  --type jwt \
  --set enabled:true \
  --set allowed-signing-algorithm:RS256 \
  --set "signing-certificate:JWT Signing Certificate"
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
  --validator-name "JWT Access Token Validator" \
  --method-name "User by uid" \
  --type scim \
  --set scim-resource-type:Users \
  --set 'match-filter:uid eq "%sub%"' \
  --set evaluation-order-index:1000
```

Provide the issuer's JSON Web Key Set (JWKS) endpoint using the jwks-endpoint-path property. The JWT access token validator then retrieves the issuer's public keys when it initializes. This method ensures that the JWT access token validator uses updated copies of the issuer's public keys.

The following example configures a JWT access token validator to retrieve public keys from a PingFederate authorization server's JWKS endpoint.

```
# Change the host name and port below, as needed
dsconfig create-external-server \
  --server-name "{pingfed} External Server" \
  --type http \
  --set base-url:https://example.com:9031
# Create the Access Token Validator
dsconfig create-access-token-validator \
  --validator-name "JWT Access Token Validator" \
  --type jwt \
  --set enabled:true \
  --set allowed-signing-algorithm:RS256 \
  --set "authorization-server:{pingfed} External Server" \
  --set jwks-endpoint-path:/ext/oauth/jwks
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
  --validator-name "JWT Access Token Validator" \
  --method-name "User by uid" \
  --type scim \
  --set scim-resource-type:Users \
  --set 'match-filter:uid eq "%sub%"' \
  --set evaluation-order-index:1000
```

Handling signed and encrypted JWTs

The JSON web token (JWT) access token validator can accept encrypted access tokens. To enable this functionality, you must configure the access token validator with a private/public key pair and provide the public key to the token issuer.

About this task

The examples in each step configure a JWT access token validator to handle access tokens signed and encrypted using elliptic curve algorithms. For RSA signing and encryption algorithms, the configuration is similar, but you would choose different values for the allowed-signing-algorithm and allowed-encryption-algorithm properties.

Steps

1. Create an encryption key pair.

Example:

```
# Create an encryption key pair
dsconfig create-key-pair \
    --pair-name "JWT Elliptic Curve Encryption Key Pair" \
    --set key-algorithm:EC_256
```

2. Create the JWT access token validator:

Choose from:

 Store the public key as a trusted certificate in PingAuthorize Server's local configuration using the signingcertificate property.

The following example configures a JWT access token validator to use a locally stored public signing certificate to validate access token signatures. The signing certificate is assumed to have been obtained out of band and must be a PEM-encoded X.509v3 certificate.

```
# Add the public signing certificate to the server configuration
dsconfig create-trusted-certificate \
  --certificate-name "JWT Signing Certificate" \
  --set "certificate</path/to/signing-certificate.pem"
# Create the Access Token Validator
dsconfig create-access-token-validator \
  --validator-name "JWT Access Token Validator" \
  --type jwt \
 --set enabled:true \
  --set allowed-signing-algorithm:ES256 \
  --set "signing-certificate:JWT Signing Certificate" \
  --set "encryption-key-pair:JWT Elliptic Curve Encryption Key Pair" \
  --set allowed-key-encryption-algorithm:ECDH_ES
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
  --validator-name "JWT Access Token Validator" \
  --method-name "User by uid" \
  --type scim \
  --set scim-resource-type:Users \
  --set 'match-filter:uid eq "%sub%"' \
  --set evaluation-order-index:1000
```

Provide the issuer's JSON Web Key Set (JWKS) endpoint using the jwks-endpoint-path property. The JWT access token validator then retrieves the issuer's public keys when it initializes. This method ensures that the JWT access token validator uses updated copies of the issuer's public keys.

The following example configures a JWT access token validator to retrieve public keys from a PingFederate authorization server's JWKS endpoint.

```
# Change the host name and port below, as needed
dsconfig create-external-server \
  --server-name "{pingfed} External Server" \
  --type http \
  --set base-url:https://example.com:9031
# Create the Access Token Validator
dsconfig create-access-token-validator \
  --validator-name "JWT Access Token Validator" \
  --type jwt \
  --set enabled:true \
 --set allowed-signing-algorithm:ES256 \
  --set "authorization-server:{pingfed} External Server" \
  --set jwks-endpoint-path:/ext/oauth/jwks \
  --set "encryption-key-pair:JWT Elliptic Curve Encryption Key Pair" \
  --set allowed-key-encryption-algorithm:ECDH_ES
# Match the token's subject (sub) claim to the uid attribute
# of a SCIM resource
dsconfig create-token-resource-lookup-method \
  --validator-name "JWT Access Token Validator" \
  --method-name "User by uid" \
  --type scim \
  --set scim-resource-type:Users \
  --set 'match-filter:uid eq "%sub%"' \
  --set evaluation-order-index:1000
```

3. Export the public encryption key from PingAuthorize Server and provide it to your token issuer.

i) Note

Without this public encryption key, the issuer cannot encrypt tokens that can be decrypted by the JWT access token validator.

Example:

You can run **dsconfig** to copy the public key to a file, or you can copy the value of the key pair's **certificate-chain** property in the administrative console. Be prepared to enter your connection properties and bind password when prompted.

```
dsconfig get-key-pair-prop \
    --pair-name "JWT Elliptic Curve Encryption Key Pair" \
    --property certificate-chain
```

Token resource lookup methods

Access token validators can use token resource lookup methods to search a datastore and retrieve the subject's profile data for use in policy decisions.

Most access tokens include a subject, which identifies the user who granted access to the application using the token. Token resource lookup methods use the access token subject value, which is usually a string identifier such as a GUID or username, to perform a search in an external datastore, such as a PingDirectory Server or an API providing user data. For this reason, the datastore or API must be accessible to PingAuthorize Server; and in most cases, it should be the same datastore or API used by the authorization server that issues the access tokens. After the lookup completes, the token subject's user attributes get passed into the policy request's **TokenOwner** attribute, allowing policies to make decisions based on some aspect of the user.

i Νote

Using a token resource lookup method is optional. If your policies don't need user profile information, you don't need to configure token resource lookup methods.

PingAuthorize Server provides the following types of token resource lookup methods:

- SCIM token resource lookup methods
- Third-party token resource lookup methods

SCIM token resource lookup methods

System for Cross-domain Identity Management (SCIM) token resource lookup methods use PingAuthorize Server's SCIM subsystem to retrieve a token subject's attributes.

i Note

Before you create a SCIM token resource lookup method, you must configure SCIM. See SCIM configuration basics.

To configure a SCIM token resource lookup method, you need to know the name of the access token claim that the authorization server uses for the subject identifier (typically, **sub**). You also need to know which user attribute is used as the subject identifier by the authorization server when it issues access token. If you have configured a mapping SCIM resource type, then the attribute name used by the authorization server and the attribute name in your SCIM schema might differ.

A SCIM token resource lookup method retrieves the token subject's attributes using the combination of the scim-resource-type and match-filter configuration properties.

Property	Description
scim-resource-type	The SCIM resource type that represents users that can be access token subjects.
match-filter	A SCIM 2 filter expression that matches a SCIM resource based on one or more access token claims.

The match-filter value must be a valid SCIM 2 filter expression that uniquely matches a single resource. The filter expression can include one or more variables that refer to claims found in the access token. These variables are indicated by enclosing a token claim name in percent (%) characters. When the token resource lookup method is invoked, the variable is filled in with the actual value from the access token claim.

For example, if a match filter has the value id eq "%sub%" and an access token contains a sub claim with the value 8ac3d8b5-4f 17-33fa-a4b4-854599ed9a89, then the token resource lookup method performs a SCIM search using the filter id eq "8ac3d8b5-4f17-33fa-a4b4-854599ed9a89".

Example

The following example shows how to create a SCIM token resource lookup method using **dsconfig**. It assumes that a SCIM resource type called **Users** and an access token validator called **JWT** Access Token Validator already exist.

```
dsconfig create-token-resource-lookup-method
   --validator-name "JWT Access Token Validator" \
   --method-name "User by uid" \
   --type scim \
   --set evaluation-order-index:10 \
   --set scim-resource-type:Users \
   --set 'match-filter:uid eq "%sub%"'
```

Third-party token resource lookup methods

A third-party token resource lookup method is a custom implementation of a token resource lookup method that you write using the Server SDK. A third-party token resource lookup method can be useful for PingAuthorize Server deployments where SCIM is not otherwise needed. For example, you could use a third-party token resource lookup method to connect a PingAuthorize Server to a system that stores user data in a cloud directory.

For more information about writing custom server extensions, see the Server SDK documentation.

Server configuration

For a detailed look at configuration, see the Ping Identity PingAuthorize Server *Configuration Reference*, located in the server's docs/config-guide directory.

This section covers basic server configuration.

PingAuthorize Server is built upon the same foundation as PingDirectory Server. Both servers use a common configuration system, and their configurations use the same tools and APIs.

The configuration system is fundamentally LDAP-based, and configuration entries are stored in a special LDAP backend, called **cn** =config. The structure is a tree structure, and configuration entries are organized in a shallow hierarchy under cn=config.

Administration accounts

Administration accounts, called root distinguished names (DNs), are stored in a branch of the configuration backend: cn=Root DNs, cn=config.

When setup is run, the process creates a superuser account that is typically named **cn=Directory Manager**. Although PingAuthorize Server is not an LDAP directory server, it follows this convention by default. As a result, its superuser account is also typically named **cn=Directory Manager**.

To create additional administration accounts, use **dsconfig** or, to add root DN users, use the PingAuthorize administrative console.

About the dsconfig tool

The dsconfig tool provides a command-line interface to configure the underlying server configuration.

Use the **dsconfig** tool whenever you administer the server from a shell. When run without arguments, **dsconfig** enters an interactive mode that lets you browse and update the configuration from a menu-based interface. Use this interface to list, update, create, and delete configuration objects.

When viewing any configuration object in dsconfig, use the d command to display the command line that is necessary to recreate a configuration object. You can use a command line in this form directly from a shell or placed in a dsconfig batch file, along with other commands.

Batch files are a powerful feature that enable scripted deployments. By convention, these scripts use a file extension of **dsconfig**. Batch files support comments by using the **#** character, and they support line continuation by using the ****, or backslash, character.

Example

This example dsconfig script configures the PingAuthorize Server policy service.

```
# Define an external {pingauthorize} PAP
dsconfig create-external-server \
    --server-name "{pingauthorize} {PAP_Name}" \
    --type policy \
    --set base-url:http://localhost:4200 \
    --set user-id:admin \
    --set "branch:Default Policies"
# Configure the policy service
dsconfig set-policy-decision-service-prop \
    --type scim \
    --set pdp-mode:external \
    --set "policy-server:{pingauthorize} PAP" \
    --set "decision-response-view:request" \
    --set "decision-response-view:decision-tree"
```

Example

To load a dsconfig batch file, run dsconfig with the --batch-file argument.

```
$ {pingauthorize}/bin/dsconfig -n --batch-file example.dsconfig
Batch file 'example.dsconfig' contains 2 commands.
Pre-validating with the local server ..... Done
Executing: create-external-server -n --server-name "{pingauthorize} PAP" --type policy --set base-url:http://
localhost:4200 --set "branch:Default Policies"
Arguments from tool properties file: --useSSL --hostname localhost --port 8636 --bindDN cn=root --bindPassword * --
trustAll
The Policy External Server was created successfully.
Executing: set-policy-decision-service-prop -n --set pdp-mode:external --set "policy-server:{pingauthorize} PAP" --
set
decision-response-view:request --set decision-response-view:decision-tree
The Policy Decision Service was modified successfully.
```

PingAuthorize administrative console

The PingAuthorize administrative console is a web-based application that provides a graphical configuration and administration interface. It is available by default from the **/console** path.

Setting the console session timeout

The session timeout for the console is 24 hours by default. When this duration is exceeded, all inactive users are logged off automatically.

To set a different timeout value, configure the **server.sessionTimeout** application parameter, which specifies the timeout duration in seconds. You can set the value as an init parameter either in the console or on the command line.

• Console

In the PingAuthorize administrative console, go to **Web Application Extensions** \rightarrow **Console**. Specify the timeout value in the **Init Parameter** field.

Command line

Use the dsconfig tool. The following example uses a value of 1800 seconds (30 minutes).

```
dsconfig set-web-application-extension-prop --no-prompt \
--extension-name Console \
--add init-parameter:server.sessionTimeout=1800
```

For the changes to take effect, restart the HTTP(S) Connection Handler, or the server itself.

About the configuration audit log

The configuration audit log records the configuration commands that represent configuration changes, as well as the configuration commands that undo the changes.

All successful configuration changes are recorded to the file logs/config-audit.log.

Example

```
$ tail -n 8 {pingauthorize}/logs/config-audit.log
# [23/Feb/2019:23:16:24.667 -0600] conn=4 op=12 dn='cn=Directory Manager,cn=Root DNs,cn=config' authtype=[Simple]
from=127.0.0.1 to=127.0.0.1
# Undo command: dsconfig delete-external-server --server-name "{pingauthorize} PAP"
dsconfig create-external-server --server-name "{pingauthorize} PAP" --type policy --set base-url:http://localhost:
4200 --set "branch:Default Policies"
# [23/Feb/2019:23:16:24.946 -0600] conn=5 op=22 dn='cn=Directory Manager,cn=Root DNs,cn=config' authtype=[Simple]
from=127.0.0.1 to=127.0.0.1
# This change was made to mirrored configuration data, which is automatically kept in sync across all servers.
# Undo command: dsconfig set-policy-decision-service-prop --set "policy-server:{pingauthorize} Cateway Policy
Example)"
dsconfig set-policy-decision-service-prop --set "policy-server:{pingauthorize} PAP"
```

About the config-diff tool

The config-diff tool compares server configurations and produces a dsconfig batch file that lists the differences.

When run without arguments, the **config-diff** tool produces a list of changes to the configuration, as compared to the server's baseline or out-of-the-box configuration. Because this list captures the customizations of your server configuration, it is useful when you transition from a development environment to a staging or production environment.

Example

```
$ {pingauthorize}/bin/config-diff
# No comparison arguments provided, so using "--sourceLocal --sourceTag postSetup --targetLocal" to compare the local
configuration with the post-setup configuration.
# Run "config-diff --help" to get a full list of options and example usages.
# Configuration changes to bring source (config-postSetup.gz) to target (config.ldif)
# Comparison options:
# Ignore differences on shared host
   Ignore differences by instance
#
  Ignore differences in configuration that is part of the topology registry
dsconfig create-external-server --server-name "DS API Server" --type api
--set base-url:https://localhost:1443 --set hostname-verification-method:allow-all --set "trust-manager-
provider:Blind Trust" --set user-name:cn=root --set "password:AADaK6dtmjJQ7W+urtx9RGhSvKX9qCS8q5Q="
dsconfig create-external-server --server-name "FHIR Sandbox" --type api
--set base-url:https://fhir-open.sandboxcerner.com[https://fhir-open.sandboxcerner.com]
. . .
```

Certificates

The server presents a server certificate when a client uses a protocol like LDAPS or HTTPS to initiate a secure connection. A client must trust the server's certificate to obtain a secure connection to it.

PingAuthorize Server uses server certificates.

During setup, administrators have the option of using self-signed certificates or certificate authority (CA)-signed certificates for the server certificate. Use CA-signed certificates wherever possible. Use self-signed certificates for demonstration and proof-of-concept environments only.

If you specify the option --generateSelfSignedCertificate during setup, the server certificate generates automatically with the alias server-cert. The key pair consists of the private key and the self-signed certificate, and is stored in a file named keystore, which resides in the server's /config directory. The certificates for all the servers that the server trusts are stored in the truststore file, which is also located under the server's /config directory.

To override the server certificate alias and the files that store the key pair and certificates, use the following arguments during setup:

- --certNickname
- --use*Keystore
- --use*Truststore

For more information about these arguments, see the setup tool's *Help and the Installation Guide*.

Replacing the server certificate

Whether the server was set up with self-signed or certificate authority (CA)-signed certificates, the steps to replace the server certificate are nearly identical.

About this task

This task makes the following assumptions:

- You are replacing the self-signed server certificate.
- The certificate alias is server-cert .
- The private key is stored in keystore .
- The trusted certificates are stored in truststore.
- The keystore and truststore use the Java KeyStore (JKS) format.

If a PKCS#12 keystore format was used for the keystore and truststore files during setup, change the --keystoretype argument in the manage-certificate commands to PKCS12 in the relevant steps.

While the certificate is being replaced, existing secure connections continue to work. If you restart the server, or if a topology change requires a reset of peer connections, the server continues authenticating with its peers, all of whom trust the new certificate.

To replace the server certificate with no downtime, perform the following steps:

Steps

- 1. Prepare a new keystore with the replacement key pair.
- 2. Import the earlier trusted certificates into the new truststore file.
- 3. Update the server configuration to use the new certificate by adding it to the server's list of listener certificates in the topology registry.

Result:

Other servers will trust the certificate.

- 4. Replace the server's keystore and truststore files with the new ones.
- 5. Retire the previous certificate by removing it from the topology registry.

Next steps

The following sections describe these tasks in more detail.

Preparing a new keystore with the replacement key pair

You can replace the self-signed certificate with an existing key pair. As an alternative, you can use the certificate that is associated with the original key pair.

• Using an existing key pair

• Replacing the certificate associated with the original key pair

Using an existing key pair

To use an existing key pair, use the **manage-certificates** tool that is located in the server's **bin** or **bat** directory, depending on your operating system.

About this task

If a private key and certificate already exist in PEM-encoded format, they can replace both the original private key and the self-signed certificate in **keystore**, instead of replacing the self-signed certificate associated with the original server-generated private key.

Steps

• Import the existing certificates using the manage-certificates import-certificate.

Order the certificates that use the **--certificate-file** option so that each subsequent certificate functions as the issuer for the previous one.

List the server certificate first, then any intermediate certificates, and then list the root certificate authority (CA) certificate. Because some deployments do not feature an intermediate issuer, you might need to import only the server certificate and a single issuer.

For example, the following command imports the existing certificates into a new keystore file named keystore.new.

```
manage-certificates import-certificate \
    --keystore keystore.new \
    --keystore-type JKS \
    --keystore-password-file keystore.pin \
    --alias server-cert \
    --private-key-file existing.key \
    --certificate-file existing.crt \
    --certificate-file intermediate.crt \
    --certificate-file root-ca.crt
```

Replacing the certificate associated with the original key pair

Replace the certificate associated with the original server-generated private key (server-cert) if it has expired or must be replaced with a certificate from a different certificate authority (CA).

About this task

Perform the following steps to replace the certificate associated with the original key pair:

Steps

1. Create a CSR file for the server-cert .

Example:

```
manage-certificates generate-certificate-signing-request \
    --keystore keystore \
    --keystore-type JKS \
    --keystore-password-file keystore.pin \
    --alias server-cert \
    --use-existing-key-pair \
    --subject-dn "CN=ldap.example.com,0=Example Corporation,C=US" \
    --output-file server-cert.csr
```

- 2. Submit server-cert.csr to a CA for signing.
- 3. Export the server's private key into server-cert.key.

Example:

```
manage-certificates export-private-key \
    --keystore keystore \
    --keystore-password-file keystore.pin \
    --alias server-cert \
    --output-file server-cert.key
```

4. Import the certificates obtained from the CA, including the CA-signed server certificate, the root CA certificate, and any intermediate certificates, into keystore.new.

Example:

```
manage-certificates import-certificate \
    --keystore keystore.new \
    --keystore-type JKS \
    --keystore-password-file keystore.pin \
    --alias server-cert \
    --private-key-file server-cert.key \
    --certificate-file server-cert.crt \
    --certificate-file intermediate.crt \
    --certificate-file root-ca.crt
```

Importing earlier trusted certificates into the new keystore

You must import the trusted certificates of other servers in the topology into the new truststore file.

About this task

To export trusted certificates from truststore and import them into truststore.new, perform the following steps for each trusted certificate:

Steps

1. Locate the currently trusted certificates.

```
manage-certificates list-certificates \
    --keystore truststore
```

- 2. For each alias other than server-cert, or whose fingerprint does not match server-cert, perform the following steps:
 - 1. Export the trusted certificate from truststore.

```
manage-certificates export-certificate \
    --keystore truststore \
    --keystore-password-file truststore.pin \
    --alias <trusted-cert-alias> \
    --export-certificate-chain \
    --output-file trusted-cert-alias.crt
```

2. Import the trusted certificate into truststore.new.

```
manage-certificates import-certificate \
    --keystore truststore.new \
    --keystore-type JKS \
    --keystore-password-file truststore.pin \
    --alias <trusted-cert-alias> \
    --certificate-file trusted-cert-alias.crt
```

Updating the server configuration to use the new certificate

Before updating the server to use the appropriate key pair, update the **listener-certificate** property for the server instance's LDAP listener in the topology registry.

About this task

To support the transition from an existing certificate to a new one, earlier and newer certificates might appear within their own beginning and ending headers in the **listener-certificate** property.

To update the server configuration to use the new certificate, perform the following steps:

Steps

1. Export the server's previous server-cert into old-server-cert.crt.

```
manage-certificates export-certificate \
    --keystore keystore \
    --keystore-password-file keystore.pin \
    --alias server-cert \
    --output-file old-server-cert.crt
```

2. Concatenate the previous and new certificate into one file.

On Windows, use a text editor like Notepad. On Unix, use the following command.

cat old-server-cert.crt new-server-cert.crt > old-new-server-cert.crt

3. Use **dsconfig** to update the **listener-certificate** property for the server instance's LDAP listener in the topology registry.

```
$ bin/dsconfig -n set-server-instance-listener-prop \
    --instance-name <instance-name> \
    --listener-name ldap-listener-mirrored-config \
    --set "listener-certificate<old-new-server-cert.crt"</pre>
```

Replacing the key store and trust store files

Replace the key store and trust store files in the server's config directory to make the new server certificates take effect.

About this task

Because the server still uses the previous server-cert, you must replace the earlier keystore and truststore files with the new ones in the server's config directory when you want the new server-cert to take effect.

Steps

• Replace the keystore and truststore as shown in the following example.

```
$ mv keystore.new keystore
mv truststore.new truststore
```

Retiring the previous certificate

Retire the previous certificate by removing it from the topology registry after it expires.

Steps

• Remove the previous certificate from the topology registry, as shown in the following example.

```
$ dsconfig -n set-server-instance-listener-prop \
    --instance-name <instance-name> \
    --listener-name ldap-listener-mirrored-config \
    --set "listener-certificate<new-server-cert.crt"</pre>
```

Listener certificates

When a client initiates TLS negotiation with the server, the server presents a certificate chain to the client and the certificate at the head of the chain functions as a listener certificate.

Because the client decides whether to trust the certificate chain, it is recommended that the chain be signed by an issuer whom the client is likely to trust or that the client can be easily configured to trust.

You can create self-signed certificates with long lifespans, but a certificate that a certification authority signs is likely to have a relatively short lifespan. Commercial authorities typically issue certificates that are valid for only one or two years, but some authorities use shorter validity windows.

Short certificate lifespans offer some security benefits. In particular, because most clients do not verify whether a certificate has been revoked, a shorter validity window minimizes the timeframe that a compromised certificate can be used. If the process for replacing certificates is streamlined or automated, administrative inconvenience can be kept to a minimum.

Listener certificates are stored in key stores that are referenced by key manager providers, which in turn provide the logic and configuration for accessing the key stores. If a server component, like a connection handler, requires access to a certificate that it presents to a peer during the TLS negotiation process, that component must reference the key manager provider that points to the key store containing the appropriate certificate. If the key store contains multiple certificates, and if the component referencing the key store includes a property specifying the certificate's nickname, the certificate with that alias is selected. Otherwise, the server lets the Java virtual machine (JVM) select a certificate that might not be well-defined.

The server also provides trust manager providers, which determine whether to trust the certificate chains with which it is presented. A trust manager provider can reference a specified trust store file, but other options include the JVM default trust store, which uses the Java installation's default set of trusted issuers, and the blind trust manager provider, which automatically trusts every certificate chain that is presented to it.

(j) Note

Never use a blind trust manager in a production environment because it leaves the server vulnerable to impersonation and man-in-the-middle attacks. However, a blind trust manager can be convenient in test environments when troubleshooting certain types of problems.

Replacing listener certificates

Certificate authorities typically restrict the lifespans of the certificates that they sign. If you use a certification authority to issue listener certificates, you are likely replacing the certificates on a regular basis.

About this task

The **replace-certificate** tool performs the following steps:

- 1. Obtain a new certificate chain.
- 2. Make necessary updates to the key manager provider and the connection handler configurations
- 3. Update the server instance listener configuration with the new certificate.

The **replace-certificate** tool offers the following modes of operation:

Interactive mode

Walks you through the process of obtaining a new certificate and installing it in the server. Interactive mode also displays the non-interactive commands that are required to achieve the same result.

Non-interactive mode

Useful when scripting the process of replacing a certificate.

Steps

• To replace a listener certificate, run the **replace-listener-certificate** subcommand of the **replace-certificate** tool.

(i) Note

You can replace certificates manually, but the **replace-certificate** tool automates the process. The **replace-certificate** tool provides information about multiple listener certificates during the transitional phase that occurs when you install them.

The **replace-listener-certificate** subcommand takes arguments that provide the following information:

- Arguments required to authenticate to , such as --bindDN and --bindPasswordFile
- $\,\circ\,$ Details about the key store that contains the new certificate
- Updates that must be made to the key and trust manager providers
- Whether to signal the HTTP connection handler to reload its certificates after the update is complete

The following arguments are available:

Argument	Description
<pre>source-key-store-file {path}</pre>	Path to the Java KeyStore (JKS) or PKCS #12 file that contains the private key entry with the new certificate chain. This argument is required.
source-key-store-password {password}	Clear-text password that is needed to access the contents of the source key store.
source-key-store-password-file {path}	Path to the file that contains the password necessary to access the contents of the source key store. The file can contain the password in the clear or can be encrypted with a definition from the server's encryption settings database.
source-certificate-alias {alias}	Password that is required to access the appropriate private key in the source key store. If neither the source-private-key-password nor thesource- private-key-password-file argument is provided, the key store password is used as the private key password.

Argument	Description
source-private-key-password-file {path}	Path to the file that contains the password needed to access the appropriate private key in the source key store. The file can contain the password in the clear or can be encrypted with a definition from the server's encryption settings database. If neither thesource-private-key-password nor thesource-private-key-password-file argument is provided, the key store password is used as the private key password.
key-manager-provider {name}	Name of the key manager provider that is updated to use the new certificate chain. The value must identify a file- based key manager provider, and the new certificate chain must be enabled. Defaults to JKS if a value is not specified.
trust-manager-provider {name}	Name of the trust manager provider that is updated with the information required to trust the new certificate chain. The value must identify a file-based trust manager provider, and the new certificate chain must be enabled. If neither this argument nor theuse-jvm-default- trust-manager-provider argument is provided, the tool assumes that the name of the trust manager provider is identical to the name of the key manager provider.
use-jvm-default-trust-manager-provider	Indicates that the server must be configured to use the JVM-default trust manager provider, which trusts certificates signed by issuers in the cacerts trust store provided with the Java virtual machine (JVM), rather than updating an existing trust manager provider.
target-certificate-alias {alias}	 Alias to use for the new certificate in the key manager provider's key store, and for appropriate updates in the trust manager provider's trust store. Defaults to an alias of server-cert if a value is not specified. Onte If the key manager provider's key store, or the trust manager provider's trust store, already contains an entry with the given alias, the existing entry is renamed.

Argument	Description
reload-http-connection-handler-certificates	Indicates that the tool is requesting that the server cause any HTTPS-based connection handlers to reload their certificates, so that the connection handlers can use the updated certificate. LDAP connection handlers react to the change immediately and start presenting the new certificate chain during subsequent TLS negotiations. HTTPS connection handlers continue using the former certificate until the connection handler is restarted or until the connection handler is asked specifically to reload its certificates. Note This option might prevent clients with existing TLS sessions that were negotiated with the former certificate from being resumed.

• To remove earlier certificates from the server instance listener configuration, run the purge-retired-listenercertificates subcommand.

) Note

The **purge-retired-listener-certificates** subcommand does not take arguments other than the ones that are required to authenticate to the server.

By default, the **replace-certificate** tool updates the server instance listener configuration object to include the new listener certificate, and it merges the old and new certificates residing in the configuration object.

X.509 certificates

The server supports X.509 certificates, the most common type of certificates. RFC 5280 \square describes X.509v3, which provides the current version of the specification.

An X.509v3 certificate includes the following components:

X.509 encoding version

Enables the differentiation between an X.509v3 certificate and one that conforms to an earlier or later version of the specification.

Serial number of the certificate

Integer value that uniquely identifies a certificate as issued by a certification authority.

Subject DN

Distinguished name for the certificate, which often provides details about the context in which the certificate is to be used. For more information, see Certificate subject DNs.

Issuer DN

Distinguished name for the issuer certificate, which is the certificate used to sign the certificate. For a self-signed certificate, this value matches the subject DN.

Validity window

Indicates the timeframe during which the certificate is considered valid. This component includes the following elements:

notBefore

Specifies the earliest time at which the certificate is considered valid.

notAfter

Specifies the latest time at which the certificate is considered valid.

Public key

Public portion of a pair of cryptographically linked keys. For more information, see Certificate key pairs.

Signature

A type of cryptographic proof that the certificate truly was sent from the issuer and has remained unaltered. A self-signed certificate is signed with its own private key. Otherwise, it is signed with the issuer's private key.

An X.509v3 certificate might also include the following optional components:

Subject unique ID

Uniquely identifies the certificate. This component has been deprecated in favor of the subject key identifier extension, so it is generally omitted from X.509v3 certificates.

Issuer unique ID

Subject unique ID of the issuer certificate, if available. This component has been deprecated in favor of the authority key identifier extension.

Set of extensions

Provides additional context for the certificate and the manner in which it is used. For more information, see Certificate extensions.

Certificate subject DNs

A certificate's subject distinguished name (DN) provides information about how the certificate should be used.

Like an LDAP DN, a certificate's subject DN consists of a comma-delimited series of attribute-value pairs. However, unlike an LDAP DN, the attribute names in a certificate subject DN are typically written in all uppercase characters.

A certificate's subject DN is also referred to as its subject. The following attributes commonly appear in a certificate subject.

Attribute name	Attribute description
CN	Common name
	Note For a listener certificate, the CN attribute typically identifies the host name that clients use to access the certificate. However, the subject alternative name extension is recommended more highly for accomplishing the same task. Most certificate subject DNs include at least the CN attribute.
E	Email address
OU	Name of the organizational unit, such as the relevant department
0	Name of the organization or company
L	Name of the locality, such as the appropriate city
ST	Full name of the state or province
С	ISO 3166 country code

A certificate subject includes at least one attribute-value pair, and the CN attribute is typically present. Other attributes can be omitted, although the 0 and C attributes are also common. For example, a listener certificate for a server with an address of ldap.example.com, which is run by the US-based company Example Corp, might have a subject of CN=ldap.example.com, 0=Exam ple Corp, C=US.

Certificate key pairs

Each certificate contains a key pair that consists of two keys that are linked cryptographically. If you encrypt data with one key, the data can be only decrypted with the other key.

Although a key pair can be created easily when both keys are generated simultaneously, the process of deriving one key from the other is extremely difficult, a process categorized in cryptographic terms as computationally infeasible.

When generating a key pair, one key is designated as the public key, and the other key is designated the private key. The public key can be made widely available, but the private key must be kept secret and not shared with anyone.

As long as the secrecy of the private key is maintained, the key pair can be used to perform the following functions:

• Encryption, sometimes referred to as confidentiality

If someone wants to send you a secret message without anyone else viewing it, the message can be encrypted with your public key. Only you possess the private key, so only you can decrypt the message.

• Digital signatures

If you encrypt data with your private key, it can be decrypted only with your public key. Because your public key can be made widely available, this encryption method does not actually protect the content. However, digital signatures prove that a message came from you because only your private key could have generated it.

i) Note

When generating a digital signature, the entire message is generally not encrypted. Only a hash of the message is encrypted, typically by using a digest algorithm like SHA-256.

This approach protects the integrity of a message. A decrypted signature that matches the digest of the original message guarantees that the message came from you and that it has remained unaltered since you signed it.

The following public key algorithms are used primarily in certificates that facilitate TLS communication:

- RSA, which is based on the multiplication of large prime numbers
- EC, which is based on computations that involve special types of elliptical curves

Although RSA is supported more widely than EC, it is slower and requires larger keys to achieve the same level of security. To support legacy clients, you should use an RSA certificate and choose a key size of at least 2,048 bits.

If all of your clients support EC certificates, you should use an EC certificate with a key size of at least 256 bits.

Certificate extensions

Extensions provide additional context for a certificate.

Some of the more common extension types include the following:

Subject key identifier

Holds a unique identifier for the certificate, which is generally derived from the certificate's public key.

Authority key identifier

Holds the subject key identifier for the issuer certificate. This extension type helps to identify the issuer certificate, especially when presented with an incomplete certificate chain.

Subject alternative name

Holds a list of ways that clients are expected to reference a server when establishing a connection to it.

(i) Note

Clients must take this information into account when deciding whether to trust a server's certificate. The most common types of values include DNS names, IP addresses, and URIs. DNS names must be fully qualified, but can optionally use an asterisk in the leftmost component to match any single name in that component. For example, *.example.com could match www.example.com or ldap.example.com, but would not match ldap.east.example.com or example.com.

Key usage

Provides information about the manner in which the certificate is expected to be used. The following key usages are allowed:

digitalSignature

Indicates that the certificate can be used for digitally signing data, excluding certificates and certificate revocation lists (CRL).

nonRepudiation

Indicates that the certificate can be used to prevent denying the authenticity of a message. nonRepudiation is also known as contentCommitment.

keyEncipherment

Indicates that the certificate can be used to protect encryption keys, such as symmetric keys that are derived during TLS key agreement.

dataEncipherment

Indicates that the certificate can be used for encrypting data directly.

keyAgreement

Indicates that the certificate's public key can be used for key agreement, such as deriving the symmetric key that protects TLS communication.

keyCertSign

Indicates that the certificate can act as a certification authority and be used for signing other certificates.

cRLSign

Indicates that the certificate can be used to sign CRLs.

encipherOnly

When used in conjunction with **keyEncipherment**, indicates that the public key can be used only for encrypting data during key agreement.

decipherOnly

When used in conjunction with **keyEncipherment**, indicates that the public key can be used only for decrypting data during key agreement.

Extended key usage

Acts as an alternative to the key usage extension and provides additional high-level functionality. The following extended key usages are allowed:

serverAuth

Indicates that the server can present the certificate to the client during TLS negotiation.

clientAuth

Indicates that the client can present the certificate to the server during TLS negotiation.

codeSigning

Indicates that the certificate can be used to sign source and compiled code.

emailProtection

Indicates that the certificate can be used to sign or encrypt email messages.

timeStamping

Indicates that the certificate can be used to assert the time that an event occurred.

ocspSigning

Indicates that the certificate can be used to sign an online certificate status protocol (OCSP) response.

Basic constraints

Indicates whether the certificate can act as a certification authority and, if so, the maximum number of intermediate certificates that can follow it in a certificate chain.

Certificate chains

A certificate chain is an ordered list of one or more certificates. In such a chain, each subsequent certificate is the issuer of the previous certificate.

During TLS negotiation, the server presents a certificate chain to the client, which determines whether to trust the chain and continue with the negotiation. The client can also present its own certificate chain to the server.

If a certificate is self-signed, its chain contains only that single certificate. If a certificate is signed by a self-signed certificate authority (CA) certificate, such as a root CA, the chain contains two certificates: the server certificate and the CA certificate that follows it. If a single intermediate CA (a CA certificate that is signed by a root CA) is present, the chain contains the server certificate, followed by the intermediate CA, and then the root CA.

Intermediate certificate authorities are useful for security purposes, especially in commercial authorities. If a client trusts a root CA certificate, it is likely to trust anything with that root CA certificate at the base of its chain. Consequently, the root CA certificate must be kept secure.

i) Note

If the root CA certificate is compromised, any certificate that is directly or indirectly signed by it can no longer be trusted.

With intermediate CA certificates, the root certificate can be kept offline in secure storage and used only when a new intermediate CA certificate must be signed. The intermediate CA certificates can be used to sign end-entity certificates, but must be protected to avoid compromising any of the certificates. A compromised certificate must be revoked along with all of the certificates that it signed. In such a scenario, the root CA can be used to sign a new certificate.

(i) Note

The certificate chain that the server presents to the client, or that the client presents to the server, during TLS negotiation does not always need to be the complete chain. If the root CA at the end of the chain is widely trusted, the server can assume that the client already has that root CA in its default set of trusted certificates. The server can leave that root CA off the chain with the assumption that the client will retrieve it from its default trust store. While the same assumption could theoretically be true for intermediate CA certificates, only the root CA certificate is commonly omitted. When a client receives an incomplete chain, the client looks in its default trust store to determine whether the trust store contains the issuer certificate, which it can identify by using properties like the issuer distinguished name (DN) or an authority key identifier extension.

The certificate at the head of a certificate chain, which appears as the first one in the list, is often called the end-entity certificate. If this certificate appears at the head of the chain that a server presents during TLS negotiation, it is referred to as the server certificate. If the certificate appears at the head of a chain that a client presents, it is referred to as a client certificate. The certificate at the end of a complete chain must be a root CA certificate. In the case of a self-signed certificate, the chain contains only a single certificate that serves both roles.

About representing certificates, private keys, and certificate signing requests

X.509 is an encoding format that uses the ASN.1 distinguished encoding rules (DER), which exist in binary format. When writing a certificate to a file, either a raw DER format or a plaintext format called PEM can be used.

PEM encoding consists of a line that contains the text -----BEGIN CERTIFICATE----- , followed by a set of lines that contains the base64-encoded representation of the raw DER bytes (typically with no more than 64 characters per line), followed by a line that contains the text -----END CERTIFICATE-----.

The X.509 encoding contains a certificate's public key, but not its private key. The PKCS #8 specification in RFC 5958 \square describes the encoding for private keys. This approach uses a DER encoding with a PEM variant that instead uses the following header and footer, respectively.

```
-----BEGIN PRIVATE KEY-----
```

RFC 5958 also describes an encrypted representation of the private key, but that format is currently unsupported.

The PKCS #10 specification in RFC 2986^C describes the CSR format. This format uses a DER encoding with a PEM variant that uses the following header and footer, respectively.

```
-----BEGIN CERTIFICATE REQUEST-----
```

Some implementations use the following alternate, nonstandard forms.

```
-----BEGIN NEW CERTIFICATE REQUEST-----
```

Certificate trust

When a server presents its certificate chain to a client during TLS negotiation, the client decides whether to trust the certificate chain and concludes whether it is communicating with a legitimate server instead of an impostor.

If a client is tricked through DNS hijacking into communicating with a rogue application instead of with a legitimate server, the application can steal the client's credentials, or can fool the client into concluding that it has performed an action that it has not performed. If a rogue application acts as a broker between the client and the legitimate server, the client might be unable to detect the change, and the malicious application might be capable of stealing data or altering the communication. Consequently, you should avoid trust all or blind trust options in a production environment.

When determining whether to trust a server certificate chain, a client performs the following steps.



Processing steps

1. Verifies that it has received the complete certificate chain.

If a server presents an incomplete chain, the client must ensure that it can complete the chain with information in an explicitly provided trust store or default trust store. If the client cannot complete the certificate chain, the chain is not trusted.

2. Verifies that each subsequent certificate in the chain is the issuer certificate for, and that its private key was used to sign, the certificate that precedes it.

(i) Note

If a certificate chain contains extraneous certificates, or if a subsequent certificate did not issue the certificate that precedes it, the chain is not trusted.

3. Confirms that it has a reason to trust the certificate at the root of the chain.

i) Note

This step is generally performed by ensuring that the root certificate authority (CA) certificate can be found in either a default trust store or a trust store that is configured for use by the client. If the client has no prior knowledge of the root CA certificate, the chain is not trusted.

4. Verifies that the current time lies within the validity window for each certificate in the chain.

(i) Note

The chain is not trusted under the following conditions:

- $^{\circ}$ When the **notBefore** value of any certificate in the chain is later than the current time.
- $\circ\,$ When the notAfter value of any certificate in the chain is earlier than the current time.

5. Verifies that the server certificate at the head of the chain is suitable for the server with which the client thinks it is communicating.

(i) Note

The client must verify that the address used to connect to the server matches one of the following values:

- The **CN** attribute of the certificate's subject.
- One of the values of any subject alternative name extension.

These steps represent a starting point. If necessary, the client can perform additional types of validation. For example, if a root or intermediate certification authority maintains a certificate revocation list (CRL) or supports the online certificate status protocol (OCSP), the client must verify that none of the certificates in the chain has been revoked. The client can also verify that the CA certificates include the basic constraints extension, and that the server certificate does not contain too many levels. Other checks, like those that use certificate policy extensions, can also be performed.

Keystores and truststores

A keystore is a type of database that holds certificates.

The following examples represent the most common forms of keystores:

- File that uses the Java-specific Java KeyStore (JKS) format
- File that uses the standard PKCS #12 format
- Collection of files that holds certificates and private keys, typically in PEM or DER format
- Hardware security module (HSM) that makes the certificate information available through an interface like PKCS #11

The server supports file-based keystores by using the JKS and PKCS #12 formats and by using hardware security modules that are accessible through PKCS #11. The server does not currently support a keystore format that consists of individual certificate and private key files. To import these files into a JKS or PKCS #12 keystore, use the **manage-certificates** tool.

A keystore also represents a collection of entries, each of which is identified by a name that an alias calls. Keystores can have the following entry types:

Private key entries

Contain a certificate chain and a private key. When a server accepts a TLS-based connection, it uses a private key entry to obtain the certificate chain that it presents to the client. The server can also use the private key from the same entry to process its key agreement. Similarly, a client uses a private key entry when presenting its own certificate chain to a server.

Trusted certificate entries

Contain a single certificate without a private key. As the name implies, a trusted certificate entry is intended primarily for use when determining whether to trust a certificate chain that is presented during TLS negotiation.

Secret key entries

Contain a secret key only, without an associated certificate. These types of entries are not used for TLS processing. Instead, they hold symmetric encryption keys or other types of secrets.

A password, sometimes called a PIN, protects the contents of a keystore. In some cases, like with JKS keystores, some content might be accessible without a password, and a password might be required only when trying to access private keys or secret keys. In other cases, like with PKCS #12 keystores, you might need a password for any interaction with the keystore.

Additional passwords can further protect private keys. This approach is often the same as with the keystore password, but the password can be different. This tactic is useful when a single keystore is shared for multiple purposes, for example, and when merely having access to the keystore does not guarantee access to all of the data that it contains.

(j) Note

A truststore is another name for a keystore that is intended primarily for use when determining whether to trust a certificate chain that has been presented. Truststores generally contain primarily trusted certificate entries, but that case is not required.

Java runtime environments typically include a default truststore, often jre/lib/security/cacerts or lib/security/cacerts, that is prepopulated with several widely trusted certification authority certificates. When presented with a certificate that one of these authorities has signed, the default truststore can allow the certificate to be trusted without any additional configuration. When presented with a self-signed certificate, or when presented with a certificate that is signed by an issuer not in the default truststore, such as a private corporate certification authority, a separate truststore is required.

Transport Layer Security (TLS)

TLS describes a mechanism for securely communicating between two parties that might have no prior knowledge of each other.

TLS is the successor to SSL, and the two terms are often used interchangeably, even though such usage might not technically be correct.

i) Note

SSL remains the more widely recognized term. The abbreviation TLS occasionally generates confusion with the StartTLS extended operation, particularly in LDAP.

TLS provides security in the form of the following main components:

Certificate trust

Is about reassuring a connection-initiating client that it is communicating with the server to which it intended to connect. To ensure that the server shares the same degree of confidence in the identity and legitimacy of the client, it can ask the client to present its own certificate chain. For more information, see Certificate Trust.

Cipher selection

Involves choosing the cipher and the key to protect the bulk of the communication. Although a client can use a server certificate's public key to encrypt data before sending it, this approach can lead to the following issues:

- Unless the client presents its own certificate chain to the server, the server cannot encrypt the data that it sends back to the client.
- Public key encryption is considerably slower than symmetric encryption, in which the same key is used for both encryption and decryption. Public key encryption is also called asymmetric encryption because different keys are used to encrypt and decrypt data.


• If you rely entirely on the security of a private key to ensure the secrecy of a communication, and if the private key becomes compromised, data that has been encrypted with the private key must also be considered compromised.

Rather than relying solely on public key encryption to protect communication between a client and server, the TLS negotiation process allows a client and server to agree on the type of encryption and the secret key to use after completing the negotiation process.

TLS handshakes

The process of negotiating the TLS is referred to as the handshake.

Although the exact process depends on the TLS version that is ultimately chosen, the following steps represent the basic components of a TLS 1.2 handshake:



TLS processing steps

- 1. The client sends a **hello** message that provides the server with the following information:
 - Highest supported version of the TLS protocol

- The cipher suites that the client uses
- Set of extensions with additional information:
 - The address that the client uses to communicate with the server
 - The signature algorithms and elliptic curves that the client supports
 - Whether the client supports secure renegotiation
- 2. The server returns a server hello message that provides the client with the following information:
 - The TLS protocol version that the server uses
 - The cipher suite that the server selects

The server can also provide its own extensions to the client.

- 3. The server sends a certificate message that provides its certificate chain to the client.
- 4. The server can optionally send a **server key exchange** message with additional information that the client might need to securely derive the same symmetric encryption key that the server generates.
- 5. The server can optionally send a certificate request message that asks the client to present its own certificate chain to the server.
- 6. The server sends a server hello done message to inform the client that it has completed its hello sequence.
- 7. The client can optionally send a certificate message to the server with its own certificate chain.

(i) Note

The client sends a **certificate** message only when the server initially sends a certificate request. If the client receives such a request, it can refuse to, and probably will not, send a certificate chain. The server decides whether to require a client certificate chain. In LDAP, the server commonly asks the client to present a certificate, but continues with TLS negotiation even if the client does not present one. This approach supports authentication methods like SASL EXTERNAL, in which a client uses the certificate chain that it presents during TLS negotiation as proof of its identity.

- 8. The client derives a symmetric key to use for the remainder of the encrypted processing, and sends a client key exchange message to the server. The client key exchange message includes the information that the server needs to generate the same key. Only the client and server know the value of the key, even if another entity can observe the communication that passes between the client and the server.
- 9. If the client presents a certificate chain to the server, it also sends a **certificate verify** message to prove that the private key for the certificate is included at the head of the chain.
- 10. The client sends a **change cipher spec** message to the server, which informs the server that the client will use the agreed-upon symmetric key to encrypt everything else that it sends to the server.
- 11. The client sends a **finished** message to the server to indicate that it has completed its portion of the handshake.
- 12. The server sends a **change cipher spec** message to the client, which informs the client that the server will use the agreed-upon symmetric key to encrypt everything else that it sends to the client.
- 13. The server sends a **finished** message to the client to indicate that it has completed its portion of the handshake.

TLS 1.3 uses a different handshake sequence that can require only a single round-trip to exchange the necessary information between the client and the server. TLS 1.2 requires two round-trips. To accomplish this task, TLS 1.3 tries to guess the type of key agreement that the server wants to use, and sends the relevant information to the server up front instead of waiting to hear from the server.

Because an extra round of communication between the client and server is eliminated, the server finishes its portion of the negotiation before the client. The server must assume that the client trusts its certificate chain. Because the server might log a successful negotiation only to discover late, through a TLS alert, that the client rejected the certificate, this approach might complicate certain types of troubleshooting.

Key agreement

Key agreement processing provides a critical component of TLS negotiation.

It allows the client and server to select the symmetric key that encrypts the remainder of the communication, but does not reveal the key to anyone who can access the communication. Although several key agreement algorithms are available, the following types are the most common:

RSA key exchange

The client generates random data, uses the server's public key to encrypt it, and provides it to the server, which uses its private key to decrypt it. The client and server alike derive the encryption key from the randomly generated data.

Diffie-Hellman (DH) key exchange

The client and server agree publicly on a pair of mathematically linked numbers, and each participant chooses its own secret value. Through a special computation, they generate a key that can be discovered only by someone who knows one of the secret values. Although several variants of the Diffie-Hellman algorithm can be used in key exchange, we recommend the ECHDE and DHE versions because they use ephemeral keys with no relation to the server's certificate. Of those two versions, ECDHE is faster and uses smaller keys.

When possible, use ECHDE over DHE, and either of those options over RSA. The DH algorithms provide a substantial benefit over RSA in the form of forward secrecy. Because RSA key exchange uses the server certificate's public key to encrypt data, the encryption can be broken if the certificate's private key is compromised. This warning applies to previously captured data as well as to communication on new TLS connections. The use of ephemeral keys in ECDHE and DHE ensures that, even if the certificate's private key is compromised, the encrypted communication remains indecipherable to anyone but the client and server, although anyone with the private key can still impersonate the legitimate server.

LDAP StartTLS extended operation

In most scenarios, a client that uses TLS establishes a connection to a port that is dedicated to its use, like 636 (LDAPS) or 443 (HTTPS).

The client begins the TLS-negotiation process by sending a **client hello** message over the connection. In some scenarios, the client establishes a non-secure connection and later converts it to a secure one. In LDAP, this task is accomplished by using the **StartTLS** extended operation.

The **StartTLS** extended operation provides the following advantages over a dedicated LDAPS connection:

• To enable secure as well as insecure communication, only one port needs to be opened through a firewall.

- A client can use opportunistic encryption, in which the client performs the following steps:
 - 1. Queries the root DSE to determine whether the server supports StartTLS.
 - 2. Secures the connection, if possible.

Opportunistic encryption is useful in scenarios like following referrals because LDAP URLs do not officially support LDAPS as a scheme.

To ensure that a communication is always secure, use LDAPS instead of establishing an insecure connection that you secure later with the **StartTLS** extended operation. If you enable support for unencrypted LDAP communication, as **StartTLS** requires, a client might send a password-containing bind request or other sensitive data over an unencrypted connection. A server can be configured to reject unencrypted communication, but it cannot prevent a client from sending an unencrypted request.

(i) Note

Although you can use **StartTLS** to temporarily secure a connection before falling back on an unencrypted LDAP communication, the server does not support this strategy.

About the manage-certificates tool

PingAuthorize Server offers a manage-certificates tool that enables interaction with Java KeyStore (JKS) and PKCS #12 key stores.

Although it behaves similarly to the **keytool** utility that accompanies most Java distributions, **manage-certificates** is easier to use, provides improved usage information, and offers additional functionality.

Available manage-certificates subcommands

The manage-certificates tool uses the following subcommands to indicate which function to invoke:

Subcommand	Function
list-certificates	Lists the certificates in a keystore.
import-certificate	Imports a certificate into a trusted certificate entry or imports a certificate chain and private key into a private key entry.
export-certificate	Exports a certificate from a keystore.
export-private-key	Exports a private key from a keystore.
generate-self-signed-certificate	Generates a self-signed certificate.
generate-certificate-signing-request	Generates a certificate-signing request that can be provided to a certification authority.
sign-certificate-signing-request	Signs a certificate-signing request with a specified issuer certificate.

Subcommand	Function
check-certificate-usability	Checks a specified certificate in a keystore to verify whether it is suitable for use as a listener certificate.
trust-server-certificate	Initiates the TLS-negotiation process with a specified server to obtain its certificate chain so that a truststore can be updated with the necessary information to trust the chain.
display-certificate-file	Displays the contents of a file that contains one or more PEM- encoded or DER-encoded X.509 certificates.
display-certificate-signing-request-file	Displays the contents of a file that contains a PEM-encoded or DER-encoded PKCS #10 certificate-signing request (CSR).
change-certificate-alias	Changes the alias for an entry in a keystore.
change-keystore-password	Changes the password for a keystore.
change-private-key-password	Changes the password that protects the private key for a specified entry in a keystore.

Using manage-certificates as a simple certification authority

If your server instances need to support an arbitrary or unknown set of clients, configure them with certificates from a trusted issuer, such as a commercial authority or the free Let's Encrypt service.

About this task

If you control every client that accesses the servers, you might want to create your own internal certification authority so that you have a common issuer for all servers. In such a scenario, the clients need to trust only the certificates that the issuer signs. Commercial and open-source software packages provide full-featured certification authority functionality, but you can use the **manage-certificates** tool to create a certificate authority (CA) certificate that you can use to sign certificate-signing requests.

Steps

1. Create a CA certificate.

A CA certificate is a self-signed certificate that possesses the following extensions:

- A key usage extension that includes at least the keyCertSign usage
- $^{\circ}$ A basic constraints extension that identifies the certificate as a CA certificate

If you do not plan to use an intermediate CA certificate, the basic constraints extension must have a path length constraint of 0. If you plan to use an intermediate CA certificate, the path length constraint must be 1. Because certificates that the CA certificate signs are valid only for as long as all certificates in the chain remain valid, we recommend that you specify a long lifespan for the CA certificate.

Example:

The following example creates a new root CA certificate.

```
$ bin/manage-certificates generate-self-signed-certificate \
     --keystore /ca/root-ca-keystore \
     --keystore-password-file /ca/root-ca-keystore.pin \
     --keystore-type JKS \
     --alias root-ca-cert \
     --subject-dn "CN=Example Root CA,O=Example Corp,C=US" \
     --days-valid 7300 \
     --key-algorithm RSA \
     --key-size-bits 4096 \
     --signature-algorithm SHA256withRSA \
     --basic-constraints-is-ca true \
     --basic-constraints-maximum-path-length 1 \
     --key-usage key-cert-sign \
     --key-usage crl-sign
Successfully created a new JKS keystore.
Successfully generated the following self-signed certificate:
Subject DN: CN=Example Root CA,O=Example Corp,C=US
Issuer DN: CN=Example Root CA,O=Example Corp,C=US
Validity Start Time: Monday, January 27, 2020 at 03:47:29 PM CST (0 seconds ago)
Validity End Time: Sunday, January 22, 2040 at 03:47:29 PM CST
                  (7299 days, 23 hours, 59 minutes, 59 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with RSA
Public Key Algorithm: RSA (4096-bit)
SHA-1 Fingerprint: bc:8e:5b:30:52:ec:03:63:b4:9a:aa:1a:45:a0:fc:84:49:dd:e8:64
SHA-256 Fingerprint:
   d5:47:06:cd:a2:95:42:61:1f:c7:aa:04:16:1e:c1:70:41:c4:44:48:bf:74:20:5f:1c:
   61:e2:aa:40:08:3a:ff
```

2. Export the public portion of the root CA certificate for future reference.

When you import a signed certificate, you can import the public portion of the root CA certificate as a standalone certificate into trust stores as well as into part of a certificate chain.

3. Create a new certificate signing request to create an intermediate CA certificate,

The certificate signing request uses essentially the same settings as the root CA. If you anticipate only a single intermediate CA, its basic constraints extension must have a path length constraint of 0, rather than 1, to indicate that it is used only to sign end-entity certificates and that it cannot create subordinate CA certificates by itself.

Example:

The following example command creates a certificate signing request.

```
$ bin/manage-certificates generate-certificate-signing-request \
     --keystore /ca/intermediate-ca-keystore \
     --keystore-password-file /ca/intermediate-ca-keystore.pin \
     --keystore-type JKS \
     --alias intermediate-ca-cert \
     --subject-dn "CN=Example Intermediate CA,O=Example Corp,C=US" \
     --key-algorithm RSA \
     --key-size-bits 4096 \
     --signature-algorithm SHA256withRSA \
     --basic-constraints-is-ca true \
     --basic-constraints-maximum-path-length 0 \
     --key-usage key-cert-sign \
     --key-usage crl-sign \
     --output-file /ca/intermediate-ca-cert.csr \
     --output-format PEM
Successfully created a new JKS keystore.
Successfully generated the key pair to use for the certificate signing
request.
Successfully wrote the certificate signing request to file
'/ca/intermediate-ca-cert.csr'.
```

4. Use the root CA certificate to sign the certificate signing request for the intermediate CA certificate with the **sign-certificate-signing-request** subcommand.

The **sign-certificate-signing-request** subcommand takes most of the same arguments as generating a self-signed certificate. The primary differences between the argument sets are as follows:

- The key store that contains the certificate uses the provided key store arguments to sign the request. To specify the name of the certificate to use when signing the request, use the **--signing-certificate-alias** argument.
- To specify the path to the file that contains the certificate signing request file to generate, provide a --requestinput-file argument.
- To specify the path to the file to which the signed certificate is written, provide a --certificate-output-file argument. If this argument is omitted, the PEM representation of the certificate is written to standard output.
- To specify the format, **PEM** or **DER**, in which the certificate is written to the output file, provide an **--output-format** argument.
- To specify the subject to use for the signed certificate, use the **--subject-dn** argument. To use the subject DN from the certificate signing request, omit this argument.
- To specify the name of the signature algorithm, use the **--signature-algorithm** argument.

Note

Because the requester generated the key, you cannot specify the key algorithm or the key length.

 To indicate that the signed certificate includes every extension that is listed in the certificate signing request, use the --include-requested-extensions argument. If this argument is not provided, explicitly specify the set of extensions to include.

Example:

The following example command signs the certificate signing request for an intermediate CA certificate.

```
$ bin/manage-certificates sign-certificate-signing-request \
     --keystore /ca/root-ca-keystore \
     --keystore-password-file /ca/root-ca-keystore.pin \
     --signing-certificate-alias root-ca-cert \
     --days-valid 7300 \
     --include-requested-extensions \
     --request-input-file /ca/intermediate-ca-cert.csr \
     --certificate-output-file /ca/intermediate-ca-cert.pem \
     --output-format PEM
Read the following certificate signing request:
PKCS #10 Certificate Signing Request Version: v1
Subject DN: CN=Example Intermediate CA,O=Example Corp,C=US
Signature Algorithm: SHA-256 with RSA
Public Key Algorithm: RSA (4096-bit)
Do you really want to sign this request? yes
Successfully wrote the signed certificate to file
'/ca/intermediate-ca-cert.pem'.
```

5. After you obtain the intermediate CA certificate, create secure, offline backups of the root CA certificate.

6. Remove the root CA certificate, or at least its private key, from all systems.

(i) Note

Make certain that all end-entity certificates are signed with the intermediate CA certificate, and that the process is identical to the previous example. Restore the root CA certificate only if you need to sign another intermediate CA certificate.

Common manage-certificates arguments

Most of the **manage-certificates** subcommands require access to a Java KeyStore (JKS) or PKCS #12 keystore. In such instances, use the **--keystore** argument to specify the path to the keystore.

If the keystore already exists, the tool detects automatically whether it is a JKS or PKCS #12 keystore. If the operation creates a new keystore, you can specify the type explicitly by using the **--keystore-type** argument, followed by a value of **JKS** or **PKCS12**. If you do not specify the keystore type, a default value of **JKS** is used.

Some situations require you to provide the password that is needed to access the keystore. For a JKS keystore, you might need to provide a keystore password only for operations that involve creating a keystore or accessing a private key. However, you will likely need to provide the password for all operations that involve a PKCS #12 keystore.

To provide a keystore password, use one of the following arguments:

• --keystore-password , followed by the clear-text password for the keystore.

- --keystore-password-file, followed by the path to a file that contains the password for the keystore. The file might contain the password in the clear, or it might be encrypted with a definition from the server's encryption-settings database.
- --prompt-for-keystore-password. If this argument is provided, the tool prompts you interactively to provide the password.

If a private key is protected with a different password than the keystore itself, specify one of the following arguments to provide the private key password:

- --private-key-password, followed by the plaintext password.
- --private-key-password-file, followed by the path to a file that contains the clear-text or encrypted password.
- --prompt-for-private-key-password, which causes the tool to prompt interactively for the password.

Several operations require you to specify the keystore entry to target. In such scenarios, provide the --alias argument, followed by the name of the alias for that entry.

Listing the certificates in a keystore

List the certificates available in a keystore.

Steps

• To list the certificates in a keystore, use the **list-certificates** subcommand.

This subcommand requires you to specify the path to the keystore file, and possibly the password that is needed to access the keystore. The following options are also available:

Option	Description
alias {alias}	Specifies the alias of the certificate to display. If this value is not provided, all certificates are displayed. To list more than one specific certificate, specify this value multiple times.
display-pem-certificate	Includes a PEM-encoded representation of each certificate as part of the output.
verbose	Includes details about each certificate.

Example:

The following command demonstrates the basic listing of a keystore that contains a single certificate chain.

```
$ bin/manage-certificates list-certificates \
     --keystore config/keystore \
     --keystore-password-file config/keystore.pin
Alias: server-cert (Certificate 1 of 2 in a chain)
Subject DN: CN=ds1.example.com,O=Example Corp,C=US
Issuer DN: CN=Example Certification Authority,O=Example Corp,C=US
Validity Start Time: Saturday, November 9, 2019 at 11:26:09 AM CST
                    (8 minutes, 15 seconds ago)
Validity End Time: Sunday, November 8, 2020 at 11:26:09 AM CST
(364 days, 23 hours, 51 minutes, 44 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Public Key Algorithm: EC (secP256r1)
SHA-1 Fingerprint: 42:f8:85:97:bf:88:bc:74:4b:5b:ce:0c:54:43:9b:44:6b:
                  81:23:a3
SHA-256 Fingerprint: 4f:be:47:ed:36:68:13:38:ba:e8:c0:c5:6c:85:51:97:
                    8b:40:1b:76:10:c0:be:80:15:62:06:96:c5:71:30:df
Private Key Available: Yes
The certificate has a valid signature.
Alias: server-cert (Certificate 2 of 2 in a chain)
Subject DN: CN=Example Certification Authority,O=Example Corp,C=US
Issuer DN: CN=Example Certification Authority,O=Example Corp,C=US
Validity Start Time: Saturday, November 9, 2019 at 11:26:08 AM CST
                   (8 minutes, 16 seconds ago)
Validity End Time: Friday, November 4, 2039 at 12:26:08 PM CDT
                   (7299 days, 23 hours, 51 minutes, 43 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Public Key Algorithm: EC (secP256r1)
SHA-1 Fingerprint: b8:d0:16:9b:5d:f2:e7:a1:80:79:95:a2:64:b5:aa:ad:80:
                   23:64:16
SHA-256 Fingerprint: cf:98:2a:66:35:6e:6d:f9:5d:25:c6:68:68:04:5a:a8:
                     88:43:ca:b5:c8:e5:c9:95:09:e9:fc:ab:b9:41:ec:71
The certificate has a valid signature.
```

Example:

The following sample represents the verbose version of the previous command.

```
$ bin/manage-certificates list-certificates \
     --keystore config/keystore \
     --keystore-password-file config/keystore.pin \
     --verbose
Alias: server-cert (Certificate 1 of 2 in a chain)
X.509 Certificate Version: v3
Subject DN: CN=ds1.example.com,O=Example Corp,C=US
Issuer DN: CN=Example Certification Authority,O=Example Corp,C=US
Serial Number: 7b:2d:91:6a:ff:51:4f:7a:19:16:26:4f:ce:cb:cb:31
Validity Start Time: Saturday, November 9, 2019 at 11:26:09 AM CST
(9 minutes, 48 seconds ago)
Validity End Time: Sunday, November 8, 2020 at 11:26:09 AM CST
                   (364 days, 23 hours, 50 minutes, 11 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Signature Value:
    30:46:02:21:00:cb:d5:5e:45:b2:8a:33:5e:2d:85:23:39:49:d1:3f:8f:dc:
     f8:9e:2f:f3:44:2f:41:0d:69:95:ec:f0:f5:c0:80:02:21:00:ef:8f:32:35:
    3c:88:f4:89:ed:f3:a6:76:
    bb:92:6c:eb:c6:17:ac:61:dc:67:26:f0:ec:67:90:51:28:a1:d0:d5
Public Key Algorithm: EC (secP256r1)
Elliptic Curve Public Key Is Compressed: false
Elliptic Curve X-Coordinate:
   -242531537200112594084676766080816663423582032543698976420161979758741
   05796326
Elliptic Curve Y-Coordinate:
   487227145385914945527872889161867481853236780821268431652936646431343
   52536146
Certificate Extensions:
     Subject Key Identifier Extension:
          OID: 2.5.29.14
         Is Critical: false
          Key Identifier:
               21:ad:b9:7a:15:e4:08:13:05:e1:c2:64:0c:86:aa:9b:f0:4c:fb:a0
     Authority Key Identifier Extension:
         OID: 2.5.29.35
          Is Critical: false
          Key Identifier:
               01:4b:69:99:93:5f:76:51:39:95:61:cc:a9:a8:cb:16:f2:0f:8c:c8
     Subject Alternative Name Extension:
         OID: 2.5.29.17
         Is Critical: false
         DNS Name: ds1.example.com
         DNS Name: ds.example.com
         DNS Name: ldap.example.com
         DNS Name: localhost
          IP Address: 127.0.0.1
         IP Address: 0:0:0:0:0:0:0:1
    Key Usage Extension:
         OID: 2.5.29.15
         Is Critical: false
          Key Usages:
               Digital Signature
               Key Encipherment
               Key Agreement
    Extended Key Usage Extension:
         OID: 2.5.29.37
          Is Critical: false
          Key Purpose ID: TLS Server Authentication
```

```
Key Purpose ID: TLS Client Authentication
SHA-1 Fingerprint:
  42:f8:85:97:bf:88:bc:74:4b:5b:ce:0c:54:43:9b:44:6b:81:23:a3
SHA-256 Fingerprint:
  4f:be:47:ed:36:68:13:38:ba:e8:c0:c5:6c:85:51:97:8b:40:1b:76:
  10:c0:be:80:15:62:06:96:c5:71:30:df
Private Key Available: Yes
The certificate has a valid signature.
Alias: server-cert (Certificate 2 of 2 in a chain)
X.509 Certificate Version: v3
Subject DN: CN=Example Certification Authority,O=Example Corp,C=US
Issuer DN: CN=Example Certification Authority,0=Example Corp,C=US
Serial Number: 43:b7:bb:0c:82:58:42:d8:06:fc:2a:f6:04:e8:2e:8c
Validity Start Time: Saturday, November 9, 2019 at 11:26:08 AM CST
                    (9 minutes, 49 seconds ago)
Validity End Time: Friday, November 4, 2039 at 12:26:08 PM CDT
                  (7299 days, 23 hours, 50 minutes, 10 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Signature Value:
    30:45:02:21:00:b9:87:50:5d:b7:6a:19:82:99:9b:aa:f1:5d:25:a1:90:3c:
    17:9d:7f:f5:7f:8d:06:b4:57:41:9e:15:c6:5a:af:02:20:0c:00:5e:17:bf:
    ca:bf:0b:ff:db:9f:dc:55:ad:35:eb:df:f6:37:4e:23:83:36:88:d2:cc:
    7d:9e:23:da:78:28
Public Key Algorithm: EC (secP256r1)
Elliptic Curve Public Key Is Compressed: false
Elliptic Curve X-Coordinate:
  Elliptic Curve Y-Coordinate:
  6707935650390842729237891844088941200265948573168357073736512795355450855373
Certificate Extensions:
    Subject Key Identifier Extension:
         OID: 2.5.29.14
         Is Critical: false
         Key Identifier:
             01:4b:69:99:93:5f:76:51:39:95:61:cc:a9:a8:cb:16:f2:0f:8c:c8
    Basic Constraints Extension:
         OID: 2.5.29.19
         Is Critical: false
         Is CA: true
         Path Length Constraint: 0
    Key Usage Extension:
         OID: 2.5.29.15
         Is Critical: false
         Key Usages:
              Key Cert Sign
              CRL Sign
SHA-1 Fingerprint: b8:d0:16:9b:5d:f2:e7:a1:80:79:95:a2:64:b5:aa:ad:80:23:64:16
SHA-256 Fingerprint:
  cf:98:2a:66:35:6e:6d:f9:5d:25:c6:68:68:04:5a:a8:88:43:ca:b5:c8:e5:c9:95:09:
  e9:fc:ab:b9:41:ec:71
The certificate has a valid signature.
```

Generating self-signed certificates

The process of creating a self-signed certificate is straightforward because a self-signed certificate claims itself as its own issuer.

Although self-signed certificates are convenient for testing environments, clients do not trust them by default. Consequently, you should not use them as listener certificates in production environments.

The **manage-certificates** tool offers a **generate-self-signed-certificate** subcommand that can create a self-signed certificate. In addition to the arguments that provide information about the keystore, certificate alias, and optional private key password, the following arguments are available.

Argument	Description
subject-dn {subject}	Subject DN for the certificate to create. This value is required.
days-valid {number}	Number of days that the certificate remains valid. Defaults to 365 if no value is specified.
validity-start-time {timestamp}	Indicates the time at which the certificate begins its validity window. This value is assumed to reflect the local time zone, and must be expressed in the form YYYYMMDDhhmmss, where a value of 20190102030405 indicates January 2, 2019, at 3:04:05 AM. Defaults to the current time if no value is specified.
key-algorithm {name}	 Name of the algorithm to use when generating the key pair. For a listener certificate, this value is typically RSA or EC. Defaults to RSA if no value is specified. Note This argument cannot be used in conjunction with thereplace-existing-certificate argument.
key-size-bits {number}	Length of the key, in bits, to generate. If thekey- algorithm argument is given, thenkey-size-bits {number} must also be specified. Conversely, if the replace-existing-certificate argument is given, then key-size-bits {number} must not be specified. Typical key sizes are: • RSA key - 2048 or 4096 bits If a default RSA key is used but this argument is not provided, a default key size of 2048 bits is used. • Elliptic curve key - 256 or 384 bits

Argument	Description
Signature-algorithm {name}	Name of the algorithm to use to sign the certificate. If the key-algorithm argument is used to specify an algorithm other than RSA, thensignature-algorithm {name} must also be specified. If thereplace-existing-certificate argument is used, thensignature-algorithm {name} must not be specified. Typical signature algorithms include SHA256withRSA for certificates with RSA keys, and SHA256withECDSA for certificates with elliptic curve keys. If a default key algorithm is used but thesignature-algorithm {name} argument is not provided, a default value of SHA256withRSA is used.
replace-existing-certificate	Uses the new certificate to replace an existing certificate in the key store (within the same alias), and reuses the key for that certificate.
inherit-extensions	Indicates that, when replacing an existing certificate, the new certificate contains the same set of extensions as the existing certificate. If thereplace-existing-certificate argument is provided, but theinherit-extensions argument is omitted, the new certificate contains only arguments that are provided explicitly.
subject-alternative-name-dns {name}	Indicates that the certificate is expected to have a subject alternative name extension with the provided DNS name. The given name must be fully qualified, although it can contain an asterisk (*) as a wildcard in the leftmost component. To include multiple DNS names in the subject alternative name extension, specify thesubject-alternative-name- dns {name} argument multiple times.
subject-alternative-name-ip-address {address}	Indicates that the certificate is expected to have a subject alternative name extension with the provided IP address. The given address must be a valid IPv4 or IPv6 address. No wildcards are allowed. To include multiple IP addresses in the subject alternative name extension, specify thesubject-alternative-name- ip-address {address} argument multiple times.
subject-alternative-name-email-address {address}	Indicates that the certificate is expected to have a subject alternative name extension with the provided email address. To include multiple email addresses in the subject alternative name extension, specify thesubject-alternative-name- email-address {address} argument multiple times.

Argument	Description
subject-alternative-name-uri {uri}	Indicates that the certificate is expected to have a subject alternative name extension with the provided URI. To include multiple URIs in the subject alternative name extension, specify thesubject-alternative-name-uri {uri} argument multiple times.
subject-alternative-name-oid {oid}	Indicates that the certificate is expected to have a subject alternative name extension with the provided object identifier (OID). The given value must be a valid OID. To include multiple OIDs in the subject alternative name extension, specify thesubject-alternative-name-oid {oid} argument multiple times.
basic-constraints-is-ca {value}	Indicates that the certificate is expected to have a basic constraints extension, with a specified value of true or fals e, for the flag indicating whether to consider the certificate a certification authority that can be used to sign other certificates.
	 For root and intermediate certificate authority (CA) certificates, thebasic-constraints-is-ca {value} argument must be present with a value of true. For end-entity certificates, thebasic-constraints-is-ca {value} argument can optionally be present with a value of false. For a self-signed certificate, specify thebasic-constraints-is-ca {value} argument with a value of false. for a self-signed certificate, specify thebasic-constraints-is-ca {value} argument with a value of false.
basic-constraints-maximum-path-length {number}	 Indicates that the basic constraints extension is expected to include a path length constraint element with the specified value. Use this argument only if basic-constraints-is-ca is provided with a value of true e. A path length constraint value of 0 indicates that the certificate can be used to issue only end-entity certificates. A path length constraint value of 1 indicates that the certificate can be used to sign end-entity certificates or intermediate CA certificates, the latter of which can be used to sign only end-entity certificates. A value greater than 1 indicates the presence of several intermediate CA certificates between it and the end-entity

Argument	Description
key-usage {value}	<pre>Indicates that the certificate is expected to have a key usage extension with the specified value. The following values are allowed:</pre>
extended-key-usage {value}	<pre>Indicates that the certificate is expected to have an extended key usage extension with the specified value. The following values are allowed:</pre>

Example

For example, the following command can be used to generate a self-signed server certificate.

```
bin/manage-certificates generate-self-signed-certificate \
    --keystore config/keystore \
    --keystore-password-file config/keystore.pin \
     --keystore-type JKS \
    --alias server-cert \
    --subject-dn "CN=ds.example.com,O=Example Corp,C=US" \
    --key-algorithm EC \
    --key-length-bits 256 \
    --signature-algorithm SHA256withECDSA \
    --subject-alternative-name-dns ds.example.com \
    --subject-alternative-name-dns ds1.example.com \
    --subject-alternative-name-dns localhost \
    --subject-alternative-name-ip-address 1.2.3.4 \
     --subject-alternative-name-ip-address 127.0.0.1 \
    --subject-alternative-name-ip-address 0:0:0:0:0:0:0:1 \
    --key-usage digital-signature \
     --key-usage key-encipherment \
    --key-usage key-agreement \
    --extended-key-usage server-auth \
     --extended-key-usage client-auth
Successfully created a new JKS keystore.
Successfully generated the following self-signed certificate:
Subject DN: CN=ds.example.com,O=Example Corp,C=US
Issuer DN: CN=ds.example.com,O=Example Corp,C=US
Validity Start Time: Monday, January 27, 2020 at 03:40:13 PM CST
                     (0 seconds ago)
Validity End Time: Tuesday, January 26, 2021 at 03:40:13 PM CST
                   (364 days, 23 hours, 59 minutes, 59 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Public Key Algorithm: EC (secP256r1)
SHA-1 Fingerprint: 4f:41:82:7f:08:e9:d8:05:8c:19:8b:3e:5b:bc:59:98:d3:15:71:3a
SHA-256 Fingerprint:
  76:e6:8e:c5:c8:8d:27:ce:2b:85:b9:8c:9d:49:3c:06:f4:40:f1:d0:70:67:39:24:fc:
  31:bc:f8:51:83:f2:42
```

Generating certificate signing requests

A certificate signing request (CSR) contains all of the information that a certification authority requires to issue a certificate.

RFC 2986^亿 defines the request format, also known as PKCS #10, and includes the following elements:

- Certificate signing request version
- Requested subject distinguished name (DN) for the certificate
- Public key for the requested certificate
- · Requested set of extensions for the certificate
- Signature that proves the requester has the private key for the given public key

To create a certificate signing request, use the **manage-certificates generate-certificate-signing-request** command, which performs the following steps:

- 1. Generated a public and private key pair.
- 2. Stores the key pair in a key store with a given alias.
- 3. Outputs the certificate signing request to the terminal.
- 4. Optionally writes the certificate signing request to a file.

Because a certificate signing request contains many of the same elements as a certificate, the command to generate one takes most of the same arguments as for generating a self-signed certificate. The following arguments are unavailable when generating a CSR:

```
    --replace-existing-certificate
```

• --days-valid {number}

```
    --validity-start-time {timestamp}
```

The following arguments are available when generating a certificate signing request but not when generating a self-signed certificate:

--output-file {path}

Path to a file to which the certificate signing request is written. If this value is not provided, the request is written only to the terminal in PEM form.

--output-format {value}

Format to use when writing the certificate signing request. This value can be **PEM** or **DER**, but the DER format is used only in conjunction with the --output-file argument. Defaults to **PEM** if the --output-format {value} argument is not provided.

--use-existing-key-pair

Indicates that the CSR uses a key pair that already exists in the key store with the given alias, rather than generating a new key pair, in which case the specified alias must not already be in use in the key store.

The following example command creates a CSR.

```
bin/manage-certificates generate-certificate-signing-request \
     --output-file ds1-cert.csr \
     --output-format PEM \
     --keystore config/keystore \
     --keystore-password-file config/keystore.pin \
     --keystore-type JKS \setminus
     --alias server-cert \
     --subject-dn "CN=ds.example.com,O=Example Corp,C=US" \
     --key-algorithm EC \setminus
     --key-length-bits 256 \
     --signature-algorithm SHA256withECDSA \
     --subject-alternative-name-dns ds.example.com \
     --subject-alternative-name-dns ds1.example.com \
     --subject-alternative-name-dns localhost \
     --subject-alternative-name-ip-address 1.2.3.4 \
     --subject-alternative-name-ip-address 127.0.0.1 \
     --subject-alternative-name-ip-address 0:0:0:0:0:0:0:1 \
     --key-usage digital-signature \
     --key-usage key-encipherment \
     --key-usage key-agreement \
     --extended-key-usage server-auth \
     --extended-key-usage client-auth
```

If the contents of the resulting CSR file are made available to a certification authority to be signed, the resulting signed certificate can be imported into the key store.

To print the contents of a certificate signing request file, use the **display-certificate-signing-request-file** subcommand, which supports the following arguments:

--certificate-signing-request-file {path}

Path to the file that contains the certificate signing request to display.

--verbose

Indicates that the command is expected to display verbose information about the request, rather than a basic information set.

The following example demonstrates the basic output from the command.

The following example demonstrates the verbose output.

```
$ bin/manage-certificates display-certificate-signing-request-file \
    --certificate-signing-request-file ds1-cert.csr \
     --verbose
PKCS #10 Certificate Signing Request Version: v1
Subject DN: CN=ds.example.com,O=Example Corp,C=US
Signature Algorithm: SHA-256 with ECDSA
Signature Value:
    30:45:02:20:46:31:be:9e:6d:2f:0e:e3:d0:80:5c:88:ef:da:86:07:fd:15:b7:62:
    83:45:39:0a:c9:f2:f9:17:eb:08:94:ff:02:21:00:c8:bd:df:57:fa:ea:8c:04:
    df:c5:27:76:e5:b3:3b:4f:df:ec:d3:e4:09:5b:c0:6c:7b:86:39:ec:d0:0e:c1:64
Public Key Algorithm: EC (secP256r1)
Elliptic Curve Public Key Is Compressed: false
Elliptic Curve X-Coordinate:
  2086285379047579631978894716670982397622966387996624365020701122793024
  3221133
Elliptic Curve Y-Coordinate:
  479697739226644990505743464941788269420922508654777168408919906254139
   60212095
Certificate Extensions:
    Subject Key Identifier Extension:
         OID: 2.5.29.14
         Is Critical: false
         Key Identifier:
              f2:de:fd:bf:d3:2f:96:ef:01:70:2d:0e:85:f5:fb:17:d5:a0:9e:67
    Subject Alternative Name Extension:
         OID: 2.5.29.17
         Is Critical: false
         DNS Name: ds.example.com
         DNS Name: ds1.example.com
         DNS Name: localhost
         IP Address: 1.2.3.4
         IP Address: 127.0.0.1
         IP Address: 0:0:0:0:0:0:0:1
     Key Usage Extension:
         OID: 2.5.29.15
         Is Critical: false
         Key Usages:
              Digital Signature
              Key Encipherment
              Key Agreement
     Extended Key Usage Extension:
         OID: 2.5.29.37
         Is Critical: false
         Key Purpose ID: TLS Server Authentication
         Key Purpose ID: TLS Client Authentication
```

Importing signed and trusted certificates

Use the manage-certificates import-certificate command to import certificates into a keystore.

This command is used to accomplish the following tasks:

• Import a certificate that a certification authority has signed into the keystore in which the key pair was generated. In this scenario, the certificate is imported into a private key entry and must be imported as a certificate chain rather than an end-entity certificate.

- Import a trusted issuer certificate into a trust store. In this scenario, the certificate is imported into a trusted certificate entry as a single certificate instead of as a chain.
- Import a certificate chain, along with the private key for the end-entity certificate. This approach imports certificates that were generated through another library, like OpenSSL.

In addition to the arguments that provide information about the key store and the alias into which the certificate or certificate chain is imported, the manage-certificates import-certificate command accepts the following arguments:

--certificate-file {path}

Path to the file that contains the certificate to import. The certificate can be in PEM or DER format and can be a single certificate or a certificate chain. If the certificates in the chain reside in separate files, specify the --certificate-file {path} argument multiple times when you import a certificate chain.

--private-key-file {path}

Path to the file containing the private key that corresponds to the certificate at the head of the imported chain. The private key can be in PEM or DER format.

--no-prompt

Indicates that the certificate is to be imported without prompting for confirmation. By default, a summary of the certificate is displayed, and you must confirm that you want to import it.

The following example command imports a signed certificate into the key store that generates the certificate signing request.

\$ bin/manage-certificates import-certificate \ --keystore config/keystore $\$ --keystore-password-file config/keystore.pin \ --alias server-cert \ --certificate-file ds1-cert.pem \ --certificate-file ca-cert.pem The following certificate chain will be imported into the keystore into alias 'server-cert', preserving the existing private key associated with that alias: Subject DN: CN=ds.example.com,O=Example Corp,C=US Issuer DN: CN=Example Root CA,O=Example Corp,C=US Validity Start Time: Sunday, November 10, 2019 at 09:09:23 PM CST (4 minutes, 16 seconds ago) Validity End Time: Monday, November 9, 2020 at 09:09:23 PM CST (364 days, 23 hours, 55 minutes, 43 seconds from now) Validity State: The certificate is currently within the validity window. Signature Algorithm: SHA-256 with ECDSA Public Key Algorithm: EC (secP256r1) SHA-1 Fingerprint: 02:51:25:43:3e:68:f5:71:36:e3:5d:df:74:de:f6:a1:5a:db:0f:eb SHA-256 Fingerprint: 1d:b5:eb:3c:f5:ff:bf:79:a2:a5:86:b8:e4:33:76:4d:d7: 50:dc:a4:34:95:37:be:89:45:86:1f:5d:79:c3:93 Subject DN: CN=Example Root CA,O=Example Corp,C=US Issuer DN: CN=Example Root CA,O=Example Corp,C=US Validity Start Time: Sunday, November 10, 2019 at 09:00:07 PM CST (13 minutes, 32 seconds ago) Validity End Time: Saturday, November 5, 2039 at 10:00:07 PM CDT (7299 days, 23 hours, 46 minutes, 27 seconds from now) Validity State: The certificate is currently within the validity window. Signature Algorithm: SHA-256 with ECDSA Public Key Algorithm: EC (secP384r1) SHA-1 Fingerprint: 0e:5c:21:c9:a5:36:0a:24:eb:aa:55:b6:a5:94:0e:e0:56:03:22:e6 SHA-256 Fingerprint: 77:cf:66:d7:3c:8a:fd:67:2d:b7:36:fd:60:1d:ca:eb:1b:03:b1: 12:7b:10:1f:26:05:b7:b9:0d:02:e0:38:3e Do you want to import this certificate chain into the keystore? yes Successfully imported the certificate chain.

If you do not provide the --no-prompt argument, the manage-certificates import-certificate tool still displays information about the certificates to import. To view additional information about a certificate before you import it, use the display-certificate-file subcommand, which supports the following arguments:

--certificate-file {path}

Path to the file that contains the certificate to view.

--verbose

Displays verbose information about the certificate.

The output of the **display-certificate-file** subcommand has the same format and content as the **list-certificates** subcommand.

Exporting certificates

Use the **export-certificate** subcommand to export a single certificate or a certificate chain from a key store to a file in PEM or DER format.

The **export-certificate** subcommand supports the normal arguments about the key store and certificate alias, in addition to the following arguments:

--output-file {path}

Path to the file to which exported certificates are written. If this value is not provided, the certificates are written to standard output rather than a file.

--output-format {format}

Format in which exported certificates are written. The value can be **PEM** or **DER**, but the DER format can be used only if the output is written to a file. Defaults to **PEM** if no value is specified.

--export-certificate-chain

Indicates that a certificate chain, rather than the end-entity certificate only, is to be exported.

--separate-file-per-certificate

Indicates the use of separate output files for each exported certificate, rather than placing all of the certificates in a single file. If this argument is provided and multiple certificates are to be exported, then .1 is appended to the path for the indicated output file for the first certificate in the chain, .2 is appended for the second certificate, and so on.

The following example exports a certificate chain.

```
$ bin/manage-certificates export-certificate \
    --keystore config/keystore \
    --keystore-password-file config/keystore.pin \
    --alias server-cert \
     --output-file server-cert.pem \
    --output-format PEM \
    --export-certificate-chain \
    --separate-file-per-certificate
Successfully exported the following certificate to '/ds/server-cert.pem.1':
Subject DN: CN=ds.example.com,O=Example Corp,C=US
Issuer DN: CN=Example Root CA,O=Example Corp,C=US
Validity Start Time: Sunday, November 10, 2019 at 09:09:23 PM CST
                    (3 hours, 26 minutes, 23 seconds ago)
Validity End Time: Monday, November 9, 2020 at 09:09:23 PM CST
                          (364 days, 20 hours, 33 minutes, 36 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Public Key Algorithm: EC (secP256r1)
SHA-1 Fingerprint: 02:51:25:43:3e:68:f5:71:36:e3:5d:df:74:de:f6:a1:5a:db:0f:eb
SHA-256 Fingerprint:
1d:b5:eb:3c:f5:ff:bf:79:a2:a5:86:b8:e4:33:76:4d:d7:50:dc:a4:34:95:37:be:89:45:
86:1f:5d:79:c3:93
Successfully exported the following certificate to '/ds/server-cert.pem.2':
Subject DN: CN=Example Root CA,O=Example Corp,C=US
Issuer DN: CN=Example Root CA,O=Example Corp,C=US
Validity Start Time: Sunday, November 10, 2019 at 09:00:07 PM CST
                     (3 hours, 35 minutes, 39 seconds ago)
Validity End Time: Saturday, November 5, 2039 at 10:00:07 PM CDT
                   (7299 days, 20 hours, 24 minutes, 20 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with ECDSA
Public Key Algorithm: EC (secP384r1)
SHA-1 Fingerprint: 0e:5c:21:c9:a5:36:0a:24:eb:aa:55:b6:a5:94:0e:e0:56:03:22:e6
SHA-256 Fingerprint:
  77:cf:66:d7:3c:8a:fd:67:2d:b7:36:fd:60:1d:ca:eb:1b:03:b1:12:7b:10:1f:26:
  05:b7:b9:0d:02:e0:38:3e
```

The **export-certificate** subcommand exports only the public portion of a certificate. Its private key is not included. To export the private key, use the **export-private-key** subcommand, which supports the following arguments, in addition to the usual key store and alias arguments:

--output-file {path}

Path to the file to which the exported private key is written. If this value is not provided, the key is written to standard output rather than a file.

--output-format {format}

Format in which the exported private key is written. The value can be **PEM** or **DER**, but the DER format is used only if the output is written to a file. Defaults to **PEM** if no value is specified.

The following code provides an example of the **export-private-key** subcommand .

```
$ bin/manage-certificates export-private-key \
         --keystore config/keystore \
         --keystore-password-file config/keystore.pin \
         --alias server-cert \
         --output-file server-cert-key.pem \
         --output-format PEM
```

Successfully exported the private key.

Enabling TLS support during server setup

Enable TLS support in the server.

To enable TLS support in the server, you should complete one of the following tasks during the setup procedure:

- Provide a key store that contains the certificate to use.
- Make the installer generate a self-signed certificate.

When using the **setup** tool in interactive mode, it prompts you for the information that it needs to configure secure communication.

When using **setup** in non-interactive mode, use the following arguments to configure TLS support.

Argument	Description
ldapsPort {port}	Server enables support for LDAPS (LDAP over TLS) on the specified TCP port.
httpsPort {port}	Server enables support for HTTPS for SCIM, the Directory REST API, and the web-based administration console on the specified TCP port.
enableStartTLS	LDAP connection handler enables support for the StartTLS extended operation.
generateSelfSignedCertificate	setup generates a self-signed certificate that is presented to clients that use LDAPS, HTTPS, and the StartTLS extended operation.
useJavaKeyStore {path}	Server uses the specified Java KeyStore (JKS) key store to obtain the certificate chain that it presents to clients that use LDAPS, HTTPS, and the StartTLS extended operation.
usePKCS12KeyStore {path}	Server uses the specified PKCS #12 key store to obtain the certificate chain that it presents to clients that use LDAPS, HTTPS, and the StartTLS extended operation.

Argument	Description
usePKCS11KeyStore	Server uses a PKCS #11 key store, like a hardware security module, to obtain the certificate chain that it presents to clients that use LDAPS, HTTPS, and the StartTLS extended operation. The Java Virtual Machine (JVM) must already be configured to access the appropriate key store through PKCS #11.
keyStorePassword {password}	Password that is needed to interact with the specified JKS, PKCS #12, or PKCS #11 key store. The setup tool assumes that the private key password matches the key store password.
keyStorePasswordFile {path}	Path to the file that contains the password needed to interact with the specified JKS, PKCS #12, or PKCS #11 key store.
certNickname {alias}	Alias of the private key entry in the specified key store that contains the certificate chain to present to clients during TLS negotiation. This argument is optional but recommended if the key store contains multiple certificates.
useJavaTrustStore {path}	Server uses the specified JKS trust store to determine whether to trust certificate chains that are presented to it during TLS negotiation.
usePKCS12TrustStore {path}	Server uses the specified PKCS #12 trust store to determine whether to trust certificate chains that are presented to it during TLS negotiation
trustStorePassword {password}	Password that is needed to interact with the specified JKS or PKCS #11 trust store.
trustStorePasswordFile {path}	Path to the file that contains the password needed to interact with the specified JKS or PKCS #11 trust store.

The following example command sets up PingAuthorize in non-interactive mode with an existing certificate.

\$./setup \ --no-prompt \ --acceptLicense $\$ --ldapPort 8389 \ --ldapsPort 8636 \ --httpsPort 8443 \ --enableStartTLS \ --useJavaKeyStore config/keystore \ --keyStorePasswordFile config/keystore.pin \ --certNickname server-cert \ --useJavaTrustStore config/truststore \ --trustStorePasswordFile config/truststore.pin \ --rootUserDN "cn=Directory Manager" \ --rootUserPasswordFile root-pw.txt \ --maxHeapSize 1g \ --location Austin $\$ --instanceName paz1 . . . Initializing Done Configuring PingAuthorize Server Done Configuring Certificates Done Creating Encryption Settings Done Starting PingAuthorize Server Done The server is now ready for configuration. You may either run the create-initial-config tool to continue configuration or import an existing configuration using dsconfig. Access product documentation from https://myhostname:8443/docs/index.html

Enabling TLS support after setup

If the server has been set up without support for TLS, enable TLS support later by completing the following tasks.

Steps

1. Obtain a certificate chain.

For more information about obtaining a certificate chain, see **Certificate chains**. To prepare a Java KeyStore JKS or PKCS #12 key store with an appropriate certificate chain and private key, use the **manage-certificates** tool. We also recommend that you create a trust store that the server can use.

2. Configure the key and trust manager providers.

For more information, see Configuring key and trust manager providers.

3. Configure connection handlers.

For more information, see Configuring TLS connection handlers.

Configuring key and trust manager providers

After you have a key store, configure a key manager provider to access it.

The server is preconfigured with key manager providers, JKS and PKCS12, that you can use with JKS or PKCS #12 key stores, respectively. You can update the appropriate key manager provider in most cases to reference the key store that you plan to use. The following code provides an example.

```
dsconfig set-key-manager-provider-prop \

--provider-name JKS \

--set enabled:true \

--set key-store-file:config/keystore \

--set key-store-pin-file:config/keystore.pin
```

A similar change configures a trust manager provider to reference the appropriate trust store. The following code provides an example.

```
dsconfig set-trust-manager-provider-prop \
    --provider-name JKS \
    --set enabled:true \
    --set include-jvm-default-issuers:true \
    --set trust-store-file:config/truststore \
    --set trust-store-pin-file:config/truststore.pin
```

(i) Note

If all clients and servers use certificates that are signed by issuers and are included in the JVM's default trust store, you can use the JVM-Default trust manager provider to accomplish this task.

Configuring TLS connection handlers

After you configure the key and trust manager providers, update the connection handlers to use the key and trust manager providers.

Steps

• For the LDAP connection handler, use the following command to enable StartTLS with a configuration change. By default, the LDAP connection handler accepts non-secure connections.

Example:

```
dsconfig set-connection-handler-prop \
    --handler-name "LDAP Connection Handler" \
    --set allow-start-tls:true \
    --set key-manager-provider:JKS \
    --set trust-manager-provider:JKS \
    --set ssl-cert-nickname:server-cert \
    --set ssl-client-auth-policy:optional
```

• If you did not configure secure communication during setup, the LDAPS connection handler is disabled. To configure LDAPS support in this scenario, enable the connection handler and configure most of the same settings. You must set allow-start-tls to false and use-ssl to true. See the following code for an example configuration.

Example:

```
dsconfig set-connection-handler-prop \
    --handler-name "LDAPS Connection Handler" \
    --set enabled:true \
    --set key-manager-provider:JKS \
    --set trust-manager-provider:JKS \
    --set ssl-cert-nickname:server-cert \
    --set ssl-client-auth-policy:optional
```

Example:

The following example uses a similar configuration change to enable the HTTPS connection handler.

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set enabled:true \
    --set listen-port:443 \
    --set key-manager-provider:JKS \
    --set trust-manager-provider:JKS \
    --set ssl-cert-nickname:server-cert
```

Updating the topology registry

After the server connection handlers are updated to enable TLS, update the topology registry to provide information about the new configuration.

The topology registry holds information about server instances that are part of the environment, and it helps to facilitate interserver communication, such as replication, mirroring portions of the configuration, and the PingAuthorize automatic backend server-discovery functionality.

The following table details the two types of entries that require updating.

Configuration	types	and	their	update	descriptions

Configuration Type	Update description		
Server instance listener configuration	 Provides information that is needed to trust the TLS certificates that instances in the topology present. The server instance listener configuration must include the server certificate, which is defined as the certificate at the head of the chain. This version must be the multi-line, PEM-formatted representation of the certificate. You can use dsconfig to import the certificate from a file, as shown in the following example. 		
	<pre>bin/dsconfig set-server-instance-listener-prop \ instance-name ds1 \ listener-name ldap-listener-mirrored-config \ set server-ldap-port:636 \ set connection-security:ssl \ set 'listener-certificate>/ca/ds1-cert.pem'</pre>		
	ONOTE The less-than operator > in the final line indicates that the value is read from a file rather than provided directly. In addition, you might not need to enclose the property name and path within single straight quotes to prevent the shell from interpreting the less-than symbol as an attempt to redirect input.		
Server instance configuration	 Provides information about options for communicating with those instances. Update the server instance configuration object to reflect the new methods that are available for communication with the instance. For example, the pr eferred-security property identifies the mechanism by which other instances in the topology attempt to communicate with the instance. The following example code sets the LDAPS and HTTPS ports, indicates that 		
	<pre>StartTLS support is enabled, and instructs other instances to use SSL (LDAPS) when communicating with the instance. dsconfig set-server-instance-prop \ instance-name ds1 \ set ldaps-port:636 \ set https-port:443 \ set preferred-security:ssl \ set start-tls-enabled:true</pre>		

Troubleshooting TLS-related issues

Use this section for troubleshooting problems that might arise during TLS configuration, including communication and security issues that affect clients as well as PingAuthorize.

- Log messages
- manage-certificates check-certificate-usability
- Idapsearch
- Using low-level TLS debugging

Log messages

The following describes how to use the server's log messages to troubleshoot TLS-related issues.

To troubleshoot TLS-related issues, start by checking the server's access log. If the client can establish a TCP connection to the server, which must occur before TLS negotiation can start, the access log shows a **CONNECT** message with the following information:

- Source and destination address and port for the connection
- Protocol
- · Selected client connection policy

The CONNECT message does not appear

If the **CONNECT** does not appear, the client might be unable to communicate with the server. The culprit can be a network problem, a firewall that is blocking attempts to communicate, or the client is trying to use an incorrect address or port.

The CONNECT message does appear

If the **CONNECT** message appears in the access log, it typically includes a **conn** element that specifies the connection ID. To view additional log messages for the client connection, use the **search-logs** tool. For example, if the connection ID is **12345**, the following command displays the complete set of associated log messages.

```
$ bin/search-logs --logFile logs/access conn=12345
```

If you are using LDAPS

If you are attempting to use LDAPS, one of the following log messages appears next:

- **SECURITY-NEGOTIATION** message Indicates that the client and server successfully completed the negotiation process and that the issue likely occurred after the TLS session was established. This message also includes details about the negotiation, including the TLS protocol and the selected cipher suite.
- **DISCONNECT** message The issue might involve a failure in the TLS-negotiation process. In such scenarios, the message usually includes a **reason** element that provides additional information about the reason for the disconnect.

If the failure occurred during TLS negotiation, the usefulness of the **DISCONNECT** message depends in part on whether the failure occurred on the client or the server. For example, if the server decided to abort the negotiation, the message ideally contains the specific reason. If the problem occurred on the client, the log message likely contains only the general category for the failure.

(i) Note

The TLS protocol does not provide a mechanism for conveying detailed error messages. Instead, it offers only a basic alert mechanism with a fixed set of alert types. For example, if a client does not trust the certificate chain that the server presents to it, the server might receive a generic alert like certificate_unknown, even if the client knows the precise reason for rejecting the chain. In such instances, you might need to determine whether the client can provide additional details about the issue.

If the access log does not provide useful information

If the access log does not provide useful information, check the server error log. Although the error log does not normally include information about issues that relate to client communication, it provides helpful information in certain circumstances, like when an internal error within the server interferes with communication attempts.

About manage-certificates check-certificate-usability

The **manage-certificates** tool offers a **check-certificate-usability** subcommand to examine a specified entry in a key store and to identify potential issues that might interfere with secure communication.

The check-certificate-usability tool completes the following tasks:

- Ensures that a specified entry in the key store includes a private key and a complete certificate chain
- Checks whether the certificate at the root of the chain is found in the Java virtual machine's (JVM's) default set of trusted certificates
- Ensures that the current time lies is within the validity window for all certificates in the chain
- · Validates the signatures for all certificates in the chain
- · Warns if the end-entity certificate is self-signed

- Warns if the end-entity certificate does not contain an extended key usage extension with the serverAuth usage
- Warns if the issuer certificates do not have a key usage extension with the keyCertSign usage
- Warns if the issuer certificates do not have a basic constraints extension indicating that it can operate as a certification authority

If the chain violates a path length constraint, the **check-certificate-usability** tool reports an error.

• Ensures that the signature algorithm uses a strong message digest algorithm, like SHA-256

The **check-certificate-usability** tool reports an error for weak digest algorithms like MD5 or SHA-1, and reports a warning for unrecognized digest algorithms.

• Ensures that none of the certificates that use an RSA key pair have a key size less than 2048 bits

The following example demonstrates the usage for the **manage-certificates check-certificate-usability** command and its output when no problems are identified.

```
$ bin/manage-certificates check-certificate-usability \
    --keystore config/keystore \
     --keystore-password-file config/keystore.pin \
     --alias server-cert
Successfully retrieved the certificate chain for alias 'server-cert':
Subject DN: CN=ds1.example.com,O=Example Corp,C=US
Issuer DN: CN=Example Intermediate CA,O=Example Corp,C=US
Validity Start Time: Tuesday, November 12, 2019 at 03:52:44 PM CST
                    (5 minutes, 45 seconds ago)
Validity End Time: Wednesday, November 11, 2020 at 03:52:44 PM CST
                  (364 days, 23 hours, 54 minutes, 14 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with RSA
Public Key Algorithm: RSA (2048-bit)
SHA-1 Fingerprint: 84:e4:00:b9:f0:6b:58:bb:ac:67:79:28:2f:43:9f:e3:ac:24:ee:98
SHA-256 Fingerprint: 63:85:4d:2c:50:ea:a8:84:54:e0:73:9a:e7:5b:e7:1b:06:85:0e:
                     28:2b:76:a9:8b:57:fc:27:f7:60:81:48:41
Subject DN: CN=Example Intermediate CA,O=Example Corp,C=US
Issuer DN: CN=Example Root CA,O=Example Corp,C=US
Validity Start Time: Tuesday, November 12, 2019 at 03:52:42 PM CST
                    (5 minutes, 47 seconds ago)
Validity End Time: Monday, November 7, 2039 at 03:52:42 PM CST
                   (7299 days, 23 hours, 54 minutes, 12 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with RSA
Public Key Algorithm: RSA (4096-bit)
SHA-1 Fingerprint: de:da:3d:fc:d4:1f:67:79:0a:a1:5a:cd:ca:4a:7e:a5:d3:46:88:27
SHA-256 Fingerprint:
  02:3c:af:ad:b7:07:81:89:45:48:d0:09:31:a8:90:c4:17:11:1c:00:11:fd:49:b2:2c:
  ba:ac:dd:c4:9f:03:36
Subject DN: CN=Example Root CA,O=Example Corp,C=US
Issuer DN: CN=Example Root CA,O=Example Corp,C=US
Validity Start Time: Tuesday, November 12, 2019 at 03:52:38 PM CST
                    (5 minutes, 51 seconds ago)
Validity End Time: Monday, November 7, 2039 at 03:52:38 PM CST
                  (7299 days, 23 hours, 54 minutes, 8 seconds from now)
Validity State: The certificate is currently within the validity window.
Signature Algorithm: SHA-256 with RSA
Public Key Algorithm: RSA (4096-bit)
SHA-1 Fingerprint: 8e:03:e4:58:e6:e3:59:9a:55:77:c0:88:3c:fa:d7:29:f4:ff:de:6c
SHA-256 Fingerprint: 95:54:0d:e2:aa:48:29:c1:25:7c:20:69:c0:27:33:31:81:07:02:
                     2e:00:24:ae:49:5e:98:bd:a3:72:a5:05:26
OK: The certificate chain is complete. Each subsequent certificate is
the issuer for the previous certificate in the chain, and the chain ends
with a self-signed certificate.
OK: Certificate 'CN=ds1.example.com,O=Example Corp,C=US' has a valid
signature.
OK: Certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' has a
valid signature.
OK: Certificate 'CN=Example Root CA,O=Example Corp,C=US' has a valid
signature.
```

OK: Certificate 'CN=ds1.example.com,O=Example Corp,C=US' will expire at Wednesday, November 11, 2020 at 03:52:44 PM CST (364 days, 23 hours, 54 minutes, 14 seconds from now), which is not in the near future.

OK: Issuer certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' will expire at Monday, November 7, 2039 at 03:52:42 PM CST (7299 days, 23 hours, 54 minutes, 12 seconds from now), which is not in the near future.

OK: Issuer certificate 'CN=Example Root CA,O=Example Corp,C=US' will expire at Monday, November 7, 2039 at 03:52:38 PM CST (7299 days, 23 hours, 54 minutes, 8 seconds from now), which is not in the near future.

 OK : Certificate 'CN=ds1.example.com,O=Example Corp,C=US' at the head of the chain includes an extended key usage extension, and that extension includes the serverAuth usage.

OK: Issuer certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' includes a basic constraints extension, and the certificate chain satisfies those constraints.

OK: Issuer certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' includes a key usage extension with the keyCertSign usage flag set to true.

OK: Issuer certificate 'CN=Example Root CA,O=Example Corp,C=US' includes a basic constraints extension, and the certificate chain satisfies those constraints.

OK: Issuer certificate 'CN=Example Root CA,O=Example Corp,C=US' includes a key usage extension with the keyCertSign usage flag set to true.

OK: Certificate 'CN=ds1.example.com,O=Example Corp,C=US' uses a signature algorithm of 'SHA-256 with RSA', which is is considered strong.

OK: Certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' uses a signature algorithm of 'SHA-256 with RSA', which is is considered strong.

OK: Certificate 'CN=Example Root CA,O=Example Corp,C=US' uses a signature algorithm of 'SHA-256 with RSA', which is is considered strong.

OK: Certificate 'CN=ds1.example.com,O=Example Corp,C=US' has a 2048-bit RSA public key, which is considered strong.

OK: Certificate 'CN=Example Intermediate CA,O=Example Corp,C=US' has a 4096-bit RSA public key, which is considered strong.

OK: Certificate 'CN=Example Root CA,O=Example Corp,C=US' has a 4096-bit RSA public key, which is considered strong.

No usability errors or warnings were identified while validating the certificate chain.

If any usability issues are identified, they might be responsible for communication problems.

Idapsearch for TLS-related arguments

The **ldapsearch** command-line utility is a powerful tool for issuing searches against an LDAP directory server. It also provides a convenient method for troubleshooting a variety of issues, including problems that are relevant to TLS communication.

The following table details arguments that are the most useful for TLS-related communication.

TLS-related communication arguments and their descriptions

Argument	Description
hostname {address}	Address of the server to which the connection is established
port {port}	TCP port of the server to which the connection is established. The standard port for non-secure LDAP, or LDAP to be secured with StartTLS, is 389 , and the standard port for secure LDAPS is 636 . Many deployments use alternate ports, especially non-privileged ports above 1024 .
useSSL	The tool establishes an initially insecure LDAP connection, which is secured later with the StartTLS extended operation.
trustStorePath {path}	Path to the trust store that is used when determining whether to trust the certificate chain that the server presents during TLS negotiation. If neither this argument nor thetrustAll argument is provided, the tool prompts you interactively whether to trust server certificates that are not signed by an issuer in the Java virtual machine's (JVM's) default trust store.
trustStoreFormat {format}	Format for the trust store, which is typically JKS or PKCS12 .
trustStorePassword {password}	Password that is required to access the contents of the trust store.
trustStorePasswordFile {path}	Path to the file that contains the password that is required to access the contents of the trust store.
trustAll	The tool blindly trusts all TLS certificate chains that are presented to it. Although this argument can prove useful for troubleshooting purposes, it is not recommended for general use.
keyStorePath {path}	Path to the key store to use if a client certificate chain is presented to the server.
	 Note Use this argument only when one of the following conditions is satisfied: • The server is configured to require clients to present a certificate. • You intend to use the certificate to authenticate through SASL EXTERNAL.
keyStoreFormat {format}	Format for the key store, which is typically JKS or PKCS12 .
keyStorePassword {password}	Password to access the key store.
keyStorePasswordFile {path}	Path to the file that contains the password necessary to access the key store.

Argument	Description
certNickname {alias}	Alias of the private key entry in the key store. Use when obtaining the certificate chain to present to the server.
useSASLExternal	The client authenticates with the EXTERNAL SASL mechanism, which typically identifies the client using the certificate chain that is presented during TLS negotiation.
enableSSLDebugging	The tool activates the low-level TLS-debugging feature that the JVM provides.

The following command provides an example of the simplest method for testing TLS communication with PingAuthorize Server.

Example

```
$ bin/ldapsearch \
     --hostname ds1.example.com \
     --port 636 \
     --useSSL \
     --baseDN "" \
     --scope base \
     "(objectClass=*)"
The server presented the following certificate chain:
     Subject: CN=ds1.example.com,0=Example Corp,C=US
     Valid From: Tuesday, November 12, 2019 at 08:28:08 PM CST
     Valid Until: Wednesday, November 11, 2020 at 08:28:08 PM CST
     SHA-1 Fingerprint:
       6a:22:2a:bd:0b:1b:09:35:63:bc:12:3e:2c:9e:e7:70:bc:a4:73:de
     256-bit SHA-2 Fingerprint:
       7a:8c:e4:76:d4:47:15:fd:65:f5:26:0e:d2:55:77:d7:03:7a:e6:79:9f:bc:
        ae:93:2c:76:9c:01:fc:ef:15:38
     Issuer 1 Subject: CN=Example Intermediate CA,O=Example Corp,C=US
     Valid From: Tuesday, November 12, 2019 at 08:28:06 PM CST
     Valid Until: Monday, November 7, 2039 at 08:28:06 PM CST
     SHA-1 Fingerprint: 01:b3:70:8b:6c:11:43:87:3b:e9:bb:73:27:99:ea:fd:08:c4:db:ec
     256-bit SHA-2 Fingerprint: 49:60:69:df:33:9d:26:d0:66:c9:6d:7b:0b:cb:3b:96:
                               40:22:dc:6d:11:32:b7:c0:30:47:d6:7c:6a:19:cd:60
     Issuer 2 Subject: CN=Example Root CA,O=Example Corp,C=US
     Valid From: Tuesday, November 12, 2019 at 08:28:03 PM CST
     Valid Until: Monday, November 7, 2039 at 08:28:03 PM CST
    SHA-1 Fingerprint: b4:83:55:db:82:e4:63:5c:3a:44:13:8f:88:44:e3:60:f2:53:80:48
     256-bit SHA-2 Fingerprint:
        e8:af:6f:ed:b9:0e:df:94:9c:20:29:53:a9:74:44:a9:17:b4:08:65:c8:19:c1:fb:
        34:34:a1:90:83:8a:d5:12
Do you wish to trust this certificate? Enter 'y' or 'n': y
dn:
objectClass: top
objectClass: ds-root-dse
startupUUID: 8d574122-4584-4522-96d9-0cdcb9d2e339
startTime: 20191113061149Z
# Result Code: 0 (success)
# Number of Entries Returned: 1
```

Trust stores and trust-related arguments

If no trust-related arguments are provided, the tool uses the JVM's default trust store to verify whether to trust the certificate chain, based on the information that it contains. If a trusted authority has signed the server certificate, the negotiation process continues without further interaction.

If the chain cannot be trusted, based on the information in the JVM-default trust store, **1dapsearch** prompts you interactively about whether to trust the certificate. If you accept the chain, the client and server complete the negotiation process, and the client sends the search request to the server. If the search succeeds, the server can communicate over TLS.

To test with a trust store instead of being prompted interactively, use the --trustStorePath argument that points to the appropriate trust store. If you are using a Java Keystore (JKS) trust store, you might not need to provide the trust store password. If you are using a PKCS #12 trust store, you need to provide the trust store password. The following code provides an example.

Example

```
$ bin/ldapsearch \
    --hostname ds1.example.com \
    --port 636 \
    --useSSL \
    --trustStorePath config/truststore.p12 \
     --trustStorePasswordFile config/truststore.pin \
     --trustStoreFormat PKCS12 \
    --baseDN "" \
    --scope base \
     "(objectClass=*)"
dn:
objectClass: top
objectClass: ds-root-dse
startupUUID: c8724159-8c37-45eb-b210-879bfcf74ad6
startTime: 20191113154023Z
# Result Code: 0 (success)
# Number of Entries Returned: 1
```

Client certificate chains and key stores

To present a client certificate chain to the server, either because the server's connection handler is configured with an **sslclient-auth-policy** value of **required** or because you plan to use the certificate to authenticate by way of the SASL EXTERNAL mechanism, provide at least the key store and its corresponding password. You can also specify the alias of the certificate chain to present, which is recommended if your client key store contains multiple certificates. The following code provides an example.

Example

```
$ bin/ldapsearch \
    --hostname ds1.example.com \
     --port 636 \
     --useSSL \
     --trustStorePath config/truststore.p12 \
     --trustStorePasswordFile config/truststore.pin \
     --trustStoreFormat PKCS12 \
     --keyStorePath client-keystore \
    --keyStorePasswordFile client-keystore.pin \
    --certNickname client-cert \
    --useSASLExternal \
    --baseDN "" \
     --scope base \
    "(objectClass=*)"
dn:
objectClass: top
objectClass: ds-root-dse
startupUUID: c8724159-8c37-45eb-b210-879bfcf74ad6
startTime: 20191113154023Z
# Result Code: 0 (success)
# Number of Entries Returned: 1
```

If you need to further troubleshoot a TLS-related issue

If you encounter a TLS-related issue that you cannot resolve by examining the **ldapsearch** output or the server logs, use the -enableSSLDebugging option to enable the JVM's support for low-level debugging of TLS processing. For more information, see Using low-level TLS debugging.

Using low-level TLS debugging

Use tools other than the command-line tools that are provided with PingDirectory Server for performing low-level TLS debugging.

Before you begin

Λοτε

If you need to use low-level debugging options, enable the Java Virtual Machine (JVM)'s support for TLS debugging. Many of the command-line tools that are provided with PingDirectory Server, such as **ldapsearch**, offer an **-enableSSLDebugging** argument that simplifies this process.

Steps

1. In the config/java.properties file, add the following line to the set of properties for the appropriate tool.

-Djavax.net.debug=all

2. For the changes to take effect, run the **bin/dsjavaproperties** command.

Next steps

The next time the tool is run, an output is generated detailing the TLS-related processing that the JVM is performing. You and the Ping Identity support team can use the output to identify the issue.

Policy Decision Service configuration

You can configure the Policy Decision Service for either of the following policy decision environments:

Development environment (external)

Policies are developed in the Policy Editor. The Policy Editor serves as the external policy decision point (PDP), and the PingAuthorize Server serves as the policy enforcement point (PEP).

Learn more about configuring the Policy Decision Service for development environments in Configuring external PDP mode.

Pre-production and production environments (embedded)

Policies are developed in the Policy Editor and deployed to the PingAuthorize Server, which serves as both the PEP and the PDP. This configuration supports policy testing in pre-production environments and live policy decisions in production environments.

Learn more about configuring the Policy Decision Service for production environments in Use policies in a production environment.

Configuring the Decision Response View

Use the Decision Response View to increase or decrease the size of the policy decision response from the policy decision point (PDP).

When a client application makes a request for API resources, PingAuthorize Server returns a decision response payload that includes, at minimum, basic information about the server instance, the requested API resources, and the inbound and outbound flow of data. The payload also includes any views added to the Decision Response View. By default, no views are present. PingAuthorize then passes the full response payload to the Policy Decision Logger.

Adding or removing views in the Decision Response View alters the verbosity of the response payload and the size of the **policydecision.log** file.

(i) Note

- If you remove all views, the Policy Decision Logger still logs an abbreviated response. To prevent this abbreviated logging, disable include-pdp-response for the File Based Policy Decision Log Publisher.
- The Decision Response View behavior doesn't significantly change between **embedded** and **external PDP** modes.

You can add the following views to the Decision Response View:

Decision Response View	Description
attributes	Inclludes full details of attributes evaluated during policy decision evaluation.
decision-tree	Includes detailed output tracing the decision's policy evaluation flow.
evaluated-entities	Includes attribute and service resolution details. This is equivalent to specifying both attributes and services .
evaluation-log	Includes attribute and service resolution details. This is similar to specifying evaluated-entities , but the data are expressed in a flat format.
evaluation-log-with-attribute-values	Includes attribute and service resolution details. This is equivalent to specifying evaluation-log but also includes values and types for successful attribute resolutions.
request	Includes the full decision request object.
	▲ Warning Selecting the request view causes the Policy Decision Logger to record potentially sensitive data in API requests and responses.
services	Includes full details of services invoked during policy evaluation.

Use the administrative console or **dsconfig** to configure the Decision Response View.

Admin console

Use the administrative console Steps

- 1. Go to **Configuration > Authorization and Policies** and click **Policy Decision Service**.
- 2. In the **Policy Request Configuration** section, next to **Decision Response View**, select a response view and click the arrow.

Trust Framework Version *	v2	○ C [*] × ×
Decision Response View	Available	Selected
	Search Q	Search Q
	request The policy decision request. May include sensitive data.	No supplementary decision response views are requested.
	decision's policy evaluation flow.	4
	attributes Full details of attributes evaluated	
	Show Descriptions	

dsconfig

Use dsconfig Steps
1. Run dsconfig with the set-policy-decision-service-prop subcommand.
Example:
<pre>PingAuthorize/bin/dsconfig set-policy-decision-service-prop \ no-promptport 5409useSSLtrustAll \ bindDN "cn=directory manager" \ bindPassword secret \ add decision-response-view:request</pre>
In this example, the request view is added to the Decision Response View.

User store configuration

If you want to control data access at the user level, configure PingAuthorize Server to use a user store so you can obtain attributes about the user who is invoking APIs, or the user about whom a service is invoking APIs, to evaluate the attributes as part of policy.

Although PingAuthorize Server assumes that PingDirectory Server is the default user store, other LDAPv3-compliant directories are also supported.

You can configure a user store using the prepare-external-store and create-initial-config commands.

prepare-external-store

When using PingDirectory Server as the user store, first prepare the server by running **prepare-external-store**. This tool completes the following tasks:

- · Creates the PingAuthorize Server user account on your instance of PingDirectory Server
- Sets the correct password
- · Configures the account with the required privileges
- Installs the schema that PingAuthorize Server requires

create-initial-config

The **create-initial-config** command configures connectivity between PingAuthorize Server and the user store. It also creates a System for Cross-domain Identity Management (SCIM) resource type through which PingAuthorize Server obtains the user attributes.

The optional **create-initial-config** command is recommended for first-time installers. If you do not use **create-initial-config**, you can configure the following objects:

- Store adapter
- SCIM resource type
- SCIM schema (optional)

(j) Note

If you do not configure these objects, you do not get the user's profile (the requester's attributes). For more information, see User profile availability in policies.

For more information about configuring SCIM, see About the SCIM service.

Example

For an example, see **Configuring the PingAuthorize user store**.

Configure access token validation

You can configure access token validators to translate an access token for policy processing.

Clients authenticate themselves to HTTP APIs and the System for Cross-domain Identity Management (SCIM) service by using OAuth2 bearer token authentication. PingAuthorize Server uses Access Token Validators to translate and decode a bearer token to a set of attributes that it represents.

For user-authorized bearer tokens, Access Token Validators are required to map the subject of the access token to the user in the user store, to evaluate the user's attributes as part of policy.

For more information about configuring Access Token Validation, see Access token validators.

Configure PingOne to use SSO for the administrative console

The steps below explain how to configure PingOne so that you can use SSO in PingOne to access the PingAuthorize administration console.

Before you begin

You should have already set up the PingAuthorize server that will be administered. This server will host the PingAuthorize administration console that is being configured for SSO.

С Тір

You can use groups to organize user identities as explained in Groups \square . Also, you can set access to applications as explained in Application access control \square .

Steps

- 1. In the PingOne administration console, add a PingAuthorize Server service to one of the existing environments. Alternatively, add a custom environment solely for a PingAuthorize Server service.
 - 1. When prompted, select the It's already been deployed option.
 - 2. Provide https://<hostname>:<port>/console/login as the value for the Admin URL, filling in the bracketed values with the PingAuthorize server's hostname and HTTP port.

) Tip

By binding to the LDAP server, you can use a single console instance to administer multiple PingAuthorize servers. Note that an LDAPS scheme is always assumed because an encrypted connection is always required for SSO.

You can specify the LDAP server to bind to using the query parameters **ldap-hostname** and **ldaps-port** when the administrative console is configured for SSO. Using these parameters, you can specify the URL as follows:

https://<hostname>:<port>/console?ldap-hostname=<my-ldap-host>&ldaps-port=<my-ldapsport>

- 2. Configure the matching administrator accounts for PingOne and the PingAuthorize server. Go to the PingOne dashboard for the environment that will be used with the PingAuthorize server. Repeat the following steps for each PingOne user for which you wish to enable SSO.
 - 1. Locate the desired user under the **Identities** tab. For the example purposes, we will assume the desired PingOne user has the following properties:
 - Given name: Jane
 - Family name: Smith
 - Username: jsmith
 - 2. Run the following **dsconfig** command against the PingAuthorize server, filling in the bracketed field with the previously located PingOne user's **Username** value.

```
dsconfig create-root-dn-user --user-name jsmith \
    --set first-name:Jane \
    --set last-name:Smith
```

- 3. Register the administrative console with PingOne. Follow the instructions for Adding an application \square and select OIDC Web App for Application Type. Configure the application properties as shown in the following list:
 - Application name: PingAuthorize administrative console
 - Description: Application for the PingAuthorize administrative console
 - Redirect URLs: https://<hostname>:<port>/console/oidc/cb
 - Attribute mapping: Username = sub

🕥 Note

Fill in the bracketed values in redirect URLs with the PingAuthorize server's hostname and HTTP port, similar to Step 2.

- 4. Edit the listed properties for the newly created application so that the properties have the values show in the following list, following the instructions in .pingidentity.com/bundle/pingone/page/jez1625773795534.html//[Editing an application OIDC] in the PingOne Administration Guide.
 - Response type: Code
 - Grant type: Authorization code
 - $^{\circ}\,$ Token endpoint authentication method: Client secret basic
- 5. Note the values for the following application properties to use in later steps:
 - Issuer
 - Client ID
 - Client Secret

- 6. Locate the enable-pingone-admin-console-sso.dsconfig file in the PingAuthorize/config/sample-dsconfig-batchfiles/ directory. Make a copy of it, and edit the copy rather than the source file.
- 7. Replace all the bracketed values in the batch file with the corresponding values from step 5. Then run the file using the following command.

```
dsconfig --batch-file \
    enable-pingone-admin-console-sso-copy.dsconfig \
    --no-prompt
```

8. Click the link to the PingAuthorize server from the PingOne solutions home page. A PingOne login page should appear. After you provide credentials, you should see the administrative console index page.

Configuring traffic through a load balancer

Use **dsconfig** or the administrative console to configure PingAuthorize Server to get traffic through a load balancer and to record the actual client's IP address.

To record the actual client's IP address to the trace log, enable X-Forwarded-* handling in both the intermediate HTTP server and the PingAuthorize Server.

By default, when a PingAuthorize Server is sitting behind an intermediate HTTP server, such as a load balancer, a reverse proxy, or a cache, it logs incoming requests as originating with the intermediate HTTP server instead of the client that sent the request.

When you set the use-forwarded-headers property and enable an HTTP connection handler to use Forwarded or X-Forwarded-* headers, many intermediate HTTP servers add information about the original request that would otherwise be lost.

If use-forwarded-headers is set to true, the server uses the client IP address and port information in the Forwarded or X-Forwarded-* headers instead of the address and port of the entity that's sending the request (the load balancer). This client address information shows up in logs, such as in the from field of the HTTP REQUEST and HTTP RESPONSE messages.

γ Note

If both the Forwarded and X-Forwarded-* headers are included in the request, the Forwarded header takes precedence. The X-Forwarded-Prefix header only overrides the context path for HTTP servlet extensions, not for web application extensions.

Dsconfig

Configuring traffic through a load balancer using dsconfig Steps

1. Edit the HTTP or HTTPS connection handler object and set use-forwarded-headers to true by running dsconfig.

Example:

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set use-forwarded-headers:true
```

2. To finalize the changes to the HTTP or HTTPS connection handler, use **dsconfig** to restart the connection handler.

Example:

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set enabled:false
dsconfig set-connection-handler-prop \
```

```
--handler-name "HTTPS Connection Handler" \
--set enabled:true
```

3. To provide the X-Forwarded-* information to your load balancer, consult your provider's guide on configuring load balancer settings.

Administrative console

```
Configuring traffic through a load balancer using the administrative console Steps
```

- 1. On the PingAuthorize administrative console Configuration page, click Connection Handlers.
- 2. To edit your HTTP or HTTPS connection handler, in the **Connection Handlers** list, select the connection handler you want to edit.
- 3. To enable Forwarded headers, go to Use Forwarded Headers and select the Enabled check box.
- 4. Click Save.
- 5. To finalize the changes to the HTTP or HTTPS connection handler, use **dsconfig** to restart the connection handler.

Example:

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set enabled:false
```

```
dsconfig set-connection-handler-prop \
    --handler-name "HTTPS Connection Handler" \
    --set enabled:true
```

i Νote

Because disabling the connection handler brings down the administrative console, you must complete this step in the command line instead of the administrative console.

6. To provide the **X-Forwarded-*** information to your load balancer, consult your provider's guide on configuring load balancer settings.

Configuring logging

Increase the default logging value to include details that will aid in debugging.

Steps

 To enable more detailed logging to understand how policy decisions are being made, including the comparison values and results of the various expressions that comprise a policy decision tree, run the dsconfig set-policy-decision-serviceprop command.

Example:

PingAuthorize/bin/dsconfig set-policy-decision-service-prop \

- --no-prompt --port 8636 --useSSL --trustAll \
- --bindDN "cn=directory manager" $\$
- --bindPassword <your-pingauthorize-password> \
- --add decision-response-view:decision-tree \
- --add decision-response-view:request $\$
- --add decision-response-view:evaluated-entities

Warning

decision-response-view:request causes the Policy Decision Logger to record potentially sensitive data in API requests and responses.

) Note

Policy Decision views affect the decision response payload of the request. You can remove added views by using the --remove decision-response-view:<view_name> argument. Learn more in Configuring the Decision Response View.

• To enable Trace (detailed) logging, including complete HTTP requests and responses, run the **dsconfig set-logpublisher-prop** command.

Example:

```
PingAuthorize/bin/dsconfig set-log-publisher-prop \
    --no-prompt --port 8636 --useSSL --trustAll \
```

```
--bindDN "cn=directory manager" \
```

```
--bindPassword <your-pingauthorize-password> \
```

```
--publisher-name "Debug Trace Logger" \
```

--set enabled:true

(i) Note

Complete HTTP requests and responses might contain sensitive data.

Learn more about enabling detailed debug logging for troubleshooting purposes in Enable detailed logging.

Enable detailed logging

Enable detailed debug logging for troubleshooting.

🕥 Note

This level of logging captures request and response data that contains potentially sensitive information. Do not use this level of logging when working with actual customer data.

Policy Decision Logger

Enabled by default, the Policy Decision Logger records decision responses that are received from the policy decision point (PDP).

Regardless of whether PingAuthorize Server is configured to evaluate a policy in embedded or external mode, a **policy-decision** file logs every policy decision per request. The file is located at **PingAuthorize/logs/policy-decision** and contains the following information:

Policy-decision response

Each client request triggers a policy-decision response that specifies the inbound actions to perform, and another policydecision response that specifies the outbound actions to perform. If you think of a policy-decision response as a set or decision tree of policies, all inbound and outbound requests are read from that set or tree.

Policy rules determine whether a request is denied, permitted, or indeterminate.

Most recent policy decision

To debug the most recent inbound request, open the policy-decision log file and locate the highest **DECISION requestID** in the section near the bottom of the file.

Alternatively, you can use the most recent request timestamp to locate the most recent request.

Policy statements

If the policy contains a statement, it is logged after the policy-decision response JSON. Statements feature the same corresponding requestID as the most recent policy decision.

To increase the level of detail that is returned in PDP decision responses, configure the Policy Decision Service as follows:

dsconfig set-policy-decision-service-prop \

```
--add decision-response-view:decision-tree \
```

--add decision-response-view:request \

```
--add decision-response-view:evaluated-entities \
```

--add decision-response-view:evaluation-log-with-attribute-values

i) Note

Policy Decision views also affect the decision response payload of the request. You can remove added views by using the --remove decision-response-view:<view_name> argument. Learn more in Configuring the Decision Response View.

Configurable attribute logging for embedded mode

When running the Policy Decision Service in embedded mode, you can exercise some control over which attributes get logged as part of the policy-decision response. The **dsconfig set-policy-decision-service-prop** command supports an attribute-logging argument. This argument allows you to log the full details of the specified attributes when they're evaluated as part of the policy-decision request.

Here's an example of how to use the attribute-logging argument for embedded mode:

```
dsconfig set-policy-decision-service-prop \
    --set embedded-mode-logged-attributes:<attribute1> \
    --set embedded-mode-logged-attributes:<attribute2>
```

🕂 Warning

Attributes specified using this argument are logged only if they get evaluated as part of the of policy-decision request. Enabling certain decision response views could override this configuration and cause all evaluated attributes to be included in the response.

Including additional attributes could cause the Trace Log Publisher or the Policy Decision Log Publisher to record sensitive data.

Debug Trace logger

The Debug Trace logger records detailed information about the processing of HTTP requests and responses.

The following example enables the log.

```
dsconfig set-log-publisher-prop \
    --publisher-name "Debug Trace Logger" \
    --set enabled:true
```

By default, the corresponding log file is located at PingAuthorize/logs/debug-trace.

Debug logger

The Debug logger records debugging information that a developer might find useful.

The following example enables the log.

```
dsconfig set-log-publisher-prop \
  --publisher-name "File-Based Debug Logger" \
  --set enabled:true
dsconfig create-debug-target \
  --publisher-name "File-Based Debug Logger" \
  --target-name com.unboundid.directory.broker.http.gateway \
  --set debug-level:verbose
dsconfig create-debug-target \
  --publisher-name "File-Based Debug Logger" \
  --target-name \setminus
  com.unboundid.directory.broker.config.GatewayConfigManager \
  --set debug-level:verbose
dsconfig create-debug-target \
  --publisher-name "File-Based Debug Logger" \
  --target-name \
 com.unboundid.directory.broker.core.policy.PolicyEnforcementPoint \
  --set debug-level:verbose
dsconfig set-log-publisher-prop \
  --publisher-name "File-Based Debug Logger" \
  --set enabled:true
```

By default, the corresponding log file is located at PingAuthorize/logs/debug.

PingAuthorize Server configuration with dsconfig

These examples show how to configure PingAuthorize Server using dsconfig.

The examples cover the following topics.

- · Configuring the PingAuthorize user store
- Configuring the PingAuthorize OAuth subject search
- Configuring logging

Configuring the PingAuthorize user store

Configure PingAuthorize Server to use PingDirectory Server as its user store.

Steps

1. To make a set of changes to PingDirectory Server that PingAuthorize Server needs, including the creation of a service account, run the **prepare-external-store** command.

Example:

{pingauthorize}/bin/prepare-external-store \
 --hostname <your-ds-host> --port 1636 --useSSL --trustAll \
 --governanceTrustStorePath {pingauthorize}/config/truststore \
 --governanceTrustStorePasswordFile \
 {pingauthorize}/config/truststore.pin \
 --bindDN "cn=directory manager" \
 --bindPassword <your-ds-password> \
 --governanceBindDN "cn=Authorize User,cn=Root DNs,cn=config" \
 --governanceBindPassword <your-pingauthorize-service-account-password> \
 --userStoreBaseDN "ou=people,dc=example,dc=com" \
 --no-prompt

2. To configure PingAuthorize Server with a store adapter that allows it to communicate with PingDirectory Server to retrieve identity attributes, run the **create-initial-config** command.

(j) Note

Using **create-initial-config** is optional. However, if you do not use it, you do not get the user's profile (the requester's attributes). For more information, see **User profile availability in policies**.

Example:

```
{pingauthorize}/bin/create-initial-config \
    --no-prompt --port 8636 --useSSL --trustAll \
    --bindDN "cn=directory manager" \
    --bindPassword <your-pingauthorize-password> \
    --governanceBindPassword <your-pingauthorize-service-account-password> \
    --externalServerConnectionSecurity useSSL \
    --governanceTrustStorePath {pingauthorize}/config/truststore \
    --governanceTrustStorePasswordFile \
    {pingauthorize}/config/truststore.pin \
    --userStoreBaseDN "ou=people,dc=example,dc=com" \
    --userStore "<your-ds-host>:1636:Austin" \
    --userObjectClass "inetOrgPerson" \
    --initialSchema pass-through
```

This command also sets up a System for Cross-domain Identity Management (SCIM) resource type that defines a Users type with a SCIM schema that is automatically mapped to an LDAP type, inetOrgPerson, on PingDirectory Server.

Configuring the PingAuthorize OAuth subject search

Configure PingAuthorize Server to search the user store for OAuth token subjects.

Steps

• To configure the PingAuthorize Server to mock OAuth access token validation, run the **dsconfig create-access-token-validator** command.

Example:

```
{pingauthorize}/bin/dsconfig create-access-token-validator \
    --no-prompt --port 8636 --useSSL --trustAll \
    --bindDN "cn=directory manager" \
    --bindPassword <your-pingauthorize-password> \
    --validator-name "Mock Access Token Validator" \
    --type mock --set enabled:true --set subject-claim-name:sub
```

The Mock Access Token Validator accepts tokens without authenticating them and is used only for demonstration and testing purposes. To use an authorization server like PingFederate, see Access token validators.

• To configure PingAuthorize Server to search the user store and retrieve the identity attributes of the OAuth token subject so the attributes can be evaluated in a policy, run the **dsconfig create-token-resource-lookup-method** command.

Example:

```
{pingauthorize}/bin/dsconfig create-token-resource-lookup-method \
    --no-prompt --port 8636 --useSSL --trustAll \
    --bindDN "cn=directory manager" \
    --bindPassword <your-pingauthorize-password> \
    --validator-name "Mock Access Token Validator" \
    --method-name "User by uid" \
    --type 'scim' \
    --set scim-resource-type:Users \
    --set 'match-filter:uid eq "%_subject_claim_name%"' \
    --set evaluation-order-index:100
```

A token resource lookup method defines the expression that is used to search System for Cross-domain Identity Management (SCIM) resources by the access token subject or additional claims. In this example, the value of the access token subject claim is used to search the **uid** attribute value of the SCIM user resource.

Deployment automation and server profiles

Administrators can export the configuration of a PingAuthorize Server instance to a directory of mostly text files, called a server profile. An administrator can then use that server profile to configure another deployment.

Organizations are adopting DevOps practices to reduce risk while providing quicker time-to-value for the services that they provide to their business and customers. Examples of such practices that are central to DevOps include automation and Infrastructure-as-Code (IaC). Organizations that combine these principles can manage the following infrastructure and service operations in the same manner as preparing application code for general release:

- Appropriate versioning
- Continuous integration
- Quality control
- Release cycles

Server profiles enable organizations to adopt these DevOps practices more easily.

Administrators can also track changes to server profile text files in a version-control system, like Git, and can install new instances of PingAuthorize Server, or update existing instances from a server profile.

The scripts and other files in the server-profile directory are declarative of the desired state of the environment. Consequently, the definitions in the server-profile directory directly influence the servers. No one needs to identify a server's current configuration and compute the differences that must be applied to attain the appropriate end state.

The primary goal of a server profile is to simplify the deployment of PingAuthorize Server by using deployment automation frameworks. By using server profiles, the amount of scripting that is required across automation frameworks, such as Docker, Kubernetes, and Ansible, is reduced considerably.

As a declarative form of a full server configuration, a server profile provides the following advantages:

- Provides a more complete and easily comparable method of defining the configuration of an individual server. Changes between different servers are easier to review and understand, and incremental changes to a server's configuration are easier to track.
- Ensures that each server instance is configured identically to its peers.
- Applies to installing new instances as well as to updating the configuration of previously installed instances.
- Shares a common configuration across a deployment environment of development, test, and production without unnecessary duplication and error-prone, environment-specific modifications. For more information about substituting variables that differ by environment, see Variable substitution using manage-profile.
- Reduces the number of additional configuration steps that are required to place a server into production.
- Makes the execution of various configuration changes more consistent and repeatable. The strategy of using a server profile to represent the final state of a server is less error-prone than recording a step-by-step process to attain that state.
- Can be managed easily in a version-control system.
- Simplifies the management of servers outside deployment-automation frameworks.

Variable substitution using manage-profile

You can use the **manage-profile** tool to substitute different variables in server profiles.

The **manage-profile** tool uses the format **\${VARIABLE}** to support the substitution of variables in profiles. To escape this format, use another **\$**. For example, after substitution, **\$\${VARIABLE}** becomes **\${VARIABLE}**.

Variable values can be read from a profile variables file or from environment variable values. If both options are used, the values in the file overwrite any environment variables.

The following lines provide an example of how you can set user-defined variables by using a variables file in the server profile.

HOSTNAME=testserver.example.com PORT=389

The following table describes built-in variables that you can also reference in the server profile. Use these variables in the format previously described.

Built-in variable	Description
PING_SERVER_ROOT	Evaluates to the absolute path of the server's root directory

Built-in variable	Description
PING_PROFILE_ROOT	Evaluates to the individual profile's root directory Note Use PING_PROFILE_ROOT only with files that are not needed after initial setup, such as password files in setup-arguments.txt. Do not use the PING_PROFILE_ROOT variable for files needed while the server is running. The manage-profile tool creates a temporary copy of the server profile that is deleted after the tool completes, so files are not accessible under PING_PROFILE_ROOT when the server is running. For files you need while the server is running, such as keystore and truststore files, copy the files into the server root using the profile's server-root/pre-setup directory, and then refer to the files using with the PING_SERVER_ROOT variable.

For more information about the tool's usage, run the command **bin/manage-profile** --help.

Layout of a server profile

When you create a server profile, you can review the typical server profile hierarchy structure.

Use either of the following methods to create a server profile:

- Extract the template named server-profile-template-paz.zip, which is located in the resource directory.
- Run the **manage-profile generate-profile** subcommand. The **manage-profile** tool references the file system directory structure.

You can add files to each directory as needed.

The following hierarchy represents the file structure of a basic server profile.

```
-server-profile/
  |-- dsconfig/
  |-- misc-files/
  |-- server-root/
  | |-- post-setup/
  | -- pre-setup/
  |-- server-sdk-extensions/
  |-- setup-arguments.txt
  |-- variables-ignore.txt
```

setup-arguments.txt

When you create a new profile, you must add arguments to the setup-arguments.txt file.

When **manage-profile** setup is run, these arguments are passed to the server's setup tool. To view the arguments that are available in this file, run the server's **setup --help** command.

To provide the equivalent, non-interactive CLI arguments after any prompts have been completed, run **setup** interactively. The **s etup-arguments.txt** file in the profile template contains an example set of arguments that you can change.

setup-arguments.txt is the only required file in the profile.

dsconfig/

You can use **dsconfig** batch files to apply **dsconfig** commands to PingAuthorize Server.

You can add **dsconfig** batch files to the **dsconfig** directory. These files, each of which must include a .dsconfig extension, contain **dsconfig** commands to apply to server.

Because the **dsconfig** batch files are ordered lexicographically, **00-base.dsconfig** runs **before 01-second.dsconfig**, and so on.

To produce a dsconfig batch file that reproduces the current configuration, run bin/config-diff.

server-root/

You can add a variety of server root files to the server-root directory.

Any server root files can be added to the server-root directory, including schema files, email template files, custom password dictionaries, and other files that must be present on the final server root. Add these files to the server-root/pre-setup or server-root/post-setup directory, depending on when they need to be copied to the server root. Most server root files are added to the server-root/pre-setup directory.

server-sdk-extensions/

Add server SDK extension .zip files to the server-sdk-extensions directory.

Include any configuration that is necessary for the extensions in the profile's dsconfig batch files.

variables-ignore.txt

You can use the variables-ignore.txt file to indicate the relative paths of any files whose variables you do not want to have substituted.

The variables-ignore.txt file is an optional component of the server profile. It is useful when adding bash scripts to the server root because such files often contain expressions that the manage-profile tool normally interprets as variables.

Add variables-ignore.txt to a profile's root directory to indicate the relative paths of any files that are not to have their variables substituted.

The following example shows the contents of a typical variables-ignore.txt file.

```
server-root/pre-setup/script-to-ignore.sh
server-root/post-setup/another-file-to-ignore.txt
```

server-root/permissions.properties

You can use server-root/permissions.properties to specify permissions you want to apply to files copied to the server root.

The **permissions.properties** file, located in the **server-root** directory, is an optional file that specifies the permissions to apply to files that are copied to the server root. These permissions are represented in octal notation. By default, server root files maintain their permissions when copied.

The following example shows the contents of a typical permissions.properties file.

```
default=700
file-with-special-permissions.txt=600
new-subdirectory/file-with-special-permissions.txt=644
bin/example-script.sh=760
```

misc-files/

You can find additional miscellaneous documentation and other files in the misc-files directory.

The **manage-profile** tool does not use the **misc-files** directory. Use the variable **PING_PROFILE_ROOT** to refer to files in this directory from other locations, such as **setup-arguments.txt**.

(i) Note

Use PING_PROFILE_ROOT only with files that are not needed after initial setup, such as password files in setuparguments.txt. Do not use the PING_PROFILE_ROOT variable for files needed while the server is running. The manage-profile tool creates a temporary copy of the server profile that is deleted after the tool completes, so files are not accessible under PING_PROFILE_ROOT when the server is running. For files you need while the server is running, such as keystore and truststore files, copy the files into the server root using the profile's server-root/presetup directory, and then refer to the files using with the PING_SERVER_ROOT variable.

For example, a password file named password.txt in the misc-files directory could be referenced with \$
{PING_PROFILE_ROOT}/misc-files/password.txt in setup-arguments.txt. Use a reference like this example to supply the file
for the --rootUserPasswordFile argument in setup-arguments.txt.

About the manage-profile tool

The **manage-profile** tool is provided with the server to work with server profiles. It includes subcommands for creating, applying, and replacing server profiles, all of which significantly reduce the effort required by an administrator to configure a server appropriately.

The following sections describe these subcommands in more detail. For more information about the **manage-profile** tool, run **manage-profile** --help. For more information about each individual subcommand and its options, run **manage-profile** <subcommand> --help.

manage-profile generate-profile

To create a server profile from a configured server, use the **generate-profile** subcommand. The generated profile contains the following information, which provides a base for completing a profile:

- · Command-line arguments that were used to set up the server
- dsconfig commands necessary to configure the server
- Installed server SDK extensions
- Files that are added to the server root

To produce a complete profile, some parts of the generated profile might require modifications, such as adding password files that setup-arguments.txt uses. The --instanceName and --localHostName arguments in setup-arguments.txt are made variables by generate-profile, and must be provided values when other manage-profile subcommands use the generated profile.

LDIF files must also be added manually to the generated profile.

The **--excludeSetupArguments** option generates a server profile without a setup-arguments.txt file. This is useful when generating server profiles for use with Docker images.

manage-profile setup

To apply a server profile to a fresh, unconfigured server, use the **setup** subcommand, which replaces the normal setup tool when using a server profile. Run **manage-profile setup** to complete the following tasks:

- · Copies the pre-setup files to the server root
- Runs the setup tool
- · Copies the post-setup files to the server root
- Installs any server SDK extensions
- Runs any dsconfig batch files
- Imports any LDIF files
- Starts the server

While manage-profile setup is running, a copy of the profile is created in a temporary directory that can be specified by using the --tempProfileDirectory argument. The command leaves the server in a complete and running state when finished, unless the --doNotStart argument is specified.

manage-profile replace-profile

Run the **replace-profile** subcommand on a server that was originally set up with a server profile to replace its configuration with a new profile. The tool applies a specified server profile to an existing server while preserving its data, topology configuration, and replication configuration. New LDIF files from the replacement server profile are not imported.

While **manage-profile replace-profile** is running, the existing server is stopped and moved to a temporary directory that the **--tempServerDirectory** argument can specify. A fresh, new server is subsequently installed and set up with the new profile. The final server is left running if it was running before the command was started, and remains stopped if it was stopped.

Run manage-profile replace-profile from a second unzipped server install package on the same host as the existing server, similar to the update tool. Use the --serverRoot argument to specify the root of the existing server that will have its profile replaced.

If files have been added or modified in the server root since the most recent **manage-profile setup** or **manage-profile replace-profile** was run, they are included in the final server with the replaced profile. Otherwise, files specifically added from the server-root directory of the previous server profile are absent from the final server with the replaced profile. If errors occur during the subcommand, such as the new profile having an invalid setup-arguments.txt file, the existing server returns to its original state from before **manage-profile replace-profile** was run.

The --skipValidation option skips the validation step when running on an offline server

🕥 Note

The **manage-profile replace-profile** tool can update the server version when needed. This tool can also directly apply configuration changes when there are no other changes in the new profile. This is a shorter process when making small changes to **dsconfig**.

Common manage-profile workflows

You can use the **manage-profile** tool to complete a variety of workflows in PingAuthorize.

This section describes how to use the **manage-profile** tool to accomplish typical server-management tasks, like the following examples:

- Creating a server profile
- Installing a new environment
- Scaling up your environment
- Rolling out an update

The following sections describe these tasks in more detail. For more information about the **manage-profile** tool, run **manageprofile** --help. For more information about each individual subcommand and its options, run **manage-profile** <**subcommand>** --help.

Creating a server profile

You can create a server profile from a configured server in PingAuthorize Server.

About this task

To create a server profile from a configured server, use the **generate-profile** subcommand.

Steps

1. Create a profile directory.

Example:

\$ mkdir -p /opt/server-profiles/pingauthorize

2. Run generate-profile.

Example:

\$ bin/manage-profile generate-profile --profileRoot /opt/server-profiles/pingauthorize

3. Customize the resulting profile to suit your needs and to remove deployment environment-specific values.

Choose from:

- Specify a consistent location for the license key file:
 - 1. Copy the license key file to the server profile's misc-files directory.

\$ cp {pingauthorize}.lic /opt/server-profiles/pingauthorize/misc-files/

- 2. Open the setup-arguments.txt file in a standard text editor.
- 3. Locate the --licenseKeyFile argument.
- 4. Change the value of --licenseKeyFile to the following value.

🕥 Note

Use PING_PROFILE_ROOT only with files that are not needed after initial setup, such as password files in setup-arguments.txt. Do not use the PING_PROFILE_ROOT variable for files needed while the server is running. The manage-profile tool creates a temporary copy of the server profile that is deleted after the tool completes, so files are not accessible under PING_PROFILE_ROOT when the server is running. For files you need while the server is running, such as keystore and truststore files, copy the files into the server root using the profile's server-root/pre-setup directory, and then refer to the files using with the PING_S ERVER_ROOT variable.

\${PING_PROFILE_ROOT}/misc-files/{pingauthorize}.lic

- 5. Save your changes.
- Remove deployment environment-specific values and replace them with variables. For example, to refer to a different PingFederate server in your development environments versus your test environments, perform the following steps:
 - 1. Open the /opt/server-profiles/pingauthorize/dsconfig/00-config.dsconfig file in a standard text editor.
 - 2. Locate the value specified for **base-url** for the external server that identifies your PingFederate server.
 - 3. Replace the value with a variable, like \${PF_BASE_URL}.
 - 4. Save your changes.
 - 5. Create or update a server profile variables file for your development environment.
 - 6. Add a row like the following example to the variables file.

PF_BASE_URL=https://sso.dev.example.com:9031

- 7. Save your changes.
- 8. Continue replacing deployment environment-specific values with variables until the server profile contains no more deployment environment-specific values.

At this point, you can check the server profile in to a version-control system, like Git, share with your team, and integrate into your deployment automation.

Installing a new environment

You can use **manage-profile** setup to set up a new server instance and deployment environment in PingAuthorize Server.

Before you begin

The steps in this section make the following assumptions:

- A server profile has already been created at the path ~/git/server-profiles/pingauthorize.
- Your development environment's variables file is saved at the path ~/pingauthorize-variables-dev.env.

About this task

After you create and customize a server profile, use the **manage-profile setup** subcommand to set up new server instances and additional deployment environments.

The **setup** subcommand completes the following tasks:

- · Copies the server root files
- Runs the setup tool
- Runs the dsconfig batch files
- Installs the server SDK extensions
- Sets the server's cluster name to a unique value

(i) Note

Cluster-wide configuration is automatically mirrored across all servers in the topology with the same cluster name. In a DevOps deployment with immutable servers, configuration mirroring introduces risk. Therefore, in most cases, cluster names should be unique for each server to avoid configuration mirroring.

Steps

1. Extract the contents of the compressed archive to a directory of your choice.

Example:

```
$ mkdir /opt/pingauthorize
$ cd /opt/pingauthorize
$ unzip {pingauthorize}-<version>.zip
```

2. Change directories.

Example:

```
$ cd {pingauthorize}
```

3. Run setup.

Example:

```
$ bin/manage-profile setup \
    --profile ~/git/server-profiles/pingauthorize \
    --profileVariablesFile ~/pingauthorize-variables-dev.env
```

Scaling up your environment

You can scale up the environment in your PingAuthorize Server instance.

About this task

The automation for this task is identical to the previous task of installing a new server in a new environment. Because each instance of PingAuthorize Server requires a unique instance name and host name, each instance must also be set up from a unique server profile variables file.

Rolling out an update

When you roll out a PingAuthorize Server update, run **manage-profile replace-profile** to use a server profile that you have set up.

Before you begin

The steps in this section make the following assumptions:

- A server profile has been created at the path ~/git/server-profiles/pingauthorize.
- The server's server profile variables file is saved at the path /opt/pingauthorize/pingauthorize-variables.env.
- The existing server with the earlier configuration is installed at /opt/pingauthorize/PingAuthorize.

About this task

Run the **replace-profile** subcommand on a server that was originally set up with a server profile to replace its configuration with a new profile. The **replace-profile** subcommand applies a specified server profile to an existing server while also preserving its configuration.

While **manage-profile replace-profile** is running, the existing server is stopped and moved to a temporary directory that the **--tempServerDirectory** argument specifies. A fresh, new server is subsequently installed and set up with the new profile. If the final server was running before the command was started, it is left running. If the final server was stopped, it remains stopped.

If files have been added or modified in the server root since you ran the most recent **manage-profile setup** or **manage-profile replace-profile** subcommand, they are included in the final server with the replaced profile. Otherwise, files added specifically from the server-root directory of the previous server profile are absent from the final server with the replaced profile.

If errors occur while running the subcommand, such as the new profile having an invalid setup-arguments.txt file, the existing server returns to its original state from before you ran manage-profile replace-profile.

Steps

1. Extract the distribution package for the same or a new version of PingAuthorize Server to a location outside the existing server's installation.

Example:

```
$ mkdir ~/stage
$ cd ~/stage
$ unzip {pingauthorize}-<version>.zip
```

2. Change directories.

You must run the **replace-profile** subcommand from the location of the distribution package, not from the existing server.

Example:

\$ cd {pingauthorize}

3. Run replace-profile.

Example:

```
$ bin/manage-profile replace-profile \
    --serverRoot /opt/pingauthorize/{pingauthorize} \
    --profile ~/git/server-profiles/pingauthorize \
    --profileVariablesFile ~/pingauthorize-variables-dev.env
```

Server profiles in a pets service model

In a pets service model, server profiles and other DevOps concepts can be invaluable for efficiency and consistency in server management, maintenance, and testing.

For example, the step of using the **manage-profile generate-profile** subcommand to generate a server profile from a production server creates an easily consumable representation of the server's configuration. In nearly every scenario, the generation of a profile from an existing server is simpler than the piecing together manually of schemas, extensions, and other configuration information to create an image of that server. Additionally, generated profiles can be backed up or checked in to source control to maintain a consistent picture of an active server's configuration.

Another valuable use of server profiles involves setting up servers in a test environment that is separate from production. For example, a profile that matches the profile of a production server can be generated and used to install a fresh test server that matches the production server. Further, variable substitution allows environmental changes, such as local host name or instance name, without requiring a separate profile. Because the server's original configuration matches the running production server, adjustments can be tested easily. This approach provides more consistency when you validate changes before moving them to production.

If a new pet server has been set up with a server profile, **manage-profile replace-profile** can be used to apply changes to the profile. Rather than using scripts or a manual process to apply individual changes, **replace-profile** provides a consistent, repeatable method of moving to a new server profile. This strategy automates more easily and is less prone to human error.

For more information about the **manage-profile** tool, see About the manage-profile tool.

Server status

You can check server status using the PingAuthorize Server administrative console, the **status** command, or the availability servlet.

Administrative console

You can access status information in the console, in the **Status** tab.

For information about how to access the console, see PingAuthorize administrative console.

status **command**

The PingAuthorize distribution includes the **bin/status** command that you can use to see various information about the server, including its status and the status of its LDAP external servers.

Availability servlet

There are cases in which you might want to obtain basic information about the state of the server over HTTP, or ideally, HTTPS. These might include:

- When server HTTP endpoints are fronted by a load balancer capable of issuing and interpreting the results of HTTP requests for health-checking purposes.
- When using an orchestration framework such as Kubernetes, you can assess the current state of the server to determine if the instance is in a state that is ready to be used or if it has encountered an issue that has caused it to become degraded or unavailable. In this case, you can call the availability servlet in a liveness or readiness probe.

To assist with this, the PingAuthorize server includes an availability state HTTP servlet that you can use to determine whether the server considers itself to be available, degraded, or unavailable. You can access the servlet using the GET, POST, or HEAD methods, and the servlet returns a configurable status code and an optional JSON-encoded response body that you can use to determine the server's self-assessed health state.

The availability state HTTP servlet extension supports two configuration properties for the JSON response body:

- include-response-body : Indicates whether the servlet response should include a JSON object. If enabled, the response will include an availability-state field with a default value of AVAILABLE, DEGRADED, or UNAVAILABLE. This configuration property allows a value of either true or false.
- additional-response-contents: Provides a JSON-formatted string containing additional fields for the servlet to include in its response.

Use **dsconfig** to update the HTTP servlet extension configuration:

```
dsconfig set-http-servlet-extension-prop \
--extension-name {name} \
(--set|--add|--remove) {propertyName}:{propertyValue}
```

There are two instances of this servlet configured by default:

- One that uses a path of /available-state that returns an HTTP status code of 200 (OK) if the server considers itself available or an HTTP status code of 503 (Service Unavailable) if the server considers itself degraded or unavailable
- One that uses a path of /available-or-degraded-state that returns an HTTP status code of 200 if the server considers itself available or degraded or an HTTP status code of 503 if the server considers itself unavailable

The server's assessment of its health state is based on the presence of any unavailable or degraded alert types that are active in the server. If the server currently has one or more unavailable alert types, then it considers itself unavailable. If the server does not have any unavailable alert types but has one or more degraded alert types, then it considers itself degraded. If the server does not have any unavailable or degraded alert types, then it considers itself available.

Server availability

You can monitor the availability of PingAuthorize Server and set up load balancing or auto-healing for it.

Use the following gauges to monitor PingAuthorize Server availability:

- User Store Availability gauge
- Endpoint Average Response Time (Milliseconds) gauge
- HTTP Processing (Percent) gauge
- Policy Decision Service Availability gauge

With monitoring, you can set up load balancing or auto-healing.

For auto-healing, configure your container orchestrator to base a health check on the availability servlet mentioned in Server status. If the availability is not as desired, fail the health check. The orchestrator should then start a replacement server for the unhealthy server.

User Store Availability gauge

The User Store Availability gauge monitors the directory servers that provide user data to PingAuthorize.

If PingAuthorize cannot reach these directory servers, it cannot:

- Retrieve token owner information using a SCIM Token Resource Lookup Method
- Handle SCIM 2 API requests

In this case, this gauge marks the status of PingAuthorize itself as UNAVAILABLE.

The status appears in the following locations:

- The administrative console on the Status tab, in the Operational Status entry.
- The Operational Status line in the bin/status output.
- The Availability servlet. See Server status.

When PingAuthorize has a status of UNAVAILABLE, a load balancer can try to route traffic to a different PingAuthorize server or take some other action. See Auto-healing for unavailable servers.

If you followed the standard setup and configuration given in Getting started with PingAuthorize (tutorials), the User Store Availability gauge should automatically work.

Important

The gauge assumes the PingAuthorize LDAP Store Adapter name is UserStoreAdapter. If your PingAuthorize SCIM configuration uses a different name, you must edit the gauge's data source to reflect the custom store adapter name. Use the following **dsconfig** command to make this change, replacing **<CustomStoreAdapter>** in the last line with the actual name.

```
dsconfig set-gauge-data-source-prop \
    --source-name "User Store Availability" \
    --set "include-filter:(store-adapter-name=<CustomStoreAdapter>)"
```

If your PingAuthorize deployment does not use SCIM or SCIM Token Resource Lookup Methods, you can disable the gauge with the following command.

```
dsconfig set-gauge-prop \
    --gauge-name "User Store Availability" \
    --set enabled:false
```

Endpoint Average Response Time (Milliseconds) gauge

The Endpoint Average Response Time (Milliseconds) gauge monitors the average time that PingAuthorize takes to respond to queries on various endpoints.

The gauge monitors the following types of endpoints:

- · Gateway endpoints
- Sideband endpoints
- System for Cross-domain Identity Management (SCIM) 2 endpoints
- OpenBanking endpoints

The gauge can raise alarms or generate a DEGRADED or UNAVAILABLE status that you can use to configure load balancing or auto-healing.

This gauge does not count the time spent waiting for an upstream server response.

By default, this gauge does nothing. To begin using it, set the levels at which the gauge activates to reasonable values for your environment using **dsconfig**.

The following table explains the values you set for this gauge.

Value	Description
minor-value	This value, in milliseconds, represents a warning condition. An alarm is raised, but the server continues to operate as normal.
major-value	This value, in milliseconds, represents the point at which the server is considered DEGRADED.

Value	Description
critical-value	This value, in milliseconds, represents the point at which the server is considered UNAVAILABLE.

You can find the server's availability state by using an option discussed in Server status.

The following example shows how to activate the gauge.

(i) Note

You might need to experiment to find values that work for your environment.

Example

```
dsconfig set-gauge-prop

--gauge-name "Endpoint Average Response Time (Milliseconds)"

--set minor-value:200

--set major-value:500

--set critical-value:2000
```

HTTP Processing (Percent) gauge

The HTTP Processing (Percent) gauge monitors usage of available HTTP worker threads.

The gauge can raise alarms or generate a DEGRADED or UNAVAILABLE status that you can use to configure load balancing or auto-healing.

By default, this gauge raises an alarm at 70% usage, and it raises an alert at 90% usage. Also by default, the gauge does not mark the server as DEGRADED or UNAVAILABLE.

The following table explains the values and descriptions you set for this gauge.

HTTP processing gauge values and d	escriptions
Value	Description

Value	Description
warning-value	This percentage value represents a warning condition. An alarm is raised, but the server continues to operate as normal. It defaults to 70%.
major-value	This percentage value represents a severe condition. An alarm is raised, and the server enters a DEGRADED state. It is not set by default. To enable the DEGRADED state, you must set server-degraded-severity-level.
critical-value	This percentage value represents a critical condition. An alarm is raised, an alert is generated, and the server is put into an UNAVAILABLE state. It defaults to 90%. To enable the UNAVAILABLE state, you must set server- unavailable-severity-level.

Value	Description
server-degraded-severity-level	The alarm level at which the server enters a DEGRADED state. By default, this gauge does not mark the server as DEGRADED. To enable the DEGRADED state, set to major .
server-unavailable-severity-level	The alarm level at which the server enters an UNAVAILABLE state. By default, this gauge does not mark the server as UNAVAILABLE. To enable the UNAVAILABLE state, set to critical .

You can find the server's availability state by using an option discussed in Server status.

The following example shows how to activate the gauge.

Note
 You might need to experiment to find values that work for your environment.

Example

```
dsconfig set-gauge-prop
  --gauge-name "HTTP Processing (Percent)"
  --set major-value:85
  --set server-degraded-severity-level:major
  --set server-unavailable-severity-level:critical
```

Policy Decision Service Availability gauge

The **Policy Decision Service Availability** gauge monitors the ability of the Policy Decision Service to respond to requests using the configured policies.

If the Policy Decision Service is misconfigured, or the configured deployment package store is not reachable, PingAuthorize can't handle requests for the following services:

- API Security Gateway
- Sideband API
- SCIM 2
- Authorization Policy Decision APIs

In this case, this gauge marks the status of PingAuthorize as DEGRADED.

Possible causes of the Policy Decision Service being unavailable include:

- The pdp-mode is set to disabled
- The trust-framework-version is set to undefined
- The configured deployment package store can't be reached

Auto-healing for unavailable servers

Using gauges, set up auto-healing in a container deployment to address an unavailable server.

Steps

- 1. Configure one or more of the gauges described in Server availability.
- 2. Configure the gauges to trigger the UNAVAILABLE status.

By default, the gauges do not trigger the UNAVAILABLE status.

As discussed in Endpoint Average Response Time (Milliseconds) gauge and HTTP Processing (Percent) gauge, use the **dsconfig** command to adjust the following values for your environment. Each system is different so you might need to adjust the values several times to determine your ideal configuration.

- 1. For the Endpoint Average Response Time (Milliseconds) gauge, set critical-value.
- 2. For the HTTP Processing (Percent) gauge, set both critical-value and server-unavailable-severitylevel.
- 3. Configure the container orchestrator to use the available-or-degraded-state endpoint to detect whether the server is alive.

For information about the endpoint, see paz_server_status.adoc#section_kgv_n53_zkb.

Available gauges

PingAuthorize makes the following gauges available. You can manage these gauges using the administrative console or the **dsconfig** tool.

Gauge name	Enabled by default	Description
Available File Descriptors	true	Monitors the number of file descriptors available to the server process. The server allows for an unlimited number of connections by default but is restricted by the file descriptor limit on the operating system. You can configure the number of file descriptors that the server uses by either setting the NUM_FILE_DESCRIPTORS environment variable or by creating a config/num-file- descriptors file with a single line such as, NUM_FILE_DESCRIPTORS=12345. If you do not use either of these options, the server uses the default of 65535. Running out of available file descriptors can lead to unpredictable behavior and severe system instability.

Gauge name	Enabled by default	Description
Certificate Expiration (Days)	true	Monitors the expiration dates of key server certificates. A server certificate expiring can cause server unavailability, degradation, or loss of key server functionality. Replace certificates nearing the end of their validity as soon as possible. For more information about server certificates and how they are managed, see the status tool or Status in the administrative console.
CPU Usage (Percent)	true	Monitors server CPU use and provides an averaged percentage for the interval defined. The monitored resource is the host system's CPU, which does not include a resource identifier. If CPU use is high, check the server's current workload and other processes on the system and make any needed adjustments. Reducing the load on the system will lead to better response times.
Disk Busy (Percent)	true	Monitors the percentage of disk use time averaged over the specified update interval. This gauge requires that you enable the Host System Monitor Provider and that you register any monitored disks by using the disk-devices property of that configuration object. The resource identifier for this gauge is the disk device name. Use the iostat command or a similar system utility to see a list of disk device names. A separate gauge monitor entry is created for each monitored disk.
Endpoint Average Response Time (Milliseconds)	false	Monitors the average response time across all endpoints since the server was started. This number does not include requests to the upstream server. There is no resource identifier associated with this gauge. The monitored resource is overall response time of all requests to PingAuthorize servlets since the server was started. High response times might be indicative of a number of factors including a disk-bound server, network latency, or misconfiguration. Enabling the Stats Logger plugin can help isolate problems. For more information, see Endpoint Average Response Time (Milliseconds) gauge.
HTTP Processing (Percent)	true	Monitors the percentage of time that request handler threads spend processing HTTP requests. This percentage represents the inverse of the server's ability to handle new requests without queueing. For more information, see HTTP Processing (Percent) gauge.

Gauge name	Enabled by default	Description
JVM Memory Usage (Percent)	true	Monitors the percentage of Java Virtual Machine memory that is in use. This value naturally fluctuates due to garbage collection, so the minimum value within an interval is reported because it is a better indication of overall memory growth. When the memory usage exceeds 90%, open a case with Ping Identity Support ^[] because the server is either misconfigured or has a memory leak. As memory usage approaches 100%, the server is more and more likely to experience garbage collection pauses, which leave the server unresponsive for a long time. Restarting the server is likely the only remedy for this situation. Before you restart the server, run collect-support-data and capture the output of jmap -histo <server-pid> to provide to customer support. The PID of the server is in <server-root>/logs/server.pid.</server-root></server-pid>
License Expiration (Days)	true	Monitors the expiration date of the product license. An expired license causes warnings to appear in the server's logs and in the status tool output. Request a license key through the Ping Identity licensing website https://www.pingidentity.com/en/account/request-license-key.html \Box or contact sales@pingidentity.com. Use the dsconfig tool to update the License configuration's license key property.
Memory Usage (Percent)	false	Monitors the percentage of memory use averaged over the update interval defined. The monitored resource is the host system's memory use, which does not have a resource identifier. Some operating systems, including Linux, use the majority of memory for file system cache, which is freed as applications need it. If memory use is high, check the applications that are running on the server.
Policy Decision Service Availability	true	Monitors availability of the Policy Decision Service. If the Policy Decision Service is misconfigured or cannot reach the deployment package store, PingAuthorize services will be unavailable. Ensure that the pdp-mode and trust-framework-version are correctly set, and that the deployment package store is reachable. For more information, see Policy Decision Service Availability gauge.

Gauge name	Enabled by default	Description
Strong Encryption Not Available	true	Indicates the JVM does not appear to support strong encryption algorithms, like 256-bit AES. The server will fall back to using weaker algorithms, like 128-bit AES. To enable support for strong encryption, update your JVM to a newer version that supports it by default; alternatively, install or enable the unlimited encryption strength jurisdiction policy files in your Java installation.
User Store Availability	true	Monitors availability of the SCIM user store. If the LDAP directory servers are unavailable, the "UserStoreAdapter" cannot forward requests. Also, the server cannot process SCIM requests or perform token owner lookups. Ensure that LDAP directory servers are available. For more information, see User Store Availability gauge.

Common server alarms

The server uses alarms and alerts to notify administrators of situations that might require intervention.

Policy Decision Service unavailable

PingAuthorize Server raises this alarm if it cannot process policy decisions because the Policy Decision Service requires further configuration. When this alarm is present, PingAuthorize Server cannot handle requests for the following services:

- API Security Gateway
- Sideband API
- SCIM 2
- Authorization Policy Decision APIs

The alarm message typically indicates the cause for the Policy Decision Service's UNAVAILABLE state. The administrator should check the Policy Decision Service configuration's **pdp-mode** and **trust-framework-version** properties to ensure that they are set correctly and that configured deployment package stores are reachable.

Trust framework update needed

The server raises this alarm if the Policy Decision Service is configured with a deprecated **trust-framework-version** value. When this alarm is present, PingAuthorize does continue to accept requests. However, the administrator is strongly encouraged to take the following actions:

- 1. Update policies to use a new Trust Framework version. See Upgrading the Trust Framework and policies.
- 2. Export a new deployment package (if using embedded PDP mode).

3. Load the updated policies and set trust-framework-version in the Policy Decision Service to the current version.

The following example uses dsconfig to set trust-framework-version to v2.

```
dsconfig set-policy-decision-service-prop \
    --set trust-framework-version:v2
```

LDAP External Server Health Reclassified from AVAILABLE to UNAVAILABLE

The server raises this alarm if an LDAP health check determines that an LDAP external server used by the SCIM subsystem is unavailable. This can occur for a number of reasons; the most typical cause is a network or SSL connectivity problem.

External server initialization failed

You see this alarm at server startup if an LDAP health check determines that an LDAP external server used by the SCIM subsystem is unavailable. This can occur for a number of reasons; the most typical cause is a network or SSL connectivity problem.

User Store Availability

The server raises this alarm if the SCIM subsystem's UserStoreAdapter is unavailable. When this alarm is present, PingAuthorize Server cannot process SCIM API requests or SCIM token resource lookup method operations. This alarm generally occurs if the underlying data stores are unavailable. To resolve this alarm, determine why the data stores are unavailable and resolve the problem.

If your PingAuthorize deployment does not require SCIM, you can disable this alarm by disabling the User Store Availability gauge using the following command.

```
dsconfig set-gauge-prop \
    --gauge-name "User Store Availability" \
    --set enabled:false
```

No Enabled Alert Handlers

By default, an administrator can check for server alerts through the error log, the **status** tool, and the administrative console. This alarm warns the administrator that they should also configure an alert handler to ensure that the server can actively notify them of current or impending problems. The server provides alert handlers for this purpose. The handlers can deliver alerts by email or through a monitoring application using JMX or SNMP.

The following example shows how to configure an alert handler to send alert emails through the SMTP server <*smtp.example.com*>.

```
dsconfig create-external-server \
    --server-name "SMTP Server" \
    --type smtp \
    --set server-host-name:<smtp.example.com>
dsconfig set-global-configuration-prop \
    --add "smtp-server:SMTP Server"
dsconfig create-alert-handler \
    --handler-name "SMTP Alert Handler" \
    --type smtp \
    --set enabled:true \
    --set 'sender-address:joey@example.com' \
    --set 'recipient-address:deedee@example.com' \
```

If you are running a nonproduction environment, you can disable this alarm by running the following dsconfig command.

```
dsconfig set-alarm-manager-prop \
    --set suppressed-alarm:no-enabled-alert-handlers
```

Insecure access token validator enabled

This alarm warns the administrator that a mock access token validator is enabled. Mock access token validators can be very useful in test environments because they allow PingAuthorize Server to accept HTTP API requests without the overhead of setting up an OAuth 2 authorization server. However, because they do not actually authenticate access tokens, they are insecure and should never be used in a production environment.

The following example shows how to disable an access token validator called "Mock Token Validator."

```
dsconfig set-access-token-validator-prop \
    --validator-name "Mock Token Validator" \
    --set enabled: false
```

Sensitive data may be logged

This alarm warns the administrator that a trace log publisher has been configured to record debug messages. Debug log messages are not guaranteed to exclude potentially sensitive data, so their use is strongly discouraged in a production environment. You should not use them with anything but test data.

To disable a trace log publisher called "Debug Trace Logger," run this command.

```
dsconfig set-log-publisher-prop \
    --publisher-name "Debug Trace Logger" \
    --set enabled:false
```

Managing monitoring

PingAuthorize provides several monitoring options.

The following sections describe the options.

- Profiling server performance using the Stats Logger
- Logging HTTP performance statistics using the Periodic Stats Logger
- StatsD monitoring endpoint
- Sending StatsD metrics to Splunk

Profiling server performance using the Stats Logger

PingAuthorize provides a Stats Logger plugin you can use to profile server performance for a given configuration.

At a specified interval, the Stats Logger can write server statistics to a JSON file or to a log file in a comma-separated value (.csv) format.

The logger has a negligible impact on server performance unless the **log-interval** property is set to a very small value (less than 1 second). You can customize the statistics logged and their verbosity.

You can also use the Stats Logger to view historical information about server statistics including LDAP operations, host information, and gauges. Your options include:

- Update the configuration of the existing Stats Logger Plugin to set the advanced gauge-info property to basic/extended to include this information.
- Create a dedicated Periodic Stats Logger for information about statistics of interest.

Enabling the Stats Logger

By default, the Stats Logger plugin is disabled. Enable it using the **dsconfig** tool (and its Advanced Objects menu and Plugin option) or the administrative console (and its Advanced Configuration menu and Plugin Root option).

About this task

The steps below show how to use **dsconfig** to enable the plugin.

Steps

1. Run dsconfig in interactive mode. Enter the LDAP or LDAPS connection parameters when prompted.

Example:

\$ bin/dsconfig

- 2. Enter o to change to the Advanced Objects menu.
- 3. On the main menu, enter the number for the Plugin menu.

- 4. On the Plugin menu, enter the number corresponding to view and edit an existing plugin.
- 5. On the Plugin selection list, enter the number corresponding to the Stats Logger.
- 6. On the Stats Logger Plugin menu, enter the number to set the enabled property to TRUE.

If the server is idle, nothing is logged. You can log data even when idle by setting the suppress-if-idle property to FALS E (suppress-if-idle=false).

i Note

On this menu, you can also change the format from csv to json.

7. When done changing properties, enter **f** to save and apply the configuration.

The default logger logs information about the server every second to <server-root>/logs/dsstats.csv . You can open the file in a spreadsheet.

Configuring multiple Periodic Stats Loggers

Create multiple, Periodic Stats Loggers to log different statistics or to view historical information about gauges. Also, you might create multiple loggers to create a log at different intervals (such as logging cumulative operations statistics every hour). To create a new log, use the existing Stats Logger as a template to get reasonable settings, including rotation and retention policy.

Steps

1. Run dsconfig in interactive mode. Enter the LDAP or LDAPS connection parameters when prompted.

Example:

\$ bin/dsconfig

- 2. Enter o to change to the Advanced Objects menu.
- 3. On the main menu, enter the number for the Plugin menu.
- 4. From the Plugin management menu, enter the number to create a new plugin.
- 5. Enter t to use an existing plugin as a template.
- 6. Enter the number corresponding to the existing stats logger as a template.
- 7. Enter a descriptive name for the new stats logger.
- 8. Enter the log file path to the file.

For example, type logs/dsstats2.csv.

9. On the menu, make any desired changes to the properties for the logger.

For information about the included-http-servlet-stat property, see Logging HTTP performance statistics using the Periodic Stats Logger.

i) Note

On this menu, you can also change the format from \mbox{csv} to \mbox{json} .

10. Enter **f** to save and apply the configuration.

Logging HTTP performance statistics using the Periodic Stats Logger

To log HTTP performance statistics, set the Periodic Stats Logger property included-http-servlet-stat.

About this task

You can log HTTP performance statistics for any combination of the following servlet extensions:

- gateway
- scim2
- sideband-api

The provided statistics come in pairs:

- One statistic represents the average latency introduced by PingAuthorize during the current log interval in microseconds. The calculation is total time to respond to a request less the time spent waiting for the upstream server.
- The other statistic represents the number of requests made during the current log interval.

These throughput and latency pairs exist for every service, action combination for the **scim2** and **sideband-api** servlet extensions and for every service, HTTP method combination for the **gateway** servlet extension.

To log these statistics:

Steps

1. Enable the Periodic Stats Logger.

For more information, see Enabling the Stats Logger.

2. Set the included-http-servlet-stat property.

For more information, see Configuring multiple Periodic Stats Loggers.

StatsD monitoring endpoint

The Monitoring Endpoint configuration type provides the StatsD Endpoint type that you can use to transfer metrics data in the StatsD format.

Examples of metrics you can send are:

- Busy worker thread count
- Garbage collection statistics
- Host system metrics such as CPU and memory

For a list of available metrics, use the interactive **dsconfig** menu for the Stats Collector plugin, or in the administrative console, edit the Stats Collector plugin as explained in the second example.

You configure the monitoring endpoint using the **dsconfig** command. When you configure the monitoring endpoint, you include:

- The endpoint's hostname
- The endpoint's port
- A toggle to use TCP or UDP
- A toggle to use SSL if you use TCP

The following example shows how to configure a new StatsD monitoring endpoint to send UDP data to localhost port 8125 using dsconfig.

```
dsconfig create-monitoring-endpoint \
    --type statsd \
    --endpoint-name StatsDEndpoint \
    --set enabled:true \
    --set hostname:localhost \
    --set server-port:8125 \
    --set connection-type:unencrypted-udp
```

If you are using the administrative console, perform the following steps.

1. Click Show Advanced Configuration.

2. In the Logging, Monitoring, and Notifications section, click Monitoring Endpoints.

3. Click New Monitoring Endpoint.

You can send data to any number of monitoring endpoints.

The Stats Collector plugin controls the metrics used by the StatsD monitoring endpoint. To send metrics with the StatsD monitoring endpoint, you must enable the Stats Collector plugin. Also, you must configure the Stats Collector plugin to indicate the metrics to send.

To enable the Stats Collector plugin or to configure the type of data sent, use the **dsconfig** command or the administrative console. This example shows how to enable the Stats Collector plugin to send host CPU metric, memory metrics, and server status metrics using **dsconfig**.

```
dsconfig set-plugin-prop \
    --plugin-name "Stats Collector" \
    --set enabled:true \
    --set host-info:cpu \
    --set host-info:disk \
    --set status-summary-info:basic
```

If you are not using Data Metrics Server to monitor your server, you can disable the generation of some metrics files that are not necessary for the StatsD Monitoring Endpoint. To do this, set the generate-collector-files property on the Stats Collector Plugin to false.

If you are using the administrative console, perform the following steps.

- 1. Click Show Advanced Configuration.
- 2. In the LDAP (Administration and Monitoring) section, click Plugin Root
- 3. Edit the Stats Collector plugin.

After you enable the Stats Collector and create the StatsD monitoring endpoint, you can:

- Use the data with Splunk as explained in Sending StatsD metrics to Splunk.
- Configure other tools that support StatsD, such as CloudWatch or a Prometheus StatsD exporter, to use the data. For more information about this configuration, see your tool's StatsD documentation. Configure the PingAuthorize StatsD monitoring endpoint to use the correct host and port. The dsconfig create-monitoring-endpoint example above uses a host of localhost and a port of 8125. You can also set these values in the administrative console.

Sending StatsD metrics to Splunk

Use a Splunk Universal Forwarder to securely send UDP (or TCP) data to Splunk.

About this task

With the StatsD Endpoint type, you can send metric data to a Splunk installation. In Splunk, you can use SSL to secure ports that are open for StatsD.

(i) Note

StatsD metrics are typically sent over UDP. By using UDP, the client sending metrics does not have to block as it would if using TCP. However, using TCP guarantees order and ensures no metrics are lost.

You can configure open UDP (or TCP) ports in Splunk to accept only connections from a certain hostname or IP address.

Steps

- 1. Send the data to a Splunk Universal Forwarder.
- 2. Have the forwarder communicate with the Splunk Indexer over SSL.

Managing HTTP correlation IDs

An HTTP correlation ID is a unique ID that you can use to track requests as they make their way through the system.

The following sections explain how to configure and use these IDs.

About HTTP correlation IDs

HTTP correlation IDs let you trace requests.

A typical request to a software system is handled by multiple subsystems, which might be distinct servers on distinct hosts across different locations. Tracing the request flow on such distributed systems can be challenging because log messages are scattered across various systems and intermingled with messages for other requests.

To solve this problem, a system can assign a correlation ID to a request that it adds to every associated operation as the request flows through the larger system. With the correlation ID, you can easily locate and group related log messages.

PingAuthorize, PingDirectory, and their related products support correlation IDs for all HTTP requests received through the HTTP(S) Connection Handler. Learn more in Configuring HTTP connection handlers \square in the PingDirectory documentation.

How PingAuthorize handles correlation IDs

- When any HTTP request is received, PingAuthorize automatically assigns the request a correlation ID.
- All related activity appears in the trace logs with this correlation ID.
- The PingAuthorize gateway adds the correlation ID header to requests it forwards.
- The LDAP Store Adapter used by the SCIM 2 service uses the correlation ID as the client request ID value in Intermediate Client Request Controls that it sends to the downstream Ping LDAP server.

You can find this value in the via key of records logged by the LDAP server's access log.

If the LDAP server is a PingDirectoryProxy Server, the Intermediate Client Request Control is forwarded in turn to the downstream LDAP server.

How other Ping products handle correlation IDs

- When any HTTP request is received, it is automatically assigned a correlation ID.
- You can use this correlation ID to correlate HTTP responses with messages recorded to the HTTP Detailed Operation log and the trace log.
- For specific web APIs, the correlation ID might also be passed to the LDAP subsystem.
- For the SCIM 1, SCIM 2, Delegated Admin, Consent, and Directory REST APIs, the correlation ID appears with associated requests in LDAP logs in the correlationID key.

Server SDK support

For Server SDK extensions that have access to the current HttpServletRequest, the extension can retrieve the current correlation ID as a String through the HttpServletRequest's com.pingidentity.pingdata.correlation_id attribute.

Consider this example.

(String) request.getAttribute("com.pingidentity.pingdata.correlation_id");

Enabling or disabling correlation ID support

Correlation ID support is enabled by default for each HTTP connection handler, but you can optionally disable it.

Steps

• To disable correlation ID support for the HTTPS connection handler, run the following command.

dsconfig set-connection-handler-prop --handler-name "HTTPS Connection Handler" --set usecorrelation-id-header:false

• To enable correlation ID support for the HTTPS connection handler, run the following command.

```
dsconfig set-connection-handler-prop --handler-name "HTTPS Connection Handler" --set use-
correlation-id-header:true
```

Configuring the correlation ID response header

You can optionally change the correlation ID response header that PingAuthorize Server sends with HTTP requests.

About this task

By default, PingAuthorize Server generates a correlation ID for every HTTP request and response header.

To customize this response header name:

Steps

• By default, PingAuthorize Server generates a correlation ID for every HTTP request and sends it in the response with the **dsconfig** command.

Example:

The following example changes the correlation ID response header to X-Request-Id.

```
dsconfig set-connection-handler-prop --handler-name "HTTPS Connection Handler" --set correlation-id-
response-header:X-Request-Id
```

How the server manages correlation IDs

By default, the server looks for a correlation ID header on the request and uses the value if found. This behavior integrates the server into a larger system of other servers using correlation IDs.

If a correlation ID header is not found, the server generates a new, unique correlation ID for each HTTP request.

The connection handler uses the **correlation-id-request-header** property to determine which request headers are correlation ID headers, as shown in the following configuration. The actual default configuration might differ.

```
dsconfig set-connection-handler-prop --handler-name "HTTPS Connection Handler" \
    --set correlation-id-request-header:X-Request-Id \
    --set correlation-id-request-header:X-Correlation-Id \
    --set correlation-id-request-header:Correlation-Id \
    --set correlation-id-request-header:X-Amzn-Trace-Id
```

If a request contains more than one of the previous correlation ID headers, the server checks the configured header names in order, and then uses the first one found.

Example: HTTP correlation ID

This example shows a SCIM 2 request with a correlation ID assigned in the response. Then the example uses that ID to locate entries in the debug trace log and the policy decision log.

First, make a SCIM 2 GET request.

The response includes a **Correlation-Id** header with the value **c52af735-788d-4798-be3b-8d1f3c8f9d64**. The ellipsis (...) in the response indicates lines removed to keep the example brief. Because the request does not include a correlation ID, the server generates the header and value.

```
GET https://localhost:8443/scim/v2/Me HTTP/1.1
Accept: /
Accept-Encoding: gzip, deflate
Authorization: Bearer ...
Connection: keep-alive
Host: localhost:1443
User-Agent: HTTPie/0.9.9
HTTP/1.1 200 OK
Content-Length: 903
Content-Type: application/scim+json
Correlation-Id: c52af735-788d-4798-be3b-8d1f3c8f9d64
Date: Mon, 15 Mar 2021 15:23:06 GMT
Request-Id: 371
{
    "mail": [
       "user.0@example.com"
    ],
    "initials": [
        "AOR"
    ],
    "homePhone": [
        "+1 295 940 2750"
    ],
    "pager": [
        "+1 604 109 3407"
    ],
    "givenName": [
       "Anett"
    ],
   . . .
}
```

Use the correlation ID to search the HTTP debug trace log for matching log records.

\$ grep 'correlationID="c52af735-788d-4798-be3b-8d1f3c8f9d64"' {pingauthorize}/logs/debug-trace

Also, use the correlation ID to search the policy decision log for matching log records.

\$ grep 'correlationID="c52af735-788d-4798-be3b-8d1f3c8f9d64"' {pingauthorize}/logs/policy-decision

Command-line tools

PingAuthorize Server provides a full suite of command-line tools to administer the server. You can run these tools in interactive, noninteractive, or script mode.

(i) Note

Most of these tools are in the **bin** directory for Linux systems and the **bat** directory for Microsoft Windows systems; however, some of the tools are in the root directory of the distribution.

Tools help

For	Use this option	Example
Information about arguments and subcommands Usage examples	help	dsconfighelp
A list of subcommands	help-subcommands	dsconfighelp-subcommands
More information about a subcommand	help with the subcommand	dsconfig list-log-publishers help

For more information and examples, see the PingAuthorize Command-Line Tool Reference at docs/cli/index.html.

Command-line tools

Tool	Description
backup	Run full or incremental backups on one or more PingAuthorize Server backends. This tools supports the use of a properties file to pass command-line arguments. See Saving command options in a file.
base64	Encode raw data using the base64 algorithm or decode base64-encoded data back to its raw representation.
collect-support-data	Collect and package system information useful in troubleshooting problems. The information is packaged as a zip archive that you can send to a technical support representative.

Tool	Description
config-diff	Compares PingAuthorize Server configurations and produces a dsconfig batch file needed to bring the source inline with the target.
create-initial-config	Create an initial PingAuthorize Server configuration.
create-rc-script	Create a Run Control (RC) script to start, stop, and restart the PingAuthorize Server on UNIX- based systems.
create-systemd-script	Create a systemd script to start and stop the PingAuthorize Server on Linux-based systems.
docker-pre-start-config	Run this tool before starting PingAuthorize Server to make configuration changes to the server that depend on the running container's environment.
dsconfig	View and edit the PingAuthorize Server configuration.
dsjavaproperties	Configure the JVM options used to run PingAuthorize Server and its associated tools. Before launching the command, edit the properties file located in config/java.properties to specify the desired JVM options and JAVA_HOME environment variable.
encrypt-file	Encrypt or decrypt data using a key generated from a user-supplied passphrase, a key generated from an encryption settings definition, or a key shared among servers in the topology. The data to be processed can be read from a file or standard input, and the resulting data can be written to a file or standard output. You can use this command to encrypt and subsequently decrypt arbitrary data, or to decrypt encrypted backups, LDIF exports, and log files generated by the server.
encryption-settings	Manage the server encryption settings database.
ldap-diff	Compare the contents of two LDAP servers.
ldap-result-code	Display and query LDAP result codes.
ldapcompare	Perform compare operations in an LDAP directory server. Compare operations can be used to efficiently determine whether a specified entry has a given value.
ldapdelete	Delete one or more entries from an LDAP directory server. You can provide the DNs of the entries to delete using named arguments, as trailing arguments, from a file, or from standard input. Alternatively, you can identify entries to delete using a search base DN and filter.
ldapmodify	Apply a set of add, delete, modify, and/or modify DN operations to a directory server. Supply the changes to apply in LDIF format, either from standard input or from a file specified with the ldifFile argument. Change records must be separated by at least one blank line.
ldappasswordmodify	Update the password for a user in an LDAP directory server using the password modify extended operation (as defined in RFC 3062), a standard LDAP modify operation, or an Active Directory-specific modification.
ldapsearch	Process one or more searches in an LDAP directory server.

Tool	Description
ldif-diff	Compare the contents of two files containing LDIF entries. The output will be an LDIF file containing the add, delete, and modify change records needed to convert the data in the source LDIF file into the data in the target LDIF file.
ldifmodify	Apply a set of changes (including add, delete, modify, and modify DN operations) to a set of entries contained in an LDIF file. The changes will be read from a second file (containing change records rather than entries), and the updated entries will be written to a third LDIF file. Unlike ldapmodify , ldifmodify cannot read the changes to apply from standard input.
ldifsearch	Search one or more LDIF files to identify entries matching a given set of criteria.
list-backends	List the backends and base DNs configured in PingAuthorize Server.
make-ldif	Generate LDIF data based on a definition in a template file. See the server's config/MakeLDIF directory for example template files. In particular, the examples-of-all-tags.template file shows how to use all of the tags for generating values.
manage-certificates	Manage certificates and private keys in a JKS, PKCS #12, PKCS #11, or BCFKS key store.
manage-extension	Install or update PingAuthorize Server extension bundles.
manage-profile	Generate, compare, install, and replace server profiles.
manage-tasks	Access information about pending, running, and completed tasks scheduled in the PingAuthorize Server.
manage-topology	Tool to manage the topology registry.
prepare-external-store	Prepare a PingAuthorize Server and an external server for communication.
reload-http-connection- handler-certificates	Reload HTTPS Connection Handler certificates.
remove-backup	Safely remove a backup and optionally all of its dependent backups from the specified PingAuthorize Server backend.
remove-defunct-server	Remove a server from this server's topology.
replace-certificate	Replace the listener certificate for this PingAuthorize Server server instance.
restore	Restore a backup of a PingAuthorize Server backend.
revert-update	Revert this server package's most recent update.
review-license	Review and/or indicate your acceptance of the license agreement defined in <pre>legal/LICENSE.txt</pre>
rotate-log	Trigger the rotation of one or more log files.

Tool	Description
sanitize-log	Sanitize the contents of a server log file to remove potentially sensitive information while still attempting to retain enough information to make it useful for diagnosing problems or understanding load patterns. The sanitization process operates on fields that consist of name-value pairs. The field name is always preserved, but field values might be tokenized or redacted if they might include sensitive information. Supported log file types include the file-based access, error, sync, and resync logs, as well as the operation timing access log and the detailed HTTP operation log.
schedule-exec-task	Schedule an exec task to run a specified command in the server. To run an exec task, a number of conditions must be satisfied: the server's global configuration must have been updated to include com.unboundid.directory.server.tasks.ExecTask in the set of allowed-task values, the requester must have the exec-task privilege, and the command to execute must be listed in the exec-command-whitelist.txt file in the server's config directory. The absolute path (on the server system) of the command to execute must be specified as the first unnamed trailing argument to this program, and the arguments to provide to that command (if any) should be specified as the remaining trailing arguments. The server root is used as the command's working directory, so any arguments that represent relative paths are interpreted as relative to that directory.
search-logs	Search across log files to extract lines matching the provided patterns, like the grep command-line tool. The benefits of using this tool over grep are its ability to handle multi-line log messages, extract log messages within a given time range, and the inclusion of rotated log files.
server-state	View information about the current state of the PingAuthorize Server process.
setup	Perform the initial setup for a server instance.
start-server	Start the PingAuthorize Server.
status	Display basic server information.
stop-server	Stop or restart the server.
sum-file-sizes	Calculate the sum of the sizes for a set of files.
uninstall	Uninstall PingAuthorize Server.
update	Update a deployed server so its version matches the version of this package.
validate-file-signature	Validate file signatures. For best results, file signatures should be validated by the same instance used to generate the file. However, it might be possible to validate signatures generated on other instances in a replicated topology.

Saving command options in a file

PingAuthorize Server supports the use of a tools properties file (config/tools.properties by default) to simplify command-line invocations by reading in a set of options for each tool from a text file.

Properties files are convenient when quickly testing PingAuthorize Server in multiple environments.

Each property takes the form of a name-value pair that defines predetermined values for a tool's options.

PingAuthorize Server supports the following types of properties:

- · Default properties that apply to all command-line tools
- Tool-specific properties

Creating a tools properties file

You can set properties that apply to all tools or are tool-specific. These properties serve as defaults for the command-line options they represent.

Steps

1. Use a text editor to open the default tools properties file (config/tools.properties) or a different properties file.


(i) Note

If you use a file other than **config/tools.properties**, invoke the tool with the **--propertiesFilePath** option to specify the path to your properties file.

2. Set or change properties that apply to all tools.

Use the standard Java properties file format (name=value) to set properties. For example, the following properties define a set of LDAP connection parameters.

```
hostname=server1.example.com
port=1389
bindDN=cn=Directory\ Manager
bindPassword=secret
baseDN=dc=example,dc=com
```



3. Set or change properties that apply to specific tools.

Tool-specific properties start with the name of the tool followed by a period. These properties take precedence over properties that apply to all tools. The following example sets two ports: one that applies to all tools (port=1389) and a tool-specific one that ldapsearch uses instead (ldapsearch.port=2389).

hostname=server1.example.com
port=1389
ldapsearch.port=2389
bindDN=cn=Directory\ Manager

4. Save your changes and close the file.

Evaluation priority of command-line options

You can specify options for a command-line tool on the command line, in a properties file, or both.

Options you specify on a tool's command line take priority over options in a properties file.

Consider the following scenarios.

Command-line options	PingAuthorize Server uses
No command-line options	The options in the default <server-root>/config/ tools.properties file</server-root>
Command-line options other than the propertiesFilePath <my-properties-file> option</my-properties-file>	The command-line options, which take priority if the options are also in the <server-root>/config/tools.properties file The file options for options that are only in the default <server-root>/config/tools.properties file</server-root></server-root>
Only thepropertiesFilePath <my-properties-file> option</my-properties-file>	The options in <my-properties-file></my-properties-file>
ThepropertiesFilePath <my-properties-file> option and other command-line options</my-properties-file>	The command-line options, which take priority if the options are also in <my-properties-file> The file options for options that are only in <my-properties- file></my-properties- </my-properties-file>

Example

Consider this example properties file that is saved as server-root>/bin/tools.properties:

hostname=server1.example.com
port=1389
bindDN=cn=Directory\ Manager
bindPassword=secret

PingAuthorize Server checks command-line options and file options to determine the options to use, as explained below.

• All options presented with the tool on the command line take precedence over any options in a properties file.

In the following example, the command runs with the options specified on the command line (--port and --baseDN). With the port value both on the command line and in the properties file, the command-line value takes priority. The command uses the bindDN and bindPassword values specified in the properties file.

```
$ bin/ldapsearch --port 2389 --baseDN ou=People,dc=example,dc=com \
    --propertiesFilePath bin/tools.properties "(objectclass=*)"
```

• If you specify the properties file using the --propertiesFilePath option and no other command-line options, PingAuthorize Server uses only the options in the specified properties file:

```
$ bin/ldapsearch --propertiesFilePath bin/tools.properties \
    "(objectclass=*)"
```

• If do not specify any command-line options, PingAuthorize Server attempts to locate the default properties file in the following location:

<server-root>/config/tools.properties

By moving your tools.properties file from <server-root>/bin to <server-root>/config, you do not have to specify the --propertiesFilePath option. That change shortens the previous command to the following command.

\$ bin/ldapsearch "(objectclass=*)"

Sample dsconfig batch files

PingAuthorize provides sample **dsconfig** batch files that you can use to easily make a number of common or recommended changes to the server configuration.

The config/sample-dsconfig-batch-files directory contains dsconfig batch files that you can use to configure various aspects of the server. For example, these files can enable additional security capabilities or take advantage of features that might require customization from one environment to another.

Each file includes comments that describe the purpose and benefit of its configuration change. You can choose which of the changes you want to apply.

You need to customize some of the batch files to provide values that might vary from one environment to another. To apply a batch file that requires changes, copy it to another directory and edit the copy. Leave the files in the config/sample-dsconfig-batch-files directory unchanged so that they can be updated when you upgrade the server. To specify the path to the file that contains the changes to apply, use the dsconfig tool (bin/dsconfig on UNIX-based systems or bat\dsconfig.bat on Windows) with the --batch-file argument.

You should also provide the arguments needed to connect and authenticate to the server. The **--no-prompt** argument ensures that the tool does not block while waiting for input if any necessary arguments are missing. Consider this example.

```
bin/dsconfig --hostname localhost \
    --port 636 --useSSL --trustStorePath config/truststore \
    --bindDN "uid=admin,dc=example,dc=com" \
    --bindPasswordFile admin-password.txt \
    --batch-file config/hardening-dsconfig-batch-files/reject-insecure-request.dsconfig \
    --no-prompt
```

Running task-based tools

PingAuthorize Server has a Tasks subsystem that allows you to schedule basic operations, such as **backup**, **restore**, **rotate-log**, **schedule-exec-task**, and **stop-server**. All task-based tools require the **--task** option that explicitly indicates the tool is to run as a task rather than in offline mode.

The following table shows the options you can use for task-based operations.

Option	Description
task	Indicates that the tool is invoked as a task. Thetask option is required. If you invoke a tool as a task without thistask option, then a warning message is displayed stating that it must be used. If thetask option is provided but the tool was not given the appropriate set of authentication arguments to the server, then an error message is displayed and the tool exits with an error.
start <starttime></starttime>	Indicates the date and time, expressed in the format 'YYYYMMDDhhmmss', when the operation is to start. A value of '0' causes the task to be scheduled for immediate execution. After the scheduled run, the tool exits immediately.
dependency <taskid></taskid>	Specifies the ID of a task upon which this task depends. A task does not start execution until all its dependencies have completed execution. You can use this option multiple times in a single command.

Options for task-based operations

Option	Description
failedDependencyAction <action></action>	 Specifies the action this task takes if one of its dependent tasks fail. Valid action values are: CANCEL (the default) Cancels the task. DISABLE Disables the task so that it is not eligible to run until you manually enable it again. PROCESS Runs the task.
startAlert	Generates an administrative alert when the task starts running.
errorAlert	Generates an administrative alert when the task fails to complete successfully.
successAlert	Generates an administrative alert when the task completes successfully.
startNotify <emailaddress></emailaddress>	Specifies an email address to notify when the task starts running. You can use this option multiple times in a single command.
completionNotify <emailaddress></emailaddress>	Specifies an email address to notify when the task completes, regardless of whether it succeeded or failed. You can use this option multiple times in a single command.
errorNotify <emailaddress></emailaddress>	Specifies an email address to notify if an error occurs when this task executes. You can use this option multiple times in a single command.
successNotify <emailaddress></emailaddress>	Specifies an email address to notify when this task completes successfully. You can use this option multiple times in a single command.

About the layout of the PingAuthorize Server folders

The following table describes the contents of the PingAuthorize Server distribution file. In addition, the table describes items created as you use PingAuthorize Server.

Directories, files, and tools	Description
README	README file that describes the steps to set up and start PingAuthorize Server.
bak	Stores the physical backup files used with the backup command-line tool.
bat	Stores Windows-based command-line tools for PingAuthorize Server.

PingAuthorize Server directories, files, and tools

Directories, files, and tools	Description
bin	Stores UNIX/Linux-based command-line tools for PingAuthorize Server.
build-info.txt	Contains build and version information for PingAuthorize Server.
collector	Used by the server to make monitored statistics available to PingDataMetrics Server.
config	Stores the configuration files for the backends (admin, config) as well as the directories for messages, schema, tools, and updates.
docs	Provides the product documentation.
extensions	Stores Server SDK extensions.
ldif	Serves as the default location for LDIF exports and imports.
legal	Stores any legal notices for dependent software used with PingAuthorize Server.
lib	Stores any scripts, jar, and library files needed for the server and its extensions.
locks	Stores any lock files in the backends.
logs	Stores log files for PingAuthorize Server.
metrics	Stores the metrics that can be gathered for this server and surfaced in PingDataMetrics Server.
resource	Stores supporting files such as default policies, a sample server profile template, and MIB files for SNMP.
revert-update	The revert-update tool for UNIX/Linux systems.
revert-update.bat	The revert-update tool for Windows systems.
setup	The setup tool for UNIX/Linux systems.
setup.bat	The setup tool for Windows systems.
tmp	Stores temporary files and directories used by the server, including extracted WAR files and compiled JSP files used by Web Application Extensions.
uninstall	The uninstall tool for UNIX/Linux systems.
uninstall.bat	The uninstall tool for Windows systems.
update	The update tool for UNIX/Linux systems.
update.bat	The update tool for Windows systems.

Directories, files, and tools	Description
velocity	Stores any customized Velocity templates and other artifacts (CSS, Javascript, images), or Velocity applications hosted by the server.
webapps	Stores web application files such as the administrative console.

About the layout of the Policy Editor folders

The following table describes the contents of the Policy Editor distribution file:

Policy Editor directories, files, and tools

Directories, files, and tools	Description
admin-point-application	Stores any .jar and library files needed for the server.
bin	Stores UNIX/Linux-based command-line tools for the Policy Editor.
build-info.txt	Contains build and version information for the Policy Editor.
config	Stores the configuration, including the keystore for the web server HTTPS certificate.
lib	<pre>Stores any .jar and library files needed by the command- line tools. To make a custom Spring Expression Language (SpEL) resolver available to the Policy Editor, add the resolver's .jar library to the /extensions subdirectory and add the SpEL Java class to the allow list. For example, PingAuthorize-PAP/lib/extensions/addl-spel- classes.jar.</pre>
logs	Stores log files for the Policy Editor.
policy-backup	Stores H2 policy database backups when such backups are enabled.
resource	Stores supporting files such as policy snapshots.

PingAuthorize Policy Administration Guide



PingAuthorize Policy Editor includes policy development and testing capabilities:

- Policy administration and delegation
- Attribute resolution and orchestration

Getting started

This guide introduces the dynamic authorization features of the PingAuthorize Policy Editor. It shows you how to create attributebased access control policies that reflect your business requirements. It also provides a tour of the various concepts involved in modeling policies in the Policy Editor.

About this task

To get started with the Policy Editor, complete the following tasks:

Steps

1. Sign on to the Policy Editor.

In demo environments, you can use the default credential:

- Username: admin
- Password: password123
- 2. Create a branch.

This branch stores your policies and other entities.

3. Define the Trust Framework.

This allows you to define the elements that will form the building blocks of your policies—the who, what, when, where, and why.

4. Define your policies and policy sets.

Build your policies to reflect your business needs.

5. Test policies and policy sets.

Verify that your policies correctly implement your business rules.

6. Commit changes.

This creates a commit, which is an immutable representation of the Trust Framework and Policies at a point in time.

7. Create a deployment package.

This creates a file that you can deploy to PingAuthorize Server instances across multiple environments.

Next steps

After you sign on to the Policy Editor, the system prompts you to set the branch on which to work. You can create a new (empty) branch, select an existing branch, or **import a branch** from a snapshot file.

The PingAuthorize Policy Editor embraces similar principles to general software source control. When you first deploy the Policy Editor, the **Branches** repository is empty, and the system prompts you to create or import a branch. You must complete one of these actions to continue using the product.

Creat	te a Branch	
Branch nam	ne	Create new branch
	Or	
	rt a Branch from a Snapsh	ot
/ Impo Snapshot	ort a Branch from a Snapsho	
0		
o Snapshot		hot file

Version control (Branch Manager)

Use the **Branch Manager** to manage your fine-grained authorization policy branches, commits, snapshots, and deployment packages.

Creating a new top-level branch

The PingAuthorize Policy Editor allows you to create a new branch in two ways: using the startup window or the Branch Manager.

About this task

i Note

Branch names must be unique. No two branches in the Policy Editor can share the same name.

Steps

1. Sign on to the Policy Editor.

2. Choose how to create the branch per the following table.

To create a new top-level branch from	Do this
The startup window	Specify a Branch name and click Create new branch .
Branch Manager	From Branch Manager → Version Control, you can create a new root, or top-level, branch: From the + menu, select Create new root branch. For the name, replace Untitled with a name for your new branch. Click Save Branch.

î Important

You can not create more than 100 top-level branches in the Policy Editor, including system and self-governance branches.

Creating a subbranch from a commit

Create a branch from a commit. For more information, see Committing changes.

About this task

This subbranch is a child of the branch from which the commit was selected. The subbranch shares the history and contents of the parent branch up to that commit.

Steps

- 1. Go to Branch Manager \rightarrow Version Control.
- 2. Select the commit from which to branch.

To branch from the latest uncommitted changes, make certain to commit before proceeding.

- 3. Click the hamburger menu and select Create new branch from commit.
- 4. Specify a name for the branch.
- 5. Click Save Branch.

Result

The system creates a new subbranch with the selected commit as the branch point.

Importing a branch

Import branches from previously exported snapshot files to share and restore Trust Framework definitions and policies across users and environments.

About this task

A snapshot file contains all the entities and policies from an existing branch. You can share the file like any other file. For more information about creating snapshots, see **Generating snapshots**.

Steps

- 1. Click Branch Manager.
- 2. Click Version Control.
- 3. Click + and select Import Snapshot.
- 4. Select the appropriate snapshot file.
- 5. Specify a name for the branch.
- 6. Click Import.

Deleting a branch

Delete a branch to remove the branch, its history, and any commits created on it from the system.

About this task

You cannot delete a branch if a deployment package has been created from that branch.

() Caution

This operation is irreversible.

To recover data from a deleted branch, load a snapshot exported from the branch if one exists. If no such snapshot is available, contact your system administrator, who might be able to recover the deleted branch from a database backup.

Steps

- 1. Click Branch Manager.
- 2. Click Version Control.
- 3. Select the branch to delete.
- 4. Click Delete Branch.

Merging branches

Merge branches to apply all of the changes made in the source branch to the target branch.

About this task

You can only merge committed branches.

Important

If two branches each contain a Trust Framework or Test Suite definition that was created natively in that branch but has the same exact name and hierarchy in the other branch, the merge operation will not complete successfully. This happens because the duplicated items don't come from the same source, making the branches ineligible for merge conflict resolution. Rename any such duplicated items in one branch before attempting to merge.

Steps

- 1. Click Branch Manager.
- 2. Click Version Control.
- 3. Select the source branch.

You can select top-level branches and subbranches.

- 4. Click Set branch as Merge Source.
- 5. Go to the target branch and click Set branch as Merge Target.

With the source and target branches selected, the Merge Branches button should appear.

6. Click Merge Branches.

The PingAuthorize Policy Editor checks for merge conflicts.

If no conflicts are found, the changes are merged from the source branch into the target branch. Your merge is complete, and you can skip the remaining step.

If conflicts are found, complete the following step to resolve the conflicts.

7. Resolve conflicts.

If an entity has changed in both the incoming and existing branches, the Policy Editor flags a conflict. You must resolve the conflict for the merge to continue. Conflicts appear in the Merge Conflicts table.

- 1. If you need all or almost all of the sections from one branch, click either the **Take All Incoming** button or the **Keep All Existing** button.
- 2. To examine conflicts one at a time, click Resolve Individual Conflicts.

On the resulting screen, select the **Show diff** check box to highlight differences.

Decide which change to keep and click either Keep Existing or Take Incoming.

3. After you resolve all conflicts, close the entity difference box.

The **Apply Merge** button becomes available.

4. Click Apply Merge.

Reverting branch changes

To undo changes since the last commit, use the **Revert** button.

About this task

Each branch has a list of previous commits and **Uncommitted Changes**. To show the changes since the last commit, click the arrow to the left of the hamburger menu in the **Uncommitted Changes** section.

i) Note

Reverting a change reverts all changes that have been made since that change as well. Make sure that you understand all the changes that will be reverted before reverting.

Steps

- 1. Click Branch Manager.
- 2. Click Version Control.
- 3. Select the branch with the uncommitted changes to revert.
- 4. Expand the **Uncommitted Changes** section by clicking the arrow to the left of the hamburger menu to show all the changes that have happened since the last commit.

To the right of each change is a **Revert** button.

5. Click the Revert button and confirm the revert.

Committing changes

To save your policy and Trust Framework changes, commit your changes.

About this task

After you finish building, testing, and analyzing your policies, commit the changes. Committed changes cannot be reverted.

With changes committed, you can create a deployment package from the commit. See Creating a deployment package.

Steps

- 1. Click Branch Manager.
- 2. Click Version Control.
- 3. Select the branch in which to put the commit.
- 4. Click Commit New Changes.

Generating snapshots

A snapshot contains all the details from a commit or from the **Uncommitted Changes** head. You can export a snapshot to import later.

Steps

1. Go to Branch Manager \rightarrow Version Control.

- 2. Click the hamburger menu for the item to snapshot.
- 3. Select Export Snapshot.
- 4. Specify a name for the snapshot.
- 5. Click Export.

Partial snapshot export and merging

With the partial snapshot export feature, you can package a subset (partial) of the policies or Trust Framework entities for export. Then you can import the partial snapshot, either as an imported new branch or merged into an existing branch.

Creating a partial snapshot export

Create a partial export to build an export snapshot of specifically selected entities from the Trust Framework, Policy Sets, and the Library.

Steps

- 1. Click Branch Manager.
- 2. Click Export Partial Snapshot.
- 3. Select the desired items from the list on the left.
- 4. Click Add selection to Snapshot at the top of the pane on the left.

This step adds the entity to the **Selected entities** list. The exported snapshot automatically includes all dependencies so you do not need to explicitly select each individual dependency.

5. Click Export.

Merging a partial snapshot

Merge a snapshot to add or update all of the entities into the current branch.

Steps

- 1. Click Branch Manager.
- 2. Click Merge Snapshot.
- 3. Select the appropriate snapshot file from your system.
- 4. Click Merge.

Result

The system displays a **Summary** page that details the results of the merge.

Next steps

In some cases, the merge function detects conflicts that arise when the current branch version of an entity differs from its snapshot version. For example, this situation might occur if you update one of the merged entities in your current branch and then try to re-merge the snapshot. In such a scenario, the system displays the following **Merge Conflict Resolution** page.

Merge		
Select a file		
File Bank Demo_partial_export.snapshot		×
Summary		
A 3 entities with conflicts - resolve these before importing!		
17 entities already exist		
Dataila		Select
Details		
Type Name	Description	Select all
📮 Untitled	A ID collision	Select -
Permit if clerk has approval		Select -
Payment clerk requires Financial Director approval for payments	A ID collision	Select -
3 total		
		I Merge
		D Mege

For each conflict detected, you can choose whether to keep your local changes or to overwrite them with the changes from the merged snapshot.

	Description		Select all
A	Conflict	Select -	
		Keep mine	
		Keep snapshot's	

After you resolve the conflicts, click Merge.

Creating a deployment package

Create a deployment package from committed changes.

About this task

A deployment package is a compiled version of the policy tree and is the key element that is deployed to PingAuthorize Server.

Steps

- 1. Click Branch Manager.
- 2. Click Deployment Packages.
- 3. Click **+**.
- 4. Replace **Untitled** with a name for the deployment package.

5. Select a Branch, Commit, and Policy Node from which to generate the package.

6. Click Create Package.

The package can be exported any number of times and will remain the same even if further changes are made to the branch.

To export the deployment package, select the package and click Export Package.

Deleting a deployment package

Delete a deployment package to remove it from the Packages list.

Steps

- 1. Click Branch Manager.
- 2. Click Deployment Packages.
- 3. Select the package.
- 4. Click Delete Package.

Self-governance

Self-governance enables you to regulate who can view or change your authorization controls within the Policy Editor.

Just as you build application policies to manage access to your API resources and functions, you build self-governance policies to manage access to your Policy Editor entities and operations. This allows you to protect against unauthorized or accidental application policy changes.

When you install the Policy Editor with self-governance enabled, the application automatically creates the **Admin Point Governance** branch, which contains the **System Policy Set** and several self-governance Trust Framework definitions.

Important

While self-governance controls are no different than standard Policy Editor controls, all of your self-governance controls must be contained within the **Admin Point Governance** branch. By default, this branch is only visible to the self-governance administrator. Any policy sets, policies, and rules you build must be children of the **System Policy Set**.

How does self-governance manage access?

When self-governance is enabled and a user attempts to perform an action within the Policy Editor, this action is subject to the authorization policies defined in the **System Policy Set** of the **Admin Point Governance** branch. These access controls are applied at the level of the Policy Editor REST API and are therefore applicable to users of the Policy Editor web application and clients of the REST API.

The Policy Editor automatically turns the attempted action into an internal decision request against these self-governance policies. This request includes:

- A service, which indicates the type of entity the user is interacting with (for example, policy set, policy, attribute, or branch)
- An action, which indicates what the user is trying to do (for example, read, update, or delete)

- Attributes that describe the existing state of the object being acted upon and the intended state of the object after the user's action
- Attributes that describe the current branch upon which the user is performing the action
- Attributes that describe the Policy Editor user performing the action

You can find more information about Self-governance Trust Framework for all of the relevant services, actions, attributes, and conditions that you can use to build policies for your Self-governance use cases.

Enable self-governance

Self-governance is not part of the baseline configuration for the Policy Editor and must be enabled during installation. Use the non-interactive setup for self-governance in either demo mode or OIDC mode, supplying the appropriate arguments. You can find more information about enabling self-governance in Installing the PingAuthorize Policy Editor non-interactively.

(i) Note

Best Practice: Self-governance is intended for use with a single Policy Editor instance. In an environment with multiple Policy Editor instances connected to a single database, restart each instance after committing your self-governance policy updates.

As part of setup, the Policy Editor creates a self-governance administrator account. This is a special user who is never subject to self-governance policies and always has full control over the entire Policy Editor.

Important

It is possible, through misconfiguration of self-governance policies, to completely lock regular users out of the Policy Editor. To address this scenario, the self-governance administrator can update or roll back self-governance policy updates to restore Policy Editor access.

HTTP caching

HTTP caching is enabled by default as part of a standard Policy Editor configuration, but can be permanently disabled. When using HTTP caching in combination with self-governance, the time-to-live value of the cache plays an important role in selfgovernance decisions. After the cache expires, the Policy Editor verifies that the user still has access to the resource, even if the resource is unchanged. You can find more information in HTTP caching.

Logging

Self-governance logging is enabled by default and all related logs are stored in the **logs** directory. Self-governance information is written to the following logs:

decision-audit.log

This log contains a list of policy decisions made by the policy decision point (PDP).

management-audit.log

The log contains a list of any actionable self-governance requests.

debug.log

This is the Policy Editor application log. You can use it to debug any application-related issues.

Self-governance use cases

You can use self-governance to control access to Policy Editor entities and operations in a wide variety of ways.

Controls that you can configure using self-governance include:

- Protecting a policy set from deletion
- Ensuring a policy can never be updated
- Preventing policies from being added or created in a policy set
- Blocking a user's ability to delete attributes
- Restricting a user's ability to read policies or policy sets
- Allowing attributes to be elevated to secret status while forbidding secret attributes from moving to non-secret status

The following use cases demonstrate how to build and deploy some common self-governance policies.

🕥 Note

To view a visual flow of your self-governance policy decisions, refer to Visualizing a policy decision response.

Use case: Preventing a user from viewing a branch

About this task

The following are the general steps needed to prevent a user from viewing a branch.

Steps

- 1. Create a policy named Prevent a user from viewing a branch in the System Policy Set of the Admin Point Governance branch.
- 2. Add a rule and name it Deny if branch is Admin Point Governance and user is Steve Smith.
- 3. Add a condition that returns true when Branch.Name equals Admin Point Governance.
- 4. Add a condition that returns true when user.name equals Steve Smith.
- 5. Select Components and drag the Core.Branch service to the Applies to section of the rule.
- 6. Drag the **Read** action to the **Applies to** section of the rule.
- 7. Save the policy.
- 8. Commit the changes to the Admin Point Governance branch in Branch Manger > Version Control.

Result

This self-governance policy returns a **Deny** response if a user named Steve Smith tries to view the **Admin Point Governance** branch.

Use case: Preventing users from updating a policy set

About this task

The following are the general steps needed to prevent users from updating a policy set:

Steps

- 1. Create a policy named Prevent users from updating a policy set in the System Policy Set of the Admin Point Governance branch.
- 2. Add a rule that returns a Deny if Object.Existing.Name equals examplePolicySet.
- 3. Select Components and drag the Core.PolicySet service to the Applies to section of the rule.
- 4. Drag the Modify.Update action to the Applies to section of the rule.
- 5. Save the policy.
- 6. Commit the changes to the Admin Point Governance branch in Branch Manger > Version Control.

Result

This self-governance policy returns a Deny response when a user tries to modify a policy set with the name examplePolicySet.

Use case: Preventing users from deleting policies

About this task

The following are the general steps needed to prevent users from deleting policies:

Steps

- 1. Create a policy named Prevent users from deleting policies in the System Policy Set of the Admin Point Governance branch.
- 2. Add a rule that always returns a Deny response.
- 3. Select Components and drag the Core.Policy service to the Applies to section of the rule.
- 4. Drag the Modify.Delete action to the Applies to section of the rule.
- 5. Save the policy.
- 6. Commit the changes to the Admin Point Governance branch in Branch Manger > Version Control.

Result

This self-governance policy returns a Deny response when a user tries to delete a policy within the system.

Self-governance Trust Framework

To make it easier to get started developing self-governance policies, the **Admin Point Governance** branch initializes with a default set of Trust Framework definitions.

Use the self-governance attributes and conditions to build your policy logic and then include self-governance actions and services to target when your policies will apply. The following tables describe the included Trust Framework definitions for self-governance.

(i) Note

Avoid using Trust Framework definitions related to self-governance permissions. While some of these items are visible and exposed within the Policy Editor, the permissions system is not enabled or supported.

Attribute Name	Scope	Description
Branch	All operations	JSON data regarding the branch on which the current operation is being performed.
Branch.ld	All operations	GUID of the branch on which the current operation is being performed.
Branch.Name	All operations	Name of the branch on which the current operation is being performed.
Branch.ParentId	All operations	GUID of the parent branch for the branch on which the current operation is being performed.
DeploymentPackage	Deployment package operations	A folder to contain nested attributes. It has no value of its own.
DeploymentPackage.Decision Node ID	Deployment package operations	GUID of the decision node referred to by the deployment package that the user is acting upon.
DeploymentPackage.Snapshot Id	Deployment package operations	GUID of the snapshot referred to by the deployment package that the user is acting upon.
fromId	Diff or merge operations	The from ID argument passed to the service, if from and to arguments are required.
id	Diff or merge operations	The ID argument passed to the service.
name	Diff or merge operations	The string argument passed to the service.
Object	None	A folder to contain nested attributes. It has no value of its own.
Object.Existing	All operations	JSON data containing details of the current state of the object that the user is acting upon. Nested attributes below this attribute in the hierarchy extract specific values from this JSON data using JSONPath.
Object.Existing.Approvals	None	Collection of all the approvals for the deployment package that the user is acting upon.
Object.Existing.Approvals.UserIds	Deployment package operations	Collection of user IDs for all approvals on the deployment package that the user is acting upon.

Attribute Name	Scope	Description
Object.Existing.Approvals.Count	Deployment package operations	Total number of approvals on the deployment package that the user is acting upon.
Object.Existing.AttributeResolvers	Attributes	Collection of all the resolvers for the attribute that the user is acting upon.
Object.Existing.BranchId	Attributes	The branch ID of the object being acted upon by the user.
Object.Existing.CacheConfig	Attributes	JSON data detailing the cache settings for the attribute that the user is acting upon.
Object.Existing.Children	All operations	The direct first level children of the object that the user is acting upon.
Object.Existing.CombiningAlgorithm	Policy sets, policies	The combining algorithm of the policy or policy set that the user is acting upon.
Object.Existing.CustomProperties	All operations	JSON data of the custom properties set for the object that the user is acting upon.
Object.Existing.DefaultValue	Attributes	The default value of the attribute that the user is acting upon.
Object.Existing.DefinitionId	Trust Framework definitions	The GUID of the Trust Framework definition that the user is acting upon.
Object.Existing.Description	All operations	The description of the object that the user is acting upon.
Object.Existing.Disabled	Policy sets, policies, rules	Boolean value indicating whether or not the policy node that the user is acting upon is disabled.
Object.Existing.FullName	Trust Framework definitions	The full name, including parent names, of the Trust Framework definition.
Object.Existing.Id	All operations	The GUID of the object that the user is acting upon.
Object.Existing.IdentityProperties	Identity classes, identity providers	Collection of all the identity properties for the definition that the user is acting upon.
Object.Existing.IsPresent	All operations	Boolean that is true if the object that the user is acting upon is present.
Object.Existing.Name	All operations	The name of the object being acted upon by the user.

Attribute Name	Scope	Description
Object.Existing.Name.lsPresent	All operations	Boolean that is true if the Object.Existing.Name attribute is present in the self-governance decision request.
Object.Existing.ObjectType	Trust Framework	The type of Trust Framework definition that the user is acting upon.
Object.Existing.ParentId	All operations	The GUID of the direct parent of the object being acted upon by the user.
Object.Existing.Resolvers	Attributes	JSON value detailing the resolvers of the attribute that the user is acting upon.
Object.Existing.Secret	Attributes	Boolean indicating whether the attribute that the user is acting upon has been marked as secret.
Object.Existing.ServiceSettings Services		JSON value detailing all of the service settings for the service that the user is acting upon.
Object.Existing.ServiceType	Services	The type of the service that the user is acting upon.
Object.Existing.Shared	Rules, targets, statements	Boolean that is true if the object that the user is acting upon is shared (appears in the Library).
Object.Existing.Statements	Policy nodes	Collection containing the list of statements for the policy node that the user is acting upon.
Object.Existing.Targets	Policy nodes	Collection containing the list of targets for the policy node that the user is acting upon.
Object.Existing.TestCase	Test case definitions	JSON representation of the test case associated with this definition.
Object.Existing.TestScenario	Test scenario definitions	JSON representation of the test scenario associated with this definition.
Object.Existing.Type	Definition	The type of definition (Trust Framework or Test Suite entity) that the user is acting upon.
Object.Existing.Version	All operations	Version of the entity that the user is acting upon.
Object.Intended	All operations	JSON data containing details of the intended state of the object after the action the user is trying to perform. Nested attributes below this attribute in the hierarchy extract specific values from this JSON data using JSONPath.

Attribute Name	Scope	Description
Object.Intended.*	All operations	Object.Intended has the same child attribute structure as Object.Existing .
Snapshot	Snapshots	JSON data regarding the commit that the user is acting upon.
Snapshot.Approval Count	Snapshots	Number of approvals on the commit that the user is acting upon.
Snapshot.Approvals	Snapshots	Collection of names of all users who have approved the commit that the user is acting upon.
Snapshot.BranchId	Snapshots	GUID of the branch of the commit that the user is acting upon.
Snapshot.Id	Snapshots	GUID of the commit that the user is acting upon.
Snapshot.ParentId	Snapshots	GUID of the direct parent of the commit that the user is acting upon.
Snapshot.State	Snapshots	Current state of the commit that the user is acting upon. The value can be either UNCOMMITTED or COMMITTED .
told	Diff or merge operations	ID of the entity the change is being merged to.
user	All operations	JSON data describing the user performing the action. User attributes like LDAP properties or OIDC claims are mapped as keys and values, where a single value is expressed as a JSON array. If OIDC claims have an attribute nickname with value abc, the JSON data will be \{"nickname":["abc"]}. To get the scalar value of an attribute, use a processor and access the zeroth value of the JSON array. Any derived user attribute that contains sensitive information must be marked as secret in Value Settings.
user.name	All operations	Name of the user performing the action.
user.name.lowercase	All operations	Lowercase value of the name.

Service Name	Description
Core	A folder containing child services. It has no other function.
Core.Branch	Targets operations involving branches.

Service Name	Description
Core.Definition	Targets operations involving Trust Framework definitions.
Core.Delta	Targets operations involving Version Control deltas.
Core.DeploymentPackage	Targets operations involving deployment packages.
Core.DiffMerge	Targets Version Control diff or merge operations.
Core.Entity.Change	Targets operations involving entity changes.
Core.Policy	Targets operations involving policies.
Core.PolicySet	Targets operations involving policy sets.
Core.RecentDecisions	Targets operations involving the recent decisions diagnostics buffers.
Core.RecentDecisions.Configuration	Targets operations involving the configuration of a recent decisions buffer.
Core.RecentDecisions.Content	Targets operations involving the content of a recent decisions buffer.
Core.Rule	Targets operations involving rules.
Core.Snapshot	Targets operations involving snapshots.
Core.Statement	Targets operations involving statements (obligations or advice).
Core.Target	Targets operations involving targets.
Test.Scenario	Targets operations involving test scenarios and scenario groups.
Test.TestCase	Targets operations involving test cases and test groups.

Action Name	Scope	Description
Modify	All operations	Targets any modification: commit, create, delete, import, roll back, or update.
Modify.Commit	Version Control	Targets commits within Branch Manager → Version Control .
Modify.Create	All operations	Targets the creation of any object, including branches, attributes, policies, and so on.
Modify.Delete	All operations	Targets the deletion of any object, including branches, attributes, policies, and so on.
Modify.Import	Snapshots	Targets importing snapshots.

Action Name	Scope	Description
Modify.Rollback	Version Control	Targets attempts to roll back deltas within Version Control.
Modify.Update	All operations	Targets the update of any object, including branches, attributes, policies, and so on.
Read	All operations	Targets reading any object, including branches, attributes, policies, and so on.
Read.Diff	Version Control	Targets reading a diff within Version Control.
Read.Export	Deployment packages and snapshots	Targets exporting a snapshot or deployment package.
Read.List	All operations	Targets any operations that read a listing (in other words, list all branches).
Read.History	All operations	Targets operations that attempt to read the history of an entity.
Condition Name	Scope	Description
Object.ls Root	All operations	True if the object is a root element (in other words, has no parent) but otherwise false.
Object.ls Shared	All operations	True if the object is a shared element (in other words, it is in the Library and has no parent) but otherwise false.
Object.Is Shared.Existing	All operations	True if the object is already shared before being updated but otherwise false.
Object.ls Shared.Intended	All operations	True if the object will be shared after being updated but

Importing a self-governance policy snapshot

If you have existing self-governance policies in a policy snapshot, you can import them using the standard snapshot import process, with some minor adjustments.

otherwise false.

Before you begin

Enable self-governance and sign on to the Policy Editor as the self-governance administrator.

Steps

1. Deactivate the previous self-governance policies:

Choose from:

- Delete the existing Admin Point Governance branch.
- Rename the existing Admin Point Governance branch.

Caution

After renaming or deleting the branch, all change requests subject to self-governance will be denied until the Policy Editor detects a branch named Admin Point Governance.

2. Import the new self-governance branch and name it Admin Point Governance.

Learn more in Loading a policy snapshot.

3. Commit the changes in Branch Manager > Version Control.

Result

You've imported a new Admin Point Governance branch and activated its self-governance policies. If you didn't delete the previous branch, you've also created a backup of the previous self-governance policies, which you can roll back to if needed.

Trust Framework

The Trust Framework tool lets you define all the entities within your organizations about which you want to build policies at a later time.

You must define anything you want to express in your policies in the Trust Framework. As a result, your policies are tightly coupled to the definitions in your Trust Framework, with strict restrictions on intermixing of values with differing data types.

When defining and using these items, you can identify all the places they are used as described in Viewing dependents.

Domains (Authorization Policy Decision APIs only)

You need to define the organizational structure of any other organizations with which you intend to interact and, consequently, on which you want to specify authorization policies.

Define these organizations under **Trust Framework**, using the **Domains** section, which is available only on servers with Authorization Policy Decision APIs enabled. Start with a relatively clean and simple domain ontology. You can extend it later if you need more granular levels.

You can import these values from your existing organizational directory, such as Active Directory. Make certain that you do not import redundant and unnecessary entities.

Services

The Services section enables the definition of the following types of services:

• The resources to which you want to control access (what your policies will protect).

For a resource, define only the top-level fields, such as **Name**, **Parent**, and **Description**. Unless you plan to also use the service as a policy information provider, leave the **Service Type** as **None**.

• The policy information providers that you use as sources of data for the attributes that comprise policy decisions.

Setting up services as policy information providers makes use of various service connectors.

When you make a selection from the **Service Type** list, settings specific to the service appear. Settings that apply to all service endpoints also appear.

When a service returns a value to resolve an attribute, you can:

- Map the response to a type.
- Apply a processor to the response to transform that response or to extract a specific part of it.

Connecting a service

Connect PingAuthorize to external services to define data integrations.

About this task

Service connections in PingAuthorize enable you to augment authorization events with real-time data. For example, you might use signals from a risk service in policies to determine if a device requires step-up authentication.

You can integrate with HTTP, Lightweight Directory Access Protocol (LDAP), and database services. Learn more about service settings in **Common settings**.

To add a new service:

Steps

- 1. Go to the Trust Framework.
- 2. On the Services tab, click the + icon and select Add new Service.
- 3. Enter a unique name for the service.

介 Important

Periods (.) are not allowed in the name.

4. Optional: For Description, enter a description of the service's purpose.

The description is only visible on the Services tab, but it can help policy authors understand how to use services in policies.

5. Optional: To nest the service under a parent in the tree, in the Parent list, select a parent service.

Nesting helps group related services together. You can move the service to another location in the tree by selecting a different parent service. To remove nesting, click the **Delete** icon and leave **Parent** blank.

6. Select a **Service Type**.

Choose from:

- **None**: This is for a parent service. Nest other services under a parent to help organize services in the tree structure. There are no additional settings to complete for this type of service.
- **Database**: Connections to database sources are currently unsupported.
- **HTTP**: Connects to HTTP endpoints accessible over the public internet. For details about HTTP service settings, see **HTTP services**.
- LDAP: Connects to LDAP sources and retrieves information through database queries. Learn more about LDAP service settings, in LDAP services.
- 7. **Optional:** In the **Value Settings** section, define the data **Type** for the data returned by the service, and select the **Secrets** checkbox to encrypt that data in PingAuthorize logs.

Depending on which mode you have configuredPingAuthorize in, service data secrets are recorded in one of two logs:

- Embedded PDP mode: The service data values are encrypted in PingAuthorize/policy-decision.log.
- External PDP mode: The service data values are encrypted in the decision-audit.log file distributed with the Policy Editor, but not PingAuthorize/policy-decision.log.

To decrypt a service's data values, run the following command. In this example, RSNH/SPsNJSFQyyLSxdKsw== represents the encrypted service value string, and 54655374506153735068526153653939 represents the encryption key in hexadecimal. By default, the encryption key is TeStPaSsPhRaSe99 and cannot be changed.

```
'echo -n "RSNH/SPsNJSFQyyLSxdKsw==" | base64 -d | openssl enc -aes-128-ecb -d -K
"54655374506153735068526153653939"
```

8. Optional: In the Timeout and Retry section, enter a Request Timeout value if you want to change the time in milliseconds that PingAuthorize waits for a service request to complete.

The default timeout is **2000**. If the timeout elapses before there is a successful service response, the service request is canceled, resulting in a timeout error.

9. Optional: In the Rate Limits section, enter a Requests per Second value to change the maximum number of requests that decision points can make to the service per second.

The default value is 1000000.

10. **Optional:** Enable caching for the service.

Caching improves system performance by storing data returned from a service and reusing it on subsequent service requests until the cache expires. Learn more in Service caching.

- 1. Select the Enable Caching checkbox.
- 2. For the **Time to Live**, enter the number of minutes that you want to store data retrieved from the service in the cache.

 Cache Settings 			
Enable Caching	2 2	Time To Live (sec)	0

The maximum time to live is 1440 minutes or 1 day.

3. **Optional:** If you are enabling caching for an HTTP service, click **+ Header** and select headers to exclude from the cache key.

-	Cache Settings				
	Enable Caching	2	Time To Live (sec)	0	
	Cache Key exclusions	example-header 🛛 🕐			
	+ Header				

Because the service cache is invalidated by any changes to the cache key, removing headers preserves the validity of the cache even when values of those headers change.

Common settings

The settings in this section apply to all service types.

Request Timeout

The number of milliseconds that PingAuthorize Server waits for the request to complete. If this time elapses before receiving a successful response, the server cancels request. If the server has retries configured, the server attempts the request again. If all requests fail to complete in time, the service result is an error that represents the timeout.

Number of Retries

If the initial request fails or times out, this value indicates the number of times PingAuthorize Server attempts the request again. To try the request only once, set this value to zero.

i) Note

If the service responds with a 4xx error, PingAuthorize Server won't make any retry attempts.

Retry Strategy

Options are:

Fixed Interval (default)

PingAuthorize Server waits for the retry delay between each attempt to perform a service request.

Exponential Backoff

PingAuthorize Server waits for an exponentially increasing amount of time between attempts.

Initial Retry Delay

For Fixed Interval, this value represents the number of milliseconds that PingAuthorize Server waits between request attempts.

For **Exponential Backoff**, PingAuthorize Server multiplies this value by 2ⁿ, where *n* represents the number of retries already made. For example, if the retry delay is 1000 and you have **Exponential Backoff** selected, PingAuthorize Server makes the initial request, then waits 1000ms before making a second attempt, 2000ms before the third attempt, 4000ms before the fourth attempt, and so on.

Delay Jitter

This setting is a percentage value that indicates the amount of variability to apply to the retry delay on each attempt. For example, if this value is set to 10%, the delays in the previous example are 1000±100ms, 2000±100ms, 4000±100ms, and so on.

Value Processors

Specify an optional processor to transform the resolved value. See Processors.

Value Settings

These are required settings that are applied and describe the resolved value after any preprocessing. Set the **Type** field to **String** for plain text, or **JSON** or **XML** for those types, and so forth.

Secret

Select the Secret check box to mark a service's response as secret and ensure this data is never leaked to log files.

HTTP services

The policy decision point (PDP) can perform requests to HTTP services. These requests can send and receive text, JavaScript Object Notation (JSON), and Extensible Markup Language (XML) content.

HTTP authentication supports using a simple username and password, bearer token, or OAuth 2.0 client credentials flow.

You can send custom headers with any request, which you can make dynamically in various ways by interpolating attribute values into various parameters. For more information, see Attribute interpolation.

Core settings

URL

URL for the REST endpoint that the PDP accesses. The Policy Manager can interpolate attributes anywhere in the URL.

∧ Important

Because no escaping of attribute values takes place, make certain that this action is completed in the attribute definition to prevent non-valid characters in the URL.

HTTP Method

Method to send in the HTTP request.

Content Type

Content-Type header to send, which relates to the body of the request.

Body

Body to send with the request. The Policy Manager can interpolate attributes anywhere in the body with no escaping.

Authentication

The **Authentication** list contains the following HTTP authentication types, which correspond to an authorization header sent with the request:

None

Default value that indicates the PDP sends no authorization header.

Basic

Reveals the choices for attributes whose values function as the username and password of an HTTP request with basic authentication.

Bearer Token

Reveals a token selector. The PDP sends the selected attribute as the authorization token in an HTTP request with bearer authentication.

OAuth 2.0 (Client Credentials)

Reduces configuration complexity and time to production when connecting to HTTP services that require OAuth authentication. Reveals four configuration options.

介 Important

This flow sends information to the authorization server in a **POST** request in the body. If the authorization server expects a different format, the flow will not complete successfully.

Token Endpoint

Authorization server's endpoint that can grant an access token.

PingAuthorize caches the token and reuses it if it is not expired.

Client Id

Unique string representing the client identifier. This value can be either a constant or an interpolated attribute to resolve the value at runtime.

Client Secret

Attribute that will resolve to the client secret.

You can resolve the **Client Id** and **Client Secret** attributes from the PingAuthorize configuration.

• Scope (optional)

Tip

A comma-separated list of scopes representing the scope of the access request.

Headers

You can add any number of custom headers to the request. The header names are fixed strings, but their values can be constants or attribute values. To switch between constant and attribute, toggle **C / A**, which is next to a header value.

Certificate validation

With certificate validation, you can define TLS and Mutual-TLS (M-TLS) certificates and keys when connecting to the TLS (or SSL) based service.

When using external PDP mode, you can declare local file-based trust stores and key stores by providing an options file during setup. For more information, see Specifying custom configuration with an options file.

When using embedded PDP mode, you can declare local file-based trust stores and key stores by assigning trust manager providers and key manager providers to the Policy Decision Service. For more information, see Use policies in a production environment.

Server (TLS)

Applies when validating the certificate or certificate chain sent from the server. You have three options when validating a server certificate:

No Validation

Skips validating the server certificates and initiates connection without any restriction.

• Default

🕥 Note

This option is the default for Server (TLS).

Uses the default trust store provided by the runtime environment.

Use this if you are trying to connect to a service that has a certificate issued from a valid certificate authority.

Custom

Allows the user to define a custom certificate or certificate chain that is stored in a trust store:

Truststore name

The name given to the trust store in **configuration.yml**.

• Alias

Certificates in the trust stores are mapped by alias. You must set the alias in the trust store to specify which certificate to use for validation.

Attributes can be interpolated anywhere in the value.

• Alias password

If the certificate is password protected, it might need to provide the password.

Attributes can be interpolated anywhere in the value.

Client (M-TLS)

Some services might require the client to provide a client certificate when initializing the connection. To provide a client certificate, enable this setting and provide a custom key store to be sent to the service:

Keystore name

The name given to the key store in configuration.yml.

Alias

Key-value pairs and the certificate entry in the key stores are mapped by alias. You must set the alias in the key store to specify which entry to use for validation.

Attributes can be interpolated anywhere in the value.

Alias password

If the certificate entry is password protected, it might need to provide the password.

Attributes can be interpolated anywhere in the value.

LDAP services

The policy decision point (PDP) can make LDAP queries to retrieve information.

You can make requests dynamic by interpolating attribute values into different parameters. See Attribute interpolation.

Configuration

Specify the following settings to configure an LDAP service. A publicly available LDAP service is used as an example.

Host and Port

The host name and port number of the LDAP server. For example:

Host: ldap.forumsys.com Port: 389

Username / Bind DN and Password

The user or bind credentials for the LDAP server. For example:

Bind DN: cn=read-only-admin,dc=example,dc=com Password: password

Use SSL

If the LDAP server is secured using SSL, enable this setting.

Enabling this setting populates the Certificate Validation section, which is useful when configuring TLS and M-TLS certificates. For more information, see paz_http_services.adoc#section_zvj_jss_tkb.

Search Base DN / LDAP filter

These settings define the LDAP query. For example:

```
Search Base DN: dc=example,dc=com
LDAP Filter: ou=mathematicians
```

Results

Because the server converts the result of an LDAP query to an XML document, you must set the service value type to XML. The previous example query results in the following document.

You can extract Individual parts or collections of the data from the resulting XML document by using XPath processors. For example, the following XPath processor extracts the set of unique members:

```
//searchResponse/searchResultEntry/attr[@name='uniqueMember']/text()
```

Applying this processor to the above XML document produces the following result:

uid=euclid, dc=example, dc=com uid=riemann, dc=example, dc=com uid=euler, dc=example, dc=com uid=gauss, dc=example, dc=com uid=test, dc=example, dc=com

Enabling Camel service connections

If your PingAuthorize implementation relies on Apache Camel, you can enable Camel for both **embedded** and **external** (PDP) modes.

Before you begin

You must install the Policy Editor and the PingAuthorize server before enabling Camel services.

About this task

To ensure that Camel is used with appropriate permissions and security controls, Camel services are disabled by default in the Policy Editor.

Warning

If you upgrade an existing installation of PingAuthorize to version 9.3.0.0 or later, and the earlier version was configured in embedded PPD mode with a deployment package containing Camel services, the upgraded PingAuthorize server will fail to start. The following steps also resolve this issue:

Steps

- 1. In the PingAuthorize server distribution, copy the symphonic-camel-pdp-<version>.jar file from resource/camel to the lib folder.
- 2. In the Policy Editor distribution, copy the symphonic-camel-pap-<version>.jar file from resource/camel to the adminpoint-application/lib folder.
- 3. In the Policy Editor distribution, add the "camel-service" flag to enabledFeatures in the config/configuration.yml file.

Example:

enabledFeatures: - "test-suite"

- "entity-dependents"
- "camel-service"
- 4. Save your changes and restart the Policy Editor.

Result

You should now be able to use Camel services to inform your authorization policy decisions in both external and embedded PDP modes.

Camel services

Overview

You can retrieve information from any endpoint that the Apache Camel \square enterprise integration platform supports. See the list of Camel components \square for a full list of supported systems.

Configure Camel components by using a combination of URI, Headers, Body, and Configuration settings. The appropriate values to provide for each setting depend on the component that is used.

You can make requests dynamic by interpolating attribute values into different parameters. See Attribute interpolation.

Camel settings

-	Service Settings		
	Service Type	Camel -	
L	Camel Settings		
	URI	S	
L	Headers	S	
L	Body	S	
	Configuration		

Setting	Description
URI	The identifier for the Camel endpoint. PingAuthorize can interpolate attribute values into this field.
Headers	Additional information to send with the Camel service request. PingAuthorize can interpolate attribute values into this field.
Body	The body to send with the Camel service request. PingAuthorize can interpolate attribute values into this field.
Configuration	Some Camel components require you to configure helper components for them to work. specify these components by using the Groovy C scripting language to write a Spring Bean configuration block. Learn more about writing configurations In Class GroovyBeanDefinitionReader C. PingAuthorize cannot interpolate attributes into this field.

(i) Note

The Camel JDBC component makes use of the Headers and Body settings and requires a JDBC data source to be set up in the Camel Configuration setting.

Value processors

You can define value processors to transform data returned by the Camel service. Learn more in Processors.

Attributes

Attributes provide the context that enables fine-grained policies.

Attribute values come from a multitude of sources. You can use the original values or modify the values. You can then use the final values in other attributes, Adding a named condition, or rules.

The system resolves an attribute only when its value is required as part of the decision request evaluation. For example, if a rule checks whether a customer's device "Risk Score" is high, then the system only attempts to resolve the attribute corresponding to "Risk Score" if that rule is required.

Creating an attribute

Create attributes using the business terms that business users and policy writers already understand.

About this task

Consider the manner in which you will structure the attributes and the naming conventions that you will use. You want policy writers to be able to build and manage policies without developing a deep understanding of the often-complex underlying data endpoints or data manipulation.

Steps

- 1. Click Trust Framework.
- 2. Click Attributes.
- 3. Click +.
- 4. Select Add new Attribute.
- 5. Update the attribute to include resolvers, value processing, and other changes, as discussed in the subsections after this one.
- 6. Click Save changes.

After you create an attribute, you can modify it to be a repeating attribute. For more information, see Repeating policies and attributes.

Attribute name, description, and location

You can give attributes any name that is unique and does not contain a period (.).

To ensure that the system can interpolate the attribute, avoid the following characters:

• {

- }
- 1

You can give the attribute a description to help policy editors understand the attribute's purpose. This description is only displayed when a user navigates to the attribute.

You can change the location of an attribute in the attribute tree using the **Parent** field.

Resolvers

Resolvers define where attributes pull information from.

An attribute can have one or more resolvers. Resolvers can be conditional. In addition, you can add a processor to a resolver to modify the attribute value.

PingAuthorize resolves an attribute when the attribute is used in a decision evaluation. Multiple resolvers are resolved in order of appearance in the attribute definition, until one of them produces a value. You can drag collapsed resolvers to change their order. If a resolver fails to resolve successfully, processing moves on to the next resolver.

Resolver types

You can use the following types of resolvers:

Resolver type	Description
Request	Looks inside the decision request to determine whether the attribute has been provided by the caller. Specify the full name of the attribute, including any parents, in the request.
Constant	Takes a constant value defined on the resolver itself. The type and value of the constant are required. ONOTE Constants undergo any value processing defined for the attribute.
Service	Resolves the attribute by using a Trust Framework service endpoint to invoke the service at runtime. The service might rely on other attributes being suplpied to invoke the service.

Resolver type	Description
Attribute	Resolves an attribute form other attributes. This enables you to extract a child attribute or subset from an attribute that contains multiple pieces of information. For example, consider a Customer.Name attribute that returns the following JSON representation: { "firstname": "Andrew", "middlename": "James", "surname": "Martin" }
	You can use an Attribute resolver to extract the surname. Create a Customer.Name.Surname attribute that resolves against the Customer.Name attribute. Then, add a JSON Path processor to extract the Surname property of the JSON using the expression \$.fullname[0].surname. When an attribute has a parent, you can click the + Add Parent Resolver button to resolve the child attribute against its parent.
System	Use standard system attributes without the need for any additional configuration: CurrentDateTime This returns the current system datetime according to the type defined for the attribute. Null This returns no value. For example, you can use Null to compare the value of an attribute to an empty string. To check against a null value, create an attribute with a System resolver and a value of Null.
Configuration Key	The policy engine can resolve attribute values using policy configuration keys. When using external PDP mode, you can declare local, file-based trust stores and key stores by providing an options file during setup. Learn more in Specifying custom configuration with an options file. When using embedded PDP mode, you do this by creating Policy Configuration Keys in the Policy Decision Service. Learn more in Use policies in a production environment.

Conditional resolvers

Resolvers can have conditional logic that invokes the resolver only under defined conditions. As with other in PingAuthorize, you can add comparisons or named conditions, combine multiple conditions using **All**, **Any**, or **None**, and add subgroups.

In the following example of a conditional resolver, the game player's email address is resolved only when the **User is over 18** attribute has a value of **true**.

Value processing for a resolver

Resolvers can have value processors that extract details and modify data when the attribute value is being resolved. As with other processors, value processors for resolvers are processed in order, with each processor receiving the output of the previous processor.

If you expect responses from different resolved sources to vary, you can add a processor to the resolvers to normalize the output. In this example, the attribute's value can come from one of the following resolvers:

• A service named GET User Profile

With this resolver, if the **Cache is Valid** attribute is false, the resolver calls the **GET User Profile** service and uses a JSON Path processor to extract the key from the profile JSON.

• An attribute named Key

In the second resolver, the attribute value comes from the Key attribute, and the value requires no processing.

The following image shows the resolvers. The resolvers apply in the order shown.

- Resolvers (2 total)

 Service - GET User Profile If condition holds 	rei () 🗮
ALL ANY NONE CLEAR ALL	
A Cache is Valid	✓ Equals ✓ C false
+ Comparison + Named Condition + Group	
- Resolve attribute using	
Resolver type Service	GET User Profile
- Then apply value processors (1 total)	
- Extract the key from user profile	<u>ش</u>
Processor JSON Pathkey	Ø
Value type String -	
+ Add Processor	
 Attribute - Key Resolve attribute using 	Ξ
Resolver type Attribute	Key

+ Add Resolver

Adding value processors directly to resolvers, rather than to the attribute itself, can be useful when pulling data from distinct sources that require different formatting.

For example, consider a bank that wants to pull in user information either from a modern system or a legacy system to authorize transactions. These systems are represented by the **Account Details System** and **Legacy Account Details System** HTTP services, respectively. With the following resolver configuration, the decision service calls to the **Account Details System** service if the user ID is above **10000** (indicating a new user), or to the **Legacy Account Details System** service if the user ID is less than or equal to **10000** (indicating a legacy user):

Account Details	es ()
if condition holds	
ALL ANY NONE CLEARALL	
A Request.User ID - Greater Than - C 10000	
+ Comparison + Named Condition + Group	
Resolve attribute using	
Resolver type Service Account Details System	
Then apply value processors (1 total)	
Extract Total Balance JSON	1
Add Processor	
Legacy Account Details	en ()
Add Precessor Legacy Account Details If condition holds ALL ANY NONE CLEAR ALL	et ()
Legacy Account Details If condition holds	M ()
Legacy Account Details If condition holds ALL ANY NONE CLEAR ALL	
Legacy Account Details If condition holds ALL ANY NONE CLEAR ALL A Request.User ID - Less Than Or Equal - C 10000	
Legacy Account Details If condition holds ALL ANY NONE CLEAR ALL A Request.User ID + Comparison + Named Condition + Group	
Legacy Account Details If condition holds ALL ANY NONE CLEARALL A Request.User ID - Less Than Or Equal - C 10000 + Comparison + Named Condition + Group Resolve attribute using	
Legacy Account Details If condition holds ALL AVY NONE CLEAR ALL A Request.User ID - Less Than Or Equal - C 10000 + Comparison + Named Condition + Group Resolve attribute using - Legacy Account Details System	
Legacy Account Details If condition holds ALL AVY NOVE CLEAR ALL A Request.User ID - C 1000 + Comparison + Named Condition + Group Resolve attribute using - C 1000 Then apply value processors (1 totol) - C Legacy Account Details System	

Data collected from the **Account Details System** service is formatted as JSON and requires a JSON Path **processor** defined on the **Account Details** resolver to extract a new user's total balance:

-	Then apply value processors (1	total)				
-	Extract Total Balance	JSON			11	
	Processor	JSON Path	-	\$.balance	0	
	Value type	Number	•			
ł	Add Processor					

Data collected from the **Legacy Account Details System** service is formatted as XML and requires an X Path **processor** defined on the **Legacy Account Details** resolver to extract a legacy user's total balance:

-	Then apply value processors (1	total)				
-	Extract Total Balance XML					
	Processor	X Path	٠	/legacy/xyz/balance	\diamond	
	Value type	Number	٠			
•	+ Add Processor					

After the decision service pulls in user data from either service, common value processing might be required regardless of where the data comes from. For example, suppose the bank has a 500 USD minimum for an active account and anything above that is available for transfers. The following SpEL processor subtracts 500 from the result of resolver processing to obtain the user's available balance for transfers:

-	Value Processors (1 total)					
	Obtain User's Availa	ble Balance for Tran	nsfers		÷	
	Processor	SpEL	•	#this.value - 500	0	
	Value type	Number	٠			
i	+ Add Processor					

Attribute caching

The policy decision point (PDP) and the PingAuthorize Policy Editor support caching for attributes. The ability to cache resolved attributes can deliver significant performance gains for the PDP.

Carefully consider this concept to ensure optimum configuration.

This section focuses on the individual cache options that you can set at the attribute level. See Configuring Trust Framework attribute caching for development or Configuring Trust Framework attribute caching for production for more information.

Attribute caching can be indefinite or time-limited, with or without the scope of another attribute value:

- With time-limited caching, you set the duration for which the cache lives (Time to Live) before it expires.
- With **Scope** set to an attribute, if the value of that attribute changes, the system invalidates the cache for the attribute you are defining.
 - In the example below, as long as the **sessionId** value remains the same, the value of the attribute you are defining is cached. When the **sessionId** changes, the system invalidates the cache and uses normal resolution.

– Caching				
Cache Strategy	Time Limited Caching with Scc 🔺			
Time to Live (s)	60	Scope	sessionId 🔺	

If the attribute does not exist in the cache, the PDP resolves the attribute automatically by using the appropriate attribute resolvers and then adds it to the cache. All subsequent attribute usages use the cached value until it expires from the cache, which results in another attribute resolution.

) Note

The cache key for a Trust Framework attribute value includes a hash of the values required for it to resolve. If one of these values changes, the cache key automatically becomes invalid. You can think of this arrangement as an aggregation of **Scope** parameters that guard against inconsistencies between your cached values.

Value settings

Every attribute has a defined data type that constrains the set of allowable values and provides a predictable behavior model for value processing and other data transformations.

Catching type inconsistencies early helps with building and testing the Trust Framework. The primary types for accepting data into the system and for producing output data are JavaScript Object Notation (JSON), Extensible Markup Language (XML), and UTF-8 text (known as string). The remaining types are used within the Trust Framework for more fine-grained data processing.

All data types have conversions to and from a canonical String representation. Conversion of other formats, such as alternative date or time representations, requires the use of user-defined value processing. Learn more in **Processors**.

Examples of type conversions when data enters the Policy Decision Point (PDP) include:

- Attribute default values you define in the user interface are textual. The system converts these to the type defined by the attribute before use.
- Attributes might take their values from fields in the decision request, which are textual. The system converts the value to the type defined by the attribute before use.
- The PDP might invoke external services to retrieve data. Typical response formats are JSON, XML and String. JSON Path or XPath value processing can extract components of a response, typically as text, which the system then converts to the types defined by an attribute before use.

Examples of type conversions when exporting data from the PDP include:

- Building a request for a service invocation. Attributes might be request parameters directly or might be used in Attribute interpolation. In both cases, the system uses the canonical conversion to a String format.
- Adding attribute data to statements, either directly or through Attribute Interpolation. Again, the system uses the canonical conversion to String format.
- In all logging and response data that includes attribute values, the system renders those values using their canonical String representations.

The following table lists the data types:

Data type	Description
Boolean	A simple true or false. True can be represented in textual form, such as in default values or decision request parameters, as true, yes, or 1. False can be represented by false, no, or 0. Case is insignificant. In value processing contexts such as SpEL expressions, the value is a java.lang.Boolean instance.

Data type	Description
Number	A numeric value. Decimal integers and reals are supported, including scientific notation. In value processing contexts, the value is a <code>java.math.BigDecimal</code> instance.
Date	A date, such as "23 April 2020." The textual representation is ISO-8601; for example, 2020-04-23. In value processing contexts, the value is a java.time.LocalDate. Date values can be converted to the following types: • Date Time (the time component becomes 00:00:00) • Zoned Date Time (the time zone is assumed to be UTC)
Time	A time of day, such as 4:15 pm and 30 seconds. The textual representation is ISO-8601. The maximum resolution is microseconds. For example, 16:15:30, 16:15:30.783, and 16:1 5:30.783239 are all valid. In value processing contexts, the value is a java.time.LocalTime. Time values cannot be converted to other types.
Date Time	A date and time of day, such as 4:15 pm and 30 seconds on April 23, 2020. The textual representation is ISO-8601. The maximum resolution is microseconds. For example, 2020-04-23T16:15:30 or 2020-04-2 3T16:15:30.783239. In value processing contexts, the value is a java.time.LocalDateTime. Date Time values can be converted to the following types: • Date and Time, dropping the appropriate information in each case. • Zoned Date Time. The time zone is assumed to be UTC.
Zoned Date Time	A date and time of day with a time zone expressed as an offset from UTC. The textual representation is ISO-8601. For example, 2020-04-23T16:15:30.783+01:00. In value processing contexts, the value is a java.time.ZonedDateTime. Zoned Date Time values can be converted to the following types, dropping the appropriate information in each case: Date Time Date Time
Duration	A time duration expressible in seconds or fractions of a second. The textual representation is ISO-8601. For example: • PT3H for 3 hours • PT2M45.836S for 2 minutes and 45.836 seconds In value processing contexts, the value is a java.time.Duration. Duration values cannot be converted to other types.

Data type	Description
Period	A time period expressible in calendric units, such as a number of days or months. The textual representation is ISO-8601. For example: • P9Y for 9 years • P3M2D for 3 months and 2 days In value processing contexts, the value is a java.time.Period. Period values cannot be converted to other types.
JSON	A JSON document. This type is most useful for bringing data into and out of the PDP. It is the only type that is subject to JSON Path value processors. The textual representation is JSON. In value processing contexts, the value is a java.util.Map or java.util.Collection.
XML	An XML document. This type is most useful for bringing data into and out of the PDP. It is the only type that is subject to XPath value processors. The textual representation is XML. In value processing contexts, the value is a org.w3c.Document.
Collection	An ordered collection of other value types. Only valid value types as described here can be members of collections. JSON-formatted arrays are valid textual representations of collections. In value processing contexts, a collection is a java.util.Collection; however, the objects contained are of an internal type. Use only the get() method to retrieve items by zero-based integer index.
String	All other data is interpreted as UTF-8 text, stored internally as UTF-16. In value processing contexts, these values are <code>java.lang.String</code> .

The legacy **Date Time** and **Time Period** types are ambiguous unions of the types described above. They are retained for backward compatibility only. For new Trust Frameworks, use the more specific types.

Default value

You can give attributes an optional default value in the event that the attribute cannot be resolved.

In addition, you can use a default value to encode constant attributes within the Trust Framework by not setting any resolvers and always resolving to the default value.

Secrets

To encrypt an attribute's values in PingAuthorize logs, you can enable secrets for that attribute.

Depending on which mode you have configured PingAuthorize in, these secrets are recorded in one of two logs:

• Embedded PDP mode: The attributes are encrypted in PingAuthorize/policy-decision.log.

• External PDP mode: The attributes are encrypted in the decision-audit.log file distributed with the Policy Editor, but not PingAuthorize/policy-decision.log.

To decrypt an attribute's value, run the following command. In this example, RSNH/SPsNJSFQyyLSxdKsw== represents the encrypted attribute string, and 54655374506153735068526153653939 represents the encryption key in hexadecimal. By default, the encryption key is TeStPaSsPhRaSe99, and cannot be changed.

```
'echo -n "RSNH/SPsNJSFQyyLSxdKsw==" | base64 -d | openssl enc -aes-128-ecb -d -K
"54655374506153735068526153653939"
```

Attribute interpolation

With attribute interpolation, you reference an attribute in a field. The system resolves the value of the referenced attribute, replacing the reference with the value itself.

About this task

You can use attribute interpolation in any field that has the label icon, shown below.



Steps

1. To reference an attribute in one of these fields, type two open curly brackets (\{\{ \ to open the attribute tree menu. Continue typing the full path to the attribute or select each level of the attribute in the attribute tree menu.



2. Complete the reference by typing two close curly brackets (}}) or by selecting the **}** complete expression item from the attribute tree menu.



{{Test.Child

Conditions

Use conditions in PingAuthorize attributes, rules, and policies to define authorization logic by comparing one thing to another. Conditions evaluate to either true or false.

You can compare requests, attributes, constant values, and regular expressions in conditions. Conditions can also serve as targets that define when a policy or rule applies to a decision request. For example, you can target a rule so that it applies when a payment amount is greater than or equal to a payment limit.

Add definitions and torrate and the form				
Add definitions and targets, or drag from Components O All Requests				
/hen				
L ANY NONE CLEAR ALL				
A Policy.Payment Amount	✓ Greater Than Or Equal ✓ A Policy.Payment Limit ✓ International Int			
A Policy.Payment Amount	✓ – Greater Than Or Equal ✓ – A Policy.Payment Limit · · · · · · · · · · · · · · · · · · ·			

When you define a condition, on the left side, select an attribute or request type that represents unknown or variable information to be validated. On the right side, enter known or predefined criteria in the form of an attribute, request, or constant value. This keeps logical statements consistent regardless of what's being compared. You can drag collapsed conditions to change their order, as needed.

You can add conditions directly to **resolvers** and rules or define them on the **Components** tab of the **Library** as reusable **named conditions**.

Condition comparators

You can use the following comparators in condition comparisons.

🕥 Note

For simplicity, the table groups logical comparator pairs together, but you can only use one comparator at a time in a condition.

Attribute comparators

Comparator	Supported data types	Description
Contains Does Not Contain	Collection, String	Checks whether a string or collection contains, or doesn't contain, another string. Use this comparator when you know part of a value that you want to check.
		 Note Matches for strings can differ from matches for collections. For example, the string 1234 contains the constant 23, but the collection [1234] does not contain this constant. One possible matching collection for the constant 23 is [21, 22, 23].
Contains Claim Pair Does Not Contain Claim Pair	String	Add defense in depth by validating token claims as part of the authorization layer. Checks whether a JSON Web Token (JWT) contains a given claim pair. Encrypted tokens are not supported. To create a comparison:
		 Select an attribute of type String that resolves to a JWT. Select the Contains Claim Pair or Does Not Contain Claim Pair comparator. Enter a claim pair using the syntax <claim-name>=<claim-value>.</claim-value></claim-name>
		 Note The claim value has to exactly match one of the possible values of that claim contained in the token. For example, aud=api1 will match against a token containing the claim "aud": "api1" or "aud"=["api1", "api2"].
		To check a multivalued claim, create a comparator for each value you want to check. Multivalued scope claims in the token must be expressed as a list of space-delimited, no-space strings.
Ends With Does Not End With	String	Checks whether a string ends with, or doesn't end with, another string.
Equals Does Not Equal	Boolean, Collection, Date, Date Time, Duration, JSON, Number, Period, String, Time, XML, Zoned Date Time	Checks whether two values are equal or not equal.
Greater Than Less Than	Boolean, Date, Date Time, Duration, Number, String, Time, Zoned Date Time	Checks whether a value is greater than, or less than, another value.

Comparator	Supported data types	Description
Greater Than Or Equal Less Than Or Equal	Boolean, Date, Date Time, Duration, Number, String, Time, Zoned Date Time	Checks whether a value is greater than or equal to, or less than or equal to, another value.
Has Valid Signature For JWKS Has Invalid Signature For JWKS	String, JSON	 Add defense in depth by validating tokens as part of the authorization layer. Checks the following for a JWT: Whether the signature can be verified using one of the public keys in the JSON web key set (JWKS) If a token expiry was set, whether the token is expired A valid token must have a verified signature and not be expired. Note In PingAuthorize 9.3.0.6, both RSA-encoded and EDSCA-encoded signatures are supported. For versions PingAuthorize 9.3.0.5 and earlier, only RSA-encoded signatures are supported. To create a comparison: Select an attribute of type String that resolves to a JWT. Select the Has Valid Signature For JWKS or Has Invalid Signature For JWKS comparator. Select a JSON attribute that resolves to a JWKS.

Comparator	Supported data types	Description
In CIDR Block Not In CIDR Block	String	 Simplify adding network checks to support your zero trust policies. Verifies whether a user's IP address is in, or not in, an IP subnet range. IPv4 and IPv6 addresses are supported. To create a comparison: Select an attribute that resolves to a valid IP address. Select the In CIDR Block or Not In CIDR Block comparator. Enter the IP address range as a constant or select an attribute that resolves to the IP address range. You must express the IP address range in Classless Inter-Domain Routing (CIDR) notation (the bitmask indicates the size of the routing prefix): IP address/bitmask For example, consider a condition that checks for IP addresses between 192.0.2.0 - 192.0.2.15. CIDR notation for this range is 192.0.2.0/28. If the IP address attribute resolves to 192.0.2.1, for example, the condition evaluates to true.
		 P Tip For help expressing an IP address range in CIDR notation, use a CIDR calculator [□].
ls In Is Not In	Collection, String	Checks whether a string or a collection is in, or not in, another collection.
Regular Expression	String	Checks whether a string matches a regular expression.
Starts With Does Not Start With	String	Checks whether a value starts with, or doesn't start with, another value.

Request comparators

Comparator	Description
Matches Does Not Match	Checks whether the inbound request name starts with, or does not start with, the conditional request name.
	ONOTE For Matches to be true, the inbound request name must contain the entirety of the conditional request name. For example, if the conditional domain is BankingChannels.OnlineBanking, a request domain of BankingChannels evaluates to false.

Comparator	Description
Equals Does Not Equal	Checks whether the inbound request equals, or does not equal, the conditional request.

Adding a named condition

Named conditions provide a way to reuse conditional logic across attributes and policies.

About this task

Named conditions can help provide consistency in authorization logic and minimize repetition throughout policies. You can use named conditions as components in more complicated condition expressions.

For example, consider a named condition that compares the account status received in a decision request to a status code to determine if the account is blocked. You can use this condition in multiple policies to check a user's account status.

Details History Test	
الأم Account Blocked	=
Returns true if the account status equals the blocked status code.	
Parent no parent selected	-
- Condition Builder	
ALL ANY NONE CLEARALL	
A Request.Account.Status	• 10
+ Comparison + Named Condition + Group	

Steps

- 1. Click Trust Framework and click the Conditions tab.
- 2. Click the + icon and select Add new Condition.
- 3. Define general information for the named condition:
 - 1. Enter a unique **Name** for the condition.
 - 2. Optional: For Description, enter information that describes the condition's purpose.
 - 3. Optional: To nest the condition under a parent in the tree, in the Parent list, select a parent condition.

Nesting helps group related conditions together. You can move the condition to another location in the tree by selecting a different parent condition.

To remove nesting, click the **Delete** icon and leave the **Parent** blank.

4. To add a comparison to the condition, click **+** Comparison.

Γ	- Condition Builder			
	ALL ANY NONE CLEAR ALL			
	A Select an Attribute	- Equals	C Type in constant value	1
	+ Comparison + Named Condition +	Group		

- 5. Select an attribute to use in the comparison, select a comparator, and then enter a constant or click the **C** icon to select an attribute.
- 6. To next a comparison under another comparison, click **+ Group**.

Subgroups allow more permutations in comparisons. To remove nesting while keeping the comparison, click Ungroup.

- 7. To add a named condition, click **+** Named Condition, select a named condition, and then select is True or False.
- 8. To combine multiple conditions, named conditions, or groups, select one of the following options.

Choose from:

- All: Invokes the condition when all of the conditions are true. If one condition evaluates to false, evaluation stops and the remaining conditions are not executed. This is like adding an AND Boolean operator between conditions.
- Any: Invokes the condition when at least one of the conditions is true. If one condition evlautes to true, evaluation stops and the remaining conditions are not executed. This is like adding an OR Boolean operator between conditions.
- None: Invokes the condition when none of the conditions are true. This like adding a NOT Boolean operator.
- 9. Click Save Changes.

i) Note

You can copy a named condition for reuse by selecting **Make Copy** from the hamburger menu of that condition. If you copy a named condition with children, only the parent is duplicated. You cannot copy a named condition at its point of use in a rule or policy.

Actions

Actions represent arbitrary values that a typical authorization request might ask to perform on a specific resource, such as view or update.

Common actions you might want to configure in the PingAuthorize Policy Editor are:

- inbound-GET
- inbound-PATCH
- inbound-POST
- inbound-PUT
- outbound-GET
- outbound-PATCH

- outbound-POST
- outbound-PUT
- create
- delete
- modify
- retrieve
- search
- search-results

Identity classifications and IdP support

The PingAuthorize Policy Editor provides the ability to generate smart identity classifications.

The purpose of these classifications is to abstract the underlying identity providers (IdPs) from their presumed level of trust. The outcome is that you will be able to build policies that target levels of trust instead of specific IdPs.

Defining trust levels has the following distinct parts:

Identity properties

Use the Identity Properties window to define objects and elements to attach to specific IdPs.

You use these properties later to map IdPs to specific identity classification levels.

Identity providers

Use the Identity Providers window to define different IdPs and to attach identity properties to them.

This task might appear irrelevant when your enterprise expects to use only one or two IdPs, but it provides significant abstraction for more complicated ecosystems in which tens or hundreds of IdPs participate.

Identity classifications

Use the Identity Classes window to create different levels of classification.

For each classification level, attach the properties that an IdP must have to be in that level.

Processors

Use value processing on responses returned from attributes or services to transform the resolved value.

Add a value processor when you create or edit an attribute or service. Alternatively, you can define a value processor to reference by name by going to **Trust Framework** \rightarrow **Processors**.

The PingAuthorize Policy Editor supports these value processors:

Collection filter

- Collection transform
- JSON Path
- X Path
- Spring Expression Language (SpEL)
- Named

You can combine these processors to form a chain of processors.

All processors have a type that indicates what the output data type should be after applying the expression.

You can reorder collapsed value processors by dragging the handles on the left. To reorder using the keyboard, press Tab to go to the processor, press Enter to select the processor, press the up arrow or down arrow to go to the desired location, and press Enter to drop the processor in the new location.

Collection filter

When the data being processed is a collection, you can set a filter to examine each item in the collection and keep only the items that satisfy some condition. A collection filter uses a value processor to yield a true or false for each item in the collection. When true, the original item goes in the resulting collection; when false, it is omitted.

Each item in the collection can optionally be preprocessed by one or more value processors before applying the condition. For example, suppose we received a JSON collection from a service invocation and we want to filter the items by the **score** field. The input data might look like the following lines:

```
[
    { "name": "Alice", "role": "Sender", "score": 72 },
    { "name": "Bob", "role": "Receiver", "score": 36 },
    { "name": "Carol", "role": "Observer", "score": 47 },
    { "name": "Dave", "role": "Attacker", "score": 99 }
]
```

A collection filter processor could achieve this by using a JSON Path preprocessor to extract the score.

\$.score

The following SpEL condition yields a true or false decision for each item.

#this > 50

Each list item is, in turn, passed through the preprocessing and the condition. The first item has a score of 72, which is greater than 50, so the condition yields true and the item is retained for the result collection. The second and third items have scores less than 50, so the condition yields false and these items are omitted. The final item also has a score higher than 50 and is retained. The result of the collection filter is:

```
[
   { "name": "Alice", "role": "Sender", "score": 72 },
   { "name": "Dave", "role": "Attacker", "score": 99 }
]
```

The values produced by the preprocessing and condition are only used to determine inclusion. The final result of a collection filter consists of those original collection items that satisfied the predicate after preprocessing. The following image shows the collection filter in the GUI.

Select items with sco	ore > 50			
Processor	Collection Filter -			
 Apply the following Proce 	ssors to prepare the Collection item	for filtering (1 total)		
Extract score from	m item			
Processor	JSON Path	S.score	\bigtriangledown	
Value type	Number			
Add Processor Define a filter to decide w	hether the item is included in the re	turned Collection		
Check score				
Processor	SpEL -	#this > 50	\bigtriangledown	
This processor must return a Boolean				
The output value type is a Co	ollection			

If the condition or preprocessing produces an error for any item in the input collection (for example, if a score field is missing or is not a number in the source data), the whole collection filter is considered to have failed.

Collection transform

When the data being processed is a collection, you can set a transform to apply a processor or a sequence of processors to each item in the collection.

Assume we have the following input collection:

```
[
   { "name": "Alice", "role": "Sender", "score": 72 },
   { "name": "Bob", "role": "Receiver", "score": 36 },
   { "name": "Carol", "role": "Observer", "score": 47 },
   { "name": "Dave", "role": "Attacker", "score": 99 }
]
```

The following JSON Path processor extracts the name field for each item:

\$.name

The following SpEL processor converts each name to upper case:

```
#this.toUpperCase()
```

Then the resulting collection consists of just the extracted names converted to upper case, preserving the order of the original collection.

["ALICE", "BOB", "CAROL", "DAVE"]

The following image shows the collection transform in the GUI.

Extract names from	records		Ŵ
Processor	Collection Transform 👻		
 Apply the following Proce 	essors to each item in the Collection (2 total)	
- Extract name			Î
Processor	JSON Path 🗸	\$.name	\bigtriangledown
Value type	String -		
Convert to uppe	r case		ŵ
Processor	SpEL -	#this.toUpperCase()	\bigtriangledown
Value type	String -]	
+ Add Processor The output value type is a C	ollection		

If the item processor produces an error for any item, the overall collection transform processor produces an error.

JSON Path

With JSON Path, you can extract data from JSON objects. For example, assume we have a service that resolves to the following JSON:

```
{
    "name": "Joe Bloggs",
    "requestedItems": [
        {
            "id": "b5f963fa-111e-49ff-994b-b89a20a2c1d5",
            "price": 125.00
        },
        {
            "id": "84e204dd-44f5-4a84-8e58-972c2a9c80b4",
            "price": 299.99
        }
     ]
}
```

To extract the price fields of all requested items, we set the value processor to JSON Path with the expression \$.requestedItem s[*].price.

Learn more about JSON Path expressions at https://github.com/json-path/JsonPath^[2].

X Path

XPath is the XML-equivalent of JSON Path and follows a very similar syntax. Learn more about XPath expressions in the XPath tutorial ^C on w3schools.com.

(i) Note

The Policy Editor only supports the use of XPath 1.0^[C]. Functions added in later versions are not available.

SpEL (Spring Expression Language)

With SpEL, you can perform more complicated data processing. Expressions are applied directly to the resolved value. For example, assume you want to search for a substring that matches the following regular expression:

```
\[[0-9]*\.[0-9]\]
```

Set the processor to SpEL and set the expression to the following text:

```
matches([[0-9]*.[0-9]])
```

Use curly brackets to interpolate attributes directly into the SpEL expression, which can be useful if you want to combine multiple attribute values into a single value. Learn more in Attribute interpolation.

```
{{Customer.Age}} - {{State.Drinking Age}} >= 0
```

You can concatenate interpolated attributes with strings in SpEL expressions. In the following example, a SpEL expression is used to dynamically concatenate a string with a user's account number to create a transaction verification message:

```
"Account " + {{Customer.AccountNumber}} + " has been charged."
```

🕥 Note

Be careful not to wrap an interpolated attribute with quotes.

Learn more about SpEL in the Spring Framework^[] documentation.

Learn more about the Java classes available for SpEL processing in Configuring SpEL Java classes for value processing.

Named

Use named value processors to create reusable value processing logic.

Extracting this logic into reusable components helps abstract some of the complexity when you define an attribute or a service. Also, it reduces repetition.

You can still create inline value processors that co-exist with named value processors.

To define a named value processor that you can reference, go to **Trust Framework** → **Processors**.

Chained value processors

You can chain processors together to combine data preprocessing steps.

For example, you can extract data using JSON Path and then apply a SpEL processor to the extracted data. Suppose you have a service response that resolves to the following JSON:

```
{
	"name": "Joe Bloggs",
	"city": "London",
	"country": "UK"
}
```

Suppose you want to extract the country data and transform the value to United Kingdom, whenever the current value is UK. You would add a JSON Path processor to extract the country value, followed by a SpEL expression to transform the value:

-	- Value Processors (2 total)				
	Country JSONPath				
	Processor	JSON Path	•	\$.country	\bigcirc
	Value type	String	•		
	Country Conversion SpEL				
	Processor	SpEL	•	#this == 'UK' ? 'United Kingdom' : #this	V
L	Value type	String	-		
+1	+ New Processor				

You can make a chained processor reusable by creating it as a named processor. That way, you can implement even more complex processing by using named processors as the building blocks.

Copying Policy Editor entities

To build your authorization logic more quickly and accurately, you can make editable copies of many of your Policy Editor entities.

About this task

Within the **Policies** and **Trust Framework** pages, you can copy whole definitions, policies, rules, statements, and **Library** entities. See the following table for page-specific capabilities and limitations.

Policy EditorPolicy Editorpage	Capabilities and limitations	
Trust Framework	 You can copy any definition. You can't copy a portion of a definition, such as a resolver. Copy the whole definition to duplicate any of its content, or manually copy the element between definitions. When you copy a definition that contains child definitions, only the parent definition is duplicated. You can't copy definition hierarchy trees. 	
Policies	 You can copy any policy, rule, or statement. You can't copy policy sets. You can't copy targets, conditions, or properties within a policy or rule. When you copy policies containing rules, targets, or statements belonging to the Library, these entities get reused in the new policy, not copied. When you copy rules or statements within a policy, you must save the policy. 	
Library	 On the Library tab, you can copy top-level Library rules, targets, and statements. You can also copy statements within rules. You can't copy targets within rules. You can copy Library rules and statements at their point of use. When you make copies of Library entities within rules or policies, the copies display at the point of use and on the Library tab. Where relevant, the copying capabilities and limitations listed for the Policies page apply to Library entities. 	
Trust Framework, Policies, and Library	 You can't use Make Copy in the tree structure view. You must save any unsaved changes to an entity before making a copy. 	

Steps

1. To create a copy of a Policy Editor entity, click **Make Copy** in the hamburger menu.

Ping	g Ping Authorize			Welcome admin (PingAuthorize Tutorials)
		Definitions Target Search		
>\$	Branch Manager	Domains Services Attributes Identity Classes Id	dentity Providers Identity Properties Actions Conditions Processo	rs
4	Trust Framework	•	Details History Test	
Ē	Policies	🔻 🚫 Gateway	🟷 BasePath	=
	Test Suite	BasePath		🔓 Copy ID to clipboard
	API Reference	🏷 TrailingPath		🔓 Make Copy 🔥
	HttpRequest			🔒 Copy full name to clipboard
		impactedAttributes Meme game answer rating	Delete Attribute	∂ Get link to here es
		Nome Game invitees		Add repetition settings

Result:

The Policy Editor creates a duplicate of the entity and its contents. The new duplicate's name is formed by adding the prefix **[Copy of]** to the original name, as in the following image.

Pin	g PingAuthorize			Welcome admin (PingAuthorize Tutorials)
		Definitions Target Search		
>\$	Branch Manager	Domains Services Attributes Identity Classes Id	dentity Providers Identity Properties Actions Conditions Processors	
4	Trust Framework	+	Details History Test	
B	Policies	🔻 🚫 Gateway	🏷 [Copy of] BasePath	Ξ
<u>19</u>	Test Suite	Copy of] BasePath		
	API Reference	S BasePath	The portion of the HTTP request URI that matches the API Endpoint's	inbound-base-path value.
		 TrailingPath HttpRequest 		li
		S impactedAttributes	Delete Attribute	불 Save changes
		Nome game answer rating		

2. Optional: Make edits to the new entity.

Trust Framework testing

The PingAuthorize Policy Editor provides testing capabilities for applicable definition types.

To prepare a test request, select a definition of type Attribute or Service and go to the Test tab.

To form a request, select the following main elements:

- Domain
- Service
- ۰IdP
- Action
- Attributes

If the information endpoints that your attribute resolvers require are running, click **Execute**. If your endpoints are not running or are otherwise unavailable, as is often the case in development, use the **Overrides** section to provide stubbed values for attributes and services that might be required during the evaluation process. This step overrides the attribute and service resolution and uses the specified values instead.

After the system evaluates the request, you will see the following set of result tabs:

Request

Shows the actual JSON request sent to the decision engine

Response

Contains the complete (high verbosity) response for the decision

Output

Provides a summary of the decision

Attributes

Contains an expandable list of all attributes executed as part of the test

Services

Contains an expandable list of all services executed as part of the test

Testing repeating attributes

Repeating attributes are resolved from values in a specified collection. A repeating attribute requires a repetition source that points to a collection. Also, to get its values from each repetition of the collection, the repeating attribute's resolver must be set to **Current Repetition Value**. When you properly configure a repeating attribute, you can test it the same way you test regular, nonrepeating attributes.

The **Output** tab in the test results will show results for each matching value from the collection. The results are ordered with indices that reflect the order of resolution.

For more information about these variables, see Repeating policies and attributes.

Viewing dependents

Before you change an entity, check what depends on that entity so that you do not introduce unintended consequences.

Steps

- 1. Select the Trust Framework entity.
- 2. Click the hamburger menu to the right of the entity name.

3. Click View Dependents.

The following image shows the scope attribute.

Definitions Target Search				
Domains Services Attributes Identity Classes Id	dentity Providers Identity Proper	ties Actions Conditions Proces	sors	
+	Details History Test			
🕆 🚫 Gateway	🏷 scope		=	
 BasePath TrailingPath HttpRequest AccessToken 	The list of scopes granted to	o this token.	 Copy ID to clipboard Copy full name to clipboard Copy full name to clipboard 	
access_token	Parent	HttpRequest.AccessToken	Add repetition settings	
 active audience 	 Resolvers (1 total) 		 Expand top level containers Collapse top level containers 	
 client_id expiration issued at 	• Attribute - Access	Token	So View Dependents	
Sissuer not_before	+ Add Resolver			
Scope	 Value Processors (1 total 	l)		

If the entity has dependents, they are displayed in a new window. For example, the following image shows the dependents for scope .

Used by (2 in total)	×
☑ Permitted SCIM scope for user	
☑ Token does not contain PDP scope	9

(i) Note

Any entity restricted by self-governance will be omitted from the list of dependents. See Self-governance for more information.

Policy management

The PingAuthorize Policy Editor provides the tools to implement attribute-based access control and dynamic authorization management, allowing you to govern the use of your organization's services and data.

The Policy Manager, located on the **Policies** page, enables you to build policies that answer the question "Should this resourceaccess request be permitted or denied?"

In a traditional role-based access control (RBAC) system, this question might instead be "Who is the user making the access request, and have they been assigned a role that is permitted access to the resource?" Although you can model such a policy, the PingAuthorize Policy Editor functions essentially as an attribute-based access-control (ABAC) system. In such a system, the question can be rephrased as:

Given the facts that I know about the user, the resource being accessed, what the user wants to do with the resource, how sure I am that the user is who they say they are, and any other pertinent facts about the world at this point in time, should the user's access request be permitted, and must anything else be done in addition to permitting or denying access?

The length of that question speaks to the inherent power of the Policy Editor. Fortunately, the Policy Manager makes harnessing this power straightforward.

Policy sets, policies, and rules

The Policy Manager reflects the structure of grouping rules for attribute-based access control (ABAC) with three types of entities and the relationship between them. The entities are policy sets, policies, and rules.

A typical enterprise-level organization might impose hundreds or thousands of conditions and constraints around access control. Such constraints comprise the business rules that define the circumstances under which users access certain protected resource.

You can group these rules together naturally, so that you can understand them without focusing on all of them at the same time. For example, a set of policies around authentication might require a user to authenticate to a certain level before they can access a certain resource. Another set of policies might gather together all of the business rules around accessing the resources of a particular business unit. Yet another set of policies might define the audit processes triggered with each attempt to access a set of restricted resources.

This structure is inherent in the problem domain of resource-access control. The Policy Manager allows you to organize these business rules into a tree structure, with a root policy set that contains policy sets for each business case. The policy sets contain related policies, and each policy contains one or more rules that help define its behavior.

🕥 Note

A root policy set is not required, but it is useful for building a deployment package from the entire policy tree. Individual policies often belong to policy sets but can also stand on their own.

Creating policies and policy sets

Create policies and policy sets to define the circumstances under which users access specific resources.

Steps


- 1. Click Policies.
- 2. Click **+**.
- 3. Select Add Policy Set or Add Policy, as appropriate.

You can name policies and policy sets anything you like. However, you should use relevant and contextual names, especially as the policy tree grows larger and more complex. When naming policies, consider the business rule that they are trying to model and verify that the names represent the operational policies of the organization.

4. Update the policy to include targets, statements, and other changes.

- 5. Optional: Use Properties to add metadata to the policy or policy set in the format of a key-value pair.
 - 1. Click + next to **Properties**.
 - 2. Click Add Property and enter a key-value pair.
- 6. Optional: Select the Disable check box to disable your policy or policy set.

If you disable the policy, it is not evaluated and produces a **Not Applicable** decision. When you disable it, the policy is shown as crossed out in the policy tree.



7. Click Save changes.

After you create a policy, you can modify it to be a repeating policy. For more information, see **Repeating policies and attributes**.

Example

In the following example, the policy name is My Basic Policy. Because the name has been changed, you see a red dot in the upper-right corner. This dot indicates that the policy contains unsaved changes. If you try to leave the page, a modal opens and prompts you to save your changes.



Adding targets to a policy


Add targets to identify the requests to which the policy applies its fine-grained authorization logic. If no targets are attached to a policy, the policy applies to all requests. To make a policy only apply for all requests to a certain database, for example, add the database domain as a target.

Steps

- 1. Go to the policy where you want to add targets.
- 2. Click the + next to Applies to.
- 3. In the left pane, click **Components**.

The list of components includes the items you created in the Trust Framework. Drag the appropriate domains, services, identity classes, and actions from the components to the **Applies to** target section on the policy.

For example, to target **Mobile Banking** requests, drag that domain in. To target all banking groups, add the **Banking Channels** domain, which is the parent of the **Online Banking** and **Mobile Banking** domains. Because the top level is also a target, this step adds a total of three targets.



4. Click Save changes.

Example

The following example features three domains because the **Banking Channels** definition is the parent of the other definitions. Logically, applying an OR operation within the definition type selects one of the channels.

The following graph shows how the server evaluates the group of targets.

Domains: 🚨 Banking Channels 🔤 🕻	CR Lanking Channels. Mobile Banking 🗵	OR Lanking Channels.Online Banking
	AND	
Services: 📀 Internal.Service Bus 🗵		
	AND	
Actions: 🕘 Execute Transaction 🖂 O	R 🚺 View 🖾	

Conditional targets (Applies to)

You can use conditional targets to extend the capability of the "Applies to" concept when creating attribute-based access control (ABAC) rules and policies.

Conditional targets extend the capability of the "Applies to" concept because they:

- Permit the interweaving of targets with other conditional logic.
- Allow standalone logic to determine if and when a policy or rule applies.

To enable this functionality, click **Applies to** and then **When**.

You can include the following types of conditions in a logical expression:

- Attribute comparison Allows the comparison of an attributes with another attribute or with a constant.
- Request comparison Allows the matching of incoming requests by answering questions like "Is the requested service equal to Banking.Payment ?"
- Named condition Click + Named Condition to show a Named Condition drop-down list that displays named conditions.

The following image provides an example. See Conditions for more information.

All Requests Add definitions and	l targets, or drag from Components	
ALL ANY NONE CLEAR ALL Image: A Risk.Combined Score	- Greater Than - C 100	
R Service	 ✓ Matches ✓ Banking.Payment 	•

You can navigate conditions using the Up Arrow and the Down Arrow to move between members of a group or using the Left Arrow and Right Arrow to move in and out of nested groups.

You can reorder conditions by dragging the handles on the left. To reorder using the keyboard, press Tab to go to the condition, press Enter to select the condition, press the Up Arrow or Down Arrow to go to the desired location, and press Enter to drop the condition in the new location.

To switch between Attribute Comparison mode and Request Comparison mode, click **A** and **R**, respectively, to the left of the comparator.



Statements

A statement is a directive that instructs the policy enforcement point (PEP) to perform additional processing in conjunction with an authorization decision.

When a policy is applied to a request or response, the policy result might include one or more statements. Statements allow the PEP—PingAuthorize Server, in this case—to do more than allow or deny access to an API resource. For example, a statement can:

- · Cause the removal of a specific set of fields from a response
- Provide details about the reason for denying access to a user

You can add a statement directly to a single policy or rule and modify that statement as part of a policy definition. You can also add a statement in **Components** for use with multiple policies or rules.

Code	RSK_CHK			
Applies To	Indeterminate	Applies If	All decisions in path match	•
Payload	Customer with account ID {{Customer.Account ID}} requires addition	nal risk checkir	ng.	\bigtriangledown
Attributes	Customer.Risk Score 🗵 🕓 Customer.Account Ba	alance ×	Customer.Account ID ×	🔓 Drag in an Attribute
Services	🕞 Drag in a Service			

Each statement contains the following mandatory fields:

Name

Human-readable label for reference in the Policy Manager

Code

Identifier that distinguishes between different types of statements

Applies To

Type of decision to which the statement is attached

Applies If

Condition under which the statement is returned in the decision response

(i) Note

If the **Applies To** criteria for a statement is met by its associated rule or policy decision, and that decision contributes to the final result, PingAuthorize uses the statement in its final response if the statement's associated **Applies If** condition is satisfied. Select an option to exercise precise control over when a qualifying statement gets returned in a decision response, which can make it easier to provide reasons for both **permit** and **deny** decisions and risk evaluation feedback.

Statements carry additional data in the form of payloads and attributes:

- The optional field **Payload** can consist of static or interpolated data.
- The Attributes field lets you return a key-value mapping of attributes that might be relevant to the statement.

To indicate that the final decision applies only if a statement can be fulfilled, mark the statement as **Obligatory**. Typically, the service that calls PingAuthorize Server handles this responsibility.

You can reorder collapsed statements by dragging the handles on the left. To reorder using the keyboard, press Tab to go to the statement, press Enter to select the statement, press the Up Arrow key or Down Arrow key to go to the desired location, and press Enter to drop the statement in the new location.

The following table identifies significant statement properties.

Property	Description
Name	Friendly name for the statement.

Property	Description
Obligatory	 When marked as Obligatory, the statement must be fulfilled as a condition of authorizing the request: If PingAuthorize can't fulfill an obligatory statement, it fails the operation and returns an error to the client application. If PingAuthorize can't fulfill a non-obligatory statement, the server logs an error, but the client's requested operation continues.
Code	Identifies the statement type. This value corresponds to a statement ID that the PingAuthorize configuration defines.
Applies To	 Specifies the decision types that should include the associated statement with the result. Available types include: Applicable: This is the default option. Select Applicable if the statement should apply to any of the following decision types. Permit Deny Permit or Deny Indeterminate
Applies If	 Specifies how the statement propagates through the decision tree and whether it is returned in the overall decision response. Available options include: All decisions in path match: The statement is returned when the decision for the rule or policy with which the statement is associated matches all decisions in the path. For example, when the decision for a rule with which the statement is associated is permit, and all decisions in the path are permit, the statement is returned. This is the default option. Final decision in path matches: The statement is returned when the decision for the rule or policy with which the statement is associated matches the overall decision. For example, when the decision for the rule with which the statement is associated is permit, and the overall decision is permit, the statement is returned even if there are deny decisions in between. All decisions in path are applicable: The statement is always returned, unless an error occurs in the associated decision.
Payload	Set of parameters governing the actions that the statement performs when PingAuthorize applies the statement. The appropriate payload value depends on the statement type.

PingAuthorize Server supports all of the **provided statement types** except for custom statements. To develop **custom statement types**, use the PingAuthorize Server SDK.

(i) Note

Many statement types let you use the JSONPath expression language to specify JSON field paths. To experiment with JSONPath, use this JSONPath evaluator \square .


Provided statements

The PingAuthorize Policy Editor comes with preconfigured statement types that are also in PingAuthorize Server.


Policy writers can use the following provided statements out of the box, and PingAuthorize Server fulfills the statements as documented:

- Add Filter
- Combine SCIM Search Authorizations
- Denied Reason
- Exclude Attributes
- Filter Response
- Include Attributes
- Modify Attributes
- Modify Headers
- Modify Query
- Modify SCIM Patch
- Regex Replace Attributes

To view the set of provided statement types within the Policy Editor, click **+** Add Statement.



You can hover over a statement type to view its description.



Selecting a statement type prepopulates the **Description** and **Code** fields and provides an example **Payload** value. Most users replace the example **Payload** value with one that is appropriate for their policy.

-	Statements (1	total)			
-	Enter a name				Obligatory 🗌 🚍
		that can be used to add administrator-re strictions on the resources that may be re			
	Code	add-filter			
	Applies To	Applicable -	Applies If	All decisions in p	ath match 🗸
	Payload	Example: employeeType eq "intern"			\bigtriangledown
_		•			
+	Add Statement				

The following sections describe the statement types built into PingAuthorize Server.

Add Filter

Use add-filter to add administrator-required filters to System for Cross-domain Identity Management (SCIM) search queries.

Description	Details
Applicable to	SCIM
Additional information	The Add Filter statement places restrictions on the resources returned to an application that can otherwise use SCIM search requests. The filters that the statement specifies are AND ed with any filter that the SCIM request includes. The payload for this statement is a string that represents a valid SCIM filter, which can contain multiple clauses separated by AND or OR. If the policy result returns multiple instances of the Add Filter statement, they are AND ed together to form a single filter that passes with the SCIM request. If the original SCIM request body included a filter, it is AND ed with the policy-generated filter to form the final filter value.

Combine SCIM Search Authorizations

Use combine-scim-search-authorizations to optimize policy processing for SCIM search responses.

Description	Details
Applicable to	SCIM
Additional information	By default, SCIM search responses are authorized by generating multiple policy decision requests with the retrieve action, one for each member of the result set. The default mode enables policy reuse but might result in greater overall policy processing time. When you use this statement type, the current SCIM search result set is processed using an alternative authorization mode in which all search results are authorized by a single policy request that uses the search-results action. The policy request includes an object with a single Resources field, which is an array that consists of each matching SCIM resource. Statements that the policy result returns are applied iteratively against each matching SCIM resource, allowing for the modification or removal of individual search results. This statement type does not use a payload. For more information about SCIM search handling, see About SCIM searches.

Denied Reason

Use **denied-reason** to allow a policy writer to provide an error message that contains the reason for denying a request.

Description	Details
Applicable to	DENY decisions
	Note The Denied Reason statement only applies to SCIM searches using the optimized search response authorization mode.
Additional information	The payload for Denied Reason statements is a JSON object string with the following fields: status - Contains the HTTP status code returned to the client. If this field is absent, the default status is 403 Forbidden. message - Contains a short error message returned to the client. detail (optional) - Contains additional, more detailed error information. The following example shows a possible response for a request made with insufficient scope: {"status":403, "message":"insufficient_scope", "detail":"Requested operation not allowed by the granted OAuth scopes."}

Exclude Attributes

Use exclude-attributes to specify the attributes to exclude from a JSON response.

Description	Details
Applicable to	PERMIT decisions, although you cannot apply Exclude Attributes statements directly to a SCIM search. Also, do not use this statement type with SCIM modifies. Instead, use the Modify SCIM Patch statement type.
Additional information	The payload for this statement is a JSON array of strings. Each string is interpreted as a JSONPath into the response body of the request being authorized. Each JSONPath can select multiple attributes in the object. The portions of the response that a JSONPath selects are removed before sending the response to the client. The following example instructs PingAuthorize Server to remove the attributes secret and data.private. ["secret", "data.private"] For more information about the processing of SCIM searches, see Filter Response.

Filter Response

Use filter-response to direct PingAuthorize Server to invoke policy iteratively over each item of a JSON array contained within an API response.

Description	Details		
Applicable to	PERMIT decisions from the gateway, although you cannot apply Filter Response statements directly to a SCIM search. However, the SCIM service performs similar processing automatically when it handles a search result. For every candidate resource in a search result, the SCIM service makes a policy request for the resource with an Action value of retrieve.		
Additional information	 When presented with a request to permit or deny a multivalued response body, Filter Response statements allow policies to require that a separate policy request be made to determine whether the client can access each individual resource that a JSON array returns. The following list identifies the fields of the JSON object that represents the payload for this statement. Path JSONPath to an array within the API's response body. The statement implementation iterates over the nodes in this array and makes a policy request for each node. This field is required. 		
	Value to pass as the action parameter on subsequent policy requests. If no value is specified, the action from the parent policy request is used. This field is optional. Service Value to pass as the service parameter on subsequent policy requests. If no value is specified, the service value from the parent policy request is used. This field is optional.		
	ResourceTypeType of object contained by each JSON node in the array, selected by the subsequent policy request, the contents of a single array element pass to the policy decision point as an attribute with the name that this field specifies. If no value is specified, the resource type of the parent policy request is used. This field is optional.		
	On each policy request, if policy returns a deny decision, the relevant array node is removed from the response. If the policy request returns a permit decision with additional statements, the statements are fulfilled within the context of the request. For example, this statement allows the policy to decide whether to exclude or obfuscate particular attributes for each array item. For a response object that contains complex data, including arrays of arrays, this statement type can descend through the JSON content of the response.		
	Note Performance might degrade as the total number of policy requests increases.		

Include Attributes

Use include-attributes to limit the attributes that a JSON response can return.

Description	Details
Applicable to	PERMIT decisions, although you cannot apply Include Attributes statements directly to a SCIM search. Also, do not use this statement type with SCIM modifies. Instead, use the Modify SCIM Patch statement type.

Description	Details
Additional	The payload for this statement is a JSON array of strings. Each string is interpreted as a JSONPath into the response body of the request being authorized. The response includes only the portions that one of the JSONPaths selects. When a single JSONPath represents multiple attributes, the response includes all of them. If the policy result returns multiple instances of Include Attributes statements, the response includes the union of all selected attributes.
information	For more information about the processing of SCIM searches, see Filter Response.

Modify Attributes

Use modify-attributes to modify the values of attributes in the JSON request or response.

Description	Details	
Applicable to	All, although you can't apply the Modify Attributes statement directly to a SCIM search. Also, do not use this statement type for SCIM modify operations. Instead, use the <mark>Modify SCIM Patch</mark> statement type.	
Additional information	The payload for this statement is a JSON object. Each key-value pair is interpreted as an attribute modification on the request or response body of the request being authorized. For each pair, the key is a JSONPath expression that selects the attribute to modify, and the value is the new value to use for the selected attribute. The value can be any valid JSON value, including a complex value such as an object or array. A null value removes the attribute from the body. Key-value pairs that do not already exist are added to the body, unless the value is null. Format: { "\$.jsonPath": "attributeValue" }	

Modify Headers

Use **modify-headers** to modify the values of request headers before PingAuthorize sends them to the upstream server or to modify the values of response headers before PingAuthorize returns them to the client.

Description	Details
Applicable to	All, although you cannot apply the Modify Headers statement directly to a SCIM search.

Description	Details
Additional information	The payload for this statement is a JSON object. The keys are the names of the headers to set, and the values are the new values of the headers. A value can be:
	 Null, which removes the header A string, which sets the header to that value An array of strings, which sets the header to all of the string values
	If the header already exists, PingAuthorize overwrites it. If the header does not exist, PingAuthorize adds it (unless the value is null). If a payload value is an array of strings:
	 Given a header that supports multiple values, such as Accept, PingAuthorize repeats the header for each string in the array. Given a header that does not support multiple values, such as Content-Type, PingAuthorize sends the last string in the array.

Modify Query

Use **modify-query** to modify the query string of the request sent to the API server.

Description	Details
Applicable to	All

Description	Details
Additional information	The payload for this statement is a JSON object. The keys are the names of the query parameters that must be modified, and the values are the new values of the parameters. A value can be one of the following options:
	null
	The query parameter is removed from the request.
	String
	The parameter is set to that specific value.
	Array of strings
	The parameter is set to all of the values in the array.
	If the query parameter already exists on the request, it is overwritten. If the query parameter does not already exist, it is added. For example, consider the following request made to a proxied API:
	curllocationrequest GET '{{apiPath}}/directory/v1/{{dn}}/subtree? searchScope=wholeSubtree&limit=1000' \ header 'Authorization: Bearer {{jwtToken}}'
	You can set a policy to limit certain groups of users to request only 20 users at a time. A payload of λ
	<pre>{"limit": 20} causes the request to be rewritten as follows:</pre>
	curllocationrequest GET '{{apiPath}}/directory/v1/{{dn}}/subtree? searchScope=wholeSubtree&limit=20' \ header 'Authorization: Bearer {{jwtToken}}'

Modify SCIM Patch

Use **modify-scim-patch** to add operations to a SCIM patch in a modify request before it is submitted to the store adapter.

Description	Details	
Applicable to	SCIM requests with an action of modify	

```
Additional
                  The payload for this statement is either a JSON array or a JSON object.
information
                  If the payload is an array, PingAuthorize treats it as a list of operations in the SCIM patch format to add to
                  the end of the operations in the patch. For example, assume the modify has the following patch.
                      {
                        "schemas": ["urn:ietf:params:scim:api:messages:2.0:PatchOp"],
                       "Operations": [
                         {"op": "replace", "path": "name.formatted", "value": "John Doe"}
                        1
                      }
                  Also, assume the statement payload is as follows.
                     [
                       {"op": "add", "path": "name.first", "value": "John"},
                       {"op": "remove": "path": "name.last"}
                     1
                  Then the resulting request to the store adapter looks like this.
                      {
                       "schemas": ["urn:ietf:params:scim:api:messages:2.0:PatchOp"],
                       "Operations": [
                         {"op": "replace", "path": "name.formatted", "value": "John Doe"},
                         {"op": "add", "path": "name.first", "value": "John"},
                         {"op": "remove", "path": "name.last"}
                       1
                      }
                  If the payload is an object, PingAuthorize interprets it as a set of new replace operations to add to the end
                  of the operations in the patch. In these replace operations, the keys from the object become the paths to
                  modify, and the values from the object become the values for those paths. For example, assume the modify
                  has the following patch.
```

```
{
    "schemas": ["urn:ietf:params:scim:api:messages:2.0:PatchOp"],
    "Operations": [
        {"op": "replace", "path": "name.formatted", "value": "John Doe"}
    ]
}
```

Also, assume the statement payload is as follows.

{"name.first": "John", "name.last": "Doe"}

Then the resulting request to the store adapter looks like this.

Description	Details
	<pre>{ "schemas": ["urn:ietf:params:scim:api:messages:2.0:PatchOp"], "Operations": [{"op": "replace", "path": "name.formatted", "value": "John Doe"}, {"op": "replace", "path": "name.first", "value": "John"}, {"op": "replace", "path": "name.last", "value": "Doe"}] </pre>

Regex Replace Attributes

Use **regex-replace-attributes** to specify a regex to search for attributes in a request or response body and replace their values with a regex replacement string.

Description	Details			
Applicable to	All, although you cannot apply the Regex Replace Attributes statement directly to a SCIM search.			
Additional information	The payload for this statement is either a JSON object or an array of JSON objects. Each object represents a single replacement operation and has up to four keys. The following list describes these keys:			
	"regex"			
	Represents the regular expression to use to find the attribute values to replace. This key is required.			
	"replace"			
	Represents the regex replacement string to use to replace the attribute values with a new value. This key is required.			
	"path"			
	A JSONPath expression that represents the nodes to start searching under. The expression can po to objects, arrays, or strings in the body. This key is optional.			
	"flags"			
	A string that contains the regex flags to use. Recognized flags include: • "i"			
	Performs case-insensitive matching.			
	• "1"			
	Treats the "regex" value as a literal string. • "c"			
	Performs "canonical equivalence" matching.			
	PingAuthorize replaces any portion of the attribute value that matches the regular expression in the "regex " value in accordance with the "replace" replacement string. If multiple substrings within the attribute value match the regular expression, PingAuthorize replaces all occurrences. The regular expression and replacement string must be valid as described in the API documentation for the java.util.regex.Pattern class, including support for capture groups.			

Example

For example, consider the following body.

```
{
    "id":5,
    "username":"jsmith",
    "description":"Has a registered ID number of '123-45-6789'.",
    "secrets":{
        "description":"Has an SSN of '987-65-4321'."
    }
}
```

Also, consider the following payload.

```
{
    "path":"$.secrets",
    "regex":"\\\d{3}-\\\d{2}-(\\\d{4})",
    "replace":"XXX-XX-$1"
}
```

Applying the statement produces the following body with a changed "secrets.description" value.

```
{
    "id":5,
    "username":"jsmith",
    "description":"Has a registered ID number of '123-45-6789'.",
    "secrets":{
        "description":"Has an SSN of 'XXX-XX-4321'."
    }
}
```

Custom statements

In addition to the statement types that are available out of the box in the PingAuthorize Policy Editor, policy writers can use a custom statement that leverages the PingAuthorize Server SDK.

For information about the implementation and configuration of such statements, see the **PingAuthorize Server Administration Guide**.

After configuring the statement properly, you can use it in a policy by selecting **Custom Statement** from the **Create new Statement** drop-down list.

Rules and combining algorithms

Policies can include one or more rules to produce a fine-grained authorization decision of Permit, Deny, Indeterminate, or Not Applicable.

To evaluate the overall decision of a policy, the policy decision point (PDP) applies a combining algorithm. The default algorithm that is set on a new policy is **The first applicable will be the final decision**. This algorithm stops evaluating as soon as it reaches a decision that is not **Not Applicable**.

The following table identifies available combining algorithms and describes their effects. The charts show one example of a decision evaluation for each combining algorithm; other evaluation paths are possible. The chart legend is displayed before the table. The first column in each chart represents the overall decision returned by the policy. The second column represents child decisions that produce the resulting policy decision.



Combining algorithm	Summary	Details
PermitUnlessDeny	Unless one decision is deny, the decision is permit.	The policy defaults to Permit unless any of its children produce the decision Deny . The evaluation of rules stops as soon as a Deny is produced.
DenyUnlessPermit	Unless one decision is permit, the decision is deny.	The policy defaults to Deny unless any of its children produce the decision Permit . The evaluation of rules stops as soon as a Permit is produced.
PermitOverrides	A single permit overrides any deny decisions.	If any children produce the decision Permit , the policy returns Permit and stops evaluating rules. If no Permit is generated, all rules are evaluated; also, the policy returns Indeterminate if a child produces Indeterminate . Otherwise, the policy returns Deny if a child produces Deny . If none of the previous situations occur, the policy returns No t Applicable .

Combining algorithm	Summary	Details
DenyOverrides	A single deny overrides any permit decisions.	If any children produce the decision Deny, the policy returns Deny and stops evaluating rules. If no Deny is generated, all rules are evaluated; also, the policy returns Indeterminate if a child produces Indeterminate. Otherwise, the policy returns Permit if a child produces Permit. If none of the previous situations occur, the policy returns Not Applicable.
FirstApplicable	The first applicable decision is the final decision.	Evaluates the children in turn until one produces an applicable value of Permit , Deny , or Indeterminate . If the evaluation produces no applicable decisions, the policy returns Not Applicable .
OnlyOneApplicable	Only one child can produce a decision. If more than one child produces a decision, the result is indeterminate.	Evaluates the children in turn. If at any point two children produce a decision other than Not Applicable , the policy returns Indeterminate . Otherwise, if precisely one child produces an applicable decision, the policy uses it. If the evaluation produces no applicable decisions, the policy returns Not Applicable .
DenyUnlessThreshold	Permit if the weighted average of applicable child decisions meets the threshold; otherwise deny.	Assigns the policy's children weights between 0 and 100. If a child returns Permit , the weight is added to a running total. If a child returns Deny , the weight is subtracted from the running total. After evaluating all children, the PDP divides the total by the number of children and compares that average against the threshold. If the average is greater than or equal to the threshold, the policy returns Permit . Otherwise, the policy returns Deny .

Rule structure

Policy rules power the fine-grained access control capability of PingAuthorize. Rules contain logical conditions that evaluate to true or false.

When you create a rule, you set the conditions and criteria that dictate when the rule applies and how the rule evaluates. The rule structure begins with the **Applies to** criteria, which define the conditions under which the rule applies.

Applies to

By default, rules target all requests with no conditions. You can leave this default criteria in place, if desired. You can also add targets, set a condition, or include a group of conditions. If the **Applies to** criteria are not met, the rule effect is **Not Applicable**.

(i) Note

The **Applies to** criteria are always enabled, whether shown or hidden. When there are **Applies to** criteria that are not met, the effect is always **Not Applicable**, regardless of which effect type is selected.

Effect

Whether you choose to change the **Applies to** criteria or not, you must give each rule one of the following effects:

- Permit
- Deny
- Permit if condition holds, otherwise deny
- · Deny if condition holds, otherwise permit

If the Applies to criteria evaluate to true, the Permit and Deny effects cause the rule to permit or deny, respectively.

The following example includes an Applies to condition and a Permit effect:

- If the condition evaluates to true, the rule permits.
- If it evaluates to false, the effect is Not Applicable.

If the example included a **Deny** effect instead, the rule would deny when the **Applies to** condition evaluated to true.

escription		
Applies to		
🕒 Add	efinitions and targets, or drag from Components O All Requests	
– When	Y NONE CLEAR ALL	
Is Using	Mobile Banking App - is True	• 🗊
+ Compa	ison + Named Condition + Group	
Effect		
Effect	Permit	•

To configure a rule to permit or deny based on how its **Effect** conditions evaluate, choose one of the following effect types:

- The **Permit if condition holds, otherwise deny** effect causes the rule to permit if the conditions are met and to deny if the conditions are not met.
- The **Deny if condition holds, otherwise permit** effect does the opposite, causing the rule to deny if the conditions are met and to permit if the conditions are not met.

í	Note
	Effect conditions are hidden until you select one of the if condition holds effect types.

- <u>О</u> Тір
- When a logical condition involves comparing two attributes, try to ensure the attributes have the same data type. Comparing different data types requires an implicit conversion that might not always yield the intended result.
- Just as with Trust Framework entities, you can check which entities depend on a policy or policy set.

The following example includes a **Permit if condition holds**, **otherwise deny** effect without any **Applies to** criteria:

- If the group Effect condition evaluates to true, the rule permits.
- If the group condition evaluates to false, the rule denies.

When there are no Applies to criteria, the rule always permits or denies.

escription		
Effect		
Effect	Permit if condition holds, otherwise deny	•
1	IV NONE CLEAR ALL	•
-: A	Mobile Banking App.Payment.Amount Less Than Or Equal C 1000	• 1
	parison - + Named Condition - + Group	

🔿 Тір

Rules with conditional effects display two effect icons in the rule header. The icon for the **if condition holds** effect displays on the left and is larger than the icon for the **otherwise** effect.

Rule order

When a policy has multiple rules, rule order can affect the way the policy evaluates. You can reorder collapsed rules by dragging the handles on the left. To reorder rules using the keyboard, do the following:

- 1. Press Tab to move the cursor to a rule. When the cursor is positioned on the entire rule, a blue box displays and the rule changes color to purple.
- 2. Press Enter to select the rule. When a rule is selected, it changes color to dark green.
- 3. Press the Up Arrow or Down Arrow to move the cursor to the desired location.
- 4. Press Enter to drop the selected rule in the new location.

Policy testing

The PingAuthorize Policy Editor provides testing capabilities to evaluate test authorization requests against any or all policy nodes.

To specify the nodes to test policies against, select the root node from the tree on the left side of the page.

In the following example, the evaluation runs against all policies because the root policy set is selected.

D root policy set					
Testing Scenario					
Request	=				
Domain	Select to add Domain to the testing scenario -				
Service	Select to add Service to the testing scenario -				
Identity Provider	Select to add Identity Provider to the testing scenario				
Action	Select to add Action to the testing scenario				
Attributes	Select an attribute to add it to the testing scenario				
Overrides					
Attributes	Select an attribute to add it to the testing scenario -				
Services	Select a service to add it to the testing scenario -				
	Import Execute				

Select the following main elements to form a request:

- Domain
- Service
- IdP
- Action

If the information endpoints that your attribute resolvers require are running, click **Execute**. If your endpoints are not running or are otherwise unavailable, as is often the case in development, use the **Overrides** section to provide stubbed values for the attributes and services that might be required during evaluation. This step overrides the attribute resolution and uses these values instead.


After a request is evaluated, you will see the following set of result tabs:

- Request Shows the actual JSON request sent to the policy engine.
- Response Contains the complete, high-verbosity response for the decision.

(i) Note

If the same comparison condition is attached to more than one rule in the policy subtree, the decision response only includes evaluation of the first occurrence of this condition. Despite only appearing once in the response, the decision service evaluates this condition wherever it is needed to make a decision. If the parent policy of the first instance of this condition is not applicable to the request, the decision response does not include evaluation of any rule containing this condition. This behavior is the same regardless of the rule's outcome (Permit, Deny, Not Applicable).

- Attributes Contains an expandable list of the attributes executed as part of the test.
- Services Contains an expandable list of the services executed as part of the test.
- Visualisation Contains a visual representation of the decision tree.
- Output Provides a summary of the decision.



Visualizing a policy decision response

When you develop and test policies in PingAuthorize, examine the decision flow and other details about recent decisions to make sure the decision service is evaluating policies according to your expectations.

Steps

- 1. In the Policy Editor, go to **Policies > Decision Visualizer**.
- 2. Select a decision to visualize.

Choose from:

- $\,\circ\,$ Select a recent decision.
 - 1. In the **Decision Visualizer**, click the **Recent Decisions** tab.
 - 2. Select a recent decision from the list.

🕥 Note

You can control the number of decisions that appear in the **Recent Decisions** list. Learn more in **Setting the request list length for Decision Visualizer**. To visualize self-governance decisions, sign on as a self-governance administrator and click **Self Governance** instead of **Recent Decisions**.

• Copy and paste a decision response from the policy decision log.


介 Important

To visualize a policy decision log entry, you must add either the decision-tree or the evaluation-log view to the Decision Response View. Learn more in **Configuring the Decision Response View**.

- 1. In the <PingAuthorize>/logs/policy-decision.log file, copy the decision response JSON object.
- 2. In the Decision Visualizer, click the Paste Logs tab.
- 3. Paste the decision response JSON object.
- 4. Click Visualise.

Result

An interactive decision tree of your policies is displayed.



3. Examine the decision flow to make sure decisions are evaluated according to your expectations.

You can click any box in the flow to show more details.

- 4. Click the other tabs for additional details.
 - **Request** tab: Shows the JSON request sent to the decision service, allowing you to confirm that the expected information was sent.
 - **Response** tab: Shows the complete, high-verbosity response for the decision.

(i) Note

If the same comparison condition is attached to more than one rule in the policy subtree, the decision response includes only the evaluation for the first instance of this comparison. Although the condition is included only once in the response, the decision service evaluates the condition wherever it is needed to make a decision.

If the parent policy of the first instance of this condition isn't applicable to the request, the decision response doesn't include evaluation of any rule containing this condition. This behavior is the same regardless of the rule's outcome (**Permit**, **Deny**, **Not Applicable**).

- **Output** tab: Shows details about the decision, including the time it took to evaluate policies and rules.
- Attributes tab: Shows details about the attributes used in the decision.
- $\,\circ\,$ Services tab: Shows details about the services used in the decision.

Repeating policies and attributes

Use repeating policies and attributes to evaluate a policy multiple times—once for each item in a collection.

For example, assume the Accounts attribute contains a list of accounts associated with a customer. You want to filter access to the accounts based on the account type. With repeating policies, a decision is made for each item in the Accounts attribute, returning statements for each account that is permitted.

Repeating policies

To make a policy repeat, from the hamburger menu, select Add repetition settings.

🕥 Note

You can only add repetition settings to an existing policy. The hamburger menu to add these settings does not appear when you are creating a new policy.

E Filter accounts by type	Disabled
	Copy ID to clipboard
	 Get link to here Add repetition settings
Applies to	+ Expand top level containers
Rules (2 total)	 Collapse top level containers
Combining Algorithm The first applicable decision will be the final decision	•

The policy repetition settings are as follows:

Apply this policy to each item of

This specifies the collection attribute to repeat over, referred to as the repetition source.

Filtering by

This represents the decision and any attached statement to filter by.

The following example uses the Accounts attribute and Permit decision. In this case, the policy applies to every item in the Accounts collection attribute. The policy keeps each result that returns Permit.

Ē	Filter accounts by type	🌒 Disabled 🗌 🗮
-	Repetition Settings	
	Apply this policy to each item of Accounts	
	Filtering by Permit	•
+	Applies to	
-	Rules (2 total)	
	Combining Algorithm The first applicable decision will be the final decision	•

When you define rules and statements for a repeating policy, you can use:

- Attributes with no repetition source
- Attributes with the same repetition source as the policy

Repeating attributes

To make an attribute repeat, from the hamburger menu, select Add repetition settings.

Yc	ote ou can only add repetition settings to an existing attribute. The ham opear when you are creating a new attribute.	burger menu to add these settings does not
🏷 Details		=
Description		Copy ID to clipboard Copy full name to clip
Parent	Accounts.Account	Add repetition settings
+ Resolvers (0 t	total)	Expand top level containers Collapse top level containers

- + Value Processors (0 total)
- Value Settings

The attribute repetition settings are as follows:

• Repeat for each item of

This specifies the attribute to repeat over, referred to as the repetition source.

(i) Note

If you set this field, you can only use the attribute in repeating policies. However, the attribute can then resolve against attributes repeating against the same collection. The attribute can still resolve against attributes that do not have this field set.

• Resolvers, Value Processors, Caching

For a resolver, if **Resolver type** is **Current Repetition Value**, resolution is against individual items in the collection itself.

For information about these items, see Resolvers, Processors, and Attribute caching.

You can use repeating attributes in named conditions and value processors. If an attribute uses a named condition or value processor, any repeating attributes referenced in the condition or value processor must have the same repetition source as the attribute itself. If a policy uses a named condition, any repeating attributes referenced in the condition must have the same repetition source as the policy itself.

Policy solutions

This section recommends how to implement commonly needed business rules in policy.

- Use case: Using consent to determine access to a resource
- Use case: Using consent to change a response
- Use case: Using a SCIM resource type or a policy request action to control behavior
- Restricting the modification of attributes

Use case: Using consent to determine access to a resource

PingAuthorize can provide attribute-based access control to a specific protected resource based on the resource owner's consent to share.

Examples of resources include:

- Health care records shared with a spouse (an individual)
- · Banking records shared with a known third party, such as an asset-monitoring tool
- Purchase history shared with an anonymous third party, possibly for improved promotional offers

In this scenario, we continue using the meme games API used in Getting started with PingAuthorize (tutorials). Assume my friend has crafted several funny memes that she wants to share with me. When my browser or app requests her memes, PingAuthorize enforces access based on her consent to share.

We first set up some Trust Framework attributes and services and then create a policy that uses those items to check consent and then permit or deny access. The following topics cover these tasks.

- 1. Getting a path component from the request URL
- 2. Getting the requestor identifier from the access token

- 3. Searching for consent granted by resource owner to requestor
- 4. Getting consent status from the consent record
- 5. Creating a policy to check consent and then permit or deny access

Getting a path component from the request URL

For this use case, the resource owner is given in the URL for the meme game API. To get the owner requires pulling the corresponding path component from the request URL.

Before you begin

This procedure assumes you have created a meme game API server named meme-game, similar to the one shown in the "Configure an API External Server for the Meme Game API" step in Configuring a reverse proxy for the Meme Game API.

About this task

In general, you can configure PingAuthorize to control access based on the path component that best suits your needs. For example, consider the /purchases/1234 path. The purchases component is a class of resources, while 1234 is a specific resource for a given purchase.

The meme game API has URLs of the form meme-game/api/v1/users/user.0/answers. The user.0 path component is a specific resource owner. The following steps explain how to get the specific resource owner from a request URL.

Steps

1. In the PingAuthorize administrative console, create a new gateway API endpoint.

A Gateway API Endpoint controls how PingAuthorize Server proxies incoming HTTP client requests to an upstream API server.

1. In the administrative console, click **Configuration** and then **Gateway API Endpoints**.

2. Click New Gateway API Endpoint.

- 3. For Name, specify meme-game user_answers.
- 4. For Inbound Base Path, specify /meme-game/api/v1/users/{UserFromUrl}/answers.

The inbound base path defines the base request path for requests to be received by PingAuthorize Server.

Using the curly braces (\{ and }) around a string creates an item with the name given by the string so that we can refer to it later. That notation also preserves the item to pass along in the next step.

5. For Outbound Base Path, specify /api/v1/users/{UserFromUrl}/answers.

The outbound base path defines the base request path for requests that PingAuthorize Server forwards to an API server.

6. For API Server, specify meme-game. This is the API External Server you defined previously.

7. For Service, specify meme-game.user_answers.


You will use this service in the PingAuthorize Policy Editor to get a value to define an attribute.

The following image shows this configuration.

Ping Identity.	PingData Administra	tive Console			
Configuration	Sc DG / Configuration	/ Gateway API Endpoints /			
Status		API Endpoint			
	General Configuration				
Name * meme-game user_answers		meme-game user_answers			
Description					
	Error Template	If no error template is specified, then a default error			
	Correlation ID Header	The correlation-id-response-header property of the HTTP Connect			
	Inbound Base Path *	/meme-game/api/v1/users/{UserFromUrl}/answers			
	Outbound Base Path *	/api/v1/users/{UserFromUrl}/answers			
API Server * meme-game X • I • • • • • • • • • • • • • • • • • • •		meme-game 🗙 - 🖍 + 📀			
		Policies			
	Service	meme-game.user_answers			

8. Save your changes.


2. Send a test request to the gateway to see how PingAuthorize handles the request. The following request uses Postman.



3. Check the request in the Policy Editor.

Go to **Policies** in the left pane and then click **Decision Visualiser** along the top. Under **Recent Decisions**, click the **Refresh** icon. Select the decision and click **Request**.

In the request, the attributes include a Gateway object. Items set in the gateway API endpoint in the previous step are in this Gateway object. One of the items in the object is UserFromUrl, providing the exact path component we want. The following image shows the Gateway object.



- 4. Create an attribute to pull UserFromUrl from the object.
 - 1. Go to **Trust Framework** and then click **Attributes** along the top.
 - 2. From the + menu, select Add new Attribute.
 - 3. For the name, replace **Untitled** with Users identifier from the URL.
 - 4. Click the + next to **Resolvers** and click + Add Resolver.
 - 5. Set Resolver type to Attribute and select the Gateway attribute.
 - 6. Click the + next to Value Processors and click + Add Processor.
 - 7. Set Processor to JSON Path to pull an item from a JSON object and specify a value of \$.UserFromUr1.

The following image shows this configuration.

		Definitions T	arget Search				
>\$	Branch Manager	Domains Services	Attributes Identity Classes	Identity Providers Identity	Properties Actions Condit	tions Processors	
4	Trust Framework	+		Details History Test			
	Policies	> 🚫 Gateway		🏷 Users identifier fro	m the URL		
$\langle \rangle$	API Reference	> 📏 HttpRequest					
		impactedAtt > SCIM2	ributes	Description			
		S TokenOwner		Parent	no parent selected		
		🚫 Users identif	ier from the URL	 Resolvers (1 total) 			
			 Attribute - Gateway Resolve attribute using 				
·				Resolver type A	ttribute	•	Gateway
			+ Add Resolver				
				 Value Processors (1 t) 	otal)		
				Untitled JSON Pa	th Processor		
				Processor	JSON Path 👻	\$.UserFromUrl	
				Value type	String -		
				+ Add Processor			
				📋 Delete Attribute			

8. Click Save changes.

5. Test the new attribute.

- 1. Click **Test** just above the attribute name.
- 2. Pass in a gateway object that uses UserFromUrl.

In the **Request**, set **Attributes** to **Gateway** and specify a value of \{"UserFromUrl":"user.0"}.

The next image shows the test setup.

>\$	Branch Manager	Definitions Target Search Domains Services Attributes Identity Classes	Identity Providers Id	dentity Properties Actions C	Conditions Processors	
-4	Trust Framework	+	Details History Te	ist		
	Policies Stateway	> 🚫 Gateway	Users identifie	er from the URL		
		 SCIM2 	Request			
		Source TokenOwner	Domain	Select to add Domain to the testing scenario		
			Service	Select to add Service to the testing scenario		
			Identity Provider	Select to add Identity Provider to the testing scenario		
			Action	Select to add Action to the testing scenario		
			Attributes	S Gateway	{"UserFromUrl": "user.0"}	
				Select an attribute to add	it to the testing scenario	
		1	Overrides			
			Attributes	Select an attribute to add it to the testing scenario		
			Services	Select a service to add it to	o the testing scenario	

3. Click Execute.

The test result should be user.0.

Result

The Users identifier from the URL attribute is available for use in policies.

Getting the requestor identifier from the access token

We need the requestor identifier to check whether the resource owner has given the requestor access to the resource.

About this task

The PingAuthorize Policy Editor provides many attributes, including HttpRequest.AccessToken. The HttpRequest.AccessToken. subject attribute has the needed information.

Steps

• Be prepared to use the HttpRequest.AccessToken attribute in a later step.

Searching for consent granted by resource owner to requestor

Using the resource owner information from the Users identifier from the URL attribute, we need to determine what consent the owner has granted to a given requestor.

About this task

This task is useful for:

• Resource sharing or delegation where consent is granted to an individual (based on the collaborator claim)

• Data sharing where consent is granted to a third party (based on the audience claim)

This task uses the Trust Framework HTTP service to pull a claim from a request.

Steps

1. Make sure you understand the body of the request that you are pulling a claim from.

The following Postman image shows a request being made to a directory server. The consent definition is in the request URL and has the form share-meme-game-answers&subject=user.0&collaborator=user.1. The resource owner is given by the subject, and the person being shared with is given by the collaborator.

We use the Consent Admin account for the service. In Postman, for **Authorization**, we use **Basic Auth** with the username **Consent Admin** and its password.

The consent record is for the PingDirectory Consent API, but you can use other consent stores. We use this consent record to determine who a resource owner has given consent to.

ilter	Pass Create consent to share game ansi GET Get consent by user.0 to share	·× + ···		
Collections	► Get consent by user.0 to share with user.1			
5				
-+	GET + https://pingdirectory:18443/consent/v1/consents?d	efinition=share-meme-game-answers&subject=us	er.0&collaborator=user.1	
Brokerage				
l request	Params Authorization Headers (1) Body Pre-requ	est Script Tests		
Cerner FHIR				
request	TYPE	Username	Consent Admin	
	Basic Auth *			
Chris Postman L		Password	********	
8 requests	The authorization header will be automatically generated when you			
	send the request. Learn more about authorization		Show Password	
Clover				
8 requests	Preview Request			
Consent				
10 requests				
	Body Cookies Headers (5) Test Results			SI
DG HowTo				
7 requests	Pretty Raw Preview JSON *			
Get user.0 answe	1 - 1			
	2 - "_embedded": {			
Get game 1 answ	3 - "consents": [
Create consent t	4- {			
Get all consent d	5- "_links": { 6- "localization": {			
Get all consent d		nadi nactoru: 18442/consent/u//defi	nitions/share-meme-game-answers/localizations/en-US",	
Get en-US localiz	8 "hreflang": "en-US"	ngutrectory.10445/consent/v1/dert	nectons/share-meme-game-answers/tocallzactons/en-os-,	
Get consent by u	9 },			
	10 - "self": {			
Get consent as u		ngdirectory:18443/consent/v1/cons	ents/3a5cc5d9-29c3-40b6-bced-f9a79c05e3d3"	
DG Training	12 },			
13 requests	13- "definition": {		and the second sec	
a reducers		ngdirectory:18443/consent/v1/defi	nitions/share-meme-game-answers"	
Epic FHIR	15 } 16 }.			
requests	16 }, 17 "id": "3a5cc5d9-29c3-40b6-b	ced-f9079c95e3d3"		
	18 "status": "accepted",	cea isarseeses ,		
OpenBanking	19 "subject": "user.0",			
6 requests	20 "subjectDN": "uid-user.0.ou	-people.dc-example.dc-com".		
	21 "actor": "user.0".			

- 2. Copy the request URL to use in defining a Trust Framework service in the Policy Editor.
- 3. Sign on to the Policy Editor.
- 4. Create Trust Framework attributes for the Consent Admin account credentials.

This is the Consent Admin account we used with Postman. We will create attributes for the username and password and then use those attributes when we define the Trust Framework HTTP service.

1. Go to Trust Framework and click Attributes.

- 2. From the + menu, select Add new Attribute.
- 3. For the name, replace Untitled with ConsentService and click Save changes.

This attribute will serve as a parent to the username and password attributes and will help organize the attributes.

4. From the + menu, select Add new Attribute.

Because the **ConsentService** attribute is selected, the new attribute is a child to it.

5. For the name, replace **Untitled** with **Username**, set **Default value** to **Consent Admin**, select the **Secret** option, and then click **Save changes**.

The following image shows this configuration.

		Definitions Target Search				
	Branch Manager	Domains Services Attributes Identity Classes Identity Providers Identity Properties Actions Conditions Processors				
4	Trust Framework	+ Details History Test				
 ✓ ✓ ✓ 	Trust Framework Policies Test Suite API Reference	ConsentService Conse	Details History Text Image: Consent Service End of the service - Resolvers (0 total) + Add Resolver + Add Parent Resolver • Value Processors (0 total) - Value Settings Default value Image: Consent Admin	•		
			Type String - Secret			
			- Caching			
			Cache Strategy No Caching +			
			Delete Attribute	🖹 Save changes		

- 6. From the + menu, select Add new Attribute.
- 7. For the name, replace **Untitled** with **Password**, set **Default value** to **Consent Admin**, select the **Secret** option, and then click **Save changes**. Selecting the **Secret** option keeps the item out of logs.

5. Create the HTTP service.

- 1. Click Services along the top.
- 2. From the + menu, select Add new Service.
- 3. For the name, replace Untitled with Search for consent to share game answers.
- 4. Set Service Type to HTTP.
- 5. Set **URL** to the request URL.

In this case, the URL is https://pingdirectory:18443/consent/v1/consents?definition=share-meme-game-answers&subject=user.0&collaborator=user.1^[2].

6. Set Authentication to Basic.

This setting requires a username and password. We will use the attributes we just created.

1. Set Username to ConsentService.Username.

- 2. Set Password to ConsentService.Password.
- 7. This setup uses a self-signed certificate, so set Server (TLS) to No Validation.

(!)	Caution
	This case is for a development environment only. Do not use this setting for other environments.

8. Under Value Settings, set Type to JSON.

The following image shows this configuration.

		Definitions Target Search												
>\$	Branch Manager	Domahs Services Attributes Identity Classes Identity Providers Identity Properties Actions Conditions Processors												
4	Trust Framework	•	Details History Test	Petade History Test										
	Policies API Reference	> 🔅 meme-game	Service Type	нттр										
		🔅 SCIM2	HTTP Settings											
		 Search for consent to share game answers 	URL	https://pingdirectory:18443/consent/v1/consents?definition	-share-meme-game-answi	rs&subject=user.0&collaborator=user.1	0							
			HTTP Method	GET -	Content Type	application/json	•							
			Body				0							
			Authentication	Basic										
			Usemame	ConsentService.Username •	Password	ConsentService.Password	• 8							
			Headers											
			+ Header											
			Certificate Validation											
										Server (TLS)	No Validation •			
			Client (M-TLS)	0										
			Value Processors (0 total	0										
			+ Add Processor											
			- Value Settings											
			Туре	JSON -	Secret	0								
			Delete Service				📩 Save changes							

9. Click Save changes.

6. Test the service.

1. Click Test above the Search for consent to share game answers service name.

2. Click Execute.

The results should include a consents array.

	Definitions Target Search	
Branch Manager	Domains Services Attributes Identity Classes	Identity Providers Identity Properties Actions Conditions Processors
Trust Framework	•	Details History Test
Policies	→ 🔅 meme-game	Search for consent to share game answers
API Reference	* PDP	Testing Scenario Test Results ×
	SCIM2	Output Request Response Attributes Services
	 Search for consent to share game answers 	
		Result type: JSON DOCUMENT
		<pre>{"_embedded":{"consents":[{"_links":{"localization":{"href":"https://</pre>

So the service works with hard-coded values: subject=user.0&collaborator=user.1. We need to use parameters in place of the subject and collaborator values so that the service works for anyone using the API.

7. Click **Details** above the service name to update the service definition to replace the values with parameters.

In the URL field, replace the collaborator value, which is user.1. Delete user.1 and type two open curly braces
 (\{\{\}). Use the pop-up that appears to choose the HttpRequest.AccessToken.subject attribute. Recall from
 Getting the requestor identifier from the access token that this attribute specifies the requestor. The resource
 owner must have a consent record for the requestor to grant access.

With this change, the URL changes from

https://pingdirectory:18443/consent/v1/consents?definition=share-meme-game-answers&subject=user. 0&collaborator=user.1^[]

to

https://pingdirectory:18443/consent/v1/consents?definition=share-meme-game-answers&subject=user. 0collaborator=\{\{HttpRequest.AccessToken.subject}\^[2]

2. Click Save changes.

3. Test the change by clicking **Test**, in the **Request** section, setting **Attributes** to HttpRequest.AccessToken.subject, specifying a value such as \{"sub":"user.1"}, where user.1 has a consent record in your consent store, and clicking **Execute**.

The result should include a consents array. Repeat the step for a user who does not have a consent record to verify that those results do not include a consents array.

4. Click **Details** to replace the subject value with a parameter.

The subject is the resource owner. Recall from Getting a path component from the request URL that we have that information in the Users identifier from the URL attribute. Using curly braces to interpolate that attribute, the URL becomes:

https://pingdirectory:18443/consent/v1/consents?definition=share-meme-game-answers&subject=\{\{Users identifier from the URL}}&collaborator=\{\{HttpRequest.AccessToken.subject}}

5. Click Save changes.

6. Test this change the same way you tested the previous change: using two users, where one has a consent record and one does not.

In the **Overrides** section, set **Attributes** to **Users identifier from the URL** with the value specifying the resource owner, which is user.0 in this case.

8. Update the service to pull only the first consent record from the response instead of the entire response.

The response starts with

\{"_embedded":\{"consents":[\{_links":"localization":

We want to pull the first consent record for the user, which starts after the square bracket ([).

- 1. Click **Details** to return to the service definition.
- 2. Click the + next to Value Processors and click + Add Processor.
- 3. Set Processor to JSON Path with a value of \$._embedded.consents[0].
- 4. Set Value type to JSON.

For an example, see the following image.

		Definitions Target Search						
	Branch Manager	Domains Services Attributes Identity Classes	Identity Providers Identity Pro	operties Actions Co	onditions	Processors		
-4	Trust Framework	+	Details History Test					
	Policies	> 🔅 meme-game	Client (M-TLS)					
API Reference PDP SCIM2 Consent to share game	 Value Processors (1 tota 	1)						
		answers	Untitled JSON Path Processor					
			Processor	JSON Path	• \$e	embedded.consents[0]		
			Value type	JSON	•			
			+ Add Processor					
			 Value Settings 					
			Туре	JSON		•	Secret	

5. Click Save changes.

6. Test the change by clicking Test, in the Request section, setting Attributes to HttpRequest.AccessToken.subject, and specifying a value such as {"sub":"user.1"}, where user.1 has a consent record in your consent store. Then in the Overrides section, set Attributes to Users identifier from the URL with the value specifying user.0 again, and click Execute.

Result

The service returns only the user's first consent record. With the record isolated, you can pull the given requestor's status from the record.

Getting consent status from the consent record

This task defines an attribute that uses a service to get a consent record and then uses a processor to pull the consent status from that record.

Steps

- 1. Sign on to the Policy Editor.
- 2. Go to Trust Framework and click Attributes.
- 3. From the + menu, select Add new Attribute.
- 4. For the name, replace **Untitled** with **Sharing consent status**.
- 5. Click the + next to **Resolvers**.
- 6. Click + Add Resolver.
- 7. Set Resolver type to Service with a value of Search for consent to share game answers.
- 8. Click the + next to Value Processors.
- 9. Click + Add Processor.
- 10. Set Processor to JSON Path with a value of \$.status.

11. Set Value type to String.

The following image shows this configuration.

		Definitions Target Search					
>	Branch Manager	Domains Services Attributes Identity Classes	Identity Providers Iden	ntity Properties Actions Condi	tions Processors		
-4	Trust Framework	+	Details History Test				
1 4)	Policies API Reference	 ▷ ConsentService ▷ Gateway 	- Resolvers (1 total)				
		Construction of Astronomy Construction of	 Service - Searce Resolve attribut 	-	consent to share game answers 9		
		Sharing consent status TokenOwner	Resolver type	Service		Search for consent to	share game answers
S Users identifier from the URL							
			+ Add Resolver	(1 total)			
			Untitled JSON	Path Processor			
			Processor	JSON Path 🔹	\$.status		
			Value type	String -			
			+ Add Processor - Value Settings				
			Default value				
			Туре	String	•	Secret	

12. Click Save changes.

Result

The Sharing consent status attribute is available for use in policies.

Creating a policy to check consent and then permit or deny access

Using the Trust Framework attributes and services we created, we now create a policy for the meme game API to get a user's answers. The policy permits access if consent exists and the consent status is **accepted**.

Steps

1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.

The following steps create a policy under an existing policy called **meme-game policies**. This existing policy is for all requests to the meme game.

- 2. Select the existing meme-game policies policy.
- 3. From the + menu, select Add Policy.
- 4. For the name, replace Untitled with Requests for a user's answers.
- 5. Click the + next to Applies to.
- 6. Click Add definitions and targets, or drag from Components and add the meme-game.user_answers service, which we set up in Getting a path component from the request URL. Also add the inbound-GET action.

7. Set Combining Algorithm to Unless one decision is permit, the decision will be deny.

8. Add a rule so that a user can access their own answers.

- 1. Click + Add Rule.
- 2. For the name, replace Untitled with Permit a user to request their own answers.
- 3. Click **+ Comparison**.
- 4. From the **Select an Attribute** list, select **Users identifier from the URL**, which we also set up in **Getting a path** component from the request URL.
- 5. In the second field, select **Equals**.
- 6. In the third field, click the **C** to toggle to an **A** (for attribute) so that you can select the **HttpRequest.AccessToken.subject** attribute.

The following image shows this configuration.

escription		
Applies to		
🔒 Add d	efinitions and targets, or drag from Components O All Requests	
- When		•
+ Compa		•
Effect		
Effect	Permit	-

7. Click Save changes.

9. Test the rule.

The following image shows a test with Postman making a request to the user.0 answers as user.0. The response shows the rule works.

GET	 https://pingdatagovernance:28443/meme-game/api/v1/users/user.0/answers 	
Params Aut	thorization Headers (1) Body Pre-request Script Tests	
TYPE	Token	{"active": true, "sub": "user.0"}
Bearer Token		(, , ,
	on header will be automatically generated the request. Learn more about authorization est	
Body Cookies Pretty Rav		
1 - {		
2 - "	data": [
3 -	{	
4 5	"id": "1", "type": "answers",	
6 -	"attributes": {	
7	"url": "https://i.imgflip.com/2fm6x.jpg",	
8 -	"captions": [
9	"Still waiting for the bus to Jennie's"	
10],	
11	"rating": null,	
12	"created_at": "2020-05-06T22:25:06+00:00"	
13	1	
14	},	
15 • 16	i "id": "2",	
10	"type": "answers",	

If we try again with user.1, the request is denied. Even though user.1 does have a consent record in our consent store, the policy does not do anything with that consent record. We need another rule to look at the consent record and get the status from that record.

10. Add a rule to get status from a consent record.

1. Click + Add Rule.

- 2. For the name, replace Untitled with Permit if resource owner gave consent to share answers.
- 3. Click + Comparison.
- 4. From the **Select an Attribute** list, select **Sharing consent status**, which we set up in **Getting consent status from** the consent record.
- 5. In the second field, select Equals.
- 6. In the third field, type accepted.
 - This value is the status to check against.
 - The following image shows this rule.

Permit a user to request their own answers	Disabled 🗌 📕
Permit if resource owner gave consent to share answers	Disabled 🗌 📒
Description	
 Applies to 	
Add definitions and targets, or drag from Components O All Requests	
– When	
ALL ANY NONE CLEAR ALL	
A Sharing consent status - Equals - C accepted + Comparison + Named Condition + Group	
- Effect	
Effect Permit	•
Hide "Applies to" Show Statements Show Properties	

7. Click Save changes.

11. Test the policy with both rules in place now.

A request to the user.0 answers as user.1 should now work.

However, a request to the user.0 answers as a user without a consent record, say user.2, is denied.

The user.2 request is denied because of the combining algorithm, **Unless one decision is permit**, **the decision will be deny**. When the policy engine evaluates the policy rules, the **Permit a user to request their own answers** rule does not produce a permit because user.2 is not requesting their own answers. The **Permit if resource owner gave consent to share answers** rule uses the **Sharing consent status** attribute. Because user.0 does not have a consent record for user. 2, there is no consent status and the policy engine cannot evaluate the rule. So this rule also does not produce a permit. Thus, the combining algorithm produces a deny for the user.2 request.

If user.0 revokes the consent given to user.1, the status in the consent record becomes **revoked**. The rule no longer applies, so user.1 requests are then denied.

Use case: Using consent to change a response

PingAuthorize can change a server response based on the resource owner's consent to share.

This feature is useful for:

- Data control
- Information security
- Resource management

Again, we continue using the meme games API used in Getting started with PingAuthorize (tutorials).

We first set up some Trust Framework attributes and services to provide consent status. Then we create a policy with rules that use the consent status to include, exclude, or modify attributes in the response. The following topics cover the Trust Framework tasks. If you completed Use case: Using consent to determine access to a resource, you have already finished the tasks of setting up Trust Framework attributes and services. Those tasks are the same for both use cases.

- 1. Getting a path component from the request URL
- 2. Getting the requestor identifier from the access token
- 3. Searching for consent granted by resource owner to requestor
- 4. Getting consent status from the consent record
- 5. What is different for this use case is the policy itself. The following topic explains how to add rules with statements to include, exclude, or modify attributes in the response.

Creating a policy to check consent and then change the server response

Creating a policy to check consent and then change the server response

Using the Trust Framework attributes and services we created, we now create a policy for the meme game API to get a user's answers and change the server response with various statements based on the consent status.

About this task

Here is a snippet of an unedited response. It shows the id, type, and attributes attributes.

```
{
    "data": [{
        "id": "1",
        "type": "answers",
        "attributes": {
            "url": "https: //l.imqflip.com/2fm6x.jpq",
            "captions": ["Still waiting for the bus to Jennie's"],
            "rating": null,
            "created_at": "2020-05-e6T22:25:06-00:00"
        }
},
```

Steps

- 1. Sign on to the Policy Editor, click Policies in the left pane, and then click Policies along the top.
- 2. Select the existing meme-game policies policy. The new policy is created under this policy.
- 3. From the + menu, select Add Policy.
- 4. For the name, replace Untitled with Control user's response to answers request.
- 5. Click + next to Applies to.
- 6. Click Add definitions and targets, or drag from Components and add the meme-game.user_answers service, which we set up in Getting a path component from the request URL. Also, because we want to control the response to the client, add the outbound-GET action.

- 7. Set Combining Algorithm to Unless one decision is deny, the decision will be permit.
- 8. Add a rule to include attributes.
 - 1. Click + Add Rule.
 - For the name, replace Untitled with If consent to share status is accepted then include attributes.
 - 2. Specify the condition.
 - 1. Click + Comparison.
 - 2. From the **Select an Attribute** list, select **Sharing consent status**, which we created in **Getting consent status from the consent record**.
 - 3. In the second field, select **Equals**.
 - 4. In the third field, type accepted.
 - 3. Specify the statement.
 - 1. Click Show Statements.
 - 2. Click + next to Statements.
 - 3. Click + Add Statement → Include Attributes.

Use this statement to be explicit about which attributes to keep, especially when you have a large set of attributes where you only need a small subset in the response.

For information about this statement, see Include Attributes.

- 4. For the name, replace Untitled with Include id and attributes attribute.
- 5. In the Code field, enter include-attributes.
- 6. From the Applies To list, select Permit.
- 7. In the **Payload** field, enter the following text to include the **id** attribute and the **attributes** attribute but not the **type** attribute.
 - ["data[].id","data[].attributes.*"]
- 8. Click Save changes.

The following screen shows the rule.

S If consent to share status is accepted then include attributes	Disabled 🗌 🚍
Description	
Applies to	
Add definitions and targets, or drag from Components	
- When ALL ANY NONE CLEARALL	
A Sharing consent status	ŝ
Effect	
Effect Permit	•
Statements (1 total)	
Include id and attributes attribute	Obligatory
+ Add Statement	
ide "Applies to" Hide Statements Show Properties	

With the policy in place, trying the request again gets a response with the **type** attribute removed, as shown in the following snippet.

```
{
    "data": [{
        "attributes": {
            "url": "https: //l.imqflip.com/2fm6x.jpq",
            "captions": ["Still waiting for the bus to Jennie's"],
            "rating": null,
            "created_at": "2020-05-e6T22:31:06-00:00"
        "id": "1",
        }
},
```

9. Add a rule to exclude attributes.

- 1. Click + Add Rule.
 - 1. For the name, replace **Untitled** with If consent to share status is revoked then exclude attributes.
 - 2. Specify the condition.
 - 1. Click + Comparison.
 - 2. From the **Select an Attribute** list, select **Sharing consent status**, which we created in **Getting consent status from the consent record**.
 - 3. In the second field, select **Equals**.
 - 4. In the third field, type revoked.

- 3. Specify the statement.
 - 1. Click Show Statements.
 - 2. Click + next to **Statements**.
 - 3. Click **+** Add Statement → Exclude Attributes.

Use this statement to be explicit about which attributes to leave out. For example, a third-party client might request banking records; the client does not need account numbers, so give them everything but the account number.

For information about this statement, see Exclude Attributes.

- 4. For the name, replace **Untitled** with **Exclude the id attribute**.
- 5. In the **Code** field, enter **exclude-attributes** .
- 6. From the Applies To list, select Anything.
- 7. In the **Payload** field, enter the following text to exclude the **id** attribute.
 - ["data[*].id"]
- 8. Click Save changes.

The following screen shows the rule.

scription	
Applies to	
Add definitions and targets, or drag from Components	
- When	
ALL ANY NONE CLEAR ALL	
A Sharing consent status	
+ Comparison + Named Condition + Group	
Effect	
Effect Permit	
tatements (1 total)	
Exclude the id attribute	Obligatory
ldd Statement	

With the policy in place, trying the request again gets a response with the **id** attribute removed, as shown in the following snippet.

```
{
    "data": [{
        "type": "answers",
        "attributes": {
            "url": "https: //l.imqflip.com/2fm6x.jpq",
                "captions": ["Still waiting for the bus to Jennie's"],
                "rating": null,
                "created_at": "2020-05-e6T22:35:06-00:00"
        }
},
```

You can use the Decision Visualiser to see how the decision engine processed the decision. In the Policy Editor, click **Policies** in the left pane, then click **Decision Visualiser** along the top, and then click **Recent Decisions**. Click a decision and follow the green paths to see which policies are executed and which rules are invoked. Click **Attributes** along the top to see the names and values of attributes that are used in the decision.

10. Add a rule to modify attributes.

1. Click + Add Rule.

- For the name, replace Untitled with If consent to share status is restricted then modify attributes.
- 2. Specify the condition.
 - 1. Click + Comparison.
 - 2. From the **Select an Attribute** list, select **Sharing consent status**, which we created in **Getting consent status from the consent record**.
 - 3. In the second field, select Equals.
 - 4. In the third field, type restricted.
- 3. Specify the statement.
 - 1. Click Show Statements.
 - 2. Click + next to **Statements**.
 - 3. Click + Add Statement → Modify Attributes.

Use this statement to change attributes. For example, the client might request health records and require all items from a record, such as a social security number, even if partially or fully hidden.

For information about this statement, see Modify Attributes.

- 4. For the name, replace Untitled with Modify all the values in attributes.
- 5. In the Code field, enter modify-attributes.
- 6. From the Applies To list, select Permit.
- 7. In the **Payload** field, enter the following text to replace all values in the **attributes** attribute with three dashes.

\{"data[].attributes.":"---"}

8. Click Save changes.

The following screen shows the rule.

If consent to share status is restricted then modify attributes	Disabled 🗌 📮
escription	
Applies to	
Add definitions and targets, or drag from Components	
- When	
ALL ANY NONE CLEARALL	
A Sharing consent status	÷
+ Comparison + Named Condition + Group	
Effect	
Effect Permit	
Statements (1 total)	
Modify all the values in attributes	Obligatory
Add Statement	
e "Applies to" Hide Statements Show Properties	

With the policy in place, trying the request now gets a response with the id and type attributes unchanged but all the attributes values changed to dashes, as shown in the following snippet.

{	
"data":	[{
	"id": "168",
	"type": "answers",
	"attributes": {
	"url": "",
	"captions": "",
	"rating": "",
	"created_at": ""
	}
},	

Result

The following image shows what the policy applies to and the three rules.

Policies Library Target Search De	cision Visualiser	
Policies Components	Details History Test	
•		le
 Global Decision Point Token Validation PDP API Endpoint Policies meme-game policies Control user's response to answers request 	 Applies to Add definitions and targets, or drag from Components outbound-GET outbound-GET + Comparison + Named Condition 	
	Rules (3 total) Combining Algorithm Unless one decision is deny, the decision will be permit	•
	• 🕴 🧭 If consent to share status is accepted then include attributes	
	• E 🕑 If consent to share status is revoked then exclude attributes	∍ ≡
	• 🕴 🧭 If consent to share status is restricted then modify attributes	
	Delete Policy	🖹 Save changes

Use case: Using a SCIM resource type or a policy request action to control behavior

SCIM (System for Cross-domain Identity Management) resource types define a class of resources, such as users or devices. The PingAuthorize Server SCIM service provides a REST API for data stored in external datastores that are based on the SCIM 2.0 standard.

The SCIM service translates each SCIM request or response into one or more policy requests to the policy decision point (PDP).

These policy requests have an **action** value that you can reference in the policies you write to deny or permit the action.

For more background information, see About the SCIM service.

For more information about actions, see SCIM policy requests.

This feature is useful for:

- Data control
- Information security
- Resource management

Example scenarios include:

- · A bank that wants to prevent delete operations of their client profiles
- A health care system that should only allow the creation of new patient records and should not allow the modification of existing patient records

• A university system that only allows the retrieval of student information from the student's defined department; the system can modify the information differently based on the department

In this use case, we define services in the Trust Framework. We then create policies that use those services or policy request actions to control various operations. The following topics cover these tasks.

- 1. Getting the SCIM resource type and the action being executed
- 2. Creating a policy to permit or deny the creation of resources
- 3. Creating a policy to control the set of actions for a specific resource
- 4. Creating a policy to restrict the ability to delete based on resource type
- 5. Creating a policy to dynamically modify a resource based on the SCIM resource type

Getting the SCIM resource type and the action being executed

The SCIM resource type indicates the class of resources with which to interact. The action indicates what the user is trying to do. Here we define Trust Framework services to use in policies and locate the resource type and actions.

About this task

The PingAuthorize Policy Editor provides a SCIM2 service in the Trust Framework. This service is for the SCIM2 REST API and does not reference resource types. This task creates two services: Users and Devices.

Steps

- 1. Sign on to the Policy Editor.
- 2. Create the Users and Devices services.
 - 1. Go to Trust Framework and click Services.
 - 2. Click the SCIM2 service so the service we create is listed under SCIM2.
 - 3. From the + menu, select Add new Service.
 - 4. For the name, replace Untitled with Users.
 - 5. Click Save changes.
 - 6. Click the SCIM2 service again.
 - 7. From the + menu, select Add new Service.
 - 8. For the name, replace Untitled with Devices.
 - 9. Click Save changes.

With the services defined, you should have a screen similar to the following one.

		Definitions Target Search	
24	Branch Manager	Domains Services Attributes Identity Classes	Identity Providers Identity Properties Actions Conditions Processors
-4	Trust Framework	+	Details History Test
	Policies	OpenBanking Account and Transaction	SCIM2
	Test Suite	API	
	API Reference	PDP	SCIM (System for Cross-domain Identity Management) 2 REST API for managing identity data.
		🔅 Devices 🔆 Users	Parent no parent selected
			- Service Settings
		•	Service Type None

We will use these services in the policies we create.

Also, we will use the attribute SCIM2.resource.meta.resourceType.

To see the attribute in the Trust Framework, click Attributes and navigate to it starting from SCIM2.

(i) Note

The SCIM2.resource attribute is only available when the SCIM resource exists. For example, the search and create actions do not have this attribute. However, the search action does have a policy request with a retrieve action that does have the attribute.

Your policy can use a service you define or the SCIM2.resource.meta.resourceType attribute.

Also, we can use these actions in our policies: create, delete, modify, retrieve, search, and search-results.

To see the actions in the Trust Framework, click Actions.

When you are creating your policy, use the Policy Editor's Decision Visualiser to make sure your policy accurately reflects the policy requests. For example, consider the following screen showing the request.

Policies	Library	Target Search	Decision Visualiser									
Visualisation	Request	Response Output	Attributes Services									
"servi "ident "actio "attri "H "H "H "H "H "H "H "H	ityProvide n": "retr: butes": { ttpRequest ttpRequest ttpRequest ttpRequest ttpRequest ttpRequest	t.CorrelationId": L.RequestURI": "ht L.PAddress": "172 t.ResourcePath": "1 L.RequestHeaders": L.ResponseHeaders" t.AccessToken": "{	Devices/e988a8b3-bb76-4e6b- "{\"Authorization\":[\"Bea	.com:3443/ 8ca-561bb7 er {\\\"ac ve\\\": tr	scim/v2/Dev 8d974a", tive\\\": 1 ue, \\\"sub	true, \\\ b\\\": \\	"sub\\\"	': \\\"d 2.3\\\"}	evice.3\` \",\"act	\\"}\"] ive\":t],\"Acce	user_toke

We can use the following lines from the Decision Visualiser:

• service line

Verify the name of the service in your Trust Framework and policy.

• action line

Verify that the request produces the expected action that the policy uses.

The PingAuthorize SCIM translates a **GET** request in the SCIM REST API to a retrieve action. For more information about actions, see SCIM policy requests.

RequestURI line

Verify that the endpoint belongs to the expected service.

• SCIM2 line

Scroll right to verify that the **resourceType** is as expected.

Creating a policy to permit or deny the creation of resources

This policy allows the creation of one resource type but not another. In particular, the policy focuses on the create action and then allows the creation of Device resources but denies the creation of User resources.

Steps

- 1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.
- 2. From the + menu, select Add Policy.
- 3. For the name, replace **Untitled** with User can only create Device resources.
- 4. Click the + next to Applies to.
- 5. Click Add definitions and targets, or drag from Components and add the create action.
- 6. Set Combining Algorithm to Unless one decision is deny, the decision will be permit.
- 7. Add a rule to allow the creation of Device resources.
 - 1. Click + Add Rule.
 - 2. For the name, replace **Untitled** with **Permit** the creation of Device resources.
 - 3. Click + Comparison.
 - 4. In the first field, click the A to toggle to an R, and from that field's drop-down list, select Service.
 - 5. In the second field, select **Equals**.
 - 6. In the third field, select the **SCIM2.Devices** service.
 - 7. Click Save changes.

You should have a screen similar to the following one for the policy and this rule.

escription		
Applies to		
Add definitions and targets, or dr	ag from Components O All Requests	
- When ALL ANY NONE CLEAR ALL		
R Service + Comparison + Named Condi	Equals SCIM2.Devices	•
Effect		
Effect Permit		•

8. Add a rule to deny the creation of User resources.

1. Click + Add Rule.

- 2. For the name, replace **Untitled** with **Deny the creation of User resources**.
- 3. Set Effect to Deny.
- 4. Click + Comparison.
- 5. In the first field, click the A to toggle to an R, and from that field's drop-down list, select Service.
- 6. In the second field, select **Equals**.
- 7. In the third field, select the **SCIM2.Users** service.
- 8. Add statements to provide a custom message.
 - 1. Within the rule, click Show Statements.
 - 2. Click + next to Statements.
 - 3. Click + Add Statement → Denied Reason.
 - 4. For the name, specify denied-reason .
 - 5. Set Applies To to Deny.
 - 6. In the Payload field:
 - Remove

Example:

Change

Human-readable error message

to

System has restricted the ability to create User resources

9. Click Save changes.

You should have a screen similar to the following one for the second rule.

Applies to			
Add definitions and targets, or drag	from Components O All Requests		
- When			
ALL ANY NONE CLEAR ALL			
R Service	✓ Equals	- SCIM2.Users	
+ Comparison + Named Conditio	+ Group		
Effect			
Effect Deny			
tatements (1 total)			
denied-reason			Obligatory

9. Send test requests to the SCIM service and verify data using the Policy Editor's Decision Visualiser.

Creating a policy to control the set of actions for a specific resource

For a given resource, control the outcomes (deny or permit) of actions on the resource. In particular, the policy focuses on the Users resource and then denies deletes but permits retrieves.

Steps

- 1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.
- 2. From the + menu, select Add Policy.
- 3. For the name, replace Untitled with Control actions for the User resource.
- 4. Click the + next to Applies to.
- 5. Click Add definitions and targets, or drag from Components and add the SCIM2.Users service.
- 6. Set Combining Algorithm to Unless one decision is deny, the decision will be permit.

You should have a screen similar to the following one for the policy so far.

		Policies Library Target Search Decision Visualiser		
>\$	Branch Manager	Policies Components	Details History Test	
$-\kappa_{0}^{\alpha}$	Trust Framework	+	Control actions for the User resource	Disabled 🗌 🗮
	Policies	y 🌖 Global Decision Point		
<u>12</u>	Test Suite	Token Validation	Description	
>	API Reference	PDP API Endpoint Policies Image: Second system Image: Second system		
		Control actions for the User resource	+ Applies to	
			- Rules (2 total)	
			Combining Algorithm Unless one decision is deny, the decision will be permit	•

- 7. Add a rule to deny the deletion of User resources.
 - 1. Click + Add Rule.
 - 2. For the name, replace **Untitled** with **Action: delete**.
 - 3. Set Effect to Deny.
 - 4. Click + Comparison.
 - 5. In the first field, click the A to toggle to an R, and from that field's drop-down list, select Action.
 - 6. In the second field, select **Equals**.
 - 7. In the third field, select the **delete** action.
 - 8. Add a statement to provide a custom message.
 - 1. Within the rule, click **Show Statements**.
 - 2. Click + next to Statements.
 - 3. Click + Add Statement → Denied Reason.
 - 4. For the name, specify denied-reason.
 - 5. Set Applies To to Deny.
 - 6. In the Payload field:
 - Remove

Example:

Change

Human-readable error message

to

System has restricted the ability to delete User resources

9. Click Save changes.

Your rule should be similar to the following one.

escription		
Applies to		
🕒 Add definitions and targets, or drag	rom Components O All Requests	
- When		
ALL ANY NONE CLEAR ALL		
R Action	- Equals - delete	•
+ Comparison + Named Conditio		
r comparison	. oroup	
Effect		
Effect Deny		
Statements (1 total)		
denied-reason		Obligatory

8. Add a rule to permit the retrieval of User resources.

1. Click + Add Rule.

- 2. For the name, replace **Untitled** with Action: retrieve.
- 3. Set Effect to Permit.
- 4. Click + Comparison.
- 5. In the first field, click the **A** to toggle to an **R**, and from that field's drop-down list, select **Action**.
- 6. In the second field, select **Equals**.
- 7. In the third field, select the **retrieve** action.
- 8. Click Save changes.

Your rule should be similar to the following one.

Description	
Applies to	
Add definitions and targets, or drag from Components	
- When	
ALL ANY NONE CLEAR ALL	
R Action - Equals - retrieve	-
+ Comparison + Named Condition + Group	
Effect	
Effect Permit	

9. Send test requests to the SCIM service, and verify data using the Policy Editor's Decision Visualiser.

Creating a policy to restrict the ability to delete based on resource type

For a given resource type, restrict the ability to delete. In particular, the policy focuses on the delete action and then denies the action when the resource type is Devices.

Steps

- 1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.
- 2. From the + menu, select Add Policy.
- 3. For the name, replace **Untitled** with User cannot delete a Device resource.
- 4. Click the + next to Applies to.
- 5. Click Add definitions and targets, or drag from Components and add the delete action.
- 6. Set Combining Algorithm to Unless one decision is deny, the decision will be permit.

You should have a screen similar to the following one for the policy so far.

		Policies Library Target Search De	ecision Visualiser
>\$	Branch Manager	Policies Components	Details History Test
$-<^*_0$	Trust Framework	+	🖹 User cannot delete a Device resource Disabled 🗌 🚍
₿	Policies	👻 💁 Global Decision Point	
<u>e</u> 1	Test Suite	Token Validation	Description
	API Reference	 PDP API Endpoint Policies User can only create Device resources Control actions for the User resource User cannot delete a Device resource 	 Applies to Add definitions and targets, or drag from Components delete delete delete delete + Comparison + Named Condition Rules (1 total) Combining Algorithm Unless one decision is deny, the decision will be permit •

- 7. Add a rule to deny the deletion of Device resources.
 - 1. Click + Add Rule.
 - 2. For the name, replace Untitled with If the SCIM resource type is Device, then deny.
 - 3. Set Effect to Deny.
 - 4. Click + Comparison.
 - 5. In the Select an Attribute list, select the SCIM2.resource.meta.resourceType attribute.
 - 6. In the second field, select **Equals**.
 - 7. In the third field, specify **Devices** as the constant.
 - 8. Add a statement to provide a custom message.
 - 1. Within the rule, click Show Statements.
 - 2. Click + next to **Statements**.
 - 3. Click + Add Statement → Denied Reason.
 - 4. For the name, specify denied-reason.
 - 5. Set Applies To to Deny.
 - 6. In the **Payload** field:
 - Remove

Example:

Change

Human-readable error message

to

System has restricted the ability to delete Device resources

9. Click Save changes.

Your rule should be similar to the following one.

Applies to	
Add definitions and targets, or drag from Components	
- When	
ALL ANY NONE CLEARALL	
A SCIM2.resource.meta.resourceType	tin and the second seco
+ Comparison + Named Condition + Group	
Effect	
Effect Deny	
Statements (1 total)	
denied-reason	Obligatory

8. Send test requests to the SCIM service, and verify data using the Policy Editor's Decision Visualiser.

Creating a policy to dynamically modify a resource based on the SCIM resource type

Given an attribute defined in multiple resource types, modify the attribute differently depending on the resource type. In particular, this policy focuses on the retrieve action and changes the **cn** attribute to one value for the Users resource type and to another value for the Devices resource type.

Steps

- 1. In the Policy Editor, go to **Policies** in the left pane and then click **Policies** along the top.
- 2. From the + menu, select Add Policy.
- 3. For the name, replace Untitled with Modify cn attribute based on the resource type.
- 4. Click the + next to Applies to.
- 5. Click Add definitions and targets, or drag from Components and add the retrieve action.
- 6. Set Combining Algorithm to Unless one decision is deny, the decision will be permit.

You should have a screen similar to the following one for the policy so far.

		Policies Library Target Search De	ecision Visualiser	
\supset	Branch Manager	Policies Components	Details History Test	
- <\$	Trust Framework	+	B Modify cn attribute based on the resource type	
Ð	Policies	🔻 일 Global Decision Point		
<u>11</u>	Test Suite	E Token Validation	Description	
	API Reference	 PDP API Endpoint Policies User can only create Device resources Control actions for the User resource User cannot delete a Device resource Modify cn attribute based on the resource type 	 Applies to Add definitions and targets, or drag from Components 	
			+ Comparison + Named Condition	
			- Rules (2 total)	
			Combining Algorithm Unless one decision is deny, the decision will be permit	

7. Add a rule for the Users resource.

- 1. Click + Add Rule.
- 2. For the name, replace **Untitled** with **If resource type is Users**.
- 3. Click + Comparison.
- 4. From the Select an Attribute list, select the SCIM2.resource.meta.resourceType attribute.
- 5. In the second field, select **Equals**.
- 6. In the third field, specify Users as the constant.
- 7. Add statements to modify attributes.
 - 1. Within the rule, click Show Statements.
 - 2. Click + next to Statements.
 - 3. Click + Add Statement → Modify Attributes.
 - $4. \ \mbox{For the name, specify} \ \mbox{Modify cn for users resource} \ .$
 - 5. Set Applies To to Permit.
 - 6. Set the **Payload** field to \{"cn":"USERS_MOD"}.
- 8. Click Save changes.

Your rule should be similar to the following one.

If resource type is Users	Disabled 🔲 📮		
escription			
Applies to			
Add definitions and targets, or drag from Components			
ALL ANY NONE CLEAR ALL			
A SCIM2.resource.meta.resourceType Equals C Users C Hommed Condition C C C C C C C C C C C C C C C C C<td>Î</td>	Î		
Effect			
Effect Permit	-		
Statements (1 total)			
Modify cn for users resource Obligatory			
Add Statement			

8. Add a rule for the Devices resource.

- 1. Click + Add Rule.
- 2. For the name, replace **Untitled** with **If resource type is Devices**.
- 3. Click + Comparison.
- 4. From the Select an Attribute list, select the SCIM2.resource.meta.resourceType attribute.
- 5. In the second field, select **Equals**.
- 6. In the third field, specify **Devices** as the constant.
- 7. Add statements to modify attributes.
 - 1. Within the rule, click **Show Statements**.
 - 2. Click + next to **Statements**.
 - 3. Click + Add Statement → Modify Attributes.
 - 4. For the name, specify Modify cn for devices resource.
 - 5. Set Applies To to Permit.
 - 6. Set the **Payload** field to \{"cn":"DEVICES_MOD"}.

8. Click Save changes.

Your rule should be similar to the following one.

escription	
Applies to	
Add definitions and targets, or drag from Components	
– When	
ALL ANY NONE CLEAR ALL	
A SCIM2.resource.meta.resourceType - Equals - C Devices + Comparison - + Named Condition - + Group	
Effect	
Effect Permit	
Statements (1 total)	
Modify cn for devices resource	Obligatory

9. Send test requests to the SCIM service, and verify data using the Policy Editor's Decision Visualiser.

Restricting the modification of attributes

Starting with PingDataGovernance 8.1, the Allow Attributes statement and Prohibit Attributes statement are no longer supported. If you have policies that use those statements, change them to use the **impactedAttributes** policy attribute.

About this task

The impactedAttributes attribute is defined in resource/policies/defaultPolicies.SNAPSHOT. If you are using a branch created from that snapshot, the attribute already exists in the branch. If not, create the attribute.

Steps

- 1. Go to Trust Framework, and then click Attributes.
- 2. From the + menu, select Add new Attribute.
- 3. For the name, replace **Untitled** with **impactedAttributes**.
- 4. Verify that in the **Parent** field, no parent is selected. To remove a parent, click the delete icon to the right of the **Parent** field.
- 5. Click + Add Resolver and set the Resolver type to Request.
- 6. In the Value Settings section:
 - 1. Select the box next to **Default value** and specify square brackets with no space between them ([]) as the value.
 - 2. Set Type to Collection.
- 7. Click Save changes.

Allowing attributes to be modified by administrators

To allow any attribute to be modified, such as for an administrator account, the policy decision point (PDP) does not need to check the **impactedAttributes** attribute.

About this task

To create a policy that allows an administrator to modify any attributes, complete the following step.

Steps

• Create a policy, and then add a rule with the **Effect** set to **Permit** the decision based on the **Condition** that the user is an administrator.

To check the user, for example, you can set up a condition to compare whether HttpRequest.AccessToken.scope equals administrator.

Adding attributes to an allow list

To allow the user to modify a set of attributes limited to an allow list and return an error if the user attempts to modify any attribute outside of the allow list, create a constant in the Trust Framework and then use the constant in a policy.

Steps

- 1. Create a constant in the Trust Framework.
 - 1. Go to Trust Framework and then Attributes.
 - 2. From the + menu, select Add new Attribute.
 - 3. For the name, replace **Untitled** with allowlistAttributes.
 - 4. Verify that in the **Parent** field, no parent is selected. To remove a parent, click the delete icon to the right of the **Parent** field.
 - 5. Click + Add Resolver and set the Resolver type to Constant.
 - 6. Set the value of the constant to a set of square brackets that contains a comma-delimited list of the attributes that can be modified.

For example, to allow the email or userName attributes to be modified, you would set the value of the constant to [email, userName].

As another example, to allow the user to modify a property or any of its subproperties, you must explicitly list them. So to allow modification of the name field on the default Users pass-through schema, set the value of the constant to [name, name.formatted, name.givenName, name.familyName].

- 1. In the Value Settings section, set Type to Collection.
- 2. Click Save changes.

2. Modify or create a policy to use that constant collection.

1. Go to Policies.

- 2. Select a policy or create a new one.
- 3. In the **Rules** section:
 - 1. Set the Combining Algorithm to Unless one decision is permit, the decision will be deny.
 - 2. Click + Add Rule.
 - 3. For the name, replace Untitled with Allow only the email and userName attributes.
 - 4. Set the Effect to Permit.
 - 5. Under **Condition**, click **+ Comparison**.
 - 6. In the comparison, we want to compare the constant collection of permitted attributes to the impactedAttr ibutes collection.
 - For the left field, select the allowlistAttributes attribute, which is the constant collection of permitted attributes defined in the beginning.

You might see the field as shown below. Click the **R** immediately above **+ Comparison** to toggle to attribute selection.

-	Cond	ition				
	ALL	ANY	NONE	CLEAR ALL		
:	R	Domain				
+ Comparison		+ Named Conditi	on	+ Group		

Set the middle field (the operator) to **Contains**.

Set the right field to the impactedAttributes attribute.

If that field has a **C** before it, click the **C** to toggle to attribute selection.



If impactedAttributes is not available, see Restricting the modification of attributes.

When applied to two collections, the **Contains** operator returns true if and only if the right-side collection is a subset of the left-side collection. Thus, the rule only returns **permit** if the set of **impactedAttributes** is a subset of the list of allowed attributes in **allowlistAttributes**.

Test Suite

Use the Test Suite to define tests, scenarios, and assertions to validate behavior for most Trust Framework and Policy Manager entities.

Policy writers can build a library of test cases to use as part of a test-driven development approach to policy and Trust Framework design. The library you develop can form a suite of regression checks that you run against each new version of policies or the Trust Framework.

The Test Suite has these components: tests, scenarios, and assertions. The following table highlights the similarities and differences. The components are very similar. However, with test cases, you specify a Trust Framework or Policy Manager entity to test. Scenarios do not use such entities and are instead for reuse across tests.

Test cases	Scenarios
A test case definition includes: • A decision request • Optional overrides for attributes • Optional overrides for services • An entity to test • Optional assertions	A scenario definition includes: • A decision request • Optional overrides for attributes • Optional overrides for services You can reuse a scenario within a test suite.

Tests

In the Test Suite, use the **Tests** tab to view and manage tests and test groups. A test group is a collection of tests.

To add a test or test group, click +.

When you create a test, keep the following items in mind:

Field	Description
Name	A unique name that avoids the following characters:
Description	A description for the test to clarify its intention and usage.
Tested Entity	The entity to verify with the test. After you assign an entity, you can run the test on that entity using the Test tab in the Trust Framework or Policy Manager pages.
Scenario Type	 The type of scenario to use: Inline—you define the scenario on the same page where you define the test Referenced—you select a scenario that you already defined in the Scenarios tab
	 Tip You can use a referenced scenario as a template for a new inline scenario by selecting that referenced scenario and then switching to Inline Scenario.

When you create a test group, you need only provide a name and description.

Scenarios

In the Test Suite, use the **Scenarios** tab to view and manage scenarios and scenario groups. A scenario group is a collection of scenarios.

Scenarios define a decision request and optional attribute and service overrides to serve as input for a test. After you define a scenario, you can reference it by name in your tests. Also, on the **Test** tab in the Trust Framework or Policy Manager pages, you can load a scenario directly into the test by clicking the **Load Scenario** button in the lower-right corner.

To add a test or test group, click +.

You can specify request and override data by hand, or by importing it in JSON format, by clicking the **Import JSON** button in the lower-right corner.

When you create a scenario group, you need only provide a name and description.

Assertions

After you define a test scenario, you can create assertions to verify content in the decision response generated by the scenario. Use assertions to ensure that a particular property in the response is behaving correctly.

In the Test Suite, use the Assertions tab to view and manage assertions and assertion groups.

To create an assertion, your options include:

• Using the Assertions tab.

О Тір

For assertions you create using the **Assertions** tab, use them in a test by clicking **+** Add Assertion, setting **Assertion Type** to **Referenced**, and then selecting the assertion in the drop-down list.

• Creating them inline when you define a test on the Tests tab.

When you define an assertion, you:

- 1. Provide a JSONPath accessor to extract information from the response.
- 2. Specify a matcher to indicate how to compare the extracted information against an expected value.
- 3. Specify the expected value type.
- 4. Specify the expected value.

The following image shows an assertion that checks whether the result value equals **PERMIT** :

Details		
V PERMIT		•
Description		
		li.
Parent	Decision Results	-
 Assertion 		
JSONPath	\$.result.value	
Matcher	Equals -	•
Expected Va	slue Type String	•
Expected Va	elue PERMIT	lle.

Test execution

After you assign a testable entity, such as a policy or attribute, to a test case, you can run the test. To view and run the test, your options are:

- In the test definition, after you add the tested entity to the test and save your changes, click the name of the tested entity to view the entity. Next, click **Test** and then **Tests**.
- View the entity through a tab on the left, such as the Policies tab. Next, click Test and then Tests.

You now see a table of the tests available for the entity. Click a test's **Execute** button to run that test. For longer running tests, you can go to other tasks in the Policy Editor and return to this page later to check progress.

If a test uses assertions, when you expand the row for the test case, an **Assertions** tab appears. Use this tab to see the results for the assertions.

Management REST API documentation

The PingAuthorize Policy Editor provides a set of REST APIs for managing policies, snapshots, and deployment packages.

Documentation for these APIs will be made available at a future date.

Troubleshooting PingAuthorize Server

. .

PingIdentity.

You can capture diagnostic data to help troubleshoot issues with PingAuthorize Server or a supporting component, such as the Java Virtual Machine (JVM), the operating system, or the hardware.

With this data, you can troubleshoot the problem quickly to determine the underlying cause and the best course of action to resolve it.

Learn about troubleshooting decision requests and responses in the following:

- Visualizing a policy decision response
- Policy Decision Logger
- Configuring the Decision Response View

Working with the collect-support-data tool

If a problem occurs with PingAuthorize Server, you should first run the collect-support-data tool in the server's bin directory.

The server provides detailed insights into its current state, including any processing issues. The **collect-support-data** tool compiles relevant support files and diagnostic data, such as outputs from the **jps**, **jstack**, and **jstat** utilities, into a .zip archive for administrators to share with their authorized support provider.

Although the **collect-support-data** tool tries to collect the same data across all systems for the target PingAuthorize Server, the resulting data might vary between operating systems. The collected data includes the configuration directory, summaries and snippets from the **logs** directory, monitor entry status, and a list of all files in the server root.

By default, the **collect-support-data** tool excludes log files that might contain sensitive customer information, including the debug logs described in Enable detailed logging. If you are using test data that doesn't include sensitive information, send the following log files along with **collect-support-data** 's compressed output file:

- PingAuthorize/logs/policy-decision.log
- PingAuthorize/logs/debug-trace.log
- PingAuthorize/logs/debug.log
- PingAuthorize/logs/policy-query.log

To prevent the support .zip archive from exceeding e-mail attachment size limits, the **collect-support-data** tool might only archive portions of certain log files.

Running the collect-support-data tool

Steps

1. Run the collect-support-data tool.

Make sure to include the host, port number, bind DN, and bind password.

Example:

```
<PingAuthorize>/bin/collect-support-data \
--hostname <host> \
--port <port> \
--bindDN "cn=<dn>" --bindPassword <password>
```

2. Email the generated .zip archive to your authorized support provider.

Invoking the collect-support-data tool as a recurring task

To automatically invoke **collect-support-data** on a regular basis, create and configure a recurring task.

Admin console

Use the administrative console Steps

1. Go to System > Recurring Tasks.

2. In the New Recurring Task list, select Collect Support Data Recurring Task.

- 3. In the Name field, enter a name for the recurring task.
- 4. In the **Output Directory** field, enter the path of the directory in which support data archive files will be placed.
- 5. Do at least one of the following:
 - In the **Retain Previous Support Data Archive Count** field, enter the number of previous support data archives that PingAuthorize Server should preserve after generating a new archive.
 - In the Retain Previous Support Data Archive Age field, enter the minimum age of previous support data archives that PingAuthorize Server should preserve after generating a new archive. Values for this property should consist of an integer followed by a time unit. For example, a value of 1w specifies that PingAuthorize Server should preserve support data archives for one week.

6. Configure the rest of the recurring task to meet your business needs.

7. Click Save.

<i>Use</i> dso	onfig
Steps	Shiring Shirin
•	Run dsconfig with the create-recurring-task subcommand and the following options and parameters:
	<pingauthorize>/bin/dsconfig create-recurring-task \ task-name <your-task-name> \ type collect-support-data \ set output-directory:<your-directory-path> \ set retain-previous-support-data-archive-count:<count></count></your-directory-path></your-task-name></pingauthorize>
	Important
	 You must include at least one of the following parameters in your command: retain-previous-support-data-archive-count : Specifies the number of previous support data archives that PingAuthorize Server should preserve after generating a new archive. retain-previous-support-data-archive-age : Specifies the minimum age of previous support data archives that PingAuthorize Server should preserve after generating a new archive. Values for this property should consist of an integer followed by a time unit. For example, a value of 1w specifies that PingAuthorize Server should preserve support data archives for one week.

Server commands used in the collect-support-data tool

The following presents a summary of the data collectors that the **collect-support-data** tool archives in .zip format. If an error occurs during processing, you can rerun the specific data collector command and send the results to your authorized support provider.

Data Collector	Description
status	Run status -F to show the full version information of PingAuthorize Server (Unix, Windows).
server-state	Run server-state to show the current state of the PingAuthorize Server process (Unix, Windows).

JDK commands used in the collect-support-data tool

Data Collector	Description
jps	Java Virtual Machine Process status tool. Reports information on the JVM (Linux, Windows, Mac OS).

Data Collector	Description
jstack	Java Virtual Machine Stack Trace. Prints the stack traces of threads for the Java process (Linux, Windows, Mac OS).
jstat	Java Virtual Machine Statistics Monitoring Tool. Displays performance statistics for the JVM (Linux, Windows, Mac OS).
jinfo	Displays the Java configuration information for the Java process (Linux, Windows, Mac OS).

Linux commands used in the collect-support-data tool

Data Collector	Description
tail	Displays the last few lines of a file. Tails the /var/logs/messages directory.
uname	Prints system, machine, and operating system information.
ps	Prints a snapshot of the current active processes.
df	Prints the amount of available disk space for file systems in 1024-byte units.
cat	<pre>Concatenates the following files and prints to standard output: /proc/cpuinfo /proc/meminfo /etc/hosts /etc/nsswitch.conf /etc/resolv.conf</pre>
netstat	Prints the state of network interfaces, protocols, and the kernel routing table.
ifconfig	Prints information on all interfaces.
uptime	Prints the time the server has been up and active.
dmesg	Prints the message buffer of the kernel.
vmstat	Prints information about virtual memory statistics.
iostat	Prints disk I/O and CPU utilization information.
mpstat	Prints performance statistics for all logical processors.
pstack	Prints an execution stack trace on an active processed specified by the pid.
top	Prints a list of active processes and how much CPU and memory each process is using.

MacOS commands used in the collect-support-data tool

Data Collector	Description
uname	Prints system, machine, and operating system information.
uptime	Prints the time the server has been up and active.
ps	Prints a snapshot of the current active processes.
system_profiler	Prints system hardware and software configuration.
vm_stat	Prints machine virtual memory statistics.
tail	Displays the last few lines of a file. Tails the /var/log/system.log directory.
netstat	Prints the state of network interfaces, protocols, and the kernel routing table.
ifconfig	Prints information on all interfaces.
df	Prints the amount of available disk space for file systems in 1024-byte units.
sample	Profiles a process during an interval.

Available tool options

The following options are available for the **collect-support-data** tool:

--noLdap

Specifies that no information should be collected over LDAP. Use this option only if the server is completely unresponsive or won't start, and only as a last resort.

--pid <pid>

Specifies the ID of an additional process from which information should be collected. This is a useful option for troubleshooting external server tools, and you can specify it multiple times for each external server.

--sequential

Use this option to troubleshoot **Out of Memory** errors. By default, the **collect-support-data** tool collects data in parallel to minimize the collection time necessary for some analysis utilities. This option specifies that data collection should be run sequentially rather than in parallel. Specifying this option reduces the initial memory footprint of the **collect-support-data** tool but increases the time required for completion.

--reportCount <count>

Specifies the number of reports generated for commands that support sampling (for example, vmstat, iostat, or mpstat). If you specify a value of 0, no reports are generated for these commands. If you don't provide this option, the number of reports generated defaults to 10.

--reportInterval <interval>

Specifies the number of seconds between reports for commands that support sampling (for example, **mpstat**). You must specify a value greater than 0 for this option. If you don't provide this option, the number of seconds between reports defaults to 1.

--maxJstacks <number>

Specifies the number of jstack samples to collect. If you don't provide this option, the number of samples collected defaults to 10.

--collectExpensiveData

Specifies that data for expensive or long-running processes should be collected. To prevent a negative impact on server performance, data for these processes are not collected by default.

--comment <comment>

Allows provisioning of additional information about the collected data set. The comment you provide will be added to the generated archive as a **README** file.

--includeBinaryFiles

Specifies that binary files should be included in the archive collection. By default, all binary files are excluded from data collection.

--outputPath

Specifies the path (and optionally, the name) for the support data archive file. If the path specifies a filename, the archive is written to that file. If the path specifies a directory, the file is written to that directory with a server-generated name.

--useRemoteServer

Invokes the **collect-support-data** tool against a remote server instance and streams the output and resulting support data archive back to the client. This is a useful option when the server instance is running in a container, as it might otherwise be difficult to invoke commands or access files in that container.

PingAuthorize Server logs for troubleshooting and monitoring

PingAuthorize Server has a comprehensive default set of log files and monitor entries that are useful when troubleshooting a particular server problem.

Error log

By default, this log file is available at **logs/errors** below the server install root, and it provides information about warnings, errors, and other significant events that occur within the server. A number of messages are written to this file on startup and shutdown, but while the server is running, there is normally little information written to it. In the event that a problem does occur, the server writes information about that problem to this file.

The following is an example of a message that might be written to the error log:

[11/Apr/2011:10:31:53.783 -0500] category=CORE severity=NOTICE msgID=458887 msg="The {pingauthorize} Server has started successfully."

The category field provides information about the area of the server from which the message was generated. Available categories include:

ACCESS_CONTROL, ADMIN, ADMIN_TOOL, BACKEND, CONFIG, CORE, DSCONFIG, EXTENSIONS, PROTOCOL, SCHEMA, JEB, SYNC, LOG, PLUGIN, PROXY, QUICKSETUP, REPLICATION, RUNTIME_INFORMATION, TASK, THIRD_PARTY, TOOLS, USER_DEFINED, UTIL, VERSION

The severity field provides information about how severe the server considers the problem to be. Available severities include:

DEBUG

Used for messages that provide verbose debugging information and do not indicate any kind of problem. Note that this severity level is rarely used for error logging, because the server provides a separate debug logging facility.

INFORMATION

Used for informational messages that can be useful from time to time but are not normally something that administrators need to see.

MILD_WARNING

Used for problems that the server detects, which can indicate something unusual occurred, but the warning does not prevent the server from completing the task it was working on. These warnings are not normally something that should be of concern to administrators.

MILD_ERROR

Used for problems detected by the server that prevented it from completing some processing normally but that are not considered to be a significant problem requiring administrative action.

NOTICE

Used for information messages about significant events that occur within the server and are considered important enough to warrant making available to administrators under normal conditions.

SEVERE_WARNING

Used for problems that the server detects that might lead to bigger problems in the future and should be addressed by administrators.

SEVERE_ERROR

Used for significant problems that have prevented the server from successfully completing processing and are considered important.

FATAL_ERROR

Used for critical problems that arise which might leave the server unable to continue processing operations normally.

The messages written to the error log can be filtered based on their severities in two ways. First, the error log publisher has a **def ault-severity** property, which can be used to specify the severity of messages logged regardless of their category. By default, this includes the **NOTICE**, **SEVERE_WARNING**, **SEVERE_ERROR**, and **FATAL_ERROR** severities.

You can override these severities on a per-category basis using the **override-severity** property. If this property is used, then each value should consist of a category name followed by an equal sign and a comma-delimited set of severities that should be logged for messages in that category. For example, the following override severity would enable logging at all severity levels in the **PROTOCOL** category:

protocol=debug,information,mild-warning,mild-error,notice,severe-warning,severe-error,fatal-error

Note that for the purposes of this configuration property, any underscores in category or severity names should be replaced with dashes. Also, severities are not inherently hierarchical, so enabling the **DEBUG** severity for a category will not automatically enable logging at the **INFORMATION**, **MILD_WARNING**, or **MILD_ERROR** severities.

The error log configuration can be altered on the fly using tools like **dsconfig**, the Administrative Console, or the LDIF connection handler, and changes will take effect immediately. You can configure multiple error logs that are active in the server at the same time, writing to different log files with different configurations. For example, a new error logger can be activated with a different set of default severities to debug a short-term problem, and then that logger can be removed after the problem is resolved, so that the normal error log does not contain any of the more verbose information.

server.out log

The server.out file holds any information written to standard output or standard error while the server is running. Normally, it includes a number of messages written at startup and shutdown, as well as information about any administrative alerts generated while the server is running. In most cases, this information is also written to the error log. The server.out file can also contain output generated by the JVM. For example, if garbage collection debugging is enabled, or if a stack trace is requested via kill -QUIT as described in a later section, then output is written to this file.

Debug log

The debug log provides a means of obtaining information that can be used for troubleshooting problems but is not necessary or desirable to have available while the server is functioning normally. As a result, the debug log is disabled by default, but it can be enabled and configured at any time.

Some of the most notable configuration properties for the debug log publisher include:

enabled

Indicates whether debug logging is enabled. By default, it is disabled.

log-file

Specifies the path to the file to be written. By default, debug messages are written to the logs/debug file.

debug-level

Specifies the minimum log level for debug messages that should be written. The default value is **error**, which only provides information about errors that occur during processing (for example, exception stack traces). Other supported debug levels include **warning**, **info**, and **verbose**. Note that unlike error log severities, the debug log levels are hierarchical. Configuring a specified debug level enables any debugging at any higher levels. For example, configuring the **info** debug level automatically enables the **warning** and **error** levels.

debug-category

Specifies the categories for debug messages that should be written. Some of the most useful categories include caught (provides information and stack traces for any exceptions caught during processing), database-access (provides information about operations performed in the underlying database), protocol (provides information about ASN.1 and LDAP communication performed by the server), and data (provides information about raw data read from or written to clients).

As with the error and access logs, multiple debug loggers can be active in the server at any time with different configurations and log files to help isolate information that might be relevant to a particular problem. Debug targets can be used to further pare down the set of messages generated. For example, you can specify that the debug logs be generated only within a specific class or package.

Caution

Enabling one or more debug loggers can have a significant impact on server performance. Enable debug loggers only when necessary, and scope them so that only pertinent debug information is recorded. If you need to enable the debug logger, you should work with your authorized support provider to best configure the debug target and interpret the output.

Config audit log and the configuration archive

The configuration audit log provides a record of any changes made to the server configuration while the server is online. This information is written to the logs/config-audit.log file and provides information about the configuration change in the form that can be used to perform the operation in a non-interactive manner with the dsconfig command. Other information written for each change includes:

- Time that the configuration change was made
- Connection ID and operation ID for the corresponding change, which can be used to correlate it with information in the access log
- DN of the user requesting the configuration change and the method by which that user authenticated to the server
- Source and destination addresses of the client connection
- Command that can be used to undo the change and revert to the previous configuration for the associated configuration object

In addition to information about the individual changes that are made to the configuration, the server maintains complete copies of all previous configurations. These configurations are provided in the **config/archived-configs** directory and are gzipcompressed copies of the **config/config.ldif** file in use before the configuration change was made. The file names contain timestamps that indicate when that configuration was first used.

Setup log

The **setup** tool writes a log file providing information about the processing that it performs. By default, this log file is written to **1 ogs/setup.log** although a different name may be used if a file with that name already exists, because the **setup** tool has already been run. The full path to the setup log file is provided when the **setup** tool has completed.

Tool log

Many of the administrative tools provided with the server (for example, import-ldif, export-ldif, backup, restore, and so on) can take a significant length of time to complete writing information to standard output or standard error (or both) while the tool is running. They also write additional output to files in the logs/tools directory (for example, logs/tools/ import-ldif.log). The information written to these log files can be useful for diagnosing problems encountered while they were running. When running using the server tasks interface, log messages generated while the task is running can alternately be written to the server error log file.

Troubleshooting resources for Java applications

Because PingAuthorize Server is written entirely in Java, it is possible to use standard Java debugging and instrumentation tools when troubleshooting problems with the server.

(i) Note

In many cases, obtaining the full benefit of these tools requires access to the server source code. These Java tools should be used under the advisement of your authorized support provider.

Java troubleshooting tools

The Java Development Kit provides a number of tools for obtaining information about Java applications and diagnosing problems. These tools are not included with the Java Runtime Environment, so the full Java Development Environment should always be installed and used to run the server.

jps

The **jps** tool is a Java-specific version of the UNIX **ps** tool. It can be used to obtain a list of all Java processes currently running and their respective process identifiers. When invoked by a non-root user, it will list only Java processes running as that user. When invoked by a root user, it lists all Java processes on the system.

This tool can be used to see if PingAuthorize Server is running and if a process ID has been assigned to it. This process ID can be used in conjunction with other tools to perform further analysis.

This tool can be run without any arguments, but some of the more useful arguments include:

-v

Includes the arguments passed to the Java Virtual Machine (JVM) for the processes that are listed.

-m

Includes the arguments passed to the main method for the processes that are listed.

-1 (lowercase L)

Includes the fully qualified name for the main class rather than only the base class name.

jstack

The **jstack** tool is used to obtain a stack trace of a running Java process, or optionally from a core file generated if the JVM happens to crash. A stack trace can be extremely valuable when trying to debug a problem, because it provides information about all threads running and exactly what each thread is doing at the point in time that the stack trace was obtained.

Stack traces are helpful when diagnosing problems in which the server appears to be hung or behaving slowly. Java stack traces are generally more helpful than native stack traces, because Java threads can have user-friendly names (as do the threads used by the server), and the frame of the stack trace may include the line number of the source file to which it corresponds. This is useful when diagnosing problems and often allows them to be identified and resolved quickly.

To obtain a stack trace from a running JVM, use the command:

jstack <processID>

Replace **<processID>** with the process ID of the target JVM as returned by the **jps** command.

To obtain a stack trace from a core file from a Java process, use the command:

jstack <pathToJava> <pathToCore>

Replace <pathToJava> with the path to the Java command from which the core file was created, and replace <pathToCore> with the path to the core file to examine. In either case, the stack trace is written to standard output and includes the names and call stacks for each of the threads that were active in the JVM.

In many cases, no additional options are necessary. The -1 option can be added to obtain a long listing, which includes additional information about locks owned by the threads. The -m option can be used to include native frames in the stack trace.

jmap

The **jmap** tool is used to obtain information about the memory consumed by the JVM. It is very similar to the native **pmap** tool provided by many operating systems. As with the **jstack** tool, **jmap** can be invoked against a running Java process by providing the process ID or against a core file. For example:

```
jmap <processID>
jmap <pathToJava> <pathToCore>
```

Some of the additional arguments include:

-dump:live,format=b,file=filename

Dumps the live heap data to a file that can be examined by the **jhat** tool.

-heap

Provides a summary of the memory used in the Java heap, along with information about the garbage collection algorithm in use.

-histo:live

Provides a count of the number of objects of each type contained in the heap. If the **live** option is included, then only live objects are included; otherwise, the count includes objects that are no longer in use and are garbage collected.

jhat

The **jhat** (Java Heap Analysis Tool) utility provides the ability to analyze the contents of the Java heap. It can be used to analyze a heap dump file, which is generated if PingAuthorize Server encounters an **out of memory** error (as a result of the **-XX**: **+HeapDumpOnOutOfMemoryError** JVM option) or from the use of the **jmap** command with the **-dump** option.

The **jhat** tool acts as a web server that can be accessed by a browser to query the contents of the heap. Several predefined queries are available to help determine the types of objects consuming significant amounts of heap space, and it also provides a custom query language (OQL, the Object Query Language) for performing more advanced types of analysis.

The **jhat** tool can be launched with the path to the heap dump file. For example:

jhat </path/to/heap.dump>

This command causes the **jhat** web server to begin listening on port 7000. It can be accessed in a browser at http://localhost: 7000^[] (or http://<address>:7000 from a remote system). An alternate port number can be specified using the **-port** option. For example:

jhat -port 1234 </path/to/heap.dump>

To issue custom OQL searches, access the web interface using the URL http://localhost:7000/oql/ \square (the trailing slash must be provided). Additional information about the OQL syntax may be obtained in the web interface at http://localhost:7000/oqlhelp/ \square .

jstat

The **jstat** tool is used to obtain a variety of statistical information from the JVM, much like the **vmstat** utility, which can be used to obtain CPU utilization information from the operating system. The general manner to invoke it is as follows:

```
jstat <type> <processID> <interval>
```

The *<interval>* option specifies the length of time in milliseconds between lines of output. The *<processID>* option specifies the process ID of the JVM used to run PingAuthorize Server, which can be obtained by running **jps** (as mentioned previously). The *<type>* option specifies the type of output that should be provided. Some of the most useful types include:

-class

Provides information about class loading and unloading.

-compile

Provides information about the activity of the JIT complex.

-printcompilation

Provides information about JIT method compilation.

-gc

Provides information about the activity of the garbage collector.

-gccapacity

Provides information about memory region capacities.

Java diagnostic information

In addition to the tools listed in the previous section, the JVM can provide additional diagnostic information in response to certain events.

JVM crash diagnostic information

If the JVM crashes, then it generates a fatal error log with information about the state of the JVM at the time of the crash. By default, this file is named hs_err_pid<processID>.log and is written into the base directory of the PingAuthorize Server installation. This file includes information on the underlying cause of the JVM crash, information about the threads running and Java heap at the time of the crash, the options provided to the JVM, environment variables that were set, and information about the underlying system.

Troubleshooting resources in the operating system

The underlying operating system also provides a significant amount of information that can help diagnose issues that impact the performance and stability of PingAuthorize Server.

In some cases, problems with the underlying system can be directly responsible for issues seen with the server, and in others, system tools can help narrow down the cause of the problem.

Identifying problems with the underlying system

If the underlying system itself is experiencing problems, it can adversely impact the function of applications running on it. To look for problems in the underlying system, review the system log file (/var/log/messages on Linux). Information about faulted or degraded devices or other unusual system conditions are written there.

Examining CPU utilization

Observing CPU utilization for the server process and the system as a whole provides clues as to the nature of the problem.

System-Wide CPU utilization

To investigate CPU consumption of the system as a whole, use the **vmstat** command with a time interval in seconds. For example:

vmstat 5

The specific output of this command varies between different operating systems, but it includes the percentage of the time the CPU was spent executing user-space code (user time), the percentage of time spent executing kernel-space code (system time), and the percentage of time not executing any code (idle time).

- If the CPUs are spending most of their time executing user-space code, the available processors are being well-utilized.
- If performance is poor or the server is unresponsive, it can indicate that the server is not optimally tuned. If there is a high system time, it can indicate that the system is performing excessive disk and/or network I/O, or in some cases, there can be some other system-wide problem, like an interrupt storm.
- If the system is mostly idle, but the server is performing poorly or is unresponsive, there can be a resource constraint elsewhere (for example, waiting on disk or memory access, or excessive lock contention), or the JVM can be performing other tasks, like stop-the-world garbage collection, that cannot be run heavily in parallel.

Per-CPU utilization

To investigate CPU consumption on a per-CPU basis, use the **mpstat** command with a time interval in seconds. For example:

mpstat 5

On Linux systems, it might be necessary to add -P ALL to the command. For example:

mpstat -P ALL 5

Among other things, this command shows the percentage of time each CPU has spent in user time, system time, and idle time. If the overall CPU utilization is relatively low but **mpstat** reports that one CPU has a much higher utilization than the others, there might be a significant bottleneck within the server, or the JVM might be performing certain types of garbage collection which cannot be run in parallel. On the other hand, if CPU utilization is relatively even across all CPUs, there is likely no such bottleneck, and the issue might be elsewhere.

Per-process utilization

To investigate CPU consumption on a per-process basis, use a command such as the **top** utility on Linux. If a process other than the Java process used to run PingAuthorize Server is consuming a significant amount of available CPU, it might be interfering with the ability of the server to run effectively.

Examining disk utilization

If the underlying system has a very high disk utilization, it can adversely impact server performance. It could delay the ability to read or write database files or write log files. It could also raise concerns for server stability if excessive disk I/O inhibits the ability of the cleaner threads to keep the database size under control.

The **iostat** tool can be used to obtain information about the disk activity on the system.

On Linux systems, **iostat** should be invoked with the **-x** argument. For example:

iostat -x 5

Several different types of information will be displayed, but to obtain an initial feel for how busy the underlying disks are, look at the **%util** column on Linux. This field shows the percentage of time that the underlying disks are actively servicing I/O requests. A system with a high disk utilization likely exhibits poor server performance.

If the high disk utilization is on one or more disks that are used to provide swap space for the system, the system might not have enough free memory to process requests. As a result, it might have started swapping blocks of memory that have not been used recently to disk. This can cause very poor server performance. It is important to ensure that the server is configured appropriately to avoid this condition.

If this problem occurs on a regular basis, then the server is likely configured to use too much memory. If swapping is not normally a problem, but it does arise, then check to see if there are any other processes running that are consuming a significant amount of memory, and check for other potential causes of significant memory consumption (for example, large files in a **tmpfs** file system).

Examining process details

There are a number of tools provided by the operating system that can help examine a process in detail.

ps

The standard **ps** tool can be used to provide a range of information about a particular process. For example, the command can be used to display the state of the process, the name of the user running the process, its process ID and parent process ID, the priority and nice value, resident and virtual memory sizes, the start time, the execution time, and the process name with arguments. For example:

ps -fly -p <processID>

Note that for a process with a large number of arguments, the standard **ps** command displays only a limited set of the arguments based on available space in the terminal window.

pstack

The **pstack** command can be used to obtain a native stack trace of all threads in a process. While a native stack trace might not be as user-friendly as a Java stack trace obtained using **jstack**, it includes threads that aren't available in a Java stack trace. For example, the command displays those threads used to perform garbage collection and other housekeeping tasks. The general usage for the **pstack** command is:

pstack <processID>

dbx / gdb

A process debugger provides the ability to examine a process in detail. Like **pstack**, a debugger can obtain a stack trace for all threads in the process, but it also provides the ability to examine a process (or core file) in much greater detail, including observing the contents of memory at a specified address and the values of CPU registers in different frames of execution. The GNU debugger **gdb** is widely-used on Linux systems.

🔨 Warning

Using a debugger against a live process interrupts that process and suspends its execution until it detaches from the process. In addition, when running against a live process, a debugger has the ability to actually alter the contents of the memory associated with that process, which can have adverse effects. As a result, it is recommended that the use of a process debugger be restricted to core files and only used to examine live processes under the direction of your authorized support provider.

pfiles / lsof

To examine the set of files that a process is using (including special types of files, like sockets), you can use a tool such as **1sof** on Linux systems. For example:

lsof -p <processID>

Tracing process execution

If a process is unresponsive but is consuming a nontrivial amount of CPU time, or if a process is consuming significantly more CPU time than is expected, it might be useful to examine the activity of that process in more detail than can be obtained using a point-in-time snapshot.

For example, if a process is performing a significant amount of disk reads or writes, it can be useful to see which files are being accessed. Similarly, if a process is consistently exiting abnormally, starting a trace for that process just before it exits can help provide additional information that cannot be captured in a core file (and if the process is exiting rather than being terminated for an illegal operation, then no core file may be available).

To perform this trace on Linux, use the **strace** tool. For example:

strace -f -p <processID>

Consult the **strace** manual page for additional information.

PingAuthorize API Reference

PingIdentity.

The PingAuthorize Server and Policy Editor provide a collection of APIs for managing authorization resources and leveraging finegrained authorization capabilities in your application or API service.

- The Authorization Policy Decision APIs support non-API use cases where the PingAuthorize Server acts as the policy decision point (PDP), and your application server acts as the policy enforcement point (PEP). Learn more in the Authorization Policy Decision API reference **C**.
- The Policy Editor APIs enable programmatic management of authorization resources, including:
 - Authorization policies, rules, targets, and statements
 - $\circ\,$ Trust Framework elements such as attributes, conditions, processors, and services
 - $\,\circ\,$ Branches, snapshots, and deployment packages
 - $\,\circ\,$ Test scenarios, test cases, and assertions

Learn more in the Policy Editor API reference \square .

• The PingAuthorize Server's built-in System for Cross-domain Identity Management (SCIM) service provides a REST API for data that is stored in one or more external datastores, based on the SCIM 2.0 standard ^C. Learn more in the SCIM API reference ^C.