

# PingIntelligence



# Contents

<b>PingIntelligence for APIs.....</b>	<b>11</b>
<b>PingIntelligence for APIs Overview.....</b>	<b>11</b>
<b>Release Notes.....</b>	<b>12</b>
PingIntelligence 5.0.1 - August 2021.....	13
PingIntelligence 5.0 - June 2021.....	13
Previous releases.....	14
<b>PingIntelligence PoC.....</b>	<b>14</b>
PingIntelligence Docker PoC deployment.....	14
Docker PoC setup.....	14
Installation requirements.....	15
Download and untar Docker package.....	16
Configure Docker PoC for sideband.....	16
Install and load Docker images.....	17
Setup the PoC environment.....	18
Start the training.....	18
Generate sample attacks.....	19
API deception.....	19
API discovery.....	20
Access PingIntelligence Dashboard.....	20
Dashboard.....	27
ABS detailed reporting.....	31
Shutdown the PoC environment.....	33
Appendix: Verify the Setup.....	33
PingIntelligence Kubernetes PoC deployment.....	34
PingIntelligence Kubernetes PoC.....	34
PingIntelligence Cloud service deployment.....	37
PingIntelligence Cloud service.....	37
Downloading and installing ASE software.....	39
Configure PingIntelligence Cloud Connection.....	40
Obfuscate access and secret key.....	41
Start and stop ASE.....	41
Enable ASE to ABS engine communication.....	42
Integrate PingIntelligence into your API environment.....	42
Configure ASE and Dashboard.....	43
Add APIs to ASE.....	43
AI engine training.....	45
Connect to the PingIntelligence dashboard.....	45
Access ABS reporting.....	45
<b>PingIntelligence Production Deployment.....</b>	<b>46</b>
Automated deployment.....	46
PingIntelligence setup.....	46

PingIntelligence deployment modes.....	48
Prerequisites.....	49
Download the deployment package.....	50
Step 1 - User and authentication.....	51
Step 2 - Copy PingIntelligence license.....	54
Step 3 - Configure hosts file and download software.....	54
Changing default settings.....	61
Step 4 - Configure system parameters.....	74
Step 5 - Install the PingIntelligence for APIs software.....	75
Install PingIntelligence as a systemd service.....	76
Verify PingIntelligence Installation.....	77
Next steps - Integrate PingIntelligence into your environment.....	80
Shut down the deployment.....	81
Logs.....	82
Manual deployment.....	84
PingIntelligence manual deployment.....	84
Part A – Install ABS and MongoDB.....	85
Part B – Install ASE.....	96
Part C – Integrate ASE and ABS.....	109
Part D – Install PingIntelligence Dashboard.....	111
Part E – Access ABS reporting.....	117
Part F - Integrate API gateways for sideband deployment.....	119
<b>API Security Enforcer.....</b>	<b>120</b>
Administration.....	122
ASE license.....	122
ASE interfaces.....	123
Customizing ASE ports.....	124
Configure time zone - ASE.....	125
Tune host system for high performance.....	126
Start and stop ASE.....	126
Change default settings.....	127
Obfuscate keys and passwords.....	128
Delete UUID to propagate changed password.....	129
PKCS#12 keystore.....	130
Directory structure.....	130
Administering an ASE cluster.....	131
Configure API JSON files.....	140
Configure SSL for external APIs.....	142
Configure SSL for management APIs.....	145
Configure native and PAM authentication.....	148
ASE management, access and audit logs.....	150
Change management log levels.....	152
Purge log files.....	153
Configure syslog.....	153
Email alerts and reports.....	154
Sideband ASE.....	160
Sideband ASE configuration - ase.conf.....	162
API naming guidelines.....	169
Defining an API using API JSON configuration file in sideband mode.....	170
Activate API cybersecurity.....	174
API deception environment.....	191
ABS AI-based security.....	193
Configure Google Pub/Sub.....	197
REST APIs for sideband token and authentication.....	199

CLI for sideband ASE.....	203
Inline ASE.....	210
Inline ASE configuration - ase.conf.....	211
API naming guidelines.....	219
Defining an API using API JSON configuration file in inline mode.....	219
API routing.....	224
Real-time API cybersecurity.....	227
API deception environment.....	247
ASE DoS and DDoS protection.....	250
ABS AI-based security.....	259
CLI for inline ASE.....	263
ASE REST APIs using Postman.....	272
ASE self-signed certificate with Postman.....	273
View ASE REST APIs in Postman.....	273
REST API for inline and sideband ASE.....	276
Audit log.....	299
Supported encryption protocols.....	302
Autoscaling ASE in AWS environment.....	303
Create an AMI for ASE.....	303
Creating an IAM role in the security, identity, and compliance.....	304
Create the security group.....	306
Creating launch configuration.....	306
Creating an auto-scale group.....	307
ASE log messages.....	307

## **ABS AI Engine..... 309**

Administration.....	309
ABS License.....	309
Change default settings.....	310
Obfuscate passwords.....	312
ABS POC mode.....	313
Start and Stop ABS.....	314
ABS users for API reports.....	315
ABS directory structure.....	315
Configure SSL.....	316
Configure time zone - ABS.....	316
Import existing CA-signed certificates.....	317
ABS ports.....	318
ABS configuration - abs.properties.....	318
Connect ABS to API Security Enforcer.....	322
ABS cluster.....	325
ABS logs.....	326
Purge the processed access logs from ABS.....	327
Purge MongoDB data.....	327
Reset MongoDB.....	329
Add a member to an existing MongoDB replica set.....	332
Remove a member from a MongoDB replica set.....	333
Verify MongoDB SSL certificates.....	334
Email alerts and reports.....	335
AI Engine training.....	338
Training the ABS model.....	338
AI Engine training variables.....	339
Training period status.....	341
Update the training variables.....	341
Tune thresholds for false positives.....	342

Resetting trained APIs.....	346
Disable attack detection.....	347
API discovery and configuration.....	347
API discovery process.....	349
Discovery Subpaths.....	351
ABS Discovery API.....	352
Manage discovery intervals.....	354
Global configuration update REST API.....	355
REST API attacks.....	357
REST API attack types.....	358
Attacks based on username activity.....	360
Attacks based on API Key activity.....	361
Attacks based on cookie activity.....	361
Attacks based on token activity.....	363
Attacks based on IP activity.....	365
WebSocket API attack detection.....	366
Attack detection on root API.....	368
Manage attack blocking.....	369
ABS blacklist reporting.....	369
Enable or disable attack IDs.....	372
TTL for client identifiers in ABS.....	374
Automated ASE attack blocking.....	377
Attack management in ASE.....	377
Attack reporting.....	381
Consolidated result of attack types.....	382
Real-time Detected attacks for inline ASE.....	385
Anomalous activity reporting.....	388
Deception and decoy API.....	389
Blocked connection reporting.....	391
API forensics reporting.....	393
API metrics reporting.....	399
Username based metrics.....	401
API Key based metrics.....	402
OAuth token based metrics.....	405
List valid URL.....	408
Hacker's URL.....	409
Backend error reporting.....	411
API DoS and DDoS threshold.....	411
API reports using Postman.....	413
Using an ABS self-signed certificate with Postman.....	413
View ABS reports in Postman.....	414
ABS CLI.....	415
ABS REST API format.....	416
ABS external REST APIs.....	417
Admin REST API.....	418
Discovery REST API.....	421
Decoy REST API.....	423
Threshold REST API.....	425
Metrics REST API.....	428
API Key Metrics REST API.....	431
OAuth2 Token Metrics REST API.....	433
Username Metrics REST API.....	435
Anomalies REST API.....	439
Anomalies across APIs.....	441
OAuth2 Token Forensics REST API.....	442
IP Forensics REST API.....	443

Cookie Forensics REST API.....	445
Token Forensics REST API.....	446
API Key Forensics REST API.....	448
Username Forensics REST API.....	449
Attack Types REST and WebSocket APIs.....	451
Flow Control REST API.....	452
Blocked Connection REST API.....	453
Backend Error REST API.....	454
List Valid URLs REST API.....	456
List Hacker's URL REST API.....	457
Delete Blacklist REST API.....	459
Threshold range for Tn and Tx.....	460
ABS log messages.....	463
<b>PingIntelligence Dashboard.....</b>	<b>465</b>
Administration.....	466
Installation prerequisite.....	466
Install PingIntelligence Dashboard.....	467
Access PingIntelligence Dashboard.....	470
Start and stop Dashboard.....	472
Obfuscate keys and passwords.....	473
Configure time zone - PingIntelligence Dashboard.....	475
Configure Dashboard properties - dashboard.properties.....	476
Configure WebGUI properties - webgui.properties.....	479
Configure dashboard engine.....	485
Configure authentication - SSO with PingFederate.....	490
Configuring SSO with PingOne.....	498
Automatic rollover index.....	504
Splunk for PingIntelligence.....	505
Dashboard log messages.....	515
Dashboard.....	519
Interactive blacklists.....	520
Dashboard time series.....	522
Per API activity.....	523
Forensic reports.....	525
Cross API attacks and recently discovered APIs.....	530
Attack insights.....	531
API groups.....	534
Administering API groups.....	536
Discovered APIs.....	540
Configure API discovery.....	541
Edit the discovered APIs.....	545
Viewing and managing Indicators of Attack.....	548
Enabling or disabling attacks.....	551
Determining the training status of an API.....	553
Configuring training settings.....	555
<b>PingIntelligence Integrations.....</b>	<b>557</b>
<b>Akana API gateway sideband integration.....</b>	<b>558</b>
Prerequisites.....	559
Add PingIntelligence ASE APIs.....	560
Secure PingIntelligence ASE APIs.....	564

Capture ASE details.....	566
Deploy PingIntelligence policies.....	568
<b>PingIntelligence Apigee integration.....</b>	<b>581</b>
Prerequisites to deploying PingIntelligence shared flow.....	582
Downloading and installing the automated policy tool.....	583
About Apigee properties file configuration.....	584
Resetting timeout configurations.....	588
Extract user information from access tokens.....	589
Deploying the PingIntelligence policy.....	590
Deploying the PingIntelligence policy for flow hook.....	590
Deploying the PingIntelligence policy for Flow Callout.....	592
Configuring PingIntelligence Flow Callout in Apigee.....	593
Changing the deployed policy mode.....	597
Add API definitions to ASE.....	599
Undeploying the PingIntelligence policy.....	599
Undeploying the PingIntelligence policy for Flow Hook.....	600
Undeploying the PingIntelligence policy for Flow Callout.....	600
Troubleshooting mismatch of self-signed certificates.....	600
<b>AWS API gateway integration.....</b>	<b>601</b>
PingIntelligence AWS API Gateway Integration.....	601
Prerequisites.....	602
Configure automated policy tool.....	604
Deploy PingIntelligence Policy for AWS.....	614
Next steps - Integrate into your API environment.....	615
Uninstall CloudFront sideband policy.....	615
<b>Axway API gateway integration.....</b>	<b>616</b>
Axway sideband integration.....	616
Prerequisites.....	618
Deploy PingIntelligence policy.....	620
API discovery.....	633
<b>Azure API gateway integration.....</b>	<b>640</b>
Azure APIM sideband integration.....	640
Prerequisites.....	642
Deploy PingIntelligence policy.....	644
Integrate PingIntelligence.....	649
Configure ASE persistent connection.....	649
<b>CA API gateway integration.....</b>	<b>649</b>
PingIntelligence - CA API gateway sideband integration.....	649
Prerequisite.....	651
Install and configure the PingIntelligence bundle.....	651
Import PingIntelligence policy.....	655
Configure ASE token and certificate.....	655
Apply PingIntelligence policy.....	656
Integrate PingIntelligence.....	658

<b>F5 BIG-IP integration.....</b>	<b>658</b>
F5 BIG-IP PingIntelligence integration.....	658
Prerequisites.....	659
Deploy PingIntelligence policy.....	660
Import and configure PingIntelligence policy.....	660
Create LX plugin.....	664
(Optional) Create backend server pool and frontend virtual server.....	665
Add PingIntelligence policy.....	668
<b>IBM DataPower gateway integration.....</b>	<b>670</b>
IBM DataPower Gateway sideband integration.....	670
Prerequisites.....	671
Deploy PingIntelligence policy.....	672
Add PingIntelligence policy components.....	672
Configure PingIntelligence policy components.....	675
<b>Kong API gateway integration.....</b>	<b>677</b>
PingIntelligence - Kong API gateway integration.....	677
Prerequisites.....	678
Deploy PingIntelligence policy.....	679
Extracting user information when OIDC plugin is used.....	683
<b>Mulesoft API gateway integration.....</b>	<b>684</b>
Mulesoft sideband integration.....	684
Prerequisites.....	686
Deploy PingIntelligence policy.....	687
PingIntelligence for Mulesoft 3.9.....	688
PingIntelligence for Mulesoft 4.x.....	690
Apply PingIntelligence policy.....	692
Remove existing PingIntelligence policy.....	696
Next steps - Integration.....	698
<b>NGINX integration.....</b>	<b>698</b>
NGINX sideband integration.....	698
Prerequisites.....	699
NGINX for RHEL 7.6.....	702
Configure NGINX for PingIntelligence.....	703
NGINX for Ubuntu 16.04.....	707
Configure NGINX for PingIntelligence.....	708
Next steps - integration.....	713
<b>NGINX Plus integration.....</b>	<b>714</b>
NGINX Plus sideband integration.....	714
Prerequisites.....	716
NGINX Plus for RHEL 7.6.....	719
Configure NGINX Plus for PingIntelligence.....	719
Configuring NGINX Plus with PingAccess agent for PingIntelligence.....	726
NGINX Plus for Ubuntu 16.0.4.....	731
Configure NGINX Plus for PingIntelligence.....	732



NGINX Plus for Debian 9.....	738
Configure NGINX Plus for PingIntelligence.....	739
<b>PingAccess API gateway integration.....</b>	<b>747</b>
PingAccess sideband integration.....	747
Prerequisites.....	748
Configure PingFederate to extract token attributes.....	749
Deploying the PingIntelligence policy.....	750
Configure ASE persistent connection.....	754
API discovery.....	755
Handle exceptions.....	756
<b>PingFederate integration.....</b>	<b>758</b>
PingFederate sideband integration.....	758
Prerequisites.....	759
Deploying the PingIntelligence policy.....	761
Configuring PingIntelligence servlet filter.....	761
Configuring API JSON.....	763
<b>WSO2 API gateway integration.....</b>	<b>764</b>
PingIntelligence WSO2 integration.....	764
<b>PingIntelligence Docker toolkit.....</b>	<b>764</b>
Untar the Docker toolkit.....	765
Build the PingIntelligence Docker images.....	766
Environment variables exposed in Docker images.....	768
ILM policy configuration in Dashboard.....	773
Using environment variables - example.....	775
<b>PingIntelligence Hardening Guide.....</b>	<b>776</b>
PingIntelligence security hardening guide.....	776
<b>PingIntelligence Monitoring Guide.....</b>	<b>777</b>
PingIntelligence Health Check Guide.....	777
Perform health checks on ASE.....	777
Perform health checks on ABS AI Engine.....	778
Perform health checks on PingIntelligence Dashboard.....	778
Logs, port numbers, PIDs.....	781
PingIntelligence Troubleshooting Guide.....	783
Troubleshooting issues between on-premise ASE and PingOne API Intelligence.....	783
<b>PingIntelligence Upgrade Guide.....</b>	<b>784</b>
Step-1 Upgrading MongoDB.....	785
Step-2 Upgrading ABS AI Engine.....	787
Step-3 Upgrading PingIntelligence Dashboard.....	788
Step-4 Upgrading ASE.....	793
Verifying MongoDB indexes.....	794

**PingIntelligence Usecases.....795**  
    Converting SSL certificates to ASE compatible format.....795

# PingIntelligence for APIs

---

PingIntelligence for APIs uses artificial intelligence (AI) to secure APIs in your environment by identifying and automatically blocking cyberattacks on APIs, exposing active APIs, and providing detailed reporting on all API activity.

## Release Notes

- [Current](#)
- [Previous releases](#) on page 14

## Get Started with PingIntelligence

- [PingIntelligence for APIs Overview](#) on page 11
- [Docker PoC setup](#) on page 14
- [Automated deployment](#)
- [Manual deployment](#)
- [PingIntelligence Kubernetes PoC](#) on page 34
- [PingIntelligence Cloud service](#) on page 37

## Use PingIntelligence

- [Converting SSL certificates to ASE compatible format](#) on page 795
- [PingIntelligence Integrations](#) on page 557

## Troubleshoot PingIntelligence

- [PingIntelligence Health Check Guide](#) on page 777
- [PingIntelligence Troubleshooting Guide](#) on page 783

## Learn More

- [Community](#)
- [Partner portal](#)

# PingIntelligence for APIs Overview

---

PingIntelligence for APIs uses artificial intelligence (AI) to secure APIs in your environment. It identifies and automatically blocks cyberattacks on APIs, exposes active APIs, and provides detailed reporting on all API activity.

Leveraging AI models specifically tailored for API security, PingIntelligence brings cyberattack protection and deep API traffic insight to existing API gateways and application server-based API environments. It detects anomalous behavior on APIs and the data and applications exposed through APIs. It also automatically block attacks across your API environment.

## Key components

PingIntelligence is a suite of three interconnected components, API Security Enforcer (ASE), API Behavioral Security (ABS) AI engine, and PingIntelligence Dashboard:

### ASE


The first processing layer in PingIntelligence. It captures the metadata of the monitored APIs and sends it to the ABS AI engine. You can deploy ASE in two modes, inline and sideband. When deployed in inline mode, ASE directly receives the API traffic or can work alongside other load balancers like AWS ELB. In sideband mode, ASE integrates with API gateways in an ecosystem and extends the cybersecurity of PingIntelligence.

### ABS AI engine

The AI engine infers the API traffic patterns in the metadata from ASE. It builds machine learning models that self-train based on the API traffic. ABS detects the attacks on APIs and blocks the clients from which the attacks originate. It also provides in-depth forensics on the activities performed by a client. The reports provide detailed information on the activity from an individual token, IP address, cookie, API key, or username. In addition to attack detection, ABS continuously discovers the new and unknown APIs in an API ecosystem and brings them under observation.

### PingIntelligence Dashboard

PingIntelligence Dashboard provides rich analytics on API activities in an environment. It gives granular insights at an API level and across APIs. It can provide information on the training status of APIs, different kinds of attacks on APIs, and much more. PingIntelligence Dashboard also supports admin activities such as attack management and discovery of APIs.



#### Related links

- [Sideband ASE](#) on page 160
- [Inline ASE](#) on page 210
- [ABS AI Engine](#)
- [PingIntelligence for APIs Dashboard](#)

## Release Notes

---

The following release notes summarize the changes in current and previous PingIntelligence product updates:

- [PingIntelligence 5.0.1 - August 2021](#) on page 13
- [PingIntelligence 5.0 - June 2021](#) on page 13
- [Previous releases](#) on page 14

## PingIntelligence 5.0.1 - August 2021

---

### New in PingIntelligence

- The API Security Enforcer (ASE) now supports integration with [PingOne](#) platform. You can deploy ASE on-premise in either inline or sideband mode and integrate it with [PingOne](#). This hybrid integration delivers API security through the new PingOne API Intelligence service. For more information, see [PingOne API Intelligence](#).
- The PingIntelligence Docker toolkit adds environment variables to support integration of ASE with the PingOne API Intelligence platform. For more information, see [PingIntelligence Docker toolkit](#) on page 764. The new environment variables support:
  - Configuring gateway credentials to use for connecting ASE with the PingOne API Intelligence platform.
  - Setting the ABS AI engine deployment type to cloud or on-premise.

## PingIntelligence 5.0 - June 2021

---

PingIntelligence 5.0 provides the following enhancements:

- All PingIntelligence components now support a single unified license.
- PingIntelligence now supports up to 10 subpath levels for API base paths when API Security Enforcer (ASE) is deployed in sideband mode. Subpath depth is the number of sub-paths for a unique API definition. For more information, see [Discovery Subpaths](#) on page 351.

### New in PingIntelligence Dashboard

The PingIntelligence Dashboard is enhanced to provide improved user experience for the following functionalities:

- The updated **Attack management** page gives a comprehensive view of Indicators of Attacks( IoAs ) on a per client basis. A separate **Enable / Disable Attacks** page helps the administrators in efficient attack management. For more information, see [Viewing and managing Indicators of Attack](#) on page 548.
- The **Training Status** page now allows you to view the training status for an API by selecting the API from a drop-down list. The page also has a new capability to download per API and across API attack thresholds in a JSON formatted text file. For more information, see [Determining the training status of an API](#) on page 553.

### New in ASE

ASE has the following new additions:

- **External Load Balancer support for ASE to ABS AI Engine traffic** -ASE can be optionally configured to utilize external load balancers to distribute traffic across ABS AI Engine nodes. This provides the flexibility to support auto-scale of ABS AI Engine nodes and more high availability configurations.
- **REST API for sideband token management** -The `Token` API helps to create, import, and delete ASE sideband tokens. You can also retrieve the list of tokens issued by ASE.
- **REST API for sideband authentication** -The `Authentication` API helps to enable and disable ASE sideband authentication. You can also retrieve the authentication status.

For more information, see [REST APIs for sideband token and authentication](#) on page 199.

### New in sideband integration policies

- **NGINX plus policy** - The updated PingIntelligence sideband policy can seamlessly integrate with NGINX Plus R22 or R23 systems. This enhanced policy supports NGINX nodes with PingAccess agents installed and can capture user information from the PingAccess token introspection. For more information, see [NGINX Plus for RHEL 7.6](#) on page 719.
- **Apigee policy** - The updated PingIntelligence sideband policy adds optional asynchronous communication between Apigee and ASE for improved performance when deployed in environments that do not require automated client blocking. For more information, see [PingIntelligence Apigee integration](#) on page 581.
- **Kong policy** - The PingIntelligence sideband policy is enhanced to support extraction of user information from JWTs when OpenID Connect (OIDC) plugin is installed in a Kong gateway. For more information, see [PingIntelligence - Kong API gateway integration](#) on page 677.

### New in deployment tools

The following PingIntelligence deployment tools have been modified to support integration with PingOne:

- [PingIntelligence Ansible deployment framework](#)
- [PingIntelligence Docker PoC deployment](#)
- [PingIntelligence Kubernetes PoC](#) on page 34
- [PingIntelligence Docker toolkit](#) on page 764

## Previous releases

---

Click on the following links, for information about enhancements and issues resolved in previous major and minor releases of PingIntelligence for APIs.

- [PingIntelligence 4.1 Release Notes](#)
  - [PingIntelligence 4.1.0 Release Notes](#)
  - [PingIntelligence 4.1.1 Release Notes](#)
- [PingIntelligence 4.2 Release Notes](#)
- [PingIntelligence 4.3 Release Notes](#)
- [PingIntelligence 4.4 - December 2020](#)
  - [PingIntelligence 4.4.1 - April 2021](#)

## PingIntelligence PoC

---

### PingIntelligence Docker PoC deployment


---

#### Docker PoC setup

This guide describes the installation and execution of PingIntelligence for APIs software in a Docker environment for inline and sideband deployment. The automation script imports and installs the Docker images. A script is run to generate normal API traffic to train the AI engine. After training is complete, another script is run to send a mixture of normal and attack traffic. The guide then explains how to access a graphical dashboard which shows activity on the test environment and detailed reporting on the API activity.

This Docker Evaluation Guide provides instructions for deploying a test configuration as shown in the diagram. The docker setup can be deployed in an inline mode where the client traffic directly reaches ASE. It can also be deployed in sideband mode where the API traffic reaches the API gateway and the

API gateway sends the request to ASE. For more information on sideband and inline deployment, see [Sideband ASE](#) on page 160 and [Inline ASE](#) on page 210.



**Note:** The Docker images provided are only for evaluation purpose of PingIntelligence for APIs product. They should not be used in production deployments or for setting up environments for security testing.

## Installation requirements

Here is a summary of the software, documentation, and server requirements.

### Docker images

Download the Docker PoC package. The Docker package creates the following five containers on the host machine:

1. API Security Enforcer (ASE)
2. API Behavioral Security Engine (ABS)
3. PingIntelligence for APIs Dashboard
4. Client that sends the traffic
5. Google Go App server

**PingIntelligence license:** PingIntelligence for APIs license is required to start ASE and ABS. Contact the Ping Identity sales team to access the trial license.

### Postman reporting

ABS generates various REST API reports. You can view these reports using Postman client or any other REST API client. PingIntelligence provides a Postman collection to view the various ABS reports. Download the Postman client from the [Postman site](#).

### Documentation

Refer the following Admin Guides:

- [ASE Admin Guide](#) - Refer the ASE admin guide to learn about administering ASE, inline ASE, real-time cybersecurity and so on.

- [ABS Admin Guide](#) - Refer to the ABS admin guide to learn about administering ABS, AI engine training, various REST API reports and so on.
- [Dashboard on page 27](#) - Refer to the Dashboard admin guide to learn about how to access and use Dashboard.

### Server requirements

The set up requires one machine which hosts all the six Docker images. The server requirement for the machine is specified in the following table:

<b>OS</b>	Ubuntu 18.04 LTS
<b>Hardware</b>	8 CPUs, 32 GB RAM, 500 GB Storage

**Note:** The server requirement is for a single server for evaluation purpose only.

### Docker version

The setup requires the Community Version (CE) of Docker 17.06 or higher. Make sure that the Docker infrastructure is set up before proceeding with installation and setup of PingIntelligence for APIs software.

## Download and untar Docker package

Contact PingIdentity Sales for instructions on accessing the Docker package. Once the Docker package is available, download and save it in the `/opt` directory.

Complete the following steps before Installing and loading the Docker images:

1. Untar the package by running the following command:

```
$sudo tar -xf /opt/pi-api-docker-poc-5.0.tar.gz
```

2. Change the directory to `/opt/pingidentity/docker-poc`.

**Note:** By default the Docker PoC package is configured to be deployed in inline mode. If you want to deploy Docker in sideband mode, see [Configure Docker PoC for sideband](#) on page 16.

### Install PingIntelligence for APIs license

PingIntelligence ASE and ABS require a valid license to start. The license file for both the products is named `PingIntelligence.lic`. Complete the following

Copy the license file in the `pingidentity/docker-poc/license` directory. Make sure that the license file is named as `PingIntelligence.lic` Following is a sample of the license file:

```
ID=981894
Product=PingIntelligence
Version=5.0
IssueDate=2021-07-01
EnforcementType=0
ExpirationDate=2020-12-30
Tier=Subscription
SignCode=
Signature=
```

## Configure Docker PoC for sideband

You can optionally configure the Docker PoC environment for a sideband deployment with an API Gateway. The Docker PoC package ships with sample API swagger definition files which can be adapted



to support your API Gateway environment. PingIntelligence sideband policies and documentation can be downloaded from the Ping download site.

### Configure Docker package for sideband

Navigate to `config` directory and edit the `poc.config` file to set mode as sideband. Following is a sample `poc.config` file.

```
# API Security Enforcer mode.
# allowed values: inline, sideband
ase_mode=inline

# initial training period in hours
training_period=1

# poc mode for training
poc_mode=true

#####
## Below Configuration is applicable only when ase_mode is set to sideband
##
#####

# API gateway ip address or dns name
gateway_ip=
# API gateway port
gateway_port=443
# set gateway protocol if API gateway is configured with ssl
# else set it to tcp
# allowed values: tcp, ssl
gateway_protocol=ssl
```

The following table describes the variables.

Variable	Description
ase_mode	Defines the deployment mode of ASE. Possible values are <code>inline</code> and <code>sideband</code> . Default value is <code>inline</code> .
training_period	Training period of AI engine in hours. Minimum value is 1-hour.
poc_mode	Defines the mode in which ABS AI engine trains its models. Default value is <code>true</code> . It is recommended to keep the value as <code>true</code> . If you change it to <code>false</code> , it may take longer time to set all the attack thresholds.
gateway_ip	Configure the URL for API gateway.
gateway_port	Port number of API gateway URL
gateway_protocol	API gateway protocol. Possible values are <code>ssl</code> or <code>tcp</code> .

### Install and load Docker images

To install and load Docker images, enter the command on the host Ubuntu 18.04 machine. This command loads and installs the Docker images from the images directory:

```
/opt/pingidentity/docker-poc$ sudo ./bin/start.sh install
```

```
ubuntu@ip-172-31-90-119:~/pingidentity/docker-poc/bin$ sudo ./start.sh
install
Tue Oct 13 05:05:14 UTC 2020 : loading ASE image
Loaded image: pingidentity/ase:5.0
Tue Oct 13 05:05:15 UTC 2020 : loading ABS image
Loaded image: pingidentity/abs:5.0
Tue Oct 13 05:05:16 UTC 2020 : loading Dashboard image
Loaded image: pingidentity/dashboard:5.0
Tue Oct 13 05:05:19 UTC 2020 : loading mongo image
Loaded image: pingidentity/mongo:4.2.0
Tue Oct 13 05:05:20 UTC 2020 : loading client image
Loaded image: pingidentity/client:5.0
Tue Oct 13 05:05:20 UTC 2020 : loading server image
Loaded image: pingidentity/server:5.0
Tue Oct 13 05:05:21 UTC 2020 : Installation completed successfully
```

## Setup the PoC environment

To start the Docker containers and setup, enter the following command on the host Ubuntu machine:

```
/opt/pingidentity/docker-poc$ sudo ./bin/start.sh setup
```

```
Tue Mar 31 05:12:28 UTC 2020 : Starting setup scripts
vm.max_map_count = 262144
Training period configured: 1 hour(s)
Creating network pingidentity_net
Creating service pingidentity_ase
Creating service pingidentity_dashboard
Creating service pingidentity_server
Creating service pingidentity_client
Creating service pingidentity_mongo
Creating service pingidentity_abs
Tue Mar 31 05:12:30 UTC 2020 : Setup successful
```

## Verify ASE and ABS startup

Wait for a minute after the successful completion of the set up and enter the following command to verify that ASE and ABS have started:

```
#sudo docker service logs pingidentity_ase | grep 'API Security Enforcer
started'
#sudo docker service logs pingidentity_abs | grep 'ABS started'
```

If a wrong license is installed, the following error is displayed:

```
Fri Jun 18 06:32:27 UTC 2021 : Starting setup scripts
License not found. Please place PingIntelligence.lic file at /<pi-ininstallpath>/
pingidentity/docker-poc/license/ location
```

**Note:** If PingIntelligence for APIs Dashboard is configured with SSO mode, then update the content of `cert/webgui-sso-oidc-provider.crt` with the PingFederate public certificate.

## Start the training

The PingIntelligence for APIs AI engine needs to be trained before it can start detecting attacks on your APIs. Enter the following command to start the training. The training duration is 85 minutes.

```
/opt/pingidentity/docker-poc$ sudo ./bin/start.sh training
```

```
root@vortex-108:/opt/pingidentity/docker-inline-poc$ sudo ./bin/start.sh
training
Tue Mar 31 06:44:25 UTC 2020 : Starting model training scripts
Tue Mar 31 06:44:25 UTC 2020 : Model training started. Wait 1 hr 25 minutes
for the model training to complete.
```

## Generate sample attacks

To generate sample attacks on the preconfigured APIs, enter the following command:

```
/opt/pingidentity/docker-poc$ sudo ./bin/start.sh attack
```

```
root@vortex-108:/opt/pingidentity/docker-poc$ sudo ./bin/start.sh attack
Tue Mar 31 09:13:02 UTC 2019 : Starting attack scripts
Tue Mar 31 09:13:02 UTC 2019 : Attack started.
```

## API deception

You can view the deception APIs by running the following command. The deception API is part of the set up. The deception command completes the following steps:

- Enables ASE detected attacks
- Fetches the list of configured APIs from ASE
- Sends traffic to the decoy API and receives a 200 OK response
- Send traffic to a regular API (for example, shopapi). The connection is blocked because any client which previously accessed a decoy API is not allowed access to "production" APIs.

**Note:** API deception works only for inline Docker PoC setup.

Execute the following script to test API deception:

```
root@vortex-108:/opt/pingidentity/docker-poc$ sudo ./bin/start.sh deception
Enabling enable_ase_detected_attack on ASE...
Press any key to continue
ASE Detected Attack is now enabled
Fetching the list of APIs from ASE
Press any key to continue
decoy ( loaded ), http, decoy: out-context, client_spike_threshold: 0/
second, server_connection_queueing: disabled
shop-books ( loaded ), http, client_spike_threshold: 300/second,
server_connection_queueing: disabled
shop-electronics ( loaded ), http, decoy: in-context,
client_spike_threshold: 700/second, server_connection_queueing: enabled
shop ( loaded ), http, decoy: in-context, client_spike_threshold: 300/
second, server_connection_queueing: disabled
Sending traffic to "decoy API" with client IP 10.10.10.10...
Press any key to continue
curl -v http://localhost:8000/decoy/myhome -H "X-Forwarded-For: 10.10.10.10"
* Trying 127.0.0.1...
* Connected to localhost (127.0.0.1) port 8000 (#0)
> GET /decoy/myhome HTTP/1.1
> Host: localhost:8000
> User-Agent: curl/7.47.0
> Accept: */*
> X-Forwarded-For: 10.10.10.10
>
< HTTP/1.1 200 OK
< Server: ASE
```

```

< Content-Length: 2
< Connection: close
<
* Closing connection 0
OK
Accessing regular API using client IP 10.10.10.10...
Press any key to continue
curl -v http://localhost:8000/shopapi/login -H "Host: shopapi" -H "Content-
Type: application/text" -H "X-Forwarded-For: 10.10.10.10" -d 'user=root'
* Trying 127.0.0.1...
* Connected to localhost (127.0.0.1) port 8000 (#0)
> POST /shopapi/login HTTP/1.1
> Host: shopapi
> User-Agent: curl/7.47.0
> Accept: */*
> Content-Type: application/text
> X-Forwarded-For: 10.10.10.10
> Content-Length: 9
>
* upload completely sent off: 9 out of 9 bytes
< HTTP/1.1 401 Unauthorized
< Server: ASE
< Connection: close
< content-length: 19
<
* Closing connection 0
Error: Unauthorized
Error: Unauthorized

```

## API discovery

ABS discovers the APIs when the discovery is enabled. The automated setup sets up the discovery mode. APIs are discovered by ABS when a global API is defined in PingIntelligence ASE. The discovered APIs from ABS are added to ASE. API model training starts after the APIs are added in ASE. For more information, See [API discovery and configuration](#) on page 347.

## Access PingIntelligence Dashboard

Access the PingIntelligence for APIs Dashboard from a browser at this default URL: [https://<pi\\_install\\_host>:8030](https://<pi_install_host>:8030).

### Users

There are two pre-configured login users in PingIntelligence for APIs Dashboard :

- admin
- ping\_user

Multiple users can share the admin and ping\_user logins simultaneously on PingIntelligence Dashboard. The admin user has access to all PingIntelligence Dashboard functions. A ping\_user can only view all the API dashboards.


At the login screen, login as admin or ping\_user. The default password for both the users is changeme.

**CAUTION:** You must change the default password for production deployments. However, in a Docker PoC deployment use the default password.

You can change the password using the following CLI command.

```
# <pi_install_dir>/webgui/bin/cli.sh -u admin update_ui_password --username
-value <admin or ping_user> --new-password -p
```

```
Enter admin password > <current admin password>
Enter new password > <new password>
Reenter new password > <new password>
success: password updated.
```



**Note:** If the Dashboard is not accessible, check if the default port (8030) was changed by your system administrator.

PingIntelligence Dashboard is categorized into the following components:


- **Main Dashboard** - Available for `admin` and `ping_user`
- **APIs** - Available only for `admin` user
- **Discovered APIs** - Available only for `admin` user
- **Attack Management** - Available only for `admin` user
- **License**

#### Session management

The PingIntelligence Dashboard allows you to configure the maximum number of active sessions. You can set the `pi.webgui.session.max-active-sessions` parameter in the `<pi_install_dir>/webgui/config/webgui.properties` file to limit the maximum number of allowable active sessions. The default value is 50.

**Delete active sessions-** You can delete active sessions using the following CLI command. The current active users will be prompted to re-login in to the Dashboard.

```
# <pi_install_dir>/webgui/bin/cli.sh -u <username> -p <password>
delete_sessions
```

 **Note:** You need to have Admin user privileges to delete active user sessions.

## API

The API tab displays all the APIs available in ABS AI engine.

- **API name:** API name used by PingIntelligence
- **Prediction mode:** A `true` status means that at least one system generated threshold value is set, while a `false` status means that the API is still under training mode
- **Training duration:** The minimum configured time in hours configured in ABS AI engine to train an API. This is configured in `abs_init.js` in ABS. For more information, see [AI Engine training](#) on page 338
- **URL:** API basepath URL configured in the API JSON file. For more information, see [API JSON definition](#)
- **Host name:** Host name of the API configured in the API JSON file. For more information, see [API JSON definition](#)
- **Protocol:** The protocol configured in the API JSON file. For more information, see [API JSON definition](#)
- **API type:** API type can be `regular`, `decoy - incontext`, or `decoy-out-of-context`. For more information on deception, see [API deception environment](#) on page 247
- **Token:** A `true` status means that PingIntelligence will use OAuth tokens for reporting and attack detection. For more information, see [API JSON definition](#)
- **API Key header and API key query string (QS):** The API Key values configured in the API JSON file and used for reporting and attack detection.. For more information, see [API JSON definition](#)
- **Cookie:** The cookie value configured in the API JSON file and used for reporting and attack detection. Displays blank, if cookie was not configured in API JSON. For more information, see [API JSON definition](#)
- **Servers:** The backend API server configured in the API JSON file - "\*" supports all the host names. For more information, see [API JSON definition](#)

Using the toggle button, you can hide or display information for the API in the PingIntelligence Dashboard.. This provides the flexibility to display only selected APIs. Even if an API is hidden from the API dashboard, the dashboard engine keeps fetching API data from ABS AI engine. The hidden API is moved to the end of list. If the APIs are paginated, the hidden APIs are moved to the last page. When you toggle the button to display a hidden API,

the dashboard displays data for the API on the Dashboard. Here is a screenshot of APIs

The screenshot shows the PingIntelligence API Dashboard. The left sidebar contains navigation options: Dashboard, APIs, Attack Management, and License. The main content area is titled 'APIs' and features a search bar and a 'Sort Based On' dropdown. Three API entries are listed:

- shop**: Created: Thu Dec 19 00:41:00 2019 – Training Started: Thu Dec 19 00:42:21 2019. API NAME: shop, PREDICTION-MODE: true, TRAINING DURATION: 1hour, URL: /shopapi, HOST NAME: shopapi, PROTOCOL: http, API TYPE: decoy-incontext, TOKEN: false, APIKEY HEADER: MyAPIKey, APIKEY QS: , COOKIE: JSESSIONID, SERVERS: 2.
- shop-electronics**: Created: Thu Dec 19 00:41:00 2019 – Training Started: Thu Dec 19 00:42:21 2019.
- shop-books**: Created: Thu Dec 19 00:41:00 2019 – Training Started: Thu Dec 19 00:42:21 2019.

Each entry has a toggle switch and a menu icon on the right. The bottom left corner of the dashboard displays the PingIntelligence logo and copyright information: Copyright © 2019-2023 Ping Identity Corporation. All rights reserved. Version: 4.1.


tab:

### Tune thresholds and unblock clients

The attack management feature of PingIntelligence for APIs Dashboard supports unblocking of clients and tuning thresholds values for attacks. Click on the **Attack Management** tab on the left pane and click **Tune/ Unblock** to access it.


**Note:** You need to have Admin user privileges to perform **Unblock** and **Tune** operations on a client identifier.

The following screenshot illustrates the Attack Management UI.



### Interactive blacklists

The PingIntelligence for APIs Dashboard provides the capability of unblocking or tuning a blacklist directly from the Dashboard. The user can select the client identifier and the Attack management action from the Dashboard. For more information, see [Interactive blacklists](#) on page 28. The following screen shot shows the client identifier blacklists across APIs in the Dashboard.



**Note:** When the user initiates Attack management from the Dashboard, the values for the client identifiers are auto-populated except the API key key-name.

### Unblock a client identifier

Complete the following steps to unblock a client identifier:


1. Select the type of client identifier from the **Client Identifier Type** list.
2. Enter the value of the client identifier.

**Note:** For API Key and Cookie, enter the name and the value.

3. Select the **Unblock Client** check box.
4. Click **Run**.



The following screenshot shows the unblock client operation.



The unblock operation deletes the client identifier from the PingIntelligence ASE and ABS AI engine blacklist. To verify that the client identifier has been deleted from ASE, run the `view_blacklist` CLI command or `blacklist` REST API in ASE. To verify that the client identifier has been deleted from ABS, use the `attacklist` REST API. For more information on ABS blacklist, see [ABS blacklist reporting](#) on page 369.

**Note:** The API keys will not be deleted from the blacklist immediately in ASE if the API Key key-name is not entered. The deletion is delayed until ASE retrieves the blacklist data from ABS.

### Tune threshold

To address false positives, the **Attack Management** feature supports automatic threshold tuning. When tuning thresholds for a specific client identifier, the Attack management functionality does the following:

1. It fetches all the attacks flagged for the client identifier from ABS AI Engine.
2. After it has identified all the attacks, it increases the threshold values for those attacks. At this point, the threshold has moved from `system` defined to `user` defined. For more information on thresholds, see [Tune thresholds for false positives](#) on page 342.

Complete the following steps to tune thresholds:

1. Select the type of client identifier from the **Client Identifier Type** list.
2. Enter the value of the client identifier.
3. Select the **Tune Threshold** check box.

4. Provide the approximate number of days since the client was blocked. The maximum value is 30-days.

**Note:** The value for **How many days ago client was blocked?** gets auto-populated when Attack Management is initiated from the Dashboard interactive blacklist. The value is calculated as follows,

$$\text{How many days ago client was blocked?} = \text{Current date} - \text{Attack detection date} + 1$$


When auto-populating, if the calculated value is more than 30 days, it is trimmed down to 30. You can use the same formula when populating the value manually. The Attack detection date for a client identifier is available in the interactive blacklists.



IP	Detected
[REDACTED]	2020-03-26 16:25
[REDACTED]	2020-03-24 22:07
[REDACTED]	2020-03-24 22:07

5. Click **Run**.

The following screenshot shows tuning threshold for a client identifier.



**PingIntelligence for APIs** MAIN SETTINGS Administrator

**Attack Management**

Tune / Unblock    Enable / Disable Attacks

CLIENT IDENTIFIER TYPE  
Select client identifier type

AMT ACTION  
 Unblock Client  
 Tune Threshold


HOW MANY DAYS AGO CLIENT WAS BLOCKED?  
1

Run

Copyright © 2013-2020 Ping Identity Corporation. All rights reserved. Version: 4.4-Beta


## Dashboard

The Dashboard provides a near real-time snapshot of your API environment. It provides insights on user activity, attack information, blocked connections, forensic data, and much more. The Dashboard makes periodic REST API calls to the ABS (API Behavioral Security) AI engine, which returns JSON reports that are used to generate visualizations and API metrics. The following illustration shows the data flow for API dashboard.




To view the API dashboard, click on **Dashboard**. The Dashboard provides information on the following::

- Global metrics like:
  - Blacklist across APIs for each client identifier. For more information, see [Interactive blacklists](#) on page 28.
  - Total attacks across APIs
  - Total requests across APIs
  - Number of APIs in your environment
- Time series visualization of total number of requests and attacks. For more information, see [Dashboard time series](#) on page 30.
- Data on Per API activity. For more information, see [Per API activity](#) on page 523.
- Data on attacks across APIs. For more information, see [Cross API attacks and recently discovered APIs](#) on page 530.
- Forensic reports across APIs. For more information, see [Forensic reports](#) on page 525.
- Recently discovered APIs in the environment.



### Interactive blacklists

PingIntelligence for APIs Dashboard provides the capability of interactive blacklist management. A blacklist is a list of client identifiers that were detected executing an attack. The dashboard enables you to unblock the blacklisted client identifiers or tune the threshold values for attack types. It supports the following client identifier types- IP address, Cookie, Token, API Key, and Username. You can view the top-500 entries on each blacklist from the dashboard.



Click on the count for any blacklist type, for example, **IP Blacklist**. The dashboard lists the blacklisted IP addresses along with the Detected date..

The following screenshot shows the expanded blacklist:


The screenshot shows the PingIntelligence for APIs dashboard. At the top, there's a navigation bar with 'MAIN' and 'SETTINGS' tabs. The main content area is titled 'Dashboard PingIntelligence for API Dashboard: Active IP Blacklist'. A search bar is present with the placeholder text '>\_ Search... (e.g. status:200 AND extension:PHP)'. On the left, there's a sidebar with navigation options: 'Dashboard', 'APIs', 'Discovered APIs', 'Attack Management', and 'License'. The main content area features a 'Home' button and a prominent box displaying '64 Active IP Blacklist'. Below this is a table with columns 'IP', 'Detected', and 'Action'. The 'Action' column for the first row is expanded, showing a dropdown menu with 'Unblock' and 'Tune' options. At the bottom left, there's a 'Ping Identity' logo and copyright information: 'Copyright © 2019-2020 Ping Identity Corporation. All rights reserved. Version: 4.11'. At the bottom right, there's an 'Export' button with options for 'Raw' and 'Formatted'.

IP	Detected	Action
[Redacted]	2020-03-26 16:25	✓ --Action-- Unblock Tune
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--
[Redacted]	2020-03-24 22:07	--Action--

For each blacklisted IP address, you get the option to Unblock or Tune in the **Action** list. Clicking on either action redirects the dashboard to the Attack management application. Attack management allows you to run the operations for unblocking the client identifiers and tuning the threshold values.

**Note:** The **Action** list is available only for an Admin user. You need to have Admin user privileges to perform **Unblock** and **Tune** operations on a client identifier.

The following screen shot shows the Attack management



UI.


The values in **Client Identifier Type** and **Enter IP Address** get auto-populated into the Attack management application from the dashboard. The **AMT Action** is auto-selected. Click **Run** to execute the operation. For more information on Attack management, see [Tune thresholds and unblock clients](#) on page 23.

**Note:** Dashboard does not populate the API key key-name in the Attack management application when the client identifier is API key. It only populates the API key value.

### Dashboard time series


PingIntelligence Dashboard shows the attacks in a time-series format. To adjust the timeframe viewed on the Dashboard, click between the **time-period** arrows located on the top right corner of the dashboard and select the desired time period.

See the example in the following screen



capture:

The following screen capture shows the total requests and number of attackers data in time series





## ABS detailed reporting

ABS Engine's REST API interface provides access to a range of JSON reports on attacks, metrics, and anomalies. To view these reports, Ping Identity provides templates which can be loaded into Postman to simplify viewing of the JSON reports.

### Install and Configure Postman Software

1. [Download](#) and install the Postman application 6.2.5 or higher.
2. [Download](#) "API Reports Using Postman Collection" from the Automated Docker PoC Installation section of the download site. `ABS_5.0_Environment` and `ABS_5.0_Reports` are files for Postman.
3. Launch the Postman application. Make sure to disable SSL verification in Postman. For more information, see [Using self-signed certificate with Postman](#)
4. Import the downloaded reports files by clicking the **Import** button



5. Click the gear  button in the top right corner
6. In the pop-up window, click **ABS\_5.0\_Environment**.

7. In the Edit Environment pop-up window, configure the following values and click **Update**.
  - a. Server IP Address – IP address of the Docker machine
  - b. Port – Default is 8080
  - c. Access\_Key, Secret\_Key - Default Access\_Key is `abs_ak` and default Secret\_Key is `abs_sk`
  - d. API\_Name – the name of API to view in reports
  - e. Later\_date, Earlier\_date – a range of dates to query
8. In the main Postman app window, select the report to display in the left column and then click **Send**.

The screenshot shows the Postman interface. On the left, the 'Collections' tab is active, displaying a folder named 'ABS\_3.2\_Reports' containing 25 requests. The 'Administration' report is selected. On the right, the details for the 'Administration' report are shown. The request method is 'GET' and the URL is '{{System\_Admin}}'. The 'Body' tab is selected, showing a JSON response in 'Pretty' format. The JSON response is as follows:

```

1 - {
2   "company": "ping identity",
3   "name": "api_admin",
4   "description": "This report contains status information on all",
5   "across_api_prediction_mode": true,
6   "api_discovery": {
7     "subpath_length": "1",
8     "status": true
9   },
10  "apis": [
11    {
12      "api_name": "apikeyquery",
13      "host_name": "*",
14      "url": "/apikeyquery",
15      "api_type": "decoy-incontext",
16      "creation_date": "Fri Dec 07 16:45:05 IST 2018",
17      "servers": 4,
18      "protocol": "https",
19      "cookie": "",
20      "token": false,
21      "training_started_at": "Fri Dec 07 16:47:00 IST 2018",
22      "training_duration": "1 hour",
23      "prediction_mode": true
24    },
25    {
26      "api_name": "ipapp",
27      "host_name": "*",
28      "url": "/ipapp",
29      "api_type": "decoy-incontext",
30      "creation_date": "Fri Dec 07 16:45:05 IST 2018",
31      "servers": 4,
32      "protocol": "https",
33      "cookie": "",
34      "token": false,
35      "training_started_at": "Fri Dec 07 16:47:00 IST 2018",
36      "trainina duration": "1 hour".

```

Other reports which can be generated for a specified time-frame (make sure you specify a time range which covers the time that you ran the attack scripts) include:

- Metrics – shows all activity on the specified API



- Attacks (set Type=0) – shows a list of all attack categories and client identifiers (for example, token, IP address, cookie) associated with the attack
- Backend Errors – shows activity which generated the errors
- IP Forensic Info - set the IP address to an attacker identified in the Attacks report– shows all API activity for the specified IP
- Token Forensic Info - set the Token address to an attacker identified in the Attacks report - shows all API activity for the specified token

## Shutdown the PoC environment

You can stop the Docker PoC setup by entering the following command to delete all containers and the data.

```
root@vortex-108:/opt/pingidentity/docker-inline-poc$ sudo ./bin/stop.sh
Tue Dec 31 09:13:02 UTC 2019 : Starting stop scripts
Removing service pingidentity_aad
Removing service pingidentity_abs
Removing service pingidentity_ase
Removing service pingidentity_client
Removing service pingidentity_mongo
Removing service pingidentity_server
Removing service pingidentity_webgui
Removing network pingidentity_net
Tue Dec 31 09:14:03 UTC 2019 : Stop successful
```

## Appendix: Verify the Setup

Carry out the following basic steps to verify the setup:

### 1. Listing the Docker Containers

List all the containers with the `docker ps` command.

### 2. Get Console Access:

To get console access for any of the Docker, fetch the Container ID of the Docker using the `docker ps` command output and use it in the following command:

```
#docker exec -it <docker-container-id> /bin/bash
```

### 3. PingIntelligence for APIs Products:

The Intelligence products are installed in the `/opt/pingidentity` directory within the Docker.

### 4. Checking the service names:

To get the service names of the containers, run the following command:

```
#docker service ls
```

The service name is the second column in the output.

### 5. Checking the logs of service:

To check the log of any service, use the following command:

```
#docker service logs <service name>
```

**For example** `docker service logs pingidentity_ase`

## PingIntelligence Kubernetes PoC deployment

---

### PingIntelligence Kubernetes PoC

This document discusses the steps for installing PingIntelligence for APIs in Kubernetes cluster.

PingIntelligence ships an example `yaml` file with its Docker toolkit package. You can use this example `yaml` file to deploy PingIntelligence for APIs in a Kubernetes cluster.

The example `yaml` file creates the following resources in the Kubernetes cluster:

- **4 statefulsets** with one container each for MongoDB, ABS AI engine, ASE, and PingIntelligence Dashboard.
- **3 external services (LoadBalancer type)** - One each for ABS AI engine, ASE, and PingIntelligence Dashboard.
- **3 internal services (clusterIP type)** - One each for MongoDB, ABS AI engine and ASE

PingIntelligence supports RHEL 7.9 and Ubuntu 18.04 LTS.

**Note:** This deployment of PingIntelligence on a Kubernetes cluster node is suitable for PoC environments only. It is not suitable for production environments or for security testing environments.

The Kubernetes cluster can be configured on Azure Kubernetes Service(AKS) or on Amazon Elastic Kubernetes Service(EKS).

### Deploying PingIntelligence PoC using Amazon EKS

This section discusses installing PingIntelligence PoC on Kubernetes cluster node using Amazon EKS.

About this task

To deploy PingIntelligence PoC:

Steps

1. Create an Amazon EKS cluster on a RHEL or Ubuntu host. You can use either `eksctl` or AWS CLI for creating the Kubernetes cluster. Refer to the following links, for creating and managing Kubernetes cluster using Amazon EKS.
  - [Getting started with Amazon EKS – eksctl](#)
  - [Getting started with Amazon EKS – AWS CLI](#)
2. Follow the steps in [Deploying PingIntelligence in Kubernetes cluster](#) on page 35, and deploy the PingIntelligence PoC on the Kubernetes cluster created in step-1.

### Deploying PingIntelligence PoC using AKS

This section discusses installing PingIntelligence PoC on Kubernetes cluster node using Azure Kubernetes Service(AKS).

About this task

To deploy PingIntelligence PoC:

Steps

1. Create an AKS cluster. Refer to [Quickstart: Deploy an Azure Kubernetes Service \(AKS\) cluster using the Azure portal](#), for detailed steps.
2. Follow the steps in [Deploying PingIntelligence in Kubernetes cluster](#) on page 35, and deploy the PingIntelligence PoC on Kubernetes cluster created in step-1.

## Deploying PingIntelligence in Kubernetes cluster

About this task

Complete the following steps to deploy PingIntelligence in a Kubernetes cluster:

Steps

1. Download PingIntelligence Docker toolkit from the [download](#) site.
2. Untar the docker toolkit by entering the following command.

```
tar -zxvf <PingIntelligence Docker toolkit>
```

3. Build the PingIntelligence docker images by completing the steps mentioned in [Build the PingIntelligence Docker images](#) on page 766 topic.
4. Navigate to `pingidentity/docker-toolkit/examples/kubernetes` directory to edit the `pi4api-k8s-cloud` file.
5. Edit the environment variable in `pi4api-k8s-cloud` file to configure the ASE deployment mode. The values can be inline or sideband. Following is a snippet of the file showing the environment variable.

```
apiVersion: apps/v1
kind: StatefulSet
metadata:
  name: ase
  labels:
    app: ase
spec:
  serviceName: ase-internal-service
  replicas: 1
  selector:
    matchLabels:
      app: ase
  template:
    metadata:
      labels:
        app: ase
    spec:
      terminationGracePeriodSeconds: 60
      securityContext:
        runAsUser: 10001
        fsGroup: 0
      containers:
        - name: ase
          image: pingidentity/ase:5.0
          imagePullPolicy: Always
          ports:
            - containerPort: 8080
              name: management
          command:
            - "/bin/bash"
            - "-c"
            - "/opt/pingidentity/ase/entrypoint.sh"
          env:
            - name: TZ
              value: "Etc/UTC"
            - name: MODE
              value: "inline"
            - name: ENABLE_CLUSTER
```

```

    value: "true"
  - name: ENABLE_ABS
    value: "true"
  - name: ABS_ENDPOINT
    value: "abs-internal-service:8080"
  - name: ABS_ACCESS_KEY
    value: "abs_ak"
  - name: ABS_SECRET_KEY
    value: "abs_sk"
  - name: ENABLE_SIDEHAND_KEEPALIVE
    value: "false"
  - name: ENABLE_ASE_HEALTH
    value: "false"

```

**6. Add PingIntelligence license in the ConfigMaps section of the pi4api-k8s-cloud file.**

```

PingIntelligence.lic: |
  ID=
  Organization=
  Product=
  Version
  IssueDate=
  EnforcementType=
  ExpirationDate=
  MaxTransactionsPerMonth=
  Tier=
  SignCode=
  Signature=

```

**7. Create a namespace.**

```

$ sudo su
# kubectl create namespace pingidentity

```

**8. Apply the edited pi4api-k8s-cloud.yml file to deploy the resources on the Kubernetes cluster.**

```

# kubectl apply -f pi4api-k8s-cloud.yml -n pingidentity

daemonset.apps/startup-script created
statefulset.apps/mongo created
statefulset.apps/abs created
statefulset.apps/ase created
statefulset.apps/dashboard created
service/abs-external-service created
service/ase-external-service created
service/dashboard-external-service created
service/mongo-internal-service created
service/abs-internal-service created
service/ase-internal-service created

```

**Next steps**

Verify that the deployment is successful by entering the following command.

```

# kubectl get pod -n pingidentity
NAME                READY   STATUS    RESTARTS   AGE
abs-0                1/1    Running   0           139m
ase-0                1/1    Running   0           25m
mongo-0             1/1    Running   1           139m
startup-script-5d5d6 1/1    Running   0           119m
dashboard-0         1/1    Running   1           139m

```

Fetch the IP addresses of ASE, ABS, and Dashboard by entering the following command.

```
# kubectl get svc -n pingidentity
NAME                                TYPE                CLUSTER-IP      EXTERNAL-IP
PORT(S)                             AGE
abs-external-service               LoadBalancer        10.0.64.46      52.151.201.34
8080:31202/TCP                     18h
abs-internal-service               ClusterIP            None            <none>
8080/TCP                             18h
ase-external-service               LoadBalancer        10.0.27.211    52.151.203.229
80:30677/TCP,443:30396/TCP         18h
ase-internal-service               ClusterIP            None            <none>
8020/TCP,8010/TCP                  18h
dashboard-external-service         LoadBalancer        10.0.121.85    52.151.204.1
443:31328/TCP                       18h
mongo-internal-service             ClusterIP            None            <none>
27017/TCP                            18h
```

If you are deploying in the sideband mode, take the NodePort IP address of ASE to use in API gateway integration.

## PingIntelligence Cloud service deployment

---

### PingIntelligence Cloud service

PingIntelligence Cloud deployment has two components which work together to complete your PingIntelligence PoC environment. The PingIntelligence Cloud environment is distributed between the following:

- PingIntelligence ABS, Dashboard, and MongoDB are hosted as a cloud service managed by Ping Identity
- PingIntelligence Cloud Connector (referred to as PingIntelligence ASE in the documentation ) is deployed in your API environment.


PingIntelligence Cloud service can be deployed in two modes:

- Inline mode
- Sideband mode

#### Inline mode

In inline mode, ASE receives API client traffic and routes the traffic to API servers. It can be deployed behind an existing load balancer, such as AWS ELB. In inline mode, ASE terminates SSL connections from API clients and then routes the API requests to the target APIs – running on an API Gateway or app servers, such as Node.js, WebLogic, Tomcat, PHP, etc. To configure ASE to work in Inline


mode, set the `mode=inline` in the `ase.conf` file. The following diagram shows the inline deployment:



### Sideband Mode

In sideband mode, ASE receives API calls from an API gateway which uses policies to send API request and response metadata to ASE. In this mode, the API Gateway still terminates the client requests and manages the traffic flow to the API servers. PingIntelligence currently supports sideband policies on the following platforms, [PingIntelligence API gateway integrations](#).

To configure ASE to work in sideband mode, set the `mode=sideband` in the `ase.conf` file. The following diagram shows the sideband mode of deployment:



For more information on different ASE modes, see the [ASE Admin Guide](#).

## Downloading and installing ASE software

About this task

ASE supports RHEL 7.9 or Ubuntu 18.04 LTS. The provisioned infrastructure can be an EC2 instance, bare metal x86 server, or VMware ESXi. You can install ASE as a root or a non-root user. You can install ASE either by downloading the ASE software from the download site or by using the ASE Docker image provided to you.

### Install ASE by downloading the ASE software

Complete the following steps to install ASE:

## Steps

1. Go the [download site](#)
2. Under PingIntelligence, click on **Select** and navigate to the ASE section to download the ASE binary. Make sure you choose the correct platform binary.
3. After downloading the file, copy the ASE file to the `/opt` directory if you are installing as a root user. You can choose any other location if you want to install ASE as a non-root user.
4. Change the working directory to `/opt`
5. At the command prompt, type the following command to untar the ASE file:

```
tar -zxvf <filename>
```

### For example:

```
tar -zxvf ase-rhel-4.0.4.tar.gz
```

6. To verify that ASE successfully installed, the `ls` command at the command prompt. This will list the pingidentity directory and the build's tar file. For example:

```
/opt/pingidentity/ase/bin/$ ls
pingidentity ase-rhel-4.0.4.tar.gz
```

## ASE License

To start ASE, you need a trial license which is valid for 30-days. At the end of the trial period, ASE stops accepting the traffic.

 **Note:** Contact PingIdentity sales to get an ASE trial license.

### Configure ASE license

After receiving the ASE license key, download and save the license file as `PingIntelligence.lic`. Copy the license file to the `/opt/pingidentity/ase/config` directory and start ASE.

**Update an existing license** If your license expires, obtain an updated license from PingIntelligence for APIs sales and replace the license file in the `/opt/pingidentity/ase/config` directory. Stop and then start ASE to activate the new license.

## Configure PingIntelligence Cloud Connection

Navigate to `/opt/pingidentity/ase/config/abs.conf` and refer to the PingIntelligence cloud information received via email to configure the following:

- Set `abs_endpoint` to ABS IP
- Set `access_key` to ABS access key
- Set `secret_key` to ABS secret key
- Set `enable_ssl` to true

Here is a sample `abs.conf`file:

```
; API Security Enforcer ABS configuration.
; This file is in the standard .ini format. The comments start with a
; semicolon (;).
; Following configurations are applicable only if ABS is enabled with true.

; a comma-separated list of abs nodes having hostname:port or ipv4:port as
; an address.
abs_endpoint=127.0.0.1:8080
```



```

; access key for abs node
access_key=OBF:AES://ENOzsqOEHDBWLDY
+ploQ:jN6wflHTTd3oVNzvtXuAaOG34c4JBD4XZHgFCaHry0

; secret key for abs node
secret_key=OBF:AES:Y2DadCU4JFZp3bx8EhnOiw:zzi77GIFF5xkQJccjlrIVWU
+RY5CxUhp3NLcNBel+3Q

; Setting this value to true will enable encrypted communication with ABS.
enable_ssl=true

; Configure the location of ABS's trusted CA certificates. If empty, ABS's
  certificate
; will not be verified
abs_ca_cert_path=

```

## Obfuscate access and secret key

Using the ASE command line interface, obfuscate the access key and secret key in `abs.conf`. The access key and secret key has been sent to you through the PingIdentity welcome email. ASE ships with a default master key (`ase_master.key`) which is used to obfuscate other keys and passwords. You can generate your own `ase_master.key`. For more information, see [Obfuscate key and passwords](#)

**Note:** During the process of obfuscation password, ASE must be stopped. For more information, see [Stop ASE](#).

## Obfuscate access and secret keys

Enter the access key and secret key provided to you in clear text in `abs.conf`. Run the `obfuscate_keys` command to obfuscate:

```

/opt/pingidentity/ase/bin/cli.sh obfuscate_keys -u admin -p

Please take a backup of config/ase_master.key, config/ase.conf, config/
abs.conf, and config/cluster.conf before proceeding

If config keys and passwords are already obfuscated using the current master
  key, they are not obfuscated again

Following keys will be obfuscated:
config/ase.conf: sender_password, keystore_password
config/abs.conf: access_key, secret_key
config/cluster.conf: cluster_secret_key

Do you want to proceed [y/n]:y
obfuscating config/ase.conf, success
obfuscating config/abs.conf, success
obfuscating config/cluster.conf, success

```

Start ASE after keys are obfuscated. For more information, see [Start ASE](#).

**Important:** `ase_master.key` must be present in the `/opt/pingidentity/ase/config/` directory for ASE to start.

## Start and stop ASE

### Start ASE

**Prerequisite** For ASE to start, the `ase_master.key` must be present in the `/opt/pingidentity/ase/config` directory. If you have moved the master key to a secured location for security reasons, copy it to the config directory before executing the start script.

Change working directory to `bin` and run the `start.sh` script.

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.1...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

### Stop ASE

Change working directory to `bin` and run the `stop.sh` script.

```
/opt/pingidentity/ase/bin/stop.sh -u admin -p admin
checking API Security Enforcer status...sending stop request to ASE. please
wait...
API Security Enforcer stopped
```

## Enable ASE to ABS engine communication

To start communication between ASE and the AI engine, run the following command:

```
./cli.sh enable_abs -u admin -p
```

To confirm an ASE Node is communicating with ABS, issue the ASE status command:

```
/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status           : started
http/ws          : port 80
https/wss        : port 443
firewall         : enabled
abs              : enabled, ssl: enabled (If ABS is enabled, then ASE is
communicating with ABS)
abs attack       : disabled
audit            : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
abs_attack_request_minutes=10
```

## Integrate PingIntelligence into your API environment

### Sideband configuration

If you configured PingIntelligence ASE for sideband connectivity with an API Gateway, then refer to the deployment guide for your environment:

- [Akana API gateway sideband integration](#) on page 558
- [PingIntelligence Apigee integration](#) on page 581
- [PingIntelligence AWS API Gateway Integration](#) on page 601
- [Axway sideband integration](#) on page 616
- [Azure APIM sideband integration](#) on page 640
- [PingIntelligence - CA API gateway sideband integration](#) on page 649
- [F5 BIG-IP PingIntelligence integration](#) on page 658
- [IBM DataPower Gateway sideband integration](#) on page 670
- [PingIntelligence - Kong API gateway integration](#) on page 677
- [Mulesoft sideband integration](#) on page 684
- [NGINX sideband integration](#) on page 698

- [NGINX Plus sideband integration](#) on page 714
- [PingAccess sideband integration](#) on page 747
- [PingFederate sideband integration](#) on page 758
- [PingIntelligence WSO2 integration](#) on page 764

After completing the setup steps in the integration guide, go to AI Engine training.

## Configure ASE and Dashboard

To configure the ASE system and Dashboard to work with PingIntelligence cloud, use the configuration details that you received in an email from PingIntelligence. The following details have been emailed to you:

### ABS configuration

- ABS IP
- ABS access key
- ABS secret key

### Dashboard Configuration

- Dashboard IP
- Dashboard username
- Dashboard password


## Add APIs to ASE

To secure an API with PingIntelligence for APIs software, an administrator can add an API definition to the Ping Identity ASE, which will then pass the API information to the AI Engine for reporting and attack detection. Complete the following steps to configure a simple REST API. For more information on advanced options, see the [ASE Admin Guide](#).

1. Navigate to `/opt/pingidentity/ase/config/api` and copy the file `rest_api.json.example` to `rest_api.json`
2. Open the `rest_api.json` file and update the following information:
  - a. Update the "url" to the base path of the API, for example, `"/apiname"`
  - b. Replace the server IP addresses and ports with the addresser/ports of your app servers.
  - c. Review the following parameter list and make other edits as applicable.

Key API JSON file parameters to configure include:

Parameter	Description
protocol	API request type with supported values of: <code>ws</code> - WebSocket ; <code>http</code> - HTTP
url	The value of the URL for the managed API. You can configure up to s <code>"/shopping"</code> - name of a 1 level API <code>"/shopping/electronics/phones"</code> -3 level API <code>"/"</code> - entire server (used for ABS API Discovery or load balancing)
hostname	Hostname for the API. The value cannot be empty. <code>"*"</code> matches any hostname.
cookie	Name of cookie used by the backend servers.

oauth2_access_token	When <code>true</code> , ASE captures OAuth2 Access Tokens. When <code>false</code> , ASE does not look for OAuth2 Tokens. Default value is <code>false</code> . For more information, see <a href="#">Configuring OAuth2 Token</a> .
apikey_qs	When API Key is sent in the query string, ASE uses the specified parameter. For more information, see <a href="#">Configuring API Keys</a> .
apikey_header	When API Key is part of the header field, ASE uses the specified parameter. For more information, see <a href="#">Configuring API Keys</a> .
login_url	Public URL used by a client to connect to the application.
health_check	When <code>true</code> , enable health checking of backend servers. When <code>false</code> , no health checks are performed. Ping Identity recommends setting this parameter as <code>true</code> .
health_check_interval	The interval in seconds at which ASE sends a health check to determine the status of the backend servers.
health_retry_count	The number of times ASE queries the backend server status after not receiving a response.
health_url	The URL used by ASE to check backend server status.
server_ssl	When set to <code>true</code> , ASE connects to the backend API server over SSL.
<b>Servers:</b>	The IP address or hostname and port number of each backend server.
host	See <a href="#">REST API Protection from DoS and DDoS</a> for information on options.
port	
server_spike_threshold	
server_connection_quota	
The following API Pattern Enforcement parameters only apply when API Firewall is activated	
<b>Flow Control</b>	ASE flow control ensures that backend API servers are protected from excessive requests.
client_spike_threshold	See <a href="#">WebSocket API Protection from DoS and DDoS</a> for information on options.
server_connection_queueing	
bytes_in_threshold	
bytes_out_threshold	
protocol_allowed	List of accepted protocols Values can be HTTP, HTTPS, WS, WSS.
<p> <b>Note:</b> When Firewall is enabled, <code>protocol_allowed</code> takes precedence over <code>protocol_allowed</code>.</p>	
methods_allowed	List of accepted REST API methods. Possible values are: <code>GET, POST, PUT, DELETE, HEAD</code>
content_type_allowed	List of content types allowed. Multiple values cannot be listed. For example, <code>text/html, application/json</code>

**Decoy Config**

decoy\_enabled

response\_code

response\_def response\_message

decoy\_subpaths

When decoy\_enabled is set to `true`, decoy sub-paths function as decoy. response\_code is the status code (for example, 200) that ASE returns. response\_def is the response definition (for example OK) that ASE returns. response\_message is the response message (for example OK) that ASE returns. decoy\_subpaths is the list of decoy API sub-paths (for example `shop`).

See [API deception](#) for details

After configuring the API JSON file, add it to ASE for it to take effect. To add a runtime API, execute the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh add_api {file_path/api_name} -u admin -p
```

**Verify/List the API**

To verify whether the API that you added has been successfully added or not, run the list API command:

```
opt/pingidentity/ase/bin/cli.sh list_api -u admin -p
```

**AI engine training**

The PingIntelligence AI Engine needs to be trained before it can detect anomalies or attacks on API services or generate reports. The AI training runs until a minimum amount of data is received, and the training period is completed for the given API.

ABS must be trained on all APIs before they can be secured. Whenever a new API is added, ABS automatically trains itself before looking for attacks.

For detailed information on training the AI Engine, see the [ABS Admin guide](#).

**Connect to the PingIntelligence dashboard**

The PingIntelligence Dashboard provides information on the APIs monitored by PingIntelligence for APIs. Until the training period is complete (based on volume of traffic) for an API, only a minimal amount of Dashboard data will be available. If traffic volume is low, it may take several days before many of the Dashboard graphs have data.

To connect to the Dashboard and work with PingIntelligence cloud, use the connection details that you received in the welcome email from Ping Identity. The following details are emailed to you :

- Dashboard URL - It is used to load the PingIntelligence for APIs Dashboard
- Dashboard User Name
- Dashboard User Password

For more information on accessing and using Dashboard, see [Access the PingIntelligence Dashboard](#).

For more information on PingIntelligence for APIs Dashboard, see [PingIntelligence Dashboard](#).

**Access ABS reporting**

The ABS AI Engine generates attack, metric, and forensics reports which are accessed using the ABS REST API to access JSON formatted reports. Ping Identity provides templates to use Postman, a free tool for formatting REST API reports.

 **Note:**

Until the training period is complete (based on volume of traffic) for an API, only a minimal amount of reporting data will be available. If traffic volume is low, it may take several days before some of the reports (e.g. attack reports) have data.

### Install Postman with PingIntelligence for API reports

Ping Identity provides configuration files which are used by [Postman](#) to access the ABS REST API JSON information reports. Make sure to install Postman 6.2.5 or higher.

### Using ABS self-signed certificate with Postman

ABS ships with a self-signed certificate. To use Postman with the self-signed certificate of ABS, disable the certificate verification option by following the steps at [this link](#)

### View ABS reports in Postman

To view the reports in Postman, complete the steps mentioned in the [View ABS reports in Postman](#) topic. In configuring the environment, the following details are required:

1. `Server`: Use the ABS URL provided in the email
2. `Port`: Use the port number located at the end of the ABS URL in the email
3. `Access_Key`: Use the ABS access key provided in the email
4. `Secret_key`: Use the ABS secret key provided in the email

`API_Name` is the name of the API. Do not edit any variables that start with "system".

 **Note:** For detailed information on ABS reports, see [Attack Reporting](#) in the ABS Admin Guide.

Following is a list of reports that you can generate using Postman or any other REST API client:

- Metrics report
- Anomalies report
- API key metrics report
- OAuth2 token metrics report
- OAuth2 token forensics report
- IP forensics report
- Cookie forensics report
- Various attack types
- Flow control report
- Blocked connections report
- Backend error report
- List of valid URLs
- List of hacker's URLs

## PingIntelligence Production Deployment

---

### Automated deployment

---

#### PingIntelligence setup


PingIntelligence software combines real-time API security and AI analytics to detect, report, and block cyberattacks on data and applications exposed through APIs. The software consists of three platforms: API Security Enforcer(ASE), API Behavioral Security(ABS) AI engine, and PingIntelligence Dashboard.

This guide describes the installation and execution of an Ansible package which automatically builds a PingIntelligence for APIs environment. The package installs and configures the following components:

- ASE (Inline or Sideband configuration)
- ABS AI Engine
- MongoDB database
- PingIntelligence for APIs Dashboard

The supported operating systems are RHEL 7.9 or Ubuntu 18.04 LTS.

The following diagram shows an example of a sideband deployment.



### API Security Enforcer (ASE)

Applies real-time API metadata ingestion and enforces optional blocking. ASE can be deployed in inline or sideband mode and works with the ABS engine to identify attacks. For more information, see [Inline ASE](#) on page 210 and [Sideband ASE](#) on page 160.

### API Behavioral Security AI engine

Executes AI algorithms to detect in near real-time cyberattacks targeting data, applications, and systems via APIs. Attack information can be automatically pushed to all ASEs to block ongoing breaches and prevent reconnection.

### PingIntelligence for APIs Dashboard

PingIntelligence for APIs Dashboard offers you the following:

- Visibility into API activity.
- View the training status and other information of your APIs
- Manage API Discovery using automatic or manual mode
- View attack insight to understand why a client was flagged for an attack
- Manage attacks by unblocking clients or tune AI Engine thresholds
- View ABS license information

The dashboard engine utilizes Elasticsearch and Kibana to provide a graphical view of an API environment including user activity, attack information, and blacklisted clients.

## Administrators

You can install all the PingIntelligence products either as a user with `sudo` access or a normal user (without `sudo` access). Make sure that the entire deployment is a homogenous deployment. Either all the products should be installed as a `sudo` user or as a normal user.

## Time zone


All PingIntelligence components (ASE, ABS AI Engine, and Dashboard) should be installed using the same time zone, either local or UTC. MongoDB should also be configured to the same time zone as PingIntelligence components.

## PingIntelligence deployment modes

### Inline mode

In PingIntelligence **inline** deployment mode, API Security Enforcer (ASE) sits at the edge of your network to receive the API traffic. It can also be deployed behind an existing load balancer such as AWS ELB. In the inline mode, ASE deployed at the edge of the datacenter, terminates SSL connections from API clients. It then forwards the requests directly to the APIs, API Gateways, or app servers such as Node.js, WebLogic, Tomcat, PHP, etc.

To configure ASE to work in the Inline mode, set the **mode=inline** in the `ase-defaults.yml` file.



Following is a high-level description of traffic flow:


1. Client request is received by ASE. The request is logged in access log file. ASE then forwards the request to the backend server. The response is received by ASE and logged in the access log file.
2. The request and response in the access log file is sent to ABS AI engine for processing. ABS AI engine generates the attack list which is fetched by ASE. The future requests received by ASE are either forwarded to the backend server or blocked by ASE based on the attack list.
3. The AI engine data is stored in MongoDB
4. PingIntelligence for APIs Web GUI fetches the data from ABS to display in the dashboard.

### Sideband mode

When PingIntelligence is deployed in the **sideband** mode, a sideband policy is added to the API Gateway which makes calls to ASE to pass API request and response metadata. In this mode, ASE does not terminate the client requests.

To configure ASE to work in the sideband mode, set the **mode=sideband** in the `ase-defaults.yml` file.





Following is a description of the traffic flow through the API gateway and Ping Identity ASE.

1. Incoming request to API gateway
2. API gateway makes an API call to send the request metadata in JSON format to ASE
3. ASE checks the request against a registered set of APIs and checks the client identifier against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the API gateway. Else, a different response code is sent to the Gateway. The request is also logged by ASE and sent to the AI Engine for processing.
4. When the API gateway receives a response from ASE, then it forwards the request to the backend server unless blocking is enabled and the client is on the blacklist.
5. The response from the backend server is received by the API gateway.
6. The API gateway makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to the API gateway.
8. API gateway sends the response received from the backend server to the client.

**Note:** Complete the ASE sideband mode deployment by referring to API gateway specific deployment section on the [PingIntelligence documentation site](#).

## Prerequisites

Commonly used terms for deployment machines

Following terms are frequently used during automated deployment steps:

- **Management machine** - Management host machine or a management machine is the server on which the PingIntelligence for APIs automated deployment script is downloaded and run.
- **Host machine** - Server or servers where PingIntelligence for APIs components are installed.

## Prerequisites

The following prerequisites must be met before proceeding with the installation:

- **Management machine operating system :**
  - PingIntelligence for APIs, automated deployment requires RHEL 7.9 operating system on the management machine.
- **Host machine operating system** -PingIntelligence for APIs host machine operating system can be RHEL 7.9 or Ubuntu 18.04 LTS.

**ⓘ Important:** For all the provisioned host machines, make sure the deployment is homogenous with respect to the operating systems and their versions. For example if the host machines are provisioned to run RHEL 7.9 then ensure all of them are running RHEL 7.9. Do not create a setup with a mixture of deployments across host machines.

- **Ansible** - The management host machine must have ansible 2.6.2 installed
- **Python** - The management host machine must have Python installed. The supported versions are Python 2.7 to Python 3.7.10.
- **User** - Automated installation requires a user with password-less authentication for SSH connection to the host machines. User should also have password-less `sudo` access to all the host machines. Alternatively, you can also set up a user with password by editing the `hosts` file. For more information on `hosts` file, see [Step 3 - Configure hosts file and download software](#) on page 54.
- **firewalld package** - All the host machines should have an active `firewalld [python 2.7]` package on both Ubuntu and RHEL machines. If the package is not available, then manually open the ports that are used in the deployment. For more information on ports, see the respective [Change default settings](#) topics.
- If you are deploying the setup on a Ubuntu machine, make sure that the MongoDB host machine has `libcurl4-openssl-dev`.
- Ensure that there are no pre-existing Java installations on the host machines. You can use the command, `# java -version` to verify this. We highly recommend that you uninstall all existing versions of Java from the host machines, before proceeding with the installation of PingIntelligence components.

## Download the deployment package

Setup the management machine

PingIntelligence automated deployment requires RHEL 7.9 management host machine to start the deployment. The automated deployment installs different PingIntelligence components from this management machine.

1. Login to the Management machine as a `root` user.
2. [Download](#) the Ansible deployment package and save it to the `/opt` directory
3. Untar the downloaded file:

```
#tar -xf /opt/pi-api-deployment-5.0.tar.gz
```

Untarring the file creates the following sub-directories in the `pi-api-deployment` directory:

Directory	Description
<code>ansible</code>	Contains the different <code>yml</code> files.
<code>bin</code>	Contains the <code>start.sh</code> and <code>stop.sh</code> scripts. Do not edit the contents of this directory.

certs	<p>Contains ASE, ABS, Elasticsearch, Kibana, Dashboard, and MongoDB self-signed certificates and keys. Elasticsearch and Kibana certificates are in the dashboard directory.</p> <p><b>Note:</b> If you want to use your own certificates and keys, then replace the default certificates and keys with your certificates. Use the same file names as that of the files present in the <code>certs</code> directory. Make sure that the keys are password-less.</p>
config	Contains the default settings file for ASE, ABS, and Dashboard. These files are used to configure the various variables for installing PingIntelligence components.
data	System directory. Do not edit the contents of this directory.
util	Contains utilities to run PingIntelligence components as a service.
external	The third-party components like MongoDB are downloaded in the <code>external</code> directory.
keys	After the installation is complete, the master keys of all the components are saved here.
license	Contains the PingIntelligence for APIs license file.
logs	Contains the log files for automated installation.
software	<p>Contains the binary files for PingIntelligence components:</p> <ul style="list-style-type: none"> <li>▪ ASE</li> <li>▪ ABS</li> <li>▪ Dashboard</li> </ul> <p>The directory also contains <code>updated_packages</code> sub-directory which stores the PingIntelligence updated binaries with new master keys. You can use these binaries for future use.</p>

## Step 1 - User and authentication

This covers concept and steps to create an SSH user. Creating a new user is an optional step. You can use the default user configured in the `hosts` file. It also discusses authentication options. You can configure password-less authentication for the SSH user or use a password to connect to the host machines.

- [User creation \(optional\)](#)
- [Authentication](#)

### User Creation (Optional)

Complete the following steps on all the provisioned host machines if you do not have a user as mentioned in the [Prerequisites](#) on page 49 section. If you already have a user as described in the prerequisite section, you can skip the following steps:

1. Create an `ec2-user`. The `hosts` file in the automation package has `ec2-user` as the default user. You can create your own username.

```
#useradd ec2-user
```

2. Change the password

```
#passwd ec2-user
```

3. **Note:** If you plan to install PingIntelligence software as a `non-sudo` user, then skip steps 3-5.

Add the user to the wheel group

```
#usermod -aG wheel ec2-user
```


4. Configure password-less `sudo` access

```
#visudo
%wheel ALL=(ALL) NOPASSWD: ALL
```

5. Verify the `/etc/ssh/sshd_config` file for `PubKeyAuthentication`. If it is set to `no`, then set it to `yes` and restart `sshd` service using the following command:

```
#systemctl restart sshd
```

The following diagram shows the management host and PingIntelligence host machines communicating either through password-less SSH communication or communicating after authenticating using a password.



### Authentication

PingIntelligence automated deployment supports the following two methods for authentication between the management host machine and PingIntelligence host machines.

- **Password-less authentication** - There are two options to achieve password-less authentication.
- **Authentication using a password** - Authentication using a password requires `sshpass` module to be installed on the RHEL host machine.

## Password-less authentication

You can set up a password-less authentication from the management machine to other machines where PingIntelligence components are installed. There are two options to configure password-less authentication.

### Option 1

1. Run the following command on the management machine. The management machine is the machine from which the automated deployment script is run to deploy the various PingIntelligence software.

```
# ssh-keygen -t rsa
```

This command generates the `ssh-keys`. Accept all the default options. Make sure that you do not set the password for the key.

2. Run the following command for each host machine but not the management machine:

```
# ssh-copy-id pi-user@<ping-machine IPv4 address>
```

For example, `ssh-copy-id pi-user@192.168.11.148 (ping-ase)`

### Option 2

1. Run the following command on the management machine. The management machine is the machine from which the automated deployment script is run to deploy the various PingIntelligence software.

```
# ssh-keygen -t rsa
```

This command generates the `ssh-keys`. Accept all the default options. Make sure that you do not set the password for the key.

2. Fetch the generated key in step 1 from `/home/$USER/.ssh/id_rsa.pub`
3. Copy and add this key in the `/home/$USER/.ssh/authorized_keys` file on all the host machines where PingIntelligence components are installed.

**ⓘ Important:** If option 1 or option 2 of configuring password-less authentication does not succeed, contact your system administrator.

## Authentication using a password

You can also use password to authenticate with PingIntelligence and MongoDB host machines. Configure the password of the host machine in the `hosts` file. Complete the following prerequisites to authenticate using a password:

### Prerequisites:

- Install `sshpass` module on the management host machine. Note that the management host machine is a RHEL 7.6 machine.
- The password that you configure for the user in the `hosts` file must already be configured on the host machines.

To add the password in the `hosts` file, edit the `hosts` file to configure password in `ansible_ssh_pass` parameter as shown in the `hosts` file snippet below.

```
# Ansible SSH user to access host machines
ansible_ssh_user=ec2-user
# Uncomment the ansible_ssh_pass line and configure password of
  ansible_ssh_user if you want to use SSH connection with password.
# If you do not use this option, then the SSH user uses password-less
  authentication.
#ansible_ssh_pass=<SSH_user_password>
```

## Verify SSH connectivity

You can manually verify SSH connectivity between the management machine and the host machine by entering the following command.

```
ssh user@remote-machine "ls"
```

## Step 2 - Copy PingIntelligence license

PingIntelligence ASE and ABS require a valid license to start. The license file is named `PingIntelligence.lic`.

Copy the license file in to the `/license/` directory. Make sure that the license file is named as `PingIntelligence.lic`. Following is a sample of the license file.

```
ID=1135816
Organization=PI
Product=PingIntelligence
Version=5.0
IssueDate=2021-01-01
EnforcementType=0
ExpirationDate=2024-01-01
MaxTransactionsPerMonth=1000000000
Tier=Subscription
SignCode=####
Signature=#####
```

## Step 3 - Configure hosts file and download software

The hosts file contains the various parameters to be configured for installation of PingIntelligence components. Complete the following steps to configure the hosts file.

The configuration file has parameters where link to download third-party component is configured. If the Management machine does not have internet access, download the [third-party components manually](#).

**Note:** Make sure that the entire deployment is homogenous with respect to the provisioned machines. All the PingIntelligence components should either be installed on an RHEL machine or on Ubuntu machines.

Configure the following fields in the `config/hosts` file:

Variable	Description
----------	-------------

<p>IP addresses</p> <ul style="list-style-type: none"> <li>▪ [ase]</li> <li>▪ [abs]</li> <li>▪ [mongodb]</li> <li>▪ [dashboard]</li> <li>▪ [elasticsearch]</li> <li>▪ [kibana]</li> <li>▪ [abs_reporting_node]</li> <li>▪ [webgui]</li> </ul>	<p>Configure the following IP addresses:</p> <ul style="list-style-type: none"> <li>▪ [ase] - ASE IP address</li> <li>▪ [abs] - ABS IP address</li> <li>▪ [mongodb] - MongoDB IP address and port. Providing the port number is mandatory.</li> <li>▪ [dashboard] - Dashboard IP address</li> <li>▪ [elasticsearch] - Elasticsearch IP address</li> <li>▪ [kibana] - Kibana IP address</li> <li>▪ [abs_reporting_node] - ABS reporting node IP address</li> </ul> <div style="border: 1px solid black; padding: 5px; margin: 5px 0;"> <p><b>i Important:</b> The IP address for [abs] and [abs_reporting_node] should be different. If you are installing all the components on a single host, leave the [abs_reporting_node] field blank.</p> </div> <ul style="list-style-type: none"> <li>▪ [webgui] - Web GUI IP address. Web GUI and dashboard engine are part of the same package, however, you can install them on separate machines. If you want to install Web GUI and dashboard engine in the same machine, configure the same IP address in [dashboard] and [webgui]</li> </ul> <p>If you are setting up a POC environment, then all the components: ASE, ABS, MongoDB, Dashboard, WebGUI, ElasticSearch, and Kibana can share a single IP address.</p> <div style="border: 1px solid black; padding: 5px; margin: 5px 0;"> <p><b>i Note:</b> Leave the abs_reporting_node field blank, when all the components have the same IP address..</p> </div> <p>For production deployments:</p> <ul style="list-style-type: none"> <li>▪ ASE, ABS AI Engine, and MongoDB should be deployed on separate servers for redundancy.</li> <li>▪ Dashboard, WebGUI, Kibana, and ABS Reporting node (optional) can be deployed on a single server.</li> <li>▪ ElasticSearch should be deployed on a standalone server.</li> </ul>
<p>installation_path</p>	<p>Configure the path where you would want the PingIntelligence components to be installed. The default value is /home/ec2-user.</p> <div style="border: 1px solid black; padding: 5px; margin: 5px 0;"> <p><b>i Important:</b> The path that you provide in the installation_path variable must exist on the machine. The automation script does not create this path. If you are installing all the PingIntelligence components on different machines, then manually create the same path on each machine before running the automation script.</p> </div>
<p>install_with_sudo</p>	<p>When set to false, the script installs PingIntelligence for a normal user. When set to true, the script installs PingIntelligence as a root user if the port number of ports configured are less than 1024.</p>

install_as_service	<p>Set it to <code>true</code> if you want to install PingIntelligence components as a service. To install PingIntelligence components, you must be a root user. Set <code>install_with_sudo</code> as <code>true</code>.</p> <p>If you install PingIntelligence components as a service, the components are automatically restarted when the system is rebooted. Check the <code>ansible.log</code> file to verify starting PingIntelligence components as a service.</p>
install_mongo	<p>Set it to <code>true</code> if you want automated deployment to install MongoDB. Set it to <code>false</code> if you want to use an existing MongoDB installation. Default value is <code>true</code>.</p> <p><b>i Important:</b> Configure the MongoDB IP address and port number even if <code>install_mongo</code> is set to <code>false</code>. MongoDB details are required to configure <code>abs.properties</code> file.</p>
install_elasticsearch	<p>Set to <code>true</code> if you want automated deployment to install Elasticsearch. Set it to <code>false</code> if you want to use an existing Elasticsearch installation. Default value is <code>true</code>. Note the following points:</p> <ul style="list-style-type: none"> <li>▪ If you have set the option as <code>true</code>, provide an IP address in the <code>hosts</code> file for Elasticsearch. Leave the IP address blank in the <code>hosts</code> file, if you configured the option as <code>false</code>.</li> <li>▪ If you have configured the variable as <code>false</code>, configure the URL of your existing Elasticsearch in <code>dashboard-defaults.yml</code> file. For more information, see <a href="#">Change Dashboard default settings</a> on page 66.</li> </ul> <p><b>i Note:</b> If you are using an existing Elasticsearch installation is an OSS package, make sure that Kibana 6.8.1 OSS package is available in <code>external</code> directory.</p>
jdk11_download_url	<p>The automated script requires OpenJDK 11.0.2.</p> <p><b>i Note:</b> If your machine does not have internet access, then download the OpenJDK 11.0.2 and save the file as <code>openjdk11.tar.gz</code> in <code>external</code> directory.</p>
mongodb_download_url	<p>MongoDB download URL. A default URL is populated in the <code>hosts</code> file.</p> <p><b>i Note:</b></p> <ol style="list-style-type: none"> <li>1. The default URL is RHEL version of MongoDB. If you are installing on Ubuntu, configure the MongoDB Ubuntu download URL.</li> <li>2. If your machine does not have internet access, then download the MongoDB 4.2.0 and save the file as <code>mongodb.tgz</code> in <code>external</code> directory.</li> </ol>



elasticsearch_download_url	Elasticsearch download URL. A default URL is populated in the <code>hosts</code> file.  <i>i</i> <b>Note:</b> If your machine does not have internet access, then download the Elasticsearch 6.8.1 and save the file as <code>elasticsearch-6.8.1.tar.gz</code> in <code>externaldirectory</code> .
timezone	Timezone setting for PingIntelligence components. It will set the timezone settings of ASE, ABS, and PingIntelligence for APIs Dashboard. Allowed values are <code>local</code> or <code>utc</code> . The default value is <code>utc</code> .
kibana_download_url	Kibana download URL. A default URL is populated in the <code>hosts</code> file.  <i>i</i> <b>Note:</b> If your machine does not have internet access, then download the Kibana 6.8.1 and save the file as <code>kibana-6.8.1.tar.gz</code> in <code>externaldirectory</code> .
ansible_ssh_user	Ansible <code>ssh</code> user. The default value is <code>ec2-user</code> .
ansible_ssh_pass	Configure the ansible SSH user's password if you want to use password to authenticate with the host machines.  <i>i</i> <b>Note:</b> If you do not configure password, SSH use establishes a password-less authenticated connection.

Add Ansible username in the `ansible_ssh_user` field. The default value is `ec2-user`.

```
[ase]
172.16.40.81

[abs]
172.16.40.81

[abs_reporting_node]

[mongodb]
172.16.40.81 mongo_port=27017

[dashboard]
172.16.40.81

[elasticsearch]
172.16.40.81

[kibana]
172.16.40.81

[webgui]
172.16.40.81

[all:vars]

# Installation Path
installation_path="/home/ec2-user"
```

```

# install_as_service set to true will start ase, abs, aad, dashboard,
  elasticsearch
# and kibana as systemd services.
install_as_service=true

# configure install_with_sudo to true if any of the ports used for ASE,
# ABS, Dashboard are <1024. That component will be started using sudo.
# when install_as_service is true, install_with_sudo should be set to true.
install_with_sudo=true

# this option can be used if there is an existing mongo installation that
  can be used
# set it to false if mongoddb need not be installed
install_mongo=true

# this option can be used if there is an existing elasticsearch installation
  that can be used.
# set it to false if elasticsearch need not be installed.
# when install_elasticsearch is set to false, remove any nodes under
  elasticsearch section and
# configure elasticsearch_url in config/dashboard-defaults.yml.
install_elasticsearch=true

# timezone setting. It will set timezone settings of ASE, ABS and Dashboard
# allowed values: local, utc
timezone=utc

# Download URLs for external packages
jdk11_download_url='https://download.java.net/java/GA/jdk11/9/GPL/
openjdk-11.0.2_linux-x64_bin.tar.gz'
mongodb_download_url='https://fastdl.mongodb.org/linux/mongodb-linux-x86_64-
rhel70-4.2.0.tgz'
elasticsearch_download_url='https://artifacts.elastic.co/downloads/
elasticsearch/elasticsearch-6.8.1.tar.gz'
kibana_download_url='https://artifacts.elastic.co/downloads/kibana/
kibana-6.8.1-linux-x86_64.tar.gz'

# Ansible SSH user to access host machines
ansible_ssh_user=ec2-user
# Uncomment the ansible_ssh_pass line and configure password of
  ansible_ssh_user if you want to use SSH connection with password.
# If you do not use this option, then the SSH user uses password-less
  authentication.
#ansible_ssh_pass=

```

### Manually download third-party components

The automated deployment downloads the third-party packages when it is executed. However, if your Management machine does not have internet access, then download the software using the steps mentioned below. Download the individual components and save the file in the `external` directory.

**i Important:** If your management host machine has internet access, you can skip downloading the third-party components manually.

1. Install Ansible version 2.6.2 on the Management machine. The Management machine is the server from which the automated deployment script is run to deploy the various PingIntelligence components.
2. Install Python on the Management host machine.

3. Download the following packages and copy to the `external` directory using the specified names:

**MongoDB** – Download MongoDB 4.2 from:

- **Linux:** [https://fastdl.mongodb.org/linux/mongodb-linux-x86\\_64-rhel70-4.2.0.tgz](https://fastdl.mongodb.org/linux/mongodb-linux-x86_64-rhel70-4.2.0.tgz) and save the file in the `external` directory as `mongodb.tgz`.
- **Ubuntu:** [http://downloads.mongodb.org/linux/mongodb-linux-x86\\_64-ubuntu1604-4.2.0.tgz](http://downloads.mongodb.org/linux/mongodb-linux-x86_64-ubuntu1604-4.2.0.tgz) and save the file in the `external` directory as `mongodb.tgz`.

**Elasticsearch** – Download Elasticsearch from: <https://artifacts.elastic.co/downloads/elasticsearch/elasticsearch-6.8.1.tar.gz> and save the file in the `external` directory as `elasticsearch-6.8.1.tar.gz`.

**Kibana** – Download from: [https://artifacts.elastic.co/downloads/kibana/kibana-6.8.1-linux-x86\\_64.tar.gz](https://artifacts.elastic.co/downloads/kibana/kibana-6.8.1-linux-x86_64.tar.gz) and save the file in the `external` directory as `kibana-6.8.1-linux-x86_64.tar.gz`.

### Download PingIntelligence for APIs software

**Download** the following PingIntelligence for APIs software to `pi-api-deployment/software` directory.

- ASE (RHEL or Ubuntu)
- ABS AI Engine
- PingIntelligence Dashboard

**Note:** Do not change the name of the downloaded files.

The `software` directory should include the following files:

```
-rw-r--r--. 1 pingidentity pingidentity 2.5M Jun 07 00:01 pi-api-
dashboard-4.4.tar.gz
-rw-r--r--. 1 pingidentity pingidentity 159M Jun 07 00:01 pi-api-
abs-4.4.tar.gz
-rw-r--r--. 1 pingidentity pingidentity 38M Jun 07 00:01 pi-api-ase-
rhel-4.4.tar.gz
```

### Checking SSH connectivity

About this task

Check the SSH connectivity from the management machine to other host machines. The SSH connectivity check provides details regarding the configured `user`, IP address of the hosts for which SSH connectivity works or fails. Run the check before deploying PingIntelligence components. Enter the following command on the management host command line.

Steps

```
$ ./bin/start.sh check
```

```
User configured for SSH: ec2-user
Checking sudo connectivity between ansible management host and other
hosts...
172.16.40.187 | SUCCESS => {
  "changed": false,
  "ping": "pong"
}
SSH connectivity to all hosts is successful
Capturing host information...
Host information is captured successfully
```

### Possible errors during SSH connectivity

During SSH connectivity check between management host machine and PingIntelligence hosts, you may encounter some errors because of user permission issues or connectivity issues between machines. Following are some of the probable error messages that you may see:

- You have configured user to use password to authenticate with the hosts machines, however, the configured password in the `hosts` file is wrong.

```
User configured for SSH: ec2-user
Checking connectivity between ansible management host and other hosts...
172.16.40.187 | UNREACHABLE! => {
  "changed": false,
  "msg": "Authentication failure.",
  "unreachable": true
}
Sun Jul 12 19:22:41 MDT 2020: SSH connection error: connectivity to all
hosts is not successful for ec2-user
```

- `ansible_ssh_pass` for authentication with password is uncommented in the `hosts` file. However, the password field has been left empty. Leaving the value empty is equivalent to password-less authentication.

```
User configured for SSH: ec2-user
Checking connectivity between ansible management host and other hosts...
172.16.40.187 | UNREACHABLE! => {
  "changed": false,
  "msg": "Failed to connect to the host via ssh: Permission denied
(publickey,password).\r\n",
  "unreachable": true
}
Sun Jul 12 19:26:16 MDT 2020: SSH connection error: connectivity to all
hosts is not successful for ec2-user
```

- `install_with_sudo` is set to true and there is an error connecting to PingIntelligence host machines.

```
User configured for SSH: ec2-user
Checking sudo connectivity between ansible management host and other
hosts...
172.16.40.187 | FAILED! => {
  "changed": false,
  "module_stderr": "Connection to 172.16.40.187 closed.\r\n",
  "module_stdout": "sudo: a password is required\r\n",
  "msg": "MODULE FAILURE",
  "rc": 1
}
Sun Jul 12 19:30:26 MDT 2020: SSH connection error: sudo connectivity to
all hosts is not successful for ec2-user
```

The probable reasons for error in connectivity could be:

- The user is not in the `sudoers` file or the user is not in any group that has `sudo` privileges
- The user does not have `NOPASSWD: ALL` privileges in the `sudoers` file.
- The IP address configured in the `hosts` file is not available.

```
User configured for SSH: ec2-user
Checking sudo connectivity between ansible management host and other
hosts...
172.16.40.81 | UNREACHABLE! => {
  "changed": false,
  "msg": "Failed to connect to the host via ssh: ssh: connect to host
172.16.40.81 port 22: Connection timed out\r\n",
  "unreachable": true
}
```

```
}
Sun Jul 12 21:41:08 MDT 2020: SSH connection error: sudo connectivity to
all hosts is not successful for ec2-user
```

- **selinux** dependency - If you encounter the following error, you need to install `selinux` package on the host machine on which you see this error. Check the machine mentioned before `FAILED!` in the output to identify the machine where `selinux` needs to be installed.

```
[localhost]: FAILED! => {"changed": false, "msg": "Aborting, target uses
selinux but python bindings (libselinux-python) aren't installed!"}
to retry, use: --limit @/home/ec2-user/411/pingidentity/pi-api-
deployment/ansible/setup.retry
```

## Changing default settings

The deployment package provides `.yaml` files to change the default settings of ASE, ABS, and Dashboard. Change the default settings before you execute the deployment package. For more information on each component, see the respective guides at [PingIntelligence documentation](#).

The following topics describe the default settings of each component:

- [Change ASE's default settings](#)
- [Change ABS default settings](#)
- [Change Dashboard default settings](#) on page 66

### Important:

Make sure that the format of default settings file is `.yaml`.

### Change ASE default settings

You can change the default settings in ASE by editing the `ase-defaults.yaml` file.

The following table lists the variables that you can set for ASE.

Variable	Description
<code>mode</code>	Sets the mode in which ASE is deployed. The default value is <code>inline</code> . Set the value to <code>sideband</code> if you want ASE to work in the sideband mode.
<code>http_ws_port</code>	Data port used for HTTP or WebSocket protocol. The default value is 8090.
<code>https_wss_port</code>	Data port used for HTTPS or secure WebSocket protocol. The default value is 8443.
<code>management_port</code>	Management port used for CLI and REST API management. The default value is 8010.
<code>cluster_manager_port</code>	ASE node uses this port number to communicate with other ASE nodes in the cluster. The default value is 8020.
<code>keystore_password</code>	The password for ASE keystore. The default password is <code>asekeystore</code> .

Variable	Description
<code>cluster_secret_key</code>	This key is used for authentication among ASE cluster node. All the nodes of the cluster must have the same <code>cluster_secret_key</code> . This key must be entered manually on each node of the ASE cluster for the nodes to communicate with each other. The default value is <code>yourclusterkey</code> .
<code>enable_ase_detected_attack</code>	This key is used to enable ASE to block auto detected attacks. Set this value to <code>true</code> to allow ASE to block auto detected attacks. The default value is <code>false</code> .
<code>enable_abs_attack</code>	This key is used to enable ASE to fetch attack list from ABS. Set this value to <code>true</code> to fetch the list from ABS. The default value is <code>false</code> .
<code>enable_sideband_keepalive</code>	This key is used only in ASE sideband mode. If set to <code>true</code> , ASE sends a keep-alive in response header for the TCP connection between API gateway and ASE. With the default <code>false</code> value, ASE sends a connection close in response header for connection between API gateway and ASE.
Email default settings	Configure the following settings: <ul style="list-style-type: none"> <li>▪ <code>enable_emails</code>: Set it to <code>true</code> for ASE to send email notifications. Default value is <code>false</code>.</li> <li>▪ <code>smtp_host</code> and <code>smtp_port</code></li> <li>▪ <code>sender_email</code>: Email address used from which email alerts and reports are sent.</li> <li>▪ <code>email_password</code>: Password of sender's email account.</li> <li>▪ <code>receiver_email</code>: Email address to which the email alerts and reports are sent.</li> </ul>
CLI admin password	The default value for CLI admin is <code>admin</code> . To change the password, you need the current password.

**ⓘ Important:**

Make sure to take a backup of the `ase-defaults.yml` file on a secure machine after the automated installation is complete.

The following is a sample `ase-defaults.yml` file.

```
---
ase:
  # Deployment mode for ASE. Valid values are inline or sideband
  mode: inline

  # Define ports for the PingIntelligence API Security Enforcer
  # Make sure ports are not same for single server installation
```

```

http_ws_port: 8090
https_wss_port: 8443
management_port: 8010
cluster_manager_port: 8020

# Password for ASE keystore
keystore_password: asekeystore

# cluster_secret_key for ASE cluster
cluster_secret_key: yourclusterkey

# enable keepalive for ASE in sideband mode
enable_sideband_keepalive: false

# Configure Email Alert. Set enable_emails to true to configure
# email settings for ASE
enable_emails: false
smtp_host: smtp.example.com
smtp_port: 587
sender_email: sender@example.com
email_password: password
receiver_email: receiver@example.com

# CLI admin password
current_admin_password: admin
new_admin_password: admin

```

### Changing ABS default settings

You can change the default settings in ABS by editing the `abs-defaults.yml` file.

#### About this task

The following table lists the variables that you can set for ABS.

Variable	Description
<code>management_port</code>	Port for ABS to ASE and REST API to ABS communication. The default value is 8080.
<code>mongo_username</code> and <code>mongo_password</code>	MongoDB username and password. The default username is <code>absuser</code> , and the default password is <code>abs123</code> .
<code>mongo_cache_size</code>	If you are running all the PingIntelligence components on the same instance, keep the MongoDB cache size to a maximum of 25% of the system memory. If you are running MongoDB on a separate instance, keep the MongoDB cache size to a maximum of 40% of the system memory.
<code>mongo_ssl</code>	Default value is <code>true</code> . PingIntelligence deployment ships with a default self-signed certificate. Setting it to <code>false</code> establishes non-SSL connection between ABS and Mongo.

Variable	Description
mongo_certificate_verify	<p>Set it to <code>true</code> if you want to verify MongoDB SSL server certificate when ABS connects to MongoDB. The default value is <code>false</code>.</p> <p><b>Note:</b> Make sure <code>mongo_ssl</code> is set to <code>true</code> before setting <code>mongo_certificate_verify</code> to <code>true</code>.</p>
mongo_replica_set	Name of the MongoDB replica set. Default name is <code>absrs01</code> .
attack_initial_training	The number of hours that you want to train the AI model before it moves to the prediction mode. Default value is 24 hours.
system_memory	Memory size in MB allocated to run machine learning jobs. Recommended to be at least 50% of system memory.
access_key and secret_key	<p>The access key and secret for the admin user. For more information on different ABS users, see <a href="#">ABS users</a>.</p> <p><b>Note:</b> ":" (colon) is a restricted character and not allowed in access key and secret key.</p>
access_key_ru and secret_key_ru	<p>The access key and secret for the restricted user. For more information on different ABS users, see <a href="#">ABS users</a>.</p> <p><b>Note:</b> ":" (colon) is a restricted character and not allowed in access key and secret key.</p>
jks_password	The password of the Java KeyStore (JKS) Keystore. The default password is <code>abs123</code> .



Variable	Description
Email default settings	<p>Configure the following settings:</p> <ul style="list-style-type: none"> <li>▪ <code>enable_emails</code>: Set it to <code>true</code> for ASE to send email notifications. Default value is <code>false</code>.</li> <li>▪ <code>smtp_host</code> and <code>smtp_port</code></li> <li>▪ <code>sender_email</code>: Email address used from which email alerts and reports are sent.</li> <li>▪ <code>email_password</code>: Password of sender's email account.</li> <li>▪ <code>receiver_email</code>: Email address at which the email alerts and reports are sent.</li> </ul>
CLI admin password	The default value for CLI admin is <code>admin</code> . To change the password, you need the current password.
<code>poc_mode</code>	Sets the mode in which AI engine sets the thresholds for the AI models. If set to <code>true</code> , AI engine sets thresholds at a lower value. It should be set to <code>true</code> only for a proof-of-concept deployment.

 **Important:**

Make sure to take a backup of the `abs-defaults.yml` file on a secure machine after the automated installation is complete.

The following is a sample `abs-defaults.yml` file.

```
---
abs:
  # Define ports for the PingIntelligence ABS
  # Make sure ports are not same for single server installation
  management_port: 8080

  # Mongo DB User and password
  mongo_username: absuser
  mongo_password: abs123
  # Define cache size for MongoDB (% of total RAM).
  # MongoDB will be configured to use this percentage of host memory.
  mongo_cache_size: 25
  # Communication between mongo and ABS
  mongo_ssl: true
  # Mongo DB Server Certificate Verification
  # Set to true if Mongo DB instance is configured in SSL mode and you want
  # to do the server certificate verification
  # By default ABS will not verify the MongoDB server certificate
  mongo_certificate_verify: false
  # Mongo replica set name
  mongo_replica_set: absrs01

  # Duration of initial training period (units in hours)
  # This value will be set in the mongo nodes
  attack_initial_training: 24

  # Memory for webserver and streaming server (unit is in MB)
```

```

system_memory: 4096

# Access keys and secret keys to access ABS
access_key: abs_ak
secret_key: abs_sk
access_key_ru: abs_ak_ru
secret_key_ru: abs_sk_ru

# Password for ABS keystore
jks_password: abs123

# Configure Email Alert. Set enable_emails to true to configure
# email settings for ABS
enable_emails: false
smtp_host: smtp.example.com
smtp_port: 587
sender_email: sender@example.com
email_password: password
receiver_email: receiver@example.com

# CLI admin password
current_admin_password: admin
new_admin_password: admin

poc_mode: false

```

To change the default system memory in the `abs.properties` file of ABS:

#### Steps

1. Go to the `software` directory.
2. Untar the ABS binary by entering the following command.

```
# tar -zxvf pi-api-abs-5.0.tar.gz
```

3. Edit the `config/abs.properties` file to change the default value of `system_memory` to 50% of host memory.

```
# vi pingidentity/abs/config/abs.properties
```

For example, if host ABS system has 16 GB of memory, set the value to 8192 MB.

4. Save the file.
5. Tar the ABS binary and save it with the same file name (`pi-api-abs-5.0.tar.gz`) in the `software` directory by entering the following command.

```
# tar -czf pi-api-abs-5.0.tar.gz pingidentity/abs
```

#### Change Dashboard default settings

You can change the default settings of PingIntelligence for APIs Dashboard.

To change the default settings, edit the `dashboard-defaults.yml` file and `ilm.json` file.

#### Change settings in dashboard-default.yml

You can change the default settings of PingIntelligence Dashboard by editing the `<pi-install-path>/pingidentity/pi-api-deployment/config/dashboard-defaults.yml` file. The following table lists the variables that you can set for PingIntelligence Dashboard in various configurations.

Variable	Description
port	Port number to connect to PingIntelligence Dashboard.
authentication_mode	<p>Defines the mode in which Dashboard authenticates. The valid values are <code>native</code> and <code>sso</code>.</p> <p><b>Note:</b> You should use <code>native</code> authentication for proof-of-concept deployments.</p>
session_max_age	Defines the maximum time for a session. The configured values should be in the form of <code>&lt;number&gt;&lt;duration_suffix&gt;</code> . Duration should be <code>&gt; 0</code> . Allowed <code>duration_suffix</code> values: <code>m</code> for minutes, <code>h</code> for hours, and <code>d</code> for days.
max_active_sessions	Defines the maximum number of active UI sessions at any given time. The value should be greater than 1.
admin_password and ping_user_password	<p>The passwords for <code>webgui admin</code> and <code>ping_user</code> accounts.</p> <p><b>Note:</b> <code>admin_password</code> and <code>ping_user_password</code> are applicable in <code>native authentication_mode</code> only.</p>
<b>Single sign-on (SSO) configurations</b> - Applicable only when <code>authentication_mode</code> is set as <code>sso</code>	
sso_oidc_client_id	Client ID value in configured in the Identity provider.
sso_oidc_client_secret	Client Secret configured for the corresponding Client ID.
sso_oidc_client_authentication_method	OpenID Connect (OIDC) Client authentication mode. The valid values are <code>BASIC</code> , <code>POST</code> , or <code>NONE</code>
sso_oidc_provider_issuer_uri	HTTPS IP address of OIDC provider. Also, place the SSO provider's issuer-certificate in the following path - <code>&lt;installation_path&gt;/pingidentity/certs/webgui/</code>
sso_oidc_provider_user_uniqueid_claim_name	Claim name for unique ID of the user in <code>UserInfo</code> response. A new user is provisioned using this unique ID value.

Variable	Description
sso_oidc_provider_user_first_name_claim_name	Claim name for first name of the user in UserInfo response. Either first name or last name can be empty, but both should not be empty.
sso_oidc_provider_user_last_name_claim_name	Claim name for last name of the user in UserInfo response. Either first name or last name can be empty, but both should not be empty.
sso_oidc_provider_user_role_claim_name	Claim name for role of the user in UserInfo response. Default value is <code>role</code> .
sso_oidc_client_additional_scopes	Additional scopes in authorization request. Multiple scopes should be comma (,) separated values. OpenID, profile scopes are always requested.
<b>-End-of-SSO-configurations-</b>	
SSL configuration for PingIntelligence Dashboard <ul style="list-style-type: none"> <li>server_ssl_key_store_password</li> <li>server_ssl_key_alias</li> </ul>	Configure the passwords for keystore and key alias.
H2 database configuration: <ul style="list-style-type: none"> <li>h2_db_password</li> <li>h2_db_encryption_password</li> </ul>	Password for H2 database and password for encryption
<p><b>Discovery configuration</b> - The following variables configure discovery settings for Dashboard:</p> <ul style="list-style-type: none"> <li>discovery_source</li> <li>discovery_mode</li> <li>discovery_mode_auto_polling_interval</li> <li>discovery_mode_auto_delete_non_discovered_apis</li> </ul> <p><b>Discovery source</b> - Defines the details of discovery source for PingAccess or Axway API gateway.</p> <p><b>PingAccess</b></p> <ul style="list-style-type: none"> <li>pingaccess_url</li> <li>pingaccess_username</li> <li>pingaccess_password</li> </ul> <p><b>Axway</b></p> <ul style="list-style-type: none"> <li>axway_url</li> <li>axway_username</li> <li>axway_password</li> </ul>	<ul style="list-style-type: none"> <li>discovery_source - Defines the source of discovered APIs. The discovery source can be <code>abs</code>, <code>pingaccess</code>, or <code>axway</code></li> <li>discovery_mode - Defines the mode in which Dashboard publishes APIs to ASE. It can either be <code>auto</code> or <code>manual</code> mode. For more information on discovery mode, see <a href="#">Discovered APIs</a> on page 540</li> <li>discovery_mode_auto_polling_interval - If the mode is set to <code>auto</code> in previous option, then configure the time interval in minutes for publishing the APIs to ASE. It recommended to keep a minimum time interval of 10 minutes.</li> <li>discovery_mode_auto_delete_non_discovered_apis - If the mode is set to <code>auto</code>, you can configure whether you want to delete the other APIs from ASE when Dashboard publishes the discovered APIs.</li> </ul> <p>Configure PingAccess or Axway URL, username and password if the discovery source is <code>pingaccess</code> or <code>axway</code>.</p>

Variable	Description
<code>enable_xpack</code>	Configures whether the deployment package installs X-pack. The default value is <code>true</code> . If you are using an existing Elasticsearch and authentication is not configured for Xpack, set <code>enable_xpack</code> to <code>false</code> .
<code>elasticsearch_url</code>	If you have set <code>install_elasticsearch</code> as <code>false</code> in the <code>hosts</code> file, configure the Elasticsearch URL. Enter the complete URL including <code>http/https</code> . For example, <a href="https://myelasticsearchurl.pi.com:443">https://myelasticsearchurl.pi.com:443</a> . Providing the port number in the URL is mandatory.
<code>elasticsearch_distro_type</code>	Configure the distribution type of Elasticsearch. Allowed values are <code>default</code> or <code>aws</code> .  <div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> This variable is available for configuration in PingIntelligence for APIs 4.4.1.</p> </div>
<code>elastic_username</code>	If you want to use an already available Elasticsearch username, configure it in <code>elastic_username</code> .
<code>kibana_port</code>	The port number on which Dashboard communicates with Kibana.
<code>elastic_password</code>	Elasticsearch password. The default value is <code>changeme</code> .  <div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> Do not change the <code>elastic_password</code> after PingIntelligence installation is complete.</p> </div>
<code>kibana_password</code>	Kibana password. The default value is <code>changeme</code> .  <div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> Do not change the <code>kibana_password</code> after PingIntelligence installation is complete.</p> </div>
<code>ping_user_password</code>	Password for the default user name <code>ping_user</code> .
<code>ping_admin_password</code>	Password for the admin.

Variable	Description
Syslog configuration: <ul style="list-style-type: none"> <li>▪ enable_syslog</li> <li>▪ host, port</li> <li>▪ facility</li> </ul>	Configure Syslog details.  Setting <code>enable_syslog</code> to <code>true</code> lets dashboard engine log the ABS detected attacks in the <code>syslog</code> server.  Provide the host and port number of syslog server.
<code>restricted_user_access</code>	Defines the user for viewing information in API Dashboard. Set it to <code>true</code> to set the user as a restricted user. The header in API query string used depends on the type of user, restricted or admin. For more information on user headers, see <a href="#">ABS users for API reports</a> on page 315

**i Important:**

Make sure to take a backup of the `dashboard-defaults.yml` file on a secure machine after the automated installation is complete.

The following is a sample `dashboard-defaults.yml` file.

```

---
webgui:
  # Define ports for PingIntelligence WebGUI
  # Make sure ports are not same for single server installation
  port: 8030

  # allowed values: native, sso.
  # In native mode, webgui users are self managed and stored in webgui.
  # In sso mode, webgui users are managed and stored in an Identity
  provider.
  authentication_mode: native
  # Maximum duration of a session.
  # Value should be in the form of <number><duration_suffix>
  # Duration should be > 0.
  # Allowed duration suffix values: m for minutes, h for hours, d for days.
  session_max_age: 6h

  # Number of active UI sessions at any time.
  # Value should be greater than 1.
  max_active_sessions: 50

  ## admin_password and ping_user_password are applicable in native
  authentication_mode only.
  # webgui "admin" account password
  admin_password: changeme
  # webgui "ping_user" account password
  ping_user_password: changeme

  ## Below sso configuration properties are applicable in sso
  authentication_mode only.
  # Client ID value in Identity provider.
  sso_oidc_client_id: pingintelligence
  # Client Secret of the above Client ID.
  sso_oidc_client_secret: changeme
  # OI DC Client authentication mode.
  # Valid values: BASIC, POST, or NONE

```

```

sso_oidc_client_authentication_method: BASIC
# OIDC Provider uri
# WebGUI queries <issuer-uri>/well-known/openid-configuration to get OIDC
provider metadata
# issuer ssl certificate is not trusted by default. So import issuer ssl
certificate into config/webgui.jks
# issuer should be reachable from both back-end and front-end
sso_oidc_provider_issuer_uri: https://127.0.0.1:9031

# Place the sso provider issuer-certificate in the following path =>
<installation_path>/pingidentity/certs/webgui/
# Name of the file should be => webgui-sso-oidc-provider.crt

# claim name for unique id of the user in UserInfo response
# a new user is provisioned using this unique id value
sso_oidc_provider_user_uniqueid_claim_name: sub
# claim name for first name of the user in UserInfo response
# either first name or last name can be empty, but both should not be
empty
sso_oidc_provider_user_first_name_claim_name: given_name
# claim name for last name of the user in UserInfo response
# either first name or last name can be empty, but both should not be
empty
sso_oidc_provider_user_last_name_claim_name: family_name
# claim name for role of the user in UserInfo response
sso_oidc_provider_user_role_claim_name: role
# additional scopes in authorization request
# multiple scopes should be comma (,) separated
# openid,profile scopes are always requested
sso_oidc_client_additional_scopes:
## End of sso configuration

# ssl key store password of webgui hosts
server_ssl_key_store_password: changeme
server_ssl_key_alias: webgui

# local h2 db datasource properties
h2_db_password: changeme
h2_db_encryption_password: changeme

# allowed values: abs/pingaccess/axway
discovery_source: abs
# allowed values: auto/manual
discovery_mode: auto
# value is in minutes
discovery_mode_auto_polling_interval: 10
discovery_mode_auto_delete_non_discovered_apis: false

# valid only if discovery_source is set to pingaccess
pingaccess_url: https://127.0.0.1:9000/
pingaccess_username: Administrator
pingaccess_password:

# valid only if discovery_source is set to axway
axway_url: https://127.0.0.1:8075/
axway_username: apiadmin
axway_password:

dashboard:
  ui:
    # Install elasticsearch with xpack enabled
    # If there is no authentication on pre-existing elasticsearch, set this
to false
    enable_xpack: true

```

```

# When install_elasticsearch is set to false in config/hosts, this url
will be used
# Give the complete url with https/http and elasticsearch port number
# Make sure elasticsearch_url is accessible from ansible management
host, dashboard, webgui and kibana nodes.
elasticsearch_url: https://search-
giueibohzd6pfijfysjfsxuucty.pingidentity.com:443
# Configuration distribution type of elasticsearch. Allowed values are
default or aws
elasticsearch_distro_type: default

# User with permission set similar to "elastic" user
elastic_username: elastic

# Passwords for "elasticsearch", "kibana", "ping_user" and "ping_admin"
users
# Dashboard will be accessible for these accounts
# Please set strong passwords
# If enable_xpack is set to false, below passwords are ignored
elastic_password: changeme
kibana_password: changeme
ping_user_password: changeme
ping_admin_password: changeme

# Define ports for the PingIntelligence Dashboard
# Make sure ports are not same for single server installation
kibana_port: 5601

syslog:
# Configuration for syslog
enable_syslog: false
host: localhost
port: 614
facility: LOCAL0

# ABS Restricted user access ( true/false )
# Set to false for displaying non-obfuscated blacklist in Kibana
abs:
restricted_user_access: false

```

### Change settings in ilm.json

You can change the default settings of Index Lifecycle Management (ILM) policy by editing the `<pi-install-path>/pingidentity/pi-api-deployment/config/ilm.json` file. The ILM policy allows you to manage the lifecycle of the Elasticsearch indices. The following table lists the variables that you can set in the `ilm.json` file. For more information on `ilm.json` configuration, see [Automatic rollover index](#) on page 504.

Variable	Description
<code>max_size</code>	Defines the maximum size of the Elasticsearch rollover index. When the index size reaches the defined value, it rolls over. <code>max_size</code> value should be a positive non-zero number. Allowed units are MB and GB.



Variable	Description
max_age	Defines the maximum age of the Elasticsearch rollover index configuration. <code>max_age</code> value should be a positive non-zero number. Allowed units are <code>h</code> for hours and <code>d</code> for the number of days. If both <code>max_size</code> and <code>max_age</code> are configured, then the index rolls over based on the value that is achieved first.
min_age	Defines the minimum age, after which the Elasticsearch rollover index enters into a different phase. Allowed units are <code>h</code> for hours and <code>d</code> for the number of days. Every index starts from <code>hot</code> phase. For more information on the phases in an index life cycle, see <a href="#">Automatic rollover index</a> on page 504.
priority	Defines the sequence in which, indices are reloaded back into memory when Elasticsearch restarts. Use a positive integer number to set the priority.

**i Important:**

Rollover index configuration takes effect only when `enable_xpack` is set to `true` in `dashboard-default.yml` file. For more information, see [Change settings in dashboard-default.yml](#) on page 66.

The following is a sample `ilm.json` file.

```
{
  "policy": {
    "phases": {
      "hot": {
        "actions": {
          "rollover": {
            "max_size": "7GB",
            "max_age": "7d"
          },
          "set_priority": {
            "priority": 100
          }
        }
      },
      "warm": {
        "min_age": "30d",
        "actions": {
          "set_priority": {
            "priority": 50
          }
        }
      },
      "cold": {
        "min_age": "90d",
        "actions": {
          "freeze": {},
          "set_priority": {
            "priority": 0
          }
        }
      }
    }
  }
}
```



1. Set the `vm.max_map_count` to 262144 on the Elasticsearch VM. To set the count, enter the following command:

```
$sudo sysctl -w vm.max_map_count=262144
```

To make the setting persistent across reboots, run the following command:

```
$sudo echo "vm.max_map_count=262144" >> /etc/sysctl.conf
```

2. Set the `ulimit` to 65536 on the ASE, ABS, MongoDB, and Elasticsearch hosts. To set the `ulimit`, complete the following:

edit `/etc/security/limits.conf` for increasing the soft limit and hard limit. Add the following two lines for the user that you have created, for example, `pi-user`:

```
pi-user soft nofile 65536
pi-user hard nofile 65536
```

**Note:** If the number of APIs in the environment is greater than 1500, then set the `ulimit` to 131070.

## Step 5 - Install the PingIntelligence for APIs software

Run the following command to setup the deployment. Accept the EULA displayed on the screen for ABS for installation to start.

```
[pi-api-deployment]# ./bin/start.sh install
Please see /opt/pingidentity/pi-api-deployment/logs/ansible.log for more
details.
```

To verify a successful setup, view the `ansible.log` file. Here is a log file snippet for a successful setup:

```
[pi-api-deployment]# tail -f logs/ansible.log
=====
Current Time: Sun Jun 07 06:06:22 EST 2020
Starting setup scripts
=====
Sun Jun 07 06:06:22 EST 2020: Setting up local environment
Sun Jun 07 06:06:22 EST 2020: Installing packages
Sun Jun 07 06:06:23 EST 2020: Installing pip and ansible
.
.
PLAY RECAP
*****
127.0.0.1           : ok=9    changed=0    unreachable=0    failed=0
192.168.11.143     : ok=25   changed=13   unreachable=0    failed=0
192.168.11.144     : ok=57   changed=39   unreachable=0    failed=0
192.168.11.145     : ok=56   changed=35   unreachable=0    failed=0

Sun Jun 07 06:23:37 EST 2020: Setup successful
=====
```

### Updated PingIntelligence packages

The automated deployment framework creates the updated package for each PingIntelligence component and stores them in the `/opt/pingidentity/pi-api-deployment/software/updated_packages` directory. The keys, passwords, and port number in these packages are the ones that you configured using the `yml` files in the `/opt/pingidentity/pi-api-deployment/config` directory. You can use these packages to install PingIntelligence components on other instances.

**Note:** The CLI admin password in ASE and ABS is saved in the updated packages. If you want to change the CLI admin password, use the `update_password` command in ASE and ABS to manually update the password.

## Install PingIntelligence as a systemd service

You can install the various PingIntelligence components as a systemd service. Installing as a service, the various components are started automatically when the host system restarts. You require `sudo` access to install PingIntelligence components as a service. Complete the following steps only if the automated deployment did not install PingIntelligence components as a service. Run the following command on the host machine for which you want to verify that is service is installed or not:

```
# systemctl status <service-name>
```

For example, to check ASE service, enter the following command on ASE host machine:

```
systemctl status pi-ase.service
● ase.service - ASE
   Loaded: loaded (/etc/systemd/system/ase.service; disabled; vendor preset:
   disabled)
   Active: active (running) since Sun 2019-11-03 23:01:19 MST; 23h ago
   .
   .
Nov 03 23:01:19 T5-06 systemd[1]: Started ASE.
```

### Prerequisite for installing PingIntelligence service:

- Verify that PingIntelligence services are not running. Use the following service names to verify the status of each component:
  - **ASE:** `pi-ase.service`
  - **ABS:** `pi-abs.service`
  - **MongoDB:** `pi-mongodb.service`
  - **Dashboard:** `pi-dashboard.service`
  - **Web GUI:** `pi-webgui.service`
  - **Elasticsearch:** `pi-elasticsearch.service`
  - **Kibana:** `pi-kibana.service`
- Stop the component for which you want to install the service.

**Steps:** Complete the following steps:

1. Make sure that the component for which you want to install the service is stopped.
2. Log in to the host machine for which you want to install the service. For example, if you want to install ASE as a service, log in to the ASE host machine.
3. Navigate to the `util` directory. Enter the following command as a `root` user to install PingIntelligence as a service:

```
#sudo ./install-systemctl-service.sh <component_name> <ansible_user_name>
```

For example, on ASE host machine:

```
#sudo ./install-as-service.sh pi-ase pi-user
```

Install service for each component in a similar way on the respective host machine.

**Order of restarting PingIntelligence components:** Edit the service files to make sure that PingIntelligence components in the following order. Use the `Required` option to set the order of starting of service. For more information, see [Creating and modifying systemd unit files](#) :

1. MongoDB
2. ABS
3. ASE
4. Elasticsearch
5. Kibana
6. Dashboard
7. Web GUI

## Verify PingIntelligence Installation

Verify that all the components have installed and started successfully.

### Verify ASE installation

Log in to the ASE host machine and navigate to `<installation-path>/pingidentity/ase/bin` directory and run the `status` command:

```
/home/pi-user/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status           : started
mode             : inline
http/ws          : port 8090
https/wss        : port 8443
firewall         : enabled
abs              : disabled, ssl: enabled
abs attack       : disabled
audit            : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

If the `status` command runs successfully, then ASE has been installed and started.

### Verify ABS and MongoDB installation

Log in to the ABS EC2 instance and run the ABS Admin REST API using a REST API client like Postman. More information on installing and configuring Postman is available in the ABS Admin Guide.

The report can be accessed by calling the ABS system at the following URL:

[https://<abs\\_ip>:<abs\\_port>/v4/abs/admin](https://<abs_ip>:<abs_port>/v4/abs/admin). Use the IP address from the hosts file.

If ABS and MongoDB has installed successfully, the Admin REST API output will display the MongoDB nodes. If the Admin API is not accessible, then ABS has not started. Following is a sample output of the Admin REST API:

```
{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "license_info": {
    "tier": "Free",
    "expiry": "Sun Jan 10 00:00:00 UTC 2021",
    "max_transactions_per_month": 0,
    "current_month_transactions": 30,
    "max_transactions_exceeded": false,
    "expired": false
  },
  "across_api_prediction_mode": true,
  "poc": true,
  "api_discovery": {
    "subpath_length": "1",
    "status": true
  }
}
```

```

},
"apis": [
  {
    "api_name": "atm_app_oauth",
    "host_name": "*",
    "url": "/atm_app_oauth",
    "api_type": "regular",
    "creation_date": "Thu Mar 05 08:54:01 UTC 2020",
    "servers": 1,
    "protocol": "https",
    "cookie": "JSESSIONID",
    "token": false,
    "training_started_at": "Fri Feb 14 06:44:06 UTC 2020",
    "training_duration": "1 hour",
    "prediction_mode": true,
    "apikey_header": "X-API-KEY-2",
    "apikey_qs": "",
    "jwt": {
      "username": "",
      "clientid": "",
      "location": ""
    }
  },
  {
    "api_name": "root_api",
    "host_name": "*",
    "url": "/",
    "api_type": "regular",
    "creation_date": "Thu Mar 05 08:54:01 UTC 2020",
    "servers": 1,
    "protocol": "https",
    "cookie": "JSESSIONID",
    "token": false,
    "training_started_at": "n/a",
    "training_duration": "n/a",
    "prediction_mode": false,
    "apikey_header": "X-API-KEY-1",
    "apikey_qs": "",
    "jwt": {
      "username": "",
      "clientid": "",
      "location": ""
    }
  }
],
"abs_cluster": {
  "abs_nodes": [
    {
      "node_ip": "127.0.0.1",
      "os": "Red Hat Enterprise Linux Server - VMware, Inc.",
      "cpu": "16",
      "memory": "31G",
      "filesystem": "3%",
      "bootup_date": "Fri Feb 28 08:13:19 UTC 2020"
    },
    {
      "node_ip": "127.0.0.1",
      "os": "Red Hat Enterprise Linux Server - VMware, Inc.",
      "cpu": "16",
      "memory": "31G",
      "filesystem": "4%",
      "bootup_date": "Tue Mar 24 06:35:47 UTC 2020"
    }
  ]
},
],

```

```

    "mongodb_nodes": [
      {
        "node_ip": "127.0.0.1:27017",
        "status": "primary"
      }
    ]
  },
  "ase_logs": [
    {
      "ase_node": "88968c39-b4ea-4481-a0b4-d0d651468ab5",
      "last_connected": "Thu Mar 05 08:40:14 UTC 2020",
      "logs": {
        "start_time": "Thu Mar 05 08:40:14 UTC 2020",
        "end_time": "Thu Mar 05 08:40:14 UTC 2020",
        "gzip_size": "0.74KB"
      }
    },
    {
      "ase_node": "e6b82ce9-afb3-431a-8faa-66f7ce2148b9",
      "last_connected": "Thu Mar 05 08:54:06 UTC 2020",
      "logs": {
        "start_time": "Thu Mar 05 08:54:06 UTC 2020",
        "end_time": "Thu Mar 05 08:54:06 UTC 2020",
        "gzip_size": "2.82KB"
      }
    },
    {
      "ase_node": "4df50c47-407a-41f9-bda6-b72dc34dadad",
      "last_connected": "Fri Feb 28 07:20:03 UTC 2020",
      "logs": {
        "start_time": "Tue Feb 25 12:50:00 UTC 2020",
        "end_time": "Fri Feb 28 07:20:03 UTC 2020",
        "gzip_size": "76.01KB"
      }
    },
    {
      "ase_node": "1910051e-5bab-44e6-8816-5b5afffdd1cf",
      "last_connected": "Tue Feb 18 08:10:05 UTC 2020",
      "logs": {
        "start_time": "Fri Feb 14 06:42:38 UTC 2020",
        "end_time": "Tue Feb 18 08:10:05 UTC 2020",
        "gzip_size": "2.89MB"
      }
    }
  ],
  "percentage_diskusage_limit": "80%",
  "scale_config": {
    "scale_up": {
      "cpu_threshold": "70%",
      "cpu_monitor_interval": "30 minutes",
      "memory_threshold": "70%",
      "memory_monitor_interval": "30 minutes",
      "disk_threshold": "70%",
      "disk_monitor_interval": "30 minutes"
    },
    "scale_down": {
      "cpu_threshold": "10%",
      "cpu_monitor_interval": "300 minutes",
      "memory_threshold": "10%",
      "memory_monitor_interval": "300 minutes",
      "disk_threshold": "10%",
      "disk_monitor_interval": "300 minutes"
    }
  }
},

```

```

    "attack_ttl": {
      "ids": [
        {
          "id": "ip",
          "ttl": 120
        },
        {
          "id": "cookie",
          "ttl": 120
        },
        {
          "id": "access_token",
          "ttl": 120
        },
        {
          "id": "api_key",
          "ttl": 240
        },
        {
          "id": "username",
          "ttl": 360
        }
      ]
    }
  }
}

```

### Verify Dashboard Installation

To verify the Dashboard installation, enter the Dashboard IP address from the hosts file in your web browser. Log in using `ping_user` or `admin` username and the password configured in the `dashboard-defaults.yml` file. If the authentication mode is set to `SSO`, then log in using your SSO username and password.

See the ASE, ABS and Dashboard guides for configuration and administration of PingIntelligence products.

## Next steps - Integrate PingIntelligence into your environment

After the installation is complete, refer the following topics based on the type of deployment.

### Sideband configuration:

After you have completed the deployment, integrate one of the following API gateways with PingIntelligence components and start sending the API traffic to your API gateway:

- [Akana API gateway sideband integration](#) on page 558
- [PingIntelligence Apigee integration](#) on page 581
- [PingIntelligence AWS API Gateway Integration](#) on page 601
- [Azure APIM sideband integration](#) on page 640
- [Axway sideband integration](#) on page 616
- [PingIntelligence - CA API gateway sideband integration](#) on page 649
- [F5 BIG-IP PingIntelligence integration](#) on page 658
- [IBM DataPower Gateway sideband integration](#) on page 670
- [PingIntelligence - Kong API gateway integration](#) on page 677
- [Mulesoft sideband integration](#) on page 684
- [NGINX sideband integration](#) on page 698
- [NGINX Plus sideband integration](#) on page 714
- [PingAccess sideband integration](#) on page 747
- [PingFederate sideband integration](#) on page 758
- [PingIntelligence WSO2 integration](#) on page 764



**Inline configuration:** If you configured PingIntelligence ASE as *Inline ASE* on page 210, the next step is to add *API definitions to the PingIntelligence for APIs* software. After this is complete, direct your API client to the IP address of the ASE software on port 80 or 443.

It is recommended to read the following topics (part of the admin guides) apart from reading the *ASE* and *ABS* Admin Guides:

- [ASE port information](#)
- [API naming guidelines](#)
- [Connect ASE and ABS](#)

After you have added your APIs in ASE, the API model needs to be trained. The training of API model is completed in ABS. The following topics give a high level view, however it is a good practice to read the entire ABS Admin Guide.

- [Train your API model](#)
- [Generate and view the REST API reports using Postman](#): To access the ABS REST API reports you would require the following information:
  - IP address: IP address of ABS configured in the `config/hosts` file.
  - Port number: default value is 8080. It is configured in `abs-defaults.yml` file
  - API Name: Name of the API for which you want to generate REST API reports
  - Later and Earlier date: The date range for which you want to generate the reports
- View [Access PingIntelligence Dashboard](#) on page 20:

Login to PingIntelligence Dashboard using the `ping_user` login ID and the password that you configured during PingIntelligence installation. For more information on password configuration, see [Change Dashboard default settings](#) on page 66. The PingIntelligence for APIs Dashboard takes approximately one hour to start showing attack information.

## Shut down the deployment

To shut down the deployment and remove all VMs and data, run the `stop.sh` command. When you shut down the deployment, all the VMs along with the data is deleted.

```
[pi-api-deployment]# ./bin/stop.sh
Please see /opt/pingidentity/pi-api-deployment/logs/ansible.log for more
details.
```

To verify whether the deployment was successfully stopped, check the `ansible.log` file:

```
[pi-api-deployment]# tail -f logs/ansible.log
=====
Current Time: Sun Jun 07 07:23:11 EST 2020
Starting stop scripts
=====
Sun Jun 07 07:23:11 EST 2020: Play stop setup
PLAY RECAP
*****
192.168.11.124 : ok=2 changed=1 unreachable=0 failed=0
192.168.11.145 : ok=2 changed=1 unreachable=0 failed=0
192.168.11.146 : ok=2 changed=1 unreachable=0 failed=0
192.168.11.148 : ok=2 changed=1 unreachable=0 failed=0
192.168.11.149 : ok=4 changed=3 unreachable=0 failed=0
Sun Jun 07 07:32:53 EST 2020: Stop successful
=====
```

Manually remove the PingIntelligence component service scripts from `/etc/systemd/system/pi-*` location.

## Logs

The `ansible.log` file for all the stages is available in the `/opt/pingidentity/pi-api-deployment/logs` directory.

The `logs` directory also stores `hostinfo.log` file. This log file stores information about all the hosts. Every time the automated deployment is run, the `hostinfo.log` file is appended with the host information. Following is a snippet of the log file.

```
***** Wed Apr 01 02:07:26 UTC 2020
*****
```

```
=====
Hostname: ping-rhel-3
Inventory Hostname: 172.16.40.69
PI components installed on this host:
- mongodb
```

```
Date & Time: 2020-03-31 20:05:46 MDT
Timezone: MDT
Distribution: RedHat
Release: Maipo
Distribution Version: 7.6
Kernel: 3.10.0-957.10.1.el7.x86_64
Architecture: x86_64
CPU Core: 4
RAM: 15.4951171875 GB
```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/mapper/rhel-root	530G	132G	398G	25%	/
devtmpfs	7.8G	0	7.8G	0%	/dev
tmpfs	7.8G	12K	7.8G	1%	/dev/shm
tmpfs	7.8G	335M	7.5G	5%	/run
tmpfs	7.8G	0	7.8G	0%	/sys/fs/cgroup
/dev/sdal	1014M	153M	862M	16%	/boot
tmpfs	1.6G	0	1.6G	0%	/run/user/988
tmpfs	1.6G	0	1.6G	0%	/run/user/1018
tmpfs	1.6G	0	1.6G	0%	/run/user/1045

```
=====
Hostname: ping-ubuntu-1
Inventory Hostname: 172.16.40.81
PI components installed on this host:
- abs
- ase
- dashboard
- kibana
- webgui
```

```
Date & Time: 2020-03-31 20:07:16 MDT
Timezone: MDT
Distribution: Ubuntu
Release: xenial
Distribution Version: 16.04
Kernel: 4.4.0-148-generic
Architecture: x86_64
CPU Core: 4
RAM: 15.6533203125 GB
```

Filesystem	Size	Used	Avail	Use%	Mounted
on					
udev	7.9G	0	7.9G	0%	/dev
tmpfs	1.6G	860K	1.6G	1%	/run
/dev/mapper/ubuntu--1604--template--vg-root	467G	106G	343G	24%	/
tmpfs	7.9G	140K	7.9G	1%	/dev/shm

```

tmpfs                    5.0M      0  5.0M    0% /run/lock
tmpfs                    7.9G      0  7.9G    0% /sys/fs/
cgroup
/dev/sda1                720M    108M   576M   16% /boot
cgmfs                    100K      0   100K    0% /run/
cgmanager/fs
tmpfs                    1.6G      0   1.6G    0% /run/
user/1012
tmpfs                    1.6G      0   1.6G    0% /run/
user/1005

```

```

=====
Hostname: ping-rhel-2
Inventory Hostname: 172.16.40.228
PI components installed on this host:
- elasticsearch

```

```

Date & Time: 2020-03-31 20:06:05 MDT
Timezone: MDT
Distribution: RedHat
Release: Maipo
Distribution Version: 7.6
Kernel: 3.10.0-957.10.1.el7.x86_64
Architecture: x86_64
CPU Core: 4
RAM: 15.5126953125 GB

```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/mapper/rhel-root	488G	7.5G	481G	2%	/
devtmpfs	7.8G	0	7.8G	0%	/dev
tmpfs	7.8G	80K	7.8G	1%	/dev/shm
tmpfs	7.8G	801M	7.0G	11%	/run
tmpfs	7.8G	0	7.8G	0%	/sys/fs/cgroup
/dev/sda1	1014M	153M	862M	16%	/boot
tmpfs	1.6G	0	1.6G	0%	/run/user/1015
tmpfs	1.6G	0	1.6G	0%	/run/user/1040

```

=====
***** Wed Apr 01 02:07:26 UTC 2020
*****
***** Wed Apr 01 02:08:13 UTC 2020
*****
=====

```

```

Hostname: ping-ubuntu-1
Inventory Hostname: 172.16.40.81
PI components installed on this host:
- abs
- ase
- dashboard
- elasticsearch
- kibana
- mongoddb
- webgui

```

```

Date & Time: 2020-03-31 20:08:10 MDT
Timezone: MDT
Distribution: Ubuntu
Release: xenial
Distribution Version: 16.04
Kernel: 4.4.0-148-generic
Architecture: x86_64
CPU Core: 4
RAM: 15.6533203125 GB

```

Filesystem	Size	Used	Avail	Use%	Mounted
on					

```

udev                7.9G      0    7.9G    0% /dev
tmpfs               1.6G    860K    1.6G    1% /run
/dev/mapper/ubuntu--1604--template--vg-root 467G    106G    343G    24% /
tmpfs               7.9G    140K    7.9G    1% /dev/shm
tmpfs               5.0M      0    5.0M    0% /run/lock
tmpfs               7.9G      0    7.9G    0% /sys/fs/
cgroup
/dev/sda1           720M    108M    576M    16% /boot
cgfs
cgmanager/fs
tmpfs               1.6G      0    1.6G    0% /run/
user/1012
tmpfs               1.6G      0    1.6G    0% /run/
user/1005
=====
***** Wed Apr 01 02:08:13 UTC 2020
*****

```

## Manual deployment

---

### PingIntelligence manual deployment

The topic gives a summary about PingIntelligence products, the different users that can install the product and the time zone in which the products can be deployed.

PingIntelligence for APIs software combines real-time security and AI analytics to detect, report, and block cyberattacks on data and applications exposed via APIs. The software consists of three platforms: API Security Enforcer(ASE), API Behavioral Security(ABS) AI engine, and PingIntelligence Dashboard.

#### API Security Enforcer (ASE)

Applies real-time API metadata ingestion and enforces optional blocking. ASE can be deployed in inline or sideband mode and works with the ABS engine to identify attacks. For more information, see [Inline ASE](#) on page 210 and [Sideband ASE](#) on page 160.

#### API Behavioral Security (ABS) AI Engine

Executes AI algorithms to detect in near real-time cyberattacks targeting data, applications, and systems via APIs. Attack information can be automatically pushed to all ASEs to block ongoing breaches and prevent reconnection.

#### PingIntelligence for APIs Dashboard

PingIntelligence for APIs Dashboard offers you the following:

- Visibility into API activity.
- View the training status and other information of your APIs
- Manage API Discovery using automatic or manual mode
- View attack insight to understand why a client was flagged for an attack
- Manage attacks by unblocking clients or tune AI Engine thresholds
- View ABS license information

The dashboard engine utilizes Elasticsearch and Kibana to provide a graphical view of an API environment including user activity, attack information, and blacklisted clients.

#### Administrators

You can install all the PingIntelligence products either as a user with `sudo` access or a normal user (without `sudo` access). Make sure that the entire deployment is a homogenous deployment. Either all the products should be installed as a `sudo` user or as a normal user.

Time zone

All PingIntelligence components (ASE, ABS AI Engine, and Dashboard) should be installed using the same time zone, either local or UTC. MongoDB should also be configured to the same time zone as PingIntelligence components.

## Part A – Install ABS and MongoDB

The ABS Engine installation process is summarized below:

- Provision systems based on the queries per second (QPS)
- Install MongoDB in a replica set
- Install ABS engine
- Connect ABS engine to MongoDB

### Install ABS AI engine software

You can install ABS as a root user or as a non-root user. The example installation path assumes that you are root user. The installation works in a similar way for a non-root user.

1. Go to the [download site](#)
2. Click on **Select** under PingIntelligence
3. Choose the build and click **Download**.

Copy the build file to the `/opt` directory if you are installing the product as a root user. Choose any other location if you want to install ABS as a non-root user.

Install ABS

Before installing ABS:

- Install OpenJDK 11.0.2 on a 64-bit architecture machine. To verify the Java version, run the following command.

```
# java -version
```

- Verify the supported operating systems. PingIntelligence supports RHEL 7.9 and Ubuntu 18.04 LTS.

It is recommended to install only one instance of ABS on each machine. MongoDB should be installed on a different machine from ABS.

To install ABS, complete the following steps:

1. Change working directory to `/opt` if you are installing the product as a root user. Choose any other location if you want to install ABS as a non-root user.
2. At the command prompt, type: `# tar -zxvf <file_name>`

For example, `# tar -zxvf pi-api-abs-4.4.tar.gz`

**Note:** If you are installing as a non-root user then, increase the `ulimit -n` to 65535.

### ABS License

To start ABS, you need a valid PingIntelligence license. There are two types of licenses:

- **Trial license** – The trial license is valid for 30-days. At the end of the trial period, ABS stops processing.
- **Subscription license** – The subscription license is based on the peak number of transactions subscribed for per month and the duration of the license. It is a good practice to [configure your email](#) before configuring the license. ABS sends an email notification to the configured email ID when the

license has expired. Contact the Ping Identity sales team for more information. The following points should be noted:

- **Maximum transaction set to 0:** If your subscription license has zero as maximum transaction, it means that the license has unlimited monthly transaction. Such a license only expires at the end of subscription period.
- **License expiry:** In case when the subscription license has expired, ABS continues to run until a restart. ABS needs a valid license file to start.

#### Add an ABS license

If you have not received license, request a license file from Ping sales. The name of the license file must be `PingIntelligence.lic`. Copy the license file to the `/opt/pingidentity/abs/config` directory and then start ABS.

#### Update an existing license

If your existing license has expired, obtain a new license from Ping sales and replace the license file in the `/opt/pingidentity/abs/config` directory. Stop and then start ABS after the license file is updated.

#### Checking the current transaction count

Use the [Admin REST API - Duplicate](#) to view the current transaction count against your subscribed transaction limit. Following snippet of the Admin REST API shows the license information:

```
{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "license_info": {
    "tier": "Subscription",
    "expiry": "Wed Jan 15 00:00:00 UTC 2020",
    "max_transactions_per_month": 1000000000,
    "current_month_transactions": 98723545,
    "max_transactions_exceeded": false,
    "expired": false
  }
}
```

#### Obfuscate passwords


Using ABS command line interface, you can obfuscate the keys and passwords configured in `abs.properties`. The following keys and passwords are obfuscated:

- `mongo_password`
- `jks_password`
- `email_password`

ABS ships with a default `abs_master.key` which is used to obfuscate the various keys and passwords. It is recommended to generate your own `abs_master.key`. The default `jks_password` `abs123` is configured in the `abs.properties` file.

**Note:** During the process of obfuscation of keys and password, ABS must be stopped.

The following diagram summarizes the obfuscation process:



### Generate abs\_master.key

You can generate the `abs_master.key` by running the **generate\_obfkey** command in the ABS CLI:

```

/opt/pingidentity/abs/bin/cli.sh generate_obfkey -u admin -p admin

Please take a backup of config/abs_master.key before proceeding.

Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh -obfuscate_keys

Warning: Obfuscation master key file
/pingidentity/abs/config/abs_master.key already exist. This command will
delete it create a new key in the same file

Do you want to proceed [y/n]: y

creating new obfuscation master key
Success: created new obfuscation master key at /pingidentity/abs/config/
abs_master.key
  
```

The new `abs_master.key` is used to obfuscate the passwords in `abs.properties` file.

**Important:** In an ABS cluster, the `abs_master.key` must be manually copied to each of the cluster nodes.

### Obfuscate key and passwords

Enter the keys and passwords in clear text in `abs.properties` file. Run the **obfuscate\_keys** command to obfuscate keys and passwords:

```

/opt/pingidentity/abs/bin/cli.sh obfuscate_keys -u admin -p admin

Please take a backup of config/abs.password before proceeding

Enter clear text keys and password before obfuscation.

Following keys will be obfuscated

config/abs.properties: mongo_password, jks_password and email_password
Do you want to proceed [y/n]: y

obfuscating /pingidentity/abs/config/abs.properties

Success: secret keys in /pingidentity/abs/config/abs.properties obfuscated
  
```

Start ABS after passwords are obfuscated.

**i Important:** After the keys and passwords are obfuscated, the `abs_master.key` must be moved to a secure location from ABS.

### Import existing CA-signed certificates

You can import your existing CA-signed certificate in ABS. To import the CA-signed certificate, stop ABS if it is already running. Complete the following steps to import the CA-signed certificate:

1. Export your CA-signed certificate to PKCS12 store by entering the following command:

```
# openssl pkcs12 -export -in <your_CA_certificate.crt> -inkey
<your_certificate_key.key> -out abs.p12 -name <alias_name>
```

For example:

```
# openssl pkcs12 -export -in ping.crt -inkey ping.key -out abs.p12 -name
exampleCAcertificate
Enter Export Password:
Verifying - Enter Export Password:
```

**i Note:** If you have intermediate certificate from CA, then append the content to the `<your_CA_certificate>.crt` file.

2. Import the certificate and key from the PKCS12 store to Java Keystore by entering the following command. The command requires the destination keystore password. The destination keystore password entered in the command should be same that is configured in the `abs.properties` file.

The following is a snippet of the `abs.properties` file where the destination keystore password is stored. The password is obfuscated.

```
# Java Keystore password
jks_password=OBF:AES:Q3vcrnj7VZILTPdJnxkOsyimHRvGDQ==:daYWJ5QgzxZJAnTkuRlFpreM1rsz3FF
```

Enter the following command:

```
# keytool -importkeystore -destkeystore abs.jks -srckeystore abs.p12 -
srcstoretype PKCS12 -alias <alias_name> -storetype jks
```

For example:

```
# keytool -importkeystore -destkeystore abs.jks -srckeystore abs.p12 -
srcstoretype PKCS12 -alias exampleCAcertificate -storetype jks

Importing keystore abs.p12 to abs.jks...
Enter destination keystore password:
Re-enter new password:
Enter source keystore password:
```

3. Copy the `abs.jks` file created in step 2 to `/opt/pingidentity/abs/config/ssl` directory.
4. Start ABS by entering the following command:

```
# /opt/pingidentity/abs/bin/start.sh
Starting API Behavioral Security 4.0...
please see /opt/pingidentity/abs/logs/abs/abs.log for more details
```

**i Note:**



ABS supports only TLS 1.1 and TLS 1.2 and requires Open JDK 11.0.2. By default SSL is enabled between ABS and ASE. If you need to disable SSL contact Ping Identity support team.

ABS ships with a default self-signed certificate with Java Keystore at `abs/config/ssl/abs.jks` and the default password set to `abs123` in the `abs.properties` file. The default password is obfuscated in the `abs.properties` file. It is recommended to change the default passwords and obfuscate the new passwords. See [Obfuscate passwords](#) on page 86 for steps to obfuscate passwords.

### Install MongoDB software

ABS uses a MongoDB database (4.2) to store analyzed logs and ABS cluster node information. MongoDB is installed using a replica set. In a replica set, MongoDB is installed on three nodes for high-availability (HA).

**Note:** If you are installing as a non-root user then, increase the `ulimit -n` to 65535.

#### Update MongoDB default username and password

You can change the default username and password of MongoDB by editing the `/opt/pingidentity/abs/mongo/abs_init.js` file. Change the username and password and save the file. The following is a snippet of the `abs_init.js` file:

```
{
  user: "absuser",
  pwd: "abs123",
  roles: [{ role: "clusterMonitor", db: "admin" },
          { role: "readWrite", db: "abs_metadata" },
          { role: "readWrite", db: "abs_data" },
          { role: "readWrite", db: "abs_mldata" },
          { role: "readWrite", db: "local" } ]
};
```

#### Install MongoDB in replica set

Download either the RHEL or Ubuntu MongoDB 4.2 Linux tarball from the MongoDB website. For more information, see <https://www.mongodb.org/downloads>.

**Important:** This document describes a RHEL 7 download, but the equivalent Ubuntu version of MongoDB is also supported. Use the Ubuntu MongoDB URL to download the Ubuntu version.

#### Prerequisite:

- Copy `/opt/pingidentity/abs/mongo/abs_init.js` file to the MongoDB node.
- Copy `/opt/pingidentity/abs/mongo/abs_rs.js` file to the MongoDB node.

**Important:** It is advised to follow MongoDB recommended setting, to avoid issues in your production MongoDB deployment. For more information, see <https://docs.mongodb.com/manual/administration/production-checklist-operations/> and <https://docs.mongodb.com/manual/administration/analyzing-mongodb-performance/>

Download MongoDB on three nodes which would form the replica set for high-availability (HA).

Install MongoDB one each node:

1. Create the MongoDB directory structure: create `mongo`, `data`, `logs`, and `key` directory on each MongoDB node.

```
# mkdir -p /opt/pingidentity/mongo/data /opt/pingidentity/mongo/logs \
```

```
/opt/pingidentity/mongo/key
```

2. Download MongoDB 4.2 on each node and extract to `/opt/pingidentity/mongo`

```
# cd /opt/pingidentity/
/opt/pingidentity# wget \
https://fastdl.mongodb.org/linux/mongodb-linux-x86_64-rhel70-4.2.0.tgz \
-O mongodb.tgz && tar xzf mongodb.tgz -C /opt/pingidentity/mongo/ --strip-
components=1
```

3. Update shell path variable and reload the shell.

```
/opt/pingidentity# echo PATH=$PATH:/opt/pingidentity/mongo/bin >>
 ~/.bashrc;
/opt/pingidentity# source ~/.bashrc
```

4. Start the MongoDB database on each node. `absrs01` is the name of the replica set. You can choose your own name for the replica set.

```
/opt/pingidentity# cd mongo
/opt/pingidentity/mongo# mongod --dbpath ./data/ --logpath ./logs/
mongo.log --port 27017 --replSet absrs01 --fork -bind_ip 0.0.0.0
```

**Note:** `bind_ip` is required for MongoDB to accept connections coming from machines other than the local host.

5. Check MongoDB connectivity among the three nodes. On MongoDB node 1, run the following command to check connectivity with node 2:

```
/opt/pingidentity/mongo# mongo --host <mongo node 2 IP address> --port
27017
```

6. Navigate to `abs_rs.js` file and edit to configure the IP address of the primary and secondary MongoDB nodes:

```
rsconf = {
  _id: "absrs01",
  members: [
    {
      _id: 0,
      host: "127.0.0.1:27017",
      priority: 10
    },
    {
      _id: 1,
      host: "<Mongo Node 2 IP>:27017",
      priority: 2
    },
    {
      _id: 2,
      host: "<Mongo Node 3 IP>:27017",
      priority: 2
    }
  ]
};
rs.initiate(rsconf)
rs.conf();
```

```
exit
```

**Note:** Make sure the secondary MongoDB nodes are reachable, and their host names are resolvable from the primary MongoDB node.

7. Initiate the configuration by entering the following command on MongoDB node 1's shell:

```
/opt/pingidentity/mongo# mongo --port 27017 < abs_rs.js
```

8. Verify that all the MongoDB nodes are running. On each MongoDB node, enter the following:

```
/opt/pingidentity/mongo# mongo --port 27017
```

The primary node will display the following prompt:

```
absrs01:PRIMARY>
```

The secondary nodes will display the following prompt:

```
absrs01:SECONDARY>
```

9. Create User and initialize the database using `abs_init.js` file after making necessary modifications. On the primary node (node 1) Enter the following command:

```
# mongo --host <mongo node 1 IP> --port 27017 < abs_init.js
```

**Note:** user name and password should be changed from the default values.

10. Generate a MongoDB key file.

```
/opt/pingidentity/mongo# openssl rand -base64 741 >key/mongodb-keyfile
```

11. Change the key file permission.

```
/opt/pingidentity/mongo# chmod 600 key/mongodb-keyfile
```

12. Copy the key file generated in step 11 on each node of the replica set

13. Shutdown MongoDB using the following command:

```
# mongod --dbpath ./data --shutdown
```

14. Restart all the MongoDB nodes with a key file and enable MongoDB authentication.

```
/opt/pingidentity/mongo# mongod --auth --dbpath ./data/ --logpath \
./logs/mongo.log --port 27017 --replSet absrs01 --fork --keyFile ./key/
mongodb-keyfile -bind_ip 0.0.0.0
```

**Note:**

- `bind_ip` is required for MongoDB to accept connections coming from machines other than the local host.
- The MongoDB cache size should be restricted to 25% of system memory. You can configure this by using MongoDB's `wiredTigerCacheSizeGB` option.

### Starting MongoDB with SSL

You can start MongoDB with SSL by using either a CA-signed or a self-signed certificate.

- **Using CA-signed certificate:** To add a CA-signed certificate, create a new PEM file by concatenating the certificate and its private key. Copy the resulting PEM file to the `/opt/pingidentity/mongo/key/` directory created in Step 1.

```
cat mongo-node-private-key mongo-node-certificate > /opt/pingidentity/mongo/key/mongodb.pem
```

- **Using self-signed certificate:** To use a self-signed certificate then as a first-step generate a self-signed certificate and keys. Complete the following steps:
  1. Change directory to `key` directory:

```
cd /opt/pingidentity/mongo/key
```

2. Generate a self-signed certificate and key:

```
openssl req -newkey rsa:2048 -new -x509 -days 365 -nodes -out mongodb-cert.crt -keyout mongodb-cert.key
```

3. Concatenate the certificate and the key:

```
cat mongodb-cert.key mongodb-cert.crt > mongodb.pem
```

After either a CA-signed certificate or self-signed certificate has been added to the `key` directory, shut down MongoDB and restart with `--tlsMode` flag.

1. Shut down MongoDB:

```
# mongod --dbpath ./data --shutdown
```

2. Restart MongoDB with `-tlsMode` flag:

```
mongod --auth --dbpath ./data/ --logpath ./logs/mongo.log --port 27017 --replSet absrs01 --fork --keyFile ./key/mongodb-keyfile -bind_ip 0.0.0.0 --tlsMode requireTLS --tlsCertificateKeyFile ./key/mongodb.pem
```

The `--tlsMode` flag can take the following three values:

- `allowTLS`
- `preferTLS`
- `requireTLS`

For more information on these options, see the [MongoDB documentation](#).

### Change default settings

It is recommended that you change the default key and password in ABS. Following is a list of commands to change the default values:

#### Change default JKS password

You can change the default password for KeyStore and the key. Complete the following steps to change the default passwords. Make sure that ABS is stopped before changing the JKS password.

**Important:** The KeyStore and Key password should be the same.

1. **Change the KeyStore password:** Enter the following command to change the KeyStore password. The default KeyStore password is `abs123`.

```
# keytool -storepasswd -keystore config/ssl/abs.jks
Enter keystore password: abs123
New keystore password: newjkspassword
```

```
Re-enter new keystore password: newjkspassword
```

- 2. Change the key password:** Enter the following command to change the key password. The default key password is abs123

```
# keytool -keypasswd -alias pingidentity -keypass abs123 -new
newjkspassword -keystore config/ssl/abs.jks
Enter keystore password: newjkspassword
```

Start ABS after you have changed the default passwords.

Change abs\_master.key

Run the following command to create your own ABS master key to obfuscate keys and password in ABS.

**Command:** generate\_obfkey. ABS must be stopped before creating a new abs\_master.key

**Stop ABS:** If ABS is running, then stop ABS before generating a new ABS master key. Enter the following command to stop ABS:

```
# /opt/pingidentity/abs/bin/stop.sh
checking API Behavioral Security status
sending shutdown signal to ABS, please wait...
API Behavioral Security stopped
```

**Change abs\_master.key:** Enter the generate\_obfkey command to change the default ABS master key:

```
/opt/pingidentity/abs/bin/cli.sh generate_obfkey -u admin -p admin
Please take a backup of config/abs_master.key before proceeding.
Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh -obfuscate_keys
Warning: Obfuscation master key file
/pingidentity/abs/config/abs_master.key already exists. This command will
delete it and create a new key in the same file
Do you want to proceed [y/n]: y
Creating new obfuscation master key
Success: created new obfuscation master key at /pingidentity/abs/config/
abs_master.key
```

Change CLI admin password

You can change the default admin password by entering the following command:

```
/opt/pingidentity/abs/bin/cli.sh update_password -u admin -p admin
New Password>
Reenter New Password>
Success. Password updated for CLI
```

Change default access and secret key in MongoDB

To change the default access and secret key, complete the following steps:

**Note:** ":" (colon) is a restricted character and not allowed in access key and secret key.

- 1. Connect to MongoDB by entering the following command:**

```
mongo --host <mongo-host> --port <mongo-port> --authenticationDatabase
admin -u absuser -p abs123
```

absuser and abs123 is the default user name and password for MongoDB.

2. On the MongoDB prompt, run the following command:

```
use abs_metadata
db.auth_info.updateOne( { access_key: "<new-access-key>", secret_key:
"<new-secret-key>" } )
```

## Connect ABS to MongoDB

### Check and open MongoDB default port

The MongoDB default port for connection with ABS is 27017. Run the `check_ports_abs.sh` script on the ABS machine to determine whether the default port is available. Input the MongoDB host IP address and default port as arguments. For example:

```
/opt/pingidentity/abs/util ./check_ports_abs.sh {MongoDB IPv4:[port]}
```

Run the script for MongoDB master and slave. If the default ports are not accessible, open the port from the MongoDB machine.

### Configure ABS to connect to MongoDB

ABS access key and secret key are used for MongoDB and REST API authentication. Edit `abs_init.js` in `/opt/pingidentity/mongo` directory to set the key values. Here is a sample `abs_init.js` file:

**Note:** ":" (colon) is a restricted character and not allowed in access key and secret key.

```
db.auth_info.insert({
"access_key" : "abs_ak",
"secret_key" : "abs_sk"
});
```

**Note:** Do not edit the `abs_init.js` file, for any subsequent changes to ABS access key and secret key. It is recommended to use `update_keys` CLI command to change the keys. For more information, see [ABS CLI](#) on page 415.

Copy the `abs_init.js` file from ABS

```
/opt/pingidentity/abs/mongo
```

folder to the MongoDB system `/opt/pingidentity/mongo` folder.

At the MongoDB command prompt, update the MongoDB settings with the latest `abs_init.js` file.

```
# mongo admin -u absuser -p abs123 < /opt/pingidentity/abs/mongo/abs_init.js
MongoDB Shell version 4.2.0
connecting to: admin
switched to db abs_metadata
WriteResult({ "nInserted" : 1})
bye
```

### Verify MongoDB SSL certificates

You can configure ABS to verify the validity of MongoDB server certificate, when ABS connects with MongoDB. This is an optional check which can be enabled by setting `mongo_certificate` parameter in `<pi_install_path>/pingidentity/abs/config/abs.properties` file. For more information, see [Verify MongoDB SSL certificates](#) on page 334.

## Start and Stop ABS

For ABS to start, the `abs_master.key` must be present in the `/opt/pingidentity/abs/config` directory. If you have moved the master key to a secured location for security reasons, copy it to the `config` directory before starting ABS.

You can start ABS in one of the following two ways:

- Using service script available in the `util` directory, or
- Using the `start.sh` script available in the `bin` directory.

### Start ABS as a service

Complete the following steps to start ABS as a service:

1. Navigate to the `util` directory and run the following command to install ABS as a service:

```
#sudo ./install-systemctl-service.sh pi-abs
```

2. Start the service by entering the following command:

```
systemctl start pi-abs.service
```

### Start ABS using start.sh script

To start ABS, run the `start.sh` script located in the `/opt/pingidentity/abs/bin` directory. Change working directory to `/opt/pingidentity/abs/bin`. Then start ABS by typing the following command:

```
$ /opt/pingidentity/abs/bin/start.sh
Starting API Behavioral Security 4.2...
please see /opt/pingidentity/abs/logs/abs/abs.log for more details
```

To verify ABS has started, change working directory to `data` directory and look for two `.pid` files, `abs.pid` and `stream.pid`. Check the newly added ABS node is connecting to MongoDB and has a heartbeat.

```
> use abs_metadata
switched to db abs_metadata
> db.abs_cluster_info.find().pretty()
{
  "_id" : ObjectId("58d0c633d78b0f6a26c056ed"),
  "cluster_id" : "c1",
  "nodes" : [
    {
      "os" : "Red Hat Enterprise Linux Server release 7.6 (Maipo)",
      "last_updated_at" : "1490088336493",
      "management_port" : "8080",
      "log_port" : "9090",
      "cpu" : "24",
      "start_time" : "1490077235426",
      "log_ip" : "2.2.2.2",
      "uuid" : "8a0e4d4b-3a8f-4df1-bd6d-3aec9b9c25c1",
      "dashboard_node" : false,
      "memory" : "62G",
      "filesystem" : "28%"
    }
  ]
}
```

Stop ABS using stop.sh script

To stop ABS, first stop API Security Enforcer (if it is running) or turn OFF the ABS flag in API Security Enforcer. If no machine learning jobs are processing, run the `stop.sh` script available in the `bin` directory.

```
# /opt/pingidentity/abs/bin/stop.sh
checking API Behavioral Security status
sending shutdown signal to ABS, please wait...
API Behavioral Security stopped
```

**Note:** If you have started ABS as a service and try to stop using the `stop.sh` script, ABS would restart after stopping.

Stop ABS using service script

Run the following command to stop the ABS service: c

```
systemctl stop pi-abs.service
```

## Part B – Install ASE

About this task

This section summarizes the key processes involved in API Enforcer Enforcer (ASE) installation.

A new ASE installation involves following steps:

1. [Understanding and determining ASE deployment modes.](#)
2. Provisioning the host system based on number of APIs and the expected queries per second (QPS). For information on sizing, contact Ping Identity support team.
3. [Reviewing port requirements.](#)
4. [Installing ASE.](#)
5. [Copying ASE license.](#)
6. [Changing default settings.](#)
7. [Obfuscating keys and passwords.](#)
8. [Tuning host system for high performance.](#)
9. [Starting ASE.](#)
10. [Configure SSL for client side connection or external APIs](#) on page 104

**Note:** ASE cluster setup facilitates high availability and increases both performance and overall system throughput. It is Ping Identity recommends setting up a cluster of ASE nodes for production environments. For more information on setting up an ASE cluster, see [Setup ASE cluster \(optional\)](#) on page 107 and [Administering an ASE cluster](#) on page 131.

Next steps

After installing ASE, proceed with the following tasks:

- **Configuring ASE** - ASE system level configuration entails modifying parameters in the `ase.conf` file located in the `config` directory. For more information, see [Sideband ASE configuration](#) or [Inline ASE configuration](#)
- **Configuring deployment method** - PingIntelligence supports on-premise and cloud deployment options. You can integrate ASE in hybrid mode with [PingOne API Intelligence](#), which is a cloud based service. For more information, see [Configure deployment method](#).



## ASE ports

ASE uses default ports as defined in the table below. If any ports configured in `ase.conf` file is unavailable, ASE will not start.

Port Number	Usage
80	Data port for HTTP and WebSocket connections. Accessible from any client (not secure). If you are installing ASE as a non-root user, choose a port that is greater than or equal to 1024.
443	Data port for HTTPS and Secure WebSocket (wss) connections. Accessible from any client. If you are installing ASE as a non-root user, choose a port that is greater than or equal to 1024.
8010	Management port used by CLI and REST API for managing ASE. Accessible from management systems and administrators
8020	Cluster port used by ASE for cluster communication. Accessible from all cluster nodes.
8080	ABS ports used by ASE for outbound connections to ABS for sending access logs and receive client identifiers of suspected attacks.


**i Important:** The management ports 8010 and 8020 should not be exposed to the Internet. If you are setting up the deployment in an AWS environment with security groups, use private IPs for ASE to ABS connections to avoid security group issues.

## ASE deployment modes

API Security Enforcer supports REST and WebSocket APIs and can dynamically scale and secure system infrastructure. ASE can be deployed in Inline or Sideband mode.

### Inline mode

In the inline deployment mode, ASE sits at the edge of your network to receive the API traffic. It can also be deployed behind an existing load balancers such as AWS ELB. In inline mode, API Security Enforcer deployed at the edge of the datacenter, terminates SSL connections from API clients. It then forwards the requests directly to the correct APIs – and app servers such as Node.js, WebLogic, Tomcat, PHP, etc.



### API Security Enforcer Inline Deployment Mode


To configure ASE to work in the Inline mode, set the `mode=inline` in the `/opt/pingidentity/ase/config/ase.conf` file.

Some load balancers (for example, AWS ELB) require responses to keep alive messages from all devices receiving traffic. In an inline mode configuration, ASE should be configured to respond to these keep alive messages by updating the `enable_ase_health` variable in the `/opt/pingidentity/ase/config/ase.conf` file. When `enable_ase_health` is true, load balancers can perform an ASE health check using the following URL: `http(s)://<ASE Name>/ase` where `<ASE Name>` is the ASE domain name. ASE will respond to these health checks.

### Sideband mode

ASE when deployed in the sideband mode, works behind an existing API gateway. The API request and response data between the client and the backend resource or API server is sent to ASE. In this case, ASE does not directly terminate the client requests.

To configure ASE to work in the Inline mode, set the `mode=sideband` in the `/opt/pingidentity/ase/config/ase.conf` file.



Following is a description of the traffic flow through the API gateway and Ping Identity ASE.

1. Incoming request to API gateway
2. API gateway makes an API call to send the request detail in JSON format to ASE
3. ASE checks the request against a registered set of APIs and checks the origin IP against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the API gateway. Else, a different response code is sent to the Gateway. The request is also logged by ASE and sent to the AI Engine for processing.
4. If the API gateway receives a 200-OK response from ASE, then it forwards the request to the backend server, else the Gateway returns a different response code to the client.
5. The response from the backend server is received by the API gateway.
6. The API gateway makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to the API gateway.
8. API gateway sends the response received from the backend server to the client.

**Note:** Complete the ASE sideband mode deployment by referring to API gateway specific deployment section on the [PingIdentity documentation site](#).

### Install ASE

ASE supports RHEL 7.9 and Ubuntu 18.04 LTS. The provisioned infrastructure can be an EC2 instance, bare metal x86 server, and VMware ESXi.

Complete the following steps to install ASE. You can install ASE as a root user or as a non-root user. The example installation path assumes that you are root user. The installation works in a similar way for a non-root user.

1. Go to the [download site](#)
2. Click on **Select** under PingIntelligence
3. Choose the correct build and click **Download**.
4. After downloading the file, copy the ASE file to the `/opt` directory or any other directory where you want to install ASE.
5. Change working directory to `/opt` if you are installing the product as a root user. Choose any other location if you want to install ASE as a non-root user.
6. At the command prompt, type the following command to untar the ASE file:

```
tar -zxvf <filename>
```

For example:

```
tar -zxvf pi-api-ase-rhel-4.4.tar.gz
```


7. To verify that ASE successfully installed, type the `ls` command at the command prompt. This should list the `pingidentity` directory and the build's `.tar` file. For example:

```
/opt/pingidentity/ase/bin/$ ls
pingidentity pi-api-ase-rhel-4.4.tar.gz
```

## ASE license

To start ASE, you need a valid PingIntelligence license. There are two types of licenses:

- **Trial license** – The trial license is valid for 30-days. At the end of the trial period, ASE stops accepting traffic.
- **Subscription license** – The subscription license is based on the subscription period. It is a good practice to [configure your email](#) before configuring the license. ASE sends an email notification to the configured email ID in case the license has expired. Contact the Ping Identity sales team for more information.

 **Note:** In case the subscription license has expired, ASE continues to run until a restart.

## Configure ASE license

To configure the license in ASE, request for a license file from the Ping Identity sales team. The name of the license file must be `PingIntelligence.lic`. Copy the license file to the `/opt/pingidentity/ase/config` directory and start ASE.

## Update an existing license

If your existing license has expired, obtain a fresh license from Ping Identity sales team and replace the license file in the `/opt/pingidentity/ase/config` directory. Make sure to stop and start ASE after the license file is updated.

## Change default settings

It is recommended that you change the default key and password in ASE. Following is a list of commands to change the default values:

### Change `ase_master.key`

Run the following command to create your own ASE master key to obfuscate keys and password in ASE.

**Command:** generate\_obfkey. ASE must be stopped before creating a new ase\_master.key

```
/opt/pingidentity/ase/bin/cli.sh generate_obfkey -u admin -p admin
API Security Enforcer is running. Please stop ASE before generating new
obfuscation master key
```

**Stop ASE:** Stop ASE by running the following command:

```
/opt/pingidentity/ase/bin/stop.sh -u admin -p admin
checking API Security Enforcer status...sending stop request to ASE. please
wait...
API Security Enforcer stopped
```

**Change ase\_master.key:** Enter the generate\_obfkey command to change the default ASE master key:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin generate_obfkey
Please take a backup of config/ase_master.key, config/ase.conf,
config/abs.conf, config/cluster.conf before proceeding
Warning: Once you create a new obfuscation master key, you should
obfuscate all config keys also using cli.sh obfuscate_keys
Warning: Obfuscation master key file /opt/pingidentity/ase/config/
ase_master.key already exist.
This command will delete it create a new key in the same file
Do you want to proceed [y/n]:
```

**Start ASE:** After a new ASE master key is generated, start ASE by entering the following command:

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.0...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

### Change keystore password

You can change the keystore password by entering the following command. The default password is asekeystore. ASE must be running for updating the keystore password.

**Command:** update\_keystore\_password

```
/opt/pingidentity/ase/bin/cli.sh update_keystore_password -u admin -p admin
New password >
New password again >
keystore password updated
```

### Change admin password

You can change the default admin password by entering the following command:

```
/opt/pingidentity/ase/bin/cli.sh update_password -u admin -p
Old password >
New password >
New password again >
Password updated successfully
```

### Obfuscate keys and passwords


You must obfuscate the keys and passwords configured in ase.conf, cluster.conf, and abs.conf in the config directory. ASE ships with a default ase\_master.key which is used to obfuscate the various keys and passwords. It is recommended to generate your own ase\_master.key.

The following keys and passwords are obfuscated in the three configuration files:

- `ase.conf` – Email and Keystore (PKCS#12) password
- `cluster.conf` – ABS access and secret key
- `abs.conf` – Cluster authentication key, `gateway_credential`

**Note:** During the process of obfuscation of keys and password, ASE must be *stopped*.

The following diagram summarizes the obfuscation process:



### Generate your `ase_master.key`

You can generate the `ase_master.key` by running the `generate_obfkey` command in the ASE CLI:

```

/opt/pingidentity/ase/bin/cli.sh generate_obfkey -u admin -p
Please take a backup of config/ase_master.key, config/ase.conf,
config/abs.conf, config/cluster.conf before proceeding

Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh obfuscate_keys

Warning: Obfuscation master key file /opt/pingidentity/ase/config/
ase_master.key
already exist.

This command will delete it create a new key in the same file
Do you want to proceed [y/n]:y
creating new obfuscation master key
Success: created new obfuscation master key at
/opt/pingidentity/ase/config/ase_master.key
  
```

The new `ase_master.key` is used to obfuscate the keys and passwords in the various configuration files.

**Important:** In an ASE cluster, the new `ase_master.key` must be manually copied to each of the cluster nodes.

### Obfuscate key and passwords

Enter the keys and passwords in clear text in `ase.conf`, `cluster.conf`, and `abs.conf`. Run the **`obfuscate_keys`** command to obfuscate keys and passwords:

```

/opt/pingidentity/ase/bin/cli.sh obfuscate_keys -u admin -p
Please take a backup of config/ase_master.key, config/ase.conf, config/
abs.conf, and config/cluster.conf before proceeding
If config keys and password are already obfuscated using the current master
key, it is not obfuscated again
Following keys will be obfuscated:
config/ase.conf: sender_password, keystore_password
config/abs.conf: access_key, secret_key
config/cluster.conf: cluster_secret_key
Do you want to proceed [y/n]:y
  
```

```
obfuscating config/ase.conf, success
obfuscating config/abs.conf, success
obfuscating config/cluster.conf, success
```

Start ASE after keys and passwords are obfuscated.

**i Important:** After the keys and passwords are obfuscated, the `ase_master.key` must be moved to a secure location from ASE.

### Tune host system for high performance

ASE ships with a script to tune the host Linux operating system for handling high TCP concurrency and optimizing performance. To understand the tuning parameters, refer to the tuning script comments. When running the tuning script, changes are displayed on the console to provide insight into system modifications. To undo system changes, run the `untune` script

**i Important:** If you are installing ASE as a non-root user, run the `tune` script for your platform before starting ASE.

The following commands are for tuning RHEL. For tuning Ubuntu, use the Ubuntu tuning scripts.

#### Tune the host system:

Enter the following command in the command line:

```
/opt/pingidentity/ase/bin/tune_rhel7.sh
```

Make sure to close the current shell after running the tune script and proceeding to start ASE.

**i Note:** If ASE is deployed in a Docker Container, run the tune script on the host system, not in the container.

#### Untune the host system:

The “untune” script brings the system back to its original state. Enter the following command in the command line:

```
/opt/pingidentity/ase/bin/untune_rhel7.sh
```

**i Note:** You should be a `root` user to run the tune and untune scripts.

### Start and Stop ASE

For ASE to start, the `ase_master.key` must be present in the `/opt/pingidentity/ase/config` directory. If you have moved the master key to a secured location for security reasons, copy it to the `config` directory before executing the `start` script.

Before starting ASE, make sure that `nofile` limit in `/etc/security/limits.conf` is set to at least 65535 or higher on the host machine. Run the following command on the ASE host machine to check the `nofile` limit:

```
ulimit -n
```

You can start ASE in one of the following two ways:

- Using service script available in the `util` directory, or
- Using the `start.sh` script available in the `bin` directory.

## Start ASE as a service

Complete the following steps to start ASE as a service:

1. Navigate to the `util` directory and run the following command to install ASE as a service:

```
#sudo ./install-systemctl-service.sh pi-ase
```

2. Start the service by entering the following command:

```
systemctl start pi-ase.service
```

## Start ASE using start.sh script

Change working directory to `bin` and run the `start.sh` script.

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 5.0...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

## Stop ASE using stop.sh

Change working directory to `bin` and run the `stop.sh` script.

```
/opt/pingidentity/ase/bin/stop.sh -u admin -p admin
checking API Security Enforcer status...
sending stop request to ASE. please wait...
API Security Enforcer stopped
```

## Stop ASE using service script

Run the following command to stop the ASE service:

```
systemctl stop pi-ase.service
```

## Configure SSL for client side connection or external APIs

ASE supports both TLS 1.2 and SSLv3 for external APIs. OpenSSL is bundled with ASE. The following are the version details:


- RHEL : OpenSSL 1.0.2k-fips 26 Jan 2017
- Ubuntu : OpenSSL 1.0.2g 1 Mar 2016

You can configure SSL in ASE for client side connection using one of the following methods:

- **Method 1:** Using CA-signed certificate
- **Method 2:** Using self-signed certificate
- **Method 3:** Importing an existing certificate

The steps provided in this section are for certificate and key generated for connections between the client and ASE as depicted in the illustration below:





In a cluster setup:

1. Stop all the ASE cluster nodes
2. Configure the certificate on the management node. For more information on management node, see [API Security Enforcer Admin Guide](#).
3. Start the cluster nodes one by one for the certificates to synchronize across the nodes

### Enable SSLv3

By default, SSLv3 is disabled due to security vulnerabilities. To change the default and enable SSLv3, stop ASE and then change `enable_sslv3` to `true` in `ase.conf` file. Restart ASE to activate SSLv3 protocol support. SSLV3 is only supported for client to ASE connections, not ASE to backend server connections.

```
; SSLv3
enable_sslv3=true
```

### Method 1: Using CA-signed certificate

To use Certificate Authority (CA) signed SSL certificates, follow the process to create a private key, generate a Certificate Signing Request (CSR), and request a certificate as shown below:



**Note:** ASE internally validates the authenticity of the imported certificate.

To use a CA-signed certificate:

1. Create a private key. ASE CLI is used to create a 2048-bit private key and to store it in the keystore.

```
/opt/pingidentity/ase/bin/cli.sh create_key_pair -u admin -p
Warning: create_key_pair will delete any existing key_pair, CSR and self-
signed certificate
Do you want to proceed [y/n]:y
OK, creating new key pair. Creating DH parameter may take around 20
minutes. Please wait
Key created in keystore
dh param file created at /opt/pingidentity/ase/config/certs/dataplane/
dh1024.pem
```

## 2. Create a CSR. ASE takes you through a CLI-based interactive session to create a CSR.

```
/opt/pingidentity/ase/bin/cli.sh create_csr -u admin -p
Warning: create_csr will delete any existing CSR and self-signed
certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >US
State > Colorado
Location >Denver
Organization >Pingidentity
Organization Unit >Pingintelligence
Common Name >ase
Generating CSR. Please wait...
OK, csr created at /opt/pingidentity/ase/config/certs/dataplane/ase.csr
```

3. Upload the CSR created in step 2 to the CA signing authority's website to get a CA signed certificate.
4. Download the CA-signed certificate from the CA signing authority's website.
5. Use the CLI to import the signed CA certificate into ASE. The certificate is imported into the keystore.

```
/opt/pingidentity/ase/bin/cli.sh import_cert <CA signed certificate path>
-u admin -p
Warning: import_cert will overwrite any existing signed certificate
Do you want to proceed [y/n]:y
Exporting certificate to API Security Enforcer...
OK, signed certificate added to keystore
```

## 6. Restart ASE by first stopping and then starting ASE.

### Method 2: Use self-signed certificate

A self-signed certificate is also supported for customer testing.

#### To create a self-signed certificate

1. Create a private key. ASE CLI is used to generate a 2048-bit private key which is in the `/opt/pingidentity/ase/config/certs/dataplane/dh1024.pem` directory.

```
/opt/pingidentity/ase/bin/cli.sh create_key_pair -u admin -p
```

```
Warning: create_key_pair will delete any existing key_pair, CSR and self-
signed certificate
Do you want to proceed [y/n]:y
OK, creating new key pair. Creating DH parameter may take around 20
minutes. Please wait
Key created in keystore
dh param file created at /opt/pingidentity/ase/config/certs/dataplane/
dh1024.pem
```

2. Create a self-signed certificate. Use the CLI to produce a self-signed certificate located in `/pingidentity/ase/config/certs/dataplane/ase.csr`

```
/opt/pingidentity/ase/bin/cli.sh create_self_sign_cert -u admin -p
Warning: create_self_sign_cert will delete any existing self-signed
certificate
Do you want to proceed [y/n]:y
Creating new self-signed certificate
OK, self-sign certificate created in keystore
```

3. Restart ASE by stopping and starting.

### Method 3: import an existing certificate and key-pair

To install an existing certificate, complete the following steps and import it into ASE. If you have intermediate certificate from CA, then append the content to your server `.crt` file.

1. Create the key from the existing `.pem` file:

```
openssl rsa -in private.pem -out private.key
```

2. Convert the existing `.pem` file to a `.crt` file:

```
openssl x509 -in server-cert.pem -out server-cert.crt
```

3. Import key pair from step 2:

```
/opt/pingidentity/ase/bin/cli.sh import_key_pair private.key -u admin -p
Warning: import_key_pair will overwrite any existing certificates
Do you want to proceed [y/n]:y
Exporting key to API Security Enforcer...
OK, key pair added to keystore
```

4. Import the `.crt` file in ASE using the `import_cert` CLI command:

```
/opt/pingidentity/ase/bin/cli.sh import_cert server-cert.crt -u admin -p
Warning: import_cert will overwrite any existing signed certificate
Do you want to proceed [y/n]:y
Exporting certificate to API Security Enforcer...
OK, signed certificate added to keystore
```

5. Restart ASE by stopping and starting.

**i Important:** You can also configure for Management APIs. For more information on configuring SSL for management APIs, see [Configure SSL for Management APIs](#).

### Setup ASE cluster (optional)

For production environments, Ping Identity recommends setting up a cluster of ASE nodes for improved performance and availability.

**i Note:** Enable NTP on each ASE node system. All cluster nodes must be in the same time zone.

To setup an ASE cluster node:

1. Navigate to the `config` directory
2. Edit `ase.conf` file:
  - a. Set `enable_cluster=true` for all cluster nodes.
  - b. Confirm that the parameter mode is the same on each ASE cluster node, either inline or sideband. If parameter mode values do not match, the nodes will not form a cluster.

### 3. Edit the `cluster.conf` file:

- a. Configure `cluster_id` with an identical value for all nodes in a single cluster (for example, `cluster_id=shopping`)
- b. Enter port number in the `cluster_manager_port` parameter. ASE node uses this port number to communicate with other nodes in the cluster.
- c. Enter an IPv4 address or hostname with the port number for `peer_node` which is the first (or any existing) node in the cluster. Keep `peer_node` empty for the first cluster node.
- d. Provide the `cluster_secret_key` which must be the same in each cluster node. It must be entered on each cluster node before the nodes to connect to each other.

Here is a sample `cluster.conf` file:

```
; API Security Enforcer's cluster configuration.
; This file is in the standard .ini format. The comments start with a
; semicolon (;).
; Section is enclosed in []
; Following configurations are applicable only if cluster is enabled
; with true in ase.conf
; unique cluster id.
; valid character class is [ A-Z a-z 0-9 _ - . / ]
; nodes in same cluster should share same cluster id
cluster_id=ase_cluster

; cluster management port.
cluster_manager_port=8020

; cluster peer nodes.
; a comma-separated list of hostname:cluster_manager_port or
; IPv4_address:cluster_manager_port
; this node will try to connect all the nodes in this list
; they should share same cluster id
peer_node=

; cluster secret key.
; maximum length of secret key is 128 characters (deobfuscated length).
; every node should have same secret key to join same cluster.
; this field can not be empty.
; change default key for production.
cluster_secret_key=OBF:AES:nPJOh3wXQWK/BOHrtKu3G2SGiAEElOSvOFYEiWfIVSdu
```

### 4. After configuring an ASE node, start the node by running the following command:

```
/opt/pingidentity/ase/bin/start.sh
```

### Scale up the ASE cluster

Scale up the ASE cluster by adding nodes to an active cluster without disrupting traffic. To add a new cluster node, enter the `peer_node` IP address or hostname in the `cluster.conf` file of the ASE node and then [start the ASE node](#). The new node will synchronize configuration and cookie data from the peer nodes. After loading, it will become part of the cluster. For example, if the IP of the first node is 192.168.20.121 with port 8020, then the `peer_node` parameter would be 192.168.20.121:8020.

```
; ASE cluster configuration. These configurations apply only when
; you have enabled cluster in the api_config file.
; Unique cluster ID for each cluster. All the nodes in the same cluster
; should have the same cluster ID.
cluster_id=ase_cluster
; Cluster management port.
cluster_manager_port=8020
; Cluster's active nodes. This can be a comma separated list of nodes in
; ipv4_address:cluster_manager_port format.
```

```
peer_node=192.168.20.121:8020
```

### Scale down the ASE cluster

A node can be removed from an active cluster without disrupting traffic by performing the following:

1. Stop the ASE node to be removed.
2. Set the `enable_cluster` option as `false` in its `ase.conf` file.

**Note:** The removed node retains the cookie and certificate data from when it was part of the cluster.

### Delete a cluster node

An inactive cluster node has either become unreachable or has been stopped. When you delete a stopped cluster node, the operation does not remove cookie and other synchronized data. To find which cluster nodes are inactive, use the `cluster_info` command:

```
/opt/pingidentity/ase/bin/cli.sh cluster_info -u admin -p
cluster id : ase_cluster
cluster nodes
127.0.0.1:8020 active
1.1.1.1:8020 active
2.2.2.2:8020 inactive
172.17.0.4:8020 (tasks.aseservice) active
172.17.0.5:8020 (tasks.aseservice) inactive
tasks.aseservice2:8020 not resolved
```

Using the `cluster_info` command output, you can remove the inactive cluster nodes `2.2.2.2:8020` and `172.17.0.5:8020`.

To delete the inactive node, use the `delete_cluster_node` command:

```
/opt/pingidentity/ase/bin/cli.sh delete_cluster_node <IP:Port>
```

### Stop ASE cluster

Stop the entire cluster by running the following command on any node in the cluster.

```
/opt/pingidentity/ase/bin/stop.sh cluster -u admin -p
```

When the cluster stops, each cluster node retains all the cookie and certificate data.

## Part C – Integrate ASE and ABS

The ABS Engine installation process is summarized below:

- Connect ASE to ABS AI engine for ASE to send access log files to ABS.
- Enable ASE to ABS engine communication: Just connecting ASE and ABS engine does not mean that access logs would be sent by ASE to ABS. ASE to ABS communication has to be enabled separately.
- Add API JSON files to ASE. The API JSON files define your API and its various parameters. For more information, see [Defining an API JSON](#) file.
- ABS AI engine models need to be trained for it to analyze and report on your API traffic.

## Connect ASE to ABS AI engine

### Check ABS port availability

The default ports for connection with ABS are 8080 and 9090. Run the `check_ports.sh` script on the ASE machine to determine accessibility of ABS. Input ABS host IP address and ports as arguments.

```
/opt/pingidentity/ase/util ./check_ports.sh {ABS IPv4:[port]}
```

### Configure ASE

Update `abs.conf` located in the ASE `/opt/pingidentity/ase/config` directory with ABS Engine address and authentication keys:

- Configure `abs_endpoint` with the ABS Engine management IP address / host name and port number (Default: 8080) which was configured in the `/opt/pingidentity/abs/config/abs.properties` file.

**Note:** Note: If ABS is in a different AWS security group, use a private IP address

- Configure ABS `access_key` and `secret_key` using the key values from the `abs_init.js` file located in `/opt/pingidentity/abs/mongo`.

Here is a sample `abs.conf` file:

```
; API Security Enforcer ABS configuration.
; This file is in the standard .ini format. The comments start with a
; semicolon (;).
; Following configurations are applicable only if ABS is enabled with true.

; a comma-separated list of abs nodes having hostname:port or ipv4:port as
; an address.
abs_endpoint=127.0.0.1:8080

; access key for abs node
access_key=OBF:AES://EN0zsqOEhDBWLDY
+pIoQ:~N6wflLiHTTd3oVNzvtXuAaOG34c4JBD4XZHgFCaHry0

; secret key for abs node
secret_key=OBF:AES:Y2DadCU4JFZp3bx8EhnOiw:zzi77GIFF5xkQJccjIrIVWU
+RY5CxUhp3NLcNBel+3Q

; Setting this value to true will enable encrypted communication with ABS.
enable_ssl=true

; Configure the location of ABS's trusted CA certificates. If empty, ABS's
; certificate
; will not be verified
abs_ca_cert_path=
```

**Important:** Make sure that ASE and ABS are in the same time zone.

### Enable ASE to ABS engine communication

To start communication between ASE and the AI engine, run the following command:

```
./cli.sh enable_abs -u admin -p admin
```

To confirm an ASE Node is communicating with ABS, issue the ASE status command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status           : started
mode             : inline
http/ws          : port 8080
https/wss        : port 8443
firewall         : enabled
abs              : enabled, ssl: enabled (If ABS is enabled, then ASE is
communicating with ABS)
abs attack       : disabled
audit            : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

### Add APIs to ASE

After the policy has been deployed to Apigee using the PingIntelligence automated policy tool, add APIs to ASE. Read the following topics to define and add APIs to ASE:

- [API naming guidelines](#)
- [Define and add an API JSON](#)

For more information on ASE sideband deployment, see [Sideband API Security Enforcer](#).

### Train ABS AI engine

For ABS to start predicting various attacks types, the model needs to be trained. The number of hours (default - 24 hours) is configurable for model training. Set the value of `training_period` parameter using [PingIntelligence Dashboard](#) or the [Global configuration update REST API](#) on page 355. For more detailed information about training AI model, see [AI Engine training](#) on page 338.

#### Start the training

The training starts as soon as ABS receives the first API traffic from API Security Enforcer and continues for the number of hours set in the `attack_initial_training` parameter. Training occurs automatically when a new API is added.

#### Verify training completion

ABS training status is checked using the ABS Admin API which returns the training duration and prediction mode. If the prediction variable is true, ABS has completed training and is discovering attacks. A false value means that ABS is still in training mode. The API URL for Admin API is: `https://<ip>:<port>/v4/abs/admin`. Following is a snippet of the output of the Admin API:

```
"message": "training started at Thu Dec 26 12:32:59 IST 2019",
"training_duration": "2 hours",
"prediction": true
```

IP and port number is of the ABS machine.

**Note:** ABS only detects attacks after the training period is over. During training, no attacks are generated.

## Part D – Install PingIntelligence Dashboard

Installing PingIntelligence for APIs Dashboard automatically installs Elasticsearch, Kibana. To install PingIntelligence Dashboard, ensure that the following prerequisites are met:

- **Server:** 8 core CPU, 16 GB, 1 TB HDD
- **Operating system:** RHEL 7.9 or Ubuntu 18.04 LTS
- **OpenJDK:** 11.0.2
- **SSL certificate:** One private key and certificate. By default, PingIntelligence Dashboard uses the private key and certificate shipped with the binary.
- **Password:** If you want to change the default password, set a minimum 8 character password
- **ABS:** ABS URL, access, and secret key. Make sure that ABS is reachable from the PingIntelligence Dashboard machine.
- **ASE:** ASE management URL, access, and secret key. Make sure that ASE is reachable from the PingIntelligence Dashboard machine.

### Port numbers

The following is a list of default port numbers. Make sure that these are available for installing PingIntelligence Dashboard.

- **PingIntelligence Dashboard:** 8030
- **Elasticsearch:** 9200
- **Kibana:** 5601
- **H2 database:** 9092. H2 database is installed and runs as a part of PingIntelligence Dashboard.

**Supported browsers:** The following Web browsers are supported:

- Google Chrome: Version 49 or later
- Mozilla Firefox: Version 69 or later
- Microsoft Edge: Version 42 or later
- Apple Safari: Version 11.1 or later

**Operating system configurations:** Complete the following configuration for the operating system:

- Increase the `ulimit` to 65536

```
# sudo sysctl -w fs.file-max=65536
# sudo sysctl -p
```

- Increase the `vm.max_map_count` limit to 262144

```
# sudo echo "vm.max_map_count=262144" >> /etc/sysctl.conf
# sudo sysctl -p
```

- **JDK installation:** Set `JAVA_HOME` to `<jdk_install>` directory and add `<jdk_install>/bin` to system `PATH` variable
- Choose the `<pi_install_dir>` directory. `<pi_install_dir>` should be readable and writable by the logged in user.

### PingIntelligence Dashboard users

There are two pre-configured login users in PingIntelligence Dashboard. The two users are:

- `admin`
- `ping_user`

Multiple `admin` and `ping_user` can simultaneously log into PingIntelligence Dashboard. The `admin` user has full access to PingIntelligence Dashboard. An `admin` can view the dashboard of various APIs as well as tune threshold and unblock a client identifier. `ping_user` can only view the API dashboard. A total of 25 `admin` and `ping_user` can log in simultaneously.

### Install PingIntelligence Dashboard

Complete the following steps to install PingIntelligence Dashboard:



1. Create a `<ping_install_dir>` directory on your host machine. Make sure that the user has read and write permissions for the `<ping_install_dir>` directory.
2. [Download](#) the PingIntelligence Dashboard binary
3. [Download](#) Elasticsearch 6.8.1 (macOS/RHEL)
4. [Download](#) Kibana 6.8.1 (RHEL 64-bit)
5. Change directory to `ping_install_dir`:

```
# cd pi_install_dir
```

6. Untar the PingIntelligence Dashboard:

```
# tar -zxf pi-api-dashboard-4.4.tar.gz
```

7. Change directory to `pingidentity/webgui/`

```
# cd pingidentity/webgui/
```

8. Install PingIntelligence Dashboard by entering the following command and follow the instructions displayed on the prompt:

```
# ./bin/pi-install-ui.sh
```

```
elasticsearch-6.8.1.tar.gz file path >
kibana-6.8.1-linux-x86_64.tar.gz file path >

Use bundled ssl key and self signed certificate for ui server [y/n]? >[n]
ssl private key path >
ssl certificate path >

Use default password [changeme] for all components and users [y/n]? > [n]
UI login admin user 'admin' password >
Renter UI login admin user 'admin' password >
UI login regular user 'ping_user' password >
Renter UI login regular user 'ping_user' password >

ABS url >
Use default access/secret key for ABS [y/n] ? > [n]
ABS access key >
ABS secret key >

ASE management url >
Use default access/secret key for ASE [y/n] ? > [n]
ASE access key >
ASE secret key >

configuring elasticsearch... please wait for 15 seconds
elasticsearch config is completed.

configuring kibana...please wait 60 seconds
kibana config is completed.

configuring dashboard...
generating new obfuscation master key
dashboard config is completed.

configuring webgui...
generating new obfuscation master key
webgui config is completed.
```

```

saving auto generated credentials for all components to
webgui_internal.creds file

WebGUI installation completed.

Start WebGUI [y/n] > [y]

start elasticsearch...
  elasticsearch started. Log is available at elasticsearch/logs/
  elasticsearch.log

start dashboard.....
  dashboard started. Log available at dashboard/logs/dashboard.log

start kibana.....
  kibana started. Log available at kibana/logs/kibana.log

start ui server.....
  UI server started. Log available at webgui/logs/admin/admin.log

WebGUI started. Log available at webgui/logs/admin/admin.log

Please access WebGUI at https://<pi_install_host>:8030

<pi_install_host> can be ip address, hostname or fully qualified domain
name of this server.
<pi_install_host> should be reachable from your computer.

Important Action:
1) Credentials for all internal components are available in
  webgui_internal.creds file. Move this file from
  this server and securely keep it elsewhere. For any debugging purposes
  you will be asked to get
  credentials for a component from this file.
2) Two obfuscation master keys are auto-generated
  pingidentity/webgui/config/webgui_master.key
  pingidentity/dashboard/config/dashboard_master.key
3) For security purposes you should move obfuscation master keys from this
  server. But when components
  are restarted, master keys should be present at the original locations.

```

 **Note:** The ASE management url is an optional parameter.

### Verify the installation

You can verify the installation by checking the process IDs (PID) of each component. You can check the pid of components at the following location:

- **Elasticsearch:** <pi\_install\_dir>/elasticsearch/logs/elasticsearch.pid
- **Kibana:** <pi\_install\_dir>/kibana/logs/kibana.pid
- **Dashboard:** <pi\_install\_dir>/dashboard/logs/dashboard.pid
- **Webgui:** <pi\_install\_dir>/webgui/logs/webgui.pid

### Tune Dashboard performance parameters

Configure the following three parameters for Dashboard's better performance. Note that the following tuning parameters if you have your setup of Elasticsearch and Kibana.

If you have used PingIntelligence automated deployment or pi-install-ui.sh script to deploy Dashboard, these tuning are done as part of installation.

Parameter	Description	Location
<b>Elasticsearch</b>		
-Xms and -Xmx	<ul style="list-style-type: none"> <li><b>Xms</b> - Defines the minimum heap size of Elasticsearch. Set it to 4GB as <code>Xms4g</code>.</li> <li><b>Xmx</b> - Defines the maximum heap size of Elasticsearch. Set it to 4GB as <code>Xmx4g</code>.</li> </ul>	<code>\$ES_HOME/config/jvm.options</code>
<code>thread_pool.search.size</code>	Defines thread pool size for count/search/suggest operations in Elasticsearch. Configure it to 50% of total CPUs allocated.	<code>\$ES_HOME/config/elasticsearch.yml</code>
<b>Kibana</b>		
<code>elasticsearch.requestTimeout</code>	Time (in milliseconds) to wait for Elasticsearch to complete the request and return the response back to Kibana. Set the value to 60000 milliseconds.	<code>\$KIBANA_HOME/config/kibana.yml</code>

### Mitigating Cross-Site-Scripting (XSS)

To detect and mitigate attacks like Cross Site Scripting(XSS), PingIntelligence Dashboard implements Content Security Policy (CSP). The following are the configuration details.

Response header - Content-Security-Policy

Response header value - `default-src 'self'; font-src 'self' use.typekit.net; script-src 'self' use.typekit.net; style-src 'self' 'unsafe-inline' use.typekit.net p.typekit.net; img-src 'self' data: p.typekit.net;`

### Start and stop Dashboard

You can choose to start and stop all the components together or individually.

It is recommended to start and stop components together using the following command:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/start-all.sh

Starting elasticsearch.. [started]

Verifying elasticsearch connectivity.. [OK]
Verifying ABS connectivity.. [OK]

Starting dashboard.. [started]
Starting kibana.. [started]

Verifying Kibana connectivity.. [OK]
Verifying ASE connectivity.. [OK]

Starting webgui.. [started]

WebGUI started.
```

To stop all the components of PingIntelligence Dashboard together, enter the following command:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/stop-all.sh

Stopping webgui.. [stopped]
Stopping dashboard.. [stopped]
Stopping kibana.. [stopped]
Stopping elasticsearch.. [stopped]

WebGUI stopped.
```

Start and stop PingIntelligence Dashboard components individually

Start the components in the following order:

**1. Start Elasticsearch:** Enter the following command to start Elasticsearch:

```
# cd <pi_install_dir>/pingidentity/elasticsearch
# ./bin/elasticsearch -d -p logs/elasticsearch.pid
```

If Elasticsearch is running as a service, use the following command:

```
# sudo systemctl start pi-elasticsearch.service
```

**2. Start Dashboard:** Enter the following command to start Dashboard:

```
# cd <pi_install_dir>/pingidentity/dashboard
# ./bin/start.sh
```

If Dashboard is running as a service, use the following command:

```
# sudo systemctl start pi-dashboard.service
```

**3. Start Kibana:** Enter the following command to start Kibana:

```
# cd <pi_install_dir>/pingidentity/kibana
# ./bin/kibana >> ./logs/kibana.log 2>&1 & echo $! > logs/kibana.pi
```

If Kibana is running as a service, use the following command:

```
# sudo systemctl start pi-kibana.service
```

**4. Start Web GUI:** Enter the following command to start Web GUI:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/start.sh
```

If Web GUI is running as a service, use the following command:

```
# sudo systemctl start pi-webgui.service
```

Stop the components in the following order:

**1. Stop Web GUI:** Enter the following command to stop Web GUI:

```
# cd <pi_install_dir>/pingidentity/webgui
```

```
# ./bin/stop.sh
```

If Web GUI is running as a service, use the following command:

```
# sudo systemctl stop pi-webgui.service
```

## 2. Stop Dashboard : Stop the dashboard engine by entering the following command:

```
# cd <pi_install_dir>/pingidentity/dashboard
# ./bin/stop.sh
```

If Dashboard is running as a service, use the following command:

```
# sudo systemctl stop pi-dashboard.service
```

## 3. Stop Kibana: Stop Kibana by entering the following command:

```
# cd <pi_install_dir>/pingidentity/kibana
# kill -9 "$(cat /logs/kibana.pid)"
```

If Kibana is running as a service, use the following command:

```
# sudo systemctl stop pi-kibana.service
```

## 4. Stop Elasticsearch: Stop Elasticsearch by entering the following command:

```
# cd <pi_install_dir>/pingidentity/elasticsearch
# kill -15 "$(cat /logs/elasticsearch.pid)"
```

If Elasticsearch is running as a service, use the following command:

```
# sudo systemctl stop pi-elasticsearch.service
```

## Part E – Access ABS reporting


The ABS AI Engine generates attack, metric, and forensics reports which are accessed using the ABS REST API to access JSON formatted reports. Ping Identity provides Postman collections to generate various API reports. You can use any other tool to access the reports using the URLs documented in the ABS Admin Guide.

### Install Postman with PingIntelligence for APIs Reports


Ping Identity provides configuration files which are used by [Postman](#) to access the ABS REST API JSON information reports. Make sure to install Postman 6.2.5 or higher.

### Using ABS self-signed certificate with Postman


ABS ships with a self-signed certificate. If you want to use Postman with the self-signed certificate of ABS, then from Postman's settings, disable the certificate verification option. Complete the following steps to disable Postman from certificate verification:

1. Click on the **spanner**  on the top-right corner of Postman client. A drop-down window is displayed.

2. Select **Settings** from the drop-down window:



3. In the Settings window, switch-off certificate verification by clicking on the SSL certificate verification button:





### View ABS Reports in Postman


To view the reports, complete the following steps:

1. Download the ABS Environment and ABS Reports JSON files from **API Reports Using Postman** folder on Ping Identity [download](#) site. These configuration files will be used by Postman.
2. [Download](#) and install the Postman application 6.2.5 or higher.

3. In Postman, **import** the two Ping Identity files downloaded in step 1 by clicking the Import button.



4. After importing the files, click the gear  button in the upper right corner.
5. In the **MANAGE ENVIRONMENTS** pop-up window, click **ABS\_4.3\_Environment**
6. In the pop-up window, configure the following values and then click **Update**
  - **Server:** IP address of the ABS node for which the `dashboard_node` was set to `true` in the `abs.properties` file.
  - **Port:** Port number of the ABS node.
  - **Access\_Key\_Header** and **Secret\_Key\_Header:** Use the Admin user or Restricted user header. A Restricted user sees obfuscated value of OAuth token, cookie and API keys. For more information of different types of user, see [ABS users for API reports](#)
  - **Access\_Key** and **Secret\_Key:** The Access Key and Secret Key configured in the `opt/pingidentity/mongo/abs_init.js` for either admin or restricted user. Make sure that access key and secret key corresponds to the admin or restricted user header configured.
  - **API\_Name:** The name of the API for which you want to generate the reports.
  - **Later\_Date:** A date which is more recent in time. For example, if the query range is between March 12 and March 14, then the later date would be March 14.
  - **Earlier\_Date:** A date which is past in time. For example, if the query range is between March 12 and March 14, then the earlier date would be March 12.

 **Note:** Do not edit any fields that start with the word `System`.

7. In the main Postman window, select the report to display on the left column and then click **Send**. ABS external REST APIs section provides detailed information on each API call and the JSON report response.

## Part F - Integrate API gateways for sideband deployment

If you have deployed ASE in the [sideband](#) mode, the next step is to integrate your API gateway with PingIntelligence products. To deploy ASE in the sideband mode, set `mode=sideband` in the `/opt/pingidentity/ase/config/ase.conf` file. This is the only configuration required on ASE for sideband deployment. For more information on ASE in sideband, see [Sideband API Security Enforcer](#)

After you have completed the parts A to E of deployment, integrate one of the following API gateways with PingIntelligence components and start sending the API traffic to your API gateway:

- [Akana API gateway sideband integration](#) on page 558
- [PingIntelligence Apigee integration](#) on page 581
- [PingIntelligence AWS API Gateway Integration](#) on page 601
- [Azure APIM sideband integration](#) on page 640
- [Axway sideband integration](#) on page 616
- [PingIntelligence - CA API gateway sideband integration](#) on page 649
- [F5 BIG-IP PingIntelligence integration](#) on page 658
- [IBM DataPower Gateway sideband integration](#) on page 670

- [PingIntelligence - Kong API gateway integration](#) on page 677
- [Mulesoft sideband integration](#) on page 684
- [NGINX sideband integration](#) on page 698
- [NGINX Plus sideband integration](#) on page 714
- [PingAccess sideband integration](#) on page 747
- [PingIntelligence WSO2 integration](#) on page 764

## API Security Enforcer

The API Security Enforcer (ASE) supports multiple deployments modes to provide customers flexibility in deploying .


This ASE admin guide covers the following deployment modes:

### Inline ASE

ASE receives API client traffic and then routes the traffic to a backend API gateway or directly to App Servers. ASE applies real time security and passes API metadata to the ABS Engine for AI powered advanced attack detection. ABS engine notifies ASE of attacks, and ASE then blocks the rogue clients.

### Sideband ASE

An API gateway receives API client traffic and then makes API calls to pass API metadata to ASE for processing. ASE passes the API metadata to the ABS Engine for AI powered advanced attack detection. ABS engine notifies ASE of attacks, and ASE then works with API gateway to block inbound rogue client requests. See ASE sideband chapter for more information.



The following tables show a summary of security and admin features available in each deployment option.

Security Features	Inline	Sideband
Interface to ABS AI Engine for AI powered attack detection.	Yes	Yes



Security Features	Inline	Sideband
API deception where decoy APIs look like legitimate APIs to hackers. After accessing a decoy API, a hacker is quarantined, plus activity information is collected.	Yes	Yes
Real-time client blocking based on lists with ASE detected attacks, ABS AI Engine detected attacks, or customer-built lists. Blocking can be based on OAuth tokens, API keys, user names, cookies, and IP addresses.	Yes	Yes
Black and whitelist management of tokens, API keys, cookies, IP addresses.	Yes	Yes
Real-time blocking of API clients with traffic that deviates from API attributes.	Yes	No
Dynamic mapping of public API identity to private internal API identity.	Yes	No
Custom API error messages prevent disclosure of sensitive error information.	Yes	No
Admin Features	Inline	Sideband
Simple deployment with modular JSON configuration files.	Yes	Yes
Live updates to add or remove without loss of traffic or stopping services.	Yes	Yes
Obfuscation of keys and passwords.	Yes	Yes
Active-active clustering that supports scaling and resiliency: all nodes are peers and self-learn the configuration, traffic information, and security updates.	Yes	Yes
Syslog information messages sent to Syslog servers in RFC 5424 format.	Yes	Yes
Automatic API discovery discovers API JSON configuration data.	Yes	Yes

Admin Features	Inline	Sideband
CLI and REST API for management and automation tool integration.	Yes	Yes
Linux PAM-based administrator authentication with existing Linux tools.	Yes	Yes
Audit log captures administrative actions for compliance reporting.	Yes	Yes
Distributed inbound flow control limits client traffic and server traffic.	Yes	No
Multiprotocol Layer 7 routing and load balancing of WebSocket, REST API.	Yes	No
Secure connection between ASE and ABS. Secure connection also between ASE and ASE REST APIs.	Yes	Yes

## Administration


API Security Enforcer (ASE) is deployed by modifying configuration files to support your environment. The configuration files consist of the following:

- `ase.conf` – the master configuration file with parameters to govern ASE functionality.
- `cluster.conf` – configures ASE cluster setup.
- `abs.conf` – configures ASE to ABS (AI Engine) connectivity. ASE sends log files to ABS for processing and receives back client identifiers (for example, token, IP address, cookie) to block.

## ASE license

To start ASE, you need a valid license. There are two types of ASE licenses:

- **Trial license** – The trial license is valid for 30 days. At the end of the trial period, ASE stops accepting traffic and shuts down.
- **Subscription license** – The subscription license is based on the subscription period. It is a good practice to [configure your email](#) before configuring the ASE license. ASE sends an email notification to the configured email ID in case the license has expired. Contact the PingIntelligence for APIs sales team for more information.

 **Note:** In case the subscription license has expired, ASE continues to run until a restart.

### Configure ASE license

To configure the license in ASE, request for a license file for the PingIntelligence from APIs sales team. The name of the license file must be `PingIntelligence.lic`. Copy the license file to the `/opt/pingidentity/ase/config` directory and start ASE.


Update an existing license

If your existing license has expired, obtain a fresh license from PingIdentity for APIs sales team and replace the license file in the `/opt/pingidentity/ase/config` directory. Make sure to stop and start ASE after the license file is updated.

## ASE interfaces

The interfaces to configure and operate ASE consist of:

- Command line interface (CLI)
- ASE REST API



### ASE CLI

Located in the `bin` directory, `cli.sh` is the script that administers ASE and performs all ASE functions except starting and stopping ASE. To execute commands, type `cli.sh` followed by the command name. To see a list of all commands, type the following command at the CLI:

```
/opt/pingidentity/ase/bin/cli.sh
```

The following table lists some basic CLI commands. For a complete list, see [CLI for inline ASE](#) on page 263 and [CLI for sideband ASE](#) on page 203

Option	Description
<code>help</code>	Displays <code>cli.sh</code> help
<code>version</code>	Displays ASE's version number
<code>status</code>	Displays ASE's status.
<code>update_password</code>	Updates the password for ASE admin account.

**Note:** After initial start-up, all configuration changes must be made using `cli.sh` or ASE REST APIs. This includes adding a server, deleting a server, adding a new API, and so on. After manually editing an operational JSON file, follow [Updating a Configured API](#)

CLI commands include the following:

#### help command

To get a list of CLI commands, enter the help command:

```
/opt/pingidentity/ase/bin/cli.sh help
```

## version command

```
To query system information, enter the version command:
/opt/pingidentity/ase/bin/cli.sh version
Ping Identity Inc., ASE 3.1.1
Kernel Version : 3.10
Operating System : Red Hat Enterprise Linux Server release 7.0 (Maipo)
Build Date : Fri Aug 24 13:43:22 UTC 2018
```

## status command

To get ASE status, enter the status command:

```
/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status : started
http/ws : port 80
https/wss : port 443
firewall : enabled
abs : disabled, ssl: enabled
abs attack : disabled
audit : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

## ASE REST API

The ASE REST API is used to administer ASE or integrate ASE with third-party products. Using the ASE REST API, you can configure ASE and display ASE statistics, including the number of backend servers, the number of APIs, and so on.

ASE REST API commands consist of the following:

- **API:** Create API (POST), Read API (GET), List API (GET), Update API (PUT), Delete API (DELETE)
- **Server:** Create Server (POST), Read Server (GET), Delete Server (DELETE)
- **Session:** Read Persistent Connections (GET)
- **Cluster:** Read Cluster (GET)
- **Firewall:** Read Firewall Status (GET), Update Firewall Status (POST)
- **Flow Control:** Read flow control (GET), Update flow control for API (POST), Update flow control of a Server for an API (POST)

## Customizing ASE ports

ASE uses default ports as defined in the table below. If any port configured in `ase.conf` file is unavailable, ASE will not start.

Port Number	Usage
80	Data port. HTTP and WebSocket (ws) connections. If you are installing ASE as a non-root user, then use port greater than 1024.
443	Data port. HTTPS and Secure WebSocket (wss) connections. If you are installing ASE as a non-root user, then use port greater than 1024.
8010	Management port. Used by CLI and REST API for managing ASE.
8020	Cluster port. Used by ASE internally to set up the cluster.
8080	ABS port. Used by ASE for outbound connections to ABS for sending access logs and receive attack information.

**Warning:** The management ports 8010 and 8020 should not be exposed to the internet and are strictly for internal use. Make sure that these ports are behind your firewall.

In an AWS environment, both management ports should be private in the Security Group for ASE.

#### Security Group “ase”:

port 80: Accessible from any client (note: not secure)

port 443: Accessible from any client

port 8010: Accessible from management systems and administrators

port 8020: Accessible from peer ASE nodes

**Note:** If you are setting up the deployment in an AWS environment with security groups, use private IPs for ABS connections to avoid security group issues.

## Configure time zone - ASE

You can set up ASE in either `local` or `UTC` time zone by configuring the `timezone` parameter in `/pingidentity/ase/config/ase.conf` file. All the management, access, and audit logs capture the time based on the time zone configured in `ase.conf` file. If the `timezone` parameter is left empty, ASE by default runs in the `UTC` time zone. Following is a snippet of `ase.conf` for `timezone` parameter.

```
; Set the timezone to utc or local. The default timezone is utc.
timezone=local

<truncated ase.conf...>
```

**Note:** Make sure that ASE, ABS AI Engine, and PingIntelligence for APIs Dashboard are all configured on the same timezone.

If ASE is deployed in a cluster, make sure to configure the same time zone on each cluster node. If you have used automated deployment to deploy PingIntelligence, the automated deployment configures the same time zone on each ASE node. However, if you have used manual installation, then you need to manually configure the time zone on each ASE node.

You can use ASE `status` command to check the current time zone of ASE.

```
#!/bin/cli.sh -u admin -p status
API Security Enforcer
status           : started
mode             : inline
http/ws         : port 8080
https/wss       : port 8443
firewall        : enabled
abs             : disabled, ssl: enabled
abs attack      : disabled
audit           : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
log level       : warn
timezone       : local (MST)
```

### Change ASE time zone

If you want to change the time zone in ASE, complete the following steps:

1. Stop ASE
2. Update the timezone parameter in `ase.conf` file
3. Start ASE

## Tune host system for high performance

ASE ships with a script to tune the host Linux operating system for handling high TCP concurrency and optimizing performance. To understand the tuning parameters, refer to the tuning script comments. When running the tuning script, changes are displayed on the console to provide insight into system modifications. To undo system changes, run the `untune` script

**i Important:** If you are installing ASE as a non-root user, run the `tune` script for your platform before starting ASE.

The following commands are for tuning RHEL. For tuning Ubuntu, use the Ubuntu tuning scripts.

### Tune the host system:

Enter the following command in the command line:

```
/opt/pingidentity/ase/bin/tune_rhel7.sh
```

Make sure to close the current shell after running the `tune` script and proceeding to start ASE.

**i Note:** If ASE is deployed in a Docker Container, run the `tune` script on the host system, not in the container.

### Untune the host system:

The “`untune`” script brings the system back to its original state. Enter the following command in the command line:

```
/opt/pingidentity/ase/bin/untune_rhel7.sh
```

**i Note:** You should be a `root` user to run the `tune` and `untune` scripts.

## Start and stop ASE

### Prerequisite:

For ASE to start, the `ase_master.key` must be present in the `/opt/pingidentity/ase/config` directory. If you have moved the master key to a secured location for security reasons, copy it to the `config` directory before executing the start script. You can run ASE as a non-root user also.

### Start ASE

Before starting ASE, make sure that `nofile` limit in `/etc/security/limits.conf` is set to at least 65535 or higher on the host machine. Run the following command on the ASE host machine to check the `nofile` limit:

```
ulimit -n
```

Change working directory to `bin` and run the `start.sh` script.

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.0.2...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

## Stop ASE

Change working directory to `bin` and run the `stop.sh` script.

```
/opt/pingidentity/ase/bin/stop.sh -u admin -p admin
checking API Security Enforcer status...sending stop request to ASE. please
wait...
API Security Enforcer stopped
```

## Change default settings

It is recommended that you change the default key and password in ASE. Following is a list of commands to change the default values:

### Change `ase_master.key`

Run the following command to create your own ASE master key to obfuscate keys and password in ASE.

**Command:** `generate_obfkey`. ASE must be stopped before creating a new `ase_master.key`

```
/opt/pingidentity/ase/bin/cli.sh admin generate_obfkey -u admin -p admin
API Security Enforcer is running. Please stop ASE before generating new
obfuscation master key
```

**Stop ASE:** Stop ASE by running the following command:

```
/opt/pingidentity/ase/bin/stop.sh -u admin -p admin
checking API Security Enforcer status...sending stop request to ASE. please
wait...
API Security Enforcer stopped
```

**Change `ase_master.key`:** Enter the `generate_obfkey` command to change the default ASE master key:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin generate_obfkey
Please take a backup of config/ase_master.key, config/ase.conf,
config/abs.conf, config/cluster.conf before proceeding
Warning: Once you create a new obfuscation master key, you should
obfuscate all config keys also using cli.sh obfuscate_keys
Warning: Obfuscation master key file /opt/pingidentity/ase/config/
ase_master.key already exist.
This command will delete it create a new key in the same file
Do you want to proceed [y/n]:
```

After you change the `ase_master.key`, you need to obfuscate all keys and passwords with the new `ase_master.key`. Enter the keys and passwords in `ase.conf`, `abs.conf`, and `cluster.conf` in plain text and run the obfuscation commands. For more information on obfuscation, see [Obfuscate keys and passwords](#) on page 128.

**Start ASE:** After a new ASE master key is generated, start ASE by entering the following command:

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.1...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

### Change keystore password

You can change the keystore password by entering the following command. The default password is `asekeystore`. ASE must be running for updating the keystore password.

**Command:** `update_keystore_password`

```
/opt/pingidentity/ase/bin/cli.sh update_keystore_password -u admin -p admin
New password >
New password again >
keystore password updated
```

### Change admin password

You can change the default admin password by entering the following command.

```
/opt/pingidentity/ase/bin/cli.sh update_password -u admin
Old password >
New password >
New password again >
Password updated successfully
```

You can change the password on a single ASE node and propagate the change to other nodes in the ASE cluster. For more information, see [Propagate changed password](#).

Any change in the ASE admin password must be updated in the PingIntelligence for APIs Dashboard. Add the new password to `<pi_install_dir>/webgui/config/webgui.properties` and obfuscate it.

## Obfuscate keys and passwords


Using the ASE command line interface, you can obfuscate keys and passwords configured in `ase.conf`, `cluster.conf`, and `abs.conf`. Here is the obfuscated data in each file:

- `ase.conf` – Email and keystore (PKCS#12) password
- `cluster.conf` – Cluster authentication key
- `abs.conf` – ABS access and secret key

ASE ships with a default master key (`ase_master.key`) which is used to obfuscate other keys and passwords. It is recommended to generate your own `ase_master.key`.

**Note:** During the process of obfuscation password, ASE must be stopped.

The following diagram summarizes the obfuscation process:



### Generating your `ase_master.key`

You can generate the `ase_master.key` by running the **generate\_obfkey** ASE CLI command.

```
/opt/pingidentity/ase/bin/cli.sh generate_obfkey -u admin -p

Please take a backup of config/ase_master.key, config/ase.conf, config/abs.conf, config/cluster.conf before proceeding
```



```
Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh obfuscate_keys

Warning: Obfuscation master key file /opt/pingidentity/ase/config/
ase_master.key already exists. This command will delete it and create a new
key in the same file.

Do you want to proceed [y/n]:y
creating new obfuscation master key
Success: created new obfuscation master key at /opt/pingidentity/ase/config/
ase_master.key
```

The new `ase_master.key` is used to obfuscate the keys and passwords in the configuration files.

**Important:** In an ASE cluster, the `ase_master.key` must be manually copied to each cluster node.

### Obfuscate keys and passwords

Enter the keys and passwords in clear text in `ase.conf`, `cluster.conf`, and `abs.conf`. Run the `obfuscate_keys` command to obfuscate keys and passwords:

```
/opt/pingidentity/ase/bin/cli.sh obfuscate_keys -u admin -p

Please take a backup of config/ase_master.key, config/ase.conf, config/
abs.conf, and config/cluster.conf before proceeding

If config keys and passwords are already obfuscated using the current master
key, they are not obfuscated again

Following keys will be obfuscated:
config/ase.conf: sender_password, keystore_password
config/abs.conf: access_key, secret_key
config/cluster.conf: cluster_secret_key

Do you want to proceed [y/n]:y
obfuscating config/ase.conf, success
obfuscating config/abs.conf, success
obfuscating config/cluster.conf, success
```

Start ASE after keys and passwords are obfuscated.

**Important:** After the keys and passwords are obfuscated, the `ase_master.key` must be moved to a secure location from ASE for security reasons. If you want to restart ASE, the `ase_master.key` must be present in the `/opt/pingidentity/ase/config/` directory.

### Delete UUID to propagate changed password

You can change the password on a single ASE node and propagate the change to other nodes in the ASE cluster. To do this, you need to copy the `/data` directory of the ASE node on which the password has been modified to the other nodes in the cluster.

**Important:** The `ase.store` file in the ASE `/data` directory stores the password information, and also the universally unique identifier ( UUID ) of the ASE node. It is important to delete the UUID of the ASE node with modified password before copying its `/data` directory to the other nodes in the cluster. This avoids cluster synchronization issues due to duplicate UUIDs.

Follow these steps to propagate the changed password to all the nodes in an ASE cluster:

1. Change the password for the ASE node. For more information, see [Change Admin password](#).
2. Stop the ASE node by following the instructions explained in [Stop ASE](#).
3. Run the `delete-uuid` script.

```
/opt/pingidentity/ase# ./util/delete-uuid
Deleting uuid 02cdf7b3-dfb7-4d5b-b9a1-171e89664d11
Success
```

4. Verify the successful deletion of UUID by re-executing the `delete-uuid` script.

```
/opt/pingidentity/ase# ./util/delete-uuid
uuid does not exist in database
```

5. Copy the `/data` directory to other nodes in the cluster.

## PKCS#12 keystore

ASE ships with a default PKCS#12 keystore. The default password is “asekeystore”. The default password is obfuscated and configured in the `ase.conf` file. You must update the default PKCS#12 keystore password by using the `update_keystore_password` command for security reasons. The password is updated and obfuscated at the same time. ASE must be running for updating the keystore password.

```
/opt/pingidentity/ase/bin/cli.sh update_keystore_password -u admin -p admin
New password >
New password again >
keystore password updated
```

## Directory structure

During the installation process, ASE creates the following directories:

Directory Name	Purpose
config	Contains files and directories to configure ASE and its APIs. The <code>certs</code> subdirectory contains the keys and certificates for SSL/TLS 1.2.
data	For internal use. Do not change anything in this directory.
logs	Stores ASE log files including access log files sent to ABS for analysis. The access log files are compressed and moved to <code>abs_uploaded</code> directory after they have been uploaded to ABS.
lib	For internal use. Do not change anything in this directory.
bin	Contains scripts including the start and stop ASE, tuning script for ASE performance.
	<b>Note:</b> The scripts in the <code>bin</code> directory are not editable.
util	The <code>util</code> directory contains scripts to check and open ABS ports as well as script to purge logs. <ul style="list-style-type: none"> <li>▪ <code>check_ports.sh</code> Check ABS ports</li> <li>▪ <code>open_ports_ase.sh</code>: Run this script on the ASE machine to open the default ASE ports: 80, 443, 8010, and 8020.</li> <li>▪ Purge logs</li> </ul>

## Administering an ASE cluster

ASE Cluster runs either in a single cloud or across multiple clouds. All ASE cluster nodes communicate over a TCP connection to continuously synchronize the configuration in real time. Cluster nodes are symmetrical which eliminates a single point of failure. Key features of ASE clustering are:

- ASE node addition to a live cluster without configuring the node – true auto-scaling
- Configuration (`ase.conf`, API JSON files) synchronization across all cluster nodes
- Update and delete operations using CLI and REST APIs
- Run time addition or deletion of cluster nodes
- Real-time blacklist synchronization across cluster
- A single cluster with nodes spanning across multiple data centers

Several cluster features are unique to the deployed environment including:

- Authentication token for API gateway (ASE sideband only)
- Cookie replication across all cluster nodes (ASE inline only)

CLI configuration commands executed at any cluster node are automatically replicated across all cluster nodes. All nodes remain current with respect to configuration modifications. Cluster nodes synchronize SSL certificates across various ASE nodes.

Add or remove a node from the cluster without disrupting any live traffic. The amount of time required to activate a new cluster node is dependent on the time to synchronize the configuration and cookie information from other nodes.


ASE cluster performs real-time synchronization of cookies for ASE inline configurations. This is critical for session mirroring or handling a DNS flip between requests from the same client. Since no master or slave nodes exist, all cluster nodes synchronize cookie information – which means that each node has the same cookies as other nodes.

ASE also synchronizes `ase.conf` files across cluster nodes with the exception of a few parameters: data ports, management ports, and number of processes.


### ASE cluster deployment

ASE cluster is a distributed node architecture. Ping Identity recommends that one cluster node be designated the management node through which all configuration changes are performed. This helps maintain consistency of operations across nodes. However, no restrictions exist on using other nodes in the cluster to make changes. If two different nodes are used to modify the ASE cluster, then the latest configuration change based on time-stamps is synchronized across the nodes.

ASE cluster uses a circular deployment. During setup, the first node of the cluster acts as the central node of the cluster from which all cluster nodes synchronize configuration and cookie data. When the setup of all nodes is complete, the nodes communicate with each other to synchronize the latest session information.

 **Note:** If the first node or management node goes down, the functioning of the other cluster nodes is not affected. Make sure the peer node provided in the `cluster.conf` is running before adding a new node.

When an ASE cluster is setup, the `peer_node` parameter must be configured with an IPv4 address and port number. ASE uses this value to connect to other nodes of the cluster. To add new cluster nodes, activate one node at a time. In the following example, the `peer_node` IP address for all nodes is the IP address of the first node. Each node must wait until the process of adding the previous node is completed.



Use the status command to verify status before adding the next node in the cluster.

```
/opt/pingidentity/ase/bin/cli.sh status -u admin -p
Status: starting
```

After all cluster nodes are added, use the management or first node to carry out all cluster operations.

**Note:** Add one node at a time to the cluster. After the node completes loading data, add the next node

Cluster nodes must be added sequentially, one node at a time, to ensure consistent cluster behavior. The following table lists the items that are synchronized across the cluster:

Item	Synchronized (Yes or No)	Synchronization (restart or live)
Certificates (keystore)	Yes	Restart
Master key	No	-
API JSON	Yes	Live and restart
Cookies	Yes	Live and restart
CLI admin password	No	No
Authorization token for sideband ASE	Yes	Live and restart
Blacklist and whitelist (create, delete, and delete all)	Yes	Live and restart
Real-time attacks (IP, cookie, and token is blocked)	Yes	Live
ase.conf	Yes	restart
abs.conf	Yes	restart

<p>CLI commands that are <i>not</i> synchronized</p>	<p>The following commands are <i>not</i> synchronized:</p> <ul style="list-style-type: none"> <li>▪ <code>create_key_pair</code></li> <li>▪ <code>create_csr</code></li> <li>▪ <code>create_self_sign_cert</code></li> <li>▪ <code>import_key_pair</code></li> <li>▪ <code>import_cert</code></li> <li>▪ <code>create_management_key_pair</code></li> <li>▪ <code>create_management_csr</code></li> <li>▪ <code>create_management_self_sign_cert</code></li> <li>▪ <code>import_management_key_pair</code></li> <li>▪ <code>import_management_cert</code></li> <li>▪ <code>update_password</code></li> <li>▪ <code>update_auth_method</code></li> <li>▪ <code>generate_obfkey</code></li> <li>▪ <code>obfuscate_keys</code></li> <li>▪ <code>update_keystore_password</code></li> </ul>	<p>-</p>
	<p><b>Note:</b> The commands listed above require the entire ASE to restart for the commands to synchronize.</p>	

### Start ASE cluster

To setup an ASE cluster, the following four steps must be completed:



### Pre-requisites

1. Obtain list of IP addresses and ports required for ASE cluster nodes
2. Enable NTP on your system.
3. If adding an existing ASE instance to a cluster, backup the ASE data first. When a node is added to a cluster, it synchronizes the data from the other nodes and overwrites existing data.

### To setup an ASE cluster node:

1. Navigate to the `config` directory
2. Edit `ase.conf` file:
  - a. Set `enable_cluster=true` for all cluster nodes.
  - b. Make sure that the value in the parameter `mode` is same on each ASE cluster node, either `inline` or `sideband`. If the value of `mode` parameter does not match, the nodes will not form a cluster.

### 3. Edit the `cluster.conf` file

- a. Configure `cluster_id` with an identical value for all nodes in a single cluster (for example, `cluster_id=shopping`)
- b. Enter port number in the `cluster_management_port` (default port is 8020) parameter. ASE node uses this port number to communicate with other nodes in the cluster.
- c. Enter an IPv4 address or hostname with the port number for the `peer_node` which is the first (or any existing) node in the cluster. Keep this parameter empty for the first node of the cluster.
- d. Provide the obfuscated `cluster_secret_key`. All the nodes of the cluster must have the same obfuscated `cluster_secret_key`. This key must be entered manually on each node of the cluster for the nodes to connect to each other.
- e. For the first node of the ASE cluster, `peer_node` should be left empty. On other nodes of the ASE cluster, enter the IP address or the hostname of the first cluster in the node in the `peer_node` variable.

Here is a sample `cluster.conf` file:

```
; API Security Enforcer's cluster configuration.
; This file is in the standard .ini format. The comments start with a
; semicolon (;).
; Section is enclosed in []
; Following configurations are applicable only if cluster is enabled with
; true in ase.conf
; unique cluster id.
; valid character class is [ A-Z a-z 0-9 _ - . / ]
; nodes in same cluster should share same cluster id
cluster_id=ase_cluster
; cluster management port.
cluster_manager_port=8020
; cluster peer nodes.
; a comma-separated list of hostname:cluster_manager_port or
; IPv4_address:cluster_manager_port
; this node will try to connect all the nodes in this list
; they should share same cluster id
peer_node=
; cluster secret key.
; maximum length of secret key is 128 characters (deobfuscated length).
; every node should have same secret key to join same cluster.
; this field cannot be empty.
; change default key for production.
cluster_secret_key=OBF:AES:nPJOh3wXQWK/
BOHrtKu3G2SGiAEElOSvOFYEiWfIVSdummoFwSR8rDh2bBnhTDdJ:7LFcqXQlqkW9kldQoFg0nJoLSojnzHDbD3
```

After configuring an ASE node, start the node by running the following command:

```
/opt/pingidentity/ase/bin/start.sh
```

### Scale up the ASE cluster

Scale up the ASE cluster by adding one node at a time to an active cluster without disrupting traffic. To add a new cluster node, enter the `peer_node` IP address or hostname in the `cluster.conf` file of the ASE node and then start the ASE node. The new node will synchronize configuration and cookie data from the peer nodes. After loading, it will become part of the cluster. For example, if the IP of the first node is 192.168.20.121 with port 8020, then the `peer_node` parameter would be 192.168.20.121:8020.

```
; ASE cluster configuration. These configurations apply only when you have
; enabled cluster in the api_config file.
; Unique cluster ID for each cluster. All the nodes in the same cluster
; should have the same cluster ID.
cluster_id=ase_cluster
```

```
; Cluster management port.
cluster_manager_port=8020
; Cluster's active nodes. This can be a comma separated list of nodes in
  ipv4_address:cluster_manager_port format.
peer_node=192.168.20.121:8020
```

### Scale down ASE cluster

A node can be removed from an active cluster without disrupting traffic by completing the following steps:

1. Stop the ASE node to be removed using the [stop command](#)
2. Set the `enable_cluster` option as `false` in its `ase.conf` file.

**Note:** The removed node retains the cookie and certificate data from when it was part of the cluster

### Delete ASE cluster node

An inactive cluster node has either become unreachable or has been stopped. When you delete a stopped cluster node, the operation does not remove cookie and other synchronized data. To find which cluster nodes are inactive, use the `cluster_info` command:

```
/opt/pingidentity/ase/bin/cli.sh cluster_info -u admin -p
cluster id : ase_cluster
cluster nodes
127.0.0.1:8020 active
1.1.1.1:8020 active
2.2.2.2:8020 inactive
172.17.0.4:8020 (tasks.aseservice) active
172.17.0.5:8020 (tasks.aseservice) inactive
tasks.aseservice2:8020 not resolved
```

Using the `cluster_info` command output, you can remove the inactive cluster nodes `2.2.2.2:8020` and `172.17.0.5:8020`.

To delete the inactive node, use the `delete_cluster_node` command:

```
/opt/pingidentity/ase/bin/cli.sh delete_cluster_node <IP:Port>
```

### Stop ASE cluster

You can stop the entire cluster by running the following command on any ASE node in the cluster.

```
/opt/pingidentity/ase/bin/stop.sh cluster -u admin -p
```

When the cluster stops, each cluster node retains all the cookie and certificate data.

### ASE Cluster SSL

ASE supports SSL over TCP for securing communications between nodes in a cluster. It uses TLS 1.2 to encrypt the communications.

You can configure SSL in ASE using one of the following three methods:

- [Using the default certificate](#) on page 136
- [Creating a new SSL certificate](#) on page 136
- [Importing an existing certificate and key-pair](#) on page 139

**Note:** You can view cluster information in the `controller.log` available in `<pi_install_path>/pingidentity/ase/logs/` directory.

## Using the default certificate

### About this task

ASE ships with its default PKCS#12 keystore located at `<pi_install_path>/pingidentity/ase/config/cert/ase.store`. The default certificate and SSL keys are stored in the PKCS store. You can use them to secure the ASE cluster. This task explains the steps to be completed to synchronize the SSL certificate and keys across different nodes in an ASE cluster:


### Steps

1. Start the ASE cluster by following the steps explained in [Start ASE cluster](#) on page 133. During the cluster start, cluster keys and certificates are synchronized across all the ASE nodes.
2. Once the cluster is started, restart the secondary nodes of the cluster for the changes to take effect. The instructions to restart the cluster are explained in [Restart ASE cluster](#) on page 139.

### Creating a new SSL certificate

You can secure an ASE cluster using a new SSL certificate. To achieve this, you can either use a self-signed certificate or use a Certificate Authority (CA) signed SSL certificate.

#### Self-signed certificate



Complete the following steps to create a self-signed certificate:

1. Create a cluster key pair using the following CLI command. The Private key in the pair is automatically created and updated in the keystore in `<pi_install_path>/pingidentity/ase/config/certs/` directory.

```
create_cluster_key_pair [--yes | -y]
create_private key for cluster server
--yes | -y : create private key without confirmation prompt
```

For example, the following command creates `dh1024.pem` in `/opt/pingidentity/ase/config/certs/cluster/` directory.

```
$ pingidentity/ase/bin/cli.sh -u admin -p admin create_cluster_key_pair
Warning: create_cluster_key_pair will delete any existing cluster
key_pair, CSR and self-signed certificate
Do you want to proceed [y/n]:y
Ok, creating new cluster key pair. Creating DH parameter may take around
20 minutes. Please wait
Cluster key created at keystore
Cluster dh param file created at /opt/pingidentity/ase/config/certs/
cluster/dh1024.pem
```

2. Generate a Certificate Signing Request (CSR) from the private key using the following CLI command. This `.csr` file gets saved in `<pi_install_path>/pingidentity/ase/config/certs/cluster/` directory.

```
create_cluster_csr [--yes | -y]
create_certificate signing request for cluster server
--yes | -y : create certificate signing request without confirmation
prompt
```



For example, the following command creates a `.csr` file under `/opt/pingidentity/ase/config/certs/cluster/` directory.

```
$ pingidentity/ase/bin/cli.sh -u admin -p admin create_cluster_csr
Warning: create_cluster_csr will delete any existing cluster CSR and self
signed certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >OP
State >GP
Location >IP
Organization >KP
Organization Unit >Kpase
Common Name >www.123.com
Generating CSR. Please wait...
OK, cluster csr created at /opt/pingidentity/ase/config/certs/cluster/
cluster.csr
```

3. Run the following CLI command to generate a self-signed certificate. The certificate is automatically created in the keystore in `<pi_install_path>/pingidentity/ase/config/certs/` directory .

```
create_cluster_self_sign_cert [--yes | -y]
--yes | -y : create self signed certificate without confirmation prompt
```

For example, the following command creates a self-signed certificate in the key store.

```
$ pingidentity/ase/bin/cli.sh -u admin -p admin
create_cluster_self_sign_cert
Warning: create_cluster_self_sign_cert will delete any existing cluster
self signed certificate
Do you want to proceed [y/n]:y
Creating new cluster self signed certificate
OK, self sign certificate created in key store
```

4. Restart the ASE cluster for synchronizing the key and certificate. To restart the ASE cluster, follow the instructions explained in [Restart ASE cluster](#) on page 139.

Obtain a CA-signed certificate



Complete the following steps to obtain Certificate Authority (CA) signed SSL certificates:

1. Create a cluster key pair using the following CLI command. The Private key in the pair is automatically created and updated in the keystore in `<pi_install_path>/pingidentity/ase/config/certs/` directory.

```
create_cluster_key_pair [--yes | -y]
create private key for cluster server
--yes | -y : create private key without confirmation prompt
```

For example, the following command creates a key in the `/opt/pingidentity/ase/config/certs/cluster/` directory.

```
$ pingidentity/ase/bin/cli.sh -u admin -p admin create_cluster_key_pair
Warning: create_cluster_key_pair will delete any existing cluster
key_pair, CSR and self-signed certificate
Do you want to proceed [y/n]:y
Ok, creating new cluster key pair. Creating DH parameter may take around
20 minutes. Please wait
Cluster key created at keystore
Cluster dh param file created at /opt/pingidentity/ase/config/certs/
cluster/dh1024.pem
```

2. Generate a Certificate Signing Request (CSR) from the private key using the following CLI command. This `.csr` file gets saved in `<pi_install_path>/pingidentity/ase/config/certs/cluster/` directory.

```
create_cluster_csr [--yes | -y]
create_certificate signing request for cluster server
--yes | -y : create certificate signing request without confirmation
prompt
```

For example, the following command creates a `.csr` file under `/opt/pingidentity/ase/config/certs/cluster/` directory.

```
$ pingidentity/ase/bin/cli.sh -u admin -p admin create_cluster_csr
Warning: create_cluster_csr will delete any existing cluster CSR and self
signed certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >OP
State >GP
Location >IP
Organization >KP
Organization Unit >Kpase
Common Name >www.123.com
Generating CSR. Please wait...
OK, cluster csr created at /opt/pingidentity/ase/config/certs/cluster/
cluster.csr
```

3. Upload the CSR created in step 2 to the CA-signing authority's website to get a CA-signed certificate.
4. Download the CA-signed certificate from the CA-signing authority's website.
5. Use the following CLI command to import the signed CA-certificate into ASE cluster. The certificate is imported into the keystore in `<pi_install_path>/pingidentity/ase/config/certs/` directory .

```
import_cluster_cert {cert_path} [--yes | -y]
import CA signed certificate for cluster server
--yes | -y : import CA signed certificate without confirmation prompt
```

For example,

```
./cli.sh -uadmin -padmin import_cluster_key_pair /home/ec2-user/
cert_folder/signed_cert/test.elasticbeam.com.key
Warning: import_cluster_key_pair will overwrite any existing cluster
certificates
```

```

Do you want to proceed [y/n]:y
Exporting cluster key to API Security Enforcer...
OK, key pair added to keystore
2:43
[ec2-user@rhel76-cluster-nodes-6-12 bin]$ ./cli.sh -uadmin -padmin
import_cluster_cert /home/ec2-user/cert_folder/signed_cert/
test.elastic.crt
Warning: import_cluster_cert will overwrite any existing cluster signed
certificate
Do you want to proceed [y/n]:y
Exporting cluster certificate to API Security Enforcer...
OK, signed certificate added to keystore


```

- Restart the ASE cluster for synchronizing the key and certificate. To restart the ASE cluster, follow the instructions explained in [Restart ASE cluster](#) on page 139.

### Importing an existing certificate and key-pair

About this task

Complete the following steps to import an existing certificate and key-pair:



#### Steps

- Convert the key to `.key` file.

```
openssl rsa -in private.pem -out private.key
```

- Convert the SSL certificate to `.crt` file.

```
openssl x509 -in server-cert.pem -out server-cert.crt
```

- Import the cluster key into the keystore using following CLI command.

```
import_cluster_key_pair {key_path} [--yes | -y]
import key pair for cluster server
--yes | -y : import key pair without confirmation prompt
```

- Import the certificate into the keystore using following CLI command.

```
import_cluster_cert {cert_path} [--yes | -y]
import CA signed certificate for cluster server
--yes | -y : import CA signed certificate without confirmation prompt
```

- Restart the ASE cluster for synchronizing the key and the certificate. To restart the ASE cluster, follow the instructions explained in [Restart ASE cluster](#) on page 139.

### Restart ASE cluster

It is recommended to restart ASE cluster nodes, one node at a time, to ensure consistent cluster behavior. To restart the ASE Cluster, complete the following steps:

- Stop all the nodes in the cluster by running the following command on any ASE node in the cluster.

```
/opt/pingidentity/ase/bin/stop.sh cluster -u admin -p
```

2. Start the first node or management node in the cluster by executing the following command.

```
/opt/pingidentity/ase/bin/start.sh
```

**Note:** The first node or management node of the ASE cluster has the `peer_node` parameter empty in the `cluster.conf` file.

3. Verify the status of the node by running the `status` command. Start the next node in the cluster only after the status of the node changes to `started`.

```
/opt/pingidentity/ase/bin/cli.sh status -u admin -p
Status: started
```

4. Repeat step-2 and step-3 for all the other nodes in the cluster, to complete the cluster restart.


## Configure API JSON files

This topic discusses what API JSON files are, and how they are configured to secure the APIs in your environment.

API JSON files are used to configure the behavior and properties of your APIs in ASE. The parameters in API JSON files help ASE to uniquely identify the APIs in your environment. Each API has a unique API JSON file in ASE. ASE ships with sample JSON files located in the `/config/api` directory.

The parameters configured in an API JSON file help ASE extract metadata from API traffic, set decoys to trap intruding attacks, perform health checks on backend servers, and so on. The API JSON parameters also help the ABS AI Engine to build AI models to detect any Indicators of Attacks (IoAs) on APIs. For more information on the parameters in API JSON files, see the following:

- [Defining an API using API JSON configuration file in sideband mode](#) on page 170
- [Defining an API using API JSON configuration file in inline mode](#) on page 219



You can manually configure the JSON file with the required parameters and add them to ASE.

**Note:** The sample JSON file has an extension of `.example`. If you are customizing the example file, then save the file as a `.json` file.

### Manually add API JSON to ASE

After configuring an API JSON file, add it to ASE to activate ASE processing. To add an API, execute the following CLI command.

```
/<ASE_Installation_path>/pingidentity/ase/bin/cli.sh -u admin -p admin
add_api {file_path/api_name}
```

You can also use the [Create API](#) in ASE Admin APIs to add an API JSON file to ASE. Here is a sample `curl` command for it.

```
curl --location --request POST '{{API}}=<API Name>' \
--header '{{Access_Key_Header}}: {{Access_Key}}' \
--header '{{Secret_Key_Header}}: {{Secret_key}}' \
--header 'Content-Type: application/json' \
--data-raw '{
  "api_metadata": {
    "protocol": "https",
    "url": "/patmapp",
    "hostname": "*",
    "oauth2_access_token": false,
    "apikey_qs": "",
    <<Request body continues...>>
  }
}
```

### List API JSON files

You can check the addition of an API JSON file to ASE by executing the following CLI command.

```
/<ASE_Installation_path>/pingidentity/ase/bin/cli.sh -u admin -p admin
list_api
```

You can also use [List API](#) in ASE Admin APIs to verify. Here is a sample `curl` command for it.

```
curl --location --request GET '{{List_API}}' \
--header '{{Access_Key_Header}}: {{Access_Key}}' \
--header '{{Secret_Key_Header}}: {{Secret_key}}'
```

### Update API JSON files

After activation, an API JSON definition can be updated in real time. Edit the API JSON file located in the `/config/api` directory and make the desired changes. Save the edited API JSON file and execute the following CLI command.

```
/<ASE_Installation_path>/pingidentity/ase/bin/cli.sh -u admin -p admin
update_api <api_name>
```

For example,

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin update_api shop
api shop updated successfully
```

You can also use [Update API](#) in ASE Admin APIs to update the JSON. Here is a sample `curl` command for it.

```
curl --location --request PUT '{{API}}=<API Name>' \
--header '{{Access_Key_Header}}: {{Access_Key}}' \
--header '{{Secret_Key_Header}}: {{Secret_key}}' \
--header 'Content-Type: application/json' \
--data-raw '{
  "api_metadata": {
    "protocol": "https",
    "url": "/pubatmapp",
    "hostname": "*",
    "oauth2_access_token": false,
    <<Request body continues...>>
  }
}
```

## Configure SSL for external APIs


ASE supports both TLS 1.2 and SSLv3 for external APIs. OpenSSL is bundled with ASE, following are the version details:

- RHEL 7 : OpenSSL 1.0.2k-fips 26 Jan 2017
- Ubuntu 16LTS : OpenSSL 1.0.2g 1 Mar 2016

You can configure SSL in ASE for client side connection using one of the following methods:

- **Method 1:** Using CA-signed certificate
- **Method 2:** Using self-signed certificate
- **Method 3:** Importing an existing certificate

The steps provided in this section are for certificate and key generated for connections between the client and ASE as depicted in the illustration below:



### In a cluster setup:

1. Stop all the ASE cluster nodes
2. Configure the certificate on the management node
3. Start the cluster nodes one by one for the certificates to synchronize across the nodes

## Method 1: Use CA-signed certificate

To use Certificate Authority (CA) signed SSL certificates, follow the process to create a private key, generate a Certificate Signing Request (CSR), and request a certificate as shown below:



**Note:** ASE internally validates the authenticity of the imported certificate.

### To use a CA-signed certificate:

1. Create a private key. ASE CLI is used to create a 2048-bit private key and to store it in the keystore.

```

/opt/pingidentity/ase/bin/cli.sh create_key_pair -u admin -p
Warning: create_key_pair will delete any existing key_pair, CSR and self-
signed certificate
Do you want to proceed [y/n]:y
Ok, creating new key pair. Creating DH parameter may take around 20
minutes. Please wait
Key created in keystore
dh param file created at /opt/pingidentity/ase/config/certs/dataplane/
dh1024.pem
  
```

2. Create a CSR. ASE takes you through a CLI-based interactive session to create a CSR.

```

/opt/pingidentity/ase/bin/cli.sh create_csr -u admin -p
Warning: create_csr will delete any existing CSR and self-signed
certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >US
State > Colorado
Location >Denver
Organization >Pingidentity
Organization Unit >Pingintelligence
Common Name >ase
Generating CSR. Please wait...
OK, csr created at /opt/pingidentity/ase/config/certs/dataplane/ase.csr
  
```

3. Upload the CSR created in step 2 to the CA signing authority's website to get a CA signed certificate.
4. Download the CA-signed certificate from the CA signing authority's website.
5. Use the CLI to import the signed CA certificate into ASE. The certificate is imported into the keystore.

```

/opt/pingidentity/ase/bin/cli.sh import_cert <CA signed certificate path>
-u admin -p
Warning: import_cert will overwrite any existing signed certificate
Do you want to proceed [y/n]:y
Exporting certificate to API Security Enforcer...
OK, signed certificate added to keystore
  
```

6. Restart ASE by first stopping and then starting ASE.

## Method 2: Use self-signed certificate

A self-signed certificate is also supported for customer testing.

### To create a self-signed certificate

1. Create a private key. ASE CLI is used to generate a 2048-bit private key which is in the `/opt/pingidentity/ase/config/certs/dataplane/dh1024.pem` directory.

```
/opt/pingidentity/ase/bin/cli.sh create_key_pair -u admin -p
Warning: create_key_pair will delete any existing key_pair, CSR and self-
signed certificate
Do you want to proceed [y/n]:y
Ok, creating new key pair. Creating DH parameter may take around 20
minutes. Please wait
Key created in keystore
dh param file created at /opt/pingidentity/ase/config/certs/dataplane/
dh1024.pem
```

2. Create a CSR file:

```
/opt/pingidentity/ase/bin/cli.sh create_csr -u admin -p
Warning: create_csr will delete any existing CSR and self-signed
certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >US
State >colorado
Location >Denver
Organization >PI
Organization Unit >TEST
Common Name >yoursiteabc.com
Generating CSR. Please wait...
OK, csr created at /opt/pingidentity/ase/config/certs/dataplane/ase.csr
```

3. Create a self-signed certificate. Use the CLI to produce a self-signed certificate using the certificate request located in `/opt/pingidentity/ase/config/certs/dataplane/ase.csr`

```
/opt/pingidentity/ase/bin/cli.sh create_self_sign_cert -u admin -p
Warning: create_self_sign_cert will delete any existing self-signed
certificate
Do you want to proceed [y/n]:y
Creating new self-signed certificate
OK, self-sign certificate created in keystore
```

4. Restart ASE by stopping and starting.

## Method 3: Import an existing certificate and key pair

To install an existing certificate, complete the following steps and import it into ASE. If you have intermediate certificate from CA, then append the content to your server crt file.

1. Import key pair:

```
/opt/pingidentity/ase/bin/cli.sh import_key_pair private.key -u admin -p
Warning: import_key_pair will overwrite any existing certificates
Do you want to proceed [y/n]:y
Exporting key to API Security Enforcer...
OK, key pair added to keystore
```

2. Import the `.crt` file in ASE using the `import_cert` CLI command

```
/opt/pingidentity/ase/bin/cli.sh import_cert server-crt.crt -u admin -p
Warning: import_cert will overwrite any existing signed certificate
```



```
Do you want to proceed [y/n]:y
Exporting certificate to API Security Enforcer...
OK, signed certificate added to keystore
```

3. Restart ASE by stopping and starting.

## Configure SSL for management APIs


ASE supports both TLS 1.2 and SSLv3 for management APIs. OpenSSL is bundled with ASE, following are the version details:

- RHEL 7 : OpenSSL 1.0.2k-fips 26 Jan 2017
- Ubuntu 16LTS: OpenSSL 1.0.2g 1 Mar 2016

You can configure SSL in ASE for *management APIs* using one of the following methods:

- **Method 1:** Using CA-signed certificate
- **Method 2:** Using self-signed certificate
- **Method 3:** Importing an existing certificate

The steps provided in this section are for certificate and key generated are for connections between a management API client and ASE:



### In a cluster setup:

1. Stop all the ASE cluster nodes
2. Configure the certificate on the management node
3. Start the cluster nodes one by one for the certificates to synchronize across the nodes

### Method 1: Use CA-signed certificate

To use Certificate Authority (CA) signed SSL certificates, follow the process to create a private key, generate a Certificate Signing Request (CSR), and request a certificate as shown below:



**Note:** ASE internally validates the authenticity of the imported certificate.

### To use a CA-signed certificate:

1. Create a private key. ASE CLI is used to create a 2048-bit private key and to store it in the `/opt/pingidentity/ase/config/certs/management` directory.

```
/opt/pingidentity/ase/bin/cli.sh create_management_key_pair -u admin -p
Warning: create_management_key_pair will delete any existing management
key_pair, CSR and self-signed certificate
Do you want to proceed [y/n]:y
Ok, creating new management key pair. Creating DH parameter may take
around 20 minutes. Please wait
Management key created at keystore
Management dh param file created at /opt/pingidentity/ase/config/certs/
management/dh1024.pem
```

2. Create a CSR. ASE takes you through a CLI-based interactive session to create a CSR.

```
/opt/pingidentity/ase/bin/cli.sh create_management_csr -u admin -p
Warning: create_management_csr will delete any existing management CSR and
self-signed certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >US
State >Colorado
Location >Denver
Organization >Pingidentity
Organization Unit >Pingintelligence
Common Name >management.ase
Generating CSR. Please wait...
OK, management csr created at /opt/pingidentity/ase/config/certs/
management/management.csr
```

3. Upload the CSR created in step 2 to the CA signing authority's website to get a CA signed certificate.
4. Download the CA-signed certificate from the CA signing authority's website.
5. Use the CLI to import the signed CA certificate into ASE. The certificate is imported into the `/opt/pingidentity/config/certs/management/management.csr` file

```
/opt/pingidentity/ase/bin/cli.sh import_management_cert <CA signed
certificate path> -u admin -p
Warning: import_management_cert will overwrite any existing management
signed certificate
Do you want to proceed [y/n]:y
Exporting management certificate to API Security Enforcer...
OK, signed certificate added to keystore
```

6. Restart ASE by first stopping and then starting ASE.

#### Method 2: Use self-signed certificate

A self-signed certificate is also supported for customer testing.

#### To create a self-signed certificate

1. Create a private key. ASE CLI is used to generate a 2048-bit private key which is in the `/ase/config/certs/` directory.

```
/opt/pingidentity/ase/bin/cli.sh create_management_key_pair -u admin -p
Warning: create_management_key_pair will delete any existing management
key_pair, CSR and self-signed certificate
Do you want to proceed [y/n]:y
Ok, creating new management key pair. Creating DH parameter may take
around 20 minutes. Please wait
Management key created at keystore
```

```
Management dh param file created at /opt/pingidentity/ase/config/certs/management/dh1024.pem
```

## 2. Create a CSR. Enter the following command.

```
/opt/pingidentity/ase/bin/cli.sh create_management_csr -u admin -p
password >
Warning: create_csr will delete any existing CSR and self signed
certificate
Do you want to proceed [y/n]:y
please provide following info
Country Code >US
State >colorado
Location >Denver
Organization >PingIdentity
Organization Unit >PI
Common Name >yoursiteabc.com

Generating CSR. Please wait...
OK, csr created at /opt/pingidentity/ase/config/certs/management/ase.csr
```

## 3. Create a self-signed certificate. Use the CLI to produce a self-signed certificate using the certificate request located in /pingidentity/ase/config/certs/management/ase.csr

```
/opt/pingidentity/ase/bin/cli.sh create_management_self_sign_cert -u admin
-p
Warning: create_management_self_sign_cert will delete any existing
management self-signed certificate
Do you want to proceed [y/n]:y
Creating new management self-signed certificate
OK, self-sign certificate created in key store
```

## 4. Restart ASE by stopping and starting.

### Method 3: Import an existing certificate and key pair

To install an existing certificate, complete the following steps and import it into ASE. If you have intermediate certificate from CA, then append the content to your server .crt file.

#### 1. Convert the key from the existing .pem file:

```
openssl rsa -in private.pem -out private.key
```

#### 2. Convert the existing .pem file to a .crt file:

```
openssl x509 -in server-cert.pem -out server-cert.crt
```

#### 3. Import key pair from step 2:

```
/opt/pingidentity/ase/bin/cli.sh import_management_key_pair private.key -u
admin -p
Warning: import_key_pair will overwrite any existing certificates
Do you want to proceed [y/n]:y
Exporting management key to API Security Enforcer...
OK, key pair added to keystore
```

#### 4. Import the .crt file in ASE using the **import\_management\_cert** CLI command

```
/opt/pingidentity/ase/bin/cli.sh import_management_cert server-cert.crt -u
admin -p
Warning: import_management_cert will overwrite any existing management
signed certificate
Do you want to proceed [y/n]:y
```

```
Exporting management certificate to API Security Enforcer...
OK, signed certificate added to keystore
```

5. Restart ASE by stopping and starting.

## Configure native and PAM authentication

ASE provides two types of authentication:


- Linux Pluggable Authentication Module (PAM)
- ASE native authentication (default method)

All actions carried out on ASE require an authenticated user.

The two methods to choose the authentication method include:

- Configure `auth_method` parameter in `ase.conf` (see ASE Initial Configuration)
- Execute a CLI command (`update_auth_method <method>`).

The sections below provide more details on configuring the desired method. The following diagram shows the transition between authentication modes. The authentication method can be changed during run-time without restarting ASE.



### ASE native authentication

By default, ASE uses native ASE authentication which ships with the system. Each user can execute CLI commands by including the shared “username” and “password” with each command. The system ships with a default username (`admin`) and password (`admin`). Always change the default password using the `update_password` command. For more information on ASE commands, see Appendix A.

To configure `ase.conf` to support native authentication, use the default configuration values:

```
auth_method=ase::db
```

To change the authentication from Native authentication to PAM mode, enter the following command in ASE command line. In the example, `login` is a PAM script used for authentication.

```
/opt/pingidentity/ase/bin/cli.sh update_auth_method pam::login -u admin -p
```

```
password>
```

To switch from PAM mode authentication back to Native authentication, issue the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh update_auth_method ase::db -u <pam_user> -p
password>
```

Here is an example of a CLI command with native authentication (-u,-p) enabled:

```
/opt/pingidentity/ase/bin/cli.sh add_server -u admin -p
password>
```

## Linux Pluggable Authentication Modules (PAM) authentication

PAM-based authentication provides the flexibility to authenticate administrators using existing authentication servers, such as your organization's LDAP directory. When PAM authentication is active, ASE logs the identity of the user executing each CLI command. This provides a user-specific audit trail of administrative access to the ASE system.

To activate PAM-based authentication, configure `auth_method` in `ase.conf` as `pam::<service>`, where `<service>` is the script that the PAM module reads to authenticate the users. Service scripts include `login`, `su`, `ldap`, etc. For example, `login` script allows all system users administrative access to ASE. To support PAM authentication with `login` script, update `auth_method` configuration values in `ase.conf`:

```
auth_method=pam::login
```

Here is an example using the CLI to change from Native to PAM authentication with `login` script:

```
/opt/pingidentity/ase/bin/cli.sh update_auth_method pam::login -u admin -p
password>
```

**Warning:** Make sure that the script name provided for PAM based authentication is the correct one. If a wrong file name is provided, ASE administrators are locked out of ASE.

To write your own PAM module script, add a custom script (for example `ldap`) which defines PAM's behavior for user authentication to the `/etc/pam.d` directory. To set the authentication method and use the `ldap` script, enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh update_auth_method pam::ldap -u admin -p
password>
```

Here is a snippet of a sample script:

```
root@localhost:/# cat /etc/pam.d/ldap
auth    sufficient    pam_ldap.so        # Authenticate with LDAP server.
#auth   sufficient    pam_permit.so     # Allow everyone. Pass-through mode.
#auth   sufficient    pam_deny.so       # Disallow everyone. Block all access.
```

In the above example, the PAM module uses the organization's LDAP server to authenticate users.

## Recovering ASE from unavailable `pam.d` script

When an invalid script name is entered while changing to PAM authentication, the PAM module defaults to `etc/pam.d/others` for authentication. This makes ASE inaccessible to administrators. If this happens, copy `etc/pam.d/login` to `etc/pam.d/other`. ASE will now use the credentials in `etc/pam.d/login` to authenticate administrators. After logging back into ASE, change the authentication method to

use the correct file name. Copying the contents of `etc/pam.d/login` to `etc/pam.d/other` does not need a restart of ASE or the host operating system.

## ASE management, access and audit logs

ASE generates two three of logs:

- **Access log** contains information about all API traffic
- **Management log** contains information about Controller and Balancer
- **Audit log** contains information about various commands executed in ASE

### Access logs

Access logs are generated for port 80 (default port) and 443 (default port) traffic. Each Balancer process has a corresponding Access log file (that is. two port 80 Balancer processes and two port 443 Balancer processes require four log files). The log file name format is `<protocol>_<port>_pid_<process-ID>_access_<date>.log`. Examples for port 80 and port 443 are:

- `http_ws_80_pid_19017__access__2018-01-22_13-10.log`
- `https_wss_443_pid_19018__access__2018-01-22_13-10.log`

Access logs are rotated every 10 minutes and archived. The archived log file format has `.gz` at the end of the log file name (for example `http_ws_80_pid_19017__access__2018-01-22_13-10.log.gz`).

ASE sends all archived log files to API Behavioral Security (ABS) to detect attacks using Machine Learning algorithms. The files are then moved to the `abs_uploaded` directory in the `logs` directory.

The following snippet shows an example log file:

```
-rw-r--r--. 1 root root 0 Aug 10 13:10
  http_ws_80_pid_0__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 0 Aug 10 13:10
  https_wss_443_pid_0__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 0 Aug 10 13:10
  http_ws_80_pid_19010__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 0 Aug 10 13:10
  http_ws_80_pid_19009__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 0 Aug 10 13:10
  https_wss_443_pid_19022__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 0 Aug 10 13:10
  https_wss_443_pid_19017__access__2018-01-22_13-10.log
-rw-r--r--. 1 root root 33223 Aug 10 13:11 balancer.log
-rw-r--r--. 1 root root 20445 Aug 10 13:11 controller.log
-rw-r--r--. 1 root root 33244 Aug 10 13:11 balancer_ssl.log
```

### Management logs

Management log detail levels (for example INFO, WARNING, DEBUG) are configured in `ase.conf`. Generated by controller and balancers, management logs are stored in the `logs` directory and include:

- Controller logs – `controller.log`
- Balancer log for port 80 (default port) – `balancer.log`
- Balancer log for port 443 – `balancer_ssl.log`

### Controller logs

`controller.log` is a log file with data from the CLI, REST API, configurations, IPC, SSL, cluster, and ABS. Rotated every 24 hours, `controller.log` is the current file name, older files are appended with a timestamp.

### Balancer logs

`balancer.log` for port 80 and `balancer_ssl.log` for port 443 are static files which are not rotated. These files contain information about IPC between controllers and balancer processes as well as IPC between balancer processes.

In a sideband ASE deployment, balancer checks for request-response parsing error at every 30-second. Parsing error statistics is logged in `balancer.log` file only if balancer encounters parsing errors. If there are no errors in a 30-second period, the `balancer.log` file does not show the JSON output. Following is a snippet of request-response parsing error statistics:

```
{
  "sideband stats": {
    "request parsing errors": {
      "total requests failed": 1,
      "request body absent": 0,
      "request body malformed": 0,
      "request source ip absent": 1,
      "request source ip invalid": 0,
      "request method absent": 0,
      "request url absent": 0,
      "request host header absent": 0,
      "request authentication failure": 0,
      "request error unknown": 0
    },
    "response parsing errors": {
      "total responses failed": 1,
      "response body absent": 0,
      "response body malformed": 0,
      "response code absent": 0,
      "response authentication failure": 0,
      "response correlation id not found": 1,
      "response error unknown": 0
    }
  }
}
```

The snippet shows that in-total there was one parsing error for request and one for the response. The statistics also lists the type of request and response error.

### Balancer log rotation

You can rotate the balancer log file by running the `rotate-logs` script available in the `util` directory of ASE. By default, ASE does not rotate the balancer log like controller logs. However, you can add the balancer log rotation script to a cron job. Once the balancer log is rotated, it is saved in `logs/backup` directory. A separate `.gz` file is created for `balancer.log` and `balancer_ssl.log` file. The balancer log rotation script also moves the rotated `controller.log` files to the backup directory.

The `rotate-logs` script takes `[ASE_ROOT_DIR]` as the only argument. `[ASE_ROOT_DIR]` is the absolute path of ASE root directory.

```
./rotate-logs.sh --help
name
  rotate-logs.sh

synopsis
  rotate-logs.sh [<ASE_ROOT_DIR> | help | --help]

description
  Rotates balancer logs and moves rotated controller/balancer logs to the
  backup directory.

arguments
```

```

<ASE_ROOT_DIR>
    absolute path of ASE root directory

help, --help
    show this help message

exit status
    0    for ok,
    1    for errors.

```

You can run the balancer log rotation script as a cron job. For example, the following command would run the cron job at mid-night. You can choose to run it at a different time.

```
0 0 * * * /opt/pingidentity/ase/util/rotate-logs.sh /opt/pingidentity/ase
```

## Audit logs

ASE logs administrator actions (for example CLI commands, configuration changes) and stores audit logs in the `opt/pingidentity/ase/logs` directory. Performed on a per ASE node basis, audit logging is enabled by default.

Use the CLI to enable or disable audit logging using the commands `enable_audit` and `disable_audit`. For example, to enable audit logs, enter the following at the command line:

```
/opt/pingidentity/ase/bin/cli.sh enable_audit -u admin -p password
```

The audit log captures information related to:

- System changes using CLI or REST API calls
- API JSON changes or `ase.conf` file updates
- SSL certificate updates

The logs are rotated every 24 hours with the current log file having no timestamp in its name. For more information, see [Audit log](#). The following is a snippet of audit log files:

```
-rw-r--r-- 1 root root 358 Aug 13 10:00 audit.log.2018-08-13_09-54
-rw-r--r-- 1 root root 301 Aug 13 10:12 audit.log.2018-08-13_10-00
-rw-r--r-- 1 root root 1677 Aug 13 11:16 audit.log.2018-08-13_10-12
-rw-r--r-- 1 root root 942 Aug 14 06:26 audit.log.2018-08-14_06-22
-rw-r--r-- 1 root root 541 Aug 15 08:19 audit.log
```

## Change management log levels

The management log (`balancer.log` and `controller.log`) levels are initially configured in `ase.conf` file by setting `log_level` to one of the following five values. The default value is `INFO`:

- FATAL
- ERROR
- WARNING
- INFO
- DEBUG

You can change the log level of management logs during run-time by using the `log_level` command. The `log_level` command works in an identical way for both sideband and inline ASE modes. In an ASE cluster set up, run the `log_level` command on all the ASE nodes. The change in log-level is also recorded in Audit logs. Following is an example CLI output of the `log_level` command to change the log-level to `warn`. The other values for the command are `info`, `error`, `fatal`, and `debug`.

```
#!/bin/cli.sh -u admin -p admin log_level warn
```



You can also verify the current log level by using the ASE `status` command.

```

#./bin/cli.sh -u admin -p status
API Security Enforcer
status           : started
mode             : inline
http/ws          : port 8080
https/wss        : port 8443
firewall         : enabled
abs              : disabled, ssl: enabled
abs attack       : disabled
audit            : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
log level       : warn
timezone         : local (MST)

```

## Purge log files

To manage storage space, you can either archive or purge access log, controller log, and audit log files that have been uploaded to ABS. ASE provides a `purge.sh` script to remove access log files from the `abs_uploaded` directory. The `purge` script is part of the `/opt/pingidentity/ase/util` directory.

**Warning:** When the purge script is run, the access log files are permanently deleted from ASE.

To run the purge script, enter the following in ASE command line:

```

/opt/pingidentity/ase/util/purge.sh -d 3
In the above example, purge.sh deletes all the access log files which are
older than 3 days. Here is a sample output for the purge script.
admin@pingidentity# ./util/purge.sh -d 3
This will delete logs in /opt/pingidentity/ase/logs/abs_uploaded that is
older than 3 days.
Are you sure (yes/no): yes
removing /opt/pingidentity/ase/logs/abs_uploaded/
Processed decoy_pid_27889__2017-04-01_11-04.log.gz : last changed at Sat Apr
 1 11:11:01 IST 2017
removing /opt/pingidentity/ase/logs/abs_uploaded/
Processed http_ws_80_pid_27905__access__2017-04-01_11-04.log.gz : last
changed at Sat Apr 1 11:11:01 IST 2017

```

## External log archival

The `purge` script can also archive logs to secondary storage for future reference. The purge script provides an option to choose the number of days to archive the log files. Use the `-l` option and the path of the secondary storage to place the archived log files. For example:

```

admin@pingidentity# ./util/purge.sh -d 3 -l /tmp/

```

In the above example, log files older than three days are archived to the `tmp` directory. To automate log archival, add the script to a cron job.

## Configure syslog

Syslog messages are a standard for sending event notification messages. These messages can be stored locally or on an external syslog server. ASE generates and sends syslog messages to an external syslog server over UDP. All the syslog messages sent belong to the informational category.

## Configuring syslog server

Configure the IP address or hostname and port number of the syslog server in the `ase.conf` file to send syslog messages to the external server. To stop generating syslog messages, remove the syslog server definition from the `ase.conf` file, stop and then start ASE. Here is a snippet from the `ase.conf` file:

```
; Syslog server settings. The valid format is host:port. Host can be an FQDN
  or an IPv4
address.
syslog_server=
```

## Listing syslog server

Show the configured syslog server by executing the `list_sys_log_server` command:

```
/opt/pingidentity/bin/cli.sh list_syslog_server -u admin -p
192.168.11.108:514, messages sent: 4, bytes sent: 565
```

Here is a sample message sent to the syslog server:

```
Aug 16 06:16:49 myhost ase_audit[11944] origin: cli, resource: add_api,
  info: config_file_path=/opt/pingidentity/ase/api.json, username=admin
Aug 16 06:16:56 myhost ase_audit[11944] origin: cli, resource: list_api,
  info: username=admin
```

## Email alerts and reports

ASE sends email notifications under two categories:

- **Alerts** – alerts are event based.
- **Reports** – sent at a configured frequency (`email_report`) from one to seven days.

In a cluster deployment, configure the e-mail on the first ASE node. In case the first ASE node is not available, the ASE node with the next highest up-time takes over the task of sending e-mail alerts and daily reports. For more information on ASE cluster, see [Administering an ASE cluster](#) on page 131.

```
; Defines report frequency in days [0=no reports, 1=every day, 2=once in two
  days and max is 7 ; days]
email_report=1
; Specify your email settings
smtp_host=smtp://<smtp-server>
smtp_port=587
; Set this value to true if smtp host support SSL
smtp_ssl=true
; Set this value to true if SSL certificate verification is required
smtp_cert_verification=false
sender_email=
sender_password=
receiver_email=

; Defines threshold for an email alert. For example, if CPU usage is 70%,
  you will get an
; alert.
cpu_usage=70
memory_usage=70
filesystem_size=70
```

### Email alerts

Email alerts are sent based on the following event categories:

- **System resource** – System resources are polled every 30 minutes to calculate usage. An email alert is sent if the value exceeds the defined threshold. The following system resources are monitored:
  - CPU: average CPU usage for a 30-minute interval
  - Memory: memory usage at the 30th minute
  - Filesystem: filesystem usage at the 30th minute
- **Configuration** – When configuration changes occur, an email alert is sent for these events:
  - Adding or removing an API
  - Adding or deleting a server
  - Nodes of a cluster are UP or DOWN
- **Decoy API** – When decoy APIs are accessed for the first time, an email alert is sent. The time between consecutive alerts is set using `decoy_alert_interval` in `ase.conf`. The default value is 180 minutes. For more information on decoy APIs, see [In-Context decoy APIs](#).
- **ASE-ABS log transfer and communication** – ASE sends an alert in the following two conditions:
  - **Access Log transfer failure** - When ASE is not able to send access log files to ABS for more than an hour, ASE sends an alert with the names of the log files.
  - **ASE-ABS communication failure** – When interruptions occur in ASE-ABS communication, an alert is sent identifying the error type. The email also mentions the current and total counter for the alert. The **current** counter lists the number of times that failure happened in last one hour. The **total** counter lists the total number of times that error has occurred since ASE was started.
    - ABS seed node resolve
    - ABS authentication
    - ABS config post
    - ABS cluster INFO
    - ABS service unavailable
    - Log upload
    - Duplicate log upload
    - Log file read
    - ABS node queue full
    - ABS node capacity low
    - ABS attack type fetch

Following is a template for alerts:

```
Event: <the type of event>
Value: <the specific trigger for the event>
When: <the date and time of the event>
Where: <the IP address or hostname of the server where the event occurred>
```

For example,

```
Event : high memory usage
Value : 82.19%
When : 2019-May-16 18:30:00 PST
Where : vortex-132
```

**Alerts logged in log file:** Following is a list of all the alerts that are logged in `controller.log` file when email alerts are disabled (`enable_email=false`) in `ase.conf` file.

- High CPU use
- High memory use
- High filesystem use
- Adding API to ASE

- Removing API from ASE
- Updating and API
- Adding a backend server
- Removing a backend server
- ASE cluster node available
- ASE cluster node unavailable
- Backend server state changed to UP
- Backend server state changed to DOWN
- Log upload service failure
- Error while uploading file
- Invalid ASE license file
- Expired ASE license file

## Email reports

### Email reports

ASE sends reports at a frequency in number of days configured in `ase.conf` file. The report is sent at midnight, 00:00:00 hours based on the local system time. The report contains the following:

- Cluster name and location
- Status information on each cluster node
  - Operating system, IP address, management port, and cluster port
  - Ports and the number of processes (PIDs)
  - Average CPU, memory utilization – average during 30-minute polling intervals
  - Disk usage and log size
- Information on each API: Name, Protocol, and Server Pool

Following is a template of weekly or daily email report:

```
Date: Sat, 29 Jun 2019 04:01:47 -0800 (PST)
To: receiver@example.com
From: sender@example.com
Subject: API Security Enforcer Daily Reports

Dear DevOps,
Please find the daily report generated by ase2 at 2019-Jun-29 00:01:01 UTC.
===== Cluster Details =====
Cluster Name: pi_cluster
Active Nodes: 2
Inactive nodes: 0
No of APIs: 7
ISM State: disabled
Manual IOC: 0
Automated IOC: 0

===== Node 1 =====
Host Name: apx1
Management Port: 8010
Cluster Port: 8020
Status: Active
Up Since: 2019-Jan-26 09:27:26
Operating System: Ubuntu 14.04.4 LTS
CPU Usage: 55.80%
Memory Usage: 38.17%
Filesystem Usage: 17.20%
Log Size: 20 GB

===== Node 2 =====
```

```

Host Name : apx2
Management Port: 8010
Cluster Port: 8020
Status: Active
Up Since: 2019-Jan-26 09:26:35
Operating System: Ubuntu 14.04.4 LTS
CPU Usage: 55.79%
Memory Usage: 38.17%
Filesystem Usage: 17.20%
Log Size: 20 GB
=====

===== API Details =====
API ID: https-app
Status: loaded
Protocol: https
decoy: in-context
Active Servers: 172.17.0.8:2800 172.17.0.7:2700
Inactive Servers:
=====

API ID: http-app
Status: loaded
Protocol: http
decoy: in-context
Active Servers: 172.17.0.7:2100 172.17.0.8:2300 172.17.0.7:2700
Inactive Servers:
=====

Best,
API Security Enforcer

```

**Decoy API access reports:** ASE sends decoy API access report at a 3-hour interval by default. You can configure this time interval in minutes in `ase.conf` file by configuring `decoy_alert_interval` variable. ASE sends the report only if the decoy API is accessed during the configured time interval. The report provides the following details:

- The start time when the decoy API was first accessed and the end time when it was last accessed
- The ASE cluster name
- The total number of requests for decoy API in the ASE cluster
- The host name of the ASE where the decoy API was accessed

Following is a sample email template for decoy API:

```

Date: Sat, 29 Jun 2019 04:01:47 -0800 (PST)
To: receiver@example.com
From: sender@example.com
Subject: API Security Enforcer Decoy Access Reports

Dear DevOps,
Please find the decoy report generated by ase2 at 2019-Jun-29 12:01:45 UTC.
The default location for the decoy log files is in the directory: /opt/
pingidentity/ase/logs/
===== Decoy Summary =====
Cluster Name: pi_cluster
Start Time: 2019-Jun-29 09:00:00
End Time: 2019-Jun-29 12:00:00
Total Requests: 875

===== Node 1 =====
Host Name: ase2
Total Requests: 428

===== Node 1 =====

```

```
Host Name: ase
Total Requests: 447
```

```
Best,
API Security Enforcer
```

### ASE alerts resolution

The following table describes the various email alerts sent by ASE and their possible resolution. The resolution provided is only a starting point to understand the cause of the alert. If ASE is reporting an alert even after the following the resolution provided, contact PingIntelligence support.

Email alert	Possible cause and resolution
ASE start or restart email	When ASE starts or restarts, it sends an email to the configured email ID. If email from ASE is not received, check the email settings in <code>ase.conf</code> file.
high CPU usage	<p><b>Cause:</b> Each ASE node polls for CPU usage of the system every 30-minutes. If the average CPU usage in the 30-minutes interval is higher than the configured threshold in <code>ase.conf</code>, then ASE sends an alert.</p> <p><b>Resolution:</b> If ASE is reporting a high CPU usage, check if other processes are running on the machine on which ASE is installed. If ASE controller or balancer processes are consuming high CPU, it may mean that ASE is receiving high traffic. You should consider adding more ASE nodes.</p>
high memory usage	<p><b>Cause:</b> Each ASE node polls for memory usage of the system every 30-minutes. If the average memory usage in the 30-minutes interval is higher than the configured threshold <code>ase.conf</code>, then ASE sends an alert.</p> <p><b>Resolution:</b> If ASE is reporting a high memory usage, check if any other process is consuming memory of the system on which ASE is installed. Kill any unnecessary process other than ASE's process.</p>
high filesystem usage	<p><b>Cause:</b> Each ASE node polls for filesystem usage of the system every 30-minutes. If the average filesystem usage in the 30-minutes interval is higher than the configured threshold <code>ase.conf</code>, then ASE sends an alert.</p> <p><b>Resolution:</b> If ASE is reporting a high filesystem usage, check if the filesystem is getting full. Run the purge script available in the <code>util</code> directory to clear the log files.</p>
API added	<p>ASE sends an email alert when an API is added to ASE using CLI or REST API.</p> <p><b>Confirm:</b> ASE admin should verify whether correct APIs were added manually or the APIs were added by AAD because of auto-discovery in ABS. If an API is accidentally added, you should immediately remove it from ASE.</p>
API removed	<p>ASE sends an email alert when an API is removed using CLI or REST API.</p> <p><b>Confirm:</b> ASE admin should verify whether the APIs were deleted intentionally or accidentally.</p>
API updated	<p>ASE sends an email alert when an API definition (the API JSON file) is updated by using CLI or REST API.</p> <p><b>Confirm:</b> ASE admin should verify whether the correct APIs was updated.</p>

Server added	ASE sends an email alert when a server is added to an API by using CLI or REST API. <b>Confirm:</b> ASE admin should verify whether the correct server was added to API.
Server removed	ASE sends an email alert when a server is removed from an API by using CLI or REST API. <b>Confirm:</b> ASE admin should verify whether the correct server was removed from an API.
cluster node up	ASE sends an email alert when a node joins an ASE cluster. <b>Confirm:</b> ASE admin should verify whether the correct ASE node joined the ASE cluster.
cluster node down	ASE sends an email alert when a node is removed from an ASE cluster. <b>Confirm:</b> ASE admin should check the reason for removal of ASE node from the cluster. ASE node could disconnect from cluster because of network issues, a manual stop of ASE, or change in IP address of the ASE machine.
server state changed to Up	ASE sends an email alert when the backend API server changes state from inactive to active. This alert is applicable for Inline ASE when health check is enabled for an API. This is an informative alert.
server changed to Down	ASE sends an email alert when the backend API server changes state from active to inactive. This alert is applicable for Inline ASE when health check is enabled for an API. <b>Resolution:</b> ASE admin should investigate the reason for the backend API server being not reachable from ASE. You can run the ASE <code>health_status</code> command to check the error which caused the server to become inactive.
decoy API accessed	ASE sends an email alert when a decoy API is accessed. This is an informative alert.

### Alerts for uploading access log files to ABS

ASE sends one or more alerts when it is not able to send access log files to ABS. The following table lists the alerts and possible resolution for the alerts.

Email alert	Possible cause and resolution
Network error	<p><b>Cause:</b> ABS IP may not be reachable or ASE is not able to connect ABS IP and port.</p> <p><b>Resolution:</b></p> <ul style="list-style-type: none"> <li>▪ If there is a firewall in the deployment, check whether firewall is blocking access to ABS.</li> <li>▪ Check whether ABS is running.</li> <li>▪ Check whether correct IP address is provided in the <code>abs.conf</code> file.</li> </ul>


ABS seed node resolve error	<b>Cause:</b> The hostname provided in <code>abs.conf</code> could not be resolved. <b>Resolution:</b> Check whether correct IP address is provided in <code>abs.conf</code> file.
ABS SSL handshake error	<b>Cause:</b> SSL handshake error could be because of an invalid CA certificate. <b>Resolution:</b> Check whether a valid CA certificate is configured in ASE.
ABS authentication error	<b>Cause:</b> Authentication error could be because of invalid access and secret key. <b>Resolution:</b> Confirm the access key and secret key configured is the same that is configured in ABS <code>abs.properties</code> file.
ABS cluster info error	<b>Cause:</b> Error while fetching ABS cluster information. <b>Resolution:</b> Check the <code>controller.log</code> file.
ABS config post error	<b>Cause:</b> Error while sending API JSON definition to ABS <b>Resolution:</b> Check the <code>controller.log</code> file.
ABS service unavailable error	<b>Cause:</b> ABS returning 503 response code. <b>Resolution:</b> Check the <code>abs.log</code> file.
Log upload error	<b>Cause:</b> API call to upload access log files to ABS fails. <b>Resolution:</b> Check both ASE's <code>controller.log</code> and ABS <code>abs.log</code> file.
Duplicate log upload error	This is an informative message.
ABS node queue full error	<b>Cause:</b> ABS responds with a message that it's queue is full. This can be because of increased traffic on ASE and large number of access log files being generated. <b>Resolution:</b> Increase the number of ABS nodes.
ABS node capacity low error	<b>Cause:</b> ABS resources are utilized to a maximum. <b>Resolution:</b> Increase the number of ABS nodes.
ABS attack get error	<b>Cause:</b> Error while fetching attack list from ABS <b>Resolution:</b> Check ASE's <code>controller.log</code> file.

## Sideband ASE

---

When deployed in sideband mode ASE receives API calls from an API gateway which passes API traffic information for AI processing. In such a deployment, ASE works along with the API gateway to protect your API environment. The following diagram shows a typical ASE sideband deployment:





The following is a description of the traffic flow through the API gateway and Ping Identity ASE.

1. Incoming request to API gateway
2. API gateway makes an API call to send the request metadata in JSON format to ASE
3. ASE checks the request against a registered set of APIs and checks the origin IP against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the API gateway. Otherwise, a different response code is sent to the Gateway. The request is also logged by ASE and sent to the AI Engine for processing.
4. If the API gateway receives a 200-OK response from ASE, then it forwards the request to the backend server. If it receives a 403, the Gateway does not forward the request to the backend server and returns a different response code to the client.
5. The response from the backend server is received by the API gateway.
6. The API gateway makes a second API call to pass the metadata information to ASE which sends the information to the AI engine for processing.
7. ASE receives the metadata information and sends a 200-OK to the API gateway.
8. API gateway sends the response received from the backend server to the client.

**Note:** Make sure that XFF is enabled in the API gateway for ASE to detect the client IP addresses correctly.

## Configuring ASE for sideband

To configure ASE to work in the sideband mode, edit the `ase.conf` file located in the `config` directory. Set the value of the mode parameter to `sideband`. The default value of the mode parameter is `inline`. Following is a snippet of the `ase.conf` file with the mode parameter set to `sideband`.

```
; Defines running mode for API Security Enforcer.
mode=sideband
```

### Enable sideband authentication

To have a secure the connection between your API gateway and ASE, enable sideband authentication in ASE and generate a sideband token. This token is configured in the API gateway for it to communicate securely with ASE.

```
/opt/pingidentity/ase/bin/cli.sh enable_sideband_authentication -u admin -p
admin
Sideband authentication is successfully enabled
```


**Generate sideband token:** Enter the following command to generate ASE sideband token:

```
/opt/pingidentity/ase/bin/cli.sh create_sideband_token -u admin -p admin
Sideband token d9b7203c97844434bd1ef9466829e019 created.
```

## Sideband ASE configuration - ase.conf

ASE system level configuration entails modifying parameters in the `ase.conf` file located in the `config` directory. Some values have default settings which can be modified to support application requirements. The parameter values and descriptions are included in the following table:

Parameter	Description
<b>ASE mode</b>	
mode	Change the mode to <code>sideband</code> for ASE to work in a sideband mode. The default value is <code>inline</code> .
<b>ASE timezone</b>	
timezone	Sets ASE's timezone. The values can be <code>local</code> or <code>UTC</code> . Default value is <code>UTC</code> . If ASE is deployed in a cluster, configure the same timezone on each cluster node manually.
enable_sideband_keepalive	When set to <code>true</code> , ASE sends a keep-alive in response header for the TCP connection between API gateway and ASE. With the default <code>false</code> value, ASE sends a connection close in response header for connection between API gateway and ASE.
enable_sideband_authentication	<p><b>Note:</b> This parameter is applicable only when mode is set to <code>sideband</code>.</p> <p>This parameter only applies in the ASE sideband mode. Set it to <code>true</code> to enable authentication between in client, for example, an API gateway and ASE. After setting it to <code>true</code>, generate a sideband authentication token using ASE <code>create_sideband_token</code> command.</p>
<b>ASE ports</b>	

http_ws_port	Data port used for http or WebSocket protocol. The default value is 80.
https_wss_port	Data port used for https or Secure WebSocket (wss). The default value is 443.
management_port	Management port used for CLI and REST API management. The default value is 8010.
<b>ASE administration and audit</b>	
admin_log_level	The level of log detail captured. Options include: Fatal – 1, Error – 2, Warning – 3, Info – 4, Debug – 5
enable_audit	When set to true, ASE logs all actions performed in ASE in the audit log files. The default value is true.
syslog_server	Syslog server hostname or IPv4 address:port number. Leave this parameter blank for no syslog generation.
hostname_refresh	N/A
auth_method	Authentication method used for administrator access. See <a href="#">Configuring Native and PAM Authentication</a> for more information on the two options <ul style="list-style-type: none"> <li>▪ ase::db (Default - Native authentication)</li> <li>▪ pam::ldap (Linux-PAM authentication with script)</li> </ul>
ase_health	When true, enables load balancers to perform a health check using the following URL: "http(s)://<ASE Name>/ase" where <ASE Name> is the ASE domain name The default value is false.
<p> <b>Note:</b> Do not configure the /ase URL in an API JSON file.</p>	
enable_1G	N/A
http_ws_process	The number of HTTP processes. It is set to 1. Do not change this value.
https_wss_process	The number of HTTPS or processes. It is set to 1. Do not change this value.
enable_access_log	When true, log client traffic request and response information. Default value is true.
flush_log_immediate	When true, log files are immediately written to the file system. When false, log files are written after a time interval. The default value is true.
attack_list_memory	The amount of memory used for maintaining black and whitelists. The default value is 128 MB.
keystore_password	Password for the keystore. For more information on updating the keystore password, see <a href="#">Updating Keystore Password</a> .

enable\_hostname\_rewrite

NA

**ASE cluster**

enable\_cluster

When `true`, run setup in cluster mode.The default value is `false`, run in standalone mode.**Security**

enable\_sslv3

When `true`, enable SSLv3. Default value is `false`.

server\_ca\_cert\_path

N/A

enable\_xff

N/A

enable\_firewall

When `true`, activates the ASE firewall.The default value is `true`.**Real-time API security**

enable\_ase\_detected\_attack

When `true`, activates the real-time security in ASE.The default value is `false`.**API deception**

decoy\_alert\_interval

The time interval between decoy API email alerts.

The default value is 180 minutes.

Maximum value is 1440 minutes (i.e. 24 hours).

**AI-based API security (ABS)**

enable\_abs

When `true`, send access log files to ABS AI Engine for generating API metrics and detecting attacks using machine learning algorithms. Make sure it is set to `true` when ASE is connected to PingOne.

enable\_abs\_attack

When `true`, ASE fetches attack list from ABS AI Engine and blocks access by clients in the attack list.

When `false`, attack list is not downloaded.

abs\_attack\_request\_minute

Time interval in minutes at which ASE fetches ABS attack list. The default value is 10 minutes.

**Google Pub/Sub configuration**

enable\_google\_pubsub

Set it to `true` if you want ASE to push metrics data to Google cloud. The default value is `false`.

**Note:** ASE must be in the `sideband` mode for Google Pub/Sub configuration to take effect.


google\_pubsub\_topic

The path to your topic for publishing and subscribing the messages. For example, `/pingidentity/topic/your_topic`, for example, `/viatests/topics/ping_incoming`.

google\_pubsub\_concurrency

The number of concurrent connection between ASE and Google Pub/Sub. The maximum value is 1024 connections. Default value is 1000 connections.

google_pubsub_qps	The number of messages per second that ASE can publish to the topic. Maximum value is 10,000. The default value is 1000.
google_pubsub_apikey	The API Key to establish connection between ASE and Google Pub/Sub. Configuring API Key for Google Pub/Sub is optional.
cache_queue_size	The number of messages that are buffered in cache when ASE is not able to publish to Google Pub/Sub. Maximum size of the queue is 10,000 messages. The default value is 300 messages.
google_pubsub_timeout	The time in seconds for which ASE tries to publish messages to Google Pub/Sub. In case of failure to publish, ASE makes three attempts to publish the message, after which it writes the message to the <code>google_pubsub_failed.log</code> file.
<b>Alerts and reports</b>	
enable_email	When <code>true</code> , send email notifications. See <a href="#">Email alerts and reports</a> on page 154 for more information. The default value is <code>false</code> .
email_report	Time interval in days at which ASE sends reports. Minimum value is one day and the maximum is seven days.  The default value is 1.
smtp_host	Hostname of SMTP server.
smtp_port	Port number of SMTP server.
smtp_ssl	Set to <code>true</code> if you want email communication to be over SSL. Make sure that the SMTP server supports SSL. If you set <code>smtp_ssl</code> to <code>true</code> and the SMTP server does not support SSL, email communication falls back to non-SSL channel. The default value is <code>true</code> .  Set it to <code>false</code> if email communication is over a non-SSL channel. The email communication will fail if you set the parameter to <code>false</code> , but the SMTP server only supports SSL communication.
smtp_cert_verification	Set to <code>true</code> if you want ASE to verify the SMTP server's SSL certificate. The default value is <code>true</code> .  If you set it to <code>false</code> , ASE does not verify SMTP server's SSL certificate; however, the communication is still over SSL.
<div style="border: 1px solid black; padding: 10px;"> <p><b>Note:</b> If you have configured an IP address as <code>smtp_host</code> and set <code>smtp_cert_verification</code> to <code>true</code>, then make sure that the certificate configured on the SMTP server has the following:</p> <pre style="margin-left: 20px;">X509v3 extensions:     X509v3 Key Usage:         Key Encipherment, Data Encipherment     X509v3 Extended Key Usage:         TLS Web Server Authentication     X509v3 Subject Alternative Name:         IP Address: X.X.X.X</pre> </div>	
sender_email	Email address for sending email alerts and reports.

sender_password	<p>Password of sender's email account.</p> <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b> You can leave this field blank if your SMTP server does not require authentication.</p> </div>
receiver_email	<p>Email address to notify about alerts and reports</p> <p>See <a href="#">email alerts</a> for more information.</p>
<b>ASE server resource utilization</b>	
cpu_usage	<p>Percentage threshold value of CPU utilization.</p> <p>See <a href="#">email alerts</a> for more information.</p>
memory_usage	<p>Percentage threshold value of memory usage.</p> <p><a href="#">email alerts</a> alerts for more information.</p>
filesystem_size	<p>Percentage threshold value of filesystem capacity.</p> <p>See <a href="#">email alerts</a> for more information.</p>
buffer_size	<p>Customizable payload buffer size to reduce the number of iterations required for reading and writing payloads.</p> <p>Default value is 16KB. Minimum is 1KB and maximum is 32KB.</p>

A sample `ase.conf` file is displayed below:

```
; This is API Security Enforcer's main configuration file. This file is in
the standard .ini format.
; It contains ports, firewall, log, ABS flags. The comments start with a
semicolon (;).

; Defines running mode for API Security Enforcer (Allowed values are inline
or sideband).
mode=inline

; Defines http(s)/websocket(s) ports for API Security Enforcer. Linux user
should have the privilege to bind to these ports.
; If you comment out a port, then that protocol is disabled.
http_ws_port=8000
https_wss_port=8443

; REST API
management_port=8010

; For controller.log and balancer.log only
; 1-5 (FATAL, ERROR, WARNING, INFO, DEBUG)
admin_log_level=4

; Defines the number of processes for a protocol.
; The maximum number of allowed process for each protocol is 6 (1 master + 5
child). The
; following defines 1 process for both http/ws and https/wss protocol.
http_ws_process=1
https_wss_process=1

; Enable or disable access logs to the filesystem (request/response).
; WARNING! It must be set to true for sending logs to ABS for analytics.
```

```

enable_access_log=true
; To write access log immediately to the filesystem, set to true.
flush_log_immediate=true

; Setting this value to true will enable this node to participate in an API
  Security Enforcer
; cluster. Define cluster configurations in the cluster.conf
enable_cluster=false

; Current API Security Enforcer version has 3 firewall features: API
  Mapping, API Pattern
; Enforcement, and Attack Types.
enable_firewall=true

; X-Forwarded For
enable_xff=false

; SSLv3
enable_sslv3=false

; enable Nagle's algorithm (if NIC card is 1G).
enable_1G=true

; tcp send buffer size in bytes(kernel)
tcp_send_buffer_size=65535
; tcp receive buffer size in bytes(kernel)
tcp_receive_buffer_size=65535

; buffer size for send and receive in KBs (user)
buffer_size=16KB

; Set this value to true, to allow API Security Enforcer to send logs to
  ABS. This
; configuration depends on the value of the enable_access_log parameter.
enable_abs=true

; Set this value to true, to allow API Security Enforcer to fetch attack
  list from ABS.
enable_abs_attack=true

; This value determines how often API Security Enforcer will get attack list
  from ABS.
abs_attack_request_minutes=10

; Set this value to true, to allow API Security Enforcer to fetch published
  API list from ABS.
enable_abs_publish=false

; This value determines how often API Security Enforcer will get published
  API list from ABS.
abs_publish_request_minutes=10

; Set this value to true, to allow API Security Enforcer to block auto
  detected attacks.
enable_ase_detected_attack=false

; Set this value to true to enable email for both alerts and daily reports.
enable_email=false

; Defines report frequency in days [0=no reports, 1=every day, 2=once in two
  days and max is 7 ; days]
email_report=1
; Specify your email settings
smtp_host=smtp://<smtp-server>

```

```

smtp_port=587
; Set this value to true if smtp host support SSL
smtp_ssl=true
; Set this value to true if SSL certificate verification is required
smtp_cert_verification=false
sender_email=
sender_password=
receiver_email=

; Defines threshold for an email alert. For example, if CPU usage is 70%,
you will get an
; alert.
cpu_usage=70
memory_usage=70
filesystem_size=70

; Authentication method. Format is <auth_agent>::<auth_service>
; Valid values for auth_agent are ase and pam
; ase agent only supports db auth_service
; pam agent can support user configured pam services
; For example ase::db, pam::passwd, pam::ldap etc
auth_method=ase::db

; Enable auditing. Valid values are true or false.
enable_audit=true

; Decoy alert interval in minutes. [min=15, default=3*60, max=24*60]
decoy_alert_interval=180

; Interval for a hostname lookup (in seconds). [min=10, default=60,
max=86400]
hostname_refresh=60

; Syslog server settings. The valid format is host:port. Host can be an FQDN
or an IPv4
; address.
syslog_server=

; Attack List size in MB or GB. [min=64MB, max=1024GB]
; ASE will take 3*(configured memory) internally. Make sure that the system
has at least
; 3*(configured memory) available
; If you are running ASE inside a container, configure the container to use
3*(configured
; memory) shared memory.
attack_list_memory=128MB

; Enable or Disable health check module. ASE uses '/ase' url for both http
and https. This is
; useful if ASE is deployed behind a load balancer.
enable_ase_health=false

; Location for server's trusted CA certificates. If empty, Server's
certificate will not be
; verified.
server_ca_cert_path=

; enable client side authentication. This setting is applicable only in
sideband mode. Once enabled
; request will be authenticated using authentication tokens.
enable_sideband_authentication=false

; enable connection keepalive for requests from gateway to ase.
; This setting is applicable only in sideband mode.

```



```

; Once enabled ase will add 'Connection: keep-alive' header in response
; Once disabled ase will add 'Connection: close' header in response
enable_sideband_keepalive=false

; keystore password
keystore_password=OBF:AES:sRNp0W7sSilzrReXeHodKQ:lXcvbBhKZgDTrjQOfOkzR2mpca4bTUcwPAuerM

; enable hostname rewrite for inline mode. ASE will rewrite the host header
; in request
; to the server's hostname
enable_hostname_rewrite=false

; enable strict parsing checks for client requests
; If enabled, ASE will block request with invalid header start
; If disabled, it will allow requests
; default value = true
enable_strict_request_parser=true

; Set the timezone to utc or local. The default timezone is utc.
timezone=utc

; Google Pub Sub Configuration
enable_google_pubsub=false

google_pubsub_topic=/topic/apimetrics

; Number of concurrent connections to Google Pub/Sub
; Minimum: 1, Default: 1000, Maximum: 1024
google_pubsub_concurrency=1000

; Number of messages published per second.
; Minimum: 1, Default: 1000, Maximum: 10000
google_pubsub_qps=1000

; Google service account API key (Optional)
google_pubsub_apikey=

; Maximum number of messages buffered in memory
; If queue is full, messages are written to logs/google_pubsub_failed.log
; Minimum: 1, Default: 300, Maximum: 10000
cache_queue_size=300

; Timeout in seconds to publish a message to Google Pub/Sub.
; Minimum: 10, Default: 30, Maximum: 300
google_pubsub_timeout=30

```

## API naming guidelines

The API name must follow the following guidelines:

- The name should not have the word “model”.
- The name should not have the word “threshold”.
- The name should not have the word “all”.
- The name should not have the word “decoyall”.

Following is the list of allowed characters in API name:

- The maximum characters in API name can be 160
- - (hyphen), \_ (underscore), and white space are allowed in the name

- a-z, A-Z, and 0-9
- The first character must be alphanumeric

## Defining an API using API JSON configuration file in sideband mode

To secure your API environment using sideband ASE deployment, APIs need to be configured in ASE using an API JSON file. Each API has a unique API JSON file. ASE ships with sample JSON files located in the `/config/api` directory. You can manually configure the JSON file with the required parameters as shown in the next section.

The API JSON file parameters define the behavior and properties of your API. The sample API JSON files shipped with ASE can be changed to your environment settings and are populated with default values.

The following table describes the JSON file parameters:

Parameter	Description
protocol	API request type with supported values of: <code>http</code> - HTTP
url	The value of the URL for the managed API. You can configure up to 10 levels of sub-paths when ASE is deployed in sideband mode. For example, <code>"/shopping"</code> - name of a 1 level API <code>"/shopping/electronics/phones/brand"</code> - 4 level API <code>"/</code> - entire server (used for ABS API Discovery or load balancing)
hostname	Hostname for the API. The value cannot be empty. <code>"*"</code> matches any hostname.
<b>Configure the client identifiers (for example, cookie, API key, OAuth2 token) used by the API</b>	
cookie	Name of cookie used by the backend servers.
cookie_idle_timeout	N/A
logout_api_enabled	
cookie_persistence_enabled	
oauth2_access_token	When <code>true</code> , ASE captures OAuth2 Access Tokens. When <code>false</code> , ASE does not look for OAuth2 Tokens. Default value is <code>false</code> . For more information, see <a href="#">Configuring OAuth2 Token</a> .
apikey_qs	When API key is sent in the query string, ASE uses the specified parameter name to capture the API key value. For more information, see <a href="#">Configuring API keys</a> .

apikey_header	When API key is part of the header field, ASE uses the specified parameter name to capture the API key value.  For more information, see <a href="#">Configuring API keys</a> .
login_url	Public URL used by a client to connect to the application.
enable_blocking	When <code>true</code> , ASE blocks all types of attack on this API. When <code>false</code> , no attacks are blocked.  Default value is <code>false</code> .
api_mapping	N/A
<b>API pattern enforcement</b>	N/A
protocol_allowed	
http_redirect	
methods_allowed	
content_type_allowed	
error_code	
error_type	
error_message_body	
<b>Flow control</b>	N/A
client_spike_threshold	
client_connection_queuing	
api_memory_size	Maximum ASE memory allocation for an API.  The default value is 128 MB. The data unit can be MB or GB.
<b>Health check</b>	N/A
health_check_interval	
health_retry_count	
health_url	
server_ssl	N/A
<b>Servers:</b>	The IP address or hostname and port number of each backend server running the API.
host	
port	
server_spike_threshold	N/A
server_connection_quota	

**Decoy Config**

decoy\_enabled

response\_code

response\_def response\_message

decoy\_subpaths

When `decoy_enabled` is set to `true`, decoy sub-paths function as decoy APIs .

`response_code` is the status code (for example 200) that ASE returns when a decoy API path is accessed.

`response_def` is the response definition (for example OK) that ASE returns when a decoy API path is accessed.

`response_message` is the response message (for example OK) that ASE returns when a decoy API path is accessed.

`decoy_subpaths` is the list of decoy API sub-paths (for example `shop/admin`, `shop/root`)

See [Configuring API deception](#) for details.

username\_header

The name of the custom header containing username. When the value of `username_header` is set, ASE extracts the username from the custom header. For more information, see [Extract username from custom header in sideband mode](#) on page 182.

**Note:** You can configure Username capture from either `username_header` or JWT object, but not both.

**JWT**

location

username

clientid

When the parameter values of JWTobject are set, ASE decodes the JWT to extract the user information from the JWT object.

`location` is the place of occurrence of JWT in an API request. The supported values are:

- `qs:<key name>`
- `h:<custom header name>`
- `h:authorization:bearer`
- `h:authorization:mac`
- `h:cookie:<cookie key>`

`username` is the JWT claim to extract the username.

`clientid` is the JWT claim to extract the client-id.

For more information, see [Extract user information from JWT in sideband mode](#) on page 178.

**Note:**

**Note:** You can configure Username capture from either JWT object or `username_header`, but not both.

Here is a sample JSON file for a REST API:

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/rest",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    },
    "api_pattern_enforcement": {
      "protocol_allowed": "",
      "http_redirect": {
        "response_code": "",
        "response_def": "",
        "https_url": ""
      },
      "methods_allowed": [],
      "content_type_allowed": "",
      "error_code": "401",
      "error_def": "Unauthorized",
      "error_message_body": "401 Unauthorized"
    },
    "flow_control": {
      "client_spike_threshold": "0/second",
      "server_connection_queueing": false
    },
    "api_memory_size": "128mb",
    "health_check": false,
    "health_check_interval": 60,
    "health_retry_count": 4,
    "health_url": "/health",
    "health_check_headers": {},
    "server_ssl": false,
    "servers": [
      {
        "host": "127.0.0.1",
        "port": 8080,
        "server_spike_threshold": "0/second",
        "server_connection_quota": 0
      },
      {
        "host": "127.0.0.1",
        "port": 8081,
        "server_spike_threshold": "0/second",
        "server_connection_quota": 0
      }
    ],
    "decoy_config": {
      "decoy_enabled": false,
      "response_code": 200,
      "response_def": "",
      "response_message": ""
    }
  }
}
```

```

"decoy_subpaths": []
},
"username_header": "x-username-header",
"jwt": {
"location": "h:authorization:bearer",
"username": "username",
"clientid": "client_id"
}
}
}

```

**Note:** The sample JSON file has an extension of `.example`. If you are customizing the example file, then save the file as a `.json` file.

### Manually add API JSON to ASE

After configuring an API JSON file, add it to ASE to activate ASE processing. To add an API, execute the following CLI command:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_api {file_path/
api_name}

```

After configuring API JSON files for each API, ASE configuration is complete.

### Update a configured API JSON

After activation, an API JSON definition can be updated in real time. Edit the API JSON file located in the `/config/api` directory and make the desired changes. Save the edited API JSON file and execute the following CLI command:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin update_api <api_name>

```

For example,

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin update_api shop
api shop updated successfully

```

## Activate API cybersecurity

API Security Enforcer provides real-time API cybersecurity using the list of attacks generated by PingIntelligence AI engine. Real time API Cyber Security is activated only when ASE firewall is enabled.

### Enable API cybersecurity

To enable API security, enter the following command:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_firewall
Firewall is now enabled

```

After enabling API Security, enter the following CLI command to verify cybersecurity is enabled:

```

/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status : started
http/ws : port 80
https/wss : port 443
firewall : enabled
abs : disabled

```

```
abs attack : disabled
audit : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

### Disable API cybersecurity

To disable ASE's cybersecurity feature, type the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_firewall
Firewall is now disabled
```

After disabling ASE's cybersecurity feature, enter the following CLI command to verify that cybersecurity is disabled:

```
/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status : started
http/ws : port 80
https/wss : port 443
firewall : disabled
abs : disabled
abs attack : disabled
audit : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

### ASE attack detection

API Security Enforcer supports real time ASE attack detection and blocking for API Deception. ASE blocks hackers who probe a decoy API (see [API Deception Environment](#)) and later try to access a real business API.

#### Enable ASE detected attacks

Enable real-time ASE attack detection by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
enable_ase_detected_attack
```

ASE detected attack is now enabled

#### Disable ASE detected attacks

Disable real-time ASE detected attacks by running the following command on the ASE command line:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
disable_ase_detected_attack
ASE detected attack is now disabled
```

**Note:** When you disable ASE detected attacks, the attacks are deleted from the Blacklist.

### Capture client identifiers

ASE identifies attackers for HTTP(s) protocol using five client identifiers:

- Username
- API keys
- OAuth2 token

- Cookie
- IP address

**Note:** ASE supports the extraction of usernames coming in a JSON Web Tokens (JWTs) or custom headers. For more information, see [Extract user information from JWT in sideband mode](#) on page 178 and [Extract username from custom header in sideband mode](#) on page 182. ASE can also receive Usernames from a gateway policy, when ASE is deployed in a sideband mode. The PingIntelligence ABS AI engine identifies them based on metadata logged in ASE's access log files.

The following sections describe how to configure ASE to capture OAuth2 Tokens and API keys.

### Configure ASE support for OAuth2 tokens


ASE supports capturing and blocking of OAuth2 tokens. To enable OAuth2 token capture, set the value of `oauth2_access_token` to `true` in the API JSON file. Here is a snippet of an API JSON file with OAuth2 token capture activated. To disable, change the value to `false`.

```
"api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": true,
  "oauth2_access_token": true,
  "apikey_qs": "",
  "apikey_header": "",
  "login_url": "",
  "enable_blocking": true,
  "api_mapping": {
    "internal_url": ""
  }
},
```

When blocking is enabled, ASE checks the token against the list of tokens in the whitelist and blacklist. If the token is in the blacklist, the client using the token is immediately blocked.

The following diagram shows the traffic flow in an OAuth2 environment:





### Configure ASE support for API keys

ASE supports capturing and blocking of API keys. Depending on the API setup, the API key can be captured from the query string or API header. Each API JSON file can be configured with either the query string (`apikey_qs`) or API header (`apikey_header`) parameter.

Here is a snippet of an API JSON file showing API key being configured to capture the API key from the Query String (`apikey_qs`).

```
"api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": true,
  "oauth2_access_token": true,
  "apikey_qs": "key_1.4",
  "apikey_header": "",
  "login_url": "",
  "enable_blocking": true,
  "api_mapping": {
    "internal_url": ""
  }
},
```

When an API key is included in the API JSON file, ASE supports blocking of API keys which are manually added to the blacklist.





```

"enable_blocking": true,
"api_mapping": {
  "internal_url": ""
},
"username_header": "",

"jwt": {
  "location": "h:authorization:bearer",
  "username": "username",
  "clientid": "client_id"
}
}
}

```

**Note:** The values assigned to username and clientid cannot be same.

The following table explains the parameters in the JWT object of API JSON file.

Parameter	Description
location	<p>location is the place of occurrence of JWT in an API request. Configure the parameter with a value applicable to your API.</p> <p>The supported values for <b>location</b> parameter are:</p> <ul style="list-style-type: none"> <li> <b>qs:&lt;key name&gt;</b> - Set the location parameter with this value when JWT occurs as part of a query string and substitute the &lt;key name&gt; with the query string parameter. For example, "location": "qs: access_token" .           <pre>https://server.example.com/resource? access_token=mF_9.B5f-4.1JqM&amp;p=q</pre> </li> <li> <b>h:&lt;custom header name&gt;</b> - Set the location parameter with this value when JWT is part of a custom header and substitute the &lt;custom header name&gt; with custom header. For example, "location": "h:X-jwt-header".           <pre>X-jwt-header: eyJhbGcUzI1NiI.eyJzdkwIG4gRG9xpZWQiOjwMjJ9.DWw5PDZEl- g</pre> </li> <li> <b>h:Authorization:bearer</b> - Set the location parameter with this value when JWT is part of Authorization header, with bearer scheme. For example, "location": "h:Authorization:bearer".           <pre>Authorization: Bearer eyJhbGIUzIiI.eyJzdiIwG4gRG9lIiwZiOjJ9.DWPwNDZEl- g</pre> </li> <li> <b>h:cookie:&lt;cookie key&gt;</b> - Set the location parameter with this value when JWT occurs as part of a cookie and substitute the &lt;cookie key&gt; with the cookie name. For example, "location": "h:cookie: access_token".           <pre>Cookie: access_token=eyJhbGiIsI.eyJpc3MiOiJodHRwczotcGx1LmFrs3Zod-</pre> </li> </ul>
username	It is the JWT claim to extract the username.

Parameter	Description
clientid	It is the JWT claim to extract the client identifier.

When `enable_blocking` is set to `true`, ASE checks the username against the list of usernames in the whitelist and blacklist. If the username is in the blacklist, the client using the username is blocked.

**Note:** ASE also supports extracting Username from a custom HTTP header. However, you can configure Username capture from either custom header or JWT, but not both. For more information, see [Extract username from custom header in sideband mode](#) on page 182.

**API discovery process** -The ABS AI Engine processes the ASE access logs and discovers new and unknown APIs in your environment. A root API JSON is defined in ASE to enable API discovery by ABS. For more information on API discovery, see [API discovery and configuration](#) on page 347. If the root API JSON has a JWT object configured with values set for all the keys, then the APIs discovered by the ABS will have the JWT object.

The following table explains the behavior of ASE when the root API JSON has an incomplete JWT object. It also describes its impact on the APIs discovered by ABS in your environment.

Scenarios	Behavior of ASE	API discovery
When a JWT object is not configured in <code>root</code> API JSON.	ASE processes the <code>root</code> API JSON file.	A JWT object gets added to the discovered APIs with all the keys but empty values. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>
When a JWT object is configured in the <code>root</code> API JSON file, but with no keys. For example. <pre> "jwt": {} </pre>	ASE does <b>not</b> process the <code>root</code> API JSON file.	The API is not discovered.
When a JWT object is configured with all the keys present but no values set. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>	ASE processes the <code>root</code> API JSON file.	A JWT object gets added to the discovered APIs with all the keys but empty values. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>

Scenarios	Behavior of ASE	API discovery
When a JWT object is configured but not all keys are set. For example. <pre>"jwt": {   "username": "",   "location": "" }</pre>	ASE does <b>not</b> process the <code>root</code> API JSON file.	The API is not discovered.

**i Note:** The API JSON file shipped with ASE is compatible with earlier versions of API JSON files. ASE automatically adds an empty JWT object to the API JSON file to maintain compatibility.

### Extract username from custom header in sideband mode

This topic discusses the extraction of username from a custom header when API Security Enforcer (ASE) is in sideband mode.

ASE supports capturing usernames from custom headers in a request. It extracts the username and logs it in ASE access logs. ASE sends these access log files to the API Behavioral Security (ABS) AI Engine to detect attacks. Following is an example snippet of username information logged to ASE access log.


```
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[connectinfo:127.0.0.0:80] [type:connection] connection received
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:request] [api_id:api1] GET /abcd
HTTP/1.1
```

#### **x-username-header: 12n4uf9ckls**

```
host: http://pi-api-mngmnt.azr-api.net/
accept: */*
content-type: text/plain;charset=UTF-8
```


```
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:backend_info]
[backend_type:nonssl] [0] [api_id:api1] [hostname:not available] backend
selected
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:req_payload] [api_id:api1]
[size:0]
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:user_info] [api_id:api1] username:
12n4uf9ckls
```

When deployed in sideband mode, ASE receives the API request information from the sideband policy and extracts the metadata like user information, IP addresses and so on. The following diagram shows the traffic flow when ASE is in sideband mode.



The sideband policy sends user information in a `user_info` object to ASE. If the `user_info` object contains username, then ASE extracts it. Otherwise, ASE checks the API JSON configuration.

The API JSON can be configured to extract username from either a JSON Web Token (JWT) or a custom header. ASE first checks the JWT object. If it is configured, then ASE extracts the username from the JWT in an incoming request. If the JWT object is not configured, then ASE checks the `username_header` parameter configuration in the API JSON file. If it is set, ASE extracts the username from the custom header that comes as part of an incoming request. For more information, see [Configure API JSON](#) section.



**i Important:** ASE supports extracting username from either JWTs or custom headers. You can configure API JSON to capture username from either custom header or JWT, but not both for a given API. For more information on extracting usernames from JWTs, see [Extract user information from JWT in sideband mode](#) on page 178.

### Configure API JSON

The behavior and properties of your API are defined in an API JSON file in the ASE. To enable username capture from a custom header, set the value of the `username_header` parameter to the custom header name containing the username. The following is an example snippet of an API JSON file.

```

{
  "api_metadata": {
    "protocol": "http",
    "url": "/",
    "cookie": "JSESSIONID",
    "hostname": "*",
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "enable_blocking": true,
  }
}

```



```

"cookie_idle_timeout": "200m",
"logout_api_enabled": false,
"cookie_persistence_enabled": false,
"login_url": "",
"api_mapping": {
  "internal_url": ""
},
"api_pattern_enforcement": {
  "protocol_allowed": "",
  "http_redirect": {
    "response_code": "",
    "response_def": "",
    "https_url": ""
  },
  "methods_allowed": [],
  "content_type_allowed": "",
  "error_code": "401",
  "error_def": "Unauthorized",
  "error_message_body": "401 Unauthorized"
},
"flow_control": {
  "client_spike_threshold": "0/second",
  "server_connection_queueing": false
},
"api_memory_size": "128mb",
"health_check": false,
"health_check_interval": 60,
"health_retry_count": 4,
"health_url": "/",
"health_check_headers": {},
"server_ssl": false,
"servers": [],
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
},
"username_header": "x-username-header",

"jwt": {
  "location": "",
  "username": "",
  "clientid": ""
}
}

```

For more information, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.

You can optionally block a client. When `enable_blocking` is set to `true`, ASE checks the username against the list of usernames in the whitelist and blacklist. If the username is in the blacklist, the client using the username is blocked.

**Note:** The API JSON file shipped with ASE is compatible with earlier versions of API JSON files. ASE automatically adds an optional `username_header` parameter to the API JSON file to maintain compatibility.

## Manage whitelist and blacklist

ASE maintains the following two types of lists:

- **Whitelist** – List of “safe” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that are not blocked by ASE. The list is manually generated by adding the client identifiers using CLI commands.
- **Blacklist** – List of “bad” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that are always blocked by ASE. The list consists of entries from one or more of the following sources:
  - ABS detected attacks (for example data exfiltration). ABS detected attacks have a time-to-live (TTL) in minutes. The TTL is configured in ABS.
  - ASE detected attacks (for example invalid method, decoy API accessed). The ASE detected attacks
  - List of “bad” clients manually generated by CLI

## Manage whitelists

Valid operations for OAuth2 Tokens, cookies, IP addresses, API keys, and usernames on a whitelist include:

### Add an entry

- Add an IP address to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist ip
10.10.10.10
ip 10.10.10.10 added to whitelist
```

- Add a cookie to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist cookie
JSESSIONID cookie_1.4
cookie JSESSIONID cookie_1.4 added to whitelist
```

- Add a token to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist token
token1.4
token token1.4 added to whitelist
```

- Add an API Key to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist api_key
X-API-KEY key_1.4
api_key X-API-KEY key_1.4 added to whitelist
```

- Add a username to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist username
abc@example.com
username abc@example.com added to whitelist
```

### View whitelist

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_whitelist
Whitelist
1) type : ip, value : 1.1.1.1
2) type : cookie, name : JSESSIONID, value : cookie_1.1
3) type : token, value : token1.3
4) type : api_key, name : X-API-KEY, value : key_1.4
5) type : username, value : abc@example.com
```

## Delete an entry

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist ip
4.4.4.4
ip 4.4.4.4 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist cookie
JSESSIONID cookie_1.1
cookie JSESSIONID cookie_1.1 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist token
token1.1
token token1.1 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist api_key
X-API-KEY key_1.4
api_key X-API-KEY key_1.4 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist username
abc@example.com

```

## Clear the whitelist

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin clear_whitelist
This will delete all whitelist Attacks, Are you sure (y/n) : y
Whitelist cleared
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin clear_whitelist
This will delete all whitelist Attacks, Are you sure (y/n) : n
Action canceled

```

## Manage blacklists

Valid operations for IP addresses, Cookies, OAuth2 Tokens, and API keys on a blacklist include:

### Add an entry

- Add an IP address to blacklist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist ip
1.1.1.1
ip 1.1.1.1 added to blacklist

```

- Add a cookie to blacklist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist cookie
JSESSIONID ad233edqsd1d23redwefew
cookie JSESSIONID ad233edqsd1d23redwefew added to blacklist

```

- Add a token to blacklist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist token
ad233edqsd1d23redwefew
token ad233edqsd1d23redwefew added to blacklist

```

- Add an API Key to blacklist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist api_key
AccessKey b31dfa4678b24aa5a2daa06aba1857d4
api_key AccessKey b31dfa4678b24aa5a2daa06aba1857d4 added to blacklist

```

- Add an username to blacklist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist username
abc@example.com
username abc@example.com added to blacklist
```

**Note:** You can also add username with space to blacklist. For example, "your name".

**View blacklist** - entire blacklist or based on the type of real time violation.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist all
Manual Blacklist
1) type : ip, value : 172.168.11.110
2) type : token, value : cdE94R3osh283B7NoiJR41XHgt7gxroot
3) type : username, value : blockeduser
4) type : cookie, name : JSESSIONID, value : pZ1hg5s3i8csImMoas7vh81vz
5) type : api_key, name : x-api-key, value :
d4d28833e2c24be0913f4267f3b91ce5
ABS Generated Blacklist
1) type : token, value : fAtTzxFJZ2Zkr7HZ9KM17s7kY2Mu
2) type : token, value : oFQOr11Gj8cCRv1k4849RZOPztPP
3) type : token, value : Rz7vn5KoLUcAhruQZ4H5cE00s2mG
4) type : token, value : gxbkGPNuFJw69Z5PF44PoRIfPugA
5) type : username, value : user1
Realtime Decoy Blacklist
1) type : ip, value : 172.16.40.15
2) type : ip, value : 1.2.3.4
```

**Blacklist based on decoy IP addresses**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist decoy
Realtime Decoy Blacklist
1) type : ip, value : 4.4.4.4
```

**Blacklist based on protocol violations**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_protocol
Realtime Protocol Blacklist
1) type : token, value : token1.1
2) type : ip, value : 1.1.1.1
3) type : cookie, name : JSESSIONID, value : cookie_1.1
```

**Blacklist based on method violations**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_method
Realtime Method Blacklist
1) type : token, value : token1.3
2) type : ip, value : 3.3.3.3
3) type : cookie, name : JSESSIONID, value : cookie_1.3
```

**Blacklist based on content-type violation**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_content_type
Realtime Content-Type Blacklist
1) type : token, value : token1.2
2) type : ip, value : 2.2.2.2
3) type : cookie, name : JSESSIONID, value : cookie_1.2
```

## ABS detected attacks

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
abs_detected
No Blacklist
```

## Delete an entry

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_blacklist ip
1.1.1.1
ip 1.1.1.1 deleted from blacklist
./bin/cli.sh -u admin -p admin delete_blacklist cookie JSESSIONID
avbry47wdfgd
cookie JSESSIONID avbry47wdfgd deleted from blacklist
./bin/cli.sh -u admin -p admin delete_blacklist token
58fcb0cb97c54afbb88c07a4f2d73c35
token 58fcb0cb97c54afbb88c07a4f2d73c35 deleted from blacklist
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_blacklist api_key
AccessKey b31dfa4678b24aa5a2daa06aba1857d4
```

## Clear the blacklist

```
./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :y
Blacklist cleared
./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :n
Action canceled
```

When clearing the blacklist, make sure that the real-time ASE detected attacks and ABS detected attacks are disabled. If not disabled, the blacklist gets populated again as both ASE and ABS are continuously detecting attacks.


## ASE generated error messages for blocked requests

ASE blocks certain requests based on API Mapping or ABS detected attacks. For these blocked requests, it sends a standard error message back to the client.

The following table describes the error messages:

Blocked Connection	HTTP Error Code	Error Definition	Message Body
Unknown API	503	Service Unavailable	Error: Unknown API
Unknown Hostname	503	Service Unavailable	Error: Unknown Hostname
Malformed Request	400	Bad Request	Error: Malformed Request
IP attack	403	Unauthorized	Error: Unauthorized
Cookie attack	403	Unauthorized	Error: Unauthorized
OAuth2 Token attack	403	Unauthorized	Error: Unauthorized
API Key attack	403	Unauthorized	Error: Unauthorized
Username attack	403	Unauthorized	Error: Unauthorized

The con  
the



### Per API blocking

ASE can be configured to selectively block on a per API basis by configuring an API JSON file parameter. To enable per API blocking for each API, set the `enable_blocking` parameter to `true` in the API JSON. For example:

```
api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": false,
  "oauth2_access_token": false,
  "apikey_qs": "",
  "apikey_header": "",
  "enable_blocking": true,
  "login_url": "",
  "api_mapping": {
    "internal_url": ""
  }
},
```

If per API blocking is disabled, ABS still detect attacks for that specific API, however, ASE does not block them. ASE will continue to block attacks on other APIs with the `enable_blocking` set to `true`.


## API deception environment


A decoy API is configured in ASE and the API gateway. It requires no changes to backend servers. It appears as part of the API ecosystem and is used to detect the attack patterns of hackers. When a hacker accesses a decoy API, ASE sends a predefined response (defined in the `response_message` parameter in API JSON file) to the client request and collects the request information as a footprint to analyze API ecosystem attacks. ASE acts as a backend for decoy APIs configured in the API gateway.

Decoy API traffic is separately logged in files named with the following format:

`decoy_pid_<pid_number>__yyyy-dd-mm-<log_file_rotation_time` (for example, `decoy_pid_8787__2017-04-04_10-57.log`). Decoy log files are rotated every 24-hours and stored in the `opt/pingidentity/ase/logs` directory.

Decoy APIs are independent APIs where every path is a decoy API. Any sub-paths accessed in the API are treated as part of the decoy API. The figure shows an example.

 **Note:** In sideband ASE deployment you can configure only out-of-context decoy API.



The following steps explain the flow of decoy API traffic:

1. The attacker sends decoy API request
2. API gateway forwards the request is to the configured decoy API which is ASE functioning as a backend server for the decoy API.
3. The configured response is sent to the API gateway.
4. The configured response from ASE is sent back to the attacker.

The decoy request is logged in `decoy.log` file and sent to PingIntelligence ABS for further analysis. Following is a snippet of an API JSON file which has been deployed as an out-of-context decoy API:

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/account",
    "hostname": "*",
  };
}
```



```
; Note – other configuration parameters removed
;
"decoy_config":
{
  "decoy_enabled": true,
  "response_code" : 200,
  "response_def" : "OK",
  "response_message" : "OK", decoy API configuration
  "decoy_subpaths": [

]
}
```

Since the `decoy_subpaths` parameter is empty, any sub-path accessed by the attacker after `/account` is regarded as a decoy path or decoy API.

After configuring a decoy API, check the API listings by running the `list_api` command:

```
opt/pingidentity/ase/bin/cli.sh list_api -u admin -p
flight ( loaded ), https
trading ( loaded ), https, decoy: out-context
```

### Real-time API deception attack blocking

When a client probes a decoy API, ASE logs but does not drop the client connection. However, if the same client tries to access a legitimate business API, then ASE block the client in real-time. Here is a snippet of an ASE access log file showing real time decoy blocking:


```
[Tue Aug 1422:51:49:707 2018] [thread:209] [info] [connectionid:1804289383]
[connectinfo:100.100.1.1:36663] [type:connection_drop] [api:decoy]
[request_payload_length:0] GET /decoy/test/test HTTP/1.1
User-Agent: curl/7.35.0
Accept: */*
Host: app
```

The blocked client is added to the blacklist which can be viewed by running the `view_blacklist` CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
Realtime Decoy Blacklist
1) type : ip, value : 100.100.1.1
```

## ABS AI-based security

ABS AI engine detects attacks using artificial intelligence (AI) algorithms. After receiving ASE access logs and API JSON configuration files, ABS applies AI algorithms to track API connections and detect attacks. If `enable_abs_attack` is `true`, ABS sends blacklist to ASE which blocks client identifiers, like, API keys, usernames, cookie, IP address, and OAuth token on the list.



### Configure ASE to ABS connectivity

To connect ASE to ABS, configure the ABS address (IPv4:Port or Hostname:Port), access key, and secret key in the `abs.conf` file located in the `/<ASE installation path>/pingidentity/ase/config` directory.

**Note:** `enable_abs` must be set to `true` in the `ase.conf` file. when ABS is in a different AWS security group, use a private IP address

The parameter values and descriptions are included in the following table:

Parameter	Description
<code>deployment_type</code>	The ABS deployment mode. Valid values are <code>cloud</code> or <code>onprem</code> . The default value is <code>onprem</code> .

gateway_credential	This parameter is used when ABS is deployed in <code>cloud</code> mode. The credential generated in PingOne, while creating a PingIntelligence connection is assigned here so that PingOne can authenticate the data sent by ASE during runtime. For more information on PingOne connections, see <a href="#">Connections</a> .
abs_cloud_endpoint	Use this parameter to assign an endpoint other than the one decoded by the gateway credentials. It's used when ABS is deployed in <code>cloud</code> mode.
abs_endpoint	The parameter has two possible configurations: <ul style="list-style-type: none"> <li>▪ <b>When ABS is deployed with a load balancer</b> - Configure the hostname and port or the IPv4 and port of the load balancer.</li> </ul> <div style="border: 1px solid #ccc; padding: 5px; margin: 5px 0;"> <p><b>Note:</b> To allow the load balancer to bind ASE's session to a specific ABS node, enable cookie stickiness in the load balancer PISESSIONID cookie.</p> </div> <ul style="list-style-type: none"> <li>▪ <b>When ABS is deployed without a load balancer</b> - Configure the parameter with the hostname and port or the IPv4 and port of all the ABS nodes in a cluster. If later a new ABS node is added to the cluster, add its hostname or IPv4 to the list and restart ASE.</li> </ul>
access_key	The access key or the username for the ABS nodes. It is the same for all the ABS nodes. The same value has to be configured in ABS MongoDB database. This value is obfuscated during the start of ASE. This parameter is used when ABS is deployed in <code>onprem</code> mode. <div style="border: 1px solid #ccc; padding: 5px; margin: 5px 0;"> <p><b>Note:</b> ":" is a restricted character and allowed in access key.</p> </div>
secret_key	The secret key or the password for the ABS nodes. It is the same for all the ABS nodes. The same value has to be configured in ABS MongoDB database. This value is obfuscated during the start of ASE. This parameter is used when ABS is deployed in <code>onprem</code> mode. <div style="border: 1px solid #ccc; padding: 5px; margin: 5px 0;"> <p><b>Note:</b> ":" is a restricted character and allowed in secret key.</p> </div>
enable_ssl	Set the value to true for SSL communication between ASE and ABS. The default value is true. ASE sends the access log files in plain text if the value is set to false. This parameter is used when ABS is deployed in <code>onprem</code> mode.
abs_ca_cert_path	Location of the trusted CA certificates for SSL/TLS connections from ASE to ABS. <p>If the path parameter value is left empty, then ASE does not verify the validity of CA certificates. However, the connection to ABS is still encrypted. This parameter is used when ABS is deployed in <code>onprem</code> mode.</p>

**Note:** The `access_key` and `secret_key` are configured in ABS. For more information, see *ABS Admin Guide*.

Here is a sample `abs.conf` file.

```
; API Security Enforcer ABS configuration.;
This file is in the standard .ini format.
The comments start with a semicolon (;).;
Following configurations are applicable only if ABS is enabled with true.
; Configure ABS deployment type. Supported values (onprem/cloud)
deployment_type=onprem

; PingIntelligence Gateway Credentials
gateway_credential=

; ABS endpoint for cloud
abs_cloud_endpoint=

; a comma-separated list of abs nodes having hostname:port or ipv4:port as
an address.
abs_endpoint=127.0.0.1:8080

; access key for abs node
access_key=OBF:AES://ENOzsqOEhDBWLDY
+pIoQ:jN6wLiHTTd3oVNzvtXuAaOG34c4JBD4XZHgFCaHry0

; secret key for abs node
secret_key=OBF:AES:Y2DadCU4JFZp3bx8EhnOiw:zzi77GIFF5xkQJccjIrIVWU
+RY5CxUhp3NLcNBel+3Q

; Setting this value to true will enable encrypted communication with ABS.
enable_ssl=true

; Configure the location of ABS's trusted CA certificates. If empty, ABS's
certificate
; will not be verified
abs_ca_cert_path=
```

### Configuring ASE-ABS encrypted communication

To enable SSL communication between ASE and ABS so that the access logs are encrypted and sent to ABS, set the value of `enable_ssl` to `true`. The `abs_ca_cert_path` is the location of ABS's trusted CA certificate. If the field is left empty, ASE does not verify ABS's certificate, however, the communication is still encrypted.

### Check and open ABS ports

The default port for connection with ABS is 8080. Run the `check_ports.sh` script on the ASE machine to determine ABS accessibility. Input ABS host IP address and ports as arguments.

```
/opt/pingidentity/ase/util ./check_ports.sh {ABS IPv4:[port]}
```

### Manage ASE blocking of ABS detected attacks

To configure ASE to automatically fetch and block ABS detected attacks, complete the following steps:

1. Enable ASE Security. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_firewall
```

2. Enable ASE to send API traffic information to ABS. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs
```

3. Enable ASE to fetch and block ABS detected attacks. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs_attack
```

After enabling automated attack blocking, ASE periodically fetches the attack list from ABS and blocks the identified connections. To set the time interval at which ASE fetches the attack list from ABS, configure the `abs_attack_request_minute` parameter in `ase.conf` file.

```
; This value determines how often ASE will query ABS.
abs_attack_request_minutes=10
```

### Disable attack list fetching from ABS

To disable ASE from fetching the ABS attack list, entering the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs_attack
```

After entering the above command, ASE will no longer fetch the attack list from ABS. However, ABS continues generating the attack list and stores it locally. The ABS attack list can be viewed using ABS APIs and used to manually configured an attack list on ASE. For more information on ABS APIs, see *ABS Admin Guide*.

To stop an ASE cluster from sending log files to ABS, enter the following ASE CLI command.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs
```

After entering this command, ABS will not receive any logs from ASE. Refer to the ABS documentation for information on types of attacks.

## Configure Google Pub/Sub

Google Cloud Pub/Sub is an enterprise event-driven message system. API Security Enforcer (ASE) integrates with Google Pub/Sub in ASE `sideband` mode. When you enable Google Pub/Sub in `ase.conf` file, ASE sends the event message in a JSON file to Google cloud. You can verify that Google Pub/Sub is enabled by running the ASE `status` command:

```
/opt/pingidentity/ase/bin/cli.sh status -u admin -p admin
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : disabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
google pubsub         : enabled
```

Complete the following steps to configure Google Pub/Sub in ASE:

1. Download the Key file in JSON format from your Google Pub/Sub account. For more information on generating the Key file, see [Quickstart: building a functioning Cloud Pub/Sub system](#)
2. Copy the downloaded Key JSON file to `/pingidentity/ase/config` directory.
3. Rename the file to `google_application_credentials.json`.

#### 4. Configure the following Google Pub/Sub options in the `ase.conf` file:

<code>enable_google_pubsub</code>	Set it to <code>true</code> if you want ASE to push metrics data to Google cloud. The default value is <code>false</code> .
<code>google_pubsub_topic</code>	The path to your topic for publishing and subscribing the messages. For example, <code>/pingidentity/topic/your_topic</code>
<code>google_pubsub_concurrency</code>	The number of concurrent connection between ASE and Google Pub/Sub. The maximum value is 1024 connections. Default value is 1000 connections.
<code>google_pubsub_qps</code>	The number of messages per second that ASE can publish to the topic. Maximum value is 10,000. The default value is 1000.
<code>google_pubsub_apikey</code>	The API Key to establish connection between ASE and Google Pub/Sub. Configuring API Key for Google Pub/Sub is optional.
<code>cache_queue_size</code>	The number of messages that are buffered in cache when ASE is not able to publish to Google Pub/Sub. Maximum size of the queue is 10,000 messages. The default value is 300 messages.
<code>google_pubsub_timeout</code>	The time in seconds for which ASE tries to publish messages to Google Pub/Sub. In case of failure to publish, ASE makes three attempts to publish the message, after which it writes the message to the <code>google_pubsub_failed.log</code> file.

**Note:** ASE must be in the `sideband` mode for Google Pub/Sub configuration to take effect.

#### Configure API Key - Optional

You can optionally configure API Key in `ase.conf` file. Obtain the API Key for your Google project and configure in `google_pubsub_apikey` option. Obfuscate the API Key for it to take effect. For more information on obfuscating keys and password, see [Obfuscate keys and passwords](#) on page 128. Following is a summary of steps that you need to complete:

1. Stop ASE
2. Edit `ase.conf` file to add API Key
3. Obfuscate the API Key
4. Start ASE

#### ASE JSON message file

ASE sends the event information to Google Pub/Sub in a JSON message. The message captures the following information:

- Method
- URL
- Host
- Request time-stamp
- Request length
- Source IP
- X-forwarded-for IPs

- Response code
- Response length, and
- Latency in milliseconds

ASE makes 3-attempts to publish the message to Google Pub/Sub after which the entire message is logged in failed log file. The message that is logged in the failed log file is not in plain text. If the message is not published to Google Pub/Sub, you can check the reason for failure in `balancer.log` file. For more information on `balancer.log` file, see [ASE management, access and audit logs](#) on page 150. When messages are successfully published to Google Pub/Sub, the message ID is logged in success log file. Following is a snippet of event message JSON file logged in `balancer.log` file when ASE is run in debug mode.

```
{
  "method": "PUT",
  "url": "/shopapi-books/order",
  "host": "shop-electronics.cloudhub.io",
  "request_timestamp": "1573767522429",
  "request_length": "464",
  "source_ip": "1.2.3.4",
  "x_forwarded_for": "1.1.1.1, 1.1.1.2",
  "response_code": "200",
  "response_length": "26",
  "latency_ms": "208"
}
```

## REST APIs for sideband token and authentication

ASE provides REST APIs for authentication and sideband token management.

### Authentication

The `Authentication` API helps to enable and disable ASE sideband authentication. You can also retrieve the authentication status.

**Description:** Enable or disable sideband authentication.

<b>URL</b>	<code>/v5/ase/sideband/authentication?status=&lt;value&gt;</code>	
<b>Method</b>	POST	
<b>Query Parameter</b>	status	Valid values: <i>enable</i> or <i>disable</i>
<b>Request Headers</b>	<pre>x-ase-access-key: &lt;value&gt; x-ase-secret-key: &lt;value&gt;</pre>	

### Sample curl command

```
curl --location --request POST '<ASE IP Address>:<port no>/v5/ase/sideband/
authentication?status=enable' \
--header 'x-ase-access-key: ase_ak' \
--header 'x-ase-secret-key: ase_sk'
```

### Sample Responses

```
{
  "status": "disabled",
  "status_message": "Sideband authentication is disabled"
```

```

}

{
  "status": "enabled",
  "status_message": "Sideband authentication is enabled"
}

```

**Description:** Get sideband authentication status.

<b>URL</b>	<a href="/v5/ase/sideband/authentication">/v5/ase/sideband/authentication</a>
<b>Method</b>	GET
<b>Request Headers</b>	x-ase-access-key: <value> x-ase-secret-key: <value>

### Sample curl command

```

curl --location --request POST '<ASE IP Address>:<port no>/v5/ase/sideband/authentication' \
--header 'x-ase-access-key: ase_ak' \
--header 'x-ase-secret-key: ase_sk'

```

### Sample Responses

```

{
  "status": "disabled",
  "status_message": "Sideband authentication is disabled"
}

```

```

{
  "status": "enabled",
  "status_message": "Sideband authentication is enabled"
}

```

### Token

The `Token` API helps to create, import, and delete ASE sideband tokens. You can also retrieve the list of tokens issued by ASE.

**Description:** Create a new sideband token.

<b>URL</b>	<a href="/v5/ase/sideband/token">/v5/ase/sideband/token</a>
<b>Method</b>	POST
<b>Request Headers</b>	x-ase-access-key: <value> x-ase-secret-key: <value>

### Sample curl command

```

curl --location --request POST '<ASE IP Address>:<port no>/v5/ase/sideband/token' \
--header 'x-ase-access-key: ase_ak' \

```



```
--header 'x-ase-secret-key: ase_sk'
```

### Sample Response

```
{
  "status": "token_created",
  "token": "dac5fkdfjdlfjdlfjldkfjdlab08903453fec4c0"
}
```

**Description:** Import a sideband token. The token should be 32 character long, and the allowable characters in the token are: alphabets in small case and digits 0-9.

<b>URL</b>	<code>/v5/ase/sideband/token</code>
<b>Method</b>	PUT
<b>Request Headers</b>	<pre>x-ase-access-key: &lt;value&gt; x-ase-secret-key: &lt;value&gt; Content-Type: application/json</pre>

### Sample curl command

```
curl --location --request PUT '<ASE IP Address>:<port no>/v5/ase/sideband/
token' \
--header 'x-ase-access-key: admin' \
--header 'x-ase-secret-key: admin' \
--header 'Content-Type: application/json' \
--data-raw '{
  "token": "dc6684370f014923b8a070c982601f7c"
}
```

### Sample Request

```
{
  "token": "dc6684370f014923b8a070c982601f75"
}
```

### Sample Response

```
{
  "status": "success",
  "status_message": "Sideband token dc6684370f014923b8a070c982601f75
imported."
}
```

**Description:** Delete a sideband token.

<b>URL</b>	<code>/v5/ase/sideband/token</code>
<b>Method</b>	DELETE
<b>Request Headers</b>	<pre>x-ase-access-key: &lt;value&gt; x-ase-secret-key: &lt;value&gt; Content-Type: application/json</pre>

### Sample curl command

```
curl --location --request DELETE '<ASE IP Address>:<port no>/v5/ase/
sideband/token' \
--header 'x-ase-access-key: admin' \
--header 'x-ase-secret-key: admin' \
--header 'Content-Type: application/json' \
--data-raw '{
  "token": "dc6684370f014923b8a070c982601f7c"
}
```

### Sample Request

```
{  "token": "dc6684370f014923b8a070c982601f75"}
```

### Sample Response

```
{
  "status": "success",
  "status_message": "Sideband token dc6684370f014923b8a070c982601f75
deleted."
}
```

**Description:** List all sideband token.

<b>URL</b>	<code>/v5/ase/sideband/token</code>
<b>Method</b>	GET
<b>Request Headers</b>	<pre>x-ase-access-key: &lt;value&gt; x-ase-secret-key: &lt;value&gt;</pre>

### Sample curl command

```
curl --location --request GET '<ASE IP Address>:<port no>/v5/ase/sideband/
token' \
--header 'x-ase-access-key: ase_ak' \
--header 'x-ase-secret-key: ase_sk'
```

### Sample Response

```
{
  "sideband_tokens": [
    {
      "token": "dac559bf75904141ab08903453fec4c0",
      "created_at": "2021-May-06 14:02:44"
    },
    {
      "token": "dc6684370f014923b8a070c982601c74",
      "created_at": "2021-May-06 13:51:55"
    }
  ]
}
```

## CLI for sideband ASE

### Start ASE

**Description**

Start ASE

**Syntax**

```
./start.sh
```

### Stop ASE

**Description**

Stop ASE

**Syntax**

```
./stop.sh
```

### Help

**Description**

Displays cli.sh help

**Syntax**

```
./cli.sh help
```

### Version

**Description**

Displays the version number of ASE

**Syntax**

```
./cli.sh version
```

### Status

**Description**

Displays the running status of ASE

**Syntax**

```
./cli.sh status
```

### Update Password

**Description**

Change ASE admin password

**Syntax**

```
./cli.sh update_password -u admin - p
```

### Change log level

**Description**

Change balancer.log and controller.log log level

**Syntax**

```
./cli.sh log_level -u admin -p
```

**options** - warn, info, error, fatal, debug

### Get Authentication Method

**Description**

Display the current authentication method

**Syntax**

```
./cli.sh get_auth_method -u admin -p
```

### Update Authentication Method

#### Description

Update ASE authentication method

#### Syntax

```
./cli.sh update_auth_method {method} -u admin -p
```

### Enable Sideband Authentication

#### Description

Enable authentication between API gateway and ASE when ASE is deployed in sideband mode

#### Syntax

```
./cli.sh enable_sideband_authentication -u admin - p
```

### Disable Sideband Authentication

#### Description

Disable authentication between API gateway and ASE when ASE is deployed in sideband mode

#### Syntax

```
./cli.sh disable_sideband_authentication -u admin - p
```

### Create ASE Authentication Token

#### Description

Create the ASE token that is used to authenticate between the API gateway and ASE

#### Syntax

```
./cli.sh create_sideband_token -u admin - p
```

### List ASE Authentication Token

#### Description

List the ASE token that is used to authenticate between the API gateway and ASE

#### Syntax

```
./cli.sh list_sideband_token -u admin - p
```

### Import ASE Authentication Token

#### Description

Import ASE token that is used for authentication between ASE and API gateway. The token should be 32 character long, and the allowable characters in the token are: alphabets in small case and digits 0-9.

#### Syntax

```
./cli.sh import_sideband_token {token} -u admin - p admin
```

### Delete ASE Authentication Token

#### Description

Delete the ASE token that is used to authenticate between the API gateway and ASE

#### Syntax

```
./cli.sh delete_sideband_token {token} -u admin - p
```

### Enable Audit Logging

#### Description

Enable audit logging

#### Syntax

```
./cli.sh enable_audit -u admin -p admin
```

### Disable Audit Logging

#### Description

Disable audit logging

#### Syntax

```
./cli.sh disable_audit -u admin -p admin
```

### Add Syslog Server

#### Description

Add a new syslog server

#### Syntax

```
./cli.sh -u admin -p admin add_syslog_server host:port
```

### Delete Syslog Server

#### Description

Delete the syslog server

#### Syntax

```
./cli.sh -u admin -p admin delete_syslog_server host:port
```

### List Syslog Server

#### Description

List the current syslog server

#### Syntax

```
./cli.sh -u admin -p admin list_syslog_server
```

### Add API

#### Description

Add a new API file in JSON format. File should have `.json` extension. Provide the complete path where you have stored the API JSON file. After running the command, API is added to `/opt/pingidentity/ase/config/api` directory

#### Syntax

```
./cli.sh -u admin -p admin add_api {config_file_path}
```

### Update API

#### Description

Update an API after the API JSON file has been edited and saved

#### Syntax

```
./cli.sh -u admin -p admin update_api {api_name}
```

### List APIs

#### Description

Lists all APIs configured in ASE

#### Syntax

```
./cli.sh -u admin -p admin list_api
```

### API Info

#### Description

Displays the API JSON file

#### Syntax

```
./cli.sh -u admin -p admin api_info {api_id}
```

### API Count

#### Description

Displays the total number of APIs configured

#### Syntax

```
./cli.sh -u admin -p admin api_count
```

### Enable Per API Blocking

#### Description

Enables attack blocking for the API

#### Syntax

```
./cli.sh -u admin -p admin enable_blocking {api_id}
```

### Disable Per API Blocking

#### Description

Disable attack blocking for the API

#### Syntax

```
./cli.sh -u admin -p admin disable_blocking {api_id}
```

### Delete API

#### Description

Delete an API from ASE. Deleting an API removes the corresponding JSON file and deletes all the cookies associated with that API

#### Syntax

```
./cli.sh -u admin -p admin delete_api {api_id}
```

### Generate Master Key

#### Description

Generate the master obfuscation key `ase_master.key`

#### Syntax

```
./cli.sh -u admin -p admin generate_obfkey
```

### Obfuscate Keys and Password

#### Description

Obfuscate the keys and passwords configured in various configuration files

#### Syntax

```
./cli.sh -u admin -p admin obfuscate_keys
```

### Create a Key Pair

#### Description

Creates private key and public key pair in keystore

#### Syntax

```
./cli.sh -u admin -p admin create_key_pair
```

### Create a CSR

#### Description

Creates a certificate signing request

#### Syntax

```
./cli.sh -u admin -p admin create_csr
```

### Create a Self-Signed Certificate

**Description**

Creates a self-signed certificate

**Syntax**

```
./cli.sh -u admin -p admin create_self_sign_cert
```

### Import Certificate

**Description**

Import CA signed certificate into keystore

**Syntax**

```
./cli.sh -u admin -p admin import_cert {cert_path}
```

### Create Management Key Pair

**Description**

Create a private key for management server

**Syntax**

```
/cli.sh -u admin -p admin create_management_key_pair
```

### Create Management CSR

**Description**

Create a certificate signing request for management server

**Syntax**

```
/cli.sh -u admin -p admin create_management_csr
```

### Create Management Self-signed Certificate

**Description**

Create a self-signed certificate for management server

**Syntax**

```
/cli.sh -u admin -p admin create_management_self_sign_cert
```

### Import Management Key Pair

**Description**

Import a key-pair for management server

**Syntax**

```
/cli.sh -u admin -p admin import_management_key_pair {key_path}
```

### Import Management Certificate

**Description**

Import CA signed certificate for management server

**Syntax**

```
/cli.sh -u admin -p admin import_management_cert {cert_path}
```

### Cluster Info

**Description**

Displays information about an ASE cluster

**Syntax**

```
./cli.sh -u admin -p admin cluster_info
```

### Delete Cluster Node

**Description**

Delete and inactive ASE cluster node

**Syntax**

```
./cli.sh -u admin -p admin delete_cluster_node host:port
```

**Enable Firewall****Description**

Enable API firewall. Activates pattern enforcement, API name mapping, manual attack type

**Syntax**

```
./cli.sh -u admin -p admin enable_firewall
```

**Disable Firewall****Description**

Disable API firewall

**Syntax**

```
./cli.sh -u admin -p admin disable_firewall
```

**Enable ASE detected attacks****Description**

Enable ASE detected attacks

**Syntax**

```
./cli.sh -u admin -p admin enable_ase_detected_attack
```

**Disable ASE Detected Attacks****Description**

Disable API firewall

**Syntax**

```
./cli.sh -u admin -p admin disable_ase_detected_attack
```

**Enable ABS****Description**

Enable ABS to send access logs to ABS

**Syntax**

```
./cli.sh -u admin -p admin enable_abs
```

**Disable ABS****Description**

Disable ABS to stop sending access logs to ABS

**Syntax**

```
./cli.sh -u admin -p admin disable_abs
```

**Adding Blacklist****Description**

Add an entry to ASE blacklist using CLI. Valid type values are: IP, Cookie, OAuth2 token, API Key, and username

If type is ip, then Name is the IP address.

If type is cookie, then name is the cookie name, and value is the cookie value

**Syntax**



```
./cli.sh -u admin -p admin add_blacklist {type}{name}{value}
```

### Example

```
/cli.sh -u admin -p admin add_blacklist ip 1.1.1.1
```

## Delete Blacklist Entry

### Description

Delete entry from the blacklist.

### Syntax

```
./cli.sh -u admin -p admin delete_blacklist {type}{name}{value}
```

### Example

```
cli.sh -u admin -p delete_blacklist token
58fcb0cb97c54afbb88c07a4f2d73c35
```

## Clear Blacklist

### Description

Clear all the entries from the blacklist

### Syntax

```
./cli.sh -u admin -p admin clear_blacklist
```

## View Blacklist

### Description

View the entire blacklist or view a blacklist for the specified attack type (for example, invalid\_method)

### Syntax

```
./cli.sh -u admin -p admin view_blacklist {all|manual|abs_generated|
invalid_content_type|invalid_method|invalid_protocol|decoy}
```

## Adding Whitelist

### Description

Add an entry to ASE whitelist using CLI. Valid type values are: IP, cookie, OAuth2 token, API key, and username

If type is IP, then name is the IP address.

If type is cookie, then name is the cookie name, and value is the cookie value

### Syntax

```
./cli.sh -u admin -p admin add_whitelist {type}{name}{value}
```

### Example

```
/cli.sh -u admin -p admin add_whitelist api_key AccessKey
065f73cdf39e486f9d7cda97d2dd1597
```

## Delete Whitelist Entry

### Description

Delete entry from the whitelist

### Syntax

```
./cli.sh -u admin -p admin delete_whitelist {type}{name}{value}
```

## Example

```
/cli.sh -u admin -p delete_whitelist token  
58fcb0cb97c54afbb88c07a4f2d73c35
```

### Clear Whitelist

**Description**

Clear all the entries from the whitelist

**Syntax**

```
./cli.sh -u admin -p admin clear_whitelist
```

### View Whitelist

**Description**

View the entire whitelist

**Syntax**

```
./cli.sh -u admin -p admin view_whitelist
```

### ABS Info

**Description**

Displays ABS status information.

ABS enabled or disabled, ASE fetching ABS attack types, and ABS cluster information


**Syntax**

```
./cli.sh -u admin -p admin abs_info
```

## Inline ASE

---

In the inline deployment mode, ASE sits at the edge of your network to receive the API traffic. It can also be deployed behind an existing load balancers such as AWS ELB. ASE deployed at the edge of the datacenter, terminates SSL connections from API clients. It then forwards routes the requests directly to the correct destination APIs – and app servers such as Node.js, WebLogic, Tomcat, PHP, etc.



To configure ASE to work in the Inline mode, set the `mode=inline` in the `ase.conf` file.

Some load balancers (for example, AWS ELB) require responses to keep alive messages from all devices receiving traffic. In an inline mode configuration, ASE should be configured to respond to these keep alive messages by updating the `ase_health` variable in the `ase.conf` file. When `ase_health` is true, load balancers can perform an ASE health check using the following URL: `http(s)://<ASE Name>/ase` where `<ASE Name>` is the ASE domain name. ASE will respond to these health checks.

### Inline ASE configuration - ase.conf

ASE system level configuration entails modifying parameters in the `ase.conf` file located in the `config` directory. Some values have default settings which can be modified to support your application requirements. The parameter values and descriptions are included in the following table:

Parameter	Description
<b>ASE mode</b>	
<code>mode</code>	The mode in which ASE works. Possible values are <code>inline</code> and <code>sideband</code> . The default value is <code>inline</code> .
<b>ASE timezone</b>	
<code>timezone</code>	Sets ASE's timezone. The values can be <code>local</code> or <code>UTC</code> . Default value is <code>UTC</code> . If ASE is deployed in a cluster, configure the same timezone on cluster node manually.
<code>enable_sideband_keepalive</code>	NA
<code>enable_sideband_authentication</code>	NA
<b>ASE ports</b>	

http_ws_port	Data port used for http or WebSocket protocol. The default value is 80.
https_wss_port	Data port used for https or Secure WebSocket (wss). The default value is 443.
management_port	Management port used for CLI and REST API management. The default value is 8010.
<b>ASE administration and audit</b>	
admin_log_level	The level of log detail captured. Options include: Fatal – 1, Error – 2, Warning – 3, Info – 4, Debug – 5
enable_audit	When set to true, ASE logs all actions performed in ASE in the audit log files. The default value is true.
syslog_server	Syslog server hostname or IPv4 address:port number. Leave this parameter blank if you do not want to generate for no syslog.
hostname_refresh	Time interval at which hostnames are refreshed. The default value is 60 secs. When ASE attempts to refresh the hostname, the hostname resolution must happen in 5 secs.
auth_method	Authentication method used for administrator access. See <a href="#">Configuring Native and PAM Authentication</a> for more information on the two options. <ul style="list-style-type: none"> <li>ase::db (Default - Native authentication)</li> <li>pam::ldap (Linux-PAM Authentication with script)</li> </ul>
enable_ase_health	When <code>true</code> , enables load balancers to perform a health check using following URL: <code>http(s)://&lt;ASE Name&gt;/ase</code> where <code>&lt;ASE Name&gt;</code> is the domain name The default value is <code>false</code> . <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> Do not configure the <code>/ase</code> URL in an API JSON file.</p> </div>
enable_1G	When <code>true</code> , enable 1Gbps Ethernet support. The default value is <code>true</code> . <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> Only applicable when using a 1G NIC card</p> </div>
http_ws_process	The number of HTTP or WebSocket processes. The default value is 1 and the maximum value is 6. <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> When running ASE in a cluster deployment, all nodes must have the same number of processes.</p> </div>

`https_wss_process`

The number of HTTPS or secure WebSocket processes.

The default value is 1 and the maximum value is 6.

**Note:** When running ASE in a cluster deployment, all nodes must have the same number of processes.

`enable_access_log`

When `true`, log client traffic request and response information. Default value is `true`. Make sure the value is set to `true` when ASE connects to PingOne.

`flush_log_immediate`

When `true`, log files are immediately written to the file system. When `false`, log files are written after a time interval. The default value is `true`.

`attack_list_memory`

The amount of memory used for maintaining black and whitelists. The default value is 128 MB.

`keystore_password`

Password for the keystore. For more information on updating the keystore password, see [Updating Keystore Password](#).

`enable_hostname_rewrite`

When set to `true`, ASE rewrites the host header in the client request with the IP or host and port number configured in the `server` section of the API JSON. Make a note of the following points:

**server\_ssl** in API JSON set to `false`:

- In the server section of API JSON, if the configured port is the standard HTTP port (port number 80), then only the IP or hostname in the request header is rewritten.
- In the server section of API JSON, if the configured port is any port other than the standard HTTP port (port number 80), then IP or hostname and port number in the request header is rewritten. For example, if the configured port number is 8080 in API JSON for a host `example.com`, then ASE rewrites the host header in request with `example.com:8080`.

**server\_ssl** in API JSON set to `true`:

- In the server section of API JSON, if the configured port is the standard HTTPS port (port number 443), then only the IP or hostname in the request header is rewritten.
- In the server section of API JSON, if the configured port is any port other than the standard HTTPS port (port number 443), then IP or hostname and port number in the request header is rewritten. For example, if the configured port number is 8443 in API JSON for a host `example.com`, then ASE rewrites the host header in request with `example.com:8443`.

### ASE cluster

`enable_cluster`

When `true`, run the setup in cluster mode.

The default value is `false`, run the setup in standalone mode.

### Security

`enable_sslv3`

When `true`, enable SSLv3. Default value is `false`.

server_ca_cert_path	<p>Location of the trusted CA certificates for SSL/TLS connections from / to backend servers.</p> <p>If the path parameter value is left empty, then ASE does not verify the validity of CA certificates. However, the backend connection is still encrypted.</p> <p>For RHEL 7.6 CA certificates, the default path is: <code>/etc/pki/tls/certs/</code>.</p> <p>Multiple certificates can be placed in this directory.</p>
enable_xff	<p>When <code>true</code>, pass XFF header with originating IP address to the backend server.</p>
enable_firewall	<p>When <code>true</code>, activate the following API security features:</p> <ul style="list-style-type: none"> <li>▪ API mapping</li> <li>▪ API pattern enforcement</li> <li>▪ Connection drop using attack types</li> <li>▪ Flow control</li> </ul> <p>Default value is <code>true</code></p>
enable_ase_detected_attack	<p>When <code>true</code>, activates the real-time security in ASE. ASE detects and blocks pattern enforcement violations, wrong API keys and clients providing decoy API and later accessing real APIs. The default value is <code>false</code>.</p>
<b>API deception</b>	
decoy_alert_interval	<p>The time interval between decoy API email alerts.</p> <p>The default value is 180 minutes.</p> <p>Maximum value is 1440 minutes (i.e. 24 hours).</p>
<b>AI-based API security (ABS)</b>	
enable_abs	<p>When <code>true</code>, send access log files to ABS AI Engine for generating API metrics and detecting attacks using machine learning algorithms. Set <code>true</code> when ASE is connected to PingOne.</p>
enable_abs_attack	<p>When <code>true</code>, ASE fetches attack list from ABS AI Engine and blocks access by the clients that are in the attack list.</p> <p>When <code>false</code>, attack list is not downloaded.</p>
abs_attack_request_minute	<p>Time interval in minutes at which ASE fetches ABS attack list. The default value is 10-minutes.</p>
<b>Google Pub/Sub configuration</b>	
enable_google_pubsub	NA
google_pubsub_topic	NA
google_pubsub_concurrency	NA
google_pubsub_qps	NA
google_pubsub_apikey	NA
cache_queue_size	NA

google\_pubsub\_timeout

NA

**Alerts and reports**

enable\_email

When `true`, send email notifications. The default value is `false`. ASE logs the alerts in `balancer.log` file even when email alerts are disabled. See [Email alerts and reports](#) on page 154 for more information.

email\_report

Time interval in days at which ASE sends reports. Minimum value is 1 and the maximum is 7-days. The default value is 1-day.

smtp\_host

Hostname of SMTP server.

smtp\_port

Port number of SMTP server.

smtp\_ssl

Set to `true` if you want email communication to be over SSL. Make sure that the SMTP server supports SSL. If you set `smtp_ssl` to `true` and SMTP server does not support SSL, email communication falls back to non-SSL channel. The default value is `true`.

Set it to `false` if email communication is over a non-SSL channel. The communication will fail if you set the parameter to `false`, but the SMTP server only supports SSL communication.

smtp\_cert\_verification

Set to `true` if you want ASE to verify the SMTP server's SSL certificate. The default value is `true`.

If you set it to `false`, ASE does not verify SMTP server's SSL certificate; however, the communication is still over SSL.

**Note:** If you have configured an IP address as `smtp_host` and set `smtp_cert_verification` to `true`, then make sure that the certificate configured on the SMTP server has the following:

```
X509v3 extensions:
    X509v3 Key Usage:
        Key Encipherment, Data Encipherment
    X509v3 Extended Key Usage:
        TLS Web Server Authentication
    X509v3 Subject Alternative Name:
        IP Address: X.X.X.X
```

sender\_email

Email address for sending email alerts and reports.

sender\_password

Password of sender's email account.

**Note:** You can leave this field blank if your SMTP server does not require authentication.

receiver\_email

Email address to notify about alerts and reports

See [email alerts](#) for more information.

**ASE server resource utilization**

cpu\_usage

Percentage threshold value of CPU utilization.

See [email alerts](#) for more information.

memory_usage	Percentage threshold value of memory usage. See <a href="#">email alerts</a> for more information.
filesystem_size	Percentage threshold value of filesystem capacity. See <a href="#">email alerts</a> for more information.
buffer_size	Customizable payload buffer size to reduce the number of iterations required for reading and writing payloads. Default value is 16KB. Minimum is 1KB and maximum is 32KB.

A sample `ase.conf` file is displayed below:

```
; This is API Security Enforcer's main configuration file. This file is in
the standard .ini format.
; It contains ports, firewall, log, ABS flags. The comments start with a
semicolon (;).

; Defines running mode for API Security Enforcer (Allowed values are inline
or sideband).
mode=inline

; Defines http(s)/websocket(s) ports for API Security Enforcer. Linux user
should have the privilege to bind to these ports.
; If you comment out a port, then that protocol is disabled.
http_ws_port=8000
https_wss_port=8443

; REST API
management_port=8010

; For controller.log and balancer.log only
; 1-5 (FATAL, ERROR, WARNING, INFO, DEBUG)
admin_log_level=4

; Defines the number of processes for a protocol.
; The maximum number of allowed process for each protocol is 6 (1 master + 5
child). The
; following defines 1 process for both http/ws and https/wss protocol.
http_ws_process=1
https_wss_process=1

; Enable or disable access logs to the filesystem (request/response).
; WARNING! It must be set to true for sending logs to ABS for analytics.
enable_access_log=true
; To write access log immediately to the filesystem, set to true.
flush_log_immediate=true

; Setting this value to true will enable this node to participate in an API
Security Enforcer
; cluster. Define cluster configurations in the cluster.conf
enable_cluster=false

; Current API Security Enforcer version has 3 firewall features: API
Mapping, API Pattern
; Enforcement, and Attack Types.
enable_firewall=true

; X-Forwarded For
enable_xff=false
```



```

; SSLv3
enable_sslv3=false

; enable Nagle's algorithm (if NIC card is 1G).
enable_1G=true

; tcp send buffer size in bytes(kernel)
tcp_send_buffer_size=65535
; tcp receive buffer size in bytes(kernel)
tcp_receive_buffer_size=65535

; buffer size for send and receive in KBs (user)
buffer_size=16KB

; Set this value to true, to allow API Security Enforcer to send logs to
  ABS. This
; configuration depends on the value of the enable_access_log parameter.
enable_abs=true

; Set this value to true, to allow API Security Enforcer to fetch attack
  list from ABS.
enable_abs_attack=true

; This value determines how often API Security Enforcer will get attack list
  from ABS.
abs_attack_request_minutes=10

; Set this value to true, to allow API Security Enforcer to fetch published
  API list from ABS.
enable_abs_publish=false

; This value determines how often API Security Enforcer will get published
  API list from ABS.
abs_publish_request_minutes=10

; Set this value to true, to allow API Security Enforcer to block auto
  detected attacks.
enable_ase_detected_attack=false

; Set this value to true to enable email for both alerts and daily reports.
enable_email=false

; Defines report frequency in days [0=no reports, 1=every day, 2=once in two
  days and max is 7 ; days]
email_report=1
; Specify your email settings
smtp_host=smtp://<smtp-server>
smtp_port=587
; Set this value to true if smtp host support SSL
smtp_ssl=true
; Set this value to true if SSL certificate verification is required
smtp_cert_verification=false
sender_email=
sender_password=
receiver_email=

; Defines threshold for an email alert. For example, if CPU usage is 70%,
  you will get an
; alert.
cpu_usage=70
memory_usage=70
filesystem_size=70

```

```

; Authentication method. Format is <auth_agent>::<auth_service>
; Valid values for auth_agent are ase and pam
; ase agent only supports db auth_service
; pam agent can support user configured pam services
; For example ase::db, pam::passwd, pam::ldap etc
auth_method=ase::db

; Enable auditing. Valid values are true or false.
enable_audit=true

; Decoy alert interval in minutes. [min=15, default=3*60, max=24*60]
decoy_alert_interval=180

; Interval for a hostname lookup (in seconds). [min=10, default=60,
max=86400]
hostname_refresh=60

; Syslog server settings. The valid format is host:port. Host can be an FQDN
or an IPv4
; address.
syslog_server=

; Attack List size in MB or GB. [min=64MB, max=1024GB]
; ASE will take 3*(configured memory) internally. Make sure that the system
has at least
; 3*(configured memory) available
; If you are running ASE inside a container, configure the container to use
3*(configured
; memory) shared memory.
attack_list_memory=128MB

; Enable or Disable health check module. ASE uses '/ase' url for both http
and https. This is
; useful if ASE is deployed behind a load balancer.
enable_ase_health=false

; Location for server's trusted CA certificates. If empty, Server's
certificate will not be
; verified.
server_ca_cert_path=

; enable client side authentication. This setting is applicable only in
sideband mode. Once enabled
; request will be authenticated using authentication tokens.
enable_sideband_authentication=false

; enable connection keepalive for requests from gateway to ase.
; This setting is applicable only in sideband mode.
; Once enabled ase will add 'Connection: keep-alive' header in response
; Once disabled ase will add 'Connection: close' header in response
enable_sideband_keepalive=false

; keystore password
keystore_password=OBF:AES:sRNp0W7sSilzrReXeHodKQ:lXcvbBhKZgDTrjQOfOkzR2mpca4bTUcwPAuerM

; enable hostname rewrite for inline mode. ASE will rewrite the host header
in request
; to the server's hostname
enable_hostname_rewrite=false

; enable strict parsing checks for client requests
; If enabled, ASE will block request with invalid header start
; If disabled, it will allow requests
; default value = true

```

```

enable_strict_request_parser=true

; Set the timezone to utc or local. The default timezone is utc.
timezone=utc

; Google Pub Sub Configuration
enable_google_pubsub=false

google_pubsub_topic=/topic/apimetrics

; Number of concurrent connections to Google Pub/Sub
; Minimum: 1, Default: 1000, Maximum: 1024
google_pubsub_concurrency=1000

; Number of messages published per second.
; Minimum: 1, Default: 1000, Maximum: 10000
google_pubsub_qps=1000

; Google service account API key (Optional)
google_pubsub_apikey=

; Maximum number of messages buffered in memory
; If queue is full, messages are written to logs/google_pubsub_failed.log
; Minimum: 1, Default: 300, Maximum: 10000
cache_queue_size=300

; Timeout in seconds to publish a message to Google Pub/Sub.
; Minimum: 10, Default: 30, Maximum: 300
google_pubsub_timeout=30

```

## API naming guidelines

The API name must follow the following guidelines:

- The name should not have the word “model”.
- The name should not have the word “threshold”.
- The name should not have the word “all”.
- The name should not have the word “decoyall”.

Following is the list of allowed characters in API name:

- The maximum characters in API name can be 160
- - (hyphen), \_ (underscore), and white space are allowed in the name
- a-z, A-Z, and 0-9
- The first character must be alphanumeric

## Defining an API using API JSON configuration file in inline mode

The API JSON file parameters define the behavior and properties of your API. The sample API JSON files shipped with ASE can be changed to your environment settings and are populated with default values.

The following table describes the JSON file parameters:

Parameter	Description
protocol	API request type with ws - WebSocket ; ht

url	The value of the URL. "/shopping"- nar "/shopping/elect "/" - entire server (
hostname	Hostname for the API "*" matches any hos
cookie	Name of cookie used
cookie_idle_timeout	The amount of time a The time duration form s: seconds, m: minute <ul style="list-style-type: none"> <li>▪ w: week</li> <li>▪ mnt: month</li> <li>▪ yr: year</li> </ul>
logout_api_enabled	When true, ASE exp
cookie_persistence_enabled	When true, the sub
oauth2_access_token	When true, ASE cap When false, ASE de For more information,
apikey_qs	When API Key is sen For more information,
apikey_header	When API Key is part For more information,
login_url	Public URL used by a
enable_blocking	When true, ASE blo Default value is false.
api_memory_size	Maximum ASE memo The default value is 1
health_check	When true, enable When false, no hea Ping Identity recomm
health_check_interval	The interval in second
health_retry_count	The number of times
health_url	The URL used by AS

health\_check\_headers

Configure one or more headers to inline ASE dependencies.

```
"health_check_headers": [
  "X-Host",
  "X-Custom-Header"
],
```

**Example**

**Example Key**

X-Host

X-Custom-Header

server\_ssl

When set to true, ASE will use SSL for the server.

**Servers:**

The IP address or host name of the server.

host

See [REST API Protection](#)

port

server\_spike\_threshold

server\_connection\_quota

**API Mapping:**

Internal URL is mapped to the external URL.

internal\_url

See [API Name Mapping](#)

The following API Pattern Enforcement parameters only apply when API Firewall is activated

**Flow Control**

ASE flow control ensures that the server does not get overwhelmed.

client\_spike\_threshold

See [WebSocket API Protection](#)

server\_connection\_queueing

bytes\_in\_threshold

bytes\_out\_threshold

protocol\_allowed

List of accepted protocols  
Values can be HTTP,

**Note:** When Fire

http\_redirect

Redirect unencrypted

response\_code

See [Configuring Patte](#)

response\_def

https\_url

methods\_allowed

List of accepted RES

GET, POST, PUT,

content\_type\_allowed

List of content types a

error\_code

Error message gener

error\_type

See [ASE Detected E](#)

error\_message\_body

### Decoy Config

decoy\_enabled

When decoy\_enabled

response\_code

response\_code is the

response\_def response\_message

response\_def is the r

response\_message is

decoy\_subpaths

decoy\_subpaths is th

See [Configuring API](#)

username\_header

The name of the custo  
from the custom head

**Note:** You can co

### JWT

location

When the parameter

location is the place o

username

▪ qs:<key name>

clientid

▪ h:<custom head

▪ h:authorizatio

▪ h:authorizatio

▪ h:cookie:<cool

username is the JWT

clientid is the JWT cla

For more information,

**Note:** You can co

Here is a sample JSON file for a REST API:

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/rest",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    }
  },
  "api_pattern_enforcement": {
    "protocol_allowed": "",
    "http_redirect": {
      "response_code": "",
      "response_def": "",
      "https_url": ""
    },
    "methods_allowed": [],
    "content_type_allowed": "",
    "error_code": "401",
    "error_def": "Unauthorized",
    "error_message_body": "401 Unauthorized"
  },
  "flow_control": {
    "client_spike_threshold": "0/second",
    "server_connection_queueing": false
  },
  "api_memory_size": "128mb",
  "health_check": false,
  "health_check_interval": 60,
  "health_retry_count": 4,
  "health_url": "/health",
  "health_check_headers": {},
  "server_ssl": false,
  "servers": [
    {
      "host": "127.0.0.1",
      "port": 8080,
      "server_spike_threshold": "0/second",
      "server_connection_quota": 0
    },
    {
      "host": "127.0.0.1",
      "port": 8081,
      "server_spike_threshold": "0/second",
      "server_connection_quota": 0
    }
  ],
  "decoy_config": {
    "decoy_enabled": false,
    "response_code": 200,
    "response_def": "",
    "response_message": "",
    "decoy_subpaths": []
  }
}
```

```

    },
    "username_header": "x-username-header",
    "jwt": {
      "location": "h:authorization:bearer",
      "username": "username",
      "clientid": "client_id"
    }
  }
}

```

### Add configured API JSON to ASE

After configuring an API JSON file, add it to ASE to activate ASE processing. To add an API, execute the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_api {file_path/
api_name}
```

After configuring API JSON files for each API, ASE configuration is complete.

### Update a configured API

After activation, an API JSON definition can be updated in real time. Edit the API JSON file located in the `/config/api` directory and make the desired changes. Save the edited API JSON file and execute the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin update_api <api_name>
```

For example,

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin update_api shop
api shop updated successfully
```

## API routing


ASE uses a combination of header hostname and URL suffix to route incoming API requests to the correct backend server. The following sections show scenarios for routing based on server and API name.

- [Multiple host names with same API name](#) for example, shopping.xyz.com/index, trading.xyz.com/index
- [Single host name with different API names](#) for example, shopping.xyz.com/index, shopping.xyz.com/auth
- [Wildcard host name and API name](#)

### Multiple host names with same API name

ASE supports configuring more than one hostname on one ASE node or cluster. It routes the incoming traffic based on the host name and the API configured in the JSON file. For example, traffic to two hosts named shopping.xyz.com and trading.xyz.com is routed based on the configurations in the respective API JSON file.





For incoming API requests, ASE first checks for the host name in the JSON file. If the host name is configured, then it checks for the API name. If both host and API name are defined, then the incoming API request is routed to one of the configured servers.

In the above example, ASE checks whether `shopping.xyz.com` is configured in the JSON file (`shopping.json`). It then checks for the API, `/index`. If it finds both to be present, then it routes the traffic to one of the defined backend servers. Following is a snippet from a sample JSON file which shows the values that should be configured for `shopping.json`:


```
"api_metadata": {
  "protocol": "https",
  "url": "/index",
  "hostname": "shopping.xyz.com",
  "cookie": "JSESSIONID",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": true,
  "cookie_persistence_enabled": false,
```

For each API, configure a separate JSON file.

#### Single host name with different API names

ASE supports configuring the same hostname with different API names. For example, hostname `shopping.xyz.com` has two different APIs, `/index` and `/auth`. Traffic to each API is routed using the API specific JSON file: `shopping-index.json` or `shopping-auth.json`.

In the following illustration, any requests for `shopping.xyz.com/index` are routed by ASE to a server configured in `shopping-index.json`. In this case, `shopping-index.json` file parameters must match for both the hostname and API. Similarly, requests to `shopping.xyz.com/auth`, are routed by ASE to a server configured in `shopping-auth.json`.




### Wildcard hostname and API name

ASE can also be used as a simple load balancer to route traffic for legacy web applications. The load balancing technique used for server load balancing is based on protocol and cookie information. To configure ASE as a simple load balancer, set the following parameters in a JSON file:

```
"hostname": "*",
"url": "/",
```

When hostname "\*" and url "/" are configured in a JSON file, any request that does not match a specific hostname and url defined in another JSON file uses the destination servers specified in this file to route the traffic.



In the above illustration, hostname is configured as "\*" and url as "/". ASE does not differentiate between hostname and API name. It simply balances traffic across all backend servers.

**Note:** For all scenarios, when connections are being routed to a backend server which goes down, ASE dynamically redirects the connections to a live server in the pool.

## Real-time API cybersecurity

API Security Enforcer provides real-time API cybersecurity to stop hackers. Violations are immediately blocked, and attack information is sent to the ABS engine. Real time API Cyber Security is activated only when ASE firewall is enabled.

Enable API cybersecurity

To enable API security, enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_firewall
Firewall is now enabled
```

After enabling API Security, enter the following CLI command to verify cybersecurity is enabled:

```
/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status : started
http/ws : port 80
https/wss : port 443
firewall : enabled
abs : disabled
abs attack : disabled
audit : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

Disable API cybersecurity

To disable ASE's cybersecurity feature, type the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_firewall
Firewall is now disabled
```

After disabling ASE's cybersecurity feature, enter the following CLI command to verify that cybersecurity is disabled:

```
/opt/pingidentity/ase/bin/cli.sh status
Ping Identity Inc., API Security Enforcer
status : started
http/ws : port 80
https/wss : port 443
firewall : disabled
abs : disabled
abs attack : disabled
audit : enabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

## ASE attack detection

API Security Enforcer supports the following real time ASE attack detection and blocking:

- **API pattern enforcement** – validate traffic to ensure it is consistent with the API definition
- **API deception** – blocks hackers probing a decoy API (see [API deception environment](#) on page 247)

#### Enable ASE detected attacks

Enable real-time ASE attack detection by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
enable_ase_detected_attack
ASE detected attack is now enabled
```

#### Disable ASE detected attacks

Disable real-time ASE detected attacks by running the following command on the ASE command line:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
disable_ase_detected_attack
ASE detected attack is now disabled
```

**Note:** When you disable ASE Detected attacks, the attacks are deleted from the blacklist.

#### Configure pattern enforcement

After enabling API cybersecurity, configure API pattern enforcement to block API traffic that does not match the permitted criteria in the following categories:

- Protocol (HTTP, HTTPS, WS, WSS) – only allow the defined protocols
- Method (GET, POST, PUT, DELETE, HEAD) – only allow the specified methods
- Content Type – only allow the defined content type, not enforced if an empty string is entered
- HTTPS Only – only allow HTTPS traffic

ASE blocks attacks based on parameters configured in the API JSON file. If a client request includes values not configured in the API JSON, ASE blocks the connection in real-time. When the connection is blocked, the OAuth2 token, cookie, or IP address is blocked from accessing any APIs.

The following API JSON file snippet shows an example of pattern enforcement parameters:

```
"api_pattern_enforcement": {
  "protocol_allowed": "https",
  "http_redirect": {
    "response_code": 301,
    "response_def": "Moved Permanently",
    "https_url": "https://shopping.xyz.com/login/"
  },
  "methods_allowed": [
    "GET",
    "POST"
  ],
  "content_type_allowed": "application/json",
  "error_code": 401,
  "error_def": "Unauthorized",
  "error_message_body": " Error: Unauthorized"
},
```

The above example sets up the following enforcement:

- Only HTTPS traffic is allowed access to the API. If an HTTP request is sent, it will be redirected to the `https_url` defined in the `http_redirect` section.
- Only GET and POST methods are allowed; PUT, DELETE, and HEAD will be blocked.

- Only application/json content type is allowed; other content types are blocked.

If a request satisfies all three parameters (protocol, method, and content type), ASE will send the request to the backend API server for processing. Otherwise, ASE sends an error code using the following API JSON parameters:

- `Error_code` – for example, “401”
- `error_def` – error definition, for example, “Unauthorized”
- `error_message_body` – error message content, for example, “Error: Unauthorized”

If an empty string is specified for `content_type_allowed`, ASE does not enforce content type for the incoming traffic.

```
"content_type_allowed": ""
```

**Note:** When API security is enabled, the `protocol_allowed` parameter takes precedence over the `protocol` parameter in the beginning of the API JSON file

#### Detection of attacks for pattern enforcement violation

The following is a snippet of access log file showing what is logged when a connection is blocked based on any pattern enforcement violation.

**Note:** Make sure that ASE detected attacks are enabled.

The following example shows a method violation for an OAuth2 token:

```
[Fri Aug 10 15:59:12:435 2018] [thread:14164] [info]
[connectionid:1681692777] [seq:1] [connectinfo:100.100.1.5:36839]
[type:request] [api_id:shop] PATCH /shopapi/categories/list HTTP/1.1
User-Agent: curl/7.35.0
Accept: */*
Host: app
Content-Type: application/text
Cookie: JSESSIONID=ebcookie
Authorization: Bearer OauthTokenusemethodid12345
[Fri Aug 10 15:59:12:435 2018] [thread:14164] [info]
[connectionid:1681692777] [seq:1] [connectinfo:100.100.1.5:36839]
[type:connection_drop] [enforcement:method] [api_id:shop] PATCH /shopapi/
categories/list HTTP/1.1
User-Agent: curl/7.35.0
Accept: */*
Host: app
Content-Type: application/text
Cookie: JSESSIONID=ebcookie
Authorization: Bearer OauthTokenusemethodid12345
```

Violations logged in the ASE access log files are sent to API Behavioral Security engine for further analysis and reporting.

#### API name mapping – hide internal URLs

After enabling API cybersecurity, API name mapping can be configured to protect API servers by hiding internal URLs from the outside world. Internal URLs may also be modified without updating entries in the public DNS server.

For example, the following JSON snippet from an API JSON file maps an external URL (“/index”) for shopping.xyz.com to an internal URL (“/a123”).


```
"api_metadata": {
```

```

"protocol": "http",
"url": "/index",
"hostname": "127.0.0.1",
"cookie": "JSESSIONID",
"cookie_idle_timeout": "200m",
"logout_api_enabled": true,
"cookie_persistence_enabled": false,
"oauth2_access_token": false,
"apikey_qs": "",
"apikey_header": "",
"cookie_persistence_enabled": true,
"login_url": "",
"enable_blocking": true,
"api_mapping": {
  "internal_url": ""
},
"login_url": "/index/login",
"api_mapping": {
  "internal_url": "/a123"
},

```

The following diagram illustrates the data flow from the client to the backend server through ASE:



### Capturing client identifiers

ASE identifies attackers for HTTP(s) and WS(s) protocols using four client identifiers:

- OAuth2 token
- Cookie
- IP address
- API keys
- Username

**Note:** Username is not configured in the `api_metadata` object of API JSON. However, ASE supports the extraction of usernames coming in a JSON Web Tokens (JWTs) or custom headers. For more information, see [Extract user information from JWT in inline mode](#) on page 232 and [Extract username from custom header in inline mode](#) on page 237. For usernames that are not part of either JWTs or custom headers, ABS AI Engine identifies them based on metadata logged in ASE's access logs.

The following sections describe how to configure ASE to capture OAuth2 Tokens and API keys.


### Configure ASE support for OAuth2 tokens

ASE supports capturing and blocking of OAuth2 tokens. To enable OAuth2 token capture, set the value of `oauth2_access_token` to `true` in the API JSON file. Here is a snippet of an API JSON file with OAuth2 Token capture activated. To disable, change the value to `false`.

```
"api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": true,
  "oauth2_access_token": true,
  "apikey_qs": "",
  "apikey_header": "",
  "login_url": "",
  "enable_blocking": true,
  "api_mapping": {
    "internal_url": ""
  }
},
```

When blocking is enabled, ASE checks the token against the list of tokens in the whitelist and blacklist. If the token is in the blacklist, the client using the token is immediately blocked.

When pattern enforcement violations are detected on an API configured to support tokens, the attacking client token is added to the blacklist in real-time, recorded in the ASE access log, and sent to ABS for further analytics. The following diagram shows the traffic flow in an OAuth2 environment:



Configure ASE support for API keys

ASE supports capturing and blocking of API keys. Depending on the API setup, the API key can be captured from the query string or API header. Each API JSON file can be configured with either the query string (`apikey_qs`) or API header (`apikey_header`) parameter.

Here is a snippet of an API JSON file showing API Key being configured to capture the API Key from the Query String (`apikey_qs`).

```
"api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": true,
  "oauth2_access_token": true,
  "apikey_qs": "key_1.4",
  "apikey_header": "",
  "login_url": "",
  "enable_blocking": true,
  "api_mapping": {
    "internal_url": ""
  }
},
```

When an API Key is included in the API JSON file, ASE supports blocking of API keys which are manually added to the Blacklist.

#### Extract user information from JWT in inline mode

ASE supports the decoding of transparent JSON Web Tokens (JWTs) received as part of API requests. It extracts the user information from the JWT and logs it in the ASE access logs. The ABS AI engine analyzes these access logs to detect attacks and anomalies.

The following diagram shows the traffic flow when ASE is in inline mode.





setup. For more information, see [Defining an API using API JSON configuration file in inline mode](#) on page 219.

The following is an example snippet of an API JSON file.

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/rest",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": true,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    },
    "username_header": "",
    "jwt": {
      "location": "h:authorization:bearer",
      "username": "username",
      "clientid": "client_id"
    }
  }
}
```

**Note:**

The values assigned to username and clientid must be different.

The following table describes the parameters in the JWT object of API JSON file.

Parameter	Description
location	<p>The JWT location in an API request. Configure the parameter with a value applicable to your API.</p> <p>The supported values for the location parameter are:</p> <p><b>qs: &lt;key name&gt;</b></p> <p>Set the location parameter with this value when JWT occurs as part of a query string and substitute the &lt;key name&gt; with the query string parameter. For example, "location": "qs:access_token".</p> <pre>https://server.example.com/resource?access_token=mF_9.B5f-4.1JqM&amp;p=q</pre> <p><b>h: &lt;custom header name&gt;</b></p> <p>Set the location parameter with this value when JWT is part of a custom header and substitute the &lt;custom header name&gt; with custom header. For example, "location": "h:X-jwt-header".</p> <pre>X-jwt-header: eyJhbGcUzI1NiI.eyJzDkwIG4gRG9xpZWQ1OjwMjJ9.Dg</pre> <p><b>h:Authorization:bearer</b></p> <p>Set the location parameter with this value when JWT is part of Authorization header, with bearer scheme. For example, "location": "h:Authorization:Bearer".</p> <pre>Authorization: Bearer eyJhbGcUzI1NiI.eyJzdiIxG4gRG9lIiwiziOjJ9.DWPWNg</pre> <p><b>h:Authorization:MAC</b></p> <p>Set the location parameter with this value when JWT is part of Authorization header, with MAC scheme. For example, "location": "h:Authorization:MAC" .</p> <pre>Authorization: MAC id="eyJhbGcUzI1NiI", nonce="272095:dp63hm5s", mac="PNPQW4mg43cjQfEpUs3QWub4o6xE="</pre> <p><b>h:cookie:&lt;cookie key&gt;</b></p> <p>Set the location parameter with this value when JWT occurs as part of a cookie and substitute the &lt;cookie key&gt; with the cookie name. For example, "location": "h:cookie:access_token".</p>

Parameter	Description
username	The JWT claim to extract the username.
clientid	The JWT claim to extract the client-id.

When `enable_blocking` is set to `true`, ASE checks the username against the list of usernames in the whitelist and blacklist. If the username is in the blacklist, the client using the username is blocked.

**Note:** ASE also supports extracting username from a custom HTTP header. However, you can configure username capture from either custom header or JWT, but not both. For more information, see [Extract username from custom header in inline mode](#) on page 237.

#### API discovery process

The ABS AI Engine processes the ASE access logs and discovers new and unknown APIs in your environment. A root API JSON is defined in ASE to enable API discovery by ABS. For more information on API discovery, see [API discovery and configuration](#) on page 347. If the root API JSON has a JWT object configured with values set for all the keys, then the APIs discovered by the ABS will have the JWT object.

The following table explains the behavior of ASE when the API JSON has an incomplete JWT object and describes its impact on the APIs discovered by ABS in your environment.

Scenarios	Behavior of ASE	Impact on API discovery
A JWT object is not configured in API JSON.	ASE processes the API JSON file.	A JWT object gets added to the discovered APIs with all the keys but empty values. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>
A JWT object is configured in API JSON file but with no keys. For example. <pre> "jwt": {} </pre>	ASE does not process the API JSON file.	The API is not discovered.
A JWT object is configured with all the keys present but with no values set. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>	ASE processes the API JSON file.	A JWT object gets added to the discovered APIs with all the keys but empty values. For example. <pre> "jwt": {   "username": "",   "clientid": "",   "location": "" } </pre>

Scenarios	Behavior of ASE	Impact on API discovery
When a JWT object is configured, but not all keys are set. For example. <pre>"jwt": {   "username": "",   "location": "" }</pre>	ASE does not process the API JSON file.	The API is not discovered.

**Note:**

The API JSON file shipped with ASE is compatible with earlier versions of API JSON files. ASE automatically adds an empty JWT object to the API JSON file to maintain compatibility.

### Extract username from custom header in inline mode

This topic discusses the extraction of username from a custom header when API Security Enforcer (ASE) is in inline mode.

ASE supports capturing usernames from custom headers in a request. It extracts the username and logs it in ASE access logs. ASE sends these access log files to API Behavioral Security (ABS) AI Engine to detect attacks. Following is an example snippet of username information logged in to ASE access log.


```
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[connectinfo:127.0.0.0:80] [type:connection] connection received
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:request] [api_id:api1] GET /abcd
HTTP/1.1
```

#### **x-username-header: 12n4uf9ckls**


```
host: http://pi-api-mngmnt.azr-api.net/
accept: */*
content-type: text/plain;charset=UTF-8
```

```
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:backend_info]
[backend_type:nonssl] [0] [api_id:api1] [hostname:not available] backend
selected
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:req_payload] [api_id:api1]
[size:0]
[Tue Dec 15 09:13:45:044 2020] [thread:999] [info] [connectionid:1801979802]
[seq:1] [connectinfo:127.0.0.0:80] [type:user_info] [api_id:api1] username:
12n4uf9ckls
```

The following diagram shows the traffic flow when ASE is in inline mode.



When deployed in inline mode, ASE extracts the username from either JSON Web Token(JWT) or a custom header. It checks the configuration of API JSON file. It first checks the JWT object. If it is configured, then ASE will capture the username from a JWT in the incoming request. Otherwise, ASE checks the `username_header` parameter in API JSON. If it is set, ASE extracts the username from the custom header that comes as part of an incoming request. For more information, see [Configure API JSON](#) section.



**i Important:** ASE supports extracting username from either JWTs or a custom headers. You can configure API JSON to capture username from either custom header or JWT, but not both for a given API. For more information on extracting usernames from JWTs, see [Extract user information from JWT in inline mode](#) on page 232.

### Configure API JSON

The behavior and properties of your API are defined in an API JSON file in the ASE. To enable username capture from a custom header, set the value of the `username_header` parameter to the custom header name containing the username. The following is an example snippet of an API JSON file.

```
{
  "api_metadata": {
```

```

"protocol": "http",
"url": "/rest",
"hostname": "*",
"cookie": "",
"cookie_idle_timeout": "200m",
"logout_api_enabled": false,
"cookie_persistence_enabled": false,
"oauth2_access_token": false,
"apikey_qs": "",
"apikey_header": "",
"login_url": "",
"enable_blocking": true,

"api_mapping": {
  "internal_url": ""
},
"api_pattern_enforcement": {
  "protocol_allowed": "",
  "http_redirect": {
    "response_code": "",
    "response_def": "",
    "https_url": ""
  },
  "methods_allowed": [],
  "content_type_allowed": "",
  "error_code": "401",
  "error_def": "Unauthorized",
  "error_message_body": "401 Unauthorized"
},
"flow_control": {
  "client_spike_threshold": "0/second",
  "server_connection_queueing": false
},
"api_memory_size": "128mb",
"health_check": false,
"health_check_interval": 60,
"health_retry_count": 4,
"health_url": "/health",
"health_check_headers": {},
"server_ssl": false,
"servers": [
  {
    "host": "127.0.0.1",
    "port": 8080,
    "server_spike_threshold": "0/second",
    "server_connection_quota": 0
  },
  {
    "host": "127.0.0.1",
    "port": 8081,
    "server_spike_threshold": "0/second",
    "server_connection_quota": 0
  }
],
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
},
"username_header": "x-username-header",
"jwt": {

```

```

    "location": "",
    "username": "",
    "clientid": ""
  }
}
}

```

For more information, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.

You can optionally block a client. When `enable_blocking` is set to `true`, ASE checks the Username against the list of usernames in the whitelist and blacklist. If the Username is in the blacklist, the client using the Username is blocked.

**Note:** The API JSON file shipped with ASE is compatible with earlier versions of API JSON files. ASE automatically adds an optional `username_header` parameter to the API JSON file to maintain compatibility.

### Manage whitelist and blacklist

ASE maintains the following two types of lists:

- **Whitelist** – List of “safe” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that are not blocked by ASE. The list is manually generated by adding the client identifiers using CLI commands.
- **Blacklist** – List of “bad” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that are always blocked by ASE. The list consists of entries from one or more of the following sources:
  - ABS detected attacks (for example data exfiltration). ABS detected attacks have a time-to-live (TTL) in minutes. The TTL is configured in ABS.
  - ASE detected attacks (for example invalid method, decoy API accessed). The ASE detected attacks
  - List of “bad” clients manually generated by CLI

### Manage whitelists

Valid operations for OAuth2 Tokens, cookies, IP addresses, API keys, and usernames on a whitelist include:

#### Add an entry

- Add an IP address to whitelist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist ip
10.10.10.10
ip 10.10.10.10 added to whitelist

```

- Add a cookie to whitelist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist cookie
JSESSIONID cookie_1.4
cookie JSESSIONID cookie_1.4 added to whitelist

```

- Add a token to whitelist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist token
token1.4
token token1.4 added to whitelist

```

- Add an API Key to whitelist:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist api_key
X-API-KEY key_1.4
api_key X-API-KEY key_1.4 added to whitelist

```



- Add a username to whitelist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist username
abc@example.com
username abc@example.com added to whitelist
```

### View whitelist

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_whitelist
Whitelist
1) type : ip, value : 1.1.1.1
2) type : cookie, name : JSESSIONID, value : cookie_1.1
3) type : token, value : token1.3
4) type : api_key, name : X-API-KEY, value : key_1.4
5) type : username, value : abc@example.com
```

### Delete an entry

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist ip
4.4.4.4
ip 4.4.4.4 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist cookie
JSESSIONID cookie_1.1
cookie JSESSIONID cookie_1.1 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist token
token1.1
token token1.1 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist api_key
X-API-KEY key_1.4
api_key X-API-KEY key_1.4 deleted from whitelist

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist username
abc@example.com
```

### Clear the whitelist

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin clear_whitelist
This will delete all whitelist Attacks, Are you sure (y/n) : y
Whitelist cleared
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin clear_whitelist
This will delete all whitelist Attacks, Are you sure (y/n) : n
Action canceled
```

### Manage blacklists

Valid operations for IP addresses, Cookies, OAuth2 Tokens, and API keys on a blacklist include:

#### Add an entry

- Add an IP address to blacklist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist ip
1.1.1.1
ip 1.1.1.1 added to blacklist
```

- Add a cookie to blacklist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist cookie
JSESSIONID ad233edqsd1d23redwefew
```

```
cookie JSESSIONID ad233edqsd1d23redwefew added to blacklist
```

- Add a token to blacklist:


```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist token
ad233edqsd1d23redwefew
token ad233edqsd1d23redwefew added to blacklist
```

- Add an API Key to blacklist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist api_key
AccessKey b31dfa4678b24aa5a2daa06aba1857d4
api_key AccessKey b31dfa4678b24aa5a2daa06aba1857d4 added to blacklist
```

- Add an username to blacklist:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist username
abc@example.com
username abc@example.com added to blacklist
```

 **Note:** You can also add username with space to blacklist. For example, "your name".

**View blacklist** - entire blacklist or based on the type of real time violation.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist all
Manual Blacklist
1) type : ip, value : 172.168.11.110
2) type : token, value : cdE94R3osh283B7NoiJR41XHgt7gxroot
3) type : username, value : blockeduser
4) type : cookie, name : JSESSIONID, value : pZlhg5s3i8csImMoas7vh81vz
5) type : api_key, name : x-api-key, value :
d4d28833e2c24be0913f4267f3b91ce5
ABS Generated Blacklist
1) type : token, value : fAtTzxFJZ2Zkr7HZ9KM17s7kY2Mu
2) type : token, value : oFQOr11Gj8cCRv1k4849RZOPztPP
3) type : token, value : Rz7vn5KoLUcAhruQZ4H5cE00s2mG
4) type : token, value : gxbkGPNuFJw69Z5PF44PoRIfPugA
5) type : username, value : user1
Realtime Decoy Blacklist
1) type : ip, value : 172.16.40.15
2) type : ip, value : 1.2.3.4
```

**Blacklist based on decoy IP addresses**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist decoy
Realtime Decoy Blacklist
1) type : ip, value : 4.4.4.4
```

**Blacklist based on protocol violations**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_protocol
Realtime Protocol Blacklist
1) type : token, value : token1.1
2) type : ip, value : 1.1.1.1
3) type : cookie, name : JSESSIONID, value : cookie_1.1
```

**Blacklist based on method violations**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_method
```

```

Realtime Method Blacklist
1) type : token, value : token1.3
2) type : ip, value : 3.3.3.3
3) type : cookie, name : JSESSIONID, value : cookie_1.3

```

### Blacklist based on content-type violation

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_content_type
Realtime Content-Type Blacklist
1) type : token, value : token1.2
2) type : ip, value : 2.2.2.2
3) type : cookie, name : JSESSIONID, value : cookie_1.2

```

### ABS detected attacks

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
abs_detected
No Blacklist

```

### Delete an entry

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_blacklist ip
1.1.1.1
ip 1.1.1.1 deleted from blacklist
./bin/cli.sh -u admin -p admin delete_blacklist cookie JSESSIONID
avbry47wdfgd
cookie JSESSIONID avbry47wdfgd deleted from blacklist
./bin/cli.sh -u admin -p admin delete_blacklist token
58fcb0cb97c54afbb88c07a4f2d73c35
token 58fcb0cb97c54afbb88c07a4f2d73c35 deleted from blacklist
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_blacklist api_key
AccessKey b31dfa4678b24aa5a2daa06aba1857d4

```

### Clear the blacklist

```


./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :y
Blacklist cleared
./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :n
Action canceled

```

When clearing the blacklist, make sure that the real-time ASE detected attacks and ABS detected attacks are disabled. If not disabled, the blacklist gets populated again as both ASE and ABS are continuously detecting attacks.

### Map server error messages to custom error messages

Backend server error messages (for example, Java stack trace) can reveal internal information to hackers. ASE supports hiding the internal details and only sending a customized simple error message. The error message mappings are defined in `/config/server_error.json` file.



For each custom HTTP error code, specify all three parameters in `server_error.json`. For example, the snippet of `server_error.json` shows parameters for mapping error codes 500 and 503.

```
{
  "server_error": [
    {
      "error_code" : "500",
      "error_def" : "Internal Server Error",
      "msg_body" : "Contact Your Administrator"
    },
    {
      "error_code" : "503",
      "error_def" : "Service Unavailable",
      "msg_body" : "Service Temporarily Unavailable"
    }
  ]
}
```

In the above example, an ASE which receives an error 500 or 503 message from the application replaces the message with a custom name `error_def` and message `msg_body` as defined in the `server_error.json` file.

To send the original error message from the backend server, do not include the associated error code in the `server_error.json` file. An empty `server_error.json` file as shown below will not translate any backend error messages.

```
{
  "server_error": [
  ]
}
```

**Note:** ASE checks for the presence of the `server_error.json` file. If this file is not available, ASE will not start.


### ASE generated error messages for blocked requests

ASE blocks certain requests based on API Mapping or ABS detected attacks. For these blocked requests, it sends a standard error message back to the client.

The following table describes the error messages:

Blocked Connection	HTTP Error Code	Error Definition	Message Body
Unknown API	503	Service Unavailable	Error: Unknown API
Unknown Hostname	503	Service Unavailable	Error: Unknown Hostname
Malformed Request	400	Bad Request	Error: Malformed Request
IP attack	403	Unauthorized	Error: Unauthorized
Cookie attack	403	Unauthorized	Error: Unauthorized
OAuth2 Token attack	403	Unauthorized	Error: Unauthorized
API Key attack	403	Unauthorized	Error: Unauthorized
Username attack	403	Unauthorized	Error: Unauthorized

The con  
the



### Per API blocking

ASE can be configured to selectively block on a per API basis by configuring an API JSON file parameter. To enable per API blocking for each API, set the `enable_blocking` parameter to `true` in the API JSON. For example:

```
api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": false,
  "oauth2_access_token": false,
  "apikey_qs": "",
  "apikey_header": "",
  "enable_blocking": true,
  "login_url": "",
  "api_mapping": {
    "internal_url": ""
  }
},
```

If per API blocking is disabled, ABS still detect attacks for that specific API, however, ASE does not block them. ASE will continue to block attacks on other APIs with the `enable_blocking` set to `true`.

## API deception environment

A decoy API is configured in ASE and requires no changes to backend servers. It appears as part of the API ecosystem and is used to detect the attack patterns of hackers. When a hacker accesses a decoy API, ASE sends a predefined response (defined in `inresponse_message` parameter in API JSON file) to the client request and collects the request information as a footprint to analyze API ecosystem attacks. ASE does not forward Decoy API request traffic to backend servers.

Decoy API traffic is separately logged in files named with the following format:


`decoy_pid_<pid_number>__yyyy-dd-mm-<log_file_rotation_time>` (for example, `decoy_pid_8787__2017-04-04_10-57.log`). decoy log files are rotated every 24-hours and stored in the `opt/pingidentity/ase/logs` directory.

ASE Provides the following decoy API types:

- In-context decoy APIs
- Out-of-context decoy APIs

### In-context decoy API

In-context decoy APIs consist of decoy paths within existing APIs supporting legitimate traffic to backend servers. Any traffic accessing a decoy path receives a preconfigured response. For example, in the `shopping` API, `/root` and `/admin` are decoy APIs; `/shoes` is a legitimate API path. Traffic accessing `/shoes` is redirected to the backend API server, while the traffic that accesses `/root` or `/admin` receives a preconfigured response.



The following snippet of an API JSON file shows an in-context decoy API:

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/shop",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "login_url": "",
    "api_mapping": {
      "internal_url": ""
    }
  },
  ;
  ; Note – other configuration parameters removed
  ;
  "decoy_config":
  {
    "decoy_enabled": true,
    "response_code" : 200, decoy API Configuration
  }
}
```



```

"response_def" : "OK",
"response_message" : "OK",
"decoy_subpaths": [
"/shop/root",
"/shop/admin"
]
}
}
}
}

```

The API JSON file defines normal API paths consisting of the path /shop. The decoy configuration is enabled for "/shop/root" and "/shop/admin" with the following parameters:


- decoy\_enabled parameter is set to true. If set to false, no decoy paths are configured.
- response\_code is set to 200. When a decoy sub-path is accessed, return a 200 response.
- response\_def is set to OK. When a decoy sub-path is accessed, return OK as the response.

An in-context decoy API can have a maximum of 32 sub-paths configured for an API.

**Warning:** When configuring in-Context decoy APIs, do not leave empty sub-paths which makes your business API into an out-of-context API. No traffic will be forwarded to backend application servers.

### Out-of-context decoy API

Out-of-Context Decoy APIs are independent APIs where every path is a decoy API. Any sub-paths accessed in the API are treated as part of the decoy API. The figure shows an example.



Following is a snippet of a trading API JSON which has been deployed as a decoy API:

```

{
  "api_metadata": {
    "protocol": "http",
    "url": "/account",
    "hostname": "*"
  }
;

```

**; Note – other configuration parameters removed**

```

;
  "decoy_config":
  {
    "decoy_enabled": true,
    "response_code" : 200,
    "response_def" : "OK",
    "response_message" : "OK",           Decoy API Configuration
    "decoy_subpaths": [

  ]
}

```

Since the `decoy_subpaths` parameter is empty, any sub-path accessed by the attacker after `/account` is regarded as a decoy path or decoy API.

After configuring In-Context or Out-of-Context Decoy API, check the API listings by running the `list_api` command:

```

opt/pingidentity/ase/bin/cli.sh list_api -u admin -p
flight ( loaded ), https
shop ( loaded ), https, decoy: in-context
trading ( loaded ), https, decoy: out-context

```

**Real-time API deception attack blocking**

ASE detects any client probing a decoy API. When a client probes an out-of-context decoy API, ASE logs but does not drop the client connection. However, if the same client tries to access a legitimate path in the in-context decoy API, then ASE block the client in real-time. Here is a snippet of an ASE access log file showing real time decoy blocking:

```

[Tue Aug 14 22:51:49:707 2018] [thread:209] [info] [connectionid:1804289383]
[connectinfo:100.100.1.1:36663] [type:connection_drop] [api:decoy]
[request_payload_length:0] GET /decoy/test/test HTTP/1.1
User-Agent: curl/7.35.0
Accept: */*
Host: app
The blocked client is added to the blacklist which can be viewed by running
the view_blacklist CLI command:
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
Realtime Decoy Blacklist
1) type : ip, value : 100.100.1.1

```

**ASE DoS and DDoS protection**

ASE flow control ensures that backend API servers are protected from unplanned or malicious (for example DDoS) surges in API traffic. flow control combines client and backend server traffic control at an API level to protect REST and WebSocket API servers.

**Protection for REST APIs**

- **Client Rate Limiting** – Protects against abnormally high traffic volumes from any client (for example, Denial-of-Service - DoS attack). By controlling inbound requests from REST API clients, client rate limiting protects API servers from being overloaded by a single client.
- **Aggregate Server TCP Connection Limits** – Prevents server overload from too many concurrent TCP connections across one or a cluster of ASE nodes. Restricts the total number of TCP connections allowed from a cluster of ASE nodes to a specific API on each server.
- **Aggregate Server HTTP Request Limits** – Prevents REST API server overload from too many concurrent HTTP requests across one or a cluster of ASE nodes. Unlike traditional per node flow control, this implementation protects any REST API server from too much aggregate client traffic










coming from a cluster of ASE nodes (for example, traffic load bursts, Distributed Denial-of-Service (DDoS) attacks).

- **Client Request Queuing** – Queues and retries REST API session requests when servers are busy.

#### Protection for WebSocket APIs

- **Client Rate Limiting** – Protects against abnormally high traffic volumes from any client (for example, Denial-of-Service - DoS attack). By controlling the client HTTP requests and WebSocket traffic volumes, rate limiting protects API servers from being overloaded by a single client.
- **Aggregate Server Connection Limits** – Prevents server overload from too many simultaneous session connections across one or a cluster of ASE nodes. Restricts the total number of WebSocket sessions allowed from a cluster of ASE nodes to a specific API on each server.
- **Outbound Rate Limiting** – Protects against abnormally high traffic volumes to a client. By managing outbound traffic volumes to WebSocket clients, outbound rate limiting protects against exfiltration.

The following table lists the control functions which apply to each protocol:

	REST API (HTTP/HTTPS)	WebSocket and Secure WebSock
Client Spike Threshold		
Server Connection Quota		
Server Connection Queuing		
Server Spike Threshold		-NA-
Bytes-in Threshold	-NA-	
Bytes-out Threshold	-NA-	

#### REST API protection from DoS and DDoS

Flow control protects REST API servers from DoS and DDoS attacks using four control variables, which are independently configured. By default, no flow control is enabled.


The following table shows the control variables that are configured once in every API JSON file.

Variable	Description
client_spike_threshold	Maximum requests per time-period from a single client IP to REST API.  Time can be in seconds, minutes, or hours.
server_connection_queueing	When <code>true</code> , queue API connection requests when all backends reach server connection quota.  The default value is <code>false</code> .

The following table shows the control variables that are configured for each server in every API JSON file.

Variable	Description
server_connection_quota	Maximum number of concurrent connections to a specific REST API on a server. Prevents aggregate connections from one or a cluster of ASE nodes from overloading a REST API running on a specific server.
server_spike_threshold	Maximum requests per time period to the REST API running on the specified server. Prevents the aggregate request rate from one or a cluster of ASE nodes from overloading a REST API running on a specific server.  Time can be in seconds, minutes, or hours

The following diagram shows the effect of the parameters on traffic flow through ASE to backend servers. In the diagram, client-side flow control is managed by client\_spike\_threshold and server-side flow control is regulated by a combination of server\_spike\_threshold and server\_connection\_quota.



Client flow control monitors incoming traffic from each client connection and drops the session when traffic limits are exceeded. The diagram shows the following client scenarios:

- IP1 sending request volumes that exceed the client\_spike\_threshold value. ASE 1 sends an error message and terminates the session to stop the attack.
- IP2 and IP3 sending request traffic that stays below the client\_spike\_threshold value. Requests are passed to the backend API servers.

Server-side flow control manages traffic volumes and session count for an API on an application server. `server_connection_quota` sets the maximum number of concurrent connections that can be established to each API on a server. `server_spike_threshold` controls the aggregate traffic rate to an API on a server.

The concurrent connections and request rate consist of the aggregate traffic from all ASE nodes forwarding traffic to an API on a server. The diagram shows two server scenarios:

- A new connection request from ASE 1 is allowed because it's within the `server_connection_quota` threshold.
- ASE 2 detects that the combined traffic rate from ASE 1 and ASE 2 will exceed the `server_spike_threshold` for REST API 1. It drops IP 3 traffic and sends an error message to the client.

The following is an example for an application server that explains the scenarios depicted by the previous diagram.

Variable	Configured value
<code>client_spike_threshold</code>	50,000 requests per second per IP
<code>server_spike_threshold</code>	30,000 requests per second per server
<code>server_connection_quota</code>	20,000 concurrent connections per server
<code>server_connection_queueing</code>	true

- Client flow control permits a maximum of 50,000 requests per second from an individual IP. If IP 1, 2, or 3 exceeds the 50,000 per second limit, ASE drops the client session. Otherwise, all requests are passed to the backend servers.
- Server flow control allows 30,000 requests per second to REST API 1 on the application server. If the sum of requests per second from the ASE cluster nodes (ASE 1 + ASE 2 request rate) to REST API1 exceeds 30,000/second, then traffic is dropped from the client causing aggregate traffic to exceed the maximum request rate. Otherwise, ASE 1 and ASE 2 forward all traffic.
- Server flow control allows 20,000 concurrent connections to REST API1 on the application server. If the sum of connections from the ASE cluster nodes (ASE 1 + ASE 2 connection count) to REST API1 exceeds 20,000, then ASE will queue the request for a time because `server_connection_queueing` is enabled. If queuing is not enabled, then the request is dropped.

#### Summary table for REST API flow control

Parameter	Notes
<code>client_spike_threshold</code>	Maximum request rate from a client to an API
<code>server_spike_threshold</code>	Maximum aggregate request rate through ASE cluster nodes to a specific API on a specific server
<code>server_connection_quota</code>	Maximum number of concurrent sessions from ASE cluster nodes to a specific API on a specific server

#### Note:

You can also configure server connection quota and server spike threshold separately for each backend server.

## JSON configuration for REST API flow control

ASE flow control is configured separately for each API using the API JSON file. The following example shows the flow control related definitions in an API JSON file.

```
{
  "api_metadata": {
    "protocol": "http",

    "flow_control": {
      "client_spike_threshold": "0/second",
      "server_connection_queueing" : false
    },
    "servers": [
      {
        "host": "127.0.0.1",
        "port": 8080,
        "server_spike_threshold": "100/second",
        "server_connection_quota": 20
      },
      {
        "host": "127.0.0.1",
        "port": 8081,
        "server_spike_threshold": "200/second",
        "server_connection_quota": 40
      }
    ]
  }
}
```

The flow control section includes definitions that apply globally across the API definition and include `client_spike_threshold` and `server_connection_queueing`. Server specific definitions include `server_spike_threshold` and `server_connection_quota`, which are configured on each individual server. The default is no flow control with all values set to 0.

You can specify different values for each server for `server_connection_quota` and `server_spike_threshold`.

### Note:

If server connection quota is set to 0 for one server, then it must be 0 for all other servers in the API JSON definition.

## Flow control CLI for REST API

You can use the ASE CLI to update flow control parameters.

### Update client spike threshold

Enter the following command to update the client spike threshold, for example,  
`update_client_spike_threshold shop_api 5000/second.`

```
update_client_spike_threshold {api_id} {+ve digit/(second|minute|hour)}
```

### Update server spike threshold

Enter the following command to update the server spike threshold, for example,  
`update_server_spike_threshold shop_api 5000/second.`

```
update_server_spike_threshold {api_id} {host:port} {+ve digit/(second|minute|hour)}
```

## Update server connection quota

Enter the following command to update the server connection quota, for example, `update_server_connection_quota shop_api 5000`.

```
update_server_connection_quota {api_id} {host:port}{+ve digit}
```

**Note:**


API security must be enabled for ASE flow control to work. For more information on enabling API security, see [Enable API security](#).

## WebSocket API protection from DoS and DDoS

Flow control protects WebSocket servers using five control variables which are independently configured. By default, no flow control is enabled.

Variable	Description
<b>Configured once in every API JSON file</b>	
<code>client_spike_threshold</code>	<p>Maximum number of HTTP requests per time-period from a single IP to a specific WebSocket API.</p> <p>Time can be in seconds, minutes or hours.</p>
<code>bytes_in_threshold</code>	<p>Maximum number of bytes per time-period from a single IP to an ASE node.</p> <p>Time can be in seconds, minutes or hours.</p>
<code>bytes_out_threshold</code>	<p>Maximum number of bytes per time-period sent from an ASE node to a single IP.</p> <p>Time can be in seconds, minutes or hours.</p>
<code>server_connection_queueing</code>	<p>When <code>true</code>, queue connection requests when all backend servers reach the server connection quota.</p> <p>The default value is <code>false</code>.</p>
<b>Configured for each server in every API JSON file</b>	
<code>server_connection_quota</code>	<p>Maximum number of concurrent connections to a specific WebSocket API on a server. Prevents aggregate connections from one or a cluster of ASE nodes from overloading a WebSocket API on a specific server.</p>

The following diagram shows the effect of the parameters on traffic flow through ASE. In the diagram, client-side flow control is managed by `client_spike_threshold`, `bytes_in_threshold`, and `bytes_out_threshold`. The `bytes_out` threshold protects against data exfiltration. Server flow control is regulated by `server_connection_quota`.



Client flow control monitors incoming traffic from each client connection and drops sessions when HTTP request or bytes in threshold limits are exceeded. In addition, outbound traffic from each ASE Node is monitored to protect against exfiltration. The diagram shows client scenarios including:

- IP1 sending HTTP request volumes which exceed the client\_spike\_threshold value. ASE 1 sends an error message and terminates the session to stop the attack.
- IP2 sending WebSocket streaming traffic volumes which exceed the bytes\_in\_threshold limits. ASE 1 sends an error message and terminates the session to stop the traffic.
- IP3 and IP4 within client spike threshold and bytes in threshold criteria and requests are forwarded to the backend server.
- Traffic from ASE 2 to IP5 exceeds the bytes out threshold value. ASE blocks the traffic and drops the client session.

The server-side flow control provides the ability to control session count to an API on an application server. server\_connection\_quota sets the maximum number of concurrent connections that can be established



to an API on a server. The concurrent connections are the aggregate connections from all ASE nodes forwarding traffic to the specified API on a given server.

### Example:

Here is an example with a hypothetical deployment for the Application Server in the previous diagram.

Variable	Configured value
client_spike_threshold	50,000 requests per second per IP
bytes_in_threshold	2000 bytes per second per IP
bytes_out_threshold	1000 bytes per second per server
server_connection_quota	20,000 concurrent connections per server
server_connection_queueing	true

Client flow control permits a maximum of 50,000 HTTP requests/second from an individual IP. If IP 1, 2, or 3 exceeds the 50,000/second limit, ASE drops the client session. Otherwise, all requests are passed to the backend servers.

Client flow control allows a maximum of 2,000 bytes/second from each WebSocket client connection to an ASE node. If IP 1, 2, or 3 exceeds the 2,000 bytes/second limit, ASE drops the client session. Otherwise, all requests are passed to the backend servers.

Server flow control allows 20,000 concurrent connections to WebSocket API 1 on the application server. If the sum of connections from the ASE cluster nodes (i.e. ASE 1 + ASE 2 connection count) to WebSocket API1 exceeds 20,000, then ASE will queue the request for a time-period since server\_connection\_queueing is enabled. If queuing is not enabled, then the request is dropped.

Client Flow Control allows a maximum of 1,000 bytes/second from a WebSocket API to any WebSocket client connection. If outbound traffic exceeds the 1,000 bytes/second limit, ASE blocks the traffic and drops the client session. Otherwise, all requests are passed to the backend servers.

### Summary table for WebSocket flow control

Parameter	Notes
client_spike_threshold	Maximum HTTP request rate from a client to an API
bytes_in_threshold	Maximum number of bytes per time-period from a client to a specific ASE node
bytes_out_threshold	Maximum number of bytes per time-period from an ASE node
server_connection_quota	Maximum number of concurrent sessions from ASE cluster nodes to an API on a specific server.

### Configuring flow control for WebSocket API

ASE flow control is configured separately for each API using the API JSON file. Here are the flow control related definitions in an API JSON file:

```
{
  "api_metadata": {
    "protocol": "ws",

    "flow_control": {
      "client_spike_threshold": "0/second",
      "bytes_in_threshold": "0/second",
      "bytes_out_threshold": "0/second",
```

```

"server_connection_queueing" : false
},
"servers": [
{
"host": "127.0.0.1",
"port": 8080,
"server_connection_quota": 10
},
{
"host": "127.0.0.1",
"port": 8081,
"server_connection_quota": 20
}
]
}

```

The flow control section includes definitions which apply globally across all servers running the defined WebSocket API. These are `client_spike_threshold`, `bytes_in_threshold`, `bytes_out_threshold`, and `server_connection_queueing`. Server specific definitions include `server_connection_quota` which is configured on each individual server. The default is no flow control with all values set to zero. Note that different values can be specified for each server for `server_connection_quota`.

**Note:** If server connection quota is set to zero for one server, then it must be zero for all other servers in the API JSON definition..

**Note:** API security must be enabled for ASE flow control to work. For more information on enabling API security using the configuration file, see [Defining an API using API JSON configuration file in inline mode](#) on page 219 or using the CLI, see [Enable API Cybersecurity](#)

### Flow control CLI for WebSocket API

ASE CLI can be used to update flow control parameters:

#### Update Client Spike Threshold:

Enter the following command to update the client spike threshold:

```
update_client_spike_threshold {api_id} {+ve digit/(second|minute|hour)}
```

For example: `update_client_spike_threshold shop_api 5000/second`

#### Update Bytes-in

```
update_bytes_in_threshold {api_id} {+ve digit/(second|minute|hour)}
```

For example: `update_bytes_in_threshold shop_api 8096/second`

#### Update Bytes-out

```
update_bytes_out_threshold {api_id} {+ve digit/(second|minute|hour)}
```

For example: `update_bytes_out_threshold shop_api 8096/second`

#### Update Server Quota

```
update_server_connection_quota {api_id} {host:port}{+ve digit}
```

For example: `update_server_connection_quota shop_api 5000`

**Note:** API security must be enabled for ASE flow control to work. For more information on enabling API security, see [Enable API Cybersecurity](#).

### Server connection queuing for REST and WebSocket APIs

ASE can queue server connection requests when the backend API servers are busy. When enabled, server connection queuing applies to both REST and WebSocket APIs and is configured in the API JSON file.

#### Connection queuing for stateless connections

Stateless connections are connections without cookies. Before enabling connection queuing, configure connection quota values for the backend API servers. After both connection quota and connection queuing are set, the requests are routed based on the following weightage formula:

$$\frac{Q_i}{\sum_{i=1}^n Q_i}$$

Where  $Q_i$  is the server connection quota for servers from  $i=1$  to  $i=n$

For example, if two backend servers have connection quota set as 20,000 and 40,000 connections, then the connections are served in a ratio of  $20000 / (20000+40000)$  and  $40000 / (20000+40000)$ , that is, in the ratio of 1/3 and 2/3 for the respective servers.

When queuing is enabled and the backend servers are occupied, the connections are queued for a period. The connections are forwarded to the next available backend server during the queuing period based on the weighted ratio of server connection quota.

#### Connection queuing for stateful connections

Stateful connections are connections with cookies. In this mode, cookies are used to establish sticky connections between the client and the server. Before enabling connection queuing, configure connection quota values for the backend API servers. After both connection quota and connection queuing are set, the requests are routed based on the following formula:

$$\frac{Q_i}{\sum_{i=1}^n Q_i}$$


Where  $Q_i$  is the server connection quota for servers from  $i=1$  to  $i=n$

For example, if two backend servers have connection quota set as 20,000 and 40,000 connections, then the connections are served in a ratio of  $20000 / (20000+40000)$  and  $40000 / (20000+40000)$ , that is, in the ratio of 1/3 and 2/3 for the respective servers. The weighted ratio of connection distribution is reached when the server connection quota is reached for all backend servers. Stateful connection distribution considers cookie stickiness with backend servers.

When queuing is enabled and the backend servers are occupied, the connections are queued for a period. Stateful connections are attempted with the same backend server. If the server becomes available during the queuing period, the connections are served. If the backend server is not available, the connections are dropped.

## ABS AI-based security

ABS AI engine detects attacks using artificial intelligence (AI) algorithms. After receiving ASE access logs and API JSON configuration files, ABS applies AI algorithms to track API connections and detect attacks. If `enable_abs_attack` is `true`, ABS sends blacklist to ASE which blocks client identifiers, like, API keys, usernames, cookie, IP address, and OAuth token on the list.



### Configure ASE to ABS connectivity

To connect ASE to ABS, configure the ABS address (IPv4:Port or Hostname:Port), access key, and secret key in the `abs.conf` file located in the `/<ASE installation path>/pingidentity/ase/config` directory.

**Note:** `enable_abs` must be set to `true` in the `ase.conf` file. when ABS is in a different AWS security group, use a private IP address

The parameter values and descriptions are included in the following table:

Parameter	Description
<code>deployment_type</code>	The ABS deployment mode. Valid values are <code>cloud</code> or <code>onprem</code> . The default value is <code>onprem</code> .

gateway_credential	This parameter is used when ABS is deployed in <code>cloud</code> mode. The credential generated in PingOne, while creating a PingIntelligence connection is assigned here so that PingOne can authenticate the data sent by ASE during runtime. For more information on PingOne connections, see <a href="#">Connections</a> .
abs_cloud_endpoint	Use this parameter to assign an endpoint other than the one decoded by the gateway credentials. It's used when ABS is deployed in <code>cloud</code> mode.
abs_endpoint	The parameter has two possible configurations: <ul style="list-style-type: none"> <li>▪ <b>When ABS is deployed with a load balancer</b> - Configure the hostname and port or the IPv4 and port of the load balancer.</li> </ul> <div data-bbox="844 567 1624 693" style="border: 1px solid #ccc; padding: 5px;"> <p><b>Note:</b> To allow the load balancer to bind ASE's session to a specific ABS node, enable cookie stickiness in the load balancer PISESSIONID cookie.</p> </div> <ul style="list-style-type: none"> <li>▪ <b>When ABS is deployed without a load balancer</b> - Configure the parameter with the hostname and port or the IPv4 and port of all the ABS nodes in a cluster. If later a new ABS node is added to the cluster, add its hostname or IPv4 to the list and restart ASE.</li> </ul>
access_key	The access key or the username for the ABS nodes. It is the same for all the ABS nodes. The same value has to be configured in ABS MongoDB database. This value is obfuscated during the start of ASE. This parameter is used when ABS is deployed in <code>onprem</code> mode. <div data-bbox="812 997 1624 1071" style="border: 1px solid #ccc; padding: 5px;"> <p><b>Note:</b> ":" is a restricted character and allowed in access key.</p> </div>
secret_key	The secret key or the password for the ABS nodes. It is the same for all the ABS nodes. The same value has to be configured in ABS MongoDB database. This value is obfuscated during the start of ASE. This parameter is used when ABS is deployed in <code>onprem</code> mode. <div data-bbox="812 1228 1624 1302" style="border: 1px solid #ccc; padding: 5px;"> <p><b>Note:</b> ":" is a restricted character and allowed in secret key.</p> </div>
enable_ssl	Set the value to true for SSL communication between ASE and ABS. The default value is true. ASE sends the access log files in plain text if the value is set to false. This parameter is used when ABS is deployed in <code>onprem</code> mode.
abs_ca_cert_path	Location of the trusted CA certificates for SSL/TLS connections from ASE to ABS. <p>If the path parameter value is left empty, then ASE does not verify the validity of CA certificates. However, the connection to ABS is still encrypted. This parameter is used when ABS is deployed in <code>onprem</code> mode.</p>

**Note:** The `access_key` and `secret_key` are configured in ABS. For more information, see *ABS Admin Guide*.

Here is a sample `abs.conf` file.

```
; API Security Enforcer ABS configuration.;
This file is in the standard .ini format.
The comments start with a semicolon (;).;
Following configurations are applicable only if ABS is enabled with true.
; Configure ABS deployment type. Supported values (onprem/cloud)
deployment_type=onprem

; PingIntelligence Gateway Credentials
gateway_credential=

; ABS endpoint for cloud
abs_cloud_endpoint=

; a comma-separated list of abs nodes having hostname:port or ipv4:port as
  an address.
abs_endpoint=127.0.0.1:8080

; access key for abs node
access_key=OBF:AES://ENOzsqOEhDBWLDY
+pIoQ:~N6wflLiHTTd3oVNzvtXuAaOG34c4JBD4XZHgFCaHry0

; secret key for abs node
secret_key=OBF:AES:Y2DadCU4JFZp3bx8EhnOiw:zzi77GIFF5xkQJccjIrIVWU
+RY5CxUhp3NLcNBel+3Q

; Setting this value to true will enable encrypted communication with ABS.
enable_ssl=true

; Configure the location of ABS's trusted CA certificates. If empty, ABS's
  certificate
; will not be verified
abs_ca_cert_path=
```

### Configuring ASE-ABS encrypted communication

To enable SSL communication between ASE and ABS so that the access logs are encrypted and sent to ABS, set the value of `enable_ssl` to `true`. The `abs_ca_cert_path` is the location of ABS's trusted CA certificate. If the field is left empty, ASE does not verify ABS's certificate, however, the communication is still encrypted.

### Check and open ABS ports

The default port for connection with ABS is 8080. Run the `check_ports.sh` script on the ASE machine to determine ABS accessibility. Input ABS host IP address and ports as arguments.

```
/opt/pingidentity/ase/util ./check_ports.sh {ABS IPv4:[port]}
```

### Manage ASE blocking of ABS detected attacks

To configure ASE to automatically fetch and block ABS detected attacks, complete the following steps:

1. Enable ASE Security. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_firewall
```

2. Enable ASE to send API traffic information to ABS. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs
```

3. Enable ASE to fetch and block ABS detected attacks. Enter the following command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs_attack
```

After enabling automated attack blocking, ASE periodically fetches the attack list from ABS and blocks the identified connections. To set the time interval at which ASE fetches the attack list from ABS, configure the `abs_attack_request_minute` parameter in `ase.conf` file.

```
; This value determines how often ASE will query ABS.
abs_attack_request_minutes=10
```

### Disable attack list fetching from ABS

To disable ASE from fetching the ABS attack list, entering the following CLI command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs_attack
```

After entering the above command, ASE will no longer fetch the attack list from ABS. However, ABS continues generating the attack list and stores it locally. The ABS attack list can be viewed using ABS APIs and used to manually configured an attack list on ASE. For more information on ABS APIs, see *ABS Admin Guide*.

To stop an ASE cluster from sending log files to ABS, enter the following ASE CLI command.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs
```

After entering this command, ABS will not receive any logs from ASE. Refer to the ABS documentation for information on types of attacks.

## CLI for inline ASE

### Start ASE

#### Description

Starts ASE

#### Syntax

```
./start.sh
```

### Stop ASE

#### Description

Stops ASE

#### Syntax

```
./stop.sh
```

### Help

#### Description

Displays cli.sh help

#### Syntax

```
./cli.sh help
```

### Version

#### Description

Displays the version number of ASE

#### Syntax

```
./cli.sh version
```

### Status

#### Description

Displays the running status of ASE

#### Syntax

```
./cli.sh status
```

### Update Password

#### Description

Change ASE admin password

#### Syntax

```
./cli.sh update_password {-u admin}
```

### Change log level

#### Description

Change balancer.log and controller.log log level

#### Syntax

```
./cli.sh log_level -u admin -p
```

**options** - warn, info, error, fatal, debug

### Get Authentication Method

#### Description

Display the current authentication method

#### Syntax

```
./cli.sh get_auth_method {method} {-u admin}
```

### Update Authentication Method

#### Description

Update ASE authentication method

#### Syntax

```
./cli.sh update_auth_method {method} {-u admin}
```

### Enable Audit Logging

#### Description

Enable audit logging

#### Syntax

```
./cli.sh enable_audit -u admin -p admin
```

### Disable Audit Logging

#### Description

Disable audit logging

#### Syntax

```
./cli.sh disable_audit -u admin -p admin
```

### Add Syslog Server

#### Description

Add a new syslog server

#### Syntax



```
./cli.sh -u admin -p admin add_syslog_server host:port
```

### Delete Syslog Server

#### Description

Delete the syslog server

#### Syntax

```
./cli.sh -u admin -p admin delete_syslog_server host:port
```

### List Syslog Server

#### Description

List the current syslog server

#### Syntax

```
./cli.sh -u admin -p admin list_syslog_server
```

### Add API

#### Description

Add a new API from config file in JSON format. File should have `.json` extension

#### Syntax

```
./cli.sh -u admin -p admin add_api {config_file_path}
```

### Update API

#### Description

Update an API after the API JSON file has been edited and saved.

#### Syntax

```
./cli.sh -u admin -p admin update_api {api_name}
```

### List APIs

#### Description

Lists all APIs configured in ASE

#### Syntax

```
./cli.sh -u admin -p admin list_api
```

### API Info

#### Description

Displays the API JSON file

#### Syntax

```
./cli.sh -u admin -p admin api_info {api_id}
```

### API Count

#### Description

Displays the total number of APIs configured

#### Syntax

```
./cli.sh -u admin -p admin api_count
```

### List API Mappings

#### Description

Lists all the external and internal URL mappings.

#### Syntax

```
./cli.sh -u admin -p admin list_api_mappings
```

## Delete API

### Description

Delete an API from ASE. Deleting an API removes the corresponding JSON file and deletes all the cookies associated with that API

### Syntax

```
./cli.sh -u admin -p admin delete_api {api_id}
```

## Add a Server

### Description

Add a backend server to an API. Provide the IP address and port number of the server

### Syntax

```
./cli.sh -u admin -p admin add_server {api_id}{host:port}[quota]  
[spike_threshold]
```

## List Server

### Description

List all servers for an API

### Syntax

```
./cli.sh -u admin -p admin list_server {api_id}
```

## Delete a Server

### Description

Delete a backend server from an API. Provide the IP address and port number of the server

### Syntax

```
./cli.sh -u admin -p admin delete_server {api_id}{host:port}
```

## Enable Per API Blocking

### Description

Enables attack blocking for the API

### Syntax

```
./cli.sh -u admin -p admin enable_blocking {api_id}
```

## Disable Per API Blocking

### Description

Disable attack blocking for the API

### Syntax

```
./cli.sh -u admin -p admin disable_blocking {api_id}
```

## Enable Health Check

### Description

Enable health check for a specific API

### Syntax

```
./cli.sh -u admin -p admin enable_health_check shop_api
```

## Disable Health Check

### Description

Disable health check for a specific API

### Syntax

```
./cli.sh -u admin -p admin disable_health_check {api_id}
```

## Generate Master Key

### Description

Generate the master obfuscation key ase\_master.key

### Syntax

```
./cli.sh -u admin -p admin generate_obfkey
```

## Obfuscate Keys and Password

### Description

Obfuscate the keys and passwords configured in various configuration files

### Syntax

```
./cli.sh -u admin -p admin obfuscate_keys
```

## Create a Key Pair

### Description

Creates private key and public key pair in keystore

### Syntax

```
./cli.sh -u admin -p admin create_key_pair
```

## Create a CSR

### Description

Creates a certificate signing request

### Syntax

```
./cli.sh -u admin -p admin create_csr
```

## Create a Self-Signed Certificate

### Description

Creates a self-signed certificate

### Syntax

```
./cli.sh -u admin -p admin create_self_sign_cert
```

## Import Certificate

### Description

Import CA signed certificate into keystore

### Syntax

```
./cli.sh -u admin -p admin import_cert {cert_path}
```

## Create Management Key Pair

### Description

Create a private key for management server

### Syntax

```
/cli.sh -u admin -p admin create_management_key_pair
```

## Create Management CSR

### Description

Create a certificate signing request for management server

### Syntax

```
/cli.sh -u admin -p admin create_management_csr
```

## Create Management Self-signed Certificate

**Description**

Create a self-signed certificate for management server

**Syntax**

```
/cli.sh -u admin -p admin create_management_self_sign_cert
```

**Import Management Key Pair****Description**

Import a key-pair for management server

**Syntax**

```
/cli.sh -u admin -p admin import_management_key_pair {key_path}
```

**Import Management Certificate****Description**

Import CA signed certificate for management server

**Syntax**

```
/cli.sh -u admin -p admin import_management_cert {cert_path}
```

**Health Status****Description**

Displays health status of all backend servers for the specified API

**Syntax**

```
./cli.sh -u admin -p admin health_status {api_id}
```

**Cluster Info****Description**

Displays information about an ASE cluster

**Syntax**

```
./cli.sh -u admin -p admin cluster_info
```

**Server Count****Description**

Lists the total number of APIs associated with an API

**Syntax**

```
./cli.sh -u admin -p admin server_count {api_id}
```

**Cookie Count****Description**

Lists the live cookie count associated with an API

**Syntax**

```
./cli.sh -u admin -p admin cookie_count {api_id}
```

**Persistent Connection Count****Description**

Lists the WebSocket or http-keep alive connection count for an API

**Syntax**

```
./cli.sh -u admin -p admin persistent_connection_count {api_id}
```

**Clear cookies****Description**

Clear all cookies for an API

**Syntax**

```
./cli.sh -u admin -p admin clear_cookies{api_id}
```

**Enable Firewall**

**Description**

Enable API firewall. Activates pattern enforcement, API name mapping, manual attack type

**Syntax**

```
./cli.sh -u admin -p admin enable_firewall
```

**Disable Firewall**

**Description**

Disable API firewall

**Syntax**

```
./cli.sh -u admin -p admin disable_firewall
```

**Enable ASE detected attacks**

**Description**

Enable ASE detected attacks

**Syntax**

```
./cli.sh -u admin -p admin enable_ase_detected_attack
```

**Disable ASE Detected Attacks**

**Description**

Disable API firewall

**Syntax**

```
./cli.sh -u admin -p admin disable_ase_detected_attack
```

**Enable ABS**

**Description**

Enable ABS to send access logs to ABS

**Syntax**

```
./cli.sh -u admin -p admin enable_abs
```

**Disable ABS**

**Description**

Disable ABS to stop sending access logs to ABS

**Syntax**

```
./cli.sh -u admin -p admin disable_abs
```

**Enable ABS Detected Attack Blocking**

**Description**

Enable ASE to fetch ABS detected attack lists and block access of list entries.

**Syntax**

```
./cli.sh -u admin -p admin enable_abs_attack
```

**Disable ABS Detected Attack Blocking**

**Description**

Stop ASE from blocking and fetching ABS detected attack list. This command does not stop ABS from detecting attacks.

**Syntax**

```
./cli.sh -u admin -p admin disable_abs_attack
```

**Adding Blacklist****Description**

Add an entry to ASE blacklist using CLI. Valid type values are: IP, Cookie, OAuth2 token, API Key, and username

If type is ip, then Name is the IP address.

If type is cookie, then name is the cookie name, and value is the cookie value

**Syntax**

```
./cli.sh -u admin -p admin add_blacklist {type}{name}{value}
```

**Example**

```
/cli.sh -u admin -p admin add_blacklist ip 1.1.1.1
```

**Delete Blacklist Entry****Description**

Delete entry from the blacklist.

**Syntax**

```
./cli.sh -u admin -p admin delete_blacklist {type}{name}{value}
```

**Example**

```
cli.sh -u admin -p delete_blacklist token 58fcb0cb97c54afbb88c07a4f2d73c35
```

**Clear Blacklist****Description**

Clear all the entries from the blacklist

**Syntax**

```
./cli.sh -u admin -p admin clear_blacklist
```

**View Blacklist****Description**

View the entire blacklist or view a blacklist for the specified attack type (for example, invalid\_method)

**Syntax**

```
./cli.sh -u admin -p admin view_blacklist {all|manual|abs_generated|invalid_content_type|invalid_method|invalid_protocol|decoy}
```

**Adding Whitelist****Description**

Add an entry to ASE whitelist using CLI. Valid type values are: IP, cookie, OAuth2 token, API key, and username

If type is IP, then name is the IP address.

If type is cookie, then name is the cookie name, and value is the cookie value

**Syntax**

```
./cli.sh -u admin -p admin add_whitelist {type}{name}{value}
```

**Example**

```
/cli.sh -u admin -p admin add_whitelist api_key AccessKey 065f73cdf39e486f9d7cda97d2dd1597
```

**Delete Whitelist Entry**

**Description**

Delete entry from the whitelist

**Syntax**

```
./cli.sh -u admin -p admin delete_whitelist {type}{name}{value}
```

**Example**

```
/cli.sh -u admin -p delete_whitelist token 58fcb0cb97c54afbb88c07a4f2d73c35
```

**Clear Whitelist****Description**

Clear all the entries from the whitelist

**Syntax**

```
./cli.sh -u admin -p admin clear_whitelist
```

**View Whitelist****Description**

View the entire whitelist

**Syntax**

```
./cli.sh -u admin -p admin view_whitelist
```

**ABS Info****Description**

Displays ABS status information.

ABS enabled or disabled, ASE fetching ABS attack types, and ABS cluster information

**Syntax**

```
./cli.sh -u admin -p admin abs_info
```

**Enable XFF****Description**

Enable X-Forwarded For

**Syntax**

```
./cli.sh -u admin -p admin enable_xff
```

**Disable XFF****Description**

Disable X-Forwarded For

**Syntax**

```
./cli.sh -u admin -p admin disable_xff
```

**Update Client Spike****Description**

Update Client Spike Threshold

**Syntax**

```
update_client_spike_threshold {api_id} {+ve digit/(second|minute|hour)}
```

**Example**

```
update_client_spike_threshold shop_api 5000/second
```

**Update Server Spike****Description**

Update Server Spike Threshold

``\*`` - use the same value for all servers

### Syntax

```
update_server_spike_threshold {api_id} {host:port} {+ve digit/(second|minute|hour)}
```

### Example

```
update_server_spike_threshold shop_api 127.0.0.1:9090 5000/second
update_server_spike_threshold shop_api "*" 5000/second
```

## Update Bytes-in

### Description

Update bytes in value for a WebSocket API

### Syntax

```
update_bytes_in_threshold {api_id} {+ve digit/(second|minute|hour)}
```

### Example

```
update_bytes_in_threshold shop_api 8096/second
```

## Update Bytes-out

### Description

Update bytes out value for a WebSocket API

### Syntax

```
update_bytes_out_threshold {api_id} {+ve digit/(second|minute|hour)}
```

### Example

```
update_bytes_out_threshold shop_api 8096/second
```

## Update Server Quota

### Description

Update the number of API connections allowed on a backend server

``\*`` - use the same value for all backend servers

### Syntax

```
update_server_connection_quota {api_id} {host:port} {+ve digit}
```

### Example

```
update_server_connection_quota shop_api 127.0.0.1:9090 5000
update_server_connection_quota shop_api "*" 5000
```

## ASE REST APIs using Postman

---

Multiple options are available for accessing the ASE REST API reporting including:

- Postman App
- Java, Python, C Sharp, or similar languages.
- Java client program (such as Jersey)
- C sharp client program (such as RestSharp)


For the Postman application, Ping Identity provides two set of Postman collections which are used by Postman to access the ASE REST API JSON information. The collections for Inline and Sideband ASE. Make sure to install Postman 6.2.5 or higher.




## ASE self-signed certificate with Postman

ASE ships with a self-signed certificate. If you want to use Postman with the self-signed certificate of ASE, then from Postman's settings, disable the certificate verification option. Complete the following steps to disable Postman from certificate verification:


1.

Click on the **spanner**  on the top-right corner of Postman client. A drop-down window is displayed.

2. Select **Settings** from the drop-down window:



3. In the Settings window, switch-off certificate verification by clicking on the SSL certificate verification button:




## View ASE REST APIs in Postman


To view the reports, complete the following steps:

1. Download `ASE_4.3_Inline` or `ASE_4.3_Sideband` and `ASE_4.3_Environment` JSON files from Ping Identity [Download](#) site. These configuration files will be used by Postman.
2. [Download](#) and install the Postman application 6.2.5 or higher.

3. In Postman, **import** the two Ping Identity files downloaded in step 1 by clicking the Import button.



4. After importing the files, click the gear  button in the upper right corner.
5. In the **MANAGE ENVIRONMENTS** pop-up window, click **ASE\_4.3\_Environment**



6. In the pop-up window, configure the following values and then click **Update**

- **ASE\_IP:** IP address of the ASE node.
- **Port:** Port number of the ASE node.
- **Access\_Key\_Header** and **Secret\_Key\_Header:** Use the default values.
- **Access\_Key** and **Secret\_Key:** Use admin for access key and secret key. If you have changed the admin password, use the updated one.
- **API\_Name:** The name of the API which you want to administer.

**Note:** Do not edit any fields that start with the word `System`.

MANAGE ENVIRONMENTS
✕

Environment Name

	VARIABLE	INITIAL VALUE ⓘ	CURRENT VALUE ⓘ	⋮	Persist All	Reset All
<input checked="" type="checkbox"/>	ASE_IP	172.16.40.214	172.16.40.214			
<input checked="" type="checkbox"/>	Port	8010	8010			
<input checked="" type="checkbox"/>	Access_Key_Header	x-ase-access-key	x-ase-access-key			
<input checked="" type="checkbox"/>	Secret_Key_Header	x-ase-secret-key	x-ase-secret-key			
<input checked="" type="checkbox"/>	Access_Key	admin	admin			
<input checked="" type="checkbox"/>	Secret_key	admin	admin			
<input checked="" type="checkbox"/>	API_Name	pubatmapp	pubatmapp			
<input checked="" type="checkbox"/>	System_URL	https://{{ASE_IP}}:{{P...	https://{{ASE_IP}}:{{Port}}/v4/ase			
<input checked="" type="checkbox"/>	List_API	{{System_URL}}/api	{{System_URL}}/api			
<input checked="" type="checkbox"/>	API	{{List_API}}?api_id	{{List_API}}?api_id			
<input checked="" type="checkbox"/>	Server	{{System_URL}}/serv...	{{System_URL}}/server?api_id			
<input checked="" type="checkbox"/>	Cluster	{{System_URL}}/clust...	{{System_URL}}/cluster			
<input checked="" type="checkbox"/>	PersistentConnection	{{System_URL}}/pers...	{{System_URL}}/persistentconnection?api_id			
<input checked="" type="checkbox"/>	FireWall	{{System_URL}}/fire...	{{System_URL}}/firewall			
<input checked="" type="checkbox"/>	UpdateFireWall	{{FireWall}}?status	{{FireWall}}?status			
<input checked="" type="checkbox"/>	Blacklist	{{FireWall}}/blacklist...	{{FireWall}}/blacklist?tag			
<input checked="" type="checkbox"/>	Whitelist	{{FireWall}}/whitelist...	{{FireWall}}/whitelist?tag			
<input checked="" type="checkbox"/>	FlowControl	{{FireWall}}/flowcont...	{{FireWall}}/flowcontrol?api_id			
<input checked="" type="checkbox"/>	FlowControlPerServer	{{FireWall}}/flowcont...	{{FireWall}}/flowcontrol/server?api_id			
	Add a new variable					

ⓘ Use variables to reuse values in different places. Work with the current value of a variable to prevent sharing sensitive values with your team. [Learn more about variable values](#)

Cancel
Update

7. In the main Postman window, select the report to display on the left column and then click **Send**.

## REST API for inline and sideband ASE

ASE REST API allows you to manage adding, removing, and modifying your backend servers. The REST API payload uses a JSON format. REST API also helps in integrating ASE with third-party products. The default port for ASE REST API is 8010.

The following is a list of formats for ASE's REST APIs:

- [Create API \(POST\)](#) – Inline and sideband ASE
- [Read API \(GET\)](#) – Inline and sideband ASE
- [List API \(GET\)](#) – Inline and sideband ASE
- [Update API \(PUT\)](#) – Inline and sideband ASE
- [Create Server \(POST\)](#) – Inline ASE
- [Read Server \(GET\)](#) – Inline ASE
- [Delete Server \(DELETE\)](#) – Inline ASE
- [Read Cluster \(GET\)](#) – Inline ASE
- [Read Persistent Connections \(GET\)](#) – Inline ASE
- [Read Firewall Status \(GET\)](#) – Inline and sideband ASE
- [Update Firewall Status \(POST\)](#) – Inline and sideband ASE
- [Add Attack Type to Blacklist \(POST\)](#) – Inline and sideband ASE
- [Delete Attack Type from the Whitelist \(DELETE\)](#) – Inline and sideband ASE
- [Clear the Blacklist \(DELETE\)](#) – Inline and sideband ASE
- [View Blacklist \(GET\)](#) – Inline and sideband ASE
- [Add Attack Type to Whitelist \(POST\)](#) – Inline and sideband ASE
- [Delete Attack Type from the Whitelist \(DELETE\)](#) – Inline and sideband ASE
- [Clear Whitelist \(DELETE\)](#) – Inline and sideband ASE
- [View Whitelist \(POST\)](#) – Inline and sideband ASE
- [Read Flow Control of an API \(GET\)](#) – Inline ASE
- [Update Flow Control for an API \(POST\)](#) – Inline ASE
- [Update Flow Control for a Server of an API \(POST\)](#) – Inline ASE

### Common request headers

Header	Value
x-ase-access-key	admin
	<b>Note:</b> The default and only allowed access key is admin.
x-ase-secret-key	<Secret Key>
	<b>Note:</b> The default secret key is admin. You can change the default secret key using the <code>update_password</code> command.
Accept	application/json

### Create API (POST)

#### Request

POST	/v4/ase/api?api_id=sample_api
Content-Type	application/json
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

### REST API request

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/your_rest_api",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    },
  },
  "api_pattern_enforcement": {
    "protocol_allowed": "",
    "http_redirect": {
      "response_code": "",
      "response_def": "",
      "https_url": ""
    },
    "methods_allowed": [],
    "content_type_allowed": "",
    "error_code": "401",
    "error_def": "Unauthorized",
    "error_message_body": "401 Unauthorized"
  },
  "flow_control": {
    "client_spike_threshold": "0/second",
    "server_connection_queueing": false
  },
  "api_memory_size": "128mb",
  "health_check": true,
  "health_check_interval": 60,
  "health_retry_count": 4,
  "health_url": "/health",
  "server_ssl": false,
  "servers": [
    {
      "host": "127.0.0.1",
      "port": 8080,
      "server_spike_threshold": "0/second",
      "server_connection_quota": 0
    },
    {
      "host": "127.0.0.1",
      "port": 8081,
      "server_spike_threshold": "0/second",
      "server_connection_quota": 0
    }
  ]
}
```

```

}
],
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
}
}
}

```

### WebSocket API request

```

{
  "api_metadata": {
    "protocol": "ws",
    "url": "/your_websocket_api",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    },
    "api_pattern_enforcement": {
      "protocol_allowed": "",
      "http_redirect": {
        "response_code": "",
        "response_def": "",
        "https_url": ""
      },
      "methods_allowed": [],
      "content_type_allowed": "",
      "error_code": "401",
      "error_def": "Unauthorized",
      "error_message_body": "401 Unauthorized"
    },
    "flow_control": {
      "client_spike_threshold": "0/second",
      "bytes_in_threshold": "0/second",
      "bytes_out_threshold": "0/second",
      "server_connection_queueing": false
    },
    "api_memory_size": "128mb",
    "health_check": true,
    "health_check_interval": 60,
    "health_retry_count": 4,
    "health_url": "/health",
    "server_ssl": false,
    "servers": [
      {
        "host": "127.0.0.1",
        "port": 8080,
        "server_connection_quota": 0
      },
      {

```

```

"host": "127.0.0.1",
"port": 8081,
"server_connection_quota": 0
},
"decoy_config": {
"decoy_enabled": false,
"response_code": 200,
"response_def": "",
"response_message": "",
"decoy_subpaths": []
}
}
}

```

### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{   "status": "success",   "status_message": "success" }</pre>
403	fail	<pre>{   "status": "api_already_exists",   "status_message": "api sample_api already exists" }</pre>
403	fail	<pre>{   "status": "validation_error",   "status_message": "&lt;detailed validation error description" }</pre>

### Read API (GET)

#### Request

GET	/v4/ase/api?api_id=sample_api
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

HTTP Code	Status	Content body (application/json)
-----------	--------	---------------------------------

200

success

**REST API**

```

{
  "api_metadata": {
    "protocol": "http",
    "url": "/your_rest_api",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    },
    "api_pattern_enforcement": {
      "protocol_allowed": "",
      "http_redirect": {
        "response_code": "",
        "response_def": "",
        "https_url": ""
      },
      "methods_allowed": [],
      "content_type_allowed": "",
      "error_code": "401",
      "error_def": "Unauthorized",
      "error_message_body": "401 Unauthorized"
    },
    "flow_control": {
      "client_spike_threshold": "0/second",
      "server_connection_queueing": false
    },
    "api_memory_size": "128mb",
    "health_check": true,
    "health_check_interval": 60,
    "health_retry_count": 4,
    "health_url": "/health",
    "server_ssl": false,
    "servers": [
      {
        "host": "127.0.0.1",
        "port": 8080,
        "server_spike_threshold": "0/second",
        "server_connection_quota": 0
      },
      {
        "host": "127.0.0.1",
        "port": 8081,
        "server_spike_threshold": "0/second",
        "server_connection_quota": 0
      }
    ],
    "decoy_config": {
      "decoy_enabled": false,
      "response_code": 200,
      "response_def": "",
      "response_message": "",
      "decoy_subpaths": []
    }
  }
}

```

**WebSocket API**



**List API (GET)****Request**

GET	/v4/ase/api
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**Response**

HTTP Code	Status	Content body (application/json)
200	success	<pre>{   "api_count": "1",   "api": [     {       "api_id": "sample_api",       "status": "loaded"     }   ] }</pre>
404	not found	<pre>{"status": "api_not_found", "status_message": "api sample_api does not exist"}</pre>

**Update API (PUT)****Request**

PUT	/v4/ase/api?api_id=sample_api
Content-Type	application/json
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**REST API request**

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/your_rest_api",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "",
    "enable_blocking": true,
    "api_mapping": {
      "internal_url": ""
    }
  }
}
```

```

},
"api_pattern_enforcement": {
  "protocol_allowed": "",
  "http_redirect": {
    "response_code": "",
    "response_def": "",
    "https_url": ""
  },
  "methods_allowed": [],
  "content_type_allowed": "",
  "error_code": "401",
  "error_def": "Unauthorized",
  "error_message_body": "401 Unauthorized"
},
"flow_control": {
  "client_spike_threshold": "0/second",
  "server_connection_queueing": false
},
"api_memory_size": "128mb",
"health_check": true,
"health_check_interval": 60,
"health_retry_count": 4,
"health_url": "/health",
"server_ssl": false,
"servers": [
  {
    "host": "127.0.0.1",
    "port": 8080,
    "server_spike_threshold": "0/second",
    "server_connection_quota": 0
  },
  {
    "host": "127.0.0.1",
    "port": 8081,
    "server_spike_threshold": "0/second",
    "server_connection_quota": 0
  }
],
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
}
}

```

### WebSocket API request

```

{
  "api_metadata": {
    "protocol": "ws",
    "url": "/your_websocket_api",
    "hostname": "*",
    "cookie": "",
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": ""
  }
}

```

```

"enable_blocking": true,
"api_mapping": {
  "internal_url": ""
},
"api_pattern_enforcement": {
  "protocol_allowed": "",
  "http_redirect": {
    "response_code": "",
    "response_def": "",
    "https_url": ""
  },
  "methods_allowed": [],
  "content_type_allowed": "",
  "error_code": "401",
  "error_def": "Unauthorized",
  "error_message_body": "401 Unauthorized"
},
"flow_control": {
  "client_spike_threshold": "0/second",
  "bytes_in_threshold": "0/second",
  "bytes_out_threshold": "0/second",
  "server_connection_queueing": false
},
"api_memory_size": "128mb",
"health_check": true,
"health_check_interval": 60,
"health_retry_count": 4,
"health_url": "/health",
"server_ssl": false,
"servers": [
  {
    "host": "127.0.0.1",
    "port": 8080,
    "server_connection_quota": 0
  },
  {
    "host": "127.0.0.1",
    "port": 8081,
    "server_connection_quota": 0
  }
],
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
}
}

```

## Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{ "status" : "success" , "status_message" :   "success" }</pre>
404	fail	<pre>{ "status" : "api_not_found" , "status_message" : "api sample_api does not exist" }</pre>

### Delete API (DELETE)

#### Request

DELETE	/v4/ase/api?api_id=sample_api
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{ "status" : "success" , "status_message" :   "success" }</pre>
404	fail	<pre>{ "status" : "api_not_found" , "status_message" : "api sample_api does not exist" }</pre>

### Create server (POST)

#### Request

POST	/v4/ase/server?api_id=<api>
Content-Type	application/json
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### REST API request

```
{
  "server":
  {
    "host": "192.168.1.100",
    "port": 8080,
    "server_spike_threshold": "1/second",
    "server_connection_quota": 100
  }
}
```

```

}
WebSocket API Request
{
  "server":
  {
    "host": "192.168.1.100",
    "port": 8080,
    "server_connection_quota": 100
  }
}

```

### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{ "status" : "success" , "status_message" : "success" }</pre>
404	fail	<pre>{ "status" : "api_not_found" , "status_message" : "api sample_api does not exist" }</pre>
403	fail	<pre>{ "status" : "validation_error" , "status_message" : "detailed info about validation error" }</pre>
403	fail	<pre>{ "status" : "server_exists" , "status_message" : "server already exists" }</pre>

### Read server (GET)

#### Request

GET	/v4/ase/server?api_id=<api_id>
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

HTTP Code	Status	Content body (application/json)
-----------	--------	---------------------------------

200	success	<p><b>REST API</b></p> <pre>{   "api_id" : "sample_api"   "server_count" : 2,   "server":   [ {     "host" : "192.168.1.100"     "port" : 8080,     "server_connection_quota": 1000,     "server_spike_threshold": "10/second",     "health_status" : "Up"   }, {     "host" : "192.168.1.100"     "port" : 8081,     "server_connection_quota": 1000,     "server_spike_threshold": "10/second",     "health_status" : "Down"   } ] }</pre> <p><b>WebSocket API</b></p> <pre>{   "api_id" : "sample_api"   "server_count" : 2,   "server":   [ {     "host" : "192.168.1.100"     "port" : 8080,     "server_connection_quota": 1000,     "health_status" : "Up"   }, {     "host" : "192.168.1.100"     "port" : 8081,     "server_connection_quota": 1000,     "health_status" : "Down"   } ] }</pre>
404	fail	<pre>{"status" : "api_not_found" , "status_message" : "api sample_api does not exist"}</pre>

**Delete server (DELETE)****Request**

DELETE	/v4/ase/server?api_id=<api>
Content-Type	application/json
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

```
{
  "server":
  {
    "host" : "192.168.1.100",
```

```
"port" : 8080
}
}
```

### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{"status" : "success" , "status_message" :   "success" }</pre>
404	fail	<pre>{"status" : "api_not_found" , "status_message" : "api sample_api does not exist"}</pre>
404	fail	<pre>{"status" : "server_not_found" , "status_message" : "server does not exist"}</pre>
403	fail	<pre>{"status" : "validation_error" , "status_message" : "detailed info about json validation error"}</pre>

### Read cluster (GET)

#### Request

GET	/v4/ase/cluster
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{   "cluster_id" : "test_cluster"   "node_count" : 2 , "node":   [     {       "host" : "192.168.2.100"       "port" : 8080       "uuid" : "1c359368-22b6-4713- a5be-15e5cbbddf7a"       "status" : "active"     },     {       "host" : "192.168.2.101"       "port" : 8080       "uuid" : "2d359368-20b6-4713- a5be-15e5cbbde8d"       "status" : "inactive"     }   ] }</pre>
404	fail	<pre>{"status" : "no_cluster_mode" , "status_message" : "ase is not in cluster mode"}</pre>

### Read persistent connections (GET)

#### Request

GET	/v4/ase/persistentconnection? api_id=sample
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

HTTP Code	Status	Content body (application/json)
200	success	<pre>{   "api_id" : "sample"   "persistent_connection_count" :   {     "ws":1,     "wss":0   } }</pre>
404	fail	<pre>{"status" : "api_not_found" , "status_message" : "api sample does not exist"}</pre>



**Read firewall status (GET)****Request**

GET	/v4/ase/firewall
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**Response**

HTTP code	Status	Content body (application/json)
200	success	{ "status" : "enabled/disabled", "status_message" : "Ok" }

**Update firewall status (POST)****Request**

POST	/v4/ase/firewall?status=enable/disable
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**Response**

HTTP Code	Status	Content body (application/json)
-----------	--------	---------------------------------

200	success	<p><b>If there is a status change</b></p> <pre>{   "status" : "enabled/disabled",   "status_message" : "Firewall is now enabled/disabled" }</pre> <p><b>If there is no change in status</b></p> <pre>{   "status" : "enabled/disabled",   "status_message" : "Firewall is already enabled/disabled" }</pre>
403	fail	<pre>{"status" : "invalid_value" , "status_message" : "query parameter status contains invalid value"}</pre>

### Add attack type to blacklist (POST)

#### Request

POST	/v4/ase/firewall/blacklist
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

```
=====for IP=====
{
  "type" : "ip",
  "value" : "1.1.1.1"
}
=====for Token=====
{
  "type" : "token",
  "value" : "sadjhasiufgkjdsbfkgfa"
}
=====for Cookie/api_key=====
{
  "type" : "cookie/token/api_key",
  "name" : "JSESSIONID",
  "value" : "ljkhasioutfdqbj sdfmakhflia"
}
```

#### Response

Status code	Response body
200 OK	Cookie JSESSIONID ljkhasioutfdqbj sdfmakhflia added to blacklist

403 Forbidden	Cookie JSESSIONID ljkhasioutfdqbjsfdmakhflia already exist
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
403 Forbidden	json parsing error
500 Internal Server Error	unknown error

### Delete attack type to blacklist (DELETE)

#### Request

DELETE	/v4/ase/firewall/blacklist
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

```

=====for IP=====
{
  "type" : "ip",
  "value" : "1.1.1.1"
}
=====for Token=====
{
  "type" : "token",
  "value" : "sadjhasiufgkjdsbfkgfa"
}
=====for Cookie/api_key=====
{
  "type" : "cookie/token/api_key",
  "name" : "JSESSIONID",
  "value" : "ljkhasioutfdqbjsfdmakhflia"
}

```

#### Response

Status code	Response body
200 OK	Cookie JSESSIONID ljkhasioutfdqbjsfdmakhflia deleted from blacklist
403 Forbidden	Cookie JSESSIONID ljkhasioutfdqbjsfdmakhflia already exist
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing

403 Forbidden	authorization failure
403 Forbidden	json parsing error
500 Internal Server Error	unknown error

### Clear the blacklist (DELETE)

#### Request

DELETE	/v4/ase/firewall/blacklist?tag=all
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

Status code	Response body
200 OK	Blacklist cleared
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
500 Internal Server Error	unknown error

### View blacklist (GET)

#### Request

GET	/v4/ase/firewall/blacklist?tag=
Tags	tag=all (default is all)
	<ul style="list-style-type: none"> <li>▪ all</li> <li>▪ manual</li> <li>▪ abs_generated</li> <li>▪ invalid_content_type</li> <li>▪ invalid_method</li> <li>▪ invalid_protocol</li> <li>▪ decoy</li> </ul>
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### Response

Status code	Response body
200 OK	<pre>{   "manual_blacklist" : [     {       "type" : "cookie",       "name" : "JSESSIONID",       "value" : "ljkhasiosalia",     },     {       "type" : "ip",       "value" : "1.1.1.1",     }   ],   "abs_generated_blacklist" : [     {       "type" : "cookie",       "name" : "JSESSIONID",       "value" : "ljkhasisadosalia",     },     {       "type" : "ip",       "value" : "1.1.1.2",     }   ] }</pre>
403 Forbidden	Cookie JSESSIONID ljkhasioutfdqbjbfdmakhflia already exist
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
500 Internal Server Error	unknown error

### Add attack type to whitelist (POST)

#### Request

POST	/v4/ase/firewall/whitelist
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

```
=====for IP=====
{
  "type" : "ip",
  "value" : "1.1.1.1"
}
=====for Token=====
{
  "type" : "token",
```

```

    "value" : "sadjhasiufgkjdsbfkgfa"
  }
  =====for Cookie/api_key=====
  {
    "type" : "cookie/token/api_key",
    "name" : "JSESSIONID",
    "value" : "ljkhasioutfdqbjjsfdmakhflia"
  }

```

## Response

Status code	Response body
200 OK	Cookie JSESSIONID ljkhasioutfdqbjjsfdmakhflia added to whitelist
403 Forbidden	Cookie JSESSIONID ljkhasioutfdqbjjsfdmakhflia already exist
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
403 Forbidden	json parsing error
500 Internal Server Error	unknown error

## Delete attack type from the whitelist (DELETE)

### Request

DELETE	/v4/ase/firewall/whitelist
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

```

  =====for IP=====
  {
    "type" : "ip",
    "value" : "1.1.1.1"
  }
  =====for Token=====
  {
    "type" : "token",
    "value" : "sadjhasiufgkjdsbfkgfa"
  }
  =====for Cookie/api_key=====
  {
    "type" : "cookie/token/api_key",
    "name" : "JSESSIONID",
    "value" : "ljkhasioutfdqbjjsfdmakhflia"
  }

```

**Response**

Status code	Response body
200 OK	Cookie JSESSIONID ljkhasioutfdqbjjsfdmakhflia added to whitelist
403 Forbidden	Cookie JSESSIONID ljkhasioutfdqbjjsfdmakhflia already exist
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
403 Forbidden	json parsing error
500 Internal Server Error	unknown error

**Clear whitelist (DELETE)****Request**

DELETE	/v4/ase/firewall/whitelist?tag=all
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**Response**

Status code	Response body
200 OK	Whitelist cleared
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
500 Internal Server Error	unknown error

**View whitelist (POST)****Request**

GET	/v4/ase/firewall/whitelist
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>

Accept	application/json
--------	------------------

**Response**

Status code	Response body
200 OK	<pre>{   "whitelist" : [     {       "type" : "cookie",       "name" : "JSESSIONID",       "value" : "ljkhasiosalia",     },     {       "type" : "ip",       "value" : "1.1.1.1",     }   ] }</pre>
403 Forbidden	content-type header missing
403 Forbidden	x-ase-access-key header missing
403 Forbidden	x-ase-secret-key header missing
403 Forbidden	authorization failure
500 Internal Server Error	unknown error

**Read flow control of an API (GET)****Request**

GET	/v4/ase/firewall/flowcontrol? api_id=<api_name>
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

**Response**

HTTP code	Status	Content body (application/json)
-----------	--------	---------------------------------



200	success	<p><b>Flow control for REST API</b></p> <pre>{   "api_id": "api_name"   "flow_control": {     "client_spike_threshold": "0/second",     "server_connection_queueing": false   } }</pre> <p><b>Flow control for WebSocket API</b></p> <pre>{   "api_id": "api_name"   "flow_control": {     "client_spike_threshold": "100/second",     "bytes_in_threshold": "10/second",     "bytes_out_threshold": "10/second",     "server_connection_queueing": false   } }</pre>
403	fail	<pre>{"status" : "validation_error" ,   "status_message" : "&lt;detailed                     validation error description" }</pre>
404	fail	<pre>{"status" : "api_not_found" , "status_message" : "api sample does not                     exist"}</pre>

### Update flow control for an API (POST)

#### Request

POST	/v4/ase/firewall/flowcontrol? api_id=<api_name>
x-ase-access-key	<Access Key>
x-ase-secret-key	<Secret Key>
Accept	application/json

#### REST APIs

```
{ "flow_control": {
  "client_spike_threshold": "0/second"
}
```

#### WebSocket APIs

```
{ "flow_control": {
  "client_spike_threshold": "10/second",
```

```
"bytes_in_threshold": "10/second",
"bytes_out_threshold": "10/second"
}
}
```

## Response

HTTP code	Status	Content body (application/json)
200	success	<p><b>Flow control for REST APIs</b></p> <pre>{   "api_id": "api_name"   "flow_control": {     "client_spike_threshold": "0/second",     "server_connection_queueing": false   } } </pre> <p><b>Flow control for WebSocket APIs</b></p> <pre>{   "api_id": "api_name"   "flow_control": {     "client_spike_threshold": "0/second",     "bytes_in_threshold": "10/second",     "bytes_out_threshold": "10/second",     "server_connection_queueing": false   } } </pre>
403	fail	<pre>{ "status" : "validation_error" ,   "status_message" : "&lt;detailed                         validation error description" } </pre>
404	fail	<pre>{ "status" : "api_not_found" , "status_message" : "api sample does not exist" } </pre>

## Update flow control for a server of an API (POST)

### Request

POST	/v4/ase/firewall/flowcontrol/server? api_id=<api_name>
x-ase-access-key	<Access Key>
x-ase-secret-key	<<Secret Key>
Accept	application/json

### REST APIs

```
{
  "server":
  {
    "host": "127.0.0.2",
```

```

"port": 8080,
"server_connection_quota": 1000,
"server_spike_threshold": "10/second"
}
}

```

## WebSocket APIs

```

{
  "server":
  {
    "host": "127.0.0.2",
    "port": 8080,
    "server_connection_quota": 100000
  }
}

```

## Response

HTTP code	Status	Content body (application/json)
200	success	<pre> {   "status": "success",   "status_message": "server updated successfully" } </pre>
403	fail	<pre> {"status" : "validation_error" ,  "status_message" : "&lt;detailed                     validation error description" } </pre>
404	fail	<pre> {"status" : "api_not_found" , "status_message" : "api sample does not                     exist"} </pre>

## Audit log

This appendix details audit log entries in the `audit.log` file. The entries in the audit log files have four components as shown in the following table:

Date	Subject	Action	Resources
YYYY-MM-DD hh:mm:ss	Subject is the module through which actions are performed: CLI, REST API or cluster	Actions are the executed commands.	Resources parameters the actions.

Following are the subjects and their description:

Subject	Description
cli	CLI commands executed
rest_api	REST API requests received by ASE

cluster

Changes requested by peer node in a cluster

Here is sample output of an audit log file:

```
2019-06-13 10:45:12 | cli | delete_api | username=admin, api_id=cart
2019-06-13 10:46:13 | rest_api | GET /v4/ase/cluster | x-ase-access-
key=admin, x-ase-secret-key=*****
2019-06-13 10:46:25 | cluster | delete_api | peer_node=192.168.11.108:8020,
api_id=shop
```

## CLI

The following table lists the actions and resources for ASE CLI

Action	Resources
status	-NA-
add_api	username=, config_file_path=
list_api	username=
api_info	username=, api_id=
api_count	username=
list_api_mappings	username=
delete_api	username=, api_id=
add_server	username=, api_id=, server=, server_spike_threshold=, server_connection_quota=
list_server	username=, api_id=
server_count	username=, api_id=
delete_server	username=, api_id=, server=
create_key_pair	username=
create_csr	username=
create_self_sign_cert	username=
import_cert	username=, cert_path=
health_status	username=, api_id=
enable_health_check	username=, api_id=
disable_health_check	username=, api_id=
update_password	username=
cluster_info	username=
cookie_count	username=, api_id=
enable_firewall	username=
disable_firewall	username=
enable_abs	username=
disable_abs	username=
enable_abs_attack	username=

disable_abs_attack	username=
abs_info	username=
enable_xff	username=
disable_xff	username=
update_bytes_in_threshold	username=, api_id=, bytes_in_threshold=
update_bytes_out_threshold	username=, api_id=, bytes_out_threshold=
update_client_spike_threshold	username=, api_id=, client_spike_threshold=
update_server_spike_threshold	username=, api_id=, server=, server_spike_threshold=
update_server_connection_quota	username=, api_id=, server=, server_connection_quota=
get_auth_method	-NA-
update_auth_method	username=, auth_method=
enable_audit	username=
disable_audit	username=
stop	username=

## REST API

Action	Resource
POST /v4/ase/api	Content-Type=application/json, x-ase-access-key=, x-ase-secret-key=*****
GET /v4/ase/api	-SAME AS ABOVE-
DELETE /v4/ase/api	-SAME AS ABOVE-
POST /v4/ase/server	-SAME AS ABOVE-
GET /v4/ase/server	-SAME AS ABOVE-
DELETE /v4/ase/server	-SAME AS ABOVE-
GET /v4/ase/cluster	-SAME AS ABOVE-
POST /v4/ase/firewall	-SAME AS ABOVE-
GET /v4/ase/firewall	-SAME AS ABOVE-
POST /v4/ase/firewall/flowcontrol	-SAME AS ABOVE-
GET /v4/ase/firewall/flowcontrol	-SAME AS ABOVE-
POST /v4/ase/firewall/flowcontrol/ server	-SAME AS ABOVE-

## Cluster

Action	Resource
add_api	peer_node=, api_id=
delete_api	peer_node=, api_id=

add_server	peer_node=, api_id=, server=, server_spike_threshold=, server_connection_quota=
delete_server	peer_node=, api_id=, server
enable_health_check	peer_node=, api_id=
disable_health_check	peer_node=, api_id=
enable_firewall	peer_node=
disable_firewall	peer_node=
enable_abs	peer_node=
disable_abs	peer_node=
enable_abs_attack	peer_node=
disable_abs_attack	peer_node=
enable_xff	peer_node=
disable_xff	peer_node=
update_bytes_in_threshold	peer_node=, api_id=, bytes_in_threshold=
update_bytes_out_threshold	peer_node=, api_id=, bytes_out_threshold=
update_client_spike_threshold	peer_node=, api_id=, client_spike_threshold=
update_server_spike_threshold	peer_node=, api_id=, server=, server_spike_threshold=
update_server_connection_quota	peer_node=, api_id=, api_id=, server=, server_connection_quota=
enable_audit	peer_node=
disable_audit	peer_node=
stop	peer_node=

## Supported encryption protocols

A complete list of supported encryption protocols for TLS1.2 based on the operating system is shown in the boxes below.

### RHEL 7.6

ECDHE-RSA-AES256-GCM-SHA384	ECDHE-ECDSA-AES128-GCM-SHA256
ECDHE-ECDSA-AES256-GCM-SHA384	DH-RSA-AES128-GCM-SHA256
ECDHE-RSA-AES256-SHA384	ECDHE-RSA-AES128-SHA256
ECDHE-ECDSA-AES256-SHA384	ECDHE-ECDSA-AES128-SHA256
DHE-DSS-AES256-GCM-SHA384	DHE-DSS-AES128-GCM-SHA256
DHE-RSA-AES256-GCM-SHA384	DHE-RSA-AES128-GCM-SHA256
DHE-RSA-AES256-SHA256	DHE-RSA-AES128-SHA256
DHE-DSS-AES256-SHA256	DHE-DSS-AES128-SHA256
ECDH-RSA-AES256-GCM-SHA384	ECDH-RSA-AES128-GCM-SHA256

ECDH-ECDSA-AES256-GCM-SHA384	ECDH-ECDSA-AES128-GCM-SHA256
ECDH-RSA-AES256-SHA384	ECDH-RSA-AES128-SHA256
ECDH-ECDSA-AES256-SHA384	ECDH-ECDSA-AES128-SHA256
AES256-GCM-SHA384	AES128-GCM-SHA256
AES256-SHA256	AES128-SHA256
ECDHE-RSA-AES128-GCM-SHA256	

### Ubuntu 16.04

ECDHE-RSA-AES256-GCM-SHA384	DHE-DSS-AES128-GCM-SHA256
ECDHE-ECDSA-AES256-GCM-SHA384	DHE-RSA-AES128-GCM-SHA256
ECDHE-RSA-AES256-SHA384	DHE-RSA-AES128-SHA256
ECDHE-ECDSA-AES256-SHA384	DHE-DSS-AES128-SHA256
DHE-DSS-AES256-GCM-SHA384	ECDH-RSA-AES128-GCM-SHA256
DHE-RSA-AES256-GCM-SHA384	ECDH-ECDSA-AES128-GCM-SHA256
DHE-RSA-AES256-SHA256	ECDH-RSA-AES128-SHA256
DHE-DSS-AES256-SHA256	ECDH-ECDSA-AES128-SHA256
ECDH-RSA-AES256-GCM-SHA384	AES128-GCM-SHA256
ECDH-ECDSA-AES256-GCM-SHA384	AES128-SHA256
ECDH-RSA-AES256-SHA384	DH-RSA-AES128-GCM-SHA256
ECDH-ECDSA-AES256-SHA384	DH-DSS-AES128-GCM-SHA256
AES256-GCM-SHA384	DH-RSA-AES128-SHA256
AES256-SHA256	DH-DSS-AES128-SHA256
ECDHE-RSA-AES128-GCM-SHA256	DH-DSS-AES256-GCM-SHA384
ECDHE-ECDSA-AES128-GCM-SHA256	DH-RSA-AES256-GCM-SHA384
ECDHE-RSA-AES128-SHA256	DH-RSA-AES256-SHA256
ECDHE-ECDSA-AES128-SHA256	DH-DSS-AES256-SHA256

## Autoscaling ASE in AWS environment

You can auto-scale ASE setup in AWS environment by completing the following steps:

1. Create and AMI for ASE
2. Create an IAM role in the Security, Identity, and Compliance
3. Create the Security Group
4. Create Launch Configuration
5. Create an Autoscale group

### Create an AMI for ASE

Complete the following steps to create an AMI for ASE:

1. Create an RHEL 7.6 or Ubuntu 16.04 LTS EC2 instance
2. Install the AWS CLI by completing the following steps:
  - a. Install Python 2.7
  - b. Enter the following command:

```
sudo curl "https://s3.amazonaws.com/aws-cli/awscli-bundle.zip" -o
"awscli-bundle.zip"
```

- c. Unzip the CLI bundle

```
sudo unzip awscli-bundle.zip
```

- d. Install the CLI:

```
sudo ./awscli-bundle/install -i /usr/local/aws -b /usr/bin/aws
```

3. Download the ASE AWS binary. After downloading the file, copy the ASE file to the `/opt` directory.
4. Untar the binary in the EC2 instance. At the command prompt, type the following command to untar the ASE file:

```
tar -zxvf <filename>
```

**For example:**

```
tar -zxvf ase-rhel-4.0.tar.gz
```

5. To verify that ASE successfully installed, enter the `ls` command at the command prompt. This should list the `pingidentity` directory and the build's tar file. **For example:**

```
/opt/$ ls
pingidentity ase-rhel-4.0.tar.gz
```

6. Change directory to `/opt/pingidentity/ase/bin`
7. Run the `install_service.sh aws` script:

```
/opt/pingidentity/ase/bin$ sudo ./install_service.sh aws
Installing ASE service for AWS Autoscale
This script will install ASE as a service
Do you wish to proceed (y/n)? y
Starting service installation
RHEL7.6 detected, installing ASE service
Created symlink from /etc/systemd/system/multi-user.target.wants/
ase.service to /etc/systemd/system/ase.service.
ASE service successfully installed
```

8. Create an AMI using this EC2 instance.

 **Note:** When you are creating the AMI, do not select the "No Reboot" option

## Creating an IAM role in the security, identity, and compliance

About this task

Complete the following steps to create an IAM role in the security, identity, and compliance:



Steps

1. Create an IAM role by selecting the EC2

Create role 1 2 3

Select type of trusted entity

**AWS service**  
EC2, Lambda and others

**Another AWS account**  
Belonging to you or 3rd party

**Web identity**  
Cognito or any OpenID provider

**SAML 2.0 federation**  
Your corporate directory

Allows AWS services to perform actions on your behalf. [Learn more](#)

Choose the service that will use this role

**EC2**  
Allows EC2 instances to call AWS services on your behalf.

**Lambda**  
Allows Lambda functions to call AWS services on your behalf.

API Gateway	DMS	Elastic Transcoder	Machine Learning	SageMaker
Application Auto Scaling	Data Pipeline	ElasticLoadBalancing	MediaConvert	Service Catalog
Auto Scaling	DeepLens	Glue	OpsWorks	Step Functions
Batch	Directory Service	Greengrass	RDS	Storage Gateway
CloudFormation	DynamoDB	GuardDuty	Redshift	
CloudHSM	EC2	Inspector	Rekognition	
CloudWatch Events	EMR	IoT	S3	
CodeBuild	ElastiCache	Kinesis	SMS	
CodeDeploy	Elastic Beanstalk	Lambda	SNS	
Config	Elastic Container Service	Lex	SWF	

\* Required Cancel Next: Permissions

instance:

2. Assign **AmazonEC2ReadOnlyAccess** privilege to the

Create role 1 2 3

Attach permissions policies

Choose one or more policies to attach to your new role.

Create policy Refresh

Filter: Policy type  Showing 367 results

<input type="checkbox"/>	Policy name	Attachments	Description
<input type="checkbox"/>	AmazonEC2ContainerServiceAutoscaleRole	0	Policy to enable Task Autoscaling for Amazon EC2 Contai...
<input type="checkbox"/>	AmazonEC2ContainerServiceEventsRole	0	Policy to enable CloudWatch Events for EC2 Container Se...
<input type="checkbox"/>	AmazonEC2ContainerServiceforEC2Role	0	Default policy for the Amazon EC2 Role for Amazon EC2 ...
<input type="checkbox"/>	AmazonEC2ContainerServiceFullAccess	0	Provides administrative access to Amazon ECS resources.
<input type="checkbox"/>	AmazonEC2ContainerServiceRole	0	Default policy for Amazon ECS service role.
<input type="checkbox"/>	AmazonEC2FullAccess	2	Provides full access to Amazon EC2 via the AWS Manage...
<input checked="" type="checkbox"/>	AmazonEC2ReadOnlyAccess	5	Provides read only access to Amazon EC2 via the AWS M...
<input type="checkbox"/>	AmazonEC2ReportsAccess	0	Provides full access to all Amazon EC2 reports via the AW...
<input type="checkbox"/>	AmazonEC2RoleforAWSCodeDeploy	0	Provides EC2 access to S3 bucket to download revision. T...
<input type="checkbox"/>	AmazonEC2RoleforDataPipelineRole	0	Default policy for the Amazon EC2 Role for Data Pipeline s...
<input type="checkbox"/>	AmazonEC2RoleforSSM	0	Default policy for Amazon EC2 Role for Simple Systems M...
<input type="checkbox"/>	AmazonEC2SpotFleetAutoscaleRole	0	Policy to enable Autoscaling for Amazon EC2 Spot Fleet

\* Required Cancel Previous Next: Review

role.

3.

Create role

Review

Provide the required information below and review this role before you create it.

Role name\*   
Use alphanumeric and '+, -, @, \_' characters. Maximum 64 characters.

Role description   
Maximum 1000 characters. Use alphanumeric and '+, -, @, \_' characters.

Trusted entities AWS service: ec2.amazonaws.com

Policies AmazonEC2ReadOnlyAccess [↗](#)

Provide the role name: \* Required Cancel Previous **Create role**

## Create the security group

You must create a security group for the following ports used by ASE:

- **Port 80:** Accessible by API Clients/ELB
- **Port 443:** Accessible by API Clients/ELB
- **Port 8010:** Accessible by operations to execute CLI commands and REST API calls.
- **Port 8020:** Only accessible by peer ASE nodes in the same security group.

Create a security group based on the following table:

Type	Protocol	Port	Source
Custom TCP	TCP	80	API clients/ELB
Custom TCP	TCP	443	API clients/ELB
Custom TCP	TCP	80	Same security group
Custom TCP	TCP	443	Same security group
Custom TCP	TCP	8010	Same security group
Custom TCP	TCP	8020	Same security group

## Creating launch configuration

About this task

Create the launch configuration that the auto-scaling group will use. To create the launch configuration, complete the following steps:

Steps

1. Select the AMI created in [Create an AMI for ASE](#) section.
2. Create the EC2 instance based on the sizing requirement.
3. Assign the IAM role created in the [Create an IAM Role in the Security, Identity, and Compliance](#) section to the launch configuration.
4. Complete the creation of launch configuration.

## Creating an auto-scale group

About this task

Complete the following steps to create the auto scale group:

Steps

1. Create an auto-scale group using the launch configuration created in the previous section.
2. (Optional) Attach the ELB to the auto-scale group created in step 1.
3. Configure the following rules for the auto scale group:
  - a. Configure the **“Increase Group Size”** rule - Add one instance, when the Average CPU utilization is greater than 90% for at least 2 consecutive periods of 5-minutes.
  - b. Configure the **“Decrease Group Size”** rule - Remove one instance, when the Average CPU utilization is less than 10% for at least two consecutive periods of 5-minutes.

### Optional: Uninstall the ASE service

If you wish to uninstall the ASE service installed in the [Create an AMI for ASE](#) section, run the following command:

```
/opt/pingidentity/ase/bin$sudo ./uninstall_service.sh
This script will uninstall ASE service
Do you wish to proceed (y/n)? y
Starting service uninstallation
RHEL 7.6 detected, uninstalling ASE Service..
ase stop/waiting
ASE service successfully uninstalled
```

## ASE log messages

The following tables list the critical log messages from `controller.log` and `balancer.log` files. Note that `balancer.log` file is not rotated while `controller.log` file is rotated every 24-hours. For more information on ASE logs, see [ASE management, access and audit logs](#) on page 150

**controller.log** messages:

Log message	Description
unknown cluster uuid	This message is logged in <code>controller.log</code> when a ASE node with a different cluster ID or secret key tries to join an ASE cluster. For more information, see <a href="#">Start ASE cluster</a> on page 133
resolve error	This message is logged in <code>controller.log</code> when ASE is not able to resolve ABS or server hostname
connect error	This message is logged in <code>controller.log</code> when ASE is not able to connect to ABS or a server.
handshake error	This message is logged in <code>controller.log</code> when connection to ABS or server because of problems in SSL handshake.
error while sending message to lb connection	This message is logged in <code>controller.log</code> when there is a IPC connection failure between ASE's controller and balancer modules.

Log message	Description
error while reading message from lb connection	This message is logged in <code>controller.log</code> when there is a IPC connection failure between ASE's controller and balancer modules
License file <i>&lt;license file path&gt;</i> is expired. Please renew your license	This message is logged in <code>controller.log</code> when PingIntelligence license has expired. For more information, see <a href="#">ASE license</a> on page 122.
Unexpected Error	This message is logged in <code>controller.log</code> when ASE's controller module is unavailable. This is a fatal error.
info   event   event type : <i>&lt;event type&gt;</i> event value : <i>&lt;value of event&gt;</i>	The following events are logged logs even if email alert is not enabled: <ul style="list-style-type: none"> <li>▪ Cluster node up</li> <li>▪ Cluster node down</li> <li>▪ server state changed to Up</li> <li>▪ server state changed to Down</li> <li>▪ log upload service failed</li> <li>▪ error while uploading log file</li> </ul> If email_alert is enabled, then all events will be available in logs. Fore more information, see <a href="#">Email alerts and reports</a> on page 154
api memory limit reached. total number of cookies dropped <i>&lt;count&gt;</i>	This message is logged in <code>controller.log</code> when ASE is dropping cookies because of low API memory. For more information, see <code>api_memory_size</code> in <a href="#">Defining an API using API JSON configuration file in sideband mode</a> on page 170
stopping API Security Enforcer	This message is logged in <code>controller.log</code> when ASE stops.
API Security Enforcer started	This message is logged in <code>controller.log</code> when ASE starts.

### balancer.log

Log message	Description
/bin/bash: line 0: echo: write error: Permission denied /bin/bash: line 0: echo: write error: Permission denied	
warn   process_id : <i>process_id_number</i>   tcp_fe   !!!! low memory : connection dropped due to low memory !!!!	This message is logged in <code>controller.log</code> when ASE is runnig low on memory because of which ASE drops the client connections.

# ABS AI Engine

---

The ABS (API Behavioral Security) AI Engine is a Java-based distributed system that analyzes API traffic to provide API traffic insight, visibility, and security.

API traffic information is received from ASE nodes in log files containing:

- Client details such as device, browser, IP address, and operating system
- Session information including HTTP or WebSocket connections and methods

These logs are periodically (every 10 minutes) forwarded to ABS nodes for processing. Using machine learning algorithms, ABS generates API traffic insight, anomaly data, and attack insight that identifies clients responsible for attacks. To prevent future attacks, ABS can automatically program inline devices, such as the ASE (API Security Enforcer), to block clients based on attack lists.

The ABS AI engine provides the following functionality:

- Collection and consolidation of access logs from ASE nodes
- Machine learning algorithms to identify anomalies and attacks
- Detection of attacks from HTTP(s) and WebSocket(s) traffic
- Optional sending of blacklists to ASE which blocks client access
- Centralized database for storing AI data
- Stateless cluster for scalability and resiliency
- REST APIs for fetching traffic metrics, anomalies, and attack information
- Email alerts

Configuring ABS consists of setting up two entities:

## Database system

ABS uses a MongoDB database to store metadata and all Machine Learning (ML) analytics. The MongoDB database system is configured in a replica set for production deployments. MongoDB is separately installed before starting ABS.

## ABS AI engine

One or more ABS instances are configured to receive and process logs and to store results in MongoDB. You should install ABS in a cluster for high availability deployments.

## Administration

---

Administering ABS requires understanding:

- Directory structure
- Obfuscating passwords for securing ABS
- Configuring SSL for secure communication for between PingIntelligence products
- Different types of ABS users
- Understanding the port requirements
- Creating ABS cluster
- Understanding ABS log files
- Purging access logs from ABS
- ABS REST API format

## ABS License

To start ABS, you need a valid license. There are two types of ABS licenses:

- **Trial license** – The trial license is valid for 30-days. At the end of the trial period, ABS stops processing and shuts down.
- **Subscription license** – The subscription license is based on the total number of transactions subscribed per month and the duration of the license. It is a good practice to [configure your email](#) before configuring the ABS license. ABS sends an email notification to the configured email ID when the license has expired. Contact the PingIdentity sales team for more information. The following points should be noted:
  - **Maximum transaction set to 0:** If your subscription ABS license has zero as maximum transaction, it means that the license has unlimited monthly transaction. Such a license only expires at the end of subscription period.
  - **License expiry:** In case when the subscription license has expired, ABS continues to run until a restart. ABS needs a valid license file to start.

### Add an ABS license

If you have not received an ABS license, request a license file from Ping sales. The name of the license file must be `PingIntelligence.lic`. Copy the license file to the `/opt/pingidentity/abs/config` directory and then start ABS.

### Update an existing license

If your existing license has expired, obtain a new license from PingIdentity sales and replace the license file in the `/opt/pingidentity/abs/config` directory. Stop and then start ABS after the license file is updated.

### Checking the current transaction count

Use the [Admin REST API - Duplicate](#) to view the current transaction count against your subscribed transaction limit. Following snippet of the Admin REST API shows the license information:

```
{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "license_info": {
    "tier": "Subscription",
    "expiry": "Wed Jan 15 00:00:00 UTC 2020",
    "max_transactions_per_month": 1000000000,
    "current_month_transactions": 98723545,
    "max_transactions_exceeded": false,
    "expired": false
  }
}
```

## Change default settings

It is recommended that you change the default key and password in ABS. Following is a list of commands to change the default values:

### Change default JKS password

You can change the default password for KeyStore and the key. Complete the following steps to change the default passwords. Make sure that ABS is stopped before changing the JKS password.

1. **Change the KeyStore password:** Enter the following command to change the KeyStore password. The default KeyStore password is `abs123`.

```
# keytool -storepasswd -keystore config/ssl/abs.jks
```

```
Enter keystore password: abs123
New keystore password: newjkspassword
Re-enter new keystore password: newjkspassword
```

- 2. Change the key password:** Enter the following command to change the key password. The default key password is abs123

```
# keytool -keypasswd -alias pingidentity -keypass abs123 -new
newjkspassword -keystore config/ssl/abs.jks
Enter keystore password: newjkspassword
```

Start ABS after you have changed the default passwords.

Change abs\_master.key

Run the following command to create your own ABS master key to obfuscate keys and password in ABS.

**Command:** generate\_obfkey. ABS must be stopped before creating a new abs\_master.key

**Stop ABS:** If ABS is running, then stop ABS before generating a new ABS master key. Enter the following command to stop ABS:

```
# /opt/pingidentity/abs/bin/stop.sh
checking API Behavioral Security status
sending shutdown signal to ABS, please wait...
API Behavioral Security stopped
```

**Change abs\_master.key:** Enter the generate\_obfkey command to change the default ABS master key:

```
/opt/pingidentity/abs/bin/cli.sh generate_obfkey -u admin -p admin
Please take a backup of config/abs_master.key before proceeding.
Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh -obfuscate_keys
Warning: Obfuscation master key file
/pingidentity/abs/config/abs_master.key already exists. This command will
delete it and create a new key in the same file
Do you want to proceed [y/n]: y
Creating new obfuscation master key
Success: created new obfuscation master key at /pingidentity/abs/config/
abs_master.key
```

Change admin password

You can change the default admin password by entering the following command:

```
/opt/pingidentity/abs/bin/cli.sh update_password -u admin -p admin
New Password>
Reenter New Password>
Success. Password updated for CLI
```

Change default access and secret key in MongoDB

To change the default access and secret key, stop the ABS nodes and complete the following steps:

- 1. Connect to MongoDB** by entering the following command:

```
mongo --host <mongo-host> --port <mongo-port> --authenticationDatabase
admin -u absuser -p abs123
```

absuser and abs123 is the default user name and password for MongoDB.

2. On the MongoDB prompt, run the following command:

```
use abs_metadata
db.auth_info.updateOne( { access_key: "<new-access-key>", secret_key:
"<new-secret-key>" } )
```

Start the ABS nodes after you have changed the default access and secret key.

## Obfuscate passwords


Using ABS command line interface, you can obfuscate the keys and passwords configured in `abs.properties`. The keys and passwords obfuscated include:

- `mongo_password`
- `jks_password`
- `email_password`

ABS ships with a default `abs_master.key` which is used to obfuscate the keys and passwords. It is recommended to generate your own `abs_master.key`.

**Note:** During the process of obfuscation of keys and password, ABS must be [stopped](#).

The following diagram summarizes the obfuscation process:



### Generate abs\_master.key

You can generate the `abs_master.key` by running the `generate_obfkey` ABS CLI command.

```
/opt/pingidentity/abs/bin/cli.sh generate_obfkey -u admin -p admin
Please take a backup of config/abs_master.key before proceeding.
Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh -obfuscate_keys
Warning: Obfuscation master key file
/pingidentity/abs/config/abs_master.key already exists. This command will
delete it and create a new key in the same file
Do you want to proceed [y/n]: y
Creating new obfuscation master key
Success: created new obfuscation master key at /pingidentity/abs/config/
abs_master.key
```

The new `abs_master.key` is used to obfuscate the passwords in `abs.properties` file.

**Important:** After the keys and passwords are obfuscated, the `abs_master.key` must be moved to a secure location and not stored on ABS.

In an ABS cluster, the `abs_master.key` must be manually copied to each of the cluster nodes.

### Obfuscate key and passwords

Enter the keys and passwords in clear text in the `abs.properties` file. Run the `obfuscate_keys` command to obfuscate keys and passwords:

```
/opt/pingidentity/abs/bin/cli.sh obfuscate_keys -u admin -p admin
Please take a backup of config/abs.password before proceeding
Enter clear text keys and passwords before obfuscation.
```



```

Following keys will be obfuscated
config/abs.properties: mongo_password, jks_password and email_password
Do you want to proceed [y/n]: y
obfuscating /pingidentity/abs/config/abs.properties
Success: secret keys in /pingidentity/abs/config/abs.properties obfuscated

```

[Start ABS](#) after passwords are obfuscated.

## ABS POC mode

You can run ABS AI engine in (proof-of-concept) POC mode which requires substantially lesser number of requests for detecting an attack. This mode is only for the purpose of demonstrating the capabilities of the AI engine. All the REST API attacks can be detected in the POC mode. For more information on different attack types, see [REST API attack types](#) on page 358 .

**Warning:** Do not deploy the AI engine in production environment in POC mode. It is recommended to uninstall all PingIntelligence components from POC mode and reinstall for production environment. The ABS AI engine in POC mode is not suitable for security testing as well.

### Configure POC mode

You can install ABS AI engine in POC mode by configuring the parameter during automated installation. For more information on configuring the POC mode at the time of installation, see [Changing ABS default settings](#) on page 63.

If you are using manual installation to install ABS AI engine and MongoDB, configure poc to true using the [Global configuration update REST API](#) on page 355.

### Verify the POC mode

Use the ABS Admin REST API to verify whether ABS AI engine is running in the POC mode. The report can be accessed by calling the ABS system at the following URL:

[https://<abs\\_ip>:<abs\\_port>/v5/abs/admin](https://<abs_ip>:<abs_port>/v5/abs/admin).

```

{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "license_info": {
    "tier": "Subscription",
    "expiry": "Sun Feb 21 00:00:00 UTC 2021",
    "max_transactions_per_month": 100000000,
    "current_month_transactions": 41243418,
    "max_transactions_exceeded": false,
    "expired": false
  },
  "across_api_prediction_mode": true,
  "poc": true,

  "api_discovery": {
    "subpath_length": "1",
    "status": true
  },
  ...truncated admin API output...
}

```

## Start and Stop ABS

### Start ABS

To start ABS, run the `start.sh` script located in the `/opt/pingidentity/abs/bin` directory. Change working directory to `/opt/pingidentity/abs/bin`. Then start ABS by typing the following command. To start ABS, you need to accept EULA. You can accept EULA in two ways:

- Scroll through the text on screen and enter `yes` to accept EULA, or
- Use the `--acceptLicense` option with `start.sh` as shown in the screen output below. By using this option, you do not have to scroll through the EULA.

Once the EULA is accepted, ABS creates a `license.accepted` file in the `/opt/pingidentity/abs/config` directory. On subsequent start of ABS, it checks for

```
$ /opt/pingidentity/abs/bin/start.sh --acceptLicense
End-User License Agreement accepted
Starting API Behavioral Security Version 4.1...
please see /opt/pingidentity/abs/logs/abs/abs.log for more details
```

To verify whether ABS has started, change the working directory to `data` directory and look for two `.pid` files, `abs.pid` and `stream.pid`. Check the newly added ABS node is connecting to MongoDB and has a heartbeat.

```
> use abs_metadata
switched to db abs_metadata
> db.abs_cluster_info.find().pretty()
{
  "_id" : ObjectId("58d0c633d78b0f6a26c056ed"),
  "cluster_id" : "c1",
  "nodes" : [
    {
      "os" : "Red Hat Enterprise Linux Server release 7.1 (Maipo)",
      "last_updated_at" : "1490088336493",
      "management_port" : "8080",
      "log_port" : "9090",
      "cpu" : "24",
      "start_time" : "1490077235426",
      "log_ip" : "2.2.2.2",
      "uuid" : "8a0e4d4b-3a8f-4df1-bd6d-3aec9b9c25c1",
      "dashboard_node" : false,
      "memory" : "62G",
      "filesystem" : "28%"
    }
  ]
}
```

### Stop ABS

To stop ABS, first stop API Security Enforcer (if it is running) or turn OFF the ABS flag in API Security Enforcer. If no machine learning jobs are processing, run the `stop.sh` script available in the `bin` directory.

```
# /opt/pingidentity/abs/bin/stop.sh
checking API Behavioral Security status
sending shutdown signal to ABS, please wait...
API Behavioral Security stopped
```

If streaming or machine learning jobs are in progress, add the `force` parameter to kill running jobs and stop ABS.

```
# /opt/pingidentity/abs/bin/stop.sh --force
```

```
checking API Behavioral Security status
sending shutdown signal to ABS, please wait...
API Behavioral Security stopped
```

**Note:** Ensure that you stop ABS before performing any of the following tasks:

- When deleting the ABS directory.
- When deleting the data or metadata DB.
- When changing the user permissions.

Omitting to do so will result in excessive logs in the Mongo DB node.

## ABS users for API reports

ABS has two type of users to access the API reports and PingIntelligence for APIs Dashboard. The API reports displayed is based on the type of user accessing the reports. The two users are:

- **Admin user:** An Admin user has complete access to API reports. All the cookies, tokens, API keys, and Username are visible in the reports. Use the following headers in the API report URL to access API reports as an Admin user:
  - `x-abs-ak` (access key header)
  - `x-abs-sk` (secret key header)
- **Restricted user:** A Restricted user has limited access to the API reports. The Restricted user can view the API reports however the cookies, tokens, and API keys are obfuscated. Use the following headers in the API report URL to access API reports as an Admin user:
  - `x-abs-ak-ru` (access key header)
  - `x-abs-sk-ru` (secret key header)

The restricted user can access all the API Reports except:

- Threshold API
- Cookie, OAuth2 Token, IP, API Key, and Username Forensics APIs

For a complete list of external REST APIs, see [ABS External REST APIs](#).

The default access and secret key are configured in the `opt/pingidentity/mongo/abs_init.js` file. Following is a snippet of the `abs_init.js` showing the default passwords for both type of users.

```
db.auth_info.insert({
  "access_key": "abs_ak",
  "secret_key": "abs_sk",
  "access_key_ru" : "abs_ak_ru",
  "secret_key_ru" : "abs_sk_ru"
});
```

**Note:** You can use `update_keys` CLI command to change access and secret keys. For more information, see [ABS CLI](#) on page 415.

## ABS directory structure

The directories that ABS creates as part of the installation process are shown in the following table:

Directory	Purpose
<code>config</code>	Contains <code>abs.properties</code> , a Java properties file used to configure ABS.
<code>data</code>	Stores logs sent by API Security Enforcer.

logs	Stores all ABS related logs.
lib	For internal use. Do not change anything in this directory.
bin	Contains various scripts to start and stop ABS.
	<div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> Do not edit the scripts in the <code>bin</code> directory.</p> </div>
mongo	Contains the <code>abs_init.js</code> file used to load the default schema, secret key, and access key.
util	<p>Contains utilities to:</p> <ul style="list-style-type: none"> <li>▪ Check and Open MongoDB Default Port</li> <li>▪ Purge the Processed Access Logs from ABS</li> <li>▪ Purge ABS Data from MongoDB</li> <li>▪ Various service and systemctl scripts</li> <li>▪ Reset MongoDB script, and</li> <li>▪ Update script to change the values of global configuration defined in <code>/pingidentity/abs/mongo/abs_init.js</code> file</li> <li>▪ <code>open_ports_abs.sh</code>: Open the default ports 8080 and 9090 for ABS REST API and connectivity from ASE respectively. Run the script on the ABS machine.</li> </ul>

## Configure SSL

ABS supports only TLS 1.1 and TLS 1.2 and requires Open JDK 11.0.2. ABS ships with a default self-signed certificate with Java Keystore at `abs/config/ssl/abs.jks` and the default password set to `abs123` in the `abs.properties` file. The default password is obfuscated in the `abs.properties` file. It is recommended to change the default passwords and obfuscate the new passwords. For more information, see [Obfuscate passwords](#) on page 312.

If you want to use your own CA-signed certificates, you can import them in ABS.

**Note:** The SSL communication between ASE and ABS is by default enabled. If you need to disable it, contact Ping Identity support team.

## Configure time zone - ABS

When configuring PingIntelligence for APIs, you can set up ABS AI Engine in either `local` or `UTC` time zone by configuring the `timezone` parameter in `/pingidentity/abs/config/abs.properties` file. If the `timezone` parameter is left empty, ABS by default runs in the `UTC` time zone. Following is a snippet of `abs.properties` for `timezone` parameter.

```
# Set the timezone to utc or local. The default timezone is utc.
timezone=utc

<truncated abs.properties...>
```

**Note:** Make sure that ASE, ABS AI Engine, and PingIntelligence for APIs are all configured on the same time zone.

If ABS AI Engine is deployed in a cluster, make sure to configure the same time zone on each cluster node. If you have used automated deployment to deploy PingIntelligence, the automated deployment configures the same time zone on each ABS node. However, if you have used manual installation, then you need to manually configure the time zone on each ABS node. You can use the [Admin API](#) to check the current time zone setting of ABS AI Engine.

### Change ABS AI Engine time zone

If you want to change the time zone in ABS AI Engine, complete the following steps:

1. Stop ABS AI Engine
2. Update the `timezone` parameter in `abs.properties` file
3. Start ABS AI Engine

**Note:** For more information, see [Start and Stop ABS](#) on page 314.

Related links

- [ABS configuration - abs.properties](#) on page 318

### Import existing CA-signed certificates

You can import your existing CA-signed certificate in ABS. To import the CA-signed certificate, stop ABS if it is already running. Complete the following steps to import the CA-signed certificate:

1. Export your CA-signed certificate to the PKCS12 store by entering the following command:

```
# openssl pkcs12 -export -in <your_CA_certificate.crt> -inkey
<your_certificate_key.key> -out abs.p12 -name <alias_name>
```

**For example:**

```
# openssl pkcs12 -export -in ping.crt -inkey ping.key -out abs.p12 -name
exampleCAcertificate
Enter Export Password:
Verifying - Enter Export Password:
```

**Note:** If you have an intermediate certificate from CA, then append the content to `<your_CA_certificate.crt>` file.

2. Import the certificate and key from the PKCS12 store to Java Keystore by entering the following command. The command requires the destination keystore password. The destination keystore password entered in the command should be same as configured in the [abs.properties](#) file.

Here is a snippet of the `abs.properties` file where the destination keystore password is stored. The password is obfuscated.

```
# Java Keystore password
jks_password=OBF:AES:Q3vcrnj7VZILTPdJnxkOsyimHRvGDQ==:daYWJ5QgzxZJAnTkuRlFpreM1rsz3FF
```

Enter the following command:

```
# keytool -importkeystore -destkeystore abs.jks -srckeystore abs.p12 -
srcstoretype PKCS12 -alias <alias_name> -storetype jks
```

**For example:**

```
# keytool -importkeystore -destkeystore abs.jks -srckeystore abs.p12 -
srcstoretype PKCS12 -alias exampleCAcertificate -storetype jks
```

```
Importing keystore abs.p12 to abs.jks...
Enter destination keystore password:
Re-enter new password:
Enter source keystore password:
```

3. Copy the `abs.jks` file created in step 2 to `/opt/pingidentity/abs/config/ssl` directory.
4. Start ABS by entering the following command:

```
# /opt/pingidentity/abs/bin/start.sh
Starting API Behavioral Security 4.0...
please see /opt/pingidentity/abs/logs/abs/abs.log for more details
```

## ABS ports

ABS uses the following ports:

Port number	Description
8080	This port is used by ASE to log in to ABS and also used by Postman to access data to generate API reports
27017	Default port for MongoDB

### Check and open MongoDB default port

MongoDB's default port for connection with ABS is 27017. Run the `check_ports_abs.sh` script on the ABS machine to determine whether MongoDB's default port is available. Provide MongoDB host IP address and default port as arguments. For example: `/opt/pingidentity/abs/util/check_ports_abs.sh {MongoDB IPv4:[port]}`

### Check and open MongoDB default port

Run the `check_ports_abs.sh` script on the ABS machine to determine whether MongoDB's default port is available. Input the MongoDB host IP address and default port (27017) as arguments. For example:

```
/opt/pingidentity/util/check_ports_abs.sh {MongoDB IPv4:[port]}
```

Run the script for MongoDB primary and secondary nodes. If the default ports are not accessible, open the port from the MongoDB machine.

## ABS configuration - `abs.properties`

The ABS configuration file (`abs.properties`) is located in the ABS `config` directory. The following table explains the parameters and provides recommended values.

Parameter	Description
<b>ABS IP, port, log level, and JKS password</b>	
<code>timezone</code>	Set the timezone to <code>utc</code> or <code>local</code> . The default timezone is <code>utc</code> .
<code>management_port</code>	Port for ABS to ASE and REST API to ABS communication. The default value is 8080.
<code>log_level</code>	Log detail captured. The default is <code>INFO</code> . Additional options - <code>DEBUG</code> , <code>ERROR</code> , <code>WARN</code> , <code>FATAL</code> .

`jks_password`

The password of the JKS Keystore. ABS ships with a default obfuscated password. You can reset the password and obfuscate it. This password should be the same that you would use in [importing your CA-signed certificate](#).

### ABS performance configurations

`system_memory`

Memory size in MB allocated to run machine learning jobs. Recommended to be at least 50% of system memory.

`queue_size`

Do not change the value of this parameter. The default is 10.

### ABS email configurations for alerts and reporting

`enable_emails`

Enable (`true`) or disable (`false`) ABS email notifications.

`sender_email`

Email address used for sending email alerts and reports.

`receiver_email`

Email address notified about alerts and reports. If you want more than one person to be notified, use an email alias.

`email_password`

Password of sender's email account.

**Note:** You can leave this field blank if your SMTP server does not require authentication.

`smtp_port`

Port number of SMTP server.

`smtp_host`

Hostname of SMTP server.

`smtp_ssl`

Set to `true` if you want email communication to be over SSL. Make sure that the SMTP server supports SSL. If you set `smtp_ssl` to `true` and the SMTP server does not support SSL, email communication falls back to the non-SSL channel. The default value is `true`.

Set it to `false` if email communication is over a non-SSL channel. The email communication will fail if you set the parameter to `false`, but the SMTP server only supports SSL communication.

`smtp_cert_verification`

Set to `true` if you want ABS to verify the SMTP server's SSL certificate. The default value is `false`.

If you set it to `false`, ASE does not verify SMTP server's SSL certificate; however, the communication is still over SSL.

**Note:** If you have configured an IP address as `smtp_host` and set `smtp_cert_verification` to `true`, then make sure that the certificate configured on the SMTP server has the following:

```
X509v3 extensions:
    X509v3 Key Usage:
        Key Encipherment, Data
    Encipherment
    X509v3 Extended Key Usage:
        TLS Web Server Authentication
    X509v3 Subject Alternative Name:
        IP Address: X.X.X.X
```

Here `x.x.x.x` is the IP address is the address configured in `smtp_host`.

### MongoDB configurations

`mongo_rs`

Comma separated MongoDB replica set URI. A maximum of three nodes can be configured.

`metadata_dbname`

The MongoDB metadata database name.

The default value is `abs_metadata`.

`data_dbname`

The MongoDB data database name.

The default value is `abs_data`.

`mldata_dbname`

The MongoDB machine learning database name.

The default value is `abs_mldata`

`mongo_auth_mechanism`

Defines the method in which MongoDB authenticates. The possible values can be:

- `NONE` - Set it to `NONE`, if authentication is not configured in MongoDB
- `DEFAULT` - Set it to `DEFAULT`, if you want to use native MongoDB username and password. Provide the values in the next two variables.
- `PLAIN` - Set it to `PLAIN`, if you want to use LDAP authentication. In this case, provide the LDAP username and password in the next two variables.

`mongo_username`

Username of MongoDB.

**Note:** Required for MongoDB authentication

`mongo_password`

MongoDB password



mongo_ssl	Set it to <code>true</code> if MongoDB is configured to use SSL connections. The default value is <code>false</code> .
mongo_certificate	Set it to <code>true</code> if you want to verify MongoDB SSL server certificate when ABS connects to MongoDB. The default value is <code>false</code> .
<p><b>Note:</b> Make sure <code>mongo_ssl</code> is set to <code>true</code> before setting <code>mongo_certificate</code> to <code>true</code>.</p>	
<b>ABS reporting node</b>	
dashboard_node	When <code>true</code> , designated as a dedicated Reporting or Dashboard node. This ABS node does not process log data or participate in an ABS cluster.  The default value is <code>false</code> .
<p><b>Note:</b> Multiple nodes can be Reporting or Dashboard nodes.</p>	
<b>Cloud and OAuth configurations</b>	
<p><b>Note:</b> The following parameters are applicable when ABS is running in <code>cloud</code> mode. These are preset configurations, which should not be edited.</p>	
bucket_name	The AWS S3 bucket name.
env_id	The environment id of the tenant.
deployment_type	The ABS deployment mode. Valid values are <code>cloud</code> or <code>onprem</code> . The default value is <code>onprem</code> .
oauth_audience	The audience claim ( <code>aud</code> ) of the access token.
oauth_issuer_whitelist	The list of valid JWT issuers from whom the tokens are expected.
oauth_jwks_endpoint	The JSON Web Key Set (JWKS) endpoint.

A sample `abs.properties` file is displayed below.

```
# Ping Identity Corporation, ABS config file
# All the keys should be present, leave blank value if not applicable

# Set the timezone to utc or local. The default timezone is utc.
timezone=utc
# REST API port
management_port=8080
# Log levels (ALL > DEBUG > INFO > WARN > ERROR > FATAL > OFF)
log_level=DEBUG
# Java KeyStore password
jks_password=OBF:AES:Q3vcrnj7VZILTPdJnxkOsyimHRvGDQ==:daYWJ5QgzxZJAnTkuRlFpreMlrsz3FFCu
# MongoDB replica set URI. For example, mongodb://
<IP1>:<Port>,<IP2>:<Port>,<IP3>:<Port>. Maximum three nodes can be
  configured.
mongo_rs=mongodb://localhost:27017
# MongoDB Database
metadata_dbname=abs_metadata
data_dbname=abs_data
mldata_dbname=abs_mldata
# MongoDB authentication
```

```


# If authentication is not enabled in MongoDB, set the mongo_auth_mechanism
to NONE
# The supported MongoDB authentication mechanisms are DEFAULT and PLAIN.
# If authentication mechanism is DEFAULT, provide MongoDB username and
password for mongo_username
# and mongo_password. If authentication mechanism is PLAIN, provide external
# LDAP username and password in mongo_username and mongo_password.
mongo_auth_mechanism=DEFAULT
mongo_username=absuser
mongo_password=OBF:AES:Q3vcrnj7VZILTPdJnxkOsyimHRvGDQ==:daYWJ5QgzxZJAnTkuRlFpreM1rsz3FF
# Mongo DB SSL
# Set to true if Mongo DB instance is configured in SSL mode.
# By default, ABS will try to connect to Mongo using non-SSL connection
mongo_ssl=false
# Mongo DB Server Certificate Verification
# Set to true if Mongo DB instance is configured in SSL mode and you want to
do the server certificate verification
# By default ABS will not verify the MongoDB server certificate
mongo_certificate=false
# Job queue size per node
queue_size=10
# Setting as true makes an ABS node for dashboard query only and does not
participate in ABS cluster for log processing
dashboard_node=false
# Memory for webserver and streaming server (unit is in MB)
system_memory=4096
# E-mail alerts
enable_emails=false
# SMTP host
smtp_host=smtp.example.com
# SMTP port
smtp_port=587
# Set this value to true if smtp host support SSL
smtp_ssl=true
# Set this value to true if SSL certificate verification is required
smtp_cert_verification=false
# Sender email id
sender_email=sender@example.com
# Sender's email password
email_password=OBF:AES:UXzB+y+69Bn3xiX6N822ad4hf5IfNfJY9w==:T
+QzM6qtc0+6MVsx4gU5p0LMHAI/y+w8DDsWv6VxVak=
# Receiver's email id
receiver_email=receiver@example.com
# Set this value to appropriate AWS S3 Bucket name, if ABS is running in
cloud mode
bucket_name=
# Set this value to appropriate Env Id, if ABS is running in cloud mode
env_id=
# Set this value to either cloud / onprem, as per the ABS running mode. By
default set to onprem
deployment_type=onprem
# Token validation params
# Audience
oauth_audience=
# Issuer whitelist
oauth_issuer_whitelist=
# JWKS endpoint
oauth_jwks_endpoint=

```

## Connect ABS to API Security Enforcer

Before connecting ABS, API Security Enforcer must be installed. For more information on installing and configuring API Security Enforcer, see the [ASE Admin guide](#).

The following diagram summarizes the process of connecting ABS to API Security Enforcer:



The following is a sample `abs.conf` file which is part of the API Security Enforcer (ASE):

```

; API Security Enforcer ABS configuration.
; This file is in the standard .ini format. The comments start with a
; semicolon (;).
; Following configurations are applicable only if ABS is enabled with true.
; a comma-separated list of abs nodes having hostname:port or ipv4:port as
; an address.
abs_endpoint=127.0.0.1:8080
; access key for abs node
access_key=OBF:AES://EN0zsQOEhDBWLDY
+pIoQ:jN6wfLiHTTd3oVNzvtXuAaOG34c4JBD4XZHgFCaHry0
; secret key for abs node
secret_key=OBF:AES:Y2DadCU4JFZp3bx8EhnOiw:zzi77GIFF5xkQJccjIrIVWU
+RY5CxUhp3NLcNBel+3Q
; Setting this value to true will enable encrypted communication with ABS.
enable_ssl=true
; Configure the location of ABS's trusted CA certificates. If empty, ABS's
; certificate
; will not be verified
abs_ca_cert_path=
  
```

The `access_key` and `secret_key` are the keys that were defined in the `abs_init.js` file when configuring MongoDB.

**Note:** To connect an API Security Enforcer cluster to ABS, configure the `abs.conf` file on any API Security Enforcer in the cluster and run the CLI commands. This ensures all the API Security Enforcer nodes in the cluster will be updated to connect with ABS.

If ABS is running in cluster mode, choose the IP address and port from any ABS node to add to the `abs.conf` file in API Security Enforcer.

### Dataflow

API Security Enforcer connects to the ABS node defined in `abs.conf` to obtain available ABS IP addresses (step 1). In stand-alone mode, ABS sends the only IP address. In cluster mode, ABS sends the IP addresses of all available ABS nodes to API Security Enforcer.

After API Security Enforcer receives the IP address, it establishes a session with ABS by sending the secret and access keys (step 2). After successful authentication, API Security Enforcer streams the access log files and API JSON files to the ABS node (step 3). After sending the files, it receives the attack lists (only available if blocking is activated for API Security Enforcer) from ABS (step 4). When the transaction is complete, API Security Enforcer logs out from ABS (step 5).


ABS uses machine learning (ML) algorithms to discover attacks, anomalies, and other traffic information. It stores incoming API Security Enforcer logs and then passes these logs to the machine learning engine

for analysis. In high load environments, a single ABS node may not be able to process all log files, and multiple ABS nodes should be deployed for log processing.

The following diagrams show the API Security Enforcer – ABS Dataflow.


### Stand-alone mode

In stand-alone mode, a single MongoDB node is used for both read and write operations. A stand-alone mode of deployment is only recommended for testing purposes.



### Cluster mode

In cluster mode, API Security Enforcer nodes synchronize the `abs.conf` file as well as the state of each ABS node. The ABS cluster nodes do not communicate among themselves. Each node records its status in MongoDB and reads about the state of other nodes from the database.




## ABS cluster

An ABS cluster consists of stateless ABS nodes communicating with a MongoDB replica set. Each ABS node connects to the MongoDB cluster to obtain cluster configuration information that describes peer nodes. ABS nodes themselves do not communicate with each other; they periodically send heartbeats to MongoDB with status information. Each ABS node exposes:

- REST APIs for log streaming between ABS and API Security Enforcer
- REST APIs between ABS and management applications which fetch metrics, anomalies, attack types, backend error, blocked connections, flow control, and cluster status.

An ABS cluster is depicted in the following diagram:



To configure an ABS cluster, complete the following steps:

1. [Install MongoDB in a replica set](#)
2. [Connect ABS to MongoDB](#)

To set up an ABS cluster, no separate steps have to be completed. To create an ABS cluster, add an ABS node and connect it to MongoDB primary node. Since ABS forms a stateless cluster, the information of all the nodes in the cluster is fetched by ABS nodes from MongoDB.

**Scale down ABS cluster:** To scale down the cluster, [stop](#) the ABS node that you wish to remove from the cluster. Edit the `abs.properties` file to remove MongoDB IP address.

## ABS logs

The active ABS log file `abs.log` is located in the `logs` directory and rotated every 24-hours at midnight local time. The rotated log files append timestamps to the name and follow the naming convention of `abs.log.<yyyy>-<mm>-<dd>` (for example, `abs.log.2018-11-24`). Here is an example:

```
-rw-r--r--. 1 root root 68K Apr 25 23:59 abs.log.2019-04-25
-rw-r--r--. 1 root root 68K Apr 25 23:59 abs.log.2019-04-24
-rw-r--r--. 1 root root 68K Apr 26 23:59 abs.log.2018-04-26
-rw-r--r--. 1 root root 158K Apr 27 23:59 abs.log.2018-04-27
-rw-r--r--. 1 root root 32K Apr 28 11:21 abs.log
```

The ABS log file contains INFO messages (for example, ABS started, MongoDB status) and ERROR messages (for example, MongoDB is not reachable). The log files also contains entry of all the email alerts sent. Here is a snippet of an `abs.log` file:

```
2019-04-28 11:16:45 INFO - starting abs periodic actions
```

```

2019-04-28 11:16:45 INFO - MongoDB heartbeat success
2019-04-28 11:16:45 INFO - notification node not set.
2019-04-28 11:16:45 INFO - training period 1 hours.
2019-04-28 11:16:45 INFO - system threshold update interval 1 hour(s) .
2019-04-28 11:16:45 INFO - api discovery interval 1 hour(s) .
2019-04-28 11:16:45 INFO - subpath limit: 100
2019-04-28 11:16:45 INFO - ABS started successfully...
2019-04-28 11:17:45 INFO - MongoDB heartbeat success
2019-04-28 11:19:45 ERROR - MongoDB heartbeat failure

```

## Purge the processed access logs from ABS

A `purge.sh` script either archives or purges processed access log files which are stored in the `/opt/pingidentity/abs/data` directory.

**Note:** When the `purge` script is run, the processed access log files are permanently deleted from the `/opt/pingidentity/abs/data` directory. Always backup the files before deleting.

Located in the `/opt/pingidentity/abs/util` directory, the `purge` script deletes logs older than the specified number of days. Run the script using the ABS command line. For example:

```

/opt/pingidentity/abs/util/purge.sh -d 3
In the above example, purge.sh deletes all access log files older than 3
days. Here is sample output.
/opt/pingidentity/abs/util/purge.sh -d 3
This will delete the data in /opt/ pingidentity/abs/data which is older than
3 days.
Are you sure (yes/no): yes
removing /opt/pingidentity/abs/
data/2018-04-10-11_21/9k2unv5l2bsgurteot3s3pmt03/ : last changed at Mon Jan
10 11:32:31 IST 2018
removing /opt/ pingidentity/abs/data/2018-04-10-11_21/
ilq67a3g5sve2pmpkcp271o37c/ : last changed at Mon Jan 10 11:32:31 IST 2018

```

### External log archival

The `purge` script can also archive logs older than the specified number of days to secondary storage. Use the `-l` option and include the path of the secondary storage to archive log files. For example:

```

/opt/pingidentity/abs/util/purge.sh -d 3 -l /tmp/

```

In the above example, log files older than 3-days are archived to the `tmp` directory. To automate log archival, add the script to a `cron` job.

## Purge MongoDB data

The ABS MongoDB purge script dumps and/or deletes processed AI Engine and machine learning data from MongoDB. It is recommended to archive the data before purging it. The `purge_mongo.sh` script is available in the `<pi-install-dir>/pingidentity/abs/util` directory.

The script offers three options:

- Only purge data
- Only dump data
- Dump data into a specified directory and then purge it

**Prerequisites**-Ensure that the following prerequisites are fulfilled, before using the script:

- Execute the script from an ABS AI Engine node with connectivity to the MongoDB primary node.
- The necessary write permissions are available on the directory where the data dump is stored.

- Database names used as command line arguments like the `data_dbname` and `mldata_dbname` should be same as configured in [ABS configuration - abs.properties](#) on page 318 file.

**Note:** It is recommended to execute the script during low load periods or during ABS down times.

The `purge_mongo.sh` script supports the following arguments:

Argument	Description
<code>--data_db &lt;abs database&gt;</code>	Use this argument to specify the name of the ABS database.
<code>--mldata_db &lt;ml database&gt;</code>	Use this argument to specify the name of the ML database.
<b>Note:</b> You must specify at least one database while executing the script. You can also specify both the databases in a single command.	
<code>-d &lt;days&gt;</code> or <code>--days &lt;days&gt;</code>	Number of days of data to be retained. The default number of days is seven. The minimum number of days that can be specified is one and the maximum is 365.
<code>-l &lt;path_to_dump_dir&gt;</code> or <code>--location &lt;path_to_dump_dir&gt;</code>	The directory path to store the MongoDB dump.
<code>--purge_only</code>	Use this option when you only need to delete the data and not take a data dump.
<code>--dump_only</code>	Use this option when you need to take the data dump without deleting the data.
<code>--h</code> or <code>--help</code>	Use this argument for more information on the purge script parameters.
<code>--gzip</code>	Use this argument to compress the data dump. It can be used with <code>dump only</code> and <code>purge and dump</code> options. This argument cannot be used with <code>purge only</code> option.

The following sections show the sample usage of `purge_mongo.sh` script with the three options:

### Purge data

The following are a few sample commands to purge the MongoDB data:

- `./purge_mongo.sh --data_db <abs database> -d <days> --purge_only`
- `./purge_mongo.sh --mldata_db <ml database> -d <days> --purge_only`
- `./purge_mongo.sh --data_db <abs database> --mldata_db <ml database> -d <days> --purge_only`

For example, the following command deletes ABS data older than 80 days.

```
./purge_mongo.sh --data_db abs_data -d 80 --purge_only
Starting the purge mongo tool
This will delete the documents in abs_data database that are older than 80
days.
Are you sure (yes/no): yes
Deleting the documents in abs_data database that are older than 80 days.
```



```
Please see /opt/pingidentity/abs/logs/purge/purge.log.2020-11-16-05-01-42
for more details
```

## Dump data

The following are a few sample commands to purge the MongoDB data:

- `./purge_mongo.sh --data_db <abs database> -d <days> -l <path> --dump_only`
- `./purge_mongo.sh --mldata_db <ml database> -d <days> -l <path> --dump_only`
- `./purge_mongo.sh --data_db <abs_database> --mldata_db <ml database> -d <days> -l <path> --dump_only`

For example, the following command dumps data older than 80 days from `ml_database` into a `/tmp` directory. It does not delete the data. `/tmp` is used as an example reference here, you can substitute `/tmp` with any other directory path in your environment.

```
./purge_mongo.sh --mldata_db abs_mldata -d 80 -l /tmp --dump_only
Starting the purge mongo tool
Storing abs ml data from mongo at /tmp/ml_mongo_data.2020-11-16-06-09-06
Please see /opt/pingidentity/abs/logs/purge/purge.log.2020-11-16-06-10-42
for more details
```

## Purge and dump data

The following are a few sample commands to purge and dump the data:

- `./purge_mongo.sh --data_db <abs database> -d <days> -l <path>`
- `./purge_mongo.sh --mldata_db <ml database> -d <days> -l <path>`
- `./purge_mongo.sh --data_db <abs_database> --mldata_db <ml database> -d <days> -l <path>`

For example, the following command dumps data older than 80 days from `ml_database` into a `/tmp` directory and deletes the data. `/tmp` is used as an example reference here, you can substitute `/tmp` with any other directory path in your environment.

```
./purge_mongo.sh --mldata_db abs_mldata -d 80 -l /tmp
Starting the purge mongo tool
Storing abs ml data from mongo at /tmp/ml_mongo_data.2020-11-16-06-12-14
This will delete the documents in abs_mldata database that are older than
80 days.
Are you sure (yes/no): yes
Deleting the documents in abs_mldata database that are older than 80 days.
Please see /opt/pingidentity/abs/logs/purge/purge.log.2020-11-16-06-12-42
for more details
```

**Note:** By default, the script dumps all data and then removes processed data older than seven days.

In case there is a failure in execution of `purge_mongo.sh` the script exits. You can retry executing the script. The execution details are logged in `</pi-install path>/pingidentity/abs/logs/purge/directory`.

## Reset MongoDB

ABS AI engine provides a script to factory reset MongoDB data. Make sure to take a backup of your current data before running the reset script. Once you run the MongoDB reset script, the deleted data cannot be retrieved.

The reset MongoDB script deletes all the documents from all the collections of `abs_data` and `abs_mldata` from MongoDB. The `reset_mongo.sh` script is available in the `/opt/pingidentity/abs/util` directory. Copy the script from the `util` directory to your MongoDB primary node.

To execute the script, you need the following information:

- **MongoDB credentials:** `mongo_username` and `mongo_password` configured in `abs.properties`.
- **Database name and port number:** `data_dbname`, `mldata_dbname`, and `mongo_master_port` configured in `abs.properties`
- If your MongoDB installation is configured to use SSL, use the `--ssl` option. The following examples assume that MongoDB is configured to use TLS.

For more information on the reset script parameters, run the reset help script from the MongoDB command line:

```
/opt/pingidentity/mongo/reset_mongo.sh -help
```

**Reset ABS and machine learning data:** The following example resets both ABS and machine learning (ml) data:

```
/opt/pingidentity/mongo/reset_mongo.sh -u absuser -p abs123 --tls --data_db abs_data --mldata_db abs_mldata --auth_db admin --port 27017
```

**Reset only machine learning (ml) data:** The following example resets only the machine learning data:

```
/opt/pingidentity/mongo/reset_mongo.sh -u absuser -p abs123 --tls --mldata_db abs_mldata --auth_db admin --port 27017
```

**Reset only ABS data:** The following example resets only the ABS data:

```
/opt/pingidentity/mongo/reset_mongo.sh -u absuser -p abs123 --tls --data_db abs_data --auth_db admin --port 27017
```

The following snippet shows the output when the reset MongoDB script is run:

```
./reset_mongo.sh -u absuser -p abs123 --port 27017 --data_db abs_data --mldata_db abs_mldata --tls
Please make sure that there is no ABS process running before running the reset_mongo script.
Are you sure you want to continue... (yes/no): yes
This will delete all the documents in abs_data database
Are you sure? (yes/no): yes
Deleting the documents in abs_data database.
2019-10-11T05:46:43.726+0000 W CONTROL [main] Option: ssl is deprecated.
Please use tls instead.
2019-10-11T05:46:43.727+0000 W CONTROL [main] Option:
sslAllowInvalidCertificates is deprecated. Please use
tlsAllowInvalidCertificates instead.
MongoDB shell version v4.2.0
connecting to: mongodb://127.0.0.1:27017/?
authSource=admin&compressors=disabled&gssapiServiceName=mongodb
2019-10-11T05:46:43.802+0000 W NETWORK [js] TLS peer certificate
validation failed: self signed certificate
Implicit session: session { "id" : UUID("400fcaa5-57dd-4123-a5e6-b54cle0bdfda") }
MongoDB server version: 4.2.0
switched to db abs_data

Removing all documents of all collections in ABS_DATA
Removing all documents from [abs_data.api_attack_dos_anomaly]
Removing all documents from [abs_data.api_config.chunks]
Removing all documents from [abs_data.api_config.files]
Removing all documents from [abs_data.api_json]
Removing all documents from [abs_data.api_key_metrics]
Removing all documents from [abs_data.attack_management]
```

```

Removing all documents from [abs_data.attack_management_audit]
Resetting the [abs_data.attack_ttl] to default values
Removing all documents from [abs_data.backend_errors]
Removing all documents from [abs_data.bc_summary]
Removing all documents from [abs_data.blocked_connections]
Removing all documents from [abs_data.discovered_apis]
Removing all documents from [abs_data.discovery_api_metadata]
Removing all documents from [abs_data.discovery_ir.chunks]
Removing all documents from [abs_data.discovery_ir.files]
Removing all documents from [abs_data.extended_ml_threshold]
Removing all documents from [abs_data.extended_trained_model]
Removing all documents from [abs_data.extended_training_model]
Removing all documents from [abs_data.external_ioc_type]
Removing all documents from [abs_data.internal_ioc]
Removing all documents from [abs_data.internal_ioc_audit]
Removing all documents from [abs_data.ioc]
Removing all documents from [abs_data.ioc_anomaly]
Removing all documents from [abs_data.ir.chunks]
Removing all documents from [abs_data.ir.files]
Removing all documents from [abs_data.log_nodes]
Removing all documents from [abs_data.ml_result]
Removing all documents from [abs_data.ml_threshold]
Removing all documents from [abs_data.notifications]
Removing all documents from [abs_data.oauth_metrics]

```

The reset script does not delete the following meta data:

- ABS cluster information
- ABS configuration
- Global configuration from `abs_init.js` file
- Scale configuration from `abs_init.js` file
- Dictionary generated by ABS AI engine

**Verifying MongoDB reset script:** To verify that the MongoDB reset script executed successfully, run the ABS Admin REST API. The output should not show any ASE access log and API information. It should only display ABS cluster information, MongoDB primary and secondary and client identifier TTL value reset to zero. Following is a sample output of Admin API after MongoDB reset script is run:

```

{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "across_api_prediction_mode": false,
  "api_discovery": {
    "subpath_length": "1",
    "status": true
  },
  "abs_cluster": {
    "abs_nodes": [
      {
        "node_ip": "172.16.40.19",
        "os": "Red Hat Enterprise Linux Server",
        "cpu": "16",
        "memory": "62G",
        "filesystem": "1%",
        "bootup_date": "Thu Oct 10 10:08:37 UTC 2019"
      }
    ],
    "mongodb_nodes": [
      {
        "node_ip": "172.16.40.236:27017",

```

```

        "status": "secondary"
      },
      {
        "node_ip": "172.16.40.237:27017",
        "status": "secondary"
      },
      {
        "node_ip": "172.16.40.235:27017",
        "status": "primary"
      }
    ]
  },
  "percentage_diskusage_limit": "80%",
  "scale_config": {
    "scale_up": {
      "cpu_threshold": "70%",
      "cpu_monitor_interval": "30 minutes",
      "memory_threshold": "70%",
      "memory_monitor_interval": "30 minutes",
      "disk_threshold": "70%",
      "disk_monitor_interval": "30 minutes"
    },
    "scale_down": {
      "cpu_threshold": "10%",
      "cpu_monitor_interval": "300 minutes",
      "memory_threshold": "10%",
      "memory_monitor_interval": "300 minutes",
      "disk_threshold": "10%",
      "disk_monitor_interval": "300 minutes"
    }
  },
  "attack_ttl": {
    "ids": [
      {
        "id": "ip",
        "ttl": 0
      },
      {
        "id": "cookie",
        "ttl": 0
      },
      {
        "id": "access_token",
        "ttl": 0
      },
      {
        "id": "api_key",
        "ttl": 0
      },
      {
        "id": "username",
        "ttl": 0
      }
    ]
  }
}

```

## Add a member to an existing MongoDB replica set

This topic discusses the steps to add a new node to an existing MongoDB replica set.

### Prerequisites:

- An active replica set.
- A new MongoDB system accessible by the replica set.
- To add a new member, the MongoDB user must have clusterAdmin privileges.

**Note:** absrs01 is the name of the replica set used in the following steps.

Complete the following steps to add a node to an existing replica set:

1. Create the MongoDB directory structure: create mongo, data, logs, and key directory on the new MongoDB node.

```
# mkdir -p /opt/pingidentity/mongo/data /opt/pingidentity/mongo/logs \ /
/opt/pingidentity/mongo/key
```

2. Download MongoDB 4.2 on the node and extract to /opt/pingidentity/mongo.

```
# cd /opt/pingidentity/ /opt/pingidentity# wget \ https://
fastdl.mongodb.org/linux/mongodb-linux-x86_64-rhel70-4.2.0.tgz \ -O
mongodb.tgz && tar xzf mongodb.tgz -C /opt/pingidentity/mongo/ --strip-
components=1
```

3. Update shell path variable and reload the shell.

```
/opt/pingidentity# echo PATH=$PATH:/opt/pingidentity/mongo/bin >>
 ~/.bashrc; /opt/pingidentity# source ~/.bashrc
```

4. Copy the contents of the /opt/pingidentity/mongo/key directory from the primary node to the new node into /opt/pingidentity/mongo/key.

5. Start the MongoDB database on the new node.

```
/opt/pingidentity# cd mongo /opt/pingidentity/mongo# mongod --auth --
dbpath ./data/ --logpath ./logs/mongo.log --port 27017 --replSet absrs01
--fork --keyFile ./key/mongodb-keyfile -bind_ip 0.0.0.0
```

6. Connect to the mongo shell of the primary node and run the following command.

```
absrs01:PRIMARY> rs.add({"host": "<IP address of new node>:27017",
 "priority": 2})
```

**Note:** On executing step-six, the state of the new node will change to STARTUP2. This indicates that the synchronization between the replica set and the new node has started.

7. Verify if the new node is added as a Secondary node to the replica set using the following command.

```
absrs01:PRIMARY> rs.status()
```

Related links

- <https://docs.mongodb.com/manual/tutorial/expand-replica-set/>

## Remove a member from a MongoDB replica set

This topic discusses the steps to remove a node from an existing MongoDB replica set.

### Prerequisites:

- An active replica set.
- To remove a member, the MongoDB user must have clusterAdmin privileges.

To remove a node from an existing replica set:

1. Connect to the node that you wish to remove and shut down the MongoDB on it using the following command.

```
absrs01:PRIMARY> db.shutdownServer()
```

2. Connect to the primary member of the replica set and run the following command to remove the node.


```
absrs01:PRIMARY> rs.remove("<IP Address or hostname of the node to be removed>:27017")
```

Related links

<https://docs.mongodb.com/manual/tutorial/remove-replica-set-member/>

## Verify MongoDB SSL certificates

You can configure ABS to verify the validity of MongoDB server certificate, when it tries to connect with MongoDB. This is an optional check and the following diagram shows the summary of steps involved in this



verification.

Ensure the following steps are completed, so that ABS can verify MongoDB server certificate before connecting to it :

1. Check if the `mongo_ssl` parameter in the `<pi_install_path>/pingidentity/abs/config/abs.properties` file is set true.
2. Check if the `mongo_certificate` parameter in the `<pi_install_path>/pingidentity/abs/config/abs.properties` file is set true.
3. Import the MongoDB Server certificate into the `abs.jks` truststore, using either of the following commands as applicable. The commands prompt for a destination keystore password, and the password entered should be same as the `jks_password` configured in the [abs.properties](#) file.

```
# keytool -import -file <mongodb-cert.crt> -storetype JKS -keystore /
<pi_install_path>/pingidentity/abs/config/ssl/abs.jks
```

If the MongoDB server certificate is in `.pem` format then use the following command to import the certificate in to the ABS truststore.

```
# keytool -import -v -trustcacerts -file server.pem -keystore /
<pi_install_path>/pingidentity/abs/config/ssl/abs.jks -storetype JKS
```

When ABS starts, it loads the certificates available in `abs.jks` truststore. If the server certificate presented by MongoDB gets validated, ABS connects with it and completes the booting.

If the SSL server certificate verification fails, ABS will not start and a `CertificateException` is thrown by ABS. The error is logged in `<pi_install_path>/pingidentity/abs/abs.log`.

**Note:** If ABS is running and the MongoDB server certificate expires in between, it will not stop. An error message is logged in `<pi_install_path>/pingidentity/abs/abs.log`.

### Using a CA-signed certificate

You can also use a CA-signed certificate to verify the MongoDB server certificate. For that, import your existing CA-signed certificate into ABS by following the instructions explained in [Import existing CA-signed certificates](#) on page 317. Once the certificate is imported, complete Step-1 through Step-3 above so that ABS can verify MongoDB server certificate.

## Email alerts and reports

ABS sends e-mail notifications under two categories:

- **Alerts** – event-based updates to notify administrators of potential issues
- **Reports** – standard reports sent every 24 hours at 00:00:00 hours midnight

Email parameters in `abs.properties` correspond to your e-mail server. By default, e-mail notifications are disabled. Enable notifications after configuring e-mail IDs and server.

**Note:** If you want more than one person to be notified, use an email alias in `sender_email` field.

```
#Enable or Disable e-mail alerts
enable_emails=false
#Provide the details of sender and receiver of e-mail
#Sender's e-mail ID
sender_email=mail@yourdomain.com
#Sender's e-mail password
email_password=mypassword
#Receiver's e-mail ID
receiver_email=mail@yourdomain.com
#SMTP port
smtp_port=587
#SMTP host
smtp_host=smtp.smtphost.com
```

### ABS alerts

Email alerts are sent based on the following category of events. These events are also logged in the `abs.log` file. The threshold values for these events are pre-set. If you want to change the threshold values after the system is running, then you have to manually change the values in MongoDB.

- **Dynamic Rate Limit:** alert sent when CPU, disk, or memory crosses the configured threshold value.
- **ABS Node:** alert sent when ABS cluster nodes are added or removed.
- **MongoDB:** alert sent when a MongoDB node is added or becomes inaccessible.
- **Percentage Disk Usage Limit:** alert sent when the disk usage reaches the configured `percentage_diskusage_limit` value. When this limit is reached, ABS stops accepting any new access log files from ASE. The alert is also logged in the `abs.log` file. You can use `update.sh` script in `/abs/util/` directory to update the thresholds for *Percentage Disk Usage Limit*.
- **License:** The following license related alerts are sent:
  - **ABS license invalid:** alert is sent if the ABS license is found to be invalid. In this case ABS shuts down.
  - **ABS license expiration:** alert sent when ABS license is expired.
  - **Transaction limit reached:** alert sent when ABS reaches the licensed monthly transaction limit.
- **Scale Up and Scale Down:** alert sent when a system resource, such as CPU, memory, or disk utilization, is above or below its threshold value for a specified interval of time. If the value is above

the threshold value, add ABS nodes to distribute the load. If the resource utilization is below the lower threshold, you may remove an ABS node from the ABS cluster.

- **DDoS attack alert:** ABS sends alerts for multi-client Login Attacks and for API DDoS Attack Type 1. The email alert provides a time period for the attack along with a URL to access information on all client IPs participating in the attack.

Following is a template for alerts:

```
Event: <the type of event>
Value: <the specific trigger for the event>
When: <the date and time of the event>
Where: <the IP address of the server where the event occurred>
```

For example,

```
Event: Scale Down ABS Node
Value : 192.168.11.166
CPU scale down threshold reached.
When : 2019-Jun-05 18:02:33 UTC
Where: 192.168.11.166
```

The following table describes the various email alerts sent by ABS and their possible resolution. The resolution provided is only a starting point to understand the cause of the alert. If ABS is reporting an alert even after the following the resolution provided, contact Ping Identity support.

Email alert	Possible cause and resolution
File System Maxed Out - Rate Limit Alert	<p><b>Cause:</b> A possible reason for this alert could be that historical access log files from ASE have accumulated on the storage disk.</p> <p><b>Resolution:</b> Purge or archive the old access log files from storage disk.</p>
ABS node added to cluster	<p>ABS sends an email alert when a node joins an ABS cluster.</p> <p><b>Confirm:</b> ABS admin should verify whether the correct ABS node joined the ABS cluster.</p>
ABS node removed from cluster	<p>ABS sends an email alert when a node is removed from an ABS cluster.</p> <p><b>Confirm:</b> ABS admin should check the reason for removal of ABS node from the cluster. ABS node could disconnect from cluster because of network issues, a manual stop of ABS, or change in IP address of the ABS machine.</p>
Memory scale up or scale down	<p><b>Cause:</b> ABS sends an email alert when the ABS node reaches the memory scale up or scale down limits in the configuration. The reason for reaching scale up limit can be because of large number of access log files coming from ASE. Scale down limit could be reached because of low number of access logs coming from ASE.</p> <p><b>Resolution:</b> If ABS reaches scale up limit, add another ABS node to the cluster. If the system utilization is low, you can remove an ABS node from the cluster.</p>



CPU scale up or scale down	<p><b>Cause:</b> ABS sends an email alert when the ABS node reaches the CPU scale up or scale down limits in the configuration. The reason for reaching scale up limit can be because of large number of access log files coming from ASE. Scale down limit could be reached because of low number of access logs coming from ASE.</p> <p><b>Resolution:</b> If ABS reaches scale up limit, add another ABS node to the cluster. If the system utilization is low, you can remove an ABS node from the cluster.</p>
Disk scale up or scale down	<p><b>Cause:</b> ABS sends an email alert when the ABS node reaches the disk scale up or scale down limits in the configuration. The reason for reaching scale up limit can be because of large number of access log files coming from ASE. Scale down limit could be reached because of low number of access logs coming from ASE.</p> <p><b>Resolution:</b> If ABS reaches scale up limit, add another ABS node to the cluster. If the system utilization is low, you can remove an ABS node from the cluster.</p>
License <i>&lt;path&gt;</i> is invalid. ABS will shut down now	<p><b>Cause:</b> ABS sends this email alert when ABS does not have correct permissions to read the license file from the configured path, or there is a typing error in the name of the license file.</p> <p><b>Resolution:</b> Validate current license file path. Also check for file permissions of the license file.</p>
ABS license at <i>&lt;path&gt;</i> has expired. Please renew your license.	<p><b>Cause:</b> ABS sends this email alert when ABS license has expired. The license expires at the end of the license period.</p> <p><b>Resolution:</b> Renew your ABS license.</p>
Maximum transaction limit reached for the current month	ABS sends this warning message when ABS crosses the licensed monthly transaction limit.
API DDoS Attack Type 1 or Login DoS detected between <i>&lt;timestamp&gt;</i> and <i>&lt;timestamp&gt;</i> on node <i>&lt;value&gt;</i>	ABS sends this warning message when it detects an API DDoS attack type 1 or a Login DoS attack.
MongoDB primary node is down	<p><b>Cause:</b> ABS sends this email alert when MongoDB process is unavailable due to a shortage in memory or CPU. This alert can also trigger because of network issues for MongoDB node.</p> <p><b>Resolution:</b> Check MongoDB Primary node status to bring it back online or add additional secondary node if needed.</p>

### ABS reports

ABS sends an e-mail report every 24 hours at midnight, 00:00:00 hours (local system time). Each report includes values for the following parameters:

- **ABS Node Status:** resource utilization of CPU, file system, and operating system
- **ASE Logs Processed:** Compressed file size of ASE logs processed in 24-hours
- **Total Requests:** The number of requests in the processed log files in 24-hours
- **Success:** The total number of requests which got a 200-OK response
- **Total Anomalies:** Total number of anomalies detected across APIs in 24-hours
- **Total IOC:** Total number of attacks detected in 24-hours
- **When:** The time when the email report was sent

- **Where:** The ABS node that sent the email report
- MongoDB node IP address and status

Following is a sample ABS email template:

```
Dear DevOps,
    Please find the daily report generated by 192.168.11.166 at 2019-Jun-25
    00:02:00 UTC
=====Cluster Details=====
ASE Logs Processed: 93.78MB
Total Request: 678590
Success: 596199
Total Anomalies: 7
Total IOC: 2
When : 2019-Jun-25 00:02:00 UTC
Where: 192.168.11.166

=====Node1 =====
Host : 192.168.11.166
OS : Red Hat Enterprise Linux Server release 7.5 (Maipo)
CPU : 24
Memory : 62G
Filesystem : 39%
=====

=====Mongo1 =====
Host : 192.168.11.162
Status : up
=====

=====Mongo2 =====
Host : 192.168.11.164
Status : up
=====

=====Mongo3 =====
Host : 192.168.11.1685
Status : up
=====

Best,
API Behavioral Security.
```

## AI Engine training

---

The ABS AI Engine needs to be trained before it can detect attacks on API services. The AI engine training is governed by global variables which are configured using [Global configuration update REST API](#) on page 355. The AI training runs for the minimum training time set, but a minimum amount of data must also be received before the training period is complete for a given API. You can check the [training status](#) by using the [ABS Admin REST API](#).


The ABS AI engine must be trained on an API before it can be secured. Whenever a new API is added, ABS automatically trains on the new API before looking for attacks.

### Training the ABS model

ABS AI engine can be trained in a live environment by analyzing ASE access logs to build its model. When ABS first receives traffic for a new API, the training period starts. After the defined training period (default is 24-hours) expires, ABS checks if sufficient training data has been collected and will continue training until

the models are ready for attack detection. ABS applies continuous learning and adapts its model over time for increased accuracy.

For example, a new API ecosystem is added with four APIs, and ABS is configured with a 24-hour training period. Two APIs have immediate API activity, so ABS begins the training period for both APIs. After 24-hours, ABS will detect attacks only for the two trained APIs.



If the remaining two APIs start sending traffic three days later, then ABS will begin the 24-hour training period for the remaining APIs and begin attack detection for those APIs at the end of the training period.

**i Important:** It is important to decide on the training and threshold update intervals prior to starting the AI system. Although you can [update](#) the training and threshold periods, it is a good practice not to change these variables frequently as this may lead to a change in the behavior of the AI model.

## AI Engine training variables

PingIntelligence AI training depends on a set of parameters configured using [Global configuration update REST API](#) on page 355. These parameters should be configured before starting the system. It is recommended that you review the variables and configure the best values for your environment. Frequent updates to the training variables may lead to a change in behavior of the AI system. Following are the parameters that need to be configured:

- `attack_initial_training`
- `attack_update_interval`
- `continuous_learning`
- `window_length`

The following table describes the various training variables:

### Training variables

Variable	Description
<code>attack_initial_training</code>	The number of hours that you want to train the AI model before it moves to the prediction mode. The default value is 24-hours. The minimum value is 1-hour.
<code>attack_update_interval</code>	The time interval in hours at which you would want the model thresholds to be updated. The default value is 24-hours. The minimum value is 1-hour.  The value in this variable takes effect only when <code>continuous_learning</code> is set to true.

<code>continuous_learning</code>	Setting this value to <code>true</code> configures the AI model to learn continuously based on the live traffic. If it is set to <code>false</code> , the AI model detects attack based on the initial training.
<code>window_length</code>	The maximum time period that the AI model uses to detect attacks across APIs. The default and maximum value for <code>window_length</code> is 24-hours. The training period should be longer than the <code>window_length</code> period.
<code>root_api_attack</code>	Configure as <code>true</code> if you want AI engine to detect attacks on the root API. Set it to <code>false</code> if you do not wish the AI engine to detect attacks on the root API. The default value is <code>false</code> .
<code>session_inactivity_duration</code>	The time in minutes for an inactive user session after which ABS decides that the session has terminated. Default value is 30-minutes. You can configure it to any value in minutes.
	<b>Note:</b> This variable only applies to account take over attack.

Following is a snippet from the response global config API.

```
{
  "company": "ping identity",
  "name": "api_globalconfig",
  "description": "This report contains status information of ABS global
configurations",
  "global_config": {
    "attack_initial_training": 2,
    "attack_update_interval": 1,
    "api_discovery": true,
    "discovery_initial_period": 100,
    "discovery_subpath": 3,
    "discovery_update_interval": 1,
    "poc": false,
    "url_limit": 120,
    "response_size": 150,
    "continuous_learning": false,
    "attack_list_count": 400000,
    "root_api_attack": true,
    "session_inactivity_duration": 10
  }
}
```

#### Miscellaneous variables

Variable	Description
----------	-------------

response_size	Maximum size in MB of the data fetched by external calls to ABS REST APIs. The default value is 100 MB.
enable_ssl	By default it is set to <code>true</code> , and SSL communication is enabled between ASE and ABS, and for external systems making rest API calls to ABS. See <a href="#">Configure SSL</a> on page 316 on page 10 for more information.

## Training period status

ABS training status is checked using the ABS Admin API which returns the training duration and prediction mode. If the prediction variable is `true`, ABS has completed training and is discovering attacks. A `false` value means that ABS is still in training mode. The API URL for Admin API is: <https://<ip>:<port>/v4/abs/admin>. Here is a snippet of the Admin API output:

```
"message": "training started at Thu Jul 30 12:32:59 IST 2018",
"training_duration": "2 hours",
"prediction": true
```

**Note:** ABS only detects attacks after the training period is over. During training, no attacks are detected.

## Update the training variables

ABS provides an `update.sh` script in the `/pingidentity/abs/util` directory to update the training related variables. Using the script, you can update the following variables:

- Continuous learning: `continuous_learning`
- Training period: `attack_initial_learning`
- Threshold update period: `attack_update_interval`
- Window length: `window_length`

You can update the training period when the system is already in a running state by using the script. Review the following use cases before changing the training and threshold period. In all the use cases, the default training period is assumed to be 24-hours.

**CAUTION:** If you want to extend the training period, it is a best practice to add new APIs after the training period is adjusted to avoid APIs completing a shorter training period.

You can also use Global Configuration REST API to update the training variables. For more information see, [Global configuration update REST API](#) on page 355

### Update the training interval

#### **Increase the training period**

You can increase the training period by executing the update script.

**Case 1** – The API model is under training, that is, the training period is not over.

**System Behavior** – In this case, if you increase the training period, for example, from 24-hours to 48-hours, the AI model trains based on the updated training period.

**Case 2** – The API model has completed the training process.

**System Behavior** – Increasing the training period has no effect on trained APIs. Any new APIs will use the new training period.

### **Decrease the training period**

You can decrease the training period by executing the update script.

**Case 1** – The API model is in the training process but has not reached the duration of the new training period.

**System Behavior** – Decreasing the training period (for example, from 24 hours to 12 hours) shortens the training period to 12 hours for the APIs that have not completed the training process. If the API has completed 10 hours of training, then it will now complete its training period after 2 more hours.

**Case 2** – The API model is in the training process and the new training duration is less than the current AI model trained duration.

**System Behavior** – In this case the API model stops training itself at the current time and moves to the prediction mode. For example, if the original training period was 24-hours and the AI model has been trained for 18-hours; at this time if the training period is reduced to 12-hours, the AI model stops training itself and moves to the prediction mode.

**Case 3** – API model has completed the training process.

**System Behavior** – Decreasing the training period has no effect on trained APIs. Any new APIs will use the new training period.

Execute the update.sh script

The update.sh script is available in the /opt/pingidentity/abs/util directory. Copy the script from the util directory to your MongoDB primary node. The training period and threshold can be changed simultaneously or individually.

**Note:** After executing the script, stop and start all ABS nodes for the updated values to take effect.

Access script help by logging into the MongoDB primary machine and running the following command:

```
/opt/pingidentity/mongo/update.sh help
```

### **Example Change the training period to 48 hours**

```
/opt/pingidentity/mongo/update.sh -u absuser -p abs123 --
attack_initial_training 48
updating training_period to 48
WriteResult({ "nMatched" : 1, "nUpserted" : 0, "nModified" : 1 })
The current values of the variables are:
attack_initial_training=48
attack_update_interval=24
api_discovery=false
discovery_update_interval=1
continuous_learning=true
discovery_initial_period=24
url_limit=100
response_size=100
window_length=24
discovery_subpath=3
percentage_diskusage_limit=80

Global Config successfully updated
```

### **Tune thresholds for false positives**

ABS automatically generates attack thresholds which are used by the machine learning system to identify attacks and anomalies. Initial attack thresholds are determined based on training and production traffic

in your API ecosystem. At the end of the training period, ABS calculates the first set of system-generated threshold values and uses these values to detect attacks.

By default, system generated threshold values are updated every 24-hours. This frequency can be changed at start-up by modifying `attack_update_interval` using [Global configuration update REST API](#) on page 355 or anytime by using the `update.sh` script available in the `util` directory. The minimum value is 1-hour as sufficient traffic is required to update the model.

You can change the threshold period at anytime by running the `update.sh` script. The value of the updated threshold period is applicable immediately. For example, if the current threshold update period is 10 hours and the new threshold period is 12 hours, then the AI model updates the threshold at the 12th hour.

Access script help by logging into the MongoDB machine and running the following command:

```
/opt/pingidentity/mongo/update.sh help
```

### Example: change the training period and threshold interval together

```
/opt/pingidentity/mongo/update.sh -u absuser -p abs123 --
attack_initial_training 24 --attack_update_interval 24
updating attack_initial_training to 24
WriteResult({ "nMatched" : 1, "nUpserted" : 0, "nModified" : 1 })
updating attack_update_interval to 24
WriteResult({ "nMatched" : 1, "nUpserted" : 0, "nModified" : 1 })
The current values of the variables are:
attack_initial_training=24
attack_update_interval=24
api_discovery=true
discovery_initial_interval=48
```

### Check threshold values

Threshold values can be checked using the ABS Threshold API. For each attack type, one or more variables (for example, Var A, B) is used by the machine learning process during attack detection. All variables have a Normal Threshold Value (tn), and some variables also have an Extreme Threshold Value (tx). These values are used during the attack detection process and automatically update over time to provide improved accuracy.

To view the current threshold settings, use the [GET method](#) with the following ABS `threshold` API:

```
https://<ip_address>:<port>/v4/abs/attack/threshold?api=<api_name>
```

The IP address and port corresponding to the host ABS machine. The API payload returned is a JSON file which shows the threshold values for each attack type. See [Get Threshold API](#) for an example.

### Change attack thresholds

Ping Identity recommends using the automatically generated system thresholds in your production operations. However, if attacks are detected for legitimate traffic (i.e. false positives), then manual tuning options are provided. An administrator has two choices:

- Change the system generated threshold value to a larger user-generated value.
- Disable the variable to stop detecting attacks (see [Disabling Attacks](#))

To identify settings to change, generate an [attack report](#) which includes attacks known to be false positives. For each identified attack, an Attack Code (for example, "varA (Tn), varB (Tn)") is listed with the threshold variable(s) that triggered the attack. The Attack Code includes the responsible variables (for example, A, B) and threshold types (for example, Tn, Tx); the threshold type can be manually adjusted. Ping Identity recommends slowly increasing the triggered threshold value(s) using user-generated

thresholds. After each update, evaluate the new setting to see if false positives are reduced. The process can be repeated until the issue is addressed.

The [Threshold API PUT method](#) is used to manually override the system generated setting with a user-defined value. When configuring the threshold manually, the normal threshold (T<sub>n</sub>), the extreme threshold (T<sub>x</sub>), or either threshold can be individually set.

You can also use [Tune thresholds and unblock clients](#) on page 23 in Dashboard to tune threshold values for a specific client identifier.

**Note:** Make sure that you are in [user](#) mode before changing the threshold manually.

### Change threshold value T<sub>n</sub> only

The T<sub>n</sub> threshold value can be changed for each attack type for a specific API. The initial T<sub>x</sub> value is automatically calculated based on the gap between the values of T<sub>n</sub> and T<sub>x</sub>. This gap is determined at the end of the [training period](#). The minimum gap is 1, and the value of T<sub>x</sub> always bigger than T<sub>n</sub>. Here is an example:

Values at end of training period:

- T<sub>n</sub> = 12
- T<sub>x</sub> = 16
- Gap = 4 (T<sub>x</sub>-T<sub>n</sub>)

Threshold API is used to set T<sub>n</sub>=13 for an API variable.

- T<sub>x</sub> = 17 (Gap value of 4 is automatically added to new T<sub>n</sub>value)

This difference between the value of T<sub>n</sub> and T<sub>x</sub> is maintained when only T<sub>n</sub> is moved. However, the difference between the value of T<sub>n</sub> and T<sub>x</sub> can be changed when only T<sub>x</sub> is changed.

**Note:** The value of T<sub>n</sub> can never be more than the value of T<sub>x</sub>.

### Changing Threshold Value T<sub>x</sub> only

Change the T<sub>x</sub> value to adjust the gap between the normal and extreme threshold setting for an attack type on a specific API. The value of T<sub>x</sub> defines the gap which ranges from a minimum of 1 to the maximum value defined in [Threshold range for T<sub>n</sub> and T<sub>x</sub>](#). When T<sub>x</sub> is moved, the system calculated gap calculated at the end of the training period is no longer used. For the attack types where T<sub>x</sub> is not applicable to the variable, " [na](#) " is displayed in the threshold API.

**Note:** If the value of only T<sub>n</sub> is moved without modifying T<sub>x</sub>, then the new gap between the value of T<sub>n</sub> and T<sub>x</sub> is used until the value of T<sub>x</sub> is changed again.

### Change threshold value T<sub>n</sub> and T<sub>x</sub> together

Both T<sub>n</sub> and T<sub>x</sub> can be changed for an attack type on a specific API. When T<sub>n</sub> and T<sub>x</sub> are moved simultaneously, the newly defined value of T<sub>n</sub> and gap for T<sub>x</sub> are changed. The ranges of T<sub>n</sub> and T<sub>x</sub> values are detailed in [Threshold range for T<sub>n</sub> and T<sub>x</sub>](#).

### How to configure threshold value

To manually set a threshold, use the PUT method with the following ABS `attack` API:

[https://<ip\\_address>:<port>/v5/abs/attack/threshold?api=<api\\_name>](https://<ip_address>:<port>/v5/abs/attack/threshold?api=<api_name>)

The IP address and port correspond to the host ABS machine. The API input payload is a JSON file which sets the threshold value for attack types. The parameters include attack type and Normal Threshold



(tn) value. When manually setting the threshold for a variable, ABS Threshold API displays both system generated and user configured threshold values. ABS applies the user configured threshold values until it is reconfigured to use system generated values (see below).

### Manually set thresholds

The threshold API with PUT method sets the operation mode for the variable by configuring mode to `system` or `user`. The following snippet of Threshold API with PUT method shows how to change the threshold mode from system to user and change value of `tn`, `tx`, or both at the same time. If you do not wish to change the value for `tn` or `tx` in user mode, leave the field blank by putting "" in the Threshold API body. In the following snippet, the value of `tn` and `tx` both are changed.

```
{
  "api_name" : "atmapp",
  "mode": "user",
  "ioc_threshold": [
    {
      "type": "api_memory_attack_type_2",
      "variable": "A",
      "tn": "9",
      "tx": "12"
    },
    {
      "type": "data_exfiltration_attack",
      "variable": "A",
      "tn": "18",
      "tx": ""
    },
    {
      "type": "data_exfiltration_attack",
      "variable": "B",
      "tn": "18",
      "tx": ""
    },
    {
      "type": "api_memory_attack_type_1",
      "variable": "A",
      "tn": "18",
      "tx": ""
    }
  ]
}
{
  "api_name" : "shop",
  "mode": "user",
  "ioc_threshold": [
    {
      "type": "api_memory_attack_type_2",
      "variable": "A",
      "tn": "13"
    },
    {
      "type": "api_memory_attack_type_2",
      "variable": "B",
      "tn": "10"
    }
  ]
}
```

The API response is displayed below:

```
{
```

```

"message": success: "Thresholds set to user mode for given variables.",
"date": "Mon Jan 08 15:36:05 IST 2018"
}

```

After a threshold value is manually set, ABS uses the updated user threshold values to detect attacks.

When threshold mode is changed back to `system`, the user-configured values are no longer used or displayed in the threshold API output. The following snippet shows changing threshold to system mode from user mode for two variables associated with an API memory attack:

```

{
  "api_name" : "shop",
  "mode": "system",
  "ioc_threshold": [
    {
      "type": "api_memory_attack_type_2",
      "variable": "A",
    },
    {
      "type": "api_memory_attack_type_2",
      "variable": "B",
    }
  ]
}

```

The API response is displayed below:

```

{
  "message": success: "Thresholds set to system mode for given variables.",
  "date": "Mon Jan 06 15:36:05 IST 2018"
}

```

## Resetting trained APIs

Reset trained APIs using `Reset Trained API` REST API of ABS.

Before you begin

- Make sure that ASE and ABS AI engine communication is disabled. The communication between ASE and ABS is disabled so that no new access log files are sent to ABS AI engine for processing. The training can be reset only when all the access logs available with ABS are processed.
- Wait for all the access logs available with ABS to be processed.

About this task

Use the API with `DELETE` method when you want to retrain the model with more inclusive API traffic or the API JSON definition has changed in ASE. When an AI model training is reset, all the training data, detected attacks for those APIs and the generated thresholds are lost. However, the metrics data is retained even after the API is retrained. Using the `Reset Trained API`, you can retrain one or more than one API at the same time. If ABS is deployed in a cluster setup, you can run the API on any of the ABS cluster nodes.

Complete the following steps to retrain the APIs:

Steps

1. Disable access log upload from ASE to ABS by entering the following command on ASE command-line.

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs

```

2. Update the API JSON definition in ASE if there are any changes in API.

### 3. Run the `reset` API in ABS.

The following is the URL for the `reset` API.

```
https://<ABS_host>:<ABS_port>/v4/abs/reset
```

- Method: DELETE
- Body:

```
{
  "apis" : ["shop", "electronics"]
}
```

#### **Note:**

If you run the `reset` API when the ABS AI engine is processing access logs, you get an error message with 409 status code.

```
{
  "error" : "AI engine is processing access logs; try later. To complete
the process,
  make sure to disable access log upload from ASE. For more information,
  see the ABS admin guide."
}
```

- ### 4. Wait for the ABS AI engine successfully to reset the APIs.
- You receive the following success message.

```
{
  "status" : "API training reset is successful"
  "apis" : [ "shop", "electronics" ]
}
```

## Disable attack detection

If you want to disable attack detection for a specific API, tune the user threshold to a maximum value. This follows the same process as changing the attack threshold and sets the user-generated normal threshold value to the maximum for the attack type (refer to [Threshold range for  \$T\_n\$  and  \$T\_x\$](#)  on page 460 for a list of maximum values). When the normal threshold is set to maximum, the machine learning system will not generate attacks based on that variable. All other variables continue to operate in either `system` or `user` mode.

You can also disable or enable an attack ID globally by using the `attackstatus` REST API. For more information, see [Enable or disable attack IDs](#) on page 372.

## API discovery and configuration

The ABS AI Engine works in tandem with ASE to automatically discover new and unknown APIs in your ecosystem. You can view the discovered APIs by using the [ABS discovery REST API](#). You can also add the discovered APIs to ASE by using API Discovery in PingIntelligence for APIs Dashboard. For more information, see [Discovered APIs](#) on page 540.

Following is the summary of the steps to configure API discovery in your environment:

1. Enable ABS in ASE
2. Define `root` API JSON in ASE. ABS discovers APIs only for a `root` API JSON in ASE.

3. Optionally, configure OAuth token and API Key parameters in `root` API JSON
4. Configure discovery related parameters using [Global configuration update REST API](#) on page 355.

**Note:** Use the `update.sh` script to edit the default values related to API discovery. For more information on update script, see [Manage discovery intervals](#) on page 354.

### Configuration in ASE for API discovery

- **Enable ABS in ASE** Enable ABS by running the `enable_abs` command in ASE:

```
./bin/cli.sh -u admin -p admin enable_abs
ABS is now enabled
```

To verify, run the `status` command in ASE:

```
./bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                  : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
  MB
google pubsub         : disabled
```

- **Configure root API in ASE:** ABS discovers APIs in your environment only when `root` API is defined in ASE. If you have configured other APIs in ASE along with the `root` API, ABS monitors traffic only on the `root` API for the discovery process.

A `root` API in ASE is an API for which the API JSON file has `url` as `"/"` and `hostname` as `"*"`. Following is a snippet of `root` API JSON:

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/",
    "hostname": "*",
    "cookie": "",
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "enable_blocking": false,
    "cookie_idle_timeout": "200m",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "login_url": "",
    "api_mapping": {
      "internal_url": ""
    }
  }
}
```

```
},
```

A sample `root` API ships with ASE in `/pingidentity/ase/config/api` directory.

**Note:** If API discovery is enabled in ABS without `root` API in ASE and you run the `discovery` REST API, it displays an error message: `root API not configured in ASE`. To discover APIs configure `root` API in ASE.

- **API JSON configuration (Optional):** You can optionally configure the settings for `cookie`, `oauth2_access_token`, `apikey_qs`, or `apikey_header` in the `root` API JSON file in ASE.

API discovery process discovers these parameters in an API only when you set these in the `root` API. API discovery reports these attributes of an API only when it receives at least 50% of traffic having these attributes. For example, if the `root` API receives 100 requests and 51 requests have OAuth token, then the OAuth token is reported in the discovered API. Similarly, if the same traffic has less than 50% traffic for API keys or cookies, then they are not reported in the discovered API.

**ABS configuration for API discovery:** Configure API discovery in ABS by setting the `api_discovery` parameter to `true` using [Global configuration update REST API](#) on page 355.

The following table summarizes the variables related to API discovery that you need to configure. If you want update the values on an already running system, use the `update.sh` script. For more information on update script, see [Manage discovery intervals](#) on page 354:

### API discovery variables

Variable	Description
<code>api_discovery</code>	Set this variable to <code>true</code> to switch on API discovery. To switch off API discovery, set it to <code>false</code> . The default value is <code>true</code> .
<code>discovery_initial_period</code>	The initial time in hours during which APIs are discovered in your API ecosystem. The default and minimum value is 1-hour.
<code>discovery_update_interval</code>	The time interval in hours at which any new discovered APIs are reported. The default and minimum value is 1-hour.
<code>discovery_subpath</code>	The number of subpaths that is discovered in an API. The minimum value is 1 and maximum value is 6. For more information, see <a href="#">Discovery Subpaths</a> on page 351.
<code>url_limit</code>	Defines the maximum number of URLs that are reported in a discovered API.

### API discovery process

ABS discovery process starts when ASE sends the access log files to ABS. The discovery process and reporting interval are defined by the variables configured using [Global configuration update REST API](#) on page 355.

1. ABS processes the ASE log files and looks for new APIs. During the discovery period, ABS monitors the traffic on the API JSON (`root` API) and requires only one valid request to report an API. ABS considers only valid (200-OK response) requests for discovering APIs. At the end of the discovery


period, ABS publishes the discovered APIs. ABS specifically looks for the following four values in the incoming traffic on the root API:

- Hostname
- Pathinfo
- Scheme or protocol
- Backend server. If ASE is deployed in a sideband mode, then backend server is not reported.

2. At the end of the initial discovery period, ABS does one of the following:

- If the API definition was learned, then ABS outputs the discovered APIs with the parameters as detailed in the [table](#) below.
- If the API definition is incomplete, then ABS repeats the discovery process (Step 1) for a `discovery_update_interval` (default is 1-hour).

The following illustration shows an example of the API discovery



process:

The illustration shows three APIs, API 1, API 2, and API 3 are the undiscovered APIs in your environment. The traffic for these APIs is coming through the root API configured in ASE. The following points explain the discovery process:

- API 1 receives a request in the initial training period with a 200-OK response. This API is discovered at the end of `discovery_initial_period` T1.
- API 2 receives one invalid request (404 response) during the initial discovery period. This API is not reported at T1.
- API 3 did not receive any request in the initial discovery period. Hence it was not reported at T1. However, API 3 got one valid request (200-OK response) in the time-period T1-T2, hence it was reported at time T2. The time period T1-T2 is `discovery_update_interval`.

**Note:** The initial discovery period applies only to fresh installation of PingIntelligence components. If you are upgrading an existing deployment, the `discovery_update_interval` applies.

ABS API definition reports include the following information for each discovered API:

Information	Description
<code>host</code>	Hostname or IP address that is serving the API.
<code>basePath</code>	The base path on which the API is served. The base path is relative to the host. The value starts with a leading / (slash).
<code>schemes</code>	API protocol - value must be HTTP, HTTPS, WS, or WSS.

consumes	A list of MIME types that the APIs can consume.
produces	A list of MIME types that the APIs can produce.
paths	Relative paths to the individual endpoints.
responses	Placeholder to hold responses.
backendHosts	Backend servers for the API.
server_ssl	Value is <code>true</code> if backend API server supports encrypted connection. Set to <code>false</code> if the backend API server does not support encrypted connection.

You can add the discovered APIs automatically to ASE using [Discovered APIs](#) on page 540 in PingIntelligence for APIs Dashboard. Note that when the root API is configured with the token, cookie, or API key parameter, PingIntelligence will expect all discovered APIs to use the defined identifiers for authentication. If this is not the case, then add the discovered APIs manually in ASE.

## Discovery Subpaths

Before starting API discovery, it is important to configure the subpath depth which allows the AI Engine to accurately detect the API environment. Subpath depth provides the number of sub-paths for a unique API definition. Here are examples of `discovery_subpath` values:

- “1”, example: `/atmapp` is basepath for `/atmapp/zipcode`, `/atmapp/update`, etc.
- “2”, example: `v1/atmapp` is basepath for `v1/atmapp/zipcode`, `v1/atmapp/update`, etc.
- “3”, example: `v1/cust1/atmapp` is basepath for `v1/cust1/atmapp/zipcode`, etc.

The `discovery_subpath` parameter is configured using the [Global configuration update REST API](#) on page 355 and it defines the number of sub-paths in the basepath of the API. The default value is set to 1. The maximum allowed value is six when API Security Enforcer (ASE) is deployed in [inline mode](#) and it is 10 when ASE is deployed in [sideband mode](#). The `url_limit` parameter defines the maximum number of URLs reported in a discovered API. The default value is 100.

**Note:** You can also update the discovery sub-path using PingIntelligence for APIs Dashboard. For more information, see [Discovered APIs](#) on page 540.

**Updating `url_limit` and `discovery_subpath`:** You can update the `url_limit` and `discovery_subpath` by running the `update.sh` script. The `update.sh` script is available in the `/opt/pingidentity/abs/util` directory. Copy the script from the `util` directory to your MongoDB primary machine.

**Note:** After executing the script, stop and start all ABS nodes for the updated values to take effect.

**Example:** Change the `url_limit` to 50

```
/opt/pingidentity/mongo/update.sh -u absuser -p abs123 --url_limit 50
updating url_limit to 50
WriteResult({ "nMatched" : 1, "nUpserted" : 0, "nModified" : 1 })
The current values of the variables are:
attack_initial_training=48
attack_update_interval=24
api_discovery=false
discovery_update_interval=1
continuous_learning=true
discovery_initial_period=1
url_limit=50
response_size=100
window_length=24
discovery_subpath=3
percentage_diskusage_limit=80
```

You need to restart all the ABS node for your changes to take effect.

Update script help is available by logging into the MongoDB primary machine and running the following command:

```
/opt/pingidentity/mongo/update.sh help
```

## ABS Discovery API

The Discovery API uses the GET method to display the discovered API details and is reported only when the `host`, `basepath`, `schemes`, `paths`, and `responses` information is populated. ABS provides the following external REST API which uses the GET method to view the discovered APIs:

**URL:** </v4/abs/discovery>

Following is a snippet of the summary output of `discovery` API:

```
{
  "company": "ping identity",
  "name": "api_discovery_summary",
  "description": "This report contains summary of discovered APIs",
  "summary": [
    {
      "api_name": "api_0",
      "host": "bothcookientoken.com",
      "basePath": "/path1",
      "created": "Fri Mar 06 09:29:51:591 2020",
      "updated": "Fri Mar 06 09:50:03:372 2020"
    },
    {
      "api_name": "api_1",
      "host": "path5",
      "basePath": "/path1/path2/path3",
      "created": "Fri Mar 06 10:59:38:975 2020",
      "updated": "Fri Mar 06 11:36:45:596 2020"
    },
    {
      "api_name": "api_14",
      "host": "path5",
      "basePath": "/path1/path2/path3/path4/path5",
      "created": "Fri Mar 06 11:59:14:804 2020",
      "updated": "Fri Mar 06 12:18:24:732 2020"
    },
    {
      "api_name": "api_15",
      "host": "pathx",
      "basePath": "/path1/path2/path3/path4",
      "created": "Fri Mar 06 11:59:16:092 2020",
      "updated": "Fri Mar 06 13:19:25:283 2020"
    },
    {
      "api_name": "api_16",
      "host": "pathx",
      "basePath": "/path1/path2/path3/path4/path5",
      "created": "Fri Mar 06 11:59:16:244 2020",
      "updated": "Fri Mar 06 12:18:26:227 2020"
    },
    {
      "api_name": "api_17",
      "host": "path6",
      "basePath": "/path1/path2/path3/path4/path5/path6",

```



```

        "created": "Fri Mar 06 11:59:14:952 2020",
        "updated": "Fri Mar 06 12:18:24:876 2020"
    },
    {
        "api_name": "api_19",
        "host": "path7",
        "basePath": "/path1/path2/path3/path4/path5/path6",
        "created": "Fri Mar 06 11:59:15:096 2020",
        "updated": "Fri Mar 06 12:18:25:028 2020"
    },
    {
        "api_name": "api_9",
        "host": "path2",
        "basePath": "/path1/path2",
        "created": "Fri Mar 06 10:59:00:616 2020",
        "updated": "Fri Mar 06 13:19:23:003 2020"
    }
]
}
}

```

Each API name (for example, `api_1`) is auto-generated and starts from `api_0`. This API name can be specified in the `api_name` query parameter to request more details as shown in the next example.

**URL:** `/v4/abs/discovery?api_name=api_1`

The following is a snippet of a discovered API:

```

{
  "company": "ping identity",
  "name": "api_discovery_details",
  "description": "This report contains details of discovered APIs",
  "info": {
    "title": "api_7"
  },
  "host": "127.0.0.1",
  "basePath": "/shop-books3",
  "cookie": "",
  "oauth2_access_token": false,
  "apikey_qs": "",
  "apikey_header": "",
  "schemes": [
    "HTTP/1.1"
  ],
  "consumes": [],
  "produces": [
    "text/html"
  ],
  "server_ssl": true,
  "backendHosts": [
    "127.0.0.1:4001"
  ],
  "backendServers": [
    "127.0.0.1:4001"
  ],
  "username_header": "",
  "jwt": {
    "username": "username",
    "clientId": "client_id",
    "location": "h:authorization:bearer"
  },
  "paths": {
    "/shop-books3": {
      "GET": {

```



## Global configuration update REST API

ABS provides a REST API to update global configurations related to ABS AI engine. The updated global configuration values take effect immediately. Following is the list of global configurations that you can update using the `globalconfig` API:

- `attack_initial_training`
- `attack_update_interval`
- `api_discovery`
- `discovery_initial_period`
- `discovery_subpath`
- `discovery_update_interval`
- `poc`

**Note:** The `poc` variable is used to set the ABS AI engine in *POC (proof-of-concept) mode* to demonstrate the capabilities of the AI engine. In a production environment the value is always set to *false*. It is recommended not to switch the mode in production environment. If you must change the ABS AI engine to `poc` mode, contact PingIdentity support.

- `url_limit`
- `response_size`
- `continous_learning`
- `attack_list_count`
- `root_api_attack`
- `session_inactivity_duration`

You can use the `globalconfig` API with GET and PUT methods. Following is the URL for `globalconfig` API. Only the Admin user can use the PUT method to update the values. For more information on different ABS users, see [ABS users for API reports](#) on page 315.

**URL** - `https://<abs_host>:<abs_port>/v5/abs/globalconfig`

	Header	Value
<b>Access Key</b>	<code>x-abs-ak</code>	<string> For example, <code>abs_ak</code> or the value of the access key that you configured at the time of installation.
<b>Secret Key</b>	<code>x-abs-sk</code>	<string> For example, <code>abs_sk</code> or the value of the secret key that you configured at the time of installation.

When you use the `globalconfig` API with GET method, it fetches the current value of the global configuration.

```
{
  "company": "ping identity",
  "name": "api_globalconfig",
  "description": "This report contains status information of ABS global configurations",
  "global_config": {
```

```

    "attack_initial_training": 2,
    "attack_update_interval": 1,
    "api_discovery": true,
    "discovery_initial_period": 100,
    "discovery_subpath": 3,
    "discovery_update_interval": 1,
    "poc": false,
    "url_limit": 120,
    "response_size": 150,
    "continuous_learning": false,
    "attack_list_count": 400000,
    "root_api_attack": true,
    "session_inactivity_duration": 10
  }
}

```

You can update the global configuration values that the API fetched using the PUT method. Provide the new values in the body as shown in the example below.

```

{
  "api_discovery": true,
  "discovery_initial_period": 1
  "discovery_update_interval": 1
}

```

```

{
  "success": "global config updated successfully"
}

```

You can update either one or more than one global configurations at once. Note that the values are updated only when the body of the request is well-formed.

**Note:** You can also update the global configurations using [Discovered APIs](#) on page 540 in PingIntelligence Dashboard or [ABS Postman collections](#). However, you can only change the following variables using PingIntelligence Dashboard:

- `attack_initial_training`
- `attack_update_interval`
- `api_discovery`
- `discovery_initial_period`
- `discovery_subpath`
- `discovery_update_interval`

#### Related links

- [AI Engine training](#) on page 338
- [AI Engine training variables](#) on page 339
- [Update the training variables](#) on page 341
- [API discovery and configuration](#) on page 347
- [Manage discovery intervals](#) on page 354

## REST API attacks

For each API, the API JSON file (see [API Security Enforcer Admin Guide](#) for information) determines whether the attacks and other reports are based on OAuth token, API Keys, username, cookie, or IP address. An environment with multiple APIs can support a mixture of identifier types in a single ABS AI Engine. Client identifier examples include. Client identifier examples include:

- **API using OAuth2 tokens** – When an API JSON file is configured with OAuth2 token `parameter = true`, then attack information is associated with the OAuth2 access token used by the hacker. Configuring the OAuth2 token parameter is recommended when access tokens are present as it is a unique client identifier that eliminates issues identified below with IP addresses.
- **APIs using API Keys:**When API JSON file is configured with API Key either in the query string or the header, ABS detects attacks on the value of the API Key. For example, if there are two API Keys in the system, X-API-KEY-1 and X-API-Key-2 with values as `api_key_1` and `api_key_2`, then a total of four client identifiers are added to blacklist of ASE:
  - X-API-KEY-1: `api_key_1`
  - X-API-KEY-2: `api_key_2`
  - X-API-KEY-1: `api_key_2`
  - X-API-KEY-2: `api_key_1`
- **APIs with cookie** – When the cookie parameter is configured, most attacks are reported with cookie identifiers, the exception being pre-authentication attacks (such as client login attacks). Configuring the cookie parameter is recommended when cookies are present as it is a unique client identifier that eliminates issues identified below with IP addresses.
- **API JSON without a cookie or token parameter** – When cookie and OAuth2 token parameters are not configured, all attacks are reported with the client IP address which is determined based on the following:
  - **XFF header present:** The first IP address in the XFF list is used as the client identifier. When forwarding traffic, load balancers and other proxy devices with XFF enabled add IP addresses to the XFF header to provide application visibility of the client IP address. The first IP address in the list is typically associated with the originating IP address.

**Note:** XFF is not always a reliable source of the client IP address and can be spoofed by a malicious proxy.

- **No XFF header:** When no XFF header is present, the source IP address of the incoming traffic is used as the client identifier. In this configuration, make sure that the incoming traffic is using public or private IP addresses associated with the actual client devices, not a load balancer or proxy device on your premise.

**Note:** When a load balancer or other proxy without XFF enabled is the source of the inbound traffic, then all client traffic will be associated with the load balancer IP addresses. This configuration will not provide effective attack reporting unless cookies or tokens are used.

### REST API attack based on username:

In some sideband deployments, for example, PingAccess with PingFederate, the username of the accessing client is available via RFC 7662 token introspection or other techniques. ABS AI Engine detects attacks based on the username. Unlike other client identifiers, username is not configured in the API JSON file. The ABS AI engine detects the username from the metadata sent by ASE.

To change the client identifier for an existing API, save the API JSON with a new name and update the configuration to include the new client identifier parameter. ABS then re-trains the model for this API and starts detecting attacks.

## REST API attack types

ABS AI Engine reports on REST API attacks by delivering reports on per API attacks, that is, client attack targeted a single API. ABS AI engine also reports across API attacks, that is, client attack targeted multiple APIs.

**Per API attacks:** These attacks are reported on a specific API and is based on activity from a client using an OAuth token, cookie or an IP address. Each attack type is assigned a type ID and can be accessed using the `attack` REST API of ABS. Entering type ID 0 reports on all attacks on the specified API except for attack types which are analyzed across APIs.

Use the following ABS REST API to access different attack types: [https://<ABS\\_IP:port>/v4/abs/attack?later\\_date=yyyy-mm-ddTth:mm&later\\_date=yyyy-mm-ddTth:mm&api=<api\\_name>&type=<type\\_id>](https://<ABS_IP:port>/v4/abs/attack?later_date=yyyy-mm-ddTth:mm&later_date=yyyy-mm-ddTth:mm&api=<api_name>&type=<type_id>).

**For example,** [https://192.168.11.166:8080/v4/abs/attack?later\\_date=2019-12-31T18:00&later\\_date=2019-10-25T13:30&api=shop&type=1](https://192.168.11.166:8080/v4/abs/attack?later_date=2019-12-31T18:00&later_date=2019-10-25T13:30&api=shop&type=1)

The following table lists the attack types for individual APIs:

### Per API attacks

Attack Type	Type ID
Data Exfiltration Attack Type 1	1
Single Client Login Attack Type 1	2
Multi-Client Login Attack	3
Stolen Token Attack Type 1 (Token)	4
Stolen Cookie Attack Type 1 (Cookie)	4
API Memory Attack Type 1	5
API Memory Attack Type 2	6
Cookie DoS Attack	7
API Probing Replay Attack Type 1	8
API DDoS Attack Type 1	9
Extreme Client Activity Attack	10
Extreme App Activity Attack	11
API DoS Attack	12
API DDoS Attack Type 2	13
Data Deletion Attack	14
Data Poisoning Attack	15
Data Exfiltration Attack Type 2	21
Content Scraping Type 2	28
Unauthorized Client Attack	29
Header Manipulation Attack	37
User Data Exfiltration Type 2	39
User Data Injection	40

Query Manipulation Attack	41
---------------------------	----

### Across API attacks:




These attacks are detected across APIs and are based on activity from a client username or client using an OAuth token, cookie or an IP address. For example, a hacker with a token may execute attacks which span across multiple APIs.

Use the following ABS REST API to access different attack types: [https://<ABS\\_IP:port>/v4/abs/attack?later\\_date=yyyy-mm-ddThh:mm&later\\_date=yyyy-mm-ddThh:mm&type=<type\\_id>](https://<ABS_IP:port>/v4/abs/attack?later_date=yyyy-mm-ddThh:mm&later_date=yyyy-mm-ddThh:mm&type=<type_id>).

**For example**, [https://192.168.11.166:8080/v4/abs/attack?later\\_date=2019-12-31T18:00&later\\_date=2019-10-25T13:30&type=18](https://192.168.11.166:8080/v4/abs/attack?later_date=2019-12-31T18:00&later_date=2019-10-25T13:30&type=18)

The following table lists the attack types for individual APIs:

### Across API attacks

Attack Type	Type ID
Stolen Token Attack Type 2	16
Stolen Cookie Attack Type 2	17
API Probing Replay Attack Type 2 (Cookie)	18
API Probing Replay Attack Type 2 (Token)	19
API Probing Replay Attack Type 2 (IP)	20
Excessive Client Connections (Cookie)	22
 <b>Note:</b> Applicable only for Inline ASE deployment. For more information, see <b>Excessive Client Connections</b> section below.	
Excessive Client Connections (Token)	23
 <b>Note:</b> Applicable only for Inline ASE deployment. For more information, see <b>Excessive Client Connections</b> section below.	
Excessive Client Connections (IP)	24
 <b>Note:</b> Applicable only for Inline ASE deployment. For more information, see <b>Excessive Client Connections</b> section below.	
Content Scraping Type 1 (Cookie)	25
Content Scraping Type 1 (Token)	26
Content Scraping Type 1 (IP)	27
Single Client Login Attack Type 2	30
Stolen API Key Attack	31
API Probing Replay Attack Type 1	32

API Probing Replay Attack Type 2	33
API Probing Replay Attack Type 1	34
API Probing Replay Attack Type 2	35
Sequence Attack	36
Abnormal API Access	38

### Excessive Client Connections

Excessive client connections attack has three attack IDs, 22, 23, and 24 for IP, cookie, and token. These three attack IDs are disabled by default when you install PingIntelligence. However, you can enable these attacks for PingIntelligence inline deployment by using the `attackstatus` REST API in ABS or through PingIntelligence for APIs Dashboard. For more information, see [Enable or disable attacks in ABS](#) and [Enable or disable attacks through PingIntelligence Dashboard](#). Attack IDs 22,23, and 24 are not available for PingIntelligence sideband deployment since ASE does not receive the API traffic directly from the client.

For more information on Inline and Sideband ASE deployment modes, see [ASE deployment modes](#).

## Attacks based on username activity

ABS AI Engine detects attacks based on behavior from the username accessing API services. PingIntelligence captures the username information in the following three ways:

- User information is captured if the incoming request has a JSON Web Token (JWT). For more information, see [Extract user information from JWT in inline mode](#) on page 232 and [Extract user information from JWT in sideband mode](#) on page 178.
- Similarly, if an incoming request has a custom header with user information, then the username is extracted. For more information see, [Extract username from custom header in sideband mode](#) on page 182 and [Extract username from custom header in inline mode](#) on page 237.
- PingIntelligence is deployed in sideband mode with an API gateway that supports capturing username information. Following is a list of PingIntelligence and API gateway integrations that support capturing username information:
  - [Akana API gateway sideband integration](#) on page 558
  - [Axway sideband integration](#) on page 616
  - [PingIntelligence Apigee integration](#) on page 581
  - [Mulesoft sideband integration](#) on page 684
  - [PingAccess sideband integration](#) on page 747
  - [NGINX sideband integration](#) on page 698
  - [NGINX Plus sideband integration](#) on page 714
  - [PingIntelligence WSO2 integration](#) on page 764

Note the following points for ABS AI engine to detect username based attacks:

- OAuth token parameter, `oauth2_access_token`, must be configured in API JSON in ASE. For more information on API JSON definition see, [Defining an API using API JSON configuration file in sideband mode](#) on page 170
- The incoming request must have an OAuth token in it for ABS AI engine to detect username based attacks

**i Important:** ABS AI engine will not detect username attacks for requests where the server responds with an HTTP 401 `Unauthorized Error` code. This will prevent blocking of a valid user if an attacker tries to impersonate the user.

### Detected attacks based on username



Attack Type	Description	id	Single or Across APIs
API Probing Replay Attack Type 1	Probing or breach attempts on an API service – also called fuzzing - Username	34	Across APIs
API Probing Replay Attack Type 2	Probing an API service over an extended time period - Username	35	Across APIs
Sequence Attack	Abnormal sequence of API transactions	36	Across APIs
Abnormal API Access	Abnormal user behavior when accessing API services	38	Across APIs
User Data Exfiltration Type 2	A User is extracting excessive data via an API service	39	Single API
User Data Injection	A User is injecting excessive data into an API service	40	Single API

**i Important:** While reporting an abnormal sequence, if username is available with the API ecosystem, ABS reports username or else it reports OAuth token.

## Attacks based on API Key activity

ABS AI Engine detects attacks based on client activity using an API Key. The following table lists the attacks detected on a single API or across multiple APIs.

### Detected attacks based on API Keys

Attack Type	Description	id	Single or Across APIs
Stolen API Key Attack	A stolen API Key is being used to attack an API service.	31	Across APIs
API Probing Replay Attack Type 1	Probing or breach attempts on an API service – also called fuzzing - API Key	32	Across APIs
API Probing Replay Attack Type 2	Probing an API service over an extended time period - API Key	33	Across APIs

## Attacks based on cookie activity

ABS AI Engine detects attack based on client activity using a Cookie. The following table lists the attacks detected on a single API or across multiple APIs.

### Detected attacks based on cookie activity

Attack Type	Description	id	Single or Across APIs
-------------	-------------	----	-----------------------


Data Exfiltration Attack Type 1	Data is being extracted via a REST API service.	1	Single API
Stolen Cookie Attack	A stolen cookie is being used to attack an API service.	4	Single API
API Memory Attack Type 1	Flooding of an API service with data or code.	5	Single API
API Memory Attack Type 2		6	Single API
Cookie DoS Attack	Client attacking session management service with a high volume of cookies.	7	Single API
API Probing Replay Attack	Probing or breach attempts on an API service – also called fuzzing.	8	Single API
API DDoS Attack Type 1	A DDoS or distributed attack is disrupting an API service.	9	Single API
Extreme Client Activity Attack	Extreme client request activity on an API service.	10	Single API
Extreme App Activity	Extreme App Activity may indicate an injection or other CPU intensive attack.	11	Single API
Data Deletion	Excessive data deletion activity on an API service.	14	Single API
Data Poisoning	Extreme create or update activity received on an API service.	15	Single API
Stolen Cookie Attack Type 2	A stolen cookie is being used to attack an API service.	17	Across APIs
API Probing Replay Attack Type 2	Probing an API service over an extended time period - Cookie	18	Across APIs
Data Exfiltration Attack Type 2	Data is being extracted via a REST API service over an extended time period.	21	Single API


Excessive Client Connections	Client is establishing an excessive number of TCP connections.	22	Across APIs
<div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> The <b>Excessive Client Connections</b> attack type is disabled by default. For more information, see <a href="#">REST API attack types</a> on page 358.</p> </div>			
Content Scraping Type 1	Client abnormally accessing API content	25	Across APIs
Content Scraping Type 2	Client abnormally accessing API content over an extended time period	28	Single API
Header Manipulation	Probing an API using malicious headers	37	Single API
Query Manipulation Attack	Modifying query string to inject malicious content or impact API service	41	Single API

## Attacks based on token activity

ABS AI Engine detects attacks based on client activity using an OAuth Token. The following table lists the detected attacks on a single API or across multiple APIs

Attack Type	Description	type_id	Single or Across APIs
Data Exfiltration Attack Type 1	Data is being extracted via a REST API service.	1	Single API
Stolen Access Token Attack	A stolen access token is being used to attack an API service.	4	Single API
API Memory Attack Type 1	Flooding of an API service with data or code.	5	Single API
API Memory Attack Type 2		6	Single API
API Probing Replay Attack	Probing or breach attempts on an API service – also called fuzzing.	8	Single API
API DDoS Attack Type 1	A DDoS or distributed attack is disrupting an API service.	9	Single API
Extreme Client Activity Attack	Extreme client request activity on an API service.	10	Single API

Extreme App Activity	Extreme App Activity may indicate an injection or other CPU intensive attack.	11	Single API
Data Deletion	Excessive data deletion activity on an API service.	14	Single API
Data Poisoning	Extreme create or update activity received on an API service.	15	Single API
Stolen Token Attack Type 2	A stolen token is being used to attack an API service.	16	Across API
API Probing Replay Type 2	robing an API service over an extended time period - Token	19	Across APIs
Data Exfiltration Attack Type 2	Data is being extracted via a REST API service over an extended time period.	21	Single API
Excessive Client Connections	Client is establishing an excessive number of TCP connections.	23	Across APIs
<div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b> The <b>Excessive Client Connections</b> attack type is disabled by default. For more information, see <a href="#">REST API attack types</a> on page 358.</p> </div>			
Content Scraping Type 1	Client abnormally accessing API content	26	Across APIs
Content Scraping Type 2	Client abnormally accessing API content over an extended time period	28	Single API
Sequence Attack	Abnormal sequence of transactions	36	Across APIs
Header Manipulation	Probing an API using malicious headers	37	Single API
Query Manipulation Attack	Modifying query string to inject malicious content or impact API service	41	Single API

 **Important:** ABS also reports Sequence attack on OAuth token. However, if a username is available, it is first reported against username.

## Attacks based on IP activity

The following table lists the REST API attacks detected using an IP address as the client identifier. The attacks can be on a single API or across APIs

Attack Type	Description	id	Single or Across APIs
Data Exfiltration Attack	Data is being extracted via a REST API service.	1	Single API
Single Client Login Attack Type 1	Login service attacked by a bot or rogue client.	2	Single API
Multi-Client Login Attack	Login service is under DDoS attack by bots.	3	Single API
API Memory Attack Type 1	Flooding of an API service with data or code.	5	Single API
API Memory Attack Type 2		6	Single API
API Probing Replay Attack	Probing or breach attempts on an API service – also called fuzzing.	8	Single API
API DDoS Attack Type 1	A DDoS or distributed attack is disrupting an API service.	9	Single API
Extreme Client Activity Attack	Extreme client request activity on an API service.	10	Single API
Extreme App Activity	Extreme App Activity may indicate an injection or other CPU intensive attack.	11	Single API
API DoS Attack	Client (IP) sending high volumes of requests to overload application services	12	Single API
API DDoS Attack Type 2	Multiple clients (IP botnet) sending high volume traffic to overload the API service	13	Single API
Data Deletion	Excessive data deletion activity on an API service.	14	Single API
Data Poisoning	Extreme create or update activity received on an API service.	15	Single API
API Probing Replay Type 2	Probing an API service over an extended time period - IP	20	Across APIs

Data Exfiltration Attack Type 2	Data is being extracted via a REST API service over an extended time period.	21	Single API
Excessive Client Connections	Client is establishing an excessive number of TCP connections.	24	Across APIs
<div style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b> The <b>Excessive Client Connections</b> attack type is disabled by default. For more information, see <a href="#">REST API attack types</a> on page 358.</p> </div>			
Content Scraping Type 1	Client abnormally accessing API content.	27	Across APIs
Content Scraping Type 2	Client abnormally accessing API content over an extended time period	28	Single API
Unauthorized client attack	Client without a token or cookie is probing an API service.	29	Single API
Single Client Login Attack Type 2	Login service attacked by a bot or rogue client over an extended time period	30	Across APIs
Header Manipulation	Probing an API using malicious headers	37	Single API
Query Manipulation Attack	Modifying query string to inject malicious content or impact API service	41	Single API

## WebSocket API attack detection

**Note:** WebSocket API attack detection is only supported when ASE is running in Inline mode.

### Client identifier determination – IP address or cookie

In each API, the presence of the cookie parameter in the API JSON file (see *API Security Enforcer Admin Guide* for information) determines whether attacks are reported based on cookie identifier or IP address. An environment with multiple APIs can support a mixture of identifier types in a single ABS system. Use cases include the following:

- **API JSON with cookie parameter** – When the cookie parameter is configured, most attacks are reported with cookie identifiers, the exception being pre-authentication attacks (for example, client login attacks). Configuring the Cookie parameter is recommended when cookies are present as it is a unique client identifier that eliminates the issues identified below with IP addresses.

- **API JSON without cookie parameter** – When the cookie parameter is not configured, all the attacks are reported with the client IP address which is determined based on the following:
- **XFF header present:** The first IP address in the XFF list is used as the client identifier. When forwarding traffic, load balancers and other proxy devices with XFF enabled add IP addresses to the XFF header to provide application visibility of the client IP address. The first IP address in the list is typically associated with the originating IP address.

**Note:** XFF is not always a reliable source of the client IP address and can be spoofed by a malicious proxy.

- **No XFF header:** When no XFF header is present, the source IP address of the incoming traffic is used as the client identifier. In this configuration, make sure that the incoming traffic is using public or private IP addresses associated with the actual client devices, not a load balancer or proxy device on your premise.

**Note:** When a load balancer or other proxy without XFF enabled is the source of the inbound traffic, then all client traffic will be associated with the load balancer IP addresses. This configuration will not provide effective attack reporting.

To change from a cookie to an IP identifier for an existing API, save the API JSON with a new name. ABS then re-trains the model for this API and starts detecting IP-based attacks. For more information on configuring API JSON files, see *API Security Enforcer Admin Guide*.

**Note:** OAuth2 token based attacks are not reported for WebSocket APIs.

The following tables list the attacks detected by ABS for WebSocket APIs for cookie and IP:

#### Cookie based detected attacks:

Attack Type	Description	id
Summary Attack Report	Provides a summary of all attacks detected.	0
WS Cookie Attack	WebSocket session management service receiving an abnormal number of cookies.	50
WS DoS Attack	Inbound streaming limits exceeded on a WebSocket service.	52
WS Data Exfiltration Attack	Data is being extracted via a WebSocket API service.	53

#### IP based detected attacks

Attack Type	Description	id
Summary Attack Report	Provides a summary of all attacks detected.	0
WS Identity Attack	WebSocket identity service receiving excessive upgrade requests.	51
WS DoS Attack	Inbound streaming limits exceeded on a WebSocket service.	52

## Attack detection on root API

A root API in ASE is defined by configuring / for `url` variable and \* for `hostname` variable. Following is a snippet of a truncated API JSON in ASE depicting the configuration of root API.

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/",
    "hostname": "*",
```

You can choose between enabling or disabling attack detection on global API by configuring `root_api_attack` global variable in the `abs_init.js` and `abs_init_ldap.js` file. By default attack detection is disabled on root API. Set it to `true` if you want to detect attacks on the root API. Configure this variable either before starting ABS, or you can use the `update.sh` script to update the value. For more information on `update.sh` script, see [Update the training variables](#)

```
db.global_config.insert({
  "attack_initial_training": "24",
  "attack_update_interval": "24",
  "url_limit": "100",
  "response_size": "100",
  "job_frequency": "10",
  "window_length": "24",
  "enable_ssl": true,
  "api_discovery": false,
  "discovery_initial_period": "24",
  "discovery_subpath": "1",
  "continuous_learning": true,
  "discovery_update_interval": "1",
  "attack_list_count": "500000",
  "resource_monitor_interval": "10",
  "percentage_diskusage_limit": "80",
  "root_api_attack": false,
  "session_inactivity_duration": "30"
});
```

**Training and attack detection:** If the attack detection is disabled on the root API, then ABS Admin REST API displays n/a (not applicable) for `training_started_at` and `training_duration`. The `prediction_mode` is `false`.

```
{
  "api_name": "rest_api",
  "host_name": "*",
  "url": "/",
  "api_type": "regular",
  "creation_date": "Fri Apr 05 05:41:00 UTC 2019",
  "servers": 2,
  "protocol": "http",
  "cookie": "",
  "token": false,
  "training_started_at": "n/a",
  "training_duration": "n/a",
  "prediction_mode": false
}
```



## Manage attack blocking

---

ASE and ABS work in tandem to detect and block attacks. ASE detects attacks in real-time, blocks the hacker, and reports attack information to ABS. ABS AI Engine uses behavioral analysis to look for advanced attacks.

Attack management is done in both ABS and ASE.

### In ABS, you can:

- List active, expired or a consolidated list of active and expired client identifiers for a specific time period. For more information see, [ABS blacklist reporting](#) on page 369.
- Delete specific client identifiers from ABS blacklist or bulk delete a type of client identifier using ABS REST API. For more information, see [Delete individual client identifiers](#) on page 370 and [Bulk delete client identifiers](#) on page 371.
- Enable or disable a specific attack ID. When you disable an attack ID, ABS stops reporting attacks across all client identifiers for that attack ID. For more information, see [Enable or disable attack IDs](#) on page 372.
- Configure the time-to-live (TTL) for each client identifier type. The TTL time applies to all the detected attacks for that client identifier. For more information, see [TTL for client identifiers in ABS](#) on page 374.

### In ASE, you can:

- Manually add or delete entries from whitelist and blacklist
- Enable or disable automatic blocking of ABS detected attack types
- Enable or disable ASE detected real-time attacks. ASE detects real time attacks only in an inline deployment.

For more information see, [Attack management in ASE](#) on page 377.

## ABS blacklist reporting

ABS Provides `attacklist` REST API to complete the following two operations:

- List the various client identifiers (API Key, OAuth token, Username, Cookie, and IP address) which are related to probable attack
- Delete the client identifiers which may be a cause of false positive

Reporting active and expired client identifiers

ABS provides an `attacklist` REST API with GET method to list of active attacks in the system, expired attacks, and consolidated (active and expired) attacks together. The list of detected client identifiers depends on the [TTL set for the client identifiers](#). The attack list reports the detected client identifiers (active or expired) for the queried period. The time-period is part of the API query parameter.

**URL:** `/v4/abs/attacklist`

**Report the active detected attacks:** Use the following REST API URL to report the active client identifiers:

`/v4/abs/attacklist?earlier_date=<>&later_date=<>&status=active`: The API lists the active client identifiers for a time-period between `earlier_date` and `later_date`. PingIntelligence ASE fetches the active client identifiers list from ABS for blocking the clients.

**Report the expired detected attacks:** Use the following REST API URL to report the expired client identifiers:

`/v4/abs/attacklist?earlier_date=<>&later_date=<>&status=expired`: The API lists the expired client identifiers for a time-period between `earlier_date` and `later_date`. The expiry of detected attacks in the system depends on the configured TTL.

**Report the consolidated (active and expired) detected attacks:** Use the following REST API URL to report the consolidated client identifiers attacks:

[/v4/abs/attacklist?earlier\\_date=<>&later\\_date=<>](/v4/abs/attacklist?earlier_date=<>&later_date=<>): The API lists all the client identifiers for a time-period between `earlier_date` and `later_date`.

### Delete individual client identifiers

Using the `attacklist` API with PUT method, you can delete the active client identifiers. The API requires only the body without any other headers. In the message body of the API, provide the client identifiers in their respective sections. The API checks if the client identifier is present in the active list or not before deleting. If you provide a client identifier which is not part of the active list, the API ignores such client identifiers.

**URL:** `/v4/abs/attacklist`

**Method:** PUT

Following is a sample message body for `attacklist` API to delete client identifiers:

```
{
  "ips": [
    "192.168.4.10",
    "10.10.10.73",
    "10.1.1.4",
    "10.9.8.7"
  ],
  "cookies": {
    "PHPSESSIONID": [
      "Cookie1",
      "Cookie2"
    ],
    "JSESSIONID": [
      "Cookie3",
      "AnyCookie",
      "Cookie4"
    ]
  },
  "oauth_tokens": [
    "Token1",
    "Token2",
    "Token3"
  ],
  "api_keys": [
    "type2_api_key",
    "api_key_1",
    "api_key_2",
  ],
  "usernames": [
    "username1",
    "username2",
    "username3",
  ]
}
```

Following is the message showing the client identifiers that were deleted:

```
{
  "message": "Success: The following attacks have been removed:",
  "date": "Thu Jun 09 03:39:12 UTC 2019",
  "attacklist": {
    "ips": [
      "192.168.4.10",
      "10.10.10.73",
    ]
  }
}
```

```

        "10.1.1.4",
        "10.9.8.7"
    ],
    "cookies": {
        "PHPSESSIONID": [
            "Cookie1",
            "Cookie2"
        ],
        "JSESSIONID": [
            "Cookie3",
            "AnyCookie",
            "Cookie4"
        ]
    },
    "oauth_tokens": [
        "Token1",
        "Token2",
        "Token3"
    ],
    "api_keys": [
        "type2_api_key",
        "api_key_1",
        "api_key_2",
    ],
    "usernames": [
        "username1",
        "username2",
        "username3",
    ]
}
}

```

You can provide only specific section of a client identifier in the message body. For example, if you only want to delete specific usernames, then provide only the username section in the message body. Make sure that the JSON file is well formed.

### Bulk delete client identifiers

Use the bulk delete option when you believe that a large number of false positives have been identified. You can also use the bulk delete option to clear the blacklist in case of a reset. To bulk delete client identifiers, use the ABS `attacklist` REST API with DELETE method. Following is the URL for the API:

**URL:** </v4/abs/attacklist>

**Method:** DELETE

To bulk delete all the entries of a client identifier or all client identifier, configure the `body` of the `attacklist` API request as show below:

```

{
  delete_all: false,
  delete_all_ips: true,
  delete_all_cookies: true,
  delete_all_oauth_tokens: false,
  delete_all_api_keys: true,
  delete_all_usernames: false,
}

```

In the sample request `body` above, the `attacklist` API deletes all entries for IP, Cookie, and API Key. If, in the next time interval, the AI engine flags the same client identifiers, the blacklist is populated again. To permanently stop a false positive from being reported, tune the thresholds using the PingIntelligence Web GUI for the specific client identifier.

The following table describes the options:

Option	Description
delete_all	This option overrides all the other configured options in the message body. If it is set to <code>true</code> , all the client identifiers are deleted irrespective of what their individual configuration is. Set it to <code>false</code> , if you want to exercise other options.
delete_all_ips	Set it true to delete all the IP addresses across all attack types from the blacklist.
delete_all_cookies	Set it true to delete all the cookies across all attack types from the blacklist.
delete_all_oauth_tokens	Set it true to delete all the OAuth token across all attack types from the blacklist.
delete_all_api_keys	Set it true to delete all the API Keys across all attack types from the blacklist.
delete_all_usernames	Set it true to delete all the usernames across all attack types from the blacklist.

## Enable or disable attack IDs

You can enable or disable one or more than one attack type using ABS `attackstatus` REST API with the PUT method. The AI engine keeps updating the thresholds in the background, even when you disable an attack ID. Calculating the thresholds in the background allows ABS to report attacks if you enable an attack ID in the future.

If you have disabled an attack while the AI engine is processing the log data, ABS may still report attacks for a few minutes. The attack IDs would be disabled when the next batch of access log files are processed. When you enable an attack from the disabled state, ABS takes a few minutes to report the API attacks.

**URL:** </v4/abs/attackstatus>

**Method:** PUT

The following attack IDs cannot be disabled from ABS as these are real-time attacks reported by ASE:

- Attack ID 13: API DDoS Attack Type 2
- Attack ID 100: Decoy Attack. This attack ID can be disabled from ASE.
- Attack ID 101: Invalid API Activity. This attack ID can be disabled from ASE.

To enable or disable an attack ID, you should:

1. Use the `attackstatus` REST API with GET method to fetch the current status of an attack ID
2. Use the `attackstatus` REST API with PUT method to enable or disable the attack IDs.

**Fetch the attack ID status:** Run the `attackstatus` REST API with the GET method to fetch the current state of all the attack IDs. The output is divided into two sections, enabled and disabled, along with the time when an attack ID was enabled or disabled. Following is a snippet of response:

```

"attack_status": {
  "enabled" : [
    {
      "attack_id" : 1,
      "attack_name" : "Data Exfiltration Attack Type 1",
      "enabled_time" : "Thu Aug 22 12:56:39:158 2019"
    },
  ],

```

```

    {
      "attack_id" : 2,
      "attack_name" : "Single Client Login Attack Type 1",
      "enabled_time" : "Thu Aug 22 12:56:39:158 2019"
    },
    {
      "attack_id" : 4,
      "attack_name" : "Stolen Token Attack Type 1",
      "enabled_time" : "Thu Aug 22 12:56:39:158 2019"
    }
  ],
  "disabled" : [
    {
      "attack_id" : 3,
      "attack_name" : "Data Exfiltration Attack Type 1",
      "disabled_time" : "Thu Aug 22 12:56:39:158 2019"
    },
    {
      "attack_id" : 5,
      "attack_name" : "Single Client Login Attack Type 1",
      "disabled_time" : "Thu Aug 22 12:56:39:158 2019"
    }
  ]
}

```

**Note:** Attack IDs 13, 100, and 101 are always displayed as enabled in the response.

**Disable or enable attack IDs:** To disable or enable an attack ID, use the PUT method with the `attackstatus` REST API. To disable or enable an attack ID, provide the `attack_id` and `action`. The `action` can be `enable` or `disable`. Following is sample body of the PUT request:

```

{
  "attacks": [
    {
      "attack_id": "1",
      "action": "disable"
    },
    {
      "attack_id": "2",
      "action": "enable"
    },
    {
      "attack_id": "13",
      "action": "disable"
    }
  ],
  {
    "attack_id": "100",
    "action": "disable"
  },
  {
    "attack_id": "101",
    "action": "disable"
  }
]
}

```

Following is a sample response:

```

{
  "attack_status": [
    {

```

```

        "attack_id": "1",
        "attack_name": "Data Exfiltration Attack Type 1",
        "status": "Attack ID disabled successfully"
    },
    {
        "attack_id": "2",
        "attack_name": "Single Client Login Attack Type 1",
        "status": "Attack ID is already enabled"
    },
    {
        "attack_id": "13",
        "attack_name": "API DDoS Attack Type 2",
        "status": "Attack ID cannot be disabled. For more information,
refer to PingIntelligence documentation."
    },
    {
        "attack_id": "100",
        "attack_name": "Decoy Attack",
        "status": "Attack ID cannot be disabled. For more information,
refer to PingIntelligence documentation."
    },
    {
        "attack_id": "101",
        "attack_name": "Invalid API Activity",
        "status": "Attack ID cannot be disabled. For more information,
refer to PingIntelligence documentation."
    }
]
}

```

## TTL for client identifiers in ABS

The ABS AI Engine blacklist supports configuring the length of time that a client identifier type (username, OAuth token, API Key, cookie, and IP address) remains on the blacklist. Each client identifier type can be configured with a different value in minutes. The default value of zero minutes means that the AI engine will not remove any client identifiers from the blacklist unless the TTL value is changed.

You can change the default value of TTL by using the `admin` ABS REST API which supports configuring a different TTL in minutes for each client identifier. Following are the recommended steps to managing client identifier TTL:

1. Use the ABS `admin` REST API to fetch the current TTL values.
2. Use the PUT method with the ABS `admin` REST API to configure the TTL.

When you update the TTL value, it applies to the client identifiers in the blacklist that the AI engine identified from that time onwards. For example, you set initial TTL of 120-minutes at 6 AM for 100 client identifiers in the blacklist, then the list will exist till 8 AM. Now, if you change the TTL at 7 AM to 30-minutes, then the initial list of 100 client identifier will still exist till 8 AM. The new 30-minute TTL will apply to the client identifiers reported from 7 AM onwards.

**Fetch the current TTL value:** Use the `admin` API to fetch the current TTL of the client identifiers:

<https://<ip>:<port>/v4/abs/admin> . Following is a sample output displaying the current TTL values:

```

{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters,
and ASE logs",
  "license_info": {

```

```

    "tier": "Subscription",
    "expiry": "Wed Jan 15 00:00:00 UTC 2020",
    "max_transactions_per_month": 1000000000,
    "current_month_transactions": 98723545,
    "max_transactions_exceeded": false,
    "expired": false
  },
  "across_api_prediction_mode": true,
  "api_discovery": {
    "subpath_length": "1",
    "status": true
  }
"apis": [
  {
    "api_name": "app",
    "host_name": "*",
    "url": "/atm_app_oauth",
    "api_type": "decoy-incontext",
    "creation_date": "Thu Dec 26 09:51:10 UTC 2019",
    "servers": 0,
    "protocol": "http",
    "cookie": "",
    "token": true,
    "training_started_at": "Thu Dec 26 09:52:29 UTC 2019",
    "training_duration": "1 hour",
    "prediction_mode": true,
    "apikey_header": "",
    "apikey_qs": ""
  }
],
"abs_cluster": {
  "abs_nodes": [
    {
      "node_ip": "172.17.0.1",
      "os": "DISTRIB_ID=Ubuntu - ",
      "cpu": "4",
      "memory": "7.8G",
      "filesystem": "19%",
      "bootup_date": "Wed Dec 25 15:01:06 UTC 2019"
    }
  ],
  "mongodb_nodes": [
    {
      "node_ip": "172.17.0.1",
      "status": "up"
    }
  ]
},
"ase_logs": [
  {
    "ase_node": "8f9d07c5-c5c4-43c3-97be-9672c7fd2986",
    "last_connected": "Thu Dec 26 10:51:13 UTC 2019",
    "logs": {
      "start_time": "Thu Dec 26 09:51:14 UTC 2019",
      "end_time": "Thu Dec 26 10:51:13 UTC 2019",
      "gzip_size": "429.96KB"
    }
  }
],
"percentage_diskusage_limit": "80%",
"scale_config": {
  "scale_up": {
    "cpu_threshold": "70%",
    "cpu_monitor_interval": "30 minutes",
    "memory_threshold": "70%",

```

```

    "memory_monitor_interval": "30 minutes",
    "disk_threshold": "70%",
    "disk_monitor_interval": "30 minutes"
  },
  "scale_down": {
    "cpu_threshold": "10%",
    "cpu_monitor_interval": "300 minutes",
    "memory_threshold": "10%",
    "memory_monitor_interval": "300 minutes",
    "disk_threshold": "10%",
    "disk_monitor_interval": "300 minutes"
  }
},
"attack_ttl": {
  "ids": [
    {
      "id": "ip",
      "ttl": 0
    },
    {
      "id": "cookie",
      "ttl": 0
    },
    {
      "id": "access_token",
      "ttl": 0
    },
    {
      "id": "api_key",
      "ttl": 0
    },
    {
      "id": "username",
      "ttl": 0
    }
  ]
}
}
}

```

**Configure the TTL:** Use the PUT method with `admin` REST API to configure the TTL in minutes:

**URL:** <https://<ip>:<port>/v4/abs/admin>

**Method:** PUT

**Body:**

```

{
  "ids" : [
    {
      "id" : "ip",
      "ttl" : 10
    },
    {
      "id" : "cookie",
      "ttl" : 10
    },
    {
      "id" : "access_token",
      "ttl" : 10
    },
  ],
}

```



```
{
  "id" : "api_key",
  "ttl" : 10
},
{
  "id" : "username",
  "ttl" : 10
}
]
```

**Response:**

```
{
  "message": "TTL updated successfully",
  "date": "Thu Dec 26 10:59:40 UTC 2019"
}
```

To verify the new TTL values, rerun the ABS `admin` REST API with the GET method.

## Automated ASE attack blocking

### Automatic blocking of attacks with ASE

When the AI Engine detects an attack, it adds an entry to its blacklist which consists of usernames, tokens, API Keys, cookies, and IP addresses of clients which were detected executing attacks. If blocking is enabled for the API, the blacklist is automatically sent to ASE nodes which blocks the client's future access using the identifiers on the list.

### Activate log processing for ABS

To activate ABS log processing, execute the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs
```

After log processing is enabled, ASE sends log data to ABS which processes the log data to look for attacks and generate reports.

### Automatically block ABS detected attacks

ABS generates a list of clients which are suspected of executing attacks. ABS can be configured to automatically send the attack list to ASE which blocks client access. By default, automatic blocking is inactive, execute the following ASE command to activate automatic client blocking.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin enable_abs_attack
```

### Disable attack blocking

To disable automatic sending of ABS attack lists to ASE, execute the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin disable_abs_attack
```

## Attack management in ASE

In ASE you manage detected attacks either through blacklist and whitelist. Client identifiers in blacklist are blocked by ASE while those in the whitelist are never blocked. You can also choose to block or allow a client identifier at API level by configuring the individual API JSON.

- **Whitelist** – List of “safe” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that will not be blocked by ASE. The list is manually created using ASE CLI commands.

- **Blacklist** – List of “bad” IP addresses, cookies, OAuth2 Tokens, API keys, or Usernames that are always blocked by ASE. The list consists of entries from one or more of the following sources:
  - ABS detected clients suspected of executing attacks (for example, data exfiltration)
  - ASE detected clients suspected of executing attacks (for example, invalid method, decoy API accessed). These attacks are reported to ABS and become part of ABS blacklist also after further AI processing.
  - List of “bad” client identifiers manually added using ASE CLI

### Manage ASE whitelist

Valid ASE operations for OAuth2 Tokens, Cookies, IP addresses, Username, and API Keys on a white list include:

- **Add an entry**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist ip
10.10.10.10
ip 10.10.10.10 added to whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist cookie
JSESSIONID cookie_1.4
cookie JSESSIONID cookie_1.4 added to whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist token
token1.4
token token1.4 added to whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist api_key
X-API-KEY key_1.4
api_key X-API-KEY key_1.4 added to whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_whitelist username
user1
username user1 added to whitelist
```

- **View whitelist**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_whitelist
Whitelist
1) type : ip, value : 1.1.1.1
2) type : cookie, name : JSESSIONID, value : cookie_1.1
3) type : token, value : token1.3
4) type : api_key, name : X-API-KEY, value : key_1.4
```

- **Delete an entry**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist ip
4.4.4.4
ip 4.4.4.4 deleted from whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist cookie
JSESSIONID cookie_1.1
```

```
cookie JSESSIONID cookie_1.1 deleted from whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist token
token1.1
token token1.1 deleted from whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist
api_key X-API-KEY key_1.4
api_key X-API-KEY key_1.4 deleted from whitelist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_whitelist
username user1
username user1 deleted from whitelist
```

- **Clear the whitelist**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin clear_whitelist
This will delete all whitelist Attacks, Are you sure (y/n) : y
Whitelist cleared
```

### Manage ASE blacklist

Valid ASE operations for IP addresses, Cookies, OAuth2 Tokens, Username, and API Keys on a black list include:

- **Add an entry**

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist ip
1.1.1.1
ip 1.1.1.1 added to blacklist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist cookie
JSESSIONID ad233edqsdld23redwefew
cookie JSESSIONID ad233edqsdld23redwefew added to blacklist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist token
ad233edqsdld23redwefew
token ad233edqsdld23redwefew added to blacklist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist api_key
AccessKey b31dfa4678b24aa5a2daa06aba1857d4
api_key AccessKey b31dfa4678b24aa5a2daa06aba1857d4 added to blacklist
```

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_blacklist username
user1
username user1 added to blacklist
```

- **View blacklist** - entire Black list or based on the type of real time violation.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist all
Manual Blacklist
1) type : ip, value : 10.10.10.10
2) type : cookie, name : JSESSIONID, value : cookie_1.4
3) type : token, value : token1.4
4) type : api_key, name : X-API-KEY, value : key_1.4
Realtime Decoy Blacklist
1) type : ip, value : 4.4.4.4
Realtime Protocol Blacklist
```

```

1) type : token, value : token1.1
2) type : ip, value : 1.1.1.1
3) type : cookie, name : JSESSIONID, value : cookie_1.1
Realtime Method Blacklist
1) type : token, value : token1.3
2) type : ip, value : 3.3.3.3
3) type : cookie, name : JSESSIONID, value : cookie_1.3
Realtime Content-Type Blacklist
1) type : token, value : token1.2
2) type : ip, value : 2.2.2.2
3) type : cookie, name : JSESSIONID, value : cookie_1.2

```

- **Blacklist based on decoy IP addresses**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist decoy
Realtime Decoy Blacklist
1) type : ip, value : 4.4.4.4

```

- **Blacklist based on protocol violations**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_protocol
Realtime Protocol Blacklist
1) type : token, value : token1.1
2) type : ip, value : 1.1.1.1
3) type : cookie, name : JSESSIONID, value : cookie_1.1

```

- **Blacklist based on method violations**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_method
Realtime Method Blacklist
1) type : token, value : token1.3
2) type : ip, value : 3.3.3.3
3) type : cookie, name : JSESSIONID, value : cookie_1.3

```

- **Blacklist based on content-type violation**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
invalid_content_type
Realtime Content-Type Blacklist
1) type : token, value : token1.2
2) type : ip, value : 2.2.2.2
3) type : cookie, name : JSESSIONID, value : cookie_1.2

```

- **Automated blacklist (ABS detected attacks)**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin view_blacklist
abs_detected
No Blacklist

```

- **Delete an entry**

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin delete_blacklist ip
1.1.1.1
ip 1.1.1.1 deleted from blacklist

```

```

./bin/cli.sh -u admin -p admin delete_blacklist cookie JSESSIONID
avbry47wdfgd

```

```
cookie JSESSIONID avbry47wdfgd deleted from blacklist
```

```
./bin/cli.sh -u admin -p admin delete_blacklist token
58fcb0cb97c54afbb88c07a4f2d73c35
token 58fcb0cb97c54afbb88c07a4f2d73c35 deleted from blacklist
```

- **Clearing the blacklist**

```
./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :y
Blacklist cleared
./bin/cli.sh -u admin -p admin clear_blacklist
This will delete all blacklist Attacks, Are you sure (y/n) :n
Action canceled
```

When clearing the Blacklist, make sure that [real-time ASE detected](#) attacks and ABS detected attacks are disabled. If not disabled, the blacklist gets populated again as both ASE and ABS are continuously detecting attacks.

### Per API blocking in ASE

ASE can be configured to selectively block on a per API basis by configuring an API JSON file parameter. To enable per API blocking for each API, set the `enable_blocking` parameter to `true` in the API JSON. For example:

```
api_metadata": {
  "protocol": "http",
  "url": "/",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "200m",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": false,
  "oauth2_access_token": false,
  "apikey_qs": "",
  "apikey_header": "",
  "enable_blocking": true,
  "login_url": "",
  "api_mapping": {
    "internal_url": ""
  }
},
```

If per API blocking is disabled, ABS still detects the suspected attacks for that specific API, however, ASE does not block them. ASE will continue to block the suspected attacks on other APIs with the `enable_blocking` set to `true`.

ASE CLI commands are also supported to enable blocking for the specified API

- `./cli.sh -u admin -p admin enable_blocking {api_id}`

Disable blocking for the specified API

- `./cli.sh -u admin -p admin disable_blocking {api_id}`

## Attack reporting

Attack reports provide information about the suspected attacks on each API. The ABS Attack API provides reports by specifying the `type_id` (see descriptions in [Attack Types](#)) and receiving attack details including time frame, client identifier, and an attack code (see [Changing Attack Thresholds](#) for an explanation of attack codes). The format of the ABS `attack` API is:

```
https://<hostname>:<port>/v4/abs/
later_date<>&earlier_date<>&api=<api_name>type=type_id
```

The hostname and port correspond to the host ABS machine.

### Understanding the API report parameters

Here is a brief description of the information available in the attack reports. Not all items are included in each of the reports. Please refer to [ABS external REST APIs](#) for detailed information in each report.

- **attack\_type:** Name of the attack type (for example, data exfiltration, stolen cookie)
- **description:** Description of the attack.
- **earlier\_date:** A date which is past in time. For example, if the query range is between March 12 and March 14, then the earlier date would be March 12.
- **later\_date:** A date which is more recent in time. For example, if the query range is between March 12 and March 14, then the later date would be March 14.
- **api\_name:** The name of the API for which report is displayed.
- **access\_time:** The time that the hacker accessed the API
- **attack\_code:** Code for the variables and thresholds used to detect attacks. For example, `attack_code": "varA(Tx, 25)` signifies that the attack was triggered because variable A with a value of 25 exceeded the Tx threshold. Current threshold values can be checked using the [Threshold API](#).
- **ddos\_info:** The `ddos_info` field provides a pointer to detailed information in the MongoDB system – for example, a list of IPs that were active during a DDoS attack (note: only included in DDoS reports). The data is accessible in the `login_dos` collection in `abs_data` database. To access the data, enter the following in your MongoDB command line:

```
>use abs_data
>db.login_dos.find({end_time:'Tue Mar 21 22:25:36:144 2017'},
{'ips':1}).pretty()
```

Use the `end_time` in the query to see the participating IPs.

The following pages provide examples of API JSON attack reports for Data Exfiltration, Stolen Cookie, and Multi-Client Login Attack.

**Note:** You can use the [Admin user or the restricted user](#) to access the API reports. For the Admin user, the cookie, token or the API key is not obfuscated.

## Consolidated result of attack types

To view all attack types on a given API in a single, consolidated report, use the ABS Attack API. Attack ID 0 gives all the attacks on a single API or across APIs based on the REST API query parameters.

### Consolidated attack report for an API:

The following attack API URL with attack ID as 0 gives all the attacks for a specific API: [https://<ABS\\_IP:port>/v4/abs/attack?later\\_date=yyyy-mm-ddTth:mm&later\\_date=yyyy-mm-ddTth:mm&api=<api\\_name>&type=<type\\_id>](https://<ABS_IP:port>/v4/abs/attack?later_date=yyyy-mm-ddTth:mm&later_date=yyyy-mm-ddTth:mm&api=<api_name>&type=<type_id>)

**Example:** [https://192.168.11.166:8080/v4/abs/attack?later\\_date=2018-12-31T18:00&later\\_date=2018-10-25T13:30&api=shop&type=0](https://192.168.11.166:8080/v4/abs/attack?later_date=2018-12-31T18:00&later_date=2018-10-25T13:30&api=shop&type=0)

You can further select a client identifier (IP, cookie, or a token) and carry out IP, cookie, or token forensics using the Forensic API.

```
{
  "company": "ping identity",
  "attack_type": "Data Exfiltration Attack",
  "cookie": "JSESSIONID",
```

```

"description": "Client (IP or Cookie) extracting an abnormal amount of data
for given API",
"earlier_date": "Tue Jan 02 16:00:00:000 2018",
"later_date": "Mon Jan 01 18:00:00:000 2018",
"api_name": "shop",
"cookies": [
{
"cookie": "extreme_client_activity_500_request",
"details": [
{
"access_time": "Fri Jan 12 08:44:39:086 2018",
"attack_code": "varA(Tx, 26)",
"attack_deviation": "varA(700%)"
},
{
"access_time": "Fri Jan 12 09:18:34:087 2018",
"attack_code": "varA(Tx, 25)",
"attack_deviation": "varA(700%)"
}
]
},
{
"company": "ping identity",
"attack_type": "API Probing Replay Attack",
"cookie": "JSESSIONID",
"description": "Client (IP or Cookie) probing or trying different parameter
values to breach
the API service for given API",
"earlier_date": "Tue Jan 02 16:00:00:000 2018",
"later_date": "Mon Jan 01 18:00:00:000 2018",
"api_name": "shop",
"cookies": [
{
"cookie": "api_dos_attack_type_1_shop_50_percent_error",
"details": [
{
"access_time": "Fri Jan 12 08:39:56:896 2018",
"attack_code": "varA(Tx, 47)",
"attack_deviation": "varA(700%)"
},
{
"access_time": "Fri Jan 12 09:18:34:087 2018",
"attack_code": "varA(Tx, 47)",
"attack_deviation": "varA(700%)"
}
]
},
}
]
}

```

### Consolidated attack report across API:

Use the following ABS REST API to access all the attack types: [https://<ABS\\_IP:port>/v4/abs/attack?later\\_date=yyyy-mm-ddThh:mm&later\\_date=yyyy-mm-ddThh:mm&type=<type\\_id>](https://<ABS_IP:port>/v4/abs/attack?later_date=yyyy-mm-ddThh:mm&later_date=yyyy-mm-ddThh:mm&type=<type_id>).

**Example:** [https://192.168.11.166:8080/v4/abs/attack?later\\_date=2018-12-31T18:00&later\\_date=2018-10-25T13:30&type=0](https://192.168.11.166:8080/v4/abs/attack?later_date=2018-12-31T18:00&later_date=2018-10-25T13:30&type=0)

You can further select a client identifier (IP, cookie, or a token) and carry out IP, cookie, or token forensics using the Forensic API.

```

[
{
"company": "ping identity",

```

```

    "attack_type": "Stolen Token Attack Type 2",
    "name": "api_attack_type",
    "description": "Client (Token) reusing cookies to deceive
application services.",
    "earlier_date": "Thu Oct 25 13:30:00:000 2018",
    "later_date": "Mon Dec 31 18:00:00:000 2018",
    "api_name": "all",
    "access_tokens": [
      {
        "access_token": "SYU4R2ZZN1IDYI0L",
        "details": [
          {
            "access_time": "Tue Nov 27 11:10:00:000 2018",
            "attack_code": "varA(Tn, 3)",
            "attack_deviation": "varA(700%)"
          },
          {
            "access_time": "Tue Nov 27 11:40:00:000 2018",
            "attack_code": "varA(Tn, 3)",
            "attack_deviation": "varA(700%)"
          },
          {
            "access_time": "Tue Nov 27 16:10:00:000 2018",
            "attack_code": "varA(Tn, 2)",
            "attack_deviation": "varA(700%)"
          }
        ]
      },
      {
        "access_token": "CT27QTP01K6ZW2AK",
        "details": [
          {
            "access_time": "Tue Nov 27 10:50:00:000 2018",
            "attack_code": "varA(Tn, 2)",
            "attack_deviation": "varA(700%)"
          },
          {
            "access_time": "Tue Nov 27 11:10:00:000 2018",
            "attack_code": "varA(Tn, 4)",
            "attack_deviation": "varA(700%)"
          },
          {
            "access_time": "Tue Nov 27 11:40:00:000 2018",
            "attack_code": "varA(Tn, 5)",
            "attack_deviation": "varA(700%)"
          }
        ]
      },
      {
        "ip": "100.64.7.124",
        "details": [
          {
            "access_time": "Tue Nov 27 11:20:00:000 2018",
            "attack_code": "varA(Tn, 3), varA(Tn, 3)",
            "attack_deviation": "varA(700%)"
          },
          {
            "access_time": "Tue Nov 27 11:30:00:000 2018",
            "attack_code": "varA(Tn, 3), varA(Tn, 3)",
            "attack_deviation": "varA(700%)"
          }
        ]
      }
    ],
  },

```



```

    {
      "ip": "100.64.10.18",
      "details": [
        {
          "access_time": "Tue Nov 27 11:10:00:000 2018",
          "attack_code": "varA(Tn, 3), varA(Tn, 3)",
          "attack_deviation": "varA(700%)"
        },
        {
          "access_time": "Tue Nov 27 11:40:00:000 2018",
          "attack_code": "varA(Tn, 3), varA(Tn, 3)",
          "attack_deviation": "varA(700%)"
        }
      ]
    }
  ]
}
]

```

## Real-time Detected attacks for inline ASE

API Security Enforcer supports real time attack detection and blocking for:

- API Pattern Enforcement – validate traffic to ensure it is consistent with the API definition
- API Deception – blocks hackers probing a Decoy API

### Enable ASE detected attacks

Enable real-time ASE detected attacks by running the following command on the ASE command line:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
enable_ase_detected_attack
ASE Detected Attack is now enabled

```

### Disable ASE detected attacks

Disable real-time ASE detected attacks by running the following command on the ASE command line:

```

/opt/pingidentity/ase/bin/cli.sh -u admin -p admin
disable_ase_detected_attack
ASE Detected Attack is now disabled

```

**Note:** When you disable ASE detected attacks, the attacks are deleted from the blacklist.

In real-time, ASE blocks hackers which violate pattern enforcement or probe decoy APIs. Hacker information is reported to ABS which generates ASE detected attack reports (type ID 101). Use the following ABS REST API to view the report:

[https://192.168.11.138:8080/v4/abs/attack?  
later\\_date=2018-07-16&earlier\\_date=2018-07-16&api=atmapp&type=101](https://192.168.11.138:8080/v4/abs/attack?later_date=2018-07-16&earlier_date=2018-07-16&api=atmapp&type=101)

### Real-time ASE detected attack based on OAuth2 token activity

```

{
  "company": "ping identity",
  "attack_type": "Invalid API Activity",
  "name": "api_attack_type",
  "description": "Clients using invalid method/protocol/content-type",
  "earlier_date": "Thu Jan 25 18:00:00:000 2018",

```

```

"later_date": "Fri Dec 28 18:00:00:000 2018",
"api_name": "atm_app_oauth",
"ips": [],
"cookies": [],
"access_tokens": [
  {
    "access_token": "token_protocol",
    "details": [
      {
        "access_time": "Fri Jan 26 20:58:04:770 2018",
        "attack_code": "protocol"
      },
      {
        "access_time": "Fri Jan 26 21:16:17:851 2018",
        "attack_code": "protocol"
      }
    ]
  },
  {
    "access_token": "token_method",
    "details": [
      {
        "access_time": "Fri Jan 26 20:58:04:819 2018",
        "attack_code": "method"
      },
      {
        "access_time": "Fri Jan 26 21:16:17:903 2018",
        "attack_code": "method"
      }
    ]
  },
  {
    "access_token": "token_contenttype",
    "details": [
      {
        "access_time": "Fri Jan 26 20:58:04:819 2018",
        "attack_code": "content_type"
      },
      {
        "access_time": "Fri Jan 26 21:16:17:903 2018",
        "attack_code": "content_type"
      }
    ]
  }
]
}

```

### Real-time ASE detected attack based on pattern enforcement violation

```

{
  "company": "ping identity",
  "attack_type": "Invalid API Activity",
  "cookie": "JSESSIONID",
  "name": "api_attack_type",
  "description": "Clients using invalid method/protocol/content-type",
  "earlier_date": "Thu Jan 25 18:00:00:000 2018",
  "later_date": "Fri Dec 28 18:00:00:000 2018",
  "api_name": "atm_app_public",
  "ips": [],
  "cookies": [
    {
      "cookie": "session_contenttype1",
      "details": [

```

```

{
  "access_time": "Fri Jan 26 21:17:10:662 2018",
  "attack_code": "content_type"
}
],
{
  "cookie": "session_method",
  "details": [
    {
      "access_time": "Fri Jan 26 20:58:06:656 2018",
      "attack_code": "method"
    },
    {
      "access_time": "Fri Jan 26 21:17:10:662 2018",
      "attack_code": "method"
    }
  ]
},
{
  "cookie": "session_contenttype",
  "details": [
    {
      "access_time": "Fri Jan 26 20:58:06:656 2018",
      "attack_code": "content_type"
    },
    {
      "access_time": "Fri Jan 26 21:17:10:662 2018",
      "attack_code": "content_type"
    }
  ]
},
{
  "cookie": "session_protocol",
  "details": [
    {
      "access_time": "Fri Jan 26 20:58:04:873 2018",
      "attack_code": "protocol"
    },
    {
      "access_time": "Fri Jan 26 21:16:47:314 2018",
      "attack_code": "protocol"
    }
  ]
},
{
  "cookie": "session_method1",
  "details": [
    {
      "access_time": "Fri Jan 26 21:17:10:662 2018",
      "attack_code": "method"
    }
  ]
},
{
  "cookie": "session_protocol1",
  "details": [
    {
      "access_time": "Fri Jan 26 21:16:47:314 2018",
      "attack_code": "protocol"
    }
  ]
}
],

```

```
"access_tokens": []
}
```

## Anomalous activity reporting

The Anomaly API provides detailed reporting on anomalous activity associated with a specified API. The types of anomalies detected include:

- Anomalies for each ABS attack type – activity which has the characteristics of one of the attack types (for example, API Memory Attack) but does not meet the threshold of an attack.
- Irregular URLs – suspicious URL traffic
- Anomalous request activity including injection attacks, overflow attacks, and system commands

This report detects leading indicators of attacks on API services and is reviewed to observe trends.

Here is an snippet from an Anomaly API JSON report for a cookie-based API:

```
{
  "company": "ping identity",
  "name": "api_anomalies",
  "description": " This report contains information on anomalous activity on
the specified
API",
  "later_date": "Tue Jan 14 18:00:00:000 2018",
  "earlier_date": "Sun Jan 12 18:00:00:000 2018",
  "api_name": "shop",
  "anomalies_summary": {
    "api_url": "shopapi",
    "total_anomalies": 14,
    "most_suspicious_ips": [],
    "most_suspicious_anomalies_urls": []
  },
  "anomalies_details": {
    "url_anomalies": {
      "suspicious_sessions": [],
      "suspicious_requests": []
    },
    "ioc_anomalies": [
      {
        "anomaly_type": "API Memory Attack Type 2",
        "cookies": [
          {
            "cookie": "AMAT_2_H",
            "access_time": [
              "Mon Jan 13 01:01:33:589 2018"
            ]
          },
          {
            "cookie": "AMAT_2_H",
            "access_time": [
              "Mon Jan 13 01:01:33:589 2018"
            ]
          }
        ]
      }
    ]
  },
}
```

## Deception and decoy API

---

### API Deception

ASE supports configuration of decoy APIs, either the for in-context or out-of-context mode. If a client accesses an ASE decoy API and later tries to access a legitimate API, ASE drops the connection and blocks the client from accessing any non-decoy APIs. *ASE Admin Guide* provides more information on API Deception Environments.

### Report ASE real-time decoy attack detection

ASE sends information about clients accessing decoy APIs to ABS which does further analysis and generates an API Deception report with type ID 100. Here is an example ABS REST API to generate an API Deception report:

[https://192.168.11.138:8080/v4/abs/attack?later\\_date=2018-07-16&earlier\\_date=2018-07-16&api=atmapp&type=100](https://192.168.11.138:8080/v4/abs/attack?later_date=2018-07-16&earlier_date=2018-07-16&api=atmapp&type=100)

```
{
  "company": "ping identity",
  "attack_type": "Decoy Attack",
  "name": "api_attack_type",
  "description": "Clients accessing decoy APIs",
  "earlier_date": "Mon Jan 01 12:00:00:000 2018",
  "later_date": "Mon Dec 31 02:28:00:000 2018",
  "api_name": "atmapp",
  "ips": [
    {
      "ip": "100.64.38.140",
      "details": [
        {
          "access_time": "Sun Jan 28 19:59:29:395 2018",
          "attack_code": "decoy"
        },
        {
          "access_time": "Sun Jan 28 19:59:29:395 2018",
          "attack_code": "decoy"
        },
        {
          "access_time": "Sun Jan 28 21:18:01:501 2018",
          "attack_code": "decoy"
        },
        {
          "access_time": "Sun Jan 28 21:18:01:501 2018",
          "attack_code": "decoy"
        },
        {
          "access_time": "Sun Jan 28 21:18:01:501 2018",
          "attack_code": "decoy"
        },
        {
          "access_time": "Sun Jan 28 21:18:01:501 2018",
          "attack_code": "decoy"
        }
      ]
    },
    {
      "ip": "100.64.38.144",
      "details": [
        {
          "access_time": "Sun Jan 28 19:59:29:395 2018",
```

```

"attack_code": "decoy"
},
{
"access_time": "Sun Jan 28 19:59:29:395 2018",
"attack_code": "decoy"
},
{
"access_time": "Sun Jan 28 21:18:01:501 2018",
"attack_code": "decoy"
},
{
"access_time": "Sun Jan 28 21:18:01:501 2018",
"attack_code": "decoy"
},
{
"access_time": "Sun Jan 28 21:18:01:501 2018",
"attack_code": "decoy"
},
{
"access_time": "Sun Jan 28 21:18:01:501 2018",
"attack_code": "decoy"
}
]
}
],
"cookies": [],
"access_tokens": []
}

```

## Decoy API

When decoy APIs are configured in ASE, then ABS generates decoy API reports with detailed information on all client access to decoy APIs including ASE detected violations. Here is a decoy API URL:

<ABS\_IP>:port/v4/abs/decoy?earlier\_date<>& later\_date<>

```

{
"company": "ping identity",
"name": "decoy_api_metrics",
"description": "This report contains detailed information on client access
to each decoy API
",
"later_date": "Tue Jan 11 18:00:00:000 2018",
"earlier_date": "Tue Jan 11 17:50:00:000 2018",
"api_name": "atmapp",
"api_type": "decoy-incontext",
"decoy_url": [
"/atmapp/decoy"
],
"summary": [
{
"decoy_url": "/atmapp/decoy",
"unique_ip_count": 122,
"total_requests": 240,
"most_used_methods": {
"GET": 88,
"DELETE": 32,
"ABDU": 32,
"POST": 30,
"PUT": 26
},
"most_used_ips": {
"100.64.9.37": 4,

```

```

"100.64.10.79": 4,
},
"most_used_devices": {
"UBUNTU": 76,
"MAC_OS_X": 69,
},
"most_used_content_types": {
"UNKNOWN": 184,
"multipart/form-data": 56
}
},
"details": [
{
"decoy_url": "/atmapp/decoy",
"source_ip": [
{
"ip": "100.64.31.183",
"total_requests": 2,
"method_count": {
"GET": {
"count": 2
}
}
},
"url_count": {
"/atmapp/decoy": 2
}
}
]

```

See [ABS external REST APIs](#) for a full report.

## Blocked connection reporting

---

ABS Blocked Connection REST API reports all connections that are blocked by ASE. Two types of reports are provided:

- Blocked Connection Summary Report
- Blocked Connection Detail Report

The blocked connections are reported for the following categories:

- API routing
- DDoS flow control
- ABS detected attacks
- Custom blacklist
- Decoy attacks
- ASE detected attacks

Use the following ABS REST API for viewing the blocked connections report:

### Blocked connection summary

URL: `<ABS_IP>:port/v4/abs/bc?earlier_date=<>T<hh:mm>&later_date=<>T<hh:mm>`

Following is a snippet of blocked connection summary report:

```

{
"company": "ping identity",
"name": "api_blockedconnections",
"description": " This report contains a summary of all API traffic blocked
by ASE for the following types: api_not_found, host_header_not_found,
backend_not_found, client_spike, server_spike, bytes_in_threshold,
bytes_out_threshold, quota_threshold, customer blacklist,
abs_detected_attacks, ase_detected_attacks, decoy_detected_attacks",

```

```

"earlier_date": "Thu Jan 18 13:00:00:000 2018",
"later_date": "Thu Feb 22 18:00:00:000 2018",
"api_name": "global",
"total_blocked_connections": 21222,
"api_not_found": 0,
"host_header_not_found": 0,
"backend_not_found": 3501,
"client_spike": 237,
"server_spike": 6179,
"bytes_in_threshold": 5938,
"bytes_out_threshold": 18,
"quota_threshold": 0,
"customer_blacklist": 0,
"abs_detected_attacks": 4576,
"ase_detected_attacks": 773,
"decoy_detected_attacks": 0

```

### Blocked Connection Details

URL: <ABS\_IP>:port/v4/abs/bc?later\_date=<>T<hh:mm>&earlier\_date=<>T<hh:mm>&details=true

Following is a snippet of Blocked Connection details report:

```

{
  "company": "ping identity",
  "name": "api_blockedconnections",
  "description": "This report contains details of all API traffic blocked by ASE for the following types: api_not_found, host_header_not_found, backend_not_found, client_spike, server_spike, bytes_in_threshold, bytes_out_threshold, quota_threshold, customer_blacklist, abs_detected_attacks, ase_detected_attacks, decoy_detected_attacks,
  "earlier_date": "Thu Jan 18 13:00:00:000 2018",
  "later_date": "Thu Feb 22 18:00:00:000 2018",
  "api_blocked_connections": [
    {
      "category": "api_routing",
      "details": [
        {
          "source": "192.168.11.161",
          "type": "backend_not_found",
          "destination_api": "/v2/pet/55"
        },
        {
          "source": "192.168.11.161",
          "type": "backend_not_found",
          "destination_api": "/v2/store/inventory"
        }
      ]
    },
    {
      "category": "ddos_flowcontrol",
      "details": [
        {
          "source": "100.64.1.24",
          "type": "bytes_in_threshold",
          "destination_api": "/app/ws"
        },
        {
          "source": "100.64.3.213",
          "type": "protocol_violation",
          "destination_api": ""
        }
      ]
    }
  ]
}

```





## Forensics on OAuth2 token

The OAuth2 token forensics report shows all activity associated with the specified token over a time period. Report information includes a detailed activity trail of accessed URLs, methods, and attacks.

```
{
  "company": "ping identity",
  "name": "api_abs_token",
  "description": "This report contains a summary and detailed information on metrics, attacks and anomalies for the specified token across all APIs.",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "summary": {
    "total_requests": 6556,
    "total_attacks": 2,
    "total_anomalies": 0
  },
  "details": {
    "metrics": {
      "token": "token1",
      "total_requests": 6556,
      "ip_list": [
        {
          "ip": "127.0.0.1",
          "total_requests": 6556,
          "devices": {
            "UNKNOWN": 6556
          }
        }
      ],
      "methods": {
        "DELETE": 472,
        "POST": 140,
        "GET": 1944,
        "PUT": 4000
      },
      "urls": {
        "/atm_app_oauth/delete200": 218,
        "/atm_app_oauth/get200": 850,
        "/atm_app_oauth/post400": 8,
        "/atm_app_oauth/post200": 62,
        "/atm_app_oauth/put400": 62,
        "/atm_app_oauth/get400": 122,
        "/atm_app_oauth/put200": 1938,
        "/atm_app_oauth/delete400": 18,
        "/2_atm_app_oauth/put200": 1938,
        "/2_atm_app_oauth/post200": 62,
        "/2_atm_app_oauth/delete200": 218,
        "/2_atm_app_oauth/delete400": 18,
        "/2_atm_app_oauth/put400": 62,
        "/2_atm_app_oauth/post400": 8,
        "/2_atm_app_oauth/get400": 122,
        "/2_atm_app_oauth/get200": 850
      },
      "apis": {
        "atm_app_oauth": 3278,
        "2_atm_app_oauth": 3278
      }
    }
  },
  "attack_types": {
    "API Memory Attack Type 1": [
      "atm_app_oauth",

```

```

"2_atm_app_oauth"
],
>Data Poisoning Attack": [
"atm_app_oauth",
"2_atm_app_oauth"
]
},
"anomaly_types": {}
}
}

```

### Forensics on an IP address

The IP Forensics report shows all activity associated with the specified IP address over a time period. Report information includes a detailed activity trail of accessed URLs, methods, and attacks.

```

{
"company": "ping identity",
"name": "api_abs_ip",
"description": "This report contains a summary and detailed information on
metrics, attacks and anomalies for the specified ip across all APIs.",
"earlier_date": "Tue Feb 13 18:00:00:000 2018",
"later_date": "Sun Feb 18 18:00:00:000 2018",
"summary": {
"total_requests": 8192,
"total_attacks": 2,
"total_anomalies": 1
},
"details": {
"metrics": {
"no_session": [
{
"start_time": "Thu Feb 15 14:04:17:959 2018",
"end_time": "Thu Feb 15 14:05:59:263 2018",
"total_requests": 4096,
"source_ip": "4.1.1.1",
"path": "/atm_app_private/get200",
"methods": [
"GET"
]
}
],
{
"start_time": "Thu Feb 15 14:14:00:724 2018",
"end_time": "Thu Feb 15 14:14:47:999 2018",
"total_requests": 4096,
"source_ip": "4.1.1.1",
"path": "/2_atm_app_private/get200",
"methods": [
"GET"
]
}
],
"session": []
},
"attack_types": {
>Data Exfiltration Attack": [
"2_atm_app_private",
"atm_app_private"
],
"Extreme App Activity Attack": [
"2_atm_app_private",
"atm_app_private"
]
}
}

```



```

"device": [
  {
    "device": "UNKNOWN",
    "count": 1
  }
],
"server": [
  {
    "server": "127.0.0.1:3000",
    "count": 1
  }
]
},
"anomalies": []
}
}

```

### Forensics on API Key

The API Key Forensics reports includes all activity associated with the specified API Key over a time period. Report information includes a detailed activity trail of accessed URLs, methods, and attacks.

```

{
  "company": "ping identity",
  "name": "api_abs_api_key",
  "description": "This report contains a summary and detailed information on metrics, attacks and anomalies for the specified api key across all APIs.",
  "earlier_date": "Sat Jan 12 13:30:00:000 2019",
  "later_date": "Tue Dec 31 18:00:00:000 2019",
  "summary": {
    "total_requests": 2621,
    "total_attacks": 1,
    "total_anomalies": 1
  },
  "details": {
    "metrics": {
      "api_key": "finite_api_key",
      "total_requests": 2621,
      "ip_list": [
        {
          "ip": "192.168.2.2",
          "total_requests": 457,
          "devices": {
            "UNKNOWN": 457
          },
          "methods": {
            "GET": 457
          },
          "urls": {
            "/atm_app/getzipcode": 457
          },
          "apis": {
            "atm_app": 457
          }
        }
      ],
    },
    "attack_types": {
      "Stolen API Key Attack- Per API Key": [
        "all"
      ]
    }
  },
}

```

```

    "anomaly_types": {
      "Stolen API Key Attack- Per API Key": [
        "all"
      ]
    }
  }
}

```

## Username Forensics

The username Forensics reports includes all activity associated with the specified username over a time period. Report information includes a detailed activity trail of accessed URLs, methods, and attacks.

```

{
  "company": "ping identity",
  "name": "api_abs_username",
  "description": "This report contains a summary and detailed information on metrics, attacks and anomalies for the specified user name across all APIs.",
  "earlier_date": "Sat Jan 12 13:30:00:000 2019",
  "later_date": "Tue Dec 31 18:00:00:000 2019",
  "summary": {
    "total_requests": 109965,
    "total_attacks": 0,
    "total_anomalies": 0
  },
  "details": {
    "metrics": {
      "username": "t4",
      "tokens": [
        "t4MFBkEe",
        "t4GpEkUS",
        "t4ZxUOjb",
        "t4QEvJKT"
      ],
      "total_requests": 109965,
      "ip_list": [
        {
          "ip": "127.0.0.28",
          "total_requests": 54983,
          "devices": {
            "Mozilla/5.0 (X11; Linux x86_64) AppleWebKit/537.36 (KHTML, like Gecko) Chrome/57.0.2987.110 Safari/537.36": 54983
          },
          "methods": {
            "POST": 54983
          },
          "urls": {
            "/atm_app_oauth": 54983
          },
          "apis": {
            "atm_app_oauth": 54983
          }
        }
      ]
    },
    "attack_types": {},
    "anomaly_types": {}
  }
}

```

## API metrics reporting

The API Metrics report provides information on client request/response activity to the requested API. It includes a summary report and detailed reporting including API access by method.

**i Note:** If ASE is deployed in sideband mode, then server field in the output shows the IP address as 0.0.0.0. For ASE deployed in inline mode, the server field shows the IP address of the backend API server. For more information on ASE sideband mode, see the ASE Admin Guide.

```
{
  "company": "ping identity",
  "name": "api_metrics",
  "description": "This report contains metrics for request/response traffic
for the specified API",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "api_name": "atm_app_public",
  "req_resp_summary": {
    "api_url": "/atm_app_public",
    "total_requests": 2508,
    "success": 2246,
    "sessions": 2,
    "no_sessions": 1,
    "most_popular_method": "POST",
    "most_popular_device": "UNKNOWN",
    "most_popular_ips": [
      "127.0.0.1",
      "3.1.1.4"
    ],
    "servers": [
      {
        "server": "127.0.0.1:3000",
        "count": 2507
      }
    ],
  },
  "req_resp_details": {
    "api_url": "/atm_app_public",
    "session_details": [
      {
        "session_id": "session_protocol",
        "total_requests": 1,
        "source_ip": [
          {
            "ip": "127.0.0.1",
            "count": 1,
            "method": [
              "GET"
            ]
          }
        ],
      }
    ],
    "user_agent": [
      {
        "user_agent": "DOWNLOAD",
        "count": 1
      }
    ],
    "path_info": [
      {
        "path": "/atm_app_public/get400",

```

```

"count": 1
}
],
"device": [
{
"device": "UNKNOWN",
"count": 1
}
],
"server": []
},
{
"session_id": "session11",
"total_requests": 2506,
"source_ip": [
{
"ip": "127.0.0.1",
"count": 2506,
"method": [
"DELETE",
"POST",
"PUT",
"GET"
]
}
],
"user_agent": [
{
"user_agent": "DOWNLOAD",
"count": 2506
}
],
"path_info": [
{
"path": "/atm_app_public/post400",
"count": 218
},
{
"path": "/atm_app_public/put400",
"count": 18
},
{
"path": "/atm_app_public/delete200",
"count": 208
},
{
"path": "/atm_app_public/get400",
"count": 14
},
{
"path": "/atm_app_public/put200",
"count": 152
},
{
"path": "/atm_app_public/delete400",
"count": 10
},
{
"path": "/atm_app_public/get200",
"count": 104
},
{
"path": "/atm_app_public/post200",
"count": 1782
}
]
}
]
}

```





```

    "name": "username metrics",
    "description": "This report contains a summary and detailed username
metrics across all APIs",
    "earlier_date": "Tue Oct 08 06:00:00:000 2019",
    "later_date": "Tue Oct 08 06:10:00:000 2019",
    "summary": {
      "usernames": 36697,
      "total_requests": 398776
    },
    "details": [
      {
        "username": "93YgxYHg7B2a9967aZCVRHfc9GEdBBS79tXNWEym",
        "token_list": [
          {
            "token":
"eyJ0eXAiOiJKV1QiLCJhbGciOiJIUzI1NiIsImtpZCI6IjAwMDEiLCJpc3MiOiJC",
            "total_requests": 4
          },
          {
            "token": "iZ4Eev2Tutah2pou8uev4kohyiesexai0rool5les8Eilae4aejair",
            "total_requests": 2
          }
        ]
      }
    ]
    "total_requests": 6,
    "ip_list": [
      {
        "ip": "2.63.6.57",
        "total_requests": 6,
        "devices": {
          "UNKNOWN": 6
        },
        "methods": {
          "GET": 6
        },
        "urls": {
          "/accounts/statement": 6
        },
        "apis": {
          "appl6": 6
        }
      }
    ]
  }
}

```

## API Key based metrics

ABS provides API key metrics including the total number of API keys and requests across all API keys. The report also lists the IP address, requesting device information, methods used, URLs accessed, and API affected. API key based metrics reporting spans all APIs.

```

{
  "company": "ping identity",
  "name": "api_key_metrics",
  "description": "This report contains a summary and detailed api key
metrics across all APIs",
  "earlier_date": "Mon May 27 13:00:00:000 2019",
  "later_date": "Sun Jun 30 18:00:00:000 2019",
  "summary": {
    "api_keys": 2,
    "total_requests": 3828
  }
}

```

```

},
"details": [
  {
    "api_key": "game_api_key",
    "total_requests": 6,
    "ip_list": [
      {
        "ip": "192.168.2.148",
        "total_requests": 2,
        "devices": {
          "UNKNOWN": 2
        },
        "methods": {
          "GET": 2
        },
        "urls": {
          "/atm_app/getzipcode": 2
        },
        "apis": {
          "atm_app": 2
        }
      },
      {
        "ip": "192.168.2.149",
        "total_requests": 2,
        "devices": {
          "UNKNOWN": 2
        },
        "methods": {
          "GET": 2
        },
        "urls": {
          "/atm_app/getzipcode": 2
        },
        "apis": {
          "atm_app": 2
        }
      },
      {
        "ip": "192.168.2.146",
        "total_requests": 2,
        "devices": {
          "UNKNOWN": 2
        },
        "methods": {
          "GET": 2
        },
        "urls": {
          "/atm_app/getzipcode": 2
        },
        "apis": {
          "atm_app": 2
        }
      }
    ]
  },
  {
    "api_key": "uber_api_key",
    "total_requests": 3822,
    "ip_list": [
      {
        "ip": "192.168.2.2",
        "total_requests": 457,
        "devices": {

```

```

        "UNKNOWN": 457
    },
    "methods": {
        "GET": 457
    },
    "urls": {
        "/atm_app/getzipcode": 457
    },
    "apis": {
        "atm_app": 457
    }
},
{
    "ip": "192.168.2.1",
    "total_requests": 561,
    "devices": {
        "UNKNOWN": 561
    },
    "methods": {
        "GET": 561
    },
    "urls": {
        "/atm_app/getzipcode": 561
    },
    "apis": {
        "atm_app": 561
    }
},
{
    "ip": "192.168.2.3",
    "total_requests": 404,
    "devices": {
        "UNKNOWN": 404
    },
    "methods": {
        "GET": 404
    },
    "urls": {
        "/atm_app/getzipcode": 404
    },
    "apis": {
        "atm_app": 404
    }
},
{
    "ip": "192.168.2.5",
    "total_requests": 2400,
    "devices": {
        "UNKNOWN": 2400
    },
    "methods": {
        "GET": 2400
    },
    "urls": {
        "/atm_app/getzipcode": 2400
    },
    "apis": {
        "atm_app": 2400
    }
}
}
]

```

```
}

```

## OAuth token based metrics

The OAuth2 token metrics report provides a summary with the total number of tokens and requests. For each token, detailed information on all activity is provided for the time period.

```
{
  "company": "ping identity",
  "name": "oauth_token_metrics",
  "description": "This report contains a summary and detailed oauth token
  metrics across all APIs",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "summary": {
    "tokens": 30,
    "total_requests": 163250
  },
  "details": [
    {
      "token": "token_highresptime",
      "total_requests": 2,
      "ip_list": [
        {
          "ip": "127.0.0.1",
          "total_requests": 2,
          "devices": {
            "UNKNOWN": 2
          },
          "methods": {
            "GET": 2
          },
          "urls": {
            "/2_atm_app_oauth/longresponse": 1,
            "/atm_app_oauth/longresponse": 1
          },
          "apis": {
            "atm_app_oauth": 1,
            "2_atm_app_oauth": 1
          }
        }
      ],
      "token": "token13",
      "total_requests": 7452,
      "ip_list": [
        {
          "ip": "127.0.0.1",
          "total_requests": 7452,
          "devices": {
            "UNKNOWN": 7452
          },
          "methods": {
            "DELETE": 564,
            "POST": 352,
            "GET": 4000,
            "PUT": 2536
          },
          "urls": {
            "/2_atm_app_oauth/put200": 1248,
            "/atm_app_oauth/delete200": 246,
            "/2_atm_app_oauth/put400": 20,

```

```

"/2_atm_app_oauth/get400": 118,
"/2_atm_app_oauth/get200": 1882,
"/2_atm_app_oauth/post200": 162,
"/2_atm_app_oauth/delete200": 246,
"/2_atm_app_oauth/delete400": 36,
"/atm_app_oauth/get200": 1882,
"/atm_app_oauth/post400": 14,
"/2_atm_app_oauth/post400": 14,
"/atm_app_oauth/post200": 162,
"/atm_app_oauth/put400": 20,
"/atm_app_oauth/get400": 118,
"/atm_app_oauth/put200": 1248,
"/atm_app_oauth/delete400": 36
},
"apis": {
  "atm_app_oauth": 3726,
  "2_atm_app_oauth": 3726
}
]
},
{
  "token": "token_probing",
  "total_requests": 64,
  "ip_list": [
    {
      "ip": "127.0.0.1",
      "total_requests": 64,
      "devices": {
        "UNKNOWN": 64
      },
      "methods": {
        "GET": 64
      },
      "urls": {
        "/2_atm_app_oauth/get400": 32,
        "/atm_app_oauth/get400": 32
      },
      "apis": {
        "atm_app_oauth": 32,
        "2_atm_app_oauth": 32
      }
    }
  ],
  {
    "token": "token_type1memory",
    "total_requests": 2,
    "ip_list": [
      {
        "ip": "127.0.0.1",
        "total_requests": 2,
        "devices": {
          "UNKNOWN": 2
        },
        "methods": {
          "PUT": 2
        },
        "urls": {
          "/2_atm_app_oauth/put200": 1,
          "/atm_app_oauth/put200": 1
        },
        "apis": {
          "atm_app_oauth": 1,

```



## List valid URL

---

The List Valid URLs report includes all URLs, access count, and allowed methods for a specified API. The report provides insight into the activity on each API URL.

```
{
  "company": "ping identity",
  "name": "api_url_list",
  "description": "This report contains list of valid URL for the specified API",
  "api_name": "shop",
  "host_name": "app",
  "api_url": "shopapi",
  "allowed_methods": [
    "GET",
    "PUT",
    "POST",
    "DELETE",
    "HEAD"
  ],
  "url_list": [
    {
      "protocol": "HTTP/1.1",
      "urls": [
        {
          "url": "/shopapi/post",
          "total_count": 2009,
          "methods": [
            {
              "method": "POST",
              "count": 2009
            }
          ]
        },
        {
          "url": "/shopapi/login",
          "total_count": 2956,
          "methods": [
            {
              "method": "POST",
              "count": 2956
            }
          ]
        },
        {
          "url": "/shopapi/login?username=v1&password=v2",
          "total_count": 87,
          "methods": [
            {
              "method": "POST",
              "count": 87
            }
          ]
        },
        {
          "url": "/shopapi/put",
          "total_count": 2159,
          "methods": [
            {
              "method": "PUT",
              "count": 2159
            }
          ]
        }
      ]
    }
  ]
}
```



}

## Hacker's URL

---

The List Invalid URLs or hacker's URL report provide information on the four types of invalid URLs: irregular URLs, system commands, buffer overflow, and SQL injection.

```
{
  "company": "ping identity",
  "name": "api_abs_cookie",
  "description": "This report contains a summary and detailed information on metrics, attacks and anomalies for the specified cookie across all APIs.",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "summary": {
    "total_requests": 32768,
    "total_attacks": 3,
    "total_anomalies": 1
  },
  "details": {
    "metrics": [
      {
        "session_id": "session_extremeactivity",
        "start_time": "Thu Feb 15 14:04:46:001 2018",
        "end_time": "Thu Feb 15 14:05:02:994 2018",
        "total_requests": 16384,
        "source_ip": [
          {
            "ip": "127.0.0.1",
            "count": 16384,
            "method": [
              "GET"
            ]
          }
        ],
        "user_agent": [
          {
            "user_agent": "DOWNLOAD",
            "count": 16384
          }
        ],
        "path_info": [
          {
            "path": "/atm_app_public/get200",
            "count": 16384
          }
        ],
        "device": [
          {
            "device": "UNKNOWN",
            "count": 16384
          }
        ],
        "server": [
          {
            "server": "127.0.0.1:3000",
            "count": 16384
          }
        ]
      }
    ]
  },
}
```

```

{
  "session_id": "session_extremeactivity",
  "start_time": "Thu Feb 15 14:13:45:795 2018",
  "end_time": "Thu Feb 15 14:14:35:268 2018",
  "total_requests": 16384,
  "source_ip": [
    {
      "ip": "127.0.0.1",
      "count": 16384,
      "method": [
        "GET"
      ]
    }
  ],
  "user_agent": [
    {
      "user_agent": "DOWNLOAD",
      "count": 16384
    }
  ],
  "path_info": [
    {
      "path": "/2_atm_app_public/get200",
      "count": 16384
    }
  ],
  "device": [
    {
      "device": "UNKNOWN",
      "count": 16384
    }
  ],
  "server": [
    {
      "server": "127.0.0.1:3000",
      "count": 16384
    }
  ],
  "attack_types": {
    "Data Exfiltration Attack": [
      "2_atm_app_public",
      "atm_app_public"
    ],
    "Extreme Client Activity Attack": [
      "2_atm_app_public",
      "atm_app_public"
    ],
    "Extreme App Activity Attack": [
      "2_atm_app_public",
      "atm_app_public"
    ]
  },
  "anomaly_types": {
    "Stolen Cookie Anomaly": [
      "2_atm_app_public",
      "atm_app_public"
    ]
  }
}

```

## Backend error reporting

---

The Backend Error Response Codes report provides information for each error code including client IP, server IP, and requested URL. ABS reports on a per API basis for the following error codes:

- 403: Forbidden
- 404: Not Found
- 500: Internal Server Error
- 503: Service Unavailable
- 504: Gateway Timeout

```
{
  "company": "ping identity",
  "name": "api_backend_errors",
  "description": "This report contains details of backend error codes for
  the specified API",
  "later_date": "Sun Feb 05 13:20:00:000 2017",
  "earlier_date": "Wed Feb 01 08:20:00:000 2017",
  "api_name": "atmapp",
  "backend_error_summary": [
    {
      "error_code": "403",
      "error": "Forbidden",
      "count": 0
    },
    {
      "error_code": "404",
      "error": "Not Found",
      "count": 0
    },
    truncated
  ],
  "backend_error_details": [
    {
      "error_code": "500",
      "details": [
        {
          "server": "192.168.11.164:3001",
          "request_url": "/atmapp/zipcode",
          "request_ip": "100.64.5.183:24078",
          "request_cookie": ""
        },
        {
          "server": "192.168.11.164:3003",
          "request_url": "/atmapp/zipcode",
          "request_ip": "100.64.19.136:61494",
          "request_cookie": "JSESSIONID=5GMNKOGNGP6FCKF9"
        }
      ]
    }
  ],
}
```

## API DoS and DDoS threshold

---

### API DoS and DDoS threshold 11

API Flow Control reports on API Security Enforcer configured flow control thresholds that are exceeded. The reporting is done on the following parameters:

- Client Spike – inbound client traffic rate
- Server Spike – aggregate traffic to an API service
- Connection Queued – connection requests queued due to server at concurrent connection limit

- Bytes-in Spike – WebSocket aggregate inbound traffic exceeds limit
- Bytes-out Spike - WebSocket aggregate outbound traffic exceeds limit

**Note:** API DoS and DDoS threshold and reporting is only available when ASE is deployed in inline mode.

For a specified API, the flow control API provides a summary of thresholds exceeded and detailed reporting on each flow control threshold exceeded:

```
{
  "company": "ping identity",
  "name": "api_flowcontrol",
  "description": "This report contains flow control information for the
specified API",
  "earlier_date": "Thu Jan 25 18:00:00:000 2018",
  "later_date": "Fri Dec 28 18:00:00:000 2018",
  "api_name": "atm_app_private",
  "server_spike_ip_count": 0,
  "summary": {
    "client_spike": 990,
    "server_spike": 0,
    "connection_queued": 0,
    "connection_quota_exceeded": 0
  },
  "details": {
    "client_spike": [
      {
        "request_time": "Mon Jan 29 13:43:20:227 2018",
        "connection_id": "2081496566",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
      {
        "request_time": "Mon Jan 29 13:43:20:228 2018",
        "connection_id": "1902346354",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
      {
        "request_time": "Mon Jan 29 13:43:20:228 2018",
        "connection_id": "1999376747",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
      {
        "request_time": "Mon Jan 29 13:43:20:228 2018",
        "connection_id": "2009947644",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
      {
        "request_time": "Mon Jan 29 13:43:20:228 2018",
        "connection_id": "934081844",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
      {
        "request_time": "Mon Jan 29 13:43:20:227 2018",
        "connection_id": "2081496566",
        "source_ip": "3.1.1.2",
        "destination_api": "/atm_app_private/get400"
      },
    ]
  }
}
```

```

{
  "request_time": "Mon Jan 29 13:43:20:228 2018",
  "connection_id": "1902346354",
  "source_ip": "3.1.1.2",
  "destination_api": "/atm_app_private/get400"
},
{
  "request_time": "Mon Jan 29 13:43:20:228 2018",
  "connection_id": "1999376747",
  "source_ip": "3.1.1.2",
  "destination_api": "/atm_app_private/get400"
},
{
  "request_time": "Mon Jan 29 13:43:20:228 2018",
  "connection_id": "2009947644",
  "source_ip": "3.1.1.2",
  "destination_api": "/atm_app_private/get400"
},
{
  "request_time": "Mon Jan 29 13:43:20:228 2018",
  "connection_id": "934081844",
  "source_ip": "3.1.1.2",
  "destination_api": "/atm_app_private/get400"
}
],
"server_spike": [],
"connections_queued": [],
"connection_quota_exceeded": []
}
}

```

## API reports using Postman

---

Multiple options are available for accessing the ABS REST API reporting including:

- Postman App
- Java, Python, C Sharp, or similar languages.
- Java client program (such as Jersey)
- C sharp client program (such as RestSharp)

For the Postman application, Ping Identity provides configuration files which are used by Postman to access the ABS REST API JSON information reports. Make sure to install Postman 6.2.5 or higher.


### Using an ABS self-signed certificate with Postman

ABS ships with a self-signed certificate. To use Postman with the ABS self-signed certificate, disable certificate verification in Postman.


About this task

To disable certificate verification:


Steps

1. Click the **Wrench**  icon on the top-right corner of the Postman client.

- In the menu, select **Settings**.




- In the **Settings** window, click the **SSL certificate verification** toggle to disable SSL certificate verification.




## View ABS reports in Postman


To view the reports, complete the following steps:

- Download `ABS_5.0_Environment` and `ABS_5.0_Reports` JSON files from **API Reports Using Postman** folder on Ping Identity [Download](#) site. These configuration files will be used by Postman.
- [Download](#) and install the Postman application 6.2.5 or higher.
- In Postman, **import** the two Ping Identity files downloaded in step 1 by clicking the Import button.



- After importing the files, click the gear  button in the upper right corner.
- In the **MANAGE ENVIRONMENTS** pop-up window, click **ABS\_5.0\_Environment**

6. In the pop-up window, configure the following values and then click **Update**
- **Server:** IP address of the ABS node for which the `dashboard_node` was set to `true` in the `abs.properties` file.
  - **Port:** Port number of the ABS node.
  - **Access\_Key\_Header** and **Secret\_Key\_Header:** Use the Admin user or Restricted user header. A Restricted user sees obfuscated value of OAuth token, cookie and API keys. For more information of different types of user, see [ABS users for API reports](#)
  - **Access\_Key** and **Secret\_Key:** The Access Key and Secret Key configured in the `opt/pingidentity/mongo/abs_init.js` for either admin or restricted user. Make sure that access key and secret key corresponds to the admin or restricted user header configured.
  - **API\_Name:** The name of the API for which you want to generate the reports.
  - **Later\_Date:** A date which is more recent in time. For example, if the query range is between March 12 and March 14, then the later date would be March 14.
  - **Earlier\_Date:** A date which is past in time. For example, if the query range is between March 12 and March 14, then the earlier date would be March 12.

 **Note:** Do not edit any fields that start with the word `System`.

7. In the main Postman window, select the report to display on the left column and then click **Send**. [ABS external REST APIs](#) section provides detailed information on each API call and the JSON report response.

## ABS CLI

---

ABS CLI provides the commands listed in the following table.

### Basic commands

- [Start ABS](#)
- [Stop ABS](#)
- [Help](#)
- [Update password](#)
- [Update keys](#)

### Obfuscation commands

- [Generate obfuscation key](#)
- [Obfuscate password](#)

### Start ABS

#### Description

Starts ABS. Run the command from `/opt/pingidentity/abs/bin` directory

#### Syntax

```
./start.sh
```

### Stop ABS

#### Description

Stops ABS. Run the command from `/opt/pingidentity/abs/bin` directory

```
./stop.sh
```

### Help

#### Description

Displays `cli.sh help`

**Syntax**

```
./cli.sh help
```

**Update Password****Description**

Change ABS admin password

**Syntax**

```
./cli.sh update_password {-u admin}
```

**Update keys****Description**

Update access and secret keys

**Syntax**

```
./cli.sh -u admin -p admin update_keys -ak <access key> -sk <secret key>
```

**Note:** It is recommended to always use `update_keys` CLI command to change the keys. However, you can directly edit the `abs_init.js` file when changing the default access and secret keys for the first time after installing ABS AI engine.

**Generate Master Key****Description**

Generate the master obfuscation key `abs_master.key`

**Syntax**

```
./cli.sh -u admin -p admin generate_obfkey
```

**Obfuscate Password****Description**

Obfuscate the passwords configured in various configuration files

**Syntax**

```
./cli.sh -u admin -p admin obfuscate_keys
```

## ABS REST API format

---

ABS provides external REST APIs which are used to access JSON reports providing deep insight into the following:


- Attack Forensics and Compliance Reporting – attacks and anomalous behavior on APIs
- API Metrics – API client and traffic details
- Administrative – ABS system information
- API Security Enforcer – decoy API, blocked connections, flow control, and backend error reporting

A REST client can securely query each ABS API and receive data back in JSON format. REST client program options include using:

- Postman App for Google Chrome browser
- Java, Python, C Sharp, or similar languages.
- Java client program (for example, Jersey)
- C sharp client program (for example, RestSharp)

The diagram shows the process for a REST API client to connect to an ABS API.





### ABS API query format

ABS API offers a common format with a consistent syntax for request parameters. Detailed information and format of all ABS REST APIs are included in [ABS external REST APIs](#).

#### Query parameters for most APIs include:

Field	Description
api_name	The API name to query for results.
earlier_date	The time to check for results going back in time. For example, to check results from 10th April, 6 PM to 14th April, 3 PM, the <code>earlier_date</code> would be 10th April, 6 PM.
later_date	The time to check the results back in time. For example, to check results from 10th April, 6 PM to 14th April, 3 PM, the <code>later_date</code> would be 14th April, 6 PM.

The following `access_key` and `secret_key` are the keys that were defined in the `abs_init.js` file. Note that ":" (colon) is a restricted character and cannot be used in access and secret key.

- `x-abs-ak` and `x-abs-ak-ru`: `access_key`
- `x-abs-sk` and `x-abs-sk-ru`: `secret_key`

**Note:** The start and end time are based on the log file data, that is, the local time where data was captured and not of the location where results are analyzed.

## ABS external REST APIs

### ABS external REST APIs

Following is a list of Ping Identity ABS APIs. The sample outputs produced are for the Admin user. You can generate the output for the restricted user as well where the cookie, token, and API keys are obfuscated. For more information on different type of users for the ABS External REST APIs, see [ABS Users for API Reports and Dashboard](#).

**Note:** Note that ":" (colon) is a restricted character and cannot be used in access and secret key headers in ABS external REST APIs

- [Admin REST API](#)
- [TTL Update REST API](#)
- [Global Config Update REST API](#)
- [Discovery REST API](#)
- [Threshold REST API](#) on page 425

- [Reset Trained API](#)
- [Decoy API](#)
- [IP Metrics REST API](#)
- [API Key Metrics REST API](#)
- [Token Metrics REST API](#)
- [Username Metrics REST API](#)
- [Anomalies REST API](#)
- [Token Forensics REST API](#)
- [IP Forensics REST API](#)
- [Cookie Forensics REST API](#)
- [API Key Forensics API REST](#)
- [Username Forensics REST API](#)
- [Attack Type REST API](#)
- [Flow Control REST API](#)
- [Blocked Connection REST API](#)
- [Backend Error REST API](#)
- [List Valid URLs REST API](#)
- [List Hacker's URLs REST API](#)

## Admin REST API

**Description:** Admin API is used to fetch the list of nodes in the ABS cluster, Mongo DB Nodes, the status of each node (CPU, memory, file System etc) and logs processed that are sent by all API Security Enforcer nodes.

**Method:** GET

**URL:** `/v5/abs/admin`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample curl command

```
curl --location --request GET 'https://<IP Address>:8080/v5/abs/admin' \
--header 'x-abs-ak: abs_ak' \
--header 'x-abs-sk: abs_sk'
```

### Sample Response

```
{
  "company": "ping identity",
  "name": "api_admin",
  "description": "This report contains status information on all APIs, ABS
clusters, and ASE logs",
  "license_info": {
    "tier": "Subscription",
    "expiry": "Mon Jan 01 00:00:00 UTC 2024",
    "max_transactions_per_month": 10000000000,
    "current_month_transactions": 0,
    "max_transactions_exceeded": false,
    "expired": false
  },
  "across_api_prediction_mode": false,
  "poc": true,
```

```

"api_discovery": {
  "status": false
},
"apis": [
  {
    "api_name": "rest_api_decoy_outcontext",
    "host_name": "*",
    "url": "/decoy",
    "api_type": "decoy-outcontext",
    "creation_date": "Mon May 31 03:41:10 UTC 2021",
    "servers": 0,
    "protocol": "http",
    "cookie": "",
    "token": false,
    "training_started_at": "n/a",
    "training_duration": "n/a",
    "prediction_mode": false,
    "apikey_header": "",
    "apikey_qs": "",
    "jwt": {
      "location": "",
      "username": "",
      "clientid": ""
    },
    "username_header": ""
  },
  {
    "api_name": "rest_api",
    "host_name": "*",
    "url": "/rest",
    "api_type": "regular",
    "creation_date": "Mon May 31 03:41:10 UTC 2021",
    "servers": 2,
    "protocol": "http",
    "cookie": "",
    "token": false,
    "training_started_at": "Mon May 31 03:42:46 UTC 2021",
    "training_duration": "20 hours",
    "prediction_mode": false,
    "apikey_header": "",
    "apikey_qs": "",
    "jwt": {
      "location": "",
      "username": "",
      "clientid": ""
    },
    "username_header": ""
  },
  {
    "api_name": "rest_api_decoy_incontext",
    "host_name": "*",
    "url": "/restdecoy",
    "api_type": "decoy-incontext",
    "creation_date": "Mon May 31 03:41:10 UTC 2021",
    "servers": 2,
    "protocol": "http",
    "cookie": "",
    "token": false,
    "training_started_at": "Mon May 31 03:42:46 UTC 2021",
    "training_duration": "20 hours",
    "prediction_mode": false,
    "apikey_header": "",
    "apikey_qs": "",
    "jwt": {

```

```

        "location": "",
        "username": "",
        "clientid": ""
    },
    "username_header": ""
},
{
    "api_name": "root_api",
    "host_name": "*",
    "url": "/",
    "api_type": "regular",
    "creation_date": "Mon May 31 03:41:10 UTC 2021",
    "servers": 1,
    "protocol": "http",
    "cookie": "JSESSIONID",
    "token": false,
    "training_started_at": "n/a",
    "training_duration": "n/a",
    "prediction_mode": false,
    "apikey_header": "X-API-KEY",
    "apikey_qs": "",
    "jwt": {
        "location": "h:authorization:bearer",
        "username": "username",
        "clientid": "client_id"
    },
    "username_header": ""
}
],
"abs_cluster": {
    "abs_nodes": [
        {
            "node_id": "937e8553-ccc6-419b-b24d-c4f9a5d46632",
            "os": "Red Hat Enterprise Linux Server - ",
            "cpu": "8",
            "memory": "15G",
            "filesystem": "6%",
            "timezone": "UTC",
            "bootup_date": "Fri May 21 04:57:08:502 UTC 2021"
        },
        {
            "node_id": "d224a4f9-3a17-423a-a7b3-571c8143cfff",
            "os": "Red Hat Enterprise Linux Server - VMware, Inc.",
            "cpu": "16",
            "memory": "62G",
            "filesystem": "2%",
            "timezone": "UTC",
            "bootup_date": "Mon May 31 03:39:14:818 UTC 2021"
        }
    ],
    "mongodb_nodes": [
        {
            "node_ip": "172.16.40.165:27017",
            "status": "primary"
        }
    ]
},
"ase_logs": [
    {
        "ase_node": "53de980b-df8e-467a-9328-04e33497d2cd",
        "last_connected": "Mon May 31 03:41:15 UTC 2021",
        "logs": {
            "start_time": "Mon May 31 03:41:15 UTC 2021",
            "end_time": "Mon May 31 03:41:15 UTC 2021",

```

```

        "gzip_size": "13.96MB"
      }
    }
  ],
  "percentage_diskusage_limit": "80%",
  "scale_config": {
    "scale_up": {
      "cpu_threshold": "70%",
      "cpu_monitor_interval": "30 minutes",
      "memory_threshold": "70%",
      "memory_monitor_interval": "30 minutes",
      "disk_threshold": "70%",
      "disk_monitor_interval": "30 minutes"
    },
    "scale_down": {
      "cpu_threshold": "10%",
      "cpu_monitor_interval": "30 minutes",
      "memory_threshold": "10%",
      "memory_monitor_interval": "30 minutes",
      "disk_threshold": "10%",
      "disk_monitor_interval": "30 minutes"
    }
  },
  "attack_ttl": {
    "ids": [
      {
        "id": "ip",
        "ttl": 0
      },
      {
        "id": "cookie",
        "ttl": 0
      },
      {
        "id": "access_token",
        "ttl": 0
      },
      {
        "id": "api_key",
        "ttl": 0
      },
      {
        "id": "username",
        "ttl": 0
      }
    ]
  }
}

```

## Discovery REST API

**Description:** The Discovery API discovers all the APIs that are available in your API ecosystem.

**Method:** GET

**URL:** </v4/abs/discovery>

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

**Sample Response**

```

{
  "company": "ping identity",
  "name": "api_discovery_summary",
  "description": "This report contains summary of discovered APIs",
  "summary": [
    {
      "api_name": "api_0",
      "host": "bothcookientoken.com",
      "basePath": "/path1",
      "created": "Fri Mar 06 09:29:51:591 2020",
      "updated": "Fri Mar 06 09:50:03:372 2020"
    },
    {
      "api_name": "api_1",
      "host": "path5",
      "basePath": "/path1/path2/path3",
      "created": "Fri Mar 06 10:59:38:975 2020",
      "updated": "Fri Mar 06 11:36:45:596 2020"
    },
    {
      "api_name": "api_10",
      "host": "pathx",
      "basePath": "/path1/path2/path3",
      "created": "Fri Mar 06 10:59:57:320 2020",
      "updated": "Fri Mar 06 13:19:24:680 2020"
    },
    {
      "api_name": "api_11",
      "host": "path8",
      "basePath": "/path1",
      "created": "Fri Mar 06 10:59:39:392 2020",
      "updated": "Fri Mar 06 13:19:23:951 2020"
    },
    {
      "api_name": "api_12",
      "host": "path3",
      "basePath": "/path1/path2/path3",
      "created": "Fri Mar 06 10:59:38:672 2020",
      "updated": "Fri Mar 06 13:19:23:152 2020"
    },
    {
      "api_name": "api_13",
      "host": "path4",
      "basePath": "/path1/path2/path3",
      "created": "Fri Mar 06 10:59:38:824 2020",
      "updated": "Fri Mar 06 11:36:45:452 2020"
    },
    {
      "api_name": "api_14",
      "host": "path5",
      "basePath": "/path1/path2/path3/path4/path5",
      "created": "Fri Mar 06 11:59:14:804 2020",
      "updated": "Fri Mar 06 12:18:24:732 2020"
    },
    {
      "api_name": "api_15",
      "host": "pathx",
      "basePath": "/path1/path2/path3/path4",
      "created": "Fri Mar 06 11:59:16:092 2020",
      "updated": "Fri Mar 06 13:19:25:283 2020"
    }
  ]
}

```

```

    {
      "api_name": "api_16",
      "host": "pathx",
      "basePath": "/path1/path2/path3/path4/path5",
      "created": "Fri Mar 06 11:59:16:244 2020",
      "updated": "Fri Mar 06 12:18:26:227 2020"
    },
    {
      "api_name": "api_17",
      "host": "path6",
      "basePath": "/path1/path2/path3/path4/path5/path6",
      "created": "Fri Mar 06 11:59:14:952 2020",
      "updated": "Fri Mar 06 12:18:24:876 2020"
    },
    {
      "api_name": "api_18",
      "host": "pathx",
      "basePath": "/path1/path2/path3/path4/path5/path6",
      "created": "Fri Mar 06 11:59:16:396 2020",
      "updated": "Fri Mar 06 12:18:26:532 2020"
    },
    {
      "api_name": "api_19",
      "host": "path7",
      "basePath": "/path1/path2/path3/path4/path5/path6",
      "created": "Fri Mar 06 11:59:15:096 2020",
      "updated": "Fri Mar 06 12:18:25:028 2020"
    },
    {
      "api_name": "api_9",
      "host": "path2",
      "basePath": "/path1/path2",
      "created": "Fri Mar 06 10:59:00:616 2020",
      "updated": "Fri Mar 06 13:19:23:003 2020"
    }
  ]
}

```

## Decoy REST API

**Description:** Decoy API provides information about the IP address that accessed the decoy URL along with the method used to access the decoy URL. It also reports about the type of device that was used to access the decoy URL.

**Method:** GET

**URL:** `/v4/abs/decoy?later_date<>&earlier_date<>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

## Sample Response

```

{
  "company": "ping identity",
  "name": "decoy_api_metrics",
  "description": "This report contains detailed information on client access to each decoy API",
  "earlier_date": "Tue Jan 11 17:50:00:000 2018",
}

```

```

"later_date": "Tue Jan 11 18:00:00:000 2018",
"api_name": "atmapp",
"api_type": "decoy-incontext",
"decoy_url": [
"/atmapp/decoy"
],
"summary": [
{
"decoy_url": "/atmapp/decoy",
"unique_ip_count": 122,
"total_requests": 240,
"most_used_methods": {
"GET": 88,
"DELETE": 32,
"ABDU": 32,
"POST": 30,
"PUT": 26
},
"most_used_ips": {
"100.64.9.37": 4,
"100.64.10.79": 4,
"100.64.31.183": 2,
"100.64.20.213": 2,
"100.64.34.239": 2
},
"most_used_devices": {
"UBUNTU": 76,
"MAC_OS_X": 69,
"WINDOWS_7": 61,
"WINDOWS_XP": 34
},
"most_used_content_types": {
"UNKNOWN": 184,
"multipart/form-data": 56
}
},
],
"details": [
{
"decoy_url": "/atmapp/decoy",
"source_ip": [
{
"ip": "100.64.31.183",
"total_requests": 2,
"method_count": {
"GET": {
"count": 2
}
}
},
],
"url_count": {
"/atmapp/decoy": 2
}
},
{
"ip": "100.64.14.28",
"total_requests": 2,
"method_count": {
"POST": {
"count": 2,
"payload_characteristics": {
"multipart/form-data": [
"354 bytes"
]
}
}
}
}
]
}

```





**Sample Response for an API**

```

{
  "company": "ping identity",
  "name": "api_threshold",
  "description": "This report contains threshold settings for all the
across API Attack IDs",
  "thresholds": [
    {
      "id": 1,
      "type": "data_exfiltration_attack",
      "user": {
        "A": {
          "tn": "18",
          "tx": "20"
        },
        "B": {
          "tn": "18",
          "tx": "20"
        }
      },
      "system": {
        "A": {
          "tn": "22",
          "tx": "24"
        },
        "B": {
          "tn": "4",
          "tx": "6"
        },
        "C": {
          "tn": "2",
          "tx": "4"
        }
      }
    },
    {
      "id": 2,
      "type": "single_client_login_attack",
      "system": {
        "A": {
          "tn": "5",
          "tx": "7"
        },
        "B": {
          "tn": "5",
          "tx": "7"
        }
      }
    }
  ],
}

```

**Sample Response for across API**

```

{
  "company": "ping identity",
  "name": "api_threshold",
  "description": "This report contains threshold settings for the
specified API",
  "api_name": "access_token",
  "threshold": [
    {
      "type": "extended_stolen_access_token",

```

```

    "system": {
      "A": {
        "tn": "2",
        "tx": "na"
      },
      "B": {
        "tn": "1",
        "tx": "na"
      },
      "C": {
        "tn": "1",
        "tx": "na"
      }
    }
  ]
}

```

### PUT Threshold

**Description:** The PUT method in Threshold API is used to set the threshold values for attack types. If you set the mode to `system`, the user set values are dropped. If you move the mode back to `user`, you would need to configure the threshold values again. For more information on manually setting threshold values, see [Manually set thresholds](#).

**Method:** PUT

**URL::** `/v4/abs/attack/threshold`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Input for an API

```

{
  "api_name" : "atmapp",
  "mode": "system",
  "ioc_threshold": [
    {
      "type": "api_memory_post",
      "variable": "A",
    },
    {
      "type": "api_memory_put",
      "variable": "B"
    }
  ]
}

```

The following is the response when the threshold values are set:

```

{
  "status_code": "SUCCESS",
  "message": "attack threshold updated"
}

```

**Sample Input for across API:**

```
{
  "id": "18",
  "mode": "user",
  "ioc_threshold": [
    {
      "type": "extended_probing_replay_cookie",
      "variable": "A",
      "tn": "25",
      "tx": "28"
    }, {
      "type": "extended_probing_replay_cookie",
      "variable": "B",
      "tn": "3",
      "tx": "4"
    }
  ]
}
```

The following is the response when the threshold values are set:

```
{
  "status_code": "SUCCESS",
  "message": "attack threshold updated"
}
```

**Metrics REST API**

**Description** The Metrics API is used to fetch API Traffic metrics. The response contains request count for each API, bad request count, request success, failure count, and so on.

**Note:** If ASE is deployed in sideband mode, then server field in the output shows the IP address as 0.0.0.0. For ASE deployed in inline mode, the server field shows the IP address of the backend API server. For more information on ASE sideband mode, see the ASE Admin Guide.

**Method:** GET

**URL:** `/v4/abs/metrics?later_date=<>&earlier_date=<>api=<api_name>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

**Sample Response**

```
{
  "company": "ping identity",
  "name": "api_metrics",
  "description": " This report contains metrics for request/response traffic
  for the specified API",
  "earlier_date": "Mon Jan 13 18:00:00:000 2018",
  "later_date": "Wed Jan 15 18:00:00:000 2018",
  "api_name": "shop",
  "req_resp_summary": {
    "api_url": "shopapi",
    "total_requests": 342102,
    "success": 279360,

```

```

"sessions": 0,
"no_sessions": 342102,
"most_popular_method": "GET",
"most_popular_device": "MAC_OS_X",
"most_popular_ips": [
"10.10.1.38",
"10.10.1.39",
"10.10.1.37"
]
"servers": [
{
"server": "192.168.11.164:3001",
"count": 5357
},
{
"server": "192.168.11.164:3002",
"count": 5354
},
{
"server": "192.168.11.164:3003",
"count": 5358
},
{
"server": "192.168.11.164:3004",
"count": 1667
}
],
"req_resp_details": {
"api_url": "shopapi",
"session_details": [],
"no_session": {
"request_details": [
{
"total_requests": 14865,
"source_ip": [
{
"ip": "10.10.1.24",
"count": 152,
"method": [
"POST"
]
},
{
"ip": "10.10.1.71",
"count": 482,
"method": [
"PUT"
]
}
]
}
],
"user_agent": [
{
"user_agent": "SAFARI",
"count": 7187
},
{
"user_agent": "FIREFOX",
"count": 12536
},
{
"user_agent": "MOZILLA",
"count": 5509
},

```

```

{
  "user_agent": "CHROME",
  "count": 29241
},
{
  "server": [
    {
      "server": "192.168.11.164:3001",
      "count": 723
    },
    {
      "server": "192.168.11.164:3002",
      "count": 689
    },
    {
      "server": "192.168.11.164:3003",
      "count": 749
    },
    {
      "server": "192.168.11.164:3004",
      "count": 237
    }
  ]
},
{
  "path": "/shopapi/put",
  "device": [
    {
      "device": "WINDOWS_8",
      "count": 8338
    },
    {
      "device": "MAC_OS_X",
      "count": 14276
    },
    {
      "device": "WINDOWS_XP",
      "count": 5990
    },
    {
      "device": "UBUNTU",
      "count": 6546
    }
  ]
},
{
  "total_requests": 2,
  "source_ip": [
    {
      "ip": "10.10.1.69",
      "count": 2,
      "method": [
        "GET"
      ]
    }
  ]
},
{
  "user_agent": [
    {
      "user_agent": "CHROME",
      "count": 2
    }
  ]
},
{
  "path": "/shopapi/get/etc",
  "device": [
    {
      "device": "MAC_OS_X",

```



```

"ip_list": [
  {
    "ip": "100.64.20.62",
    "total_requests": 1,
    "devices": {
      "WINDOWS_XP": 1
    },
    "methods": {
      "DELETE": 1
    },
    "urls": {
      "/apikeyheader/zipcode": 1
    },
    "apis": {
      "apikeyheader": 1
    }
  },
  {
    "api_key": "86ELLUSN6RAHEPF7",
    "total_requests": 1,
    "ip_list": [
      {
        "ip": "100.64.17.79",
        "total_requests": 1,
        "devices": {
          "MAC_OS_X": 1
        },
        "methods": {
          "GET": 1
        },
        "urls": {
          "/apikeyheader/zipcode": 1
        },
        "apis": {
          "apikeyheader": 1
        }
      }
    ],
    {
      "api_key": "5JSKZZ53TGBQZ8V2",
      "total_requests": 1,
      "ip_list": [
        {
          "ip": "100.64.33.183",
          "total_requests": 1,
          "devices": {
            "WINDOWS_7": 1
          },
          "methods": {
            "POST": 1
          },
          "urls": {
            "/apikeyheader/login": 1
          },
          "apis": {
            "apikeyheader": 1
          }
        }
      ]
    }
  ]
]

```



}

## OAuth2 Token Metrics REST API

**Description:** The OAuth2 token-based API is used to fetch the metrics for OAuth2 token across all APIs.

**Method:** GET

**URL:** /v4/abs/oauthtokens?later\_date=<yy-mm-dd>T<hh:mm>&earlier\_date=<yy-mm-dd>T<hh:mm>

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "oauth_token_metrics",
  "description": "This report contains a summary and detailed oauth token
  metrics across all APIs",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "summary": {
    "tokens": 30,
    "total_requests": 163250
  },
  "details": [
    {
      "token": "token_highresptime",
      "total_requests": 2,
      "ip_list": [
        {
          "ip": "127.0.0.1",
          "total_requests": 2,
          "devices": {
            "UNKNOWN": 2
          }
        },
        {
          "methods": {
            "GET": 2
          }
        },
        {
          "urls": {
            "/2_atm_app_oauth/longresponse": 1,
            "/atm_app_oauth/longresponse": 1
          }
        },
        {
          "apis": {
            "atm_app_oauth": 1,
            "2_atm_app_oauth": 1
          }
        }
      ]
    },
    {
      "token": "token10",
      "total_requests": 4596,
      "ip_list": [
        {
          "ip": "127.0.0.1",
          "total_requests": 4596,
          "devices": {
```

```

"UNKNOWN": 4596
},
"methods": {
"DELETE": 148,
"POST": 1036,
"GET": 1796,
"PUT": 1616
},
"urls": {
"/2_atm_app_oauth/put200": 656,
"/atm_app_oauth/delete200": 68,
"/2_atm_app_oauth/put400": 152,
"/atm_app_oauth/delete400": 6
},
"apis": {
"atm_app_oauth": 2298,
"2_atm_app_oauth": 2298
}
}
],
},
{
"token": "token14",
"total_requests": 7604,
"ip_list": [
{
"ip": "127.0.0.1",
"total_requests": 7604,
"devices": {
"UNKNOWN": 7604
},
"methods": {
"DELETE": 1596,
"POST": 160,
"GET": 4000,
"PUT": 1848
},
"urls": {
"/2_atm_app_oauth/put200": 846,
"/atm_app_oauth/delete200": 742,
"/2_atm_app_oauth/put400": 78,
"/2_atm_app_oauth/get400": 264
},
"apis": {
"atm_app_oauth": 3802,
"2_atm_app_oauth": 3802
}
}
],
},
{
"token": "token_type2memory",
"total_requests": 2,
"ip_list": [
{
"ip": "127.0.0.1",
"total_requests": 2,
"devices": {
"UNKNOWN": 2
},
"methods": {
"POST": 2
},
"urls": {

```



```

    "total_requests": 700
  },
  "details": [
    {
      "username": "t4",
      "tokens": [
        "t4VjqtSC",
        "t4XjDKtD",
        "t4JGkNZO",
        "t4gTqCqM",
        "t4UTgLaK",
        "t4mhTDNj",
        "t4srzDrl"
      ],
      "total_requests": 70,
      "ip_list": [
        {
          "ip": "127.0.0.28",
          "total_requests": 35,
          "devices": {
            "LINUX": 35
          },
          "methods": {
            "POST": 35
          },
          "urls": {
            "/atm_app_oauth": 35
          },
          "apis": {
            "atm_app_oauth": 35
          }
        },
        {
          "ip": "127.0.0.1",
          "total_requests": 35,
          "devices": {
            "LINUX": 35
          },
          "methods": {
            "POST": 35
          },
          "urls": {
            "/atm_app_oauth": 35
          },
          "apis": {
            "atm_app_oauth": 35
          }
        }
      ]
    },
    {
      "username": "t7",
      "tokens": [
        "t7cnVFBi",
        "t7wQSnC",
        "t7XnAlRa",
        "t7MYwQan",
        "t7jzNFVF",
        "t7nsdecG",
        "t7Datxrw"
      ],
      "total_requests": 70,
      "ip_list": [

```

```

        "ip": "127.0.0.28",
        "total_requests": 35,
        "devices": {
            "LINUX": 35
        },
        "methods": {
            "POST": 35
        },
        "urls": {
            "/atm_app_oauth": 35
        },
        "apis": {
            "atm_app_oauth": 35
        }
    },
    {
        "ip": "127.0.0.1",
        "total_requests": 35,
        "devices": {
            "LINUX": 35
        },
        "methods": {
            "POST": 35
        },
        "urls": {
            "/atm_app_oauth": 35
        },
        "apis": {
            "atm_app_oauth": 35
        }
    }
]
},
{
    "username": "t0",
    "tokens": [
        "t0iPoYEc",
        "t0wkCuYC",
        "t0YXowow",
        "t0NSwIjU",
        "t0PRwPik",
        "t0tEtlzI",
        "t0XBLmcE"
    ],
    "total_requests": 70,
    "ip_list": [
        {
            "ip": "127.0.0.28",
            "total_requests": 35,
            "devices": {
                "LINUX": 35
            },
            "methods": {
                "POST": 35
            },
            "urls": {
                "/atm_app_oauth": 35
            },
            "apis": {
                "atm_app_oauth": 35
            }
        },
        {
            "ip": "127.0.0.1",

```

```

        "total_requests": 35,
        "devices": {
            "LINUX": 35
        },
        "methods": {
            "POST": 35
        },
        "urls": {
            "/atm_app_oauth": 35
        },
        "apis": {
            "atm_app_oauth": 35
        }
    }
]
},
{
    "username": "t3",
    "tokens": [
        "t3GUUfmD",
        "t3tRVhdk",
        "t3nkCZIR",
        "t3EFpRTc",
        "t3PuDsBr",
        "t3xGzXXB",
        "t3pZoWgX"
    ],
    "total_requests": 70,
    "ip_list": [
        {
            "ip": "127.0.0.28",
            "total_requests": 35,
            "devices": {
                "LINUX": 35
            },
            "methods": {
                "POST": 35
            },
            "urls": {
                "/atm_app_oauth": 35
            },
            "apis": {
                "atm_app_oauth": 35
            }
        },
        {
            "ip": "127.0.0.1",
            "total_requests": 35,
            "devices": {
                "LINUX": 35
            },
            "methods": {
                "POST": 35
            },
            "urls": {
                "/atm_app_oauth": 35
            },
            "apis": {
                "atm_app_oauth": 35
            }
        }
    ]
}
]

```

}

## Anomalies REST API

**Description:** The Anomalies API is used to fetch the list of anomalies. The response contains anomalies count for the API, request success or failure count, and so on.

**Method:** GET

**URL:** `/v4/abs/anomalies?later_date=<>earlier_date=<>&api=<api_name>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "api_anomalies",
  "description": "This report contains information on anomalous activity
  on the specified API.",
  "earlier_date": "Sun Jan 12 18:00:00:000 2018",
  "later_date": "Tue Jan 14 18:00:00:000 2018",
  "api_name": "shop",
  "anomalies_summary": {
    "api_url": "shopapi",
    "total_anomalies": 14,
    "most_suspicious_ips": [],
    "most_suspicious_anomalies_urls": []
  },
  "anomalies_details": {
    "url_anomalies": {
      "suspicious_sessions": [],
      "suspicious_requests": []
    },
    "ioc_anomalies": [
      {
        "anomaly_type": "API Memory Attack Type 2",
        "cookies": [
          {
            "cookie": "AMAT_2_H",
            "access_time": [
              "Mon Jan 13 01:01:33:589 2018"
            ]
          },
          {
            "cookie": "AMAT_2_H",
            "access_time": [
              "Mon Jan 13 01:01:33:589 2018"
            ]
          }
        ]
      },
      {
        "anomaly_type": "Data Exfiltration Attack",
        "cookies": [
          {
            "cookie": "data_exfiltration_VH",
            "access_time": [
              "Mon Jan 13 04:54:49:222 2018"
            ]
          }
        ]
      }
    ]
  }
}
```

```

]
},
{
  "cookie": "data_exfiltration_H",
  "access_time": [
    "Mon Jan 13 05:26:53:981 2018"
  ]
}
],
},
{
  "anomaly_type": "Cookie DoS Attack",
  "cookies": [
    {
      "cookie": "data_exfiltration_VH",
      "access_time": [
        "Mon Jan 13 04:54:49:222 2018"
      ]
    },
    {
      "cookie": "AMAT_1_freq_VH",
      "access_time": [
        "Sun Jan 12 23:17:55:931 2018"
      ]
    },
    {
      "cookie": "data_exfiltration__H__H",
      "access_time": [
        "Mon Jan 13 05:39:18:515 2018"
      ]
    },
    {
      "cookie": "AMAT_2_VH",
      "access_time": [
        "Sun Jan 12 23:59:39:483 2018"
      ]
    }
  ]
},
{
  "anomaly_type": "Extreme Client Activity Attack",
  "cookies": [
    {
      "cookie": "data_exfiltration_VH",
      "access_time": [
        "Mon Jan 13 04:54:49:222 2018"
      ]
    },
    {
      "cookie": "AMAT_1_VH",
      "access_time": [
        "Sun Jan 12 23:17:55:931 2018"
      ]
    },
    {
      "cookie": "data_exfiltration_H_H",
      "access_time": [
        "Mon Jan 13 05:39:18:515 2018"
      ]
    },
    {
      "cookie": "AMAT_2_VH",
      "access_time": [
        "Sun Jan 12 23:59:39:483 2018"
      ]
    }
  ]
}

```



```
]
}
]
}
]
}
}
```

## Anomalies across APIs

**Description:** The across APIs Anomalies REST API is used to fetch the list of anomalies. The response contains the type of anomalies, the type ID and the date range when the anomaly was detected.

**Method:** GET

**URL:** `/v4/abs/anomalies?later_date=<>earlier_date=<>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

## Sample Response

```
[
  {
    "company": "ping identity",
    "anomaly_type": "Stolen API Key Attack - Per API Key",
    "type": 31,
    "name": "api_anomaly_type",
    "description": "Client (API Key) reusing API Keys to deceive
application services",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  },
  {
    "company": "ping identity",
    "anomaly_type": "Probing Replay Attack - API Key",
    "type": 32,
    "name": "api_anomaly_type",
    "description": "Probing or breach attempts on an API service - also
called fuzzing",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  },
  {
    "company": "ping identity",
    "anomaly_type": "Extended Probing Replay Attack - API key",
    "type": 33,
    "name": "api_anomaly_type",
    "description": "Probing or breach attempts on an API service - also
called fuzzing",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  },
  {
    "company": "ping identity",
    "anomaly_type": "Account Takeover Attack Type 1 - Username",
    "type": 34,
```

```

    "name": "api_anomaly_type",
    "description": "Abnormal activity by user indicating his/her
credentials are compromised",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  },
  {
    "company": "ping identity",
    "anomaly_type": "Account Takeover Attack Type 2 - Username",
    "type": 35,
    "name": "api_anomaly_type",
    "description": "Abnormal activity by user indicating his/her
credentials are compromised",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  },
  {
    "company": "ping identity",
    "anomaly_type": "Sequence Attack",
    "type": 36,
    "name": "api_anomaly_type",
    "description": "Abnormal sequence of transactions",
    "earlier_date": "Wed May 22 12:00:00:000 2019",
    "later_date": "Fri Jun 28 12:00:00:000 2019",
    "api_name": "all"
  }
]

```

## OAuth2 Token Forensics REST API

**Description:** The OAuth2 token forensics provides information like total number of requests for a token and the number of attacks identified using the token.

**Method:** GET

**URL:** `/v4/abs?later_date=<>T<hh:mm>&earlier_date=<>T<hh:mm>&token=<oauth2_token>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```

{
  "company": "ping identity",
  "name": "api_abs_token",
  "description": "This report contains a summary and detailed information on
metrics, attacks and anomalies for the specified token across all APIs.",
  "earlier_date": "Tue Feb 13 18:00:00:000 2018",
  "later_date": "Sun Feb 18 18:00:00:000 2018",
  "summary": {
    "total_requests": 6556,
    "total_attacks": 2,
    "total_anomalies": 0
  },
  "details": {
    "metrics": {
      "token": "token1",
      "total_requests": 6556,

```

```

"ip_list": [
{
"ip": "127.0.0.1",
"total_requests": 6556,
"devices": {
"UNKNOWN": 6556
},
"methods": {
"DELETE": 472,
"POST": 140,
"GET": 1944,
"PUT": 4000
},
"urls": {
"/atm_app_oauth/delete200": 218,
"/atm_app_oauth/get200": 850,
"/atm_app_oauth/post400": 8,
"/atm_app_oauth/post200": 62,
"/atm_app_oauth/put400": 62,
"/atm_app_oauth/get400": 122,
"/atm_app_oauth/put200": 1938,
"/atm_app_oauth/delete400": 18,
"/2_atm_app_oauth/put200": 1938,
"/2_atm_app_oauth/post200": 62,
"/2_atm_app_oauth/delete200": 218,
"/2_atm_app_oauth/delete400": 18,
"/2_atm_app_oauth/put400": 62,
"/2_atm_app_oauth/post400": 8,
"/2_atm_app_oauth/get400": 122,
"/2_atm_app_oauth/get200": 850
},
"apis": {
"atm_app_oauth": 3278,
"2_atm_app_oauth": 3278
}
}
],
"attack_types": {
"API Memory Attack Type 1": [
"atm_app_oauth",
"2_atm_app_oauth"
],
"Data Poisoning Attack": [
"atm_app_oauth",
"2_atm_app_oauth"
]
},
"anomaly_types": {}
}
}

```

## IP Forensics REST API

**Description:** The IP forensics API provides forensics information for an IP address during a specified period. Information delivered includes attack types, metrics, and anomaly details.

**Method:** GET

**URL:** `/v4/abs?later_date=<>T<hh:mm>&earlier_date=<>T<hh:mm>&IP=<IP_address>`

	Header	Value
--	--------	-------

<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "api_abs_ip",
  "description": " This report contains a summary and detailed information
  on all attacks, metrics, and anomalies for the specified IP address on
  the defined API.",
  "summary": {
    "total_requests": 18222,
    "total_ioctypes": 0,
    "total_anomalies": 0
  },
  "details": {
    "ioc_types": [],
    "metrics": {
      "no_session": [
        {
          "start_time": "Sat Jan 04 15:30:00:000 2018",
          "end_time": "Sat Jan 04 15:39:59:952 2018",
          "total_requests": 2749,
          "source_ip": "100.64.10.203",
          "path": "/atmapp/login"
          "methods": [
            "GET"
          ]
        },
        {
          "start_time": "Sat Jan 04 15:30:00:000 2018",
          "end_time": "Sat Jan 04 15:39:59:952 2018",
          "total_requests": 2952,
          "source_ip": "100.64.10.203",
          "path": "/atmapp/upload"
        },
        {
          "start_time": "Sat Jan 04 15:30:00:000 2018",
          "end_time": "Sat Jan 04 15:39:59:952 2018",
          "total_requests": 9547,
          "source_ip": "100.64.10.203",
          "path": "/atmapp/zipcode"
        },
        {
          "start_time": "Sat Jan 04 15:30:00:000 2018",
          "end_time": "Sat Jan 04 15:39:59:952 2018",
          "total_requests": 2964,
          "source_ip": "100.64.10.203",
          "path": "/atmapp/update"
        }
      ],
      "session": [
        {
          "session_id": "ZP7FE32357SPVT5X",
          "start_time": "Sat Jan 04 15:35:14:241 2018",
          "end_time": "Sat Jan 04 15:35:14:241 2018",
          "total_requests": 1,
          "source_ip": [
            {
              "ip": "100.64.10.203",
```

```

"count": 1,
"method": [
  "POST"
]
},
"user_agent": [
  {
    "user_agent": "IE11",
    "count": 1
  }
],
"path_info": [
  {
    "path": "/atmapp/upload",
    "count": 1
  }
],
"device": [
  {
    "device": "WINDOWS_7",
    "count": 1
  }
],
"device": [
  {
    "device": "MAC_OS_X",
    "count": 1
  }
],
"start_time": "Sat Jan 04 15:40:00:000 2018",
"end_time": "Sat Jan 04 15:30:00:000 2018",
"api_name": "atmapp"
}

```

## Cookie Forensics REST API

**Description:** Cookie forensics API provides forensics information for a cookie during a specified period. Information provided includes attack types, metrics, and anomaly details.

**Method:** GET

**URL:** [/v4/abs?later\\_date=<>T<hh:mm>&earlier\\_date=<>T<hh:mm>&cookie=<cookie\\_value>](/v4/abs?later_date=<>T<hh:mm>&earlier_date=<>T<hh:mm>&cookie=<cookie_value>)

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```

{
  "company": "ping identity",
  "name": "api_abs_cookie",
  "description": "This report contains a summary and detailed information on all attacks, metrics, and anomalies for the specified cookie on

```

```

    the defined API",
    "earlier_date": "Mon Jan 17 06:40:00:000 2018",
    "later_date": "Mon Jan 17 07:00:00:000 2018",
    "api_name": "shop",
    "summary": {
      "total_requests": 501,
      "total_anomalies": 0,
      "total_ioc": 3
    },
    "details": {
      "ioc_types": [
        "data_exfiltration_attack",
        "cookie_dos_attack",
        "extreme_client_activity_attack"
      ],
      "metrics": [
        {
          "session_id": "extreme_client_activity_500_request",
          "start_time": "Mon Jan 17 06:47:19:687 2018",
          "end_time": "Mon Jan 17 06:47:20:505 2018",
          "total_requests": 501,
          "source_ip": [
            {
              "ip": "100.100.10.12",
              "count": 501,
              "method": [
                "POST",
                "GET"
              ]
            }
          ],
          "user_agent": [
            {
              "user_agent": "CHROME",
              "count": 501
            }
          ],
          "path_info": [
            {
              "path": "/shopapi/get",
              "count": 500
            },
            {
              "path": "/shopapi/login",
              "count": 1
            }
          ],
          "device": [
            {
              "device": "LINUX",
              "count": 501
            }
          ]
        }
      ],
      "anomalies": []
    }
  }
}

```

## Token Forensics REST API

**Description:** Token forensics API provides forensics information for a token during a specified period. Information provided includes attack types, metrics, and anomaly details.

**Method:** GET**URL:** /v4/abs?later\_date=<>T<hh:mm>&earlier\_date=<>T<hh:mm>  
&token=<oauth2\_token>

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

**Sample Response**

```
{
  "company": "ping identity",
  "name": "api_abs_token",
  "description": "This report contains a summary and detailed information
on metrics, attacks and anomalies for the specified token across all
APIs.",
  "earlier_date": "Wed May 22 12:00:00:000 2019",
  "later_date": "Fri Jun 28 12:00:00:000 2019",
  "summary": {
    "total_requests": 10,
    "total_attacks": 0,
    "total_anomalies": 0
  },
  "details": {
    "metrics": {
      "token": "t3nkCZIR",
      "total_requests": 10,
      "ip_list": [
        {
          "ip": "127.0.0.28",
          "total_requests": 5,
          "devices": {
            "LINUX": 5
          },
          "methods": {
            "POST": 5
          },
          "urls": {
            "/atm_app_oauth": 5
          },
          "apis": {
            "atm_app_oauth": 5
          }
        },
        {
          "ip": "127.0.0.1",
          "total_requests": 5,
          "devices": {
            "LINUX": 5
          },
          "methods": {
            "POST": 5
          },
          "urls": {
            "/atm_app_oauth": 5
          },
          "apis": {
            "atm_app_oauth": 5
          }
        }
      ]
    }
  }
}
```

```

    ]
  },
  "attack_types": {},
  "anomaly_types": {}
}
}

```

## API Key Forensics REST API

API Key forensics API provides forensics information for a API Key during a specified period. Information provided includes attack types, metrics, and anomaly details.

**Method:** GET

**URL:** `/v4/abs?later_date=<>T<hh:mm>&earlier_date=<>T<hh:mm> &api_key=<api_key>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```

{
  "company": "ping identity",
  "name": "api_abs_api_key",
  "description": "This report contains a summary and detailed information on metrics, attacks and anomalies for the specified api key across all APIs.",
  "earlier_date": "Sat Jan 12 13:30:00:000 2019",
  "later_date": "Tue Dec 31 18:00:00:000 2019",
  "summary": {
    "total_requests": 2621,
    "total_attacks": 1,
    "total_anomalies": 1
  },
  "details": {
    "metrics": {
      "api_key": "finite_api_key",
      "total_requests": 2621,
      "ip_list": [
        {
          "ip": "192.168.2.2",
          "total_requests": 457,
          "devices": {
            "UNKNOWN": 457
          },
          "methods": {
            "GET": 457
          },
          "urls": {
            "/atm_app/getzipcode": 457
          },
          "apis": {
            "atm_app": 457
          }
        },
        {
          "ip": "192.168.2.1",
          "total_requests": 560,
          "devices": {
            "UNKNOWN": 560
          }
        }
      ]
    }
  }
}

```



```

    },
    "methods": {
      "GET": 560
    },
    "urls": {
      "/atm_app/getzipcode": 560
    },
    "apis": {
      "atm_app": 560
    }
  },
  {
    "ip": "192.168.2.3",
    "total_requests": 404,
    "devices": {
      "UNKNOWN": 404
    },
    "methods": {
      "GET": 404
    },
    "urls": {
      "/atm_app/getzipcode": 404
    },
    "apis": {
      "atm_app": 404
    }
  },
  {
    "ip": "192.168.2.5",
    "total_requests": 1200,
    "devices": {
      "UNKNOWN": 1200
    },
    "methods": {
      "GET": 1200
    },
    "urls": {
      "/atm_app/getzipcode": 1200
    },
    "apis": {
      "atm_app": 1200
    }
  }
]
},
"attack_types": {
  "Stolen API Key Attack- Per API Key": [
    "all"
  ]
},
"anomaly_types": {
  "Stolen API Key Attack- Per API Key": [
    "all"
  ]
}
}
}

```

## Username Forensics REST API

Username forensics API provides forensics information for a username during a specified period. Information provided includes attack types, metrics, and anomaly details.

**Method:** GET**URL:** /v4/abs?later\_date=<>T<hh:mm>&earlier\_date=<>T<hh:mm> &username=<username>

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

**Sample Response**

```
{
  "company": "ping identity",
  "name": "api_abs_username",
  "description": "This report contains a summary and detailed information
on metrics, attacks and anomalies for the specified user name across all
APIs.",
  "earlier_date": "Sat Jan 12 13:30:00:000 2019",
  "later_date": "Tue Dec 31 18:00:00:000 2019",
  "summary": {
    "total_requests": 109965,
    "total_attacks": 0,
    "total_anomalies": 0
  },
  "details": {
    "metrics": {
      "username": "t4",
      "tokens": [
        "t4MFBkEe",
        "t4GpEkUS",
        "t4ZxUOjb",
        "t4QEvJKT"
      ],
      "total_requests": 109965,
      "ip_list": [
        {
          "ip": "127.0.0.28",
          "total_requests": 54983,
          "devices": {
            "Mozilla/5.0 (X11; Linux x86_64) AppleWebKit/537.36
(KHTML, like Gecko) Chrome/57.0.2987.110 Safari/537.36": 54983
          },
          "methods": {
            "POST": 54983
          },
          "urls": {
            "/atm_app_oauth": 54983
          },
          "apis": {
            "atm_app_oauth": 54983
          }
        },
        {
          "ip": "127.0.0.1",
          "total_requests": 54982,
          "devices": {
            "Mozilla/5.0 (X11; Linux x86_64) AppleWebKit/537.36
(KHTML, like Gecko) Chrome/57.0.2987.110 Safari/537.36": 54982
          },
          "methods": {
            "POST": 54982
          }
        }
      ]
    }
  }
}
```

```

        "urls": {
          "/atm_app_oauth": 54982
        },
        "apis": {
          "atm_app_oauth": 54982
        }
      ]
    },
    "attack_types": {},
    "anomaly_types": {}
  }
}

```

## Attack Types REST and WebSocket APIs

**Description:** The Attack Type API lists attack details based on the attack ID provided in the API query parameter. The attack type ID ranges from 1-37 for REST APIs and 50-53 for WebSocket APIs. The REST API attacks can be per API or across APIs. For more information see, [REST API attacks](#) and [WebSocket API attacks](#)

**Method:** GET

**URL for per API attacks (REST and WebSocket):** `/v4/abs/attack?later_date<>&earlier_date<>&api=<api_name>&type=<type_id>`

**URL for across API attacks:** `/v4/abs/attack?later_date<>&earlier_date<>&type=<type_id>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```

{
  "company": "ping identity",
  "description": " Client (IP or Cookie) extracting an abnormal amount of
  data for given API",
  "earlier_date": "Sat Jun 01 08:20:00:000 2019",
  "later_date": "Wed Jun 05 13:20:00:000 2019",
  "api_name": "atmapp",
  "ioc_type": "Data Exfiltration",
  "ips": [
    {
      "ip": "100.64.6.50",
      "access_time": [
        "Tue Jun 04 16:09:59:935 2019"
      ]
    },
    {
      "ip": "100.64.6.51",
      "access_time": [
        "Tue Jun 04 16:09:59:935 2019",
        "Tue Jun 04 16:39:59:996 2019"
      ]
    }
  ]
}

```

## Flow Control REST API

**Description:** The Flow Control API is used to fetch details of all connections that exceeded the threshold value for client spike, server spike, connection queued, connection rejected, bytes-in spike, and bytes-out spike.

**Note:** The flow control report is only available when ASE is deployed in inline mode.

**Method:** GET

**URL:** `/v4/abs/flowcontrol?later_date=<>&earlier_date=<>&api=<api_name>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "api_flowcontrol",
  "description": "This report contains flow control information for the
    specified API.",
  "earlier_date": "Wed Jan 01 08:20:00:000 2018",
  "later_date": "Sun Jan 05 13:20:00:000 2018",
  "api_name": "websocket",
  "summary": {
    "client_spike": 610,
    "connection_queued": 0,
    "connection_quota_exceeded": 0,
    "bytes_in_spike": 2743,
    "bytes_out_spike": 287
  },
  "details": {
    "client_spike": [],
    "server_spike": [
      {
        "request_time": "Fri Jan 09 17:19:55:977 2016",
        "connection_id": "147378243",
        "source_ip": "100.64.26.163",
        "destination_api": "/atmapp/login"
      },
      {
        "request_time": "Fri Jan 09 17:19:55:991 2016",
        "connection_id": "1919058221",
        "source_ip": "100.64.20.230",
        "destination_api": "/atmapp/zipcode"
      }
    ],
    "connections_queued": [],
    "connections_rejected": [],
    "bytes_in_spike": [],
    "bytes_out_spike": []
  }
}
```

## Blocked Connection REST API

**Description:** The Blocked Connection API is used to fetch the list of blocked or dropped connections. The response includes anomalies count for the given API, such as request success or failure count.

**Method:** GET

**URL** `/v4/abs/bc?later_date=<>T<hh:mm>&earlier_date=<>T<hh:mm>&details=true`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "earlier_date": "Wed Jan 01 08:20:00:000 2018",
  "later_date": "Sun Jan 05 13:20:00:000 2018",
  "api_blocked_connections": [
    {
      "date": "05September2016",
      "blocked_connections": [
        {
          "apiproxy_node": "204101a4-8b70-489d-98e9-aa3f6e67a93f",
          "blocked_connections": [
            {
              "category": "ioc",
              "details": []
            },
            {
              "category": "api",
              "details": [
                {
                  "source": "100.64.31.235",
                  "type": "no_backend_available",
                  "destination_api": "/atmapp/zipcode"
                },
                {
                  "source": "100.64.25.184",
                  "type": "no_backend_available",
                  "destination_api": "/atmapp/zipcode"
                },
                {
                  "source": "100.64.6.137",
                  "type": "no_backend_available",
                  "destination_api": "/atmapp/zipcode"
                },
                {
                  "source": "100.64.1.251",
                  "type": "no_backend_available",
                  "destination_api": "/atmapp/zipcode"
                }
              ]
            }
          ]
        }
      ]
    }
  ]
}
```

## Backend Error REST API

**Description:** The Backend Error API displays errors reported by the backend servers.

**Method:** GET

**URL:** `/v4/abs/be?earlier_date=<>T<hh:mm>&later_date=<>T<hh:mm>&api=<api_name>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "api backend_errors",
  "description": "This report contains details of backend error
  codes for the specified API",
  "earlier_date": "Wed Jan 01 08:20:00:000 2018",
  "later_date": "Sun Jan 05 13:20:00:000 2018",
  "api_name": "atmapp",
  "backend_error_summary": [
    {
      "error_code": "403",
      "error": "Forbidden",
      "count": 0
    },
    {
      "error_code": "404",
      "error": "Not Found",
      "count": 0
    },
    {
      "error_code": "500",
      "error": "Internal Server Error",
      "count": 16
    },
    {
      "error_code": "503",
      "error": "Service Unavailable",
      "count": 0
    },
    {
      "error_code": "504",
      "error": "Gateway Timeout",
      "count": 0
    }
  ],
  "backend_error_details": [
    {
      "error_code": "403",
      "details": []
    },
    {
      "error_code": "404",
      "details": []
    },
    {
      "error_code": "500",
      "details": [
```

```

{
  "server": "192.168.11.164:3001",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.5.183:24078",
  "request_cookie": ""
},
{
  "server": "192.168.11.164:3002",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.18.126:61932",
  "request_cookie": ""
},
{
  "server": "192.168.11.164:3004",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.27.176:2908",
  "request_cookie": "JSESSIONID=6UQANJWB42U4A4PF"
},
{
  "server": "192.168.11.164:3004",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.14.237:21973",
  "request_cookie": "JSESSIONID=LJ66P3NQW5SDVW8Q"
},
{
  "server": "192.168.11.164:3003",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.5.101:5523",
  "request_cookie": ""
},
{
  "server": "192.168.11.164:3003",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.23.132:14473",
  "request_cookie": "JSESSIONID=NCTZ4RSOZP2IT2OU"
},
{
  "server": "192.168.11.164:3003",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.5.197:50811",
  "request_cookie": ""
},
{
  "server": "192.168.11.164:3003",
  "request_url": "/atmapp/zipcode",
  "request_ip": "100.64.26.70:49425",
  "request_cookie": ""
}
],
{
  "error_code": "503",
  "details": []
},
{
  "error_code": "504",
  "details": []
}
]
}

```

## List Valid URLs REST API

**Description:** The List Valid URL API provides information on all the URLs for the API. The API reports the allowed methods and the count of number of times each URL has been accessed.

**Method:** GET

**URL:** `_/v4/abs/validurl?api=<api_name>`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "name": "api url list",
  "description": "This report provides information on access to each
  unique URL for the specified API",
  "api_name": "shop",
  "host_name": "app",
  "api_url": "shopapi",
  "allowed_methods": [
    "GET",
    "PUT",
    "POST",
    "DELETE",
    "HEAD"
  ],
  "url_list": [
    {
      "protocol": "HTTP/1.1",
      "urls": [
        {
          "url": "/shopapi/get_delay",
          "total_count": 11,
          "methods": [
            {
              "method": "GET",
              "count": 11
            }
          ]
        },
        {
          "url": "/shopapi/post",
          "total_count": 62109,
          "methods": [
            {
              "method": "POST",
              "count": 62109
            }
          ]
        },
        {
          "url": "/shopapi/get_mb",
          "total_count": 2,
          "methods": [
            {
              "method": "GET",
              "count": 2
            }
          ]
        }
      ]
    }
  ]
}
```



```

}
]
},
{
"url": "/shopapi/login",
"total_count": 2686,
"methods": [
{
"method": "POST",
"count": 2686
}
]
},
{
"url": "/shopapi/get?dyanmic_cookie",
"total_count": 378,
"methods": [
{
"method": "GET",
"count": 378
}
]
},
{
"url": "/shopapi/logout",
"total_count": 16964,
"methods": [
{
"method": "POST",
"count": 16964
}
]
},
{
"url": "/shopapi/get?passwd",
"total_count": 1,
"methods": [
{
"method": "GET",
"count": 1
}
]
},
{
"url": "/shopapi/put",
"total_count": 62060,
"methods": [
{
"method": "PUT",
"count": 62060
}
]
}
] ] }

```

## List Hacker's URL REST API

**Description:** The List Invalid URL API provides information on all invalid URLs accessed for an API. The four types of invalid URLs are:

- Irregular URL
- System Commands

- SQL Injection, and
- Buffer Overflow

**Method:** GET

**URL:** `/v4/abs/hackersurl?api=<api_name>&earlier_date=""&later_date=""`

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Response

```
{
  "company": "ping identity",
  "description": "This report contains list of hackers URL for given API",
  "name": "api_hackers_url",
  "api_name": "universal_api",
  "invalid_urls": [
    {
      "url": "/index.php?id=abc') UNION ALL SELECT NULL,NULL,NULL,NULL,NULL,-- ",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=abc') UNION ALL SELECT NULL,NULL,NULL,NULL#",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=(SELECT 46 FROM(SELECT COUNT(*),CONCAT(0x717a71,))",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=abc') UNION ALL SELECT NULL,NULL,NULL#",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=abc UNION ALL SELECT NULL,NULL,NULL,NULL,NULL,#",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=abc' UNION ALL SELECT NULL,NULL,NULL,NULL,,NULL#",
      "ips": [
        "127.0.0.1"
      ]
    },
    {
      "url": "/index.php?id=abc UNION ALL SELECT NULL,NULL,NULL,NULL,NULL#",
      "ips": [
        "127.0.0.1"
      ]
    }
  ],
}
```

```

{
  "url": "/index.php?id=abc' UNION ALL SELECT NULL,NULL,NULL,NULL,NULL-- ",
  "ips": [
    "127.0.0.1"
  ]
},
{
  "url": "/index.php?id=abc') UNION ALL SELECT NULL,NULL-- ",
  "ips": [
    "127.0.0.1"
  ]
},
{
  "url": "/index.php?id=abc UNION ALL SELECT NULL,NULL,NULL,NULL,NULL#",
  "ips": [
    "127.0.0.1"
  ]
},
{
  "url": "/index.php?id=abc%' UNION ALL SELECT NULL-- ",
  "ips": [
    "127.0.0.1"
  ]
},
{
  "url": "/index.php?id=abc) UNION ALL SELECT NULL,NULL,NULL,NULL-- ",
  "ips": [
    "127.0.0.1"
  ]
},
{
  "url": "/index.php?id=abc' UNION ALL SELECT NULL,NULL,NULL-- ",
  "ips": [
    "127.0.0.1"
  ]
}
}

```

## Delete Blacklist REST API

**Description:** The Delete Blacklist REST API deletes active blacklists in ABS. The API checks if the client identifier is present in the active list or not before deleting.

**Method:** PUT

**URL for the API:** [\\_v4/abs/attacklist/](/v4/abs/attacklist/)

	Header	Value
<b>Access Key</b>	x-abs-ak	<string>
<b>Secret Key</b>	x-abs-sk	<string>

### Sample Request to the API

```

{
  "ips": [],
  "cookies": {},
  "oauth_tokens": [],
  "api_keys": [],
  "usernames": ["user_70"]
}

```

}

**Sample response from the API when the client identifiers from active blacklists are deleted**

```
{
  "message": "The following attacks have been removed:",
  "attacklist": {
    "ips": [],
    "cookies": {},
    "oauth_tokens": [
      "SYU4R2ZZN1IDYI0L"
    ],
    "api_keys": [],
    "usernames": []
  },
  "status_code": "SUCCESS"
}
```

**Sample response from the API when the deletion fails**

```
{
  "status_code": "INVALID_JSON",
  "message": "Invalid json. Please ensure all input fields are present and
  have valid values"
}
```

## Threshold range for Tn and Tx

**Threshold range for Tn and Tx**

The following table details the range of Tn and Tx for each attack type. When manually adjusting the threshold values, the values must fall within the specified ranges.

Attack Type	type_id	Variable A (Range)	Variable B (Range)	Variable C (Range)	Variable D (Range)
<b>REST API</b>					
Data Exfiltration	1	Tn = [1-32] Tx = [2-33]	Tn = [1-19] Tx = [2-20]	Tn = [1-99] Tx = [2-100]	NA
Single Client Login	2	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	NA	NA
Multi Client Login	3	Tn = [1-100] Tx = "na"	NA	NA	NA
Stolen Cookie / Access Token	4	Tn = [2-10]	Tn = [1-19], Tx = [2-20]	NA	NA
API Memory Attack Type 1	5	Tn = [1-32] Tx = [2-33]	Tn = [1-19] Tx = [2-20]	Tn = [1-99] Tx = [2-100]	NA
API Memory Attack Type 2	6	Tn = [1-32] Tx = [2-33]	Tn = [1-19] Tx = [2-20]	Tn = [1-99] Tx = [2-100]	NA
Cookie DoS	7	Tn = [1-9] Tx = [2-10]	Tn = [1-19] Tx = [2-20]	NA	NA

API Probing Replay	8	Tn = [1-99] Tx = [2-100]	NA	NA	NA
API DoS Attack Type 1	9	Tn = [1-100] Tx = "[2-100]"	NA	NA	NA
Extreme Client Activity	10	Tn = [1-19] Tx = [2-20]	NA	NA	NA
Extreme App Activity	11	Tn = [1-19] Tx = [2-20]	NA	NA	NA
API DoS Attack	12	Tn = [1- 100] Tx = "na"	NA	NA	NA
API DDoS Attack Type 2	13	NA	NA	NA	NA
Data Deletion	14	Tn = [1- 19] Tx = [2-20]	Tn = [1-99] Tx = [2-100]	NA	NA
Data Poisoning	15	Tn = [1- 19] Tx = [2-20]	Tn = [1-99] Tx = [2-100]	Tn = [1-32] Tx = [2-33]	NA
Stolen Token Attack Type 2	16	Tn = [2-10] Tx = "na"	Tn = [1-100]	Tn = [1-100]	NA
Stolen Cookie Attack Type 2	17	Tn = [2-10] Tx = "na"	Tn = [1-100]	Tn = [1-100]	NA
API Probing Replay Attack 2 (client identifier: cookie)	18	Tn = [1-99] Tx = [2-100]	Tn = [1-19] Tx = [2-20]	NA	NA
API Probing Replay Attack 2 (client identifier: token)	19	Tn = [1-99] Tx = [2-100]	Tn = [1-19] Tx = [2-20]	NA	NA
API Probing Replay Attack 2 (client identifier: IP address)	20	Tn = [1-99] Tx = [2-100]	Tn = [1-19] Tx = [2-20]	NA	NA
Data Exfiltration Attack Type 2	21	Tn = [1-42] Tx = [2-43]	Tn = [0-30]	Tn = [1-100]	NA
Excessive Client Connections (client identifier : cookie)	22	Tn = [1-19], Tx =[2-20]	NA	NA	NA
Excessive Client Connections (client identifier : token)	23	Tn = [1-19], Tx =[2-20]	NA	NA	NA
Excessive Client Connections (client identifier : IP address)	24	Tn = [1-19], Tx =[2-20]	NA	NA	NA

Content Scraping Type 1 (client identifier : cookie)	25	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]
Content Scraping Type 1 (client identifier : token)	26	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]
Content Scraping Type 1 (client identifier : IP address)	27	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]
Content Scraping Type 2	28	Tn = [1-29] Tx = [2-30]	Tn = [1-100]	NA	NA
Unauthorized client attack (client identifier: IP address)	29	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	NA	NA
Single Client Login Attack Type 2 (client identifier: IP address)	30	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	NA	NA
Stolen API Key Attack- API Key	31	Tn = [1-100] Tx = NA	Tn = [1-100] Tx = NA	Tn = [1-100] Tx = NA	Tn = [1-100] Tx = NA
Probing Replay Attack - API Key	32	Tn = [1-100] Tx = NA	Tn = [1-100] Tx = NA	NA	NA
Extended Probing Replay Attack - API Key	33	Tn = [1-100] Tx = NA	Tn = [1-100] Tx = NA	NA	NA
User Probing Type 1	34	Tn = [1-99] Tx = [2-100]	Tn = [1-99] Tx = [2-100]	Tn = [1-9] Tx = [2-10]	Tn = [1-9] Tx = [2-20]
User Probing Type 2	35	Tn = [1-99] Tx = [2-100]	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	Tn = [1-29] Tx = [2-30]
Sequence attack	36	Tn = [1-19] Tx = [2-20]	NA	NA	NA
Header Manipulation	37	Tn = [1-99] Tx = [2-100]	Tn = [1-20] Tx = NA	Tn = [1-29] Tx = [2-30]	Tn = [1-100] Tx = NA
Account Takeover -UBA	38	Tn = [1-100] Tx = NA	Tn = [1-99] Tx = [2-100]	NA	NA
User Data Exfiltration Type 2	39	Tn = [1-32] Tx = [2-33]	Tn = [1-32] Tx = [2-33]	Tn = [1-19] Tx = [2-20]	NA
User Data Injection	40	Tn = [1-32] Tx = [2-33]	Tn = [1-19] Tx = [2-20]	NA	NA
Query Manipulation Attack	41	Tn = [1-20] Tx = NA	Tn = [1-2] Tx = NA	Tn = [1-2] Tx = NA	Tn = [1-100] Tx = NA
<b>WebSocket API</b>					
WS Cookie Attack	50	Tn = [1-99] Tx = [2-100]	Tn = [1-19] Tx = [2-20]	NA	NA

WS Identity Attack	51	Tn = [1-19] Tx = [2-20]	Tn = [1-19] Tx = [2-20]	NA	NA
WS DoS Attack	53	Tn = [1- 100] Tx = "na"	NA	NA	NA
WS Data Exfiltration Attack	54	Tn = [1- 100] Tx = "na"	NA	NA	NA

## ABS log messages

The following tables list the critical log messages from `abs.log` and `aad.log` file. `abs.log` file is rotated every 24-hours. For more information, see [ABS logs](#) on page 326

### abs.log messages:

Log message	Description
Warn :-Maximum Transaction limit is reached for this month	This message is logged in <code>abs.log</code> when the transaction limit is reached for the allotted license usage. For more information, see <a href="#">ABS License</a> on page 309
Warn :- Attempt to shutdown ABS from 127.0.0.1	This message is logged in <code>abs.log</code> when shutdown of ABS AI engine is initiated.
Warn :- Failed to delete IPs from IOCs - try again	This message is logged in <code>abs.log</code> when the Attack list REST API encounters an issues while deleting the IP address from the blacklist.
Warn :- Failed to delete tokens from IOCs - try again	This message is logged in <code>abs.log</code> when the Attack list REST API encounters an issues while deleting the OAuth token from the blacklist
Warn :- Failed to delete usernames from IOCs - try again	This message is logged in <code>abs.log</code> when the Attack list REST API encounters an issues while deleting the usernames from the blacklist.
Warn :- Failed to delete api keys from IOCs - try again	This message is logged in <code>abs.log</code> when the Attack list REST API encounters an issues while deleting the API Keys from the blacklist.
Warn :- License is Expired. Please renew your license	This message is logged in <code>abs.log</code> when ABS license has expired. For more information, see <a href="#">ABS License</a> on page 309
Warn :- MongoDB primary node is down	This message is logged in <code>abs.log</code> when a MongoDB connection failure occurs.
Warn :- Stream init-wait interrupted	This message is logged in <code>abs.log</code> when streaming of access log files is interrupted.
Warn :- File system usage reached configured value of: 80 % ABS will not accept new logs from ASE.	This message is logged in <code>abs.log</code> when ABS stops accepting access log files from ASE because of maximum use of filesystem.
Warn :- Error while closing mongo connections	This message is logged in <code>abs.log</code> when shutdown of MongoDB connection was not successful.

Log message	Description
Warn :- Error while loading anomaly dictionary from mongo	This message is logged in <code>abs.log</code> when writing of anomalies to data directory fails.
Warn :- Error while closing file handle for stream config	This message is logged in <code>abs.log</code> when an error occurs while closing the streaming configuration file.
Error: exception while parsing license file <code>/opt/pingidentity/abs/config/PingIntelligence.lic</code>	This message is logged in <code>abs.log</code> when an error occurs while reading the license file.  Add the file named "PingIntelligence.lic" to the specified path with read permission and restart the ABS AI engine
Error: License <code>/opt/pingidentity/abs/config/PingIntelligence.lic</code> is invalid. ABS will shut down now.	This message is logged in <code>abs.log</code> when an error is encountered while validating the license file.  Provide a valid license file and restart the ABS AI engine
ABS will shut down now	This message is logged in <code>abs.log</code> when your free ABS license expires.
Attempting to initialize abs, but abs is already in <message>	This message is logged in <code>abs.log</code> when another ABS process is already running.
error while loading <code>abs.properties</code> <Custom run-time message>  The various custom error messages could be: <ul style="list-style-type: none"> <li>▪ property &lt;<code>abs_propertie</code>&gt; is missing</li> <li>▪ invalid value for property <code>log_level</code>. Value should be string and member of [ALL,DEBUG,INFO,WARN,ERROR,FATAL,OFF]</li> <li>▪ property <code>management_port</code> is missing</li> <li>▪ invalid value for property <code>management_port</code>, value should be integer and ( <math>\geq 1</math> &amp;&amp; <math>\leq 65535</math> )</li> <li>▪ invalid value for property <code>jks_password</code>, deobfuscation of password failed. Please make sure you are using the correct <code>config/abs_master.key</code> file</li> <li>▪ invalid value for property <code>jks_password</code>, value should be obfuscated using the 'bin/cli.sh -u admin -p &lt;password&gt; obfuscate_keys' command</li> <li>▪ invalid value for property <code>host_ip</code>, value should be string and ipv4 address</li> <li>▪ property <code>enable_emails</code> is missing</li> <li>▪ invalid value for property <code>smtp_host</code> value should be string and should be as per rfc1024 and rfc1123</li> </ul>	This message is logged in <code>abs.log</code> when: <ul style="list-style-type: none"> <li>▪ Error occurs when <code>abs.properties</code> file is not configured with <code>log_level</code> specifications</li> <li>▪ Error occurs when <code>abs.properties</code> file is not configured with <code>management_port</code> specifications</li> </ul>
error while loading <code>abs_resources.properties</code>	This message is logged in <code>abs.log</code> when <code>abs_resources.properties</code> doesn't contain values for memory and CPU parameters




Log message	Description
error while initializing mongodb replica set connections	This message is logged in <code>abs.log</code> when MongoDB initialization fails and cannot access a read or write client for connections.
error while reading enable_ssl key from mongo master	This message is logged in <code>abs.log</code> when MongoDB client tries to fetch the key from MongoDB collections.
error while reading root_api_attack key from mongo master	This message is logged in <code>abs.log</code> when MongoDB client tries to fetch the key from MongoDB collections.
error while reading <code>/config/abs.properties</code>	This message is logged in <code>abs.log</code> while loading and validating the <code>abs.properties</code> file. Check whether file exists and its permission.
invalid value for property <code>jks_password</code> , value should be obfuscated using the 'bin/cli.sh -u admin -p <password> obfuscate_keys' command	This message is logged in <code>abs.log</code> when an error occurs while deobfuscating the <code>jks_password</code> using the <code>master_key</code>
error while loading auth keys from metadata db in mongo	This message is logged in <code>abs.log</code> when MongoDB is not accessible.
error while loading restricted user auth keys from metadata db in mongo	This message is logged in <code>abs.log</code> when MongoDB is not accessible.
Unable to read <code>&lt;abs_root_dir&gt;/config/abs.jks</code> file	This message is logged in <code>abs.log</code> when <code>abs.jks</code> is not created properly or could not read the file or there is a permission issue.
error while starting management server <i>&lt;runtime exception&gt;</i>	This message is logged in <code>abs.log</code> when there is an issue when ABS starts.
API Behavioral Security stopped	This message is logged in <code>abs.log</code> when ABS is shut down.
MongoDB heartbeat failure	This message is logged in <code>abs.log</code> when ABS is unable to connect to MongoDB primary node.
ABS started successfully	This message is logged in <code>abs.log</code> when ABS starts.

## PingIntelligence Dashboard

---

PingIntelligence for APIs Dashboard provides a graphical view of an API environment. It provides insights on user activity, attack information, blocked connections, forensic data, and much more.

The following diagram shows the data flow between ASE, ABS AI Engine, and PingIntelligence Dashboard.



The Dashboard fetches data from the ABS AI engine and lets you :

- View API activity.
- View the training status and other API information.
- Organize APIs into logical groups.
- Hide or display APIs from the main API dashboard, sort and search for APIs.
- View the API dashboard.
- View attack insight to understand why a client was flagged for an attack.
- Unblock a client or tune AI engine thresholds.
- Manage API Discovery using automatic or manual mode.

## Administration

---

### Installation prerequisite

The prerequisites are divided in the following two categories:

- [Hardware and software prerequisites](#) on page 466
- [Browser support](#) on page 467

Hardware and software prerequisites

Ensure that the following prerequisites are completed before installing PingIntelligence Dashboard:

- **Server:** 8 core CPU, 16 GB RAM, 1 TB HDD
- **Operating system:** RHEL 7.9 or Ubuntu 18.0.4 LTS
- **OpenJDK:** 11.0.2 to 11.0.6
- **SSL certificate:** One private key and certificate. By default, PingIntelligence Dashboard uses the private key and certificate shipped with the binary.
- **Password:** To change the default password, set a minimum 8 character password
- **ABS:** ABS AI engine URL, access, and secret key. Make sure that ABS is reachable from PingIntelligence Dashboard.
- **ASE:** ASE management URL, access, and secret key. Make sure that ASE is reachable from the PingIntelligence Dashboard.

**Note:** Connecting Dashboard to ASE is optional. Functionality like adding discovered APIs to ASE and attack management will be limited.

**Port numbers:** The following is a list of default port numbers. Make sure that these are available for installing PingIntelligence Dashboard.

- **PingIntelligence Dashboard server:** 8030. Port number 8030 should be exposed to public internet. Make sure that your organization's firewall allow access to this port.
- **Elasticsearch:** 9200
- **Kibana:** 5601
- **H2 database:** 9092. H2 database is installed and runs as a part of PingIntelligence Dashboard.

**Operating system configurations:** Modify the following settings for the operating system:

- Increase the `ulimit` to 65536

```
# sudo sysctl -w fs.file-max=65536
# sudo sysctl -p
```

- Increase the `vm.max_map_count` limit to 262144

```
# sudo echo "vm.max_map_count=262144" >> /etc/sysctl.conf
# sudo sysctl -p
```

- **JDK installation:** Set environment variable `JAVA_HOME` to `<jdk_install_dir>` directory and add `<jdk_install_dir>/bin` to system `PATH` variable. `<jdk_install_dir>` is the directory where JDK is installed.
- Choose the `<pi_install_dir>` directory. The `<pi_install_dir>` directory is the directory where PingIntelligence Dashboard is installed. This directory should be readable and writable by the logged in user.

### Browser support

The following table shows the compatibility of PingIntelligence for APIs Dashboard with different browsers and their versions.

Operating System	Google Chrome	Mozilla Firefox	Apple Safari	Microsoft Edge
Mac OS Mojave -10.14	Version 56.0 and later	Version 69.0 and later	Version 12.0 and later	
Mac OS Sierra -10.12	Version 56.0 and later	Version 69.0 and later	Version 10.1 and later	
Mac OS High Sierra - 10.13	Version 56.0 and later	Version 69.0 and later	Version 11.1 and later	
Mac OS Catalina -10.15	Version 56.0 and later	Version 69.0 and later	Version 13.0 and later	
Windows 8.1	Version 56.0 and later	Version 69.0 and later		
Windows 10	Version 56.0 and later	Version 69.0 and later		Version 79.0 and later

## Install PingIntelligence Dashboard

Complete the following steps to install PingIntelligence Dashboard:

1. Create a `<ping_install_dir>` directory on your host machine. Make sure that the user has read and write permissions for the `<ping_install_dir>` directory.
2. [Download](#) the PingIntelligence Dashboard binary
3. [Download](#) Elasticsearch 6.8.1 (macOS/RHEL)
4. [Download](#) Kibana 6.8.1 (RHEL 64-bit)

**5. Change directory to ping\_install\_dir:**

```
# cd pi_install_dir
```

**6. Untar the PingIntelligence Dashboard:**

```
# tar -zxf pi-api-dashboard-4.4.tar.gz
```

**7. Change directory to pingidentity/webgui/**

```
# cd pingidentity/webgui/
```

**8. Install PingIntelligence Dashboard by entering the following command and follow the instructions displayed on the prompt:**

```
# ./bin/pi-install-ui.sh
```

```
elasticsearch-6.8.1.tar.gz file path >
kibana-6.8.1-linux-x86_64.tar.gz file path >

Use bundled ssl key and self signed certificate for ui server [y/n]? >[n]
ssl private key path >
ssl certificate path >

Use default password [changeme] for all components and users [y/n]? > [n]
UI login admin user 'admin' password >
Renter UI login admin user 'admin' password >
UI login regular user 'ping_user' password >
Renter UI login regular user 'ping_user' password >

ABS url >
Use default access/secret key for ABS [y/n] ? > [n]
ABS access key >
ABS secret key >

ASE management url >
Use default access/secret key for ASE [y/n] ? > [n]
ASE access key >
ASE secret key >

configuring elasticsearch... please wait for 15 seconds
elasticsearch config is completed.

configuring kibana...please wait 60 seconds
kibana config is completed.

configuring dashboard...
generating new obfuscation master key
dashboard config is completed.

configuring webgui...
generating new obfuscation master key
webgui config is completed.

saving auto generated credentials for all components to
webgui_internal.creds file

WebGUI installation completed.

Start WebGUI [y/n] > [y]
```

```

start elasticsearch...
  elasticsearch started. Log is available at elasticsearch/logs/
  elasticsearch.log

start dashboard.....
  dashboard started. Log available at dashboard/logs/dashboard.log

start kibana.....
  kibana started. Log available at kibana/logs/kibana.log

start ui server.....
  UI server started. Log available at webgui/logs/admin/admin.log

WebGUI started. Log available at webgui/logs/admin/admin.log

Please access WebGUI at https://<pi_install_host>:8030

<pi_install_host> can be ip address, hostname or fully qualified domain
name of this server.
<pi_install_host> should be reachable from your computer.

Important Action:
1) Credentials for all internal components are available in
  webgui_internal.creds file. Move this file from
  this server and securely keep it elsewhere. For any debugging purposes
  you will be asked to get
  credentials for a component from this file.
2) Two obfuscation master keys are auto-generated
  pingidentity/webgui/config/webgui_master.key
  pingidentity/dashboard/config/dashboard_master.key
3) For security purposes you should move obfuscation master keys from this
  server. But when components
  are restarted, master keys should be present at the original locations.

```

**Note:** The ASE management url is an optional parameter.

### Verify the installation

You can verify the installation by checking the process IDs (PID) of each component. You can check the pid of components at the following location:

- **Elasticsearch:** <pi\_install\_dir>/elasticsearch/logs/elasticsearch.pid
- **Kibana:** <pi\_install\_dir>/kibana/logs/kibana.pid
- **Dashboard:** <pi\_install\_dir>/dashboard/logs/dashboard.pid
- **Webgui:** <pi\_install\_dir>/webgui/logs/webgui.pid

### Tune Dashboard performance parameters

Configure the following three parameters for Dashboard's better performance. Note that the following tuning parameters if you have your setup of Elasticsearch and Kibana.

If you have used PingIntelligence automated deployment or pi-install-ui.sh script to deploy Dashboard, these tuning are done as part of installation.

Parameter	Description	Location
Elasticsearch		

Parameter	Description	Location
-Xms and -Xmx	<ul style="list-style-type: none"> <li>▪ <b>Xms</b> - Defines the minimum heap size of Elasticsearch. Set it to 4GB as <code>Xms4g</code>.</li> <li>▪ <b>Xmx</b> - Defines the maximum heap size of Elasticsearch. Set it to 4GB as <code>Xmx4g</code>.</li> </ul>	<code>\$ES_HOME/config/jvm.options</code>
<code>thread_pool.search.size</code>	Defines thread pool size for count/search/suggest operations in Elasticsearch. Configure it to 50% of total CPUs allocated.	<code>\$ES_HOME/config/elasticsearch.yml</code>
<b>Kibana</b>		
<code>elasticsearch.requestTimeout</code>	Time (in milliseconds) to wait for Elasticsearch to complete the request and return the response back to Kibana. Set the value to 60000 milliseconds.	<code>\$KIBANA_HOME/config/kibana.yml</code>

### Mitigating Cross-Site-Scripting (XSS)

To detect and mitigate attacks like Cross Site Scripting(XSS), PingIntelligence Dashboard implements Content Security Policy (CSP). The following are the configuration details.

Response header - `Content-Security-Policy`

Response header value - `default-src 'self'; font-src 'self' use.typekit.net; script-src 'self' use.typekit.net; style-src 'self' 'unsafe-inline' use.typekit.net p.typekit.net; img-src 'self' data: p.typekit.net;`

### Access PingIntelligence Dashboard

Access the PingIntelligence for APIs Dashboard from a browser at this default URL: [https://<pi\\_install\\_host>:8030](https://<pi_install_host>:8030).

#### Users

There are two pre-configured login users in PingIntelligence for APIs Dashboard :

- `admin`
- `ping_user`

Multiple users can share the `admin` and `ping_user` logins simultaneously on PingIntelligence Dashboard. The `admin` user has access to all PingIntelligence Dashboard functions. A `ping_user` can only view all the API dashboards.


At the login screen, login as `admin` or `ping_user`. The default password for both the users is `changeme`.

**CAUTION:** You must change the default password for production deployments. However, in a Docker PoC deployment use the default password.

You can change the password using the following CLI command.

```
# <pi_install_dir>/webgui/bin/cli.sh -u admin update_ui_password --username
-value <admin or ping_user> --new-password -p
Enter admin password > <current admin password>
Enter new password > <new password>
Reenter new password > <new password>
```

success: password updated.



**Note:** If the Dashboard is not accessible, check if the default port (8030) was changed by your system administrator.

PingIntelligence Dashboard is categorized into the following components:

- **Main Dashboard** - Available for `admin` and `ping_user`
- **APIs** - Available only for `admin` user
- **Discovered APIs** - Available only for `admin` user
- **Attack Management** - Available only for `admin` user
- **License**

#### Session management

The PingIntelligence Dashboard allows you to configure the maximum number of active sessions. You can set the `pi.webgui.session.max-active-sessions` parameter in the `<pi_install_dir>/webgui/config/webgui.properties` file to limit the maximum number of allowable active sessions. The default value is 50.

**Delete active sessions-** You can delete active sessions using the following CLI command. The current active users will be prompted to re-login in to the Dashboard.

```
# <pi_install_dir>/webgui/bin/cli.sh -u <username> -p <password>
delete_sessions
```

**Note:** You need to have Admin user privileges to delete active user sessions.

## Start and stop Dashboard

You can choose to start and stop all the components together or individually.

It is recommended to start and stop components together using the following command:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/start-all.sh

Starting elasticsearch.. [started]

Verifying elasticsearch connectivity.. [OK]
Verifying ABS connectivity.. [OK]

Starting dashboard.. [started]
Starting kibana.. [started]

Verifying Kibana connectivity.. [OK]
Verifying ASE connectivity.. [OK]

Starting webgui.. [started]

WebGUI started.
```

To stop all the components of PingIntelligence Dashboard together, enter the following command:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/stop-all.sh

Stopping webgui.. [stopped]
Stopping dashboard.. [stopped]
Stopping kibana.. [stopped]
Stopping elasticsearch.. [stopped]

WebGUI stopped.
```

Start and stop PingIntelligence Dashboard components individually

Start the components in the following order:

**1. Start Elasticsearch:** Enter the following command to start Elasticsearch:

```
# cd <pi_install_dir>/pingidentity/elasticsearch
# ./bin/elasticsearch -d -p logs/elasticsearch.pid
```

If Elasticsearch is running as a service, use the following command:

```
# sudo systemctl start pi-elasticsearch.service
```

**2. Start Dashboard:** Enter the following command to start Dashboard:

```
# cd <pi_install_dir>/pingidentity/dashboard
# ./bin/start.sh
```

If Dashboard is running as a service, use the following command:

```
# sudo systemctl start pi-dashboard.service
```

**3. Start Kibana:** Enter the following command to start Kibana:

```
# cd <pi_install_dir>/pingidentity/kibana
```



```
# ./bin/kibana >> ./logs/kibana.log 2>&1 & echo $! > logs/kibana.pi
```

If Kibana is running as a service, use the following command:

```
# sudo systemctl start pi-kibana.service
```

#### 4. Start Web GUI: Enter the following command to start Web GUI:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/start.sh
```

If Web GUI is running as a service, use the following command:

```
# sudo systemctl start pi-webgui.service
```

Stop the components in the following order:

#### 1. Stop Web GUI: Enter the following command to stop Web GUI:

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/stop.sh
```

If Web GUI is running as a service, use the following command:

```
# sudo systemctl stop pi-webgui.service
```

#### 2. Stop Dashboard : Stop the dashboard engine by entering the following command:

```
# cd <pi_install_dir>/pingidentity/dashboard
# ./bin/stop.sh
```

If Dashboard is running as a service, use the following command:

```
# sudo systemctl stop pi-dashboard.service
```

#### 3. Stop Kibana: Stop Kibana by entering the following command:

```
# cd <pi_install_dir>/pingidentity/kibana
# kill -9 "$(<logs/kibana.pid) "
```

If Kibana is running as a service, use the following command:

```
# sudo systemctl stop pi-kibana.service
```

#### 4. Stop Elasticsearch: Stop Elasticsearch by entering the following command:

```
# cd <pi_install_dir>/pingidentity/elasticsearch
# kill -15 "$(<logs/elasticsearch.pid) "
```

If Elasticsearch is running as a service, use the following command:

```
# sudo systemctl stop pi-elasticsearch.service
```

## Obfuscate keys and passwords

Using the PingIntelligence Dashboard command line interface, you can obfuscate the keys and passwords configured in `dashboard.properties`. The following keys and passwords are obfuscated:


- `abs.access_key`
- `abs.secret_key`

- es.password

Dashboard ships with a default `dashboard_master.key` which is used to obfuscate the keys and passwords. It is recommended to generate your own `dashboard_master.key`.

**Note:** During the process of obfuscation of keys and password, Dashboard must be stopped. For more information, see [Start and stop Dashboard](#) on page 115.

The following diagram summarizes the obfuscation process:



### Generate dashboard\_master.key

You can generate the `dashboard_master.key` by running the **generate\_obfkey** command in the Dashboard CLI:

```

/opt/pingidentity/dashboard/bin/cli.sh generate_obfkey -u admin -p
Password>

Please take a backup of config/dashboard_master.key before proceeding.

Warning: Once you create a new obfuscation master key, you should obfuscate
all config keys also using cli.sh obfuscate_keys

Warning: Obfuscation master key file /opt/pingidentity/dashboard/config/
dashboard_master.key already exist. This command will delete it create a new
key in the same file

Do you want to proceed [y/n]: y

creating new obfuscation master key
Success: created new obfuscation master key at /opt/pingidentity/dashboard/
config/dashboard_master.key
  
```

### Obfuscate key and passwords

Enter the keys and passwords in clear text in `dashboard.properties` file. Run the **obfuscate\_keys** command to obfuscate keys and passwords:

```

/opt/pingidentity/dashboard/bin/cli.sh obfuscate_keys -u admin -p
Password>

Please take a backup of config/dashboard.properties before proceeding

Enter clear text keys and password before obfuscation.

Following keys will be obfuscated
config/dashboard.properties: abs.access_key, abs.secret_key and es.password

Do you want to proceed [y/n]: y

obfuscating /opt/pingidentity/dashboard/config/dashboard.properties
  
```

```
Success: secret keys in /opt/pingidentity/dashboard/config/
dashboard.properties obfuscated
```

Start the Dashboard after passwords are obfuscated. For more information, see [Start and stop Dashboard](#) on page 115.

**i Important:** After the keys and passwords are obfuscated and the Dashboard has started, move the `dashboard_master.key` to a secure location away from the Dashboard for security reasons. Before restarting the Dashboard, the `dashboard_master.key` must be present in the `/opt/pingidentity/dashboard/config/` directory.

## Configure time zone - PingIntelligence Dashboard

This topic discusses the steps involved in configuring the timezone settings in PingIntelligence for APIs Dashboard.

You can set up the PingIntelligence Dashboard in either `local` or `utc` time zone. The Dashboard by default runs in UTC time zone. Configure the following parameters to set the time zone.

Parameter	File name	Description
<code>pi.webgui.server.timezone</code>	This parameter must be configured in <code>&lt;pi_install_dir&gt;/webgui/config/webgui.properties</code> file.	The valid values are <code>local</code> or <code>utc</code> . The default value is <code>utc</code> .
<code>dashboard.timezone</code>	This parameter must be configured in <code>&lt;pi_install_dir&gt;/dashboard/config/dashboard.properties</code> file.	The valid values are <code>local</code> or <code>utc</code> . The default value is <code>utc</code> .

Following is a snippet of `webgui.properties` for timezone parameter

```
### Timezone configuration
# valid values: local, utc
pi.webgui.server.timezone=local

<truncated webgui.properties...>
```

Following is a snippet of `dashboard.properties` for timezone parameter

```
### Timezone configuration
# valid values: local, utc
dashboard.timezone=local

<truncated dashboard.properties...>
```

**i Note:** Make sure that the time zone parameter is set to the same value in both `webgui.properties` and `dashboard.properties`. Also make sure that ASE, ABS AI Engine, and PingIntelligence for APIs Dashboard are all configured on the same timezone.

### Change PingIntelligence Dashboard time zone

To change the time zone in PingIntelligence for APIs Dashboard, complete the following steps:


1. Stop PingIntelligence for APIs Dashboard
2. Update the timezone parameters in `webgui.properties` and `dashboard.properties` files.
3. Start PingIntelligence for APIs Dashboard

**Note:** For more information, see [Start and stop Dashboard](#) on page 115.

## Configure Dashboard properties - `dashboard.properties`

The Dashboard configuration file (`dashboard.properties`) is located in the `<pi_install_dir>/dashboard/config/` directory. The following table explains the parameters and provides recommended values.

Parameter	Description
<b>ABS IP, port, log level, and JKS password</b>	
<code>abs.host</code>	ABS URL
<code>abs.port</code>	ABS port number. Default value is 8080.
<code>abs.ssl</code>	Set the value, to enable or disable SSL connection with ABS. Valid values are <code>true</code> and <code>false</code> .
<code>abs.restricted_user_access</code>	Set the value, to enable or disable restricted user access to ABS. Valid values are <code>true</code> and <code>false</code> .
<code>abs.access_key</code>	ABS access key.
<code>abs.secret_key</code>	ABS secret key.
<code>abs.query.interval</code>	ABS query polling interval in minutes. Default value is 10 minutes.
<code>abs.query.offset</code>	ABS query offset in minutes. Minimum value is 30 minutes.
<b>Publish to UI, Elasticsearch distribution type, Elasticsearch URL, Elasticsearch username, Elasticsearch password, ILM policy, Kibana version</b>	
<code>publish.ui.enable</code>	Set the value, to enable or disable publishing of attack information and other metrics to the dashboard. Valid values are <code>true</code> and <code>false</code> .
<code>es.distro.type</code>	Elasticsearch distribution type. Valid values are <code>default</code> and <code>aws</code> .
<code>es.url</code>	Elasticsearch URL.
<code>es.username</code>	The username credential to Elasticsearch.
<code>es.password</code>	The password credentials to Elasticsearch.
<code>es.index.dashboard.activity.ilm.policy</code>	Location of Index Lifecycle Management (ILM) policy. If a policy is provided, it should be a valid JSON file. It is not a mandatory policy. The default directory is <code>&lt;pi_install_dir&gt;/dashboard/config/</code> directory.

Parameter	Description
es.index.dashboard.activity.ism.policy	Location of Index State Management (ISM) policy. If a policy is provided, it should be a valid JSON file and es.distro.type should be set to <code>aws</code> . It is not a mandatory policy. The default directory is <code>&lt;pi_install_dir&gt;/dashboard/config/directory</code> .
kibana.version	Kibana version. The default value is 6.8.1.
<b>Log4j2 configuration properties</b>	
publish.log4j2.enable	Set the value, to enable publishing attack details to Log4j2. Valid values <code>true</code> or <code>false</code> . By default dashboard provides syslog support.
log4j2.config	Log4j2 configuration file to log attacks to an external service. For example, <code>Syslog</code> . Use <code>com.pingidentity.abs.publish</code> as logger name in log4j2 configuration.
log4j2.log.level	Log4j2 log level for attack logging. The default value is <code>info</code> .
log4j2.dependencies.dir	Directory for any log4j2 config dependency jar's. This is useful for third party log4j2 appenders. Default directory is <code>&lt;pi_install_dir&gt;/dashboard/plugins/</code> .
<b>Log level, Timezone configuration</b>	
dashboard.log.level	The applicable log levels. Valid values are : <code>all</code> , <code>trace</code> , <code>debug</code> , <code>info</code> , <code>warn</code> , <code>error</code> , <code>fatal</code> , <code>off</code> . Default value is <code>info</code> .
dashboard.timezone	Set timezone configuration for Dashboard. Valid values are <code>local</code> or <code>utc</code> .
<b>Dashboard fastforward properties</b>	
<p> <b>Note:</b> The properties are only applicable if dashboard is started with <code>start.sh --fast-forward</code> option.</p>	
dashboard.fastforward.earlier_time	Dashboard fast forward earlier time. Allowed format is <code>YYYY-MM-DDTHH:mm</code> .
dashboard.fastforward.later_time	Dashboard fast forward later time. Allowed format is <code>YYYY-MM-DDTHH:mm</code> .
dashboard.fastforward.query.range	Dashboard query range in minutes. It should be multiples of ten. Minimum value is ten.
dashboard.fastforward.query.cooling_period	Cooling period between each query polling batch in seconds. Minimum value is 30 seconds.

The following is a sample `dashboard.properties` file.

```
# Dashboard properties file
```

```

### ABS
# ABS Hostname/IPv4 address
abs.host=127.0.0.1
# ABS REST API port
abs.port=8080
# ABS SSL enabled ( true/false )
abs.ssl=true
# ABS Restricted user access ( true/false )
abs.restricted_user_access=false
# ABS access key
abs.access_key=OBF:AES:NuBmDdIhJM7KOB3BbXr4db5DfGJcrA==:hUsqFeTUmH5cOjiUPyws9WwTPYw9yAg
# ABS secret key
abs.secret_key=OBF:AES:NuBmDcAhXgsQu8qzJgIo1Mq97B/
PVw==:7GpDn83ZAU6GRKYsZe86x0gdnYOZfTbi8rUimDW100o=
# ABS query polling interval (minutes)
abs.query.interval=10
# ABS query offset (minutes. minimum value 30 minutes)
abs.query.offset=30

### UI
# publish attacks+metrics to UI. Valid values true or false
publish.ui.enable=true
# elasticsearch Distribution Type
# valid values are default and aws
es.distro.type=default
# elasticsearch URL
es.url=https://localhost:9200/
# elasticsearch username. User should have manage_security privilege
# If elasticsearch is NOT configured with authentication security, leave
  this blank
es.username=elastic
# elasticsearch user password
es.password=OBF:AES:NOp0PNQvc/RLUN5rbvZLtTPghqVZzD9V:
+ZGHbhpY4HENYYqJ4wn50AmoO6CZ30cfjqTYQCfGbgc=
# index lifecycle management (ILM) policy, it can be empty
# If a policy is provided, it should be a valid JSON file
es.index.dashboard.activity.ilm.policy=config/ilm.json
# index stae management (ISM) policy, it can be empty
# If a policy is provided, it should be a valid JSON file
es.index.dashboard.activity.ism.policy=config/ism.json
# kibana version
kibana.version=6.8.1

### Log4j2
# publish attacks to Log4j2. Valid values true or false
# By default it provides syslog support
publish.log4j2.enable=false
# log4j2 config file to log attacks to an external service. For example,
  Syslog
# use com.pingidentity.abs.publish as logger name in log4j2 configuration
log4j2.config=config/syslog.xml
# log4j2 log level for attack logging
log4j2.log.level=INFO
# directory for any log4j2 config dependency jar's.
# useful for third party log4j2 appenders
# it should be a directory
log4j2.dependencies.dir=plugins/

### Log level
dashboard.log.level=INFO

### Timezone configuration

```

```
# valid values: local, utc
dashboard.timezone=local

## Fastforward. Only applicable if dashboard is started with 'start.sh --
fast-forward'

# earlier time. format YYYY-MM-DDTHH:mm
# E.g 2019-07-12T10:00
dashboard.fastforward.earlier_time=2019-07-12T10:00


# later time. format YYYY-MM-DDTHH:mm
# E.g 2019-11-13T23:50
dashboard.fastforward.later_time=2019-11-13T23:50

# query range in minutes. It should be multiple of 10
# minimum value is 10
dashboard.fastforward.query.range=60

# cooling period between each query polling batch in seconds
# minimum value 30 seconds
dashboard.fastforward.query.cooling_period=60
```

## Configure WebGUI properties - webgui.properties

The WebGUI configuration file (WebGUI.properties) is located in the `<pi_install_dir>/webgui/config/` directory. The following table explains the parameters and provides recommended values.

Parameters	Description
<b>Server , timezone properties</b>	
pi.webgui.server.port	WebGUI sever port number. The default value is 8030.   <b>Note:</b> You can specify the port number as 443 to run WebGUI on HTTPS. This option is only available if WebGUI <code>start.sh</code> is executed by root user.
pi.webgui.server.timezone	The timezone configuration for WebGUI. Valid values are <code>local</code> or <code>utc</code> . The default value is <code>utc</code> .
<b>Log level, authentication mode properties</b>	
pi.webgui.admin.log.level	The applicable log levels. Valid values are : <code>all</code> , <code>trace</code> , <code>debug</code> , <code>info</code> , <code>warn</code> , <code>error</code> , <code>fatal</code> , <code>off</code> . The values are not case sensitive.
pi.webgui.server.authentication-mode	The authentication mode. Valid values are <code>native</code> or <code>sso</code> .
<b>Session properties</b>	

Parameters	Description
pi.webgui.session.max-age	<p>The maximum allowed duration for a session. After max-age duration, user will be asked to re-authenticate. The allowed format is &lt;duration number&gt;m (minutes) or &lt;duration number&gt;h (hours) or &lt;duration number&gt;d (days). For example, 20m or 20h or 20d.</p> <p><b>Note:</b> The duration value must be greater than zero.</p>
pi.webgui.session.expiry-time	The maximum duration allowed for a session to remain inactive. The value should be provided in minutes. After inactivity period, user will be asked to re-authenticate.
pi.webgui.session.max-active-sessions	The maximum number of active sessions allowed. The default value is 50.
<b>SSL properties</b>	
pi.webgui.server.ssl.enabled-protocols	The supported SSL enabled protocols. For more information, see <a href="https://docs.oracle.com/en/java/javase/11/docs/specs/security/standard-names.html#sslcontext-algorithms">https://docs.oracle.com/en/java/javase/11/docs/specs/security/standard-names.html#sslcontext-algorithms</a> . For multiple SSL protocols use comma separated list. For example, TLSv1.1,TLSv1.2.
pi.webgui.server.ssl.ciphers	The supported ssl ciphers. For the list of valid cipher names, see <a href="https://docs.oracle.com/en/java/javase/11/docs/specs/security/standard-names.html#jsse-cipher-suite-names">https://docs.oracle.com/en/java/javase/11/docs/specs/security/standard-names.html#jsse-cipher-suite-names</a> . For multiple cipher names use comma separated list. For example, TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_DHE_RS
pi.webgui.server.ssl.key-store	The SSL server keystore location value. For JKS keystore, keystore password and private key password should be same when you generate a JKS keystore.
pi.webgui.server.ssl.key-store-type	The SSL keystore type. The default value is <code>JKS</code> .
pi.webgui.server.ssl.key-store-password	The password credentials to SSL keystore.
pi.webgui.server.ssl.key-alias	Alias for SSL key. Default value is <code>PingIntelligence</code> .
<b>ABS properties</b>	
pi.webgui.abs.url	ABS URL
pi.webgui.abs.access-key	ABS access key.
pi.webgui.abs.secret-key	ABS secret key.
<b>ASE properties</b>	



Parameters	Description
pi.webgui.ase.url	ASE Management URL value.  <b>Note:</b> The ASE management URL is an optional parameter.
pi.webgui.ase.mode	ASE deployment mode. Valid values are <code>inline</code> or <code>sideband</code> . When PingIntelligence is deployed on cloud, the default value is <code>inline</code> .
pi.webgui.ase.access-key	ASE access key.
pi.webgui.ase.secret-key	ASE secret key.
<b>Kibana properties</b>	
pi.webgui.dashboard.url	The Kibana URL.
pi.webgui.dashboard.username	The Kibana username credentials.
pi.webgui.dashboard.password	The Kibana password credentials.
<b>Elasticsearch properties</b>	
pi.webgui.elasticsearch.url	Elasticsearch URL.
pi.webgui.elasticsearch.username	The username credential to Elasticsearch.
pi.webgui.elasticsearch.password	The password credentials to Elasticsearch.
pi.webgui.elasticsearch.distro-type	Elasticsearch distribution type. Valid values are <code>default</code> and <code>aws</code> .
<b>API discovery properties</b>	
pi.webgui.discovery.source	Source for API discovery. Valid values are <code>abs</code> , <code>axway</code> , and <code>pingaccess</code> .
<b>Indicators of Attack (IoA) listing properties</b>	
pi.webgui.ioclisting.fetchsize	The limit of documents that can be pulled from Elasticsearch. The default value is 2000. The upper limit is 10000.
<b>h2 database properties</b>	
pi.webgui.datasource.url	h2 database URL. The database is started on default port number 9092. Total number of documents that can be fetched in an Elasticsearch search query to list IoAs for different client identifier types.
pi.webgui.datasource.username	Username credentials to h2 database.
pi.webgui.datasource.password	Password to h2 database.
pi.webgui.datasource.encryption-password	Password to encrypt h2 database.

Parameters	Description
<p><b>Note:</b></p> <p>The h2 database will use the properties when it is first started. If you want to change them, stop webgui server and delete <code>data/h2</code> directory and start again. When you delete <code>data/h2</code> directory, WebGUI is reset. The login passwords, login sessions, and api state information is lost when the WebGUI is reset.</p>	
<b>Connection timeout properties</b>	
<code>pi.webgui.http-client.timeout</code>	Total number of documents that can be fetched in an Elasticsearch TCP connection timeout value in milliseconds. Timeout after which TCP connection to ABS, ASE, Dashboard, ElasticSearch is closed by the WebGUI.
<code>pi.webgui.http-client.socket-timeout</code>	Socket timeout value in milliseconds. Timeout after which socket to ABS, ASE, Dashboard, ElasticSearch is closed by the WebGUI.
<b>JDK truststore properties</b>	
<code>pi.webgui.jdk.truststore</code>	The location of JDK truststore. The default value is <code>\$JAVA_HOME/lib/security/cacerts</code> .
<code>pi.webgui.jdk.truststore-password</code>	The password to JDK truststore.
<p><b>Note:</b> Configure the values of JDK truststore and its password only if the defaults don't match.</p>	
<b>HTTP client connection properties</b>	
<code>pi.webgui.http-client.max-connections</code>	Maximum allowed HTTP connections
<code>pi.webgui.http-client.request-timeout</code>	Request timeout for the HTTP clients.
<code>pi.webgui.http-client.keep-alive-time</code>	Connection keep-alive time
<code>pi.webgui.http-client.idle-time</code>	HTTP client idle time

A sample `webgui.properties` file is displayed here.

```
#### PingIntelligence WebGUI properties file
# This is in standard java properties file format
# comments are denoted by number sign (#) as the first non blank character
# multiline values are ended with '\' as end of line

### server listening port
# server listens on 0.0.0.0 ( all interfaces )
# server enables only https(ssl) on this port
pi.webgui.server.port=8030

### Timezone configuration
# valid values: local, utc
pi.webgui.server.timezone=utc

### log level
# valid values: ALL, TRACE, DEBUG, INFO, WARN, ERROR, FATAL, OFF
# filtering sequence: ALL > TRACE > DEBUG > INFO > WARN > ERROR > FATAL >
OFF
# higher level in the sequence will allow all the lower level log messages
```

```

# case insensitive
pi.webgui.admin.log.level=INFO

### Authentication mode
# valid values: native, sso
pi.webgui.server.authentication-mode=native

### ui login session
# maximum duration of a session
# after max-age duration, user will be asked to re-authenticate
# format: <duration>m (minutes) /h (hours) /d (days)
# duration should be > 5 minutes
pi.webgui.session.max-age=6h

# maximum session inactivity duration( No requests from the session ). In
  minutes
# after inactivity period, user will be asked to re-authenticate
pi.webgui.session.expiry-time=30

# maximum active sessions allowed
pi.webgui.session.max-active-sessions=50

### server ssl properties
# ssl enabled protocols ( https://docs.oracle.com/en/java/javase/11/docs/
  specs/security/standard-names.html#sslcontext-algorithms)
# for multiple SSL protocols use comma separated list. e.g TLSv1.1,TLSv1.2
pi.webgui.server.ssl.enabled-protocols=TLSv1.2

# supported ssl ciphers
# valid cipher names: https://docs.oracle.com/en/java/javase/11/docs/specs/
  security/standard-names.html#jsse-cipher-suite-names
# for multiple cipher names use comma separated list. e.g
  TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_DHE_RSA_WITH_AES_256_CBC_SHA256
pi.webgui.server.ssl.ciphers=TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,
  \
  TLS_RSA_WITH_AES_256_CBC_SHA256,TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384,TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384,
  \
  TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA,TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA,TLS_ECDH_RSA_WITH_AES_256_CBC_SHA,
  \
  TLS_ECDH_RSA_WITH_AES_256_CBC_SHA384,TLS_ECDH_RSA_WITH_AES_256_CBC_SHA,TLS_ECDH_ECDSA_WITH_AES_256_CBC_SHA,
  \
  TLS_RSA_WITH_AES_128_GCM_SHA256,TLS_RSA_WITH_AES_128_CBC_SHA256,TLS_RSA_WITH_AES_128_CBC_SHA,
  \
  TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256,TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA,TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA,
  \
  TLS_ECDH_RSA_WITH_AES_128_CBC_SHA256,TLS_ECDH_RSA_WITH_AES_128_CBC_SHA,TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA,

## server ssl keystore
# for JKS keystore, keystore password and private key password should be
  same when you generate a jks keystore.
pi.webgui.server.ssl.key-store=config/webgui.jks
pi.webgui.server.ssl.key-store-type=JKS
pi.webgui.server.ssl.key-store-password=OBF:AES:NOp0PNQvc/
  RLUN5rbvZLTpghqVZzD9V:+ZGHbhpY4HENYqJ4wn50AmoO6CZ3OcfjqTYQCfBgBgc=
pi.webgui.server.ssl.key-alias=PingIntelligence

### abs properties
pi.webgui.abs.url=https://localhost:8080
pi.webgui.abs.access-
  key=OBF:AES:NuBmDdIhJM7KOB3BbXr4db5DfGJcrA==:hUsqFeTUmH5cOjiUPyws9WwTPYw9yAg0C1X1HSmSI3
pi.webgui.abs.secret-key=OBF:AES:NuBmDcAhXgsQu8qzJgIo1Mq97B/
  PVw==:7GpDn83ZAU6GRKYsZe86x0gdnYOZfTbi8rUimDW100o=

### ase properties

```

```

# ASE management url
pi.webgui.ase.url=https://localhost:8010
# ASE mode: valid values: inline or sideband
pi.webgui.ase.mode=inline
pi.webgui.ase.access-key=OBF:AES:NuZ4O93cWBKyKDFOZFINHeBew8sQ:eu//
E2CIObNNGvFOfHrLuAuec4WvN4yZsThAea4iBLA=
pi.webgui.ase.secret-key=OBF:AES:NuZ4O93cWBKyKDFOZFINHeBew8sQ:eu//
E2CIObNNGvFOfHrLuAuec4WvN4yZsThAea4iBLA=

### kibana rendering ( dashboard ) properties
pi.webgui.dashboard.url=https://localhost:5601
pi.webgui.dashboard.username=ping_user
pi.webgui.dashboard.password=OBF:AES:NOp0PNQvc/RLUN5rbvZLtTPghqVZzD9V:
+ZGHbhpY4HENYYqJ4wn50AmoO6CZ30cfjqTYQCfGbgc=

### elasticsearch properties
pi.webgui.elasticsearch.url=https://localhost:9200
pi.webgui.elasticsearch.username=elastic
pi.webgui.elasticsearch.password=OBF:AES:NOp0PNQvc/RLUN5rbvZLtTPghqVZzD9V:
+ZGHbhpY4HENYYqJ4wn50AmoO6CZ30cfjqTYQCfGbgc=
# ES distribution type
# valid values: default, aws
pi.webgui.elasticsearch.distro-type=default

### api discovery properties
# discovery source
# valid values: abs, axway and pingaccess
# for axway and pingaccess, see config/discovery.properties
pi.webgui.discovery.source=abs

### ioc listing properties
# total number of documents that can be fetched in an elasticsearch search
# query to list iocs for different client identifier types.
pi.webgui.ioclisting.fetchsize=2000

### server internal configurations

## local h2 db datasource properties
# h2 db is started on default port 9092
pi.webgui.datasource.url=jdbc:h2:ssl://localhost/webgui_data;CIPHER=AES

# h2 db will use following properties when it is first started. There is no
way to change it afterwards
# If you want to change it, you should stop webgui server and delete data/h2
directory and start again.
# when you delete data/h2 directory, webgui is reset. you will loose login
passwords/login sessions/api state info.
pi.webgui.datasource.username=sa
pi.webgui.datasource.password=OBF:AES:NOp0PNQvc/RLUN5rbvZLtTPghqVZzD9V:
+ZGHbhpY4HENYYqJ4wn50AmoO6CZ30cfjqTYQCfGbgc=
pi.webgui.datasource.encryption-password=OBF:AES:NOp0PNQvc/
RLUN5rbvZLtTPghqVZzD9V:+ZGHbhpY4HENYYqJ4wn50AmoO6CZ30cfjqTYQCfGbgc=

### server to abs/ase/dashboard http connection properties
# tcp connect timeout in milliseconds
pi.webgui.http-client.timeout=15000
# timeout after which socket to abs/ase/dashboard/elasticsearch is closed by
the webgui
pi.webgui.http-client.socket-timeout=120000

## http client connection pool configurations
pi.webgui.http-client.max-connections=256
pi.webgui.http-client.request-timeout=30000
pi.webgui.http-client.keep-alive-time=120000

```

```
pi.webgui.http-client.idle-time=120000
```

## Configure dashboard engine

When you install the PingIntelligence Dashboard, the on-prompt installation steps asks for configuration values including, access and secret key, ABS and ASE URL and so on. These values after installation are populated in the `<pi_install_dir>/dashboard/config/dashboard.properties` file. To change these values, stop the dashboard engine, edit the `dashboard.properties` file and then start the dashboard engine. See, [Start and stop Dashboard](#) on page 115 on how to start and stop each component individually.

```
# Dashboard properties file


### ABS
# ABS Hostname/IPv4 address
abs.host=127.0.0.1
# ABS REST API port
abs.port=8080
# ABS SSL enabled ( true/false )
abs.ssl=true
# ABS Restricted user access ( true/false )
abs.restricted_user_access=true
# ABS access key
abs.access_key=OBF:AES:NuBmDdIhQeNlRtU8SMKMoLaSpJviT4kArw==:HHuA9sAPDiOen3VU
+qp6kMrkgNjAwnKO6aa8pMuZkQw=
# ABS secret key
abs.secret_key=OBF:AES:NuBmDcAhQeNlPBDmyxX+685CBe8c3/STVA==:BIfH
+FKmL5cNaIDrfVuyc5hIYjimqh7Rnf3bv9hW0+4=
# ABS query polling interval (minutes)
abs.query.interval=10
# ABS query offset (minutes. minimum value 30 minutes)
abs.query.offset=30

### UI
# publish attacks+metrics to UI. Valid values true or false
publish.ui.enable=true
# elasticsearch URL
es.url=https://localhost:9200/
# elasticsearch username. User should have manage_security privilege
es.username=elastic
# elasticsearch user password
es.password=OBF:AES:NOp0PNQvc/RLUN5rbvZLtTPghqVZzD9V:
+ZGHbhpY4HENYYqJ4wn50AmoO6CZ3OcfjqTYQCfGbgc=
# kibana version
kibana.version=6.8.1

### Log4j2
# publish attacks to Log4j2. Valid values true or false
# By default it provides syslog support
publish.log4j2.enable=false
# log4j2 config file to log attacks to an external service. For example,
  Syslog
# use com.pingidentity.abs.publish as logger name in log4j2 configuration
log4j2.config=config/syslog.xml
# log4j2 log level for attack logging
log4j2.log.level=INFO
# directory for any log4j2 config dependency jar's.
# useful for third party log4j2 appenders
# it should be a directory
log4j2.dependencies.dir=plugins/
```

```
### Log level
dashboard.log.level=INFO
```

The following table describes all the parameters in the `dashboard.properties` file:

Parameter	Description
<b>ABS</b>	
<code>abs.host</code>	IP address of the ABS server
	<div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b> Two options exist to choose an ABS server: 1) Utilize an existing ABS server. 2) For production deployments, Ping Identity recommends dedicating an exclusive <a href="#">ABS reporting node</a>.</p> </div>
<code>abs.port</code>	REST API port number of the ABS host – See <code>abs.properties</code> Default value is 8080
<code>abs.ssl</code>	Setting the value to <code>true</code> ensures SSL communication between ABS and dashboard engine.
<code>abs.restricted_user</code>	When set to <code>true</code> , Elasticsearch uses the restricted user header (configured in <code>pingidentity/abs/mongo/abs_init.js</code> file) to fetch the obfuscated values of OAuth token, cookie and API keys. When set to <code>false</code> , the admin user header is used to fetch the data in plain text. For more information on admin and restricted user header, see <a href="#">ABS users for API reports</a>
<code>abs.access_key</code>	Access key from ABS – See <code>pingidentity/abs/mongo/abs_init.js</code> . Make sure to enter the access key based on the value set in the previous variable. For example, if <code>abs.restricted_user</code> is set to <code>true</code> , then enter the access key for restricted user. If <code>abs.restricted_user</code> is set to <code>false</code> , then use the access key for the admin user.
<code>abs.secret_key</code>	Secret key from ABS – See <code>pingidentity/abs/mongo/abs_init.js</code> . Make sure to enter the secret key based on the value set in the previous variable. For example, if <code>abs.restricted_user</code> is set to <code>true</code> , then enter the secret key for restricted user. If <code>abs.restricted_user</code> is set to <code>false</code> , then use the secret key for the admin user.
<code>abs.query.interval</code>	Polling interval to fetch data from ABS. The default is 10 minutes
<code>abs.query.offset</code>	The time required by ABS to process access logs and generate result. The minimum and default value is 30-minutes.
<b>UI</b>	
<code>publish.ui.enable</code>	Set it to <code>true</code> to display PingIntelligence Dashboard. The Dashboard displays attack and metrics data. Set it to <code>false</code> , if you do not want to display the Dashboard.
<code>es.url</code>	Elasticsearch URL
<code>es.username</code>	Elasticsearch username
<code>es.password</code>	Elasticsearch password.
<code>kibana.version</code>	Kibana version - default is 6.8.1


dashboard.log.level	Log level for Dashboard Default log level is <code>INFO</code> . Another log level is <code>DEBUG</code>
<b>Log4j</b>	
publish.log4j2.enable	Set it to <code>true</code> to send attack data to syslog server. Set it to <code>false</code> to disable sending attack data to syslog server.
<div style="border: 1px solid black; padding: 5px;"> <p><span style="border: 1px solid black; border-radius: 50%; padding: 2px;">i</span> <b>Note:</b> Dashboard and Syslog cannot be disabled together.</p> </div>	
log4j2.config	The log4j2 config file which logs the attack data.
log4j2.log.level	Log level for log4j. Default log level is <code>INFO</code> .
log4j2.dependencies.dir	The directory for any log4j configuration dependency. Make sure that it is a directory.

### Dashboard engine fast forward

Start PingIntelligence Dashboard in fast-forward mode to populate the Dashboard with historical data. Possible scenarios in which running Dashboard in fast-forward mode is useful are:

- Elasticsearch data was accidentally deleted, and you want to repopulate the Dashboard.
- The Dashboard was not available for a specific duration of time, and you wish to fetch the data for that time duration.
- The Dashboard was installed after the other PingIntelligence components were deployed, and you want to populate the Dashboard with data from when PingIntelligence was first started.

The following diagrams summarize the use case for Dashboard's fast-forward



### Missing data in Elasticsearch

mode:

When you run Dashboard in fast-forward mode, it fetches data from a time frame you define in `YYYY-MM-DDTHH:mm` format in the `dashboard.properties` file. For example, if you want to fetch data from January 1, 2019 01:00 to March 31, 2019 23:00, then `earlier-date` in `dashboard.properties` would be `2019-01-01T01:00` and `later-date` would be `2019-03-31T23:00`.

Dashboard stops querying the AI engine when its query reaches the later date. The Dashboard stopping time is logged in the `logs/dashboard_fastforward.log` file along with the other Dashboard activities. The `logs/dashboard_fastforward.log` file is rotated every 24-hours. You can see the data visualization of the specified period in the Dashboard UI already running.

**i Attention:** If your current Dashboard engine is running in `/opt/pingidentity/dashboard/`, make sure that you use a different directory to run Dashboard in fast-forward mode, for example, `/opt/pingidentity/dashboard_fast_forward/`.

Copy the Dashboard binary and configure the `dashboard.properties` file with `earlier-date` and `later-date` in the `Fastforward` section of the properties file. The following table shows the available parameters for Dashboard fast-forward mode.

Parameter	Description
<code>dashboard.fastforward.earlier_time</code>	The query start date and time in YYYY-DD-MMTHH:mm format.
<code>dashboard.fastforward.later_time</code>	The query end date and time in YYYY-DD-MMTHH:mm format.
<code>dashboard.fastforward.query.range</code>	The time in minutes that Dashboard queries the AI engine in a single pass.
<code>dashboard.fastforward.query.cooling_period</code>	The time in seconds between two Dashboard queries to the AI engine. The minimum and the default value is 60 seconds.

The following is an example of the `Fastforward` section of the `dashboard.properties` file.

```
## Fastforward. Only applicable if dashboard is started with 'start.sh --
fast-forward'

# earlier time. format YYYY-MM-DDTHH:mm
# E.g 2019-07-12T10:00
dashboard.fastforward.earlier_time=2019-07-12T10:00

# later time. format YYYY-MM-DDTHH:mm
# E.g 2019-11-13T23:50
dashboard.fastforward.later_time=2019-11-13T23:50

# query range in minutes. It should be multiple of 10
# minimum value is 10
dashboard.fastforward.query.range=60

# cooling period between each query polling batch in seconds
dashboard.fastforward.query.cooling_period=60
```

### Start dashboard engine in fast-forward mode

Install a new instance of dashboard binary in a different directory in `/opt/pingidentity/`, for example, `/opt/pingidentity/dashboard_fast_forward`. Enter the following command to start Dashboard in fast-forward mode:

```
# /opt/pingidentity/dashboard_fast_forward/bin/start.sh --fast-forward
starting Dashboard Fastforward 4.1
```

### Configure dashboard engine for syslog

PingIntelligence dashboard engine supports sending attack information to a `syslog` server. Enable `syslog` support by editing the `dashboard.properties` file. By default `syslog` is disabled. Dashboard uses Log4j version 2.11.2 to publish attack data to `syslog`.



Following is a snippet of `dashboard.properties` with `syslog` enabled.

```
### Log4j2
# publish attacks to Log4j2. Valid values true or false
# By default it provides syslog support
publish.log4j2.enable=true
# log4j2 config file to log attacks to an external service. For example,
  Syslog
# use com.pingidentity.abs.publish as logger name in log4j2 configuration
log4j2.config=config/syslog.xml

# log4j2 log level for attack logging
log4j2.log.level=INFO
# directory for any log4j2 config dependency jar's.
# useful for third party log4j2 appenders
# it should be a directory
log4j2.dependencies.dir=plugins/
```

The attack data is published to a Log4j logger named `com.pingidentity.abs.publish`. The Log4j configuration file must have a logger named `com.pingidentity.abs.publish`. Any Log4j2 config file that wants to capture attack data from Dashboard must have at least one logger with name `com.pingidentity.abs.publish`.

PingIntelligence Dashboard ships with a `syslog.xml` and `attack_log.xml` file in the Dashboard config directory. The config file supports other formats available with Log4j including `.properties`, `.json`, or `.yaml`.

### syslog.xml

Following is a snippet of the `syslog.xml` file.

```
<?xml version="1.0" encoding="UTF-8"?>
<Configuration status="warn" name="APIIntelligence" packages="">
  <Appenders>
    <!--<Syslog name="bsd" host="localhost" port="514" protocol="TCP"
      ignoreExceptions="false" immediateFlush="true" />-->
    <Syslog name="RFC5424" host="localhost" port="614" protocol="TCP"
      format="RFC5424" appName="APIIntelligence" mdcId="mdc"
      facility="LOCAL0" enterpriseNumber="18060" newLine="true"
      messageId="Audit" id="App" ignoreExceptions="false"
      immediateFlush="true"/>
  </Appenders>
  <Loggers>
    <Logger name="com.pingidentity.abs.publish" level="info" additivity="false">
      <AppenderRef ref="RFC5424"/>
    </Logger>
  </Loggers>
</Configuration>
```

### Configure server and port number of syslog server

Configure the server and port number of syslog server in `config/syslog.xml` file. Following is a snippet of the `syslog.xml` file displaying the server and port number parameters:

```
<!-- ### Syslog RFC5424 format, TCP -->
  <Syslog name="TCP_RFC5424"
    host="localhost"
    port="614"
    appName="APIIntelligence"
    id="App"
    enterpriseNumber="18060"
    facility="LOCAL0"
```

```
messageId="Audit"
format="RFC5424"
newLine="true"
protocol="TCP"
ignoreExceptions="false"
mdcId="mdc" immediateFail="false" immediateFlush="true"
connectTimeoutMillis="30000" reconnectionDelayMillis="5000"/>
```

## Configure authentication - SSO with PingFederate

PingIntelligence for APIs Dashboard provides two methods for user authentication: native or single sign-on (SSO).

You can configure the authentication method by configuring `pi.webgui.server.authentication-mode` property in the `<pi_install_dir>/pingidentity/webgui/config/webgui.properties` file. The default authentication method is `native`.

### Note:

SSO authentication should be used only for production deployments. Use native authentication for PoC deployments.

### SSO configuration for PingIntelligence for APIs Dashboard

SSO configuration for PingIntelligence Dashboard involves configuring both Dashboard and PingFederate. The following is a summary of configuration steps:

1. Verify the prerequisites.
2. Configure an OAuth client in PingFederate.
3. Configure the `webgui.properties` file.
4. Configure the `sso.properties` file in Dashboard.
5. Import the PingFederate SSL server certificate.
6. Obfuscate `sso.properties`.
7. Start Dashboard.

### Verify the prerequisites

Ensure the following prerequisites are complete before SSO configuration:

- PingFederate is installed and configured to support OIDC SSO for any client. The current supported PingFederate versions are 9.3 or 10.1.
- PingIntelligence for APIs Dashboard is installed.

### Configure OAuth client in PingFederate

Creating and configuring an OAuth client in PingFederate is an essential step for PingIntelligence Dashboard's SSO authentication. If the OAuth client is not correctly configured in PingFederate, it results in authentication failure. To configure an OAuth client, complete the steps in [Configuring an OAuth client in PingFederate for PingIntelligence Dashboard SSO](#) on page 492 .

### Configure `webgui.properties` file

Edit the `<pi_install_dir>/pingidentity/webgui/config/webgui.properties` to set the value of `pi.webgui.server.authentication-mode` to `sso` to configure authentication using SSO.

```
### Authentication mode
# valid values: native, sso
```

**pi.webgui.server.authentication-mode=sso**

Configure SSO properties file in Dashboard

Configure the `<pi_install_dir>/pingidentity/webgui/sso.properties` file to complete the PingIntelligence Dashboard's SSO authentication. For more information, see [Configuring Dashboard sso.properties for PingFederate](#) on page 494.

Import the PingFederate SSL server certificate

After the PingIntelligence Dashboard configuration for SSO is complete, import the PingFederate's SSL server certificate to the PingIntelligence Dashboard's truststore `<pi_install_dir>/pingidentity/webgui/config/webgui.jks`.

Complete the following steps to import SSL certificate:

1. Copy Pingfederate's SSL server certificate to `<pi_install_dir>/pingidentity/webgui/config/` directory
2. Execute the following command.

```
# cd <pi_install_dir>/pingidentity/webgui/config/
keytool -import -trustcacerts -file <pf_certificate.crt> -alias pi-sso -
keystore webgui.jks
```

**Note:**

The default password to import `pf_certificate.crt` to `webgui.jks` is `changeme`.

Obfuscate sso.properties

You can obfuscate keys added in SSO properties using the following commands.

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/cli.sh obfuscate_keys
```

Start PingIntelligence for APIs Dashboard


Start the PingIntelligence for APIs Dashboard. For more information, see [Start and stop Dashboard](#) on page 115.

When the PingIntelligence Dashboard is started successfully, access it using `https://<pi_install_host>:8030`. The Dashboard will start SSO Authentication, and a new session will get created for the logged-in users.

**Note:**

Every PingIntelligence Dashboard SSO authentication event is attached with a unique ID, which is logged in `<pi_install_dir>/pingidentity/webgui/logs/admin/sso.log`.

If SSO authentication fails for any reason, PingIntelligence Dashboard shows the following error message.



**Note:**

You can filter `sso-event-ref = <unique ID>` in the `<pi_install_dir>/pingidentity/webgui/logs/admin/sso.log` file to find the reason for SSO failure.

### Configuring an OAuth client in PingFederate for PingIntelligence Dashboard SSO

Configure an OAuth client in PingFederate for PingIntelligence Dashboard single sign-on (SSO).

About this task

For more information on creating and configuring an OAuth client in PingFederate, see [Managing OAuth clients](#).

#### Steps

- Create and configure an OAuth client in PingFederate with the following configuration details.

Option	Description
<b>Client ID</b>	Create an OAuth client in PingFederate with Client ID as PingIntelligence. You can use any other value for Client ID in place of PingIntelligence.
<b>Client Authentication</b>	<p>The current release of PingIntelligence Dashboard supports NONE and CLIENT SECRET authentication methods.</p> <p>Client TLS Certificate authentication and Private Key JWT based authentication are not supported by the Dashboard.</p> <p>When CLIENT SECRET is selected as the client authentication method, you can generate a random client secret or use a custom secret, which is used by PingIntelligence Dashboard for client authentication.</p>

Option	Description
<b>Require Signed Request</b>	Do not enable.
	<p><b>i Important:</b></p> <p>PingIntelligence Dashboard does not support signed requests.</p>
<b>Redirection URIs</b>	<p>Set the redirection URI in the PingFederate OAuth client configuration. The path in the URI is as follows: <code>https://pi_install_host:8030/login/oauth2/code/PingIntelligence</code>.</p> <p>Do not change the path in the URI, just substitute the hostname. For example, <code>https://172.16.40.180:8030/login/oauth2/code/PingIntelligence</code>.</p>
<b>Claims</b>	<p>The following Claims must be configured in PingFederate, and are mandatory for a successful authentication of a logged in user in PingIntelligence Dashboard.</p> <ul style="list-style-type: none"> <li>▪ A Claim for Subject Identifier, which should provide the unique identifier for the logged in user.</li> <li>▪ A Claim for providing First Name.</li> <li>▪ A Claim for providing Last Name.</li> <li>▪ A Claim for providing the Role information.</li> </ul> <p><b>i Note:</b></p> <p>PingIntelligence Dashboard fetches the claims for an authenticated User from the PingFederate UserInfo endpoint.</p> <p>In PingIntelligence 4.4, the supported values for the Role Claim are ADMIN and REGULAR. They are case-sensitive, if a blank or any other value is configured, SSO will fail. Roles assigned to Users with in an enterprise should be mapped to ADMIN or REGULAR.</p> <p>PingIntelligence 4.4.1 and later versions support both single or multiple values for the Role Claim. If you are configuring the Role Claim with a single value then the allowed values are ADMIN and REGULAR and they are case-sensitive.</p> <p>If multiple values are sent, then one of the values must end with either of the following, and the values are not case-sensitive:</p> <ul style="list-style-type: none"> <li>▪ <i>Ping-Dashboard-Admin</i></li> <li>▪ <i>Ping-Dashboard-Regular</i></li> </ul>

Option	Description
	If multiple values are configured for the Role Claim and one of them is an Admin role, then the Admin role takes a precedence.
<b>Scopes</b>	<p>The Scopes required to be configured in PingFederate for PingIntelligence Dashboard application are:</p> <ul style="list-style-type: none"> <li>▪ Mandatory Scopes- <code>profile</code> and <code>openid</code></li> <li>▪ Additional Scopes</li> </ul> <p><b>Note:</b> The Claims configured for PingIntelligence Dashboard can be mapped to the Mandatory Scope <code>profile</code> or to one or more Additional Scopes.</p>
<b>Allowed Grant Types</b>	Enable Authorization Code. PingIntelligence Dashboard supports only Authorization Code as the grant type.
<b>Restrict Response Types</b>	If enabled, select <code>code</code> .
<b>Proof Key For Code Exchange (PKCE)</b>	<p>Do not enable.</p> <p><b>Important:</b> PingIntelligence Dashboard does not support PKCE.</p>
<b>ID Token Signing Algorithm</b>	<p>The supported ID Token Signing Algorithms are:</p> <ul style="list-style-type: none"> <li>▪ Default</li> <li>▪ RSA using SHA-256</li> </ul>
<b>ID Token Key Management Encryption Algorithm</b>	Select <b>No Encryption</b> because encryption is not supported by PingIntelligence Dashboard.

### Configuring Dashboard `sso.properties` for PingFederate

To complete the Dashboard's SSO authentication, configure the `<installation_path>/pingidentity/webgui/sso.properties` file.

The following table describes the SSO properties.

Property	Description
pi.webgui.sso.oidc.provider.issuer-uri	<p>Configure the URI of the OIDC service provider (PingFederate). For example, <code>pi.webgui.sso.oidc.provider.issuer-uri=https://pf_installed_host:9031</code>.</p> <p>Dashboard retrieves the PingFederate OpenID Provider configuration using the following URL:  <code>&lt;pi.webgui.sso.oidc.provider.issuer-uri&gt;/.well-known/openid-configuration</code>.</p> <p><b>Note:</b> This is a mandatory property.</p>
pi.webgui.sso.oidc.client.id	<p>Configure the OIDC client ID. The default value is <code>PingIntelligence</code>. Make sure to configure the same value in PingFederate. If you want to change the default value, change the client ID in PingFederate as well. For more information, see <a href="#">Configuring an OAuth client in PingFederate for PingIntelligence Dashboard SSO</a> on page 492.</p> <p><b>Note:</b> This is a mandatory property.</p>
pi.webgui.sso.oidc.client.secret	<p>Set the client secret value in plain-text of the OAuth client created for Dashboard application in PingFederate. The secret value is obfuscated in Dashboard. The default value configured in <code>sso.properties</code> is <code>changeme</code>.</p> <p><b>Note:</b> This is a required property only if the value of the property <b>pi.webgui.sso.oidc.client.authentication-method</b> is not set to <code>NONE</code>.</p>
pi.webgui.sso.oidc.client.authentication-method	<p>Configure the OIDC client authentication method. The possible values are:</p> <ul style="list-style-type: none"> <li>▪ <code>BASIC</code> - Basic authentication header based client authentication</li> <li>▪ <code>POST</code> - Client credentials sent in POST body for authentication</li> <li>▪ <code>NONE</code> - Client does not authenticate itself</li> </ul> <p>The default value is <code>BASIC</code>.</p> <p><b>Note:</b> If Client Authentication configuration in the OAuth client created in PingFederate is set to <code>NONE</code>, then use <code>NONE</code> for this property. If Client Authentication is set to <code>CLIENT SECRET</code>, use <code>BASIC</code> or <code>POST</code>. This is a mandatory property.</p>

Property	Description
pi.webgui.sso.oidc.provider.user-uniqueid-claim-name	<p>The value of this property should be the claim name that holds the unique value to identify the signed-on user. It provisions a new user in Dashboard data source or updates the user if it already exists with updated claim, if any. The default value in Dashboard is <code>sub</code>.</p> <p><b>Note:</b> This is a mandatory property.</p>
pi.webgui.sso.oidc.provider.user-first-name-claim-name	<p>The value of this property should be the claim name that holds the first name of the signed-on user.</p> <p>The default value for the claim is <code>given_name</code>.</p> <p>If you configure any other non-standard claim to send the value of first name in UserInfo, the name of that claim should be configured in Dashboard properties as follows.</p> <pre>pi.webgui.sso.oidc.provider.user-first-name-claim-name=my_first_name_claim</pre> <p><b>Note:</b> This is a mandatory property.</p>
pi.webgui.sso.oidc.provider.user-last-name-claim-name	<p>The value of this property should be a claim name that holds the last name of the signed-on user.</p> <p>The default value for the claim is <code>family_name</code>.</p> <p>If you configure any other non-standard claim to send the value of last name in UserInfo, the name of that claim should be configured in Dashboard properties as follows.</p> <pre>pi.webgui.sso.oidc.provider.user-last-name-claim-name=my_last_name_claim</pre> <p><b>Note:</b> This is a mandatory property.</p>



Property	Description
pi.webgui.sso.oidc.provider.user-role-claim-name	<p>The value of this property should be a claim name that holds the value of the role of the signed-on user.</p> <p>The default value in Dashboard is <code>role</code>.</p> <p>If the user uses a different claim name in PingFederate to send the role value, the same should be updated in this property. For example, <code>pi.webgui.sso.oidc.provider.user-role-claim-name=my_role_claim_name</code>.</p>
	<p><b>Note:</b></p> <p>This is a mandatory property.</p>
pi.webgui.sso.oidc.client.additional-scopes	<p>The value of this property should be any additional scopes (comma separated) that need to be passed in the authorization request if required by the enterprise for retrieving the role claim. For example, <code>pi.webgui.sso.oidc.client.additional-scopes=read,read_role</code>.</p> <p>Such scopes, if any, should be created in PingFederate and attached to the OAuth client created in PingFederate for Dashboard and configured to return the role claim for authorization in Dashboard. This is not a mandatory property.</p>

The following is a sample snippet of `sso.properties`.

```
#### PingIntelligence WebGUI SSO properties file
# This is in standard java properties file format
# comments are denoted by number sign (#) as the first non blank
  character
# multiline values are ended with '\n' as end of line

# OIDC Provider uri
# WebGUI queries <issuer-uri>/well-known/openid-configuration
to get OIDC provider metadata
# issuer ssl certificate is not trusted by default. So import
  issuer ssl certificate into config/webgui.jks
# issuer should be reachable from both back-end and front-end
pi.webgui.sso.oidc.provider.issuer-uri=https://localhost:9031

# OIDC Client id
pi.webgui.sso.oidc.client.id=PingIntelligence

# OIDC Client secret
# This can be empty
pi.webgui.sso.oidc.client.secret=OBF:AES:CbB3MOE/K
+VAa579oBpky4Prlo4z9LnI4vXsltql=

# OIDC Client authentication mode.
# Valid values: BASIC, POST, and NONE
pi.webgui.sso.oidc.client.authentication-method=BASIC
```

```
# claim name for unique id of the user in UserInfo response
# a new user is provisioned using this unique id value
pi.webgui.sso.oidc.provider.user-uniqueid-claim-name=sub

# claim name for first name of the user in UserInfo response
# either first name or last name can be empty, but both should
  not be empty
pi.webgui.sso.oidc.provider.user-first-name-claim-name=given_name

# claim name for last name of the user in UserInfo response
# either first name or last name can be empty, but both should
  not be empty
pi.webgui.sso.oidc.provider.user-last-name-claim-name=family_name

# claim name for role of the user in UserInfo response
# valid values for roles are ADMIN,REGULAR
pi.webgui.sso.oidc.provider.user-role-claim-name=role

# additional scopes in authorization request
# multiple scopes should be comma (,) separated
# openid,profile scopes are always requested
pi.webgui.sso.oidc.client.additional-scopes=exclusive
```

## Configuring SSO with PingOne

This topic discusses steps involved in configuring single sign-on (SSO) to PingIntelligence for APIs Dashboard from PingOne. This feature is available in PingIntelligence for APIs 4.4.1 and later versions.

Before you begin

Verify the following prerequisites for SSO configuration:

- An installed PingIntelligence for APIs Dashboard.
- Access to the the PingOne administration console console. For more information, see [Accessing the admin console home page](#).

About this task

SSO configuration for PingIntelligence Dashboard involves configuring both Dashboard and PingOne.

Steps

1. Create an OIDC (OpenID Connect) web application in PingOne to setup SSO to PingIntelligence Dashboard . To configure the OIDC application, complete the steps explained in [Configuring an OIDC Application in PingOne for PingIntelligence Dashboard](#) on page 499.
2. Set the value of `pi.webgui.server.authentication-mode` to `sso` in `<pi_install_dir>/pingidentity/webgui/config/webgui.properties` file.

```
### Authentication mode
# valid values: native, sso
pi.webgui.server.authentication-mode=sso
```


**Note:** PingIntelligence for APIs Dashboard provides two methods for user authentication: native or SSO. SSO authentication should be used only for production deployments. Use native authentication for PoC deployments.

3. Configure the `<pi_install_dir>/pingidentity/webgui/sso.properties` file to complete the PingIntelligence Dashboard's SSO authentication. For more information, see [Configuring Dashboard sso.properties for PingOne](#) on page 501.
4. Obfuscate keys added in SSO properties using the following commands.

```
# cd <pi_install_dir>/pingidentity/webgui
# ./bin/cli.sh obfuscate_keys
```

5. Restart the PingIntelligence Dashboard after configuring SSO in PingOne and PingIntelligence Dashboard. For more information, see [Start and stop Dashboard](#) on page 115.
6. When the PingIntelligence Dashboard is started successfully, access it using `https://<pi_install_host>:8030`. The Dashboard will start SSO Authentication, and a new session will get created for the logged-in users.

If the SSO authentication fails for any reason, PingIntelligence Dashboard shows the following error message.



**Note:** Every PingIntelligence Dashboard SSO authentication event is attached with a unique ID, which is logged in `<pi_install_dir>/pingidentity/webgui/logs/admin/sso.log`. You can filter `sso-event-ref = <unique ID>` in the `<pi_install_dir>/pingidentity/webgui/logs/admin/sso.log` file to find the reason for SSO failure.

### Configuring an OIDC Application in PingOne for PingIntelligence Dashboard

Complete the following steps in PingOne, to create and configure an OIDC(Open ID Connect) application for setting up single signon (SSO) to PingIntelligence for APIs Dashboard.

#### Steps


1. From the PingOne dashboard, create a new connection.
  - a. Go to **Connections # Applications**, and click **Add Application**.
  - b. On the New Application page, select **Web App # OIDC**, and click **Configure**.
2. On the Create App Profile page, provide the information for following fields, and then click **Next**.
  - APPLICATION NAME
  - DESCRIPTION (Optional)
  - ICON (Optional)

3. On the Configure page, enter the following URL in the **Redirect URLs** field and click **Save and Continue**.


The path in the URI is as follows: `https://<pi_install_host>:8030/login/oauth2/code/PingIntelligence`. Do not change the path in the URI, just substitute the hostname. For example, `https://127.161.140.180:8030/login/oauth2/code/PingIntelligence`.

4. On the Grant Resource Access to Your Application page, to add the **profile scope** to the list of scope grants, click the associated **Plus** icon. Click **Save and Continue**.
5. On the Attribute Mapping page, add the following attributes and map them to the PingIntelligence Dashboard SSO.properties. Select the **Required** check box for each attribute. When you are finished, click **Save and Close**.

OIDC Attributes	Value
<b>User ID</b> PingOne User Attribute	The value defaults to <b>sub</b> .
<b>Family Name</b> PingOne User Attribute	The value of this property should be a claim name that holds the last name of the signed-on user in <code>&lt;pi_installation_path&gt;/pingidentity/webgui/sso.propertiesfile</code> . The default value for the claim is <code>family_name</code> . For more information, see <a href="#">Configuring Dashboard sso.properties for PingOne</a> on page 501.
<b>Given Name</b> PingOne User Attribute	The value of this property should be a claim name that holds the first name of the signed-on user in <code>&lt;pi_installation_path&gt;/pingidentity/webgui/sso.properties file</code> . The default value for the claim is <code>given_name</code> . For more information, see <a href="#">Configuring Dashboard sso.properties for PingOne</a> on page 501.
<b>Role</b> Static Key	<p>The value of this property should be a claim name that holds the value of the role of the signed-on user in <code>&lt;pi_installation_path&gt;/pingidentity/webgui/sso.properties file</code>. For more information, see <a href="#">Configuring Dashboard sso.properties for PingOne</a> on page 501. <a href="#">Configuring an OIDC Application in PingOne for PingIntelligence Dashboard</a> on page 499</p> <p>The default value in Dashboard is <code>role</code>. Supported values for the Role claim are ADMIN and REGULAR.</p>

6. On the Applications page, click the  icon next to PingIntelligence Dashboard application. Click the **Configuration** tab and record the values for the following application properties to use in later steps in [Configuring Dashboard sso.properties for PingOne](#) on page 501 :

- Issuer
- Client ID
- Client Secret



7. Click the **pencil** icon on the right and set the following properties and click **Save**.

Property	Value
Response Type	Select <b>Code</b> .
Grant Type	Select <b>Authorization Code</b> . Keep the PKCE as <b>OPTIONAL</b> .
Token Endpoint Authentication Method	Select <b>None</b> , <b>Client Secret Basic</b> , or <b>Client Secret Post</b> .

8. To enable the application, click the toggle switch to the on (green) position.

**Next steps**

Complete the SSO configuration in PingIntelligence for APIs Dashboard. For more information see, [Configuring Dashboard sso.properties for PingOne](#) on page 501.

**Configuring Dashboard sso.properties for PingOne**

**About this task**

To complete the Dashboard's SSO authentication, configure the `<pi_installation_path>/pingidentity/webgui/sso.properties` file.

## Steps

To complete the Dashboard's SSO authentication, configure the `<pi_installation_path>/pingidentity/webgui/sso.properties` file. The following table describes the SSO properties.

Property	Mandatoy	Description
pi.webgui.sso.oidc.provider.issuer-uri	Yes	Configure the Issuer URI auto generate in PingOne for PingIntelligence Dashboard application. For more information, see step-6 in <a href="#">Configuring an OIDC Application in PingOne for PingIntelligence Dashboard</a> on page 499.
pi.webgui.sso.oidc.client.id	Yes	Configure the client ID. Make sure to configure the same value auto generated in PingOne for PingIntelligence Dashboard application. For more information, see step-6 in <a href="#">Configuring an OIDC Application in PingOne for PingIntelligence Dashboard</a> on page 499.
pi.webgui.sso.oidc.client.secret pi.webgui.sso.oidc.client.authentication	This is a required property only if the value of the property method is not set to NONE.	Configure the client secret value in plain-text. Make sure to configure the same value auto generated in PingOne for PingIntelligence Dashboard application. For more information, see step-6 in <a href="#">Configuring an OIDC Application in PingOne for PingIntelligence Dashboard</a> on page 499..
pi.webgui.sso.oidc.client.authentication-method	Yes	Configure the PingOne OIDC application authentication method. The possible values are: <ul style="list-style-type: none"> <li>BASIC - Basic authentication header based client authentication</li> <li>POST - Client credentials sent in POST body for authentication</li> <li>NONE - Client does not authenticate itself</li> </ul> The default value is BASIC. <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> If the Authentication method in the OIDC application created in PingOne is set to None, then use NONE for this property. If Authentication is set to Client Secret Basic, Client Secret Post use BASIC or POST.</p> </div>
pi.webgui.sso.oidc.provider.user-uniqueid-claim-name	Yes	The value of this property should be <code>sub</code> . It defaults to the value of User ID in PingOne OIDC Attributes.
pi.webgui.sso.oidc.provider.user-first-name-claim-name	Yes	The value of this property should be the PingOne OIDC Attribute value that holds the first name of the signed-on user. The default value for the claim is <code>given_name</code> .

Property	Mandatoy	Description
pi.webgui.sso.oidc.provider.user-last-name-claim-name	Yes	The value of this property should be the PingOne OIDC Attribute value that holds the last name of the signed-on user. The default value for the claim is <code>family_name</code> .
pi.webgui.sso.oidc.provider.user-role-claim-name	Yes	The value of this property should be the PingOne OIDC Attribute value that holds the role of the signed-on user. The default value in Dashboard is <code>role</code> . Supported values for the Role claim are ADMIN and REGULAR.
pi.webgui.sso.oidc.client.additional-scopes	No	Not applicable for PingOne SSO configuration

The following is a sample snippet of `sso.properties`.

```
#### PingIntelligence WebGUI SSO properties file
# This is in standard java properties file format
# comments are denoted by number sign (#) as the first non blank character
# multiline values are ended with '\' as end of line

# OIDC Provider uri
# WebGUI queries <issuer-uri>/.well-known/openid-configuration to get OIDC
# provider metadata
# issuer ssl certificate is not trusted by default. So import issuer ssl
# certificate into config/webgui.jks
# issuer should be reachable from both back-end and front-end
pi.webgui.sso.oidc.provider.issuer-uri=https://auth.pingone.asia/7e49bb56-72f8-485d-810e-ae3d619ca670/as

# OIDC Client id
pi.webgui.sso.oidc.client.id=PingIntelligence

# OIDC Client secret
# This can be empty
pi.webgui.sso.oidc.client.secret=OBF:AES:BcB3MOE/K+VAa579oBpky4Prlo4z9LnI4vXsltql=

# OIDC Client authentication mode.
# Valid values: BASIC, POST, and NONE
pi.webgui.sso.oidc.client.authentication-method=BASIC

# claim name for unique id of the user in UserInfo response
# a new user is provisioned using this unique id value
pi.webgui.sso.oidc.provider.user-uniqueid-claim-name=sub

# claim name for first name of the user in UserInfo response
# either first name or last name can be empty, but both should not be empty
pi.webgui.sso.oidc.provider.user-first-name-claim-name=given_name

# claim name for last name of the user in UserInfo response
# either first name or last name can be empty, but both should not be empty
```

**pi.webgui.sso.oidc.provider.user-last-name-claim-name=family\_name**

```
# claim name for role of the user in UserInfo response
# valid values for roles are ADMIN and REGULAR
```

**pi.webgui.sso.oidc.provider.user-role-claim-name=role**

```
# additional scopes in authorization request
# multiple scopes should be comma (,) separated
# openid,profile scopes are always requested
pi.webgui.sso.oidc.client.additional-scopes=exclusive
```

**Next steps**

Complete step 4- 6 [Configuring SSO with PingOne](#) on page 498.

**Automatic rollover index**

PingIntelligence for APIs Dashboard uses Index Lifecycle Management (ILM) policy support of Elasticsearch to rollover time-series data. Rolling over the time-series data is important to maintain a low latency during search operations. The ILM policy allows for an automatic rollover of index based on time or size of data.

**Note:** ILM policy for automatic rollover index works in Elasticsearch with X-Pack.


**Configuring automatic rollover index**

Configure the path to the ILM policy in `es.index.dashboard.activity.ilm.policy` property in `dashboard/config/dashboard.properties` file. The ILM policy file should be a valid JSON. Following is a sample `ilm.json` file available in the `dashboard/config` directory. Leave the value of `es.index.dashboard.activity.ilm.policy` property empty if you do not wish to use ILM policy.

```
{
  "policy": {
    "phases": {
      "hot": {
        "actions": {
          "rollover": {
            "max_size": "30GB",
            "max_age": "30d"
          },
          "set_priority": {
            "priority": 100
          }
        }
      },
      "warm": {
        "min_age": "30d",
        "actions": {
          "shrink": {
            "number_of_shards": 1
          },
          "readonly": {},
          "forcemerge": {
            "max_num_segments": 1
          },
          "set_priority": {
            "priority": 50
          }
        }
      }
    }
  }
}
```







**Note:** PingIntelligence for APIs is qualified for Splunk 8.0.0.

## Installing and configuring Splunk for PingIntelligence

Before you begin

To complete the configuration of Splunk for PingIntelligence, you need to create a source type. Creating a source type helps Splunk to understand the event format.

The **source type** is one of the default fields that Splunk assigns to all the incoming data. Configuring the source type informs Splunk about the type of data ABS provides. This helps Splunk in formatting data intelligently during indexing.

About this task

To create a source type:

Steps

1. Configure a new source type by navigating to **Splunk Enterprise# Settings# Source Types# New Source type**. The source type events page is displayed.
2. Configure the **New Source type**. The fields are defined in the following table:

Name	Value
Source type name	pi_events_source_type
Destination app	Search and Reporting (Can change for your apps)
Category	Structures
Indexed extractions	json

Name	Value
SEDCMD-alter	s/pi-attack-info-//

**Edit Source Type: pi\_events\_source\_type**
✕

Description

Destination app

Category

Indexed Extractions ?

Timestamp Advanced

Name	Value	
CHARSET	UTF-8 ▼	✕
DATETIME_CONFIG	<input type="text"/>	✕
BREAK_ONLY_BEFORE_DATE	<input type="text"/>	✕
INDEXED_EXTRACTIONS	json	✕
LINE_BREAKER	([\r\n]+)	✕
NO_BINARY_CHECK	true	✕
SEDCMD-alter	s/pi-attack-info-//	✕
SHOULD_LINEMERGE	false	✕
category	Custom	✕
disabled	false	✕
pulldown_type	true	✕

[New setting](#)

### 3. Create a new index `pi_events` by navigating to **Enterprise# Settings# Indexes# New Index**.

**New Index**
✕

---

**General Settings**

Index Name   
Set index name (e.g., INDEX\_NAME). Search using index=INDEX\_NAME.

Index Data Type  Events  Metrics  
The type of data to store (event-based or metrics).

Home Path   
Hot/warm db path. Leave blank for default (\$SPLUNK\_DB/INDEX\_NAME/db).

Cold Path   
Cold db path. Leave blank for default (\$SPLUNK\_DB/INDEX\_NAME/colddb).

Thawed Path   
Thawed/resurrected db path. Leave blank for default (\$SPLUNK\_DB/INDEX\_NAME/thaweddb).

Data Integrity Check  Enable  Disable  
Enable this if you want Splunk to compute hashes on every slice of your data for the purpose of data integrity.

Max Size of Entire Index  GB ▾  
Maximum target size of entire index.

Max Size of Hot/Warm/Cold Bucket  GB ▾  
Maximum target size of buckets. Enter 'auto\_high\_volume' for high-volume indexes.

Frozen Path   
Frozen bucket archive path. Set this if you want Splunk to automatically archive frozen buckets.

App

**Storage Optimization**

Tsidx Retention Policy  Enable Reduction  Disable Reduction

### Types of data captured

Splunk for PingIntelligence captures attack data. The attack event captures the components listed in the following table:

Field	Description
timestamp	epoch timestamp
protocol	HTTP(s) /Websocket (ws)
attack_id	PingIntelligence <a href="#">Attack ID</a>
description	Description of the attack
attack_bucket	Attack on an API or a DDoS attack
attack_scope	Single or multiple APIs
attacked_api	Name of the API. In case of multiple API, MULTI_API is reported
attack_identifier_type	Username, API Key, OAuth token, Cookie, or IP address
attack_key	Details of APIKEY or Cookie
attack_value	Value of the client identifier.

## Installing and configuring the Splunk Universal Forwarder

Install and configure the Splunk Universal Forwarder to collect attack data and forward it to the Splunk Server.

### Steps

1. Download Splunk Universal Forwarder 8.0.0. For more information, see [Splunk® Universal Forwarder Manual](#)
2. Install the Splunk Universal Forwarder by entering the following command.

```
[root@ABS]# tar -xvf splunkforwarder-8.0.0-8c86330ac18-Linux-x86_64.tgz
splunkforwarder/
splunkforwarder/share/
```

#### **Note:**

Replace the file name given in the example command with the name of the file you downloaded in step 1.

3. Start the Splunk Universal Forwarder.

```
[root@ABS]# cd splunkforwarder/bin
[root@ABS]# ./splunk start --accept-license
```

4. Add forward server details (the receiver host and port in Splunk).

```
[root@dashboard]# ./splunk add forward-server ip:port
Splunk username: admin Password: Added forwarding to: 192.168.1.158:9997.
```

#### **Note:**

Enable the receiving port in Splunk. For example, configure port number 9997 from the previous example in your Splunk deployment.

5. Edit the `inputs.conf` file on your Splunk Universal Forwarder as shown in the following example.

```
[root@ABS]# ./splunk add monitor /opt/pingidentity/splunk/data/
Added monitor of '/opt/pingidentity/splunk/data/'.
```

6. Edit the `inputs.conf` file on your Splunk Universal Forwarder.

```
[root@dashboard]# cat /opt/splunkforwarder/etc/apps/search/local/
inputs.conf

[monitor:///opt/pingidentity/pingidentity/dashboard/logs/attack.log/]

index = pi_events
sourcetype=pi_events_source_type
disabled = false
```

7. Restart the Splunk Universal Forwarder.

```
[root@ABS]# ./splunk restart
```

## 8. Verify if data is flowing to Splunk on the Splunk Dashboard.

i	Time	Event
>	10/12/2019 08:20:00.000	<pre>{ [-]   attack_bucket: API   attack_id: 26   attack_identifier_type: TOKEN   attack_key:   attack_scope: MULTI_API   attack_value: 343077883101e1c8f2b3ec0fbf6a32ab2327e4c2e7ebe525a27a125225fa136d   attacked_api:   description: Content Scraping   protocol: HTTP   timestamp: 1575966000000 }</pre> <p>Show as raw text</p> <p>host = 16Core-48G-500HDD-Ubuntu   source = /tmp/attack.log   sourcetype = pi_events_source_type</p>

If no data is available in Splunk, check your firewall settings.

### Alert notification on Slack and Email

You can configure Splunk to send alert notification to a Slack channel or through and email.


#### Slack

##### Prerequisites:

- The Slack app should already be installed in your Splunk setup.
- Connect Slack and Splunk using webhooks. For more information on Slack webhooks, see [Incoming Webhooks](#)

Complete the following steps to create an alert for Slack:

#### 1. Navigate to **Settings #> Searches, reports and alerts**

 **Note:** Alert should be created for App: Search & Reporting(search)

2. Create new alerts

**Settings**

Alert **PingIntelligence for APIs Alert**

Description

PingIntelligence for APIs Alert

Search

index="pi\_events" sourcetype="pi\_events\_source\_type" access\_type="atta

Alert type

Scheduled

Real-time

Run on Cron Schedule ▾

Time Range

Last 600 seconds ▶

Cron Expression

\*/10 \* \* \* \*

e.g. 00 18 \*\*\* (every day at 6PM). [Learn More](#)

Expires

24

hour(s) ▾

**Trigger Conditions**

Trigger alert when

Number of Results ▾

is greater than ▾

0

Trigger

Once

For each result

Throttle ?

Enter the values as described in the table below:

Value	Description
Description	PingIntelligence for APIs Alert
Search	Search: index="pi_events" sourcetype="pi_events_source_type" access_type="attack"
Alert Type	Scheduled -> <b>Run on Cron Schedule</b>
Cron Expression	*/10 * * * *

Time Range	600
Expires	24-hours
Trigger alert when	The alert should be triggered for results when greater than 0
Trigger	For each result. This would trigger a new alert for each event.
Throttle	Do not throttle the events



### 3. Configure alert action

+ Add Actions ▾

When triggered

▾ Slack

Channel

Message 

```
-----  
$result.attack_type$ has been  
detected on API: $result.api_  
name$  
-----  
More details :  
`$result._raw$`
```

Attachment

Fields

Advanced settings:

Webhook URL

Slack  
sage t  
)

Enter  
to the  
sage c  
sert te  
the se

Option  
ment.

Show  
the se  
Slack  
rated  
wildca

You ca  
hook U  
send t  
ferent

Value	Description
Add Actions	Choose the slack app to add actions
Channel	Use the channel which has been configured with webhook URL which starts with either # or @  In this example, we are using channel name as:  # PingIntelligence_alerts
Message	This is the message which will be posted along with the alert in slack, We recommend using the below message:  ----- \$result.attack_type\$ has been detected on API: \$result.api_name\$ -----  More details : `\$result._raw\$`
Attachments	NA
Fields	NA
Webhook URL	NA

#### 4. Post a message in Splunk to verify that it is notified in Slack

##### attack.log for Splunk

##### Configure dashboard.properties for attack.log

Edit the `pingidentity/dashboard/config/dashboard.properties` file to send the attack data to `attack.log`. By default `syslog` is configured. To send the attack data to `attack.log`, edit the `dashboard.properties` file as shown in the snippet below:

```
### Log4j2
# publish attacks to Log4j2. Valid values true or false
# By default it provides syslog support
publish.log4j2.enable=true
# log4j2 config file to log attacks to an external service. For example,
  Syslog
# use com.pingidentity.abs.publish as logger name in log4j2 configuration
log4j2.config=config/attack_log.xml
# log4j2 log level for attack logging
log4j2.log.level=INFO
# directory for any log4j2 config dependency jar's.
# useful for third party log4j2 appenders
# it should be a directory
log4j2.dependencies.dir=plugins/
```

**attack\_log.xml:** Following is a snippet of the `attack_log.xml`. The `attack_log.xml` produces `attack.log` that is consumed by Splunk. The `attack.log` captures the attack data in a JSON format.

```
<?xml version="1.0" encoding="UTF-8"?>
<Configuration name="APIIntelligence" packages="" status="warn">
  <Appenders>
    <RollingFile name="attack_log" append="true"
      fileName="${sys:dashboard.rootdir}/logs/attack.log"
      filePattern="logs/attack.log.%d{yyyy-MM-dd}" immediateFlush="true" >
    <PatternLayout>
```

```

    <Pattern>pi-attack-info-%m%n</Pattern>
  </PatternLayout>
  <Policies>
    <TimeBasedTriggeringPolicy/>
  </Policies>
</RollingFile>
</Appenders>

<!-- Attacks are logged to logger with name com.pingidentity.abs.publish
     There should be at least one logger with name
     com.pingidentity.abs.publish
     It is better to set additivity="false" so that same attacks will not
     be logged in dashboard.log -->

<Loggers>
  <Logger additivity="false" level="info" name="com.pingidentity.abs.publish">

    <AppenderRef ref="attack_log"/>
  </Logger>
</Loggers>
</Configuration>

```

The attack data is published to a Log4j logger named `com.pingidentity.abs.publish`. The Log4j configuration file must have a logger named `com.pingidentity.abs.publish`. Any Log4j2 config file that wants to capture attack data from Dashboard must have at least one logger with name `com.pingidentity.abs.publish`.

## Dashboard log messages

The following tables list the critical log messages from `dashboard.log` file. The `dashboard.log` file is rotated every 24-hours.

Log messages	Description
error - fatal protocol violation	This message is logged in <code>dashboard.log</code> when there is a HTTP/(S) protocol error while connecting to ABS or Elasticsearch.
error - fatal transport error	This message is logged in <code>dashboard.log</code> when there is an unknown host for ABS or Elasticsearch.
error - error while sending message to syslog	This message is logged in <code>dashboard.log</code> when the syslog server is not reachable, or there is an error in configuration of SSL or non-SSL connections.
error - capacity full in syslog consumer worker, retries exhausted, ignoring this message	This message is logged in <code>dashboard.log</code> when the Syslog server is not reachable, or there is an error in the configuration of SSL or non-SSL connections.
error - error while closing response stream	This message is logged in <code>dashboard.log</code> when ABS, or Elasticsearch socket is not closed properly.
error - error while flushing file stream	This message is logged in <code>dashboard.log</code> when there is a failure in the storage disk, or the storage disk is full..

Log messages	Description
error - error while closing file stream	This message is logged in <code>dashboard.log</code> when there is a failure in the storage disk, or the storage disk is full..
error - error while parsing access_time from file	This message is logged in <code>dashboard.log</code> when ABS returns an invalid access_time or the time format is not consistent.
error - error while parsing api_key name from file	This message is logged in <code>dashboard.log</code> when ABS returns an empty API Key in the API Key metrics or attack report.
error - error while parsing cookie name from file	This message is logged in <code>dashboard.log</code> when ABS returns an empty cookie name in the metrics or attack report.
warn - http request " + <URL> + ", response status: " + <Response status>	This message is logged in <code>dashboard.log</code> when ABS or Elasticsearch returns HTTP status code that is greater than or equal to 300.
Dashboard stopped	This message is logged in <code>dashboard.log</code> when Dashboard is shutdown.

### Purge dashboard logs

The `purge.sh` script either archives or purges processed access log files which are stored in the `/opt/pingidentity/dashboard/logs` directory.

**Note:** When the `purge` script is run, the log files are permanently deleted from the `/opt/pingidentity/dashboard/logs` directory. Always backup the files before deleting.

Located in the `/opt/pingidentity/dashboard/util` directory, the `purge` script deletes logs older than the specified number of days. Run the script using the Dashboard command line.

**Note:** The number of days specified should be between 1-365 days.

For example.

```
/opt/pingidentity/dashboard/util/purge.sh -d 3
In the above example, purge.sh deletes all access log files older than 3
days. Here is sample output.
/opt/pingidentity/dashboard/util/purge.sh -d 3
This will delete the data in /opt/pingidentity/dashboard/logs which is older
than 3 days.
Are you sure (yes/no): yes
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-07 : last
changed at Sat Feb 9 00:29:43 EST 2019
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-09 : last
changed at Mon Feb 11 00:29:48 EST 2019
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-08 : last
changed at Sun Feb 10 00:29:56 EST 2019
Done.
```

**Force delete:** You can force delete the Dashboard log files by using the `-f` option with the `purge.sh` script. When using this option, the script does not check for confirmation to purge the log files. Use the force purge option with the `-d` option to provide the number of days of logs to keep.

**Example:** The following snippet shows an example of the force purge and `-d` option.

```
/opt/pingidentity/dashboard/util/purge.sh -d 3 -f
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-07 : last
changed at Sat Feb 9 00:31:26 EST 2019
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-09 : last
changed at Mon Feb 11 00:31:30 EST 2019
removing /opt/pingidentity/dashboard/logs/dashboard.log.2019-02-08 : last
changed at Sun Feb 10 00:31:35 EST 2019
Done.
```

In the above example, the script force purges the Dashboard log files while keeping log files of 3-days.

### External log archival

The `purge` script can also archive logs older than the specified number of days to secondary storage. Use the `-l` option and include the path of the secondary storage to archive log files. For example:

```
/opt/pingidentity/dashboard/util/purge.sh -d 3 -l /tmp/
```

In the above example, log files older than 3-days are archived to the `tmp` directory. To automate log archival, add the script to a `cron` job.

### Purge data from Elasticsearch

To manage storage on the Dashboard server, you can either archive or purge Elasticsearch data. PingIntelligence provides a purge script to remove older Elasticsearch data.

**i Warning:** When the purge script is run, all files are permanently deleted from the Elasticsearch data directory. Hence it is recommended to take a backup of Elasticsearch documents before proceeding with the purge.

Run the purge script, on the dashboard engine command line. The number of days specified should be between 1-365 days.

```
/opt/pingidentity/dashboard/util/purge_elasticsearch.sh -d 3
```

In the following example, `purge_elasticsearch.sh` deletes all files older than 3 days. Here is a sample output:

```
/opt/pingidentity/dashboard/util/purge_elasticsearch.sh -d 3
This will delete the data in elastic search which is older than 3 days.
Are You sure(yes/no):yes
2017-04-17 11:13:07 INFO Starting purge with options, days : 3 path : /opt/
poc/pingidentity/dashboard/config/dashboard.properties
```

To delete all data and Elasticsearch templates, use the following:

```
curl -s https://<elasticsearch_ip_address>:<port>/_all -X DELETE -u elastic
```

When you use the `-X DELETE` option, the system goes back to a fresh installation state.

**i Note:** Purge for Elasticsearch runs in the background. Documents are not deleted immediately after `purge_elasticsearch.sh` execution. Elasticsearch deletes purged documents with a lag of 5 minutes.

The following example illustrates deletion of Elasticsearch records older than 15 days. The Number of Records Purged : null is an expected message due to the time lag in actual deletion.

```
[xxxxxxxx@T5-03 dashboard]$ ./util/purge_elasticsearch.sh -d 15
This will delete the data in elasticsearch cluster which are older than 15
days.
Are You sure(yes/no):yes
Starting Elasticsearch purge
2020-04-09 03:16:44 INFO Starting purge with options, days : 15 path : /
home/xxxxxxxx/pingidentity/dashboard/config/dashboard.properties
2020-04-09 03:16:45 INFO API's Loaded from elasticsearch : [app54, app58,
app63, app8, app2, app3, app66, app74, app79, app77]
2020-04-09 03:16:45 INFO Purging data for global indice activity-api
2020-04-09 03:16:45 INFO Number of Records Purged : null
2020-04-09 03:16:45 INFO Purging data for global indice activity-api-key
2020-04-09 03:16:45 INFO Number of Records Purged : null
2020-04-09 03:16:45 INFO Purging data for global indice activity-token
2020-04-09 03:16:45 INFO Number of Records Purged : null
.
.
```

**Note:** It is recommended to run `purge_elasticsearch.sh` during lean API traffic periods.

### Purge Web GUI logs

The `purge.sh` script either archives or purges processed access log files and admin log files which are stored in the `/opt/pingidentity/webgui/logs/access/` and `/opt/pingidentity/webgui/logs/admin/` directories respectively.

**Note:** When the `purge` script is run, the log files are permanently deleted. Hence it is recommended to always backup the files before deleting.

Located in the `/opt/pingidentity/webgui/util` directory, the `purge` script deletes logs older than the specified number of days. Run the script using the webgui command line.

**Note:** The number of days specified should be between 1-365 days.

For example.

```
/opt/pingidentity/webgui/util/purge.sh -d 1
This will delete the logs in /opt/e2e/pingidentity/webgui/logs/admin and /
opt/e2e/pingidentity/webgui/logs/access that are older than 1 days.
Are you sure (yes/no): yes
Removing /opt/e2e/pingidentity/webgui/logs/admin/admin.log.2020-04-08 : last
changed at Wed Apr 8 17:07:49 UTC 2020
removing /opt/e2e/pingidentity/webgui/logs/access/access.log.2020-04-08 :
last changed at Wed Apr 8 19:03:31 UTC 2020
Done
```

**Force delete:** You can force delete the webgui log files by using the `-f` option with the `purge.sh` script. When using this option, the script does not check for confirmation to purge the log files. Use the force purge option with the `-d` option to provide the number of days of logs to keep.

**Example:** The following snippet shows an example of the force purge and `-d` option.

```
/opt/pingidentity/webgui/util/purge.sh -d 2 -f
```

In the above example, the script force purges the webgui log files while keeping log files of 2-days.

### External log archival

The `purge` script can also archive logs older than the specified number of days to secondary storage. Use the `-l` option and include the path of the secondary storage to archive log files. For example.


```
/opt/pingidentity/webgui/util/purge.sh -d 2 -l /backup/
```

In the above example, log files older than 2-days are archived to the `backup` directory. To automate log archival, add the script to a `cron` job.

## Dashboard


---

The Dashboard provides a near real-time snapshot of your API environment. It provides insights on user activity, attack information, blocked connections, forensic data, and much more. The Dashboard makes periodic REST API calls to the ABS (API Behavioral Security) AI engine, which returns JSON reports that are used to generate visualizations and API metrics. The following illustration shows the data flow for API dashboard.




To view the API dashboard, click on **Dashboard**. The Dashboard provides information on the following::

- Global metrics like:
  - Blacklist across APIs for each client identifier. For more information, see [Interactive blacklists](#) on page 28.
  - Total attacks across APIs
  - Total requests across APIs
  - Number of APIs in your environment
- Time series visualization of total number of requests and attacks. For more information, see [Dashboard time series](#) on page 30.
- Data on Per API activity. For more information, see [Per API activity](#) on page 523.
- Data on attacks across APIs. For more information, see [Cross API attacks and recently discovered APIs](#) on page 530.
- Forensic reports across APIs. For more information, see [Forensic reports](#) on page 525.
- Recently discovered APIs in the environment.



## Interactive blacklists

PingIntelligence for APIs Dashboard provides the capability of interactive blacklist management. A blacklist is a list of client identifiers that were detected executing an attack. The dashboard enables you to unblock the blacklisted client identifiers or tune the threshold values for attack types. It supports the following client identifier types- IP address, Cookie, Token, API Key, and Username. You can view the top-500 entries on each blacklist from the dashboard.



Click on the count for any blacklist type, for example, **IP Blacklist**. The dashboard lists the blacklisted IP addresses along with the Detected date..



The following screenshot shows the expanded blacklist:

The screenshot displays the PingIntelligence dashboard for API. The main section is titled 'Active IP Blacklist' and shows a summary of 64 active IP addresses. Below this is a table with the following columns: IP, Detected, and Action. The Action column for the first row is expanded, showing options for 'Unblock' and 'Tune'. The table contains 14 rows of data, all with a detected date of 2020-03-24 22:07. The first row has a detected date of 2020-03-26 16:25. The Action column for the first row is expanded, showing options for 'Unblock' and 'Tune'. The footer includes copyright information for Ping Identity Corporation.

IP	Detected	Action
[blurred]	2020-03-26 16:25	✓ --Action-- Unblock Tune
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--
[blurred]	2020-03-24 22:07	--Action--

For each blacklisted IP address, you get the option to Unblock or Tune in the **Action** list. Clicking on either action redirects the dashboard to the Attack management application. Attack management allows you to run the operations for unblocking the client identifiers and tuning the threshold values.

**Note:** The **Action** list is available only for an Admin user. You need to have Admin user privileges to perform **Unblock** and **Tune** operations on a client identifier.

The following screen shot shows the Attack management

The screenshot shows the 'Attack Management' interface in the PingIntelligence dashboard. The left sidebar has 'Attack Management' highlighted. The main content area contains the following fields:

- CLIENT IDENTIFIER TYPE:** A dropdown menu with 'IP Address' selected.
- ENTER IP ADDRESS:** A text input field containing a masked IP address.
- AMT ACTION:** Radio buttons for 'Unblock Client' (selected) and 'Tune Threshold'.
- Run:** A blue button at the bottom of the form.

Yellow arrows point to the 'IP Address' dropdown, the IP input field, and the 'AMT ACTION' label.

UI.

The values in **Client Identifier Type** and **Enter IP Address** get auto-populated into the Attack management application from the dashboard. The **AMT Action** is auto-selected. Click **Run** to execute the operation. For more information on Attack management, see [Tune thresholds and unblock clients](#) on page 23.

**Note:** Dashboard does not populate the API key key-name in the Attack management application when the client identifier is API key. It only populates the API key value.

## Dashboard time series

PingIntelligence Dashboard shows the attacks in a time-series format. To adjust the timeframe viewed on the Dashboard, click between the **time-period** arrows located on the top right corner of the dashboard and select the desired time period.

See the example in the following screen


The screenshot shows the 'Time Range' dropdown menu in the dashboard. The menu is open, showing the following options:

Quick	Relative	Absolute	Recent
Today	Last 15 minutes	Last 30 days	
This week	Last 30 minutes	Last 60 days	
This month	Last 1 hour	Last 90 days	
This year	Last 4 hours	Last 6 months	
Today so far	Last 12 hours	Last 1 year	
Week to date	Last 24 hours	Last 2 years	
Month to date	Last 7 days	Last 5 years	
Year to date			

The 'Last 7 days' option is highlighted with a yellow box. A yellow arrow points to the 'Last 7 days' button in the top right corner of the dashboard.

capture:


The following screen capture shows the total requests and number of attackers data in time series



## Per API activity


PingIntelligence for APIs Dashboard provides detailed analytics on each API. On the main Dashboard, the following information is available:

- Training status - An API is trained after the ABS AI engine analyzes its traffic patterns and builds AI models to detect attacks on the API. For more information, see [AI Engine training](#) on page 338
- Total number of requests made to the API during the requested timeframe
- Total attacks on the API during the requested timeframe




Click on the API name to launch an API-specific dashboard. The dashboard provides following insight into the API activity:

- Client attacks on the API - PingIntelligence for APIs identifies the number of individual clients executing attacks by client identifier - API Keys, Cookies, IP addresses, OAuth2 tokens, and Usernames. It also displays the total number of attacks (including multiple attacks per client) originating from any client identifier
- API Attacks - ABS AI Engine reports on client attacks targeted on a specific API. It identifies different attack types on your API based on client activity. The dashboard displays information that can be sorted by attack type or count. For more information, see [REST API attacks](#) on page 357.
- API Activity and Attacks - The API dashboard provides the total number of requests and attackers for the API in a time-series format.
- Top Resources Accessed - The most frequently accessed API resources can be viewed in sorted order by URL or number of requests.
- Top IP Addresses - The IP addresses from which the API requests have originated can be viewed in sorted order by IP or number of requests.
- Top Device Types - The device type from which the API requests have originated can be viewed in sorted order by device type or the number of requests.
- Top Users - The username accessing the API can be viewed in sorted order by username or number of requests.
- Error Codes - The number of failed requests are categorized by HTTP status codes in a bar chart.




## Forensic reports


The Forensic reports provided by PingIntelligence for APIs Dashboard render deep insights into the client API activity. They provide analytics on recent attacks and API activities of top clients. The ABS AI Engine generates forensic insights by analyzing the API traffic patterns. PingIntelligence for APIs Dashboard projects these insights as Forensic reports.



An example of top clients is the Top IP Addresses forensic report, which gives insight into the activity of the most common IP addresses accessing APIs in your environment.



Click on the individual IP addresses to drill down further and get details on the APIs accessed by the IP address, attacks generated by it and so on.



You can get similar insights on activities from other client identifiers including Usernames, API Keys, Tokens, and Cookies.

**Note:** For client identifiers that exceed 4096 characters, the Dashboard displays only attack information. It does not report forensic details, such as APIs accessed by the identifiers, number of requests, and so forth.

The following table shows the forensics reported by the Dashboard.

Forensic reports	Analytics reported
Recent Attacks	<p>The forensic report on recent attacks give following information:</p> <ul style="list-style-type: none"> <li>▪ The time of the attack.</li> <li>▪ The API attacked.</li> <li>▪ The client identifier from which the attack originated - The identifier can be IP address, cookie, token, username, API key.</li> <li>▪ Count of attacks.</li> </ul>
<ul style="list-style-type: none"> <li>▪ Top Users</li> <li>▪ Top Tokens</li> <li>▪ Top API Keys</li> <li>▪ Top Cookies</li> <li>▪ Top IP Addressess</li> </ul>	<p>The Top client identifier reports provide a list of following information for each client identifier:</p> <ul style="list-style-type: none"> <li>▪ Client identifier value.</li> <li>▪ Count of APIs attacked using the client identifier.</li> <li>▪ Number of attacks from the client identifier.</li> <li>▪ Number of requests made using the client identifier.</li> </ul>

**Note:** You can drill down on each client identifier to get more finer insights like APIs accessed, count of requests made to each API, type of attacks generated from the client identifier, devices from which the request initiated and much more.

With PingIntelligence Dashboard, you can get the attack insights for different time-periods. For more information, see [Dashboard time series](#) on page 30.

### Client forensic report

The Client Forensic report provides insights into client activity in the course of an attack. It presents a detailed analysis of the client traffic patterns prior to an attack. The report gives the following information :

- The APIs accessed by the client and the total number of requests made to these APIs.
- The different types of attacks executed by the client and the count of those attacks.
- The URLs accessed by the client and the total number of requests made to these URLs.

The client activity is reported in the time intervals of 10-minutes.

### View the Client Forensic report

To know the details of client activity before an attack, complete the following steps :

**Note:** The steps are explained using IP Address as the client identifier. You can follow the same process to retrieve client forensics for other client identifier types.

1. Click **Recent Attacks** in **Forensic Reports**, to open the Recent Attacks report.

The screenshot shows the PingIntelligence dashboard with the following metrics:


- 69 IP Blacklist
- 10,692 Cookie Blacklist
- 8,037 Token Blacklist
- 14 API Key Blacklist
- 6 User Blacklist
- 11,841 Total Attacks
- 4 Total APIs
- 6,214,669 Total Requests

The 'Per API Activity' table is as follows:

API	Trained	Total Requests	Total Attacks
shop	yes	2,355,589	574
shop-electronics	yes	1,759,950	291
shop-books	yes	2,099,130	148
decoy	n/a	0	30

The 'Global Activity and Attacks' chart shows 'Total Requests' (orange bars) and 'Number of Attackers' (blue line) over time. A 'Forensic Reports' menu is highlighted with a yellow box, containing the following items:

- Recent Attacks (indicated by a yellow arrow)
- Top Users
- Top Tokens
- Top API Keys
- Top Cookies
- Top IP Addresses

2. Click on  icon next to **IP** to sort the recent attacks for that client identifier type. Click on the IP Address for which the client forensics are to be retrieved. This opens the detailed report for the client.


The screenshot shows the 'Recent Attacks' report with the following table:

Time	API	IP	Username	Cookie	API Key	Token	Attacks
July 9th 2020, 09:10:00.000	ACROSS API	[blurred]					1
July 9th 2020, 09:10:00.000	shop-books	[blurred]					1
July 9th 2020, 03:40:00.000	ACROSS API	[blurred]					1
July 9th 2020, 03:40:00.000	shop-books	[blurred]					1
July 9th 2020, 09:09:59.999	shop-books	[blurred]					1
July 9th 2020, 03:39:59.999	shop-books	[blurred]					1
July 9th 2020, 09:10:00.000	ACROSS API	[blurred]					1
July 9th 2020, 03:40:00.000	ACROSS API	[blurred]					1
July 9th 2020, 09:09:59.999	shop-books	[blurred]					2
July 9th 2020, 03:39:59.999	shop-books	[blurred]					2
July 9th 2020, 09:10:00.000	ACROSS API	[blurred]					2
July 9th 2020, 09:10:00.000	shop	[blurred]					1
July 9th 2020, 09:10:00.000	shop-electronics	[blurred]					1
July 9th 2020, 03:40:00.000	ACROSS API	[blurred]					2
July 9th 2020, 03:40:00.000	shop	[blurred]					1


The 'IP' column header is highlighted with a yellow box, and a yellow arrow points to a specific IP address in the first row of the table.




- In the IP report, select the **Attack** for which the client forensics are required. This opens the Attack Insights report for the client.



- In the Attack Insight report, select the **Attack Time** from Client Forensics Links to open the Client Forensics report for the client.




5. The Client Forensic report provides detailed client activity prior to the attack time that is selected in the step-4. It displays details like the APIs and URLs accessed by the client, other attacks executed by the client. It also provides the count of such requests and attacks.



**Note:** Changes to the **Time Range** filter on the top-right corner of the Dashboard will not impact the results retrieved by the Client Forensic report.

## Cross API attacks and recently discovered APIs

PingIntelligence for APIs Dashboard provides data on attacks on the APIs in your ecosystem, along with their count. PingIntelligence for APIs can detect per API attacks and across API attacks. For more information, see [REST API attack types](#) on page 358.



The Dashboard also displays APIs discovered in your ecosystem. For more information, see [Discovered APIs](#) on page 540.

## Attack insights

Attack insights provides information on why an attack was identified. The Dashboard displays the percentage by which the normal behavior was exceeded and hence an attack was reported. The attack insight is rendered for a specific API, a client identifier and an attack type, for example, header manipulation attack. To view the attack insight, navigate to the main **Dashboard**. Click on **Recent Attacks** and then click on a **client identifier**. In the Dashboard page of the client identifier that is displayed, click on the **Attack** to display the Attack Insight Dashboard page for that specific

attack. To view the percentage deviation from the normal behavior, hover your mouse over the

The dashboard displays several key metrics at the top: 70 IP Blacklist, 23,495 Cookie Blacklist, 20,329 Token Blacklist, 92 API Key Blacklist, 6 User Blacklist, 15,726 Total Attacks, 6 Total APIs, and 13,624,238 Total Requests.

**Per API Activity**

API	Trained	Total Requests	Total Attacks
shop	yes	4,834,966	2,284
shop-electronics	yes	4,444,832	1,606
shop-books	yes	4,344,440	811
decoy	n/a	0	199

**Global Activity and Attacks**

A bar chart showing Total Requests (left axis, 0 to 2,000,000) and Number of Attackers (right axis, 0 to 1,500) over time from 2020-09-16 to 2020-10-08. The chart shows several peaks in activity, with the highest peak occurring around 2020-09-16.

**Cross API Attacks**

Attack	Count
Extended Probing - IP	4,905
Extended Probing - Token	1,795
Extended Probing - Cookie	2,858
Content Scraping - Token	226

**Forensic Reports**


- Recent Attacks
- Top Users
- Top Tokens
- Top API Keys
- Top Cookies
- Top IP Addresses

The dashboard displays a list of recent attacks under the heading "Recent Attacks". The table includes columns for Time, API, IP, Username, Cookie, API Key, Token, and Attacks.


Time	API	IP	Username	Cookie	API Key	Token	Attacks
September 30th 2020, 18:20:00.000	ACROSS API						2
September 30th 2020, 18:20:00.000	ACROSS API						3
September 30th 2020, 18:19:59.952	shop-electronics						1
September 30th 2020, 18:10:00.000	ACROSS API						2
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1
September 30th 2020, 18:10:00.000	ACROSS API						1

Export: Raw Formatted

1 2 3 4 5 ... 81 >



In the following screenshot, the deviations are 5 and 9900% from the normal




behavior.

### Attack remediation

Attack remediation allows you to verify if the client that has executed an attack is on the active blacklist at that point in time. You can unblock a client and remove from the blacklist. If blocking is not enabled, then the client will be on the blacklist but not blocked. You can access the Attack management Dashboard to **Unblock** the client or **Tune** the thresholds from Attack

remediation. For more information, see [Tune thresholds and unblock clients](#) on page 23.



## API groups


The Dashboard provides the capability to organize the APIs in your environment into logical groups. You can create API groups as per your requirements. For example, you can group your APIs location-wise, functionality-wise, and so on.

The **API** tab displays all the APIs available in . Every API will be part of at least one API group in the Dashboard. The APIs grouping feature makes searching for a specific API quick and easy. The Dashboard supports two kinds of groups:


- **Default API group:** This is the global API group. All the existing as well as newly discovered APIs will be part of it initially. APIs that do not belong to any other API group will automatically get added to the default API group. You can only view and move APIs from the default APIs group. You cannot delete an API from a default API group.
- **User-defined API groups:** These are the API groups that you can create based on your requirements. You can add or delete an API from the user-defined API groups.


The screenshot shows the 'APIs Grouping' interface in the PingIntelligence dashboard. At the top, there are navigation links for 'MAIN' and 'SETTINGS', and a user profile for 'Administrator'. The left sidebar contains a menu with 'Dashboard', 'APIs', 'Discovered APIs', 'Attack Management', and 'License'. The main content area is titled 'APIs Grouping' and includes a search bar, a 'Filters' dropdown, and a '+ Create New API group' button. Below this, there are 6 groups listed, each with a 'Sort By' dropdown set to 'Sort Based On'. The groups are: 'Default API Group' (GroupType: Default), 'Axway' (API Gateway: Axway), 'Electronics' (Category: Electronics), 'Books' (Category: Books), 'Appliances' (Category: Appliances), and 'Apparel and Fashion' (Category: Fashion). Each group has a '+ Add APIs' button and a toggle icon on the right.


## API details

You can click on  icon to expand an API group. The following details are available for each API within an API group:

- **API name:** API name used by PingIntelligence
- **Prediction mode:** A `true` status means that at least one training threshold value is set. It does not necessarily mean that all the training is complete. A `false` status means that the API is still under training mode
- **Training duration:** The minimum configured time in hours configured in ABS AI engine to train an API. This is configured in `abs_init.js` in ABS. For more information, see [AI Engine training](#) on page 338
- **URL:** API basepath URL configured in the API JSON file. For more information, see [API JSON definition](#)
- **Host name:** Host name of the API configured in the API JSON file. For more information, see [API JSON definition](#)
- **Protocol:** The protocol configured in the API JSON file. For more information, see [API JSON definition](#)
- **API type:** API type can be `regular`, `decoy - incontext`, or `decoy-out-of-context`. For more information on deception, see [API deception environment](#) on page 247
- **Token:** A `true` status means that PingIntelligence will use OAuth tokens for reporting and attack detection. For more information, see [API JSON definition](#)
- **API Key header and API key query string (QS):** The API Key values configured in the API JSON file and used for reporting and attack detection.. For more information, see [API JSON definition](#)
- **Cookie:** The cookie value configured in the API JSON file and used for reporting and attack detection. Displays blank, if cookie was not configured in API JSON. For more information, see [API JSON definition](#)
- **Servers:** The backend API server configured in the API JSON file - "\*" supports all the host names. For more information, see [API JSON definition](#)

Using the toggle button , you can hide or display information for the API in the PingIntelligence Dashboard. This provides the flexibility to display only selected APIs. Even if an API is hidden from the API dashboard, the dashboard engine keeps fetching API data from ABS AI engine. The hidden API is moved to the end of list. If the APIs are paginated, the hidden APIs are moved to the last page. When you toggle

the button to display a hidden API, the Dashboard displays data for the API on the Dashboard. You can also go to the dashboard for the API by clicking the API analytics icon .



## Administering API groups

This topic discusses administrative tasks associated with your API groups.



Before you begin

- Make sure you have admin user privileges to administer the API groups in the dashboard.

About this task

You can perform the following administrative operations on API groups:

- [Creating and deleting API groups](#) on page 537
- [Adding, deleting, and moving APIs](#) on page 538
- [Merging a user-defined API group into the default API group](#) on page 539
- [Searching or sorting API groups and APIs](#) on page 539


 **Note:** A successful execution of these operations is followed by a success notification. Click the  button on the top-right corner to reflect the changes made to the API groups.





## Creating and deleting API groups

### Steps

- To create an API group, click **Create New API group** on the top-right corner. Fill in the following details for the new API group, and click **Save**:
  - GROUP NAME: The display name of the API group.
  - GROUP DESCRIPTION: Additional information about the API group.
  - CUSTOM ATTRIBUTE KEY: The metadata key for the API group.
  - CUSTOM ATTRIBUTE VALUE: Metadata about the API group. This can be used in search operations.




- To edit an API group click  icon. You can modify the metadata of the group.
- To delete an API group, click  icon on the bottom-right corner of the API group. APIs in the group that are not part of any other API groups, will be added to the default API group. You cannot delete the default API group.

## Adding, deleting, and moving APIs


You can add, delete, or move an API from an API group.

### Steps


- To add an API to group, click **Add APIs** on the top-right corner of the API group. Select the API from the **Add APIs to the Group** pop-up and click **Submit**. You can select more than one API and add them to a group in one instance.



- To delete an API from an API group, click **Move API**. Select **Delete API** in the **Move/Delete from the Group** pop-up. Now click **Submit**. After an API which does not belong to any other group is deleted from a group, then it automatically gets added to the default group..



- To move an API to a different API group, click **Move API**. Select **Move API** in the **Move/Delete from the Group** pop-up. Now select the target API group and click **Submit**. You can move the API to more than one target API groups. Once the API is moved it'll no longer be part of that API group.



## Merging a user-defined API group into the default API group

You can convert a user-defined API group in to the default API group, by completing the following steps:

### Steps


1. Click **SETTINGS**.
2. On the left pane, Click **API Grouping Settings**.
3. From the **SELECT GROUP** list, select the API group that you want to move to the default group.
4. Click **Save**.

## Searching or sorting API groups and APIs

### Steps


- You can search for a specific API in an API group or across multiple API groups. For quick and easy retrieval, when you search at the API group level, you can filter your search based on **Group name**, **Attribute**, or **API**. When API is chosen for filtering, only non- empty API groups are loaded.

- You can sort API groups based on **Group name**, **Group creation date**, or **Last modified**



date.

- You can also sort the APIs within an API group based on **Creation date** or **Training start date**.




## Discovered APIs

API discovery is a process to discover APIs in your API environment. The discovery process involves all PingIntelligence components.


- ASE** - A `root` API is defined in ASE for the discovery process to start. The `root` API access log data is sent to ABS AI engine for processing.

- **ABS AI engine** - The ASE access logs are processed to discover APIs in your environment.
- **Dashboard** - Displays, manages, and renders the discovered APIs. Dashboard allows you to edit the discovered APIs and publish them to ASE. To view the APIs discovered from your API ecosystem, navigate to **Discovered APIs** in the Dashboard as shown in the screenshot below.



## Configure API discovery

To customize the discovery process, configure the discovery parameters on the Dashboard. Navigate to **Discovered APIs > Settings** as shown in the screenshot below.



Discovery settings consists of the following three parts:

- **Mode** - Configure the mode in which APIs are published to ASE. The mode can be **Manual** or **Auto**

**Note:** When PingIntelligence is deployed on cloud Mode is always set to Manual.


- **Discovery Configuration** - Switch discovery ON or OFF, configure the subpath depth of the API base path and discovery interval.
- **Default API Properties** - Configure the default properties of discovered APIs. You can edit the properties of an individual API in manual mode before publishing it to ASE.

The following sections explain each parts of Discovery settings in detail.


## Mode

Configure the mode in which Dashboard publishes the discovered APIs to ASE. The two modes are:

- **Manual mode** - In the manual mode, you can review the discovered APIs, edit the properties of the APIs and then publish one or more APIs to ASE. For more information on editing the discovered APIs, see [Edit the discovered APIs](#) on page 545.



- **Auto mode** - In the auto mode, Dashboard automatically publishes the APIs to ASE after a configured time interval. In auto mode, if you edit an API, it is published to ASE in the subsequent interval. Configure the following for auto mode:
  - **Polling Interval** - The time interval at which Dashboard publishes APIs to ASE. It is a good practice to have a minimum of a 10-minute interval.
  - **Delete non-discovered APIs** - When enabled, any APIs manually added to ASE are deleted.



- **ASE Deployment** - Displays the ASE deployment mode - inline or sideband. The deployment mode is configured in the `/pingidentity/webgui/config/webgui.properties` file. Here is a snippet of the `webgui.properties` file to configure the ASE deployment mode.

```
### ase properties
# ASE management url
pi.webgui.ase.url=https://localhost:8010
# ASE mode: valid values: inline or sideband
pi.webgui.ase.mode=inline
```

```
pi.webgui.ase.access-key=OBF:AES:NuZ4O93cWBKyKDFOFINHeBew8sQ:eu//
E2CIObNNGvFOfHrLuAuec4WvN4yZsThAea4iBLA=
pi.webgui.ase.secret-key=OBF:AES:NuZ4O93cWBKyKDFOFINHeBew8sQ:eu//
E2CIObNNGvFOfHrLuAuec4WvN4yZsThAea4iBLA=
```

**Note:** When PingIntelligence is deployed on cloud `pi.webgui.ase.mode` is always set to `inline` mode. However, when PingIntelligence is deployed on on-prem, make sure that the ASE mode configured in `webgui.properties` matches the configuration in `pingidentity/ase/config/ase.conf` file in ASE.

## Discovery Configuration

Configure enabling or disabling discovery from the **Discovery Configuration** tab by toggling the **AI Engine Discovery** button. Configure the following:

- **Discovery Source** - Dashboard can discover APIs from three sources, ABS AI engine, PingAccess, and Axway API gateway. The discovery source is configured in the `/pingidentity/webgui/config/webgui.properties` file. Following is a snippet of the `webgui.properties` file for configuring the discovery source.

```
### api discovery properties
# discovery source
# valid values: abs, axway and pingaccess
# for axway and pingaccess, see config/discovery.properties
pi.webgui.discovery.source=abs
```

When the API discovery source is PingAccess or Axway, configure the gateway management URL and credentials in the `/pingidentity/webgui/config/discovery.properties` file. Following is a snippet of the `discovery.properties` file for configuring the credentials.

```
### Axway API Gateway config. Only valid if
pi.webgui.discovery.source=axway
# API Manager URL
axway.management.url=https://127.0.0.1:8075/
# API Manager admin username
axway.management.username=username
# API Manager admin password
axway.management.password=xxxxxxx

### PingAccess config. Only valid if pi.webgui.discovery.source=pingaccess
# Admin URL
pingaccess.management.url=https://127.0.0.1:9000/
# Admin username
pingaccess.management.username=username
# Admin password
pingaccess.management.password=xxxxxx
```

- **AI Engine Discovery** - Toggle the button to start or stop API discovery. Make sure a root API is configured in ASE for the AI engine to discover APIs. For more information on discovery process, see [API discovery and configuration](#) on page 347.
- **AI Engine Subpath Depth** - Defines the number of subpaths used to uniquely discover the base path of a new API. The maximum allowed value is 6 when ASE is deployed in inline mode and it is 10 when ASE is deployed in sideband mode. For more information, see [Discovery Subpaths](#) on page 351.
- **AI Engine Discovery Update Interval** - Defines the time interval at which new discovered APIs are updated in the Dashboard. The minimum value is 1-hour.

PingIntelligence  
for APIs

MAIN SETTINGS Administrator

SETTINGS

Discovery Settings

API Grouping Settings

## Discovery Settings

Mode | Discovery Configuration | Default API Properties

---

SETTINGS


DISCOVERY SOURCE  
AI ENGINE

AI ENGINE DISCOVERY

AI ENGINE SUBPATH DEPTH  
1

AI ENGINE DISCOVERY UPDATE INTERVAL  
1 hours

Save

  
Copyright © 2019-2021  
Ping Identity Corporation.  
All rights reserved.  
Version: 4.4

### Default API Properties

You can configure the default API JSON properties from this tab. These properties apply to all the discovered APIs. You can edit the properties of the discovered APIs in the manual mode before publishing to ASE. For more information on the API properties, see [Define an API JSON](#)



**Discovery Settings**

Mode | Discovery Configuration | Default API Properties

**PROFILE**

API MEMORY SIZE: 16 MB | ENABLE BLOCKING:

**SERVER HEALTH CHECK**

SERVER HEALTH CHECK:

**RATE LIMITING**

CLIENT SPIKE THRESHOLD: 0 second | SERVER CONNECTION QUEUEING:

**PATTERN ENFORCEMENT**

PROTOCOL ALLOWED: | CONTENT TYPE ALLOWED: \*Custom | METHODS ALLOWED: |

PATTERN ENFORCEMENT ERROR MESSAGE

Save

API CODE	ERROR DEFINITION	ERROR MESSAGE BODY

## Edit the discovered APIs

You can edit the discovered APIs from the **Discovered APIs** page. To edit an API, click on the buttons as shown in the next two screenshots.

### Step 1

**Discovered APIs**

Search APIs | Filters | Refresh

17 Discovered APIs | By Discovered Date | Export All | Publish All

« 1 2 »

API ID	API Name	DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete
		DISCOVERED	Export	Publish	Delete

### Step 2

You can download the API definition in `.json` format by clicking on **Export**. Click **Publish** to add API to PingIntelligence and begin the training process. You will be notified on successful publication of the API

PingIntelligence for APIs

MAIN SETTINGS Administrator

Discovered APIs

Search APIs Filters Refresh

17 Discovered APIs | By Discovered Date Export All Publish All

1 2

malls-api\_shopping\_asia\_india\_bangalore\_mall\_movie  
URL: /shopping/asia/india/bangalore/mall/movie - Hostname: malls-api

DISCOVERED Export Publish

hotel-api\_hotel\_asia\_india\_bangalore\_lunch\_veg  
URL: /hotel/asia/india/bangalore/lunch/veg - Hostname: hotel-api

DISCOVERED Export Publish

music-api\_category  
URL: /category - Hostname: music-api

DISCOVERED Export Publish

COOKIE NAME:  
ACCESS TOKEN: false  
API KEY IN QUERY STRING:  
API KEY IN HEADER:  
LOGIN URL:  
ENABLE BLOCKING: false

2

The edit API page is displayed when you click on the edit button as shown in step 2.

PingIntelligence for APIs

MAIN SETTINGS Administrator

music-api\_category

Profile Servers Inline Security

Reset to default discovery config

RATE LIMITING

CLIENT SPIKE THRESHOLD

0 second

SERVER CONNECTION QUEUEING

PATTERN ENFORCEMENT

PROTOCOL ALLOWED CONTENT TYPE ALLOWED METHODS ALLOWED

\*Custom

URL MAPPING

INTERNAL URL

PATTERN ENFORCEMENT ERROR MESSAGE

ERROR CODE ERROR DEFINITION ERROR MESSAGE BODY

Save Reset

Ping  
Copyright © 2013-2021  
Ping Identity Corporation.  
All rights reserved.  
Version: 4.4

The edit API page allows you to set properties of an API JSON file. These are the same properties that you configure when you define an API JSON in ASE. For more information on defining an API JSON, see [Define an API JSON](#). You can also reset the edited changes by clicking on the **Reset to default discovery config** button on the top-right corner. This resets the API properties to the one that was set during the [Configure API discovery](#) on page 541 step. The edit API page is divided into three tabs.

## Profile

PROFILE

API ID  
[Redacted]

HOST NAME <sup>?</sup>  API BASE PATH URL

COOKIE <sup>?</sup>  
[Redacted]

ACCESS TOKEN

API KEY IN QUERY STRING  API KEY IN HEADER

LOGIN URL

API MEMORY SIZE  MB  ENABLE BLOCKING

### SELECT

JWT  Username Header

**Note:** The **Profile** tab also provides option to extract the username from either a JWT token or a custom header. On the dashboard you can select either **JWT** or **Username Header** to configure API JSON, but not both. For more information, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.

## Servers

SERVERS

SERVER	PORT	SERVER SPIKE THRESHOLD	SERVER CONNECTION QUOTA	
127.0.0.1	5000	0/SECOND	0	
<input type="text"/>	<input type="text"/>	<input type="text"/> <input type="text"/> minute <input type="text"/>	<input type="text"/>	<input type="button" value="+ Add"/>

SERVER SETTINGS

SERVER SSL

SERVER HEALTH CHECK

SERVER HEALTH CHECK

- **Inline Security**

RATE LIMITING		
CLIENT SPIKE THRESHOLD		
0	↑	second ↓
SERVER CONNECTION QUEUEING		
<input type="checkbox"/>		
PATTERN ENFORCEMENT		
PROTOCOL ALLOWED	CONTENT TYPE ALLOWED	METHODS ALLOWED
<input type="text"/>	*Custom	<input type="text"/>
URL MAPPING		
INTERNAL URL		
<input type="text"/>		
PATTERN ENFORCEMENT ERROR MESSAGE		
ERROR CODE	ERROR DEFINITION	ERROR MESSAGE BODY
<input type="text"/>	<input type="text"/>	<input type="text"/>

## Viewing and managing Indicators of Attack

---

Attack management provides a consolidated view of Indicators of Attack(IoAs) and enables efficient management of attacks on a per client basis.


Before you begin

- Make sure you have admin user privileges to view the Attack Management dashboard.

Steps


- Click on the **Attack Management** tab on the left pane. By default the Attack Management page retrieves the Indicators of Attack(IoAs) for all client identifier types - IP address, Cookie, Token, API

Key, and Username. However, you can also specify individual client identifier types in **CLIENT IDS** to get details on specific client IDs.



**Note:** For on-premise Dashboard deployments, you can configure the number of IoAs that can be fetched for a client identifier using the `pi.webgui.ioclisting.fetchsize` parameter in `<pi_install_dir>/webgui/config/webgui.properties` file. For more information, see [Configure WebGUI properties - webgui.properties](#) on page 479.


- Get the information for desired time periods by selecting the time ranges from the **QUICK DATES** list. In addition to quick time ranges like last one, seven, or 30 days, you can also specify a custom time period.





**Note:** When the **Attack Management** loads for the first time, the **QUICK DATE** list defaults to **Last 1 Day**.


- Apply the following filters on the search results:
  - REVIEWED**- Specify the IoA review status for a client identifier.
  - APIs**- Enter the APIs for which the IoA details are to be retrieved.
  - IoA TYPE**- Specify the IoA type.

- Sort the results based on the following:
  - Detected Time**- The most recent IoA for each client identifier.
  - IoA Count**- The count of IoA for each client identifier.



- To get more information on the Indicators of Attack for a client identifier, click the **Expand**  icon. You can see details like the attack detection time, the number of IOAs for the client identifier, the impacted APIs, and whether the client identifier is on the active blacklist.





- Click the  icon to remove the client identifier from blacklists and unblock it. The operation deletes the client identifier from the PingIntelligence API Security Enforcer (ASE) and ABS (API Behavioral Security) AI engine blacklists.


**Note:** If ASE is not configured to synchronize its blacklist with ABS's blacklist, then the following warning message appears while unblocking the client identifier.

```
ASE
warning :- <client identifier> <client identifier value> does not exist in
blacklist
For example:
warning :- ip 100.100.13.6 does not exist in blacklist
```

You can modify the `enable_abs_attack` parameter in `ase.conf` file to synchronize ASE and AI engine blacklists. For more information, see [Sideband ASE configuration - ase.conf](#) on page 162 and [Attack management in ASE](#) on page 377. You can alternatively use the CLI commands to set the parameters. For more information, see [CLI for ASE](#).

- Click the  icon to open the client activity report, and to change the review status of an Indicator of Attack, click the **Reviewed/Not Reviewed** toggle.
- When you click the number of IoAs, you get the list of Indicators of Attack detected for the client. Click **Expand**  icon to find more insights on the IoAs. For the client identifiers incorrectly flagged for

IoAs, you can click **Tune IoA Detection** to adjust the IoA threshold limits in the ABS AI engine for the particular client and all the future clients exhibiting similar access behavior.



**Note:** For more information, see [Tune thresholds for false positives](#) on page 342.

## Enabling or disabling attacks

The AI Engine detects multiple types of Indicators of Attack(IoAs) on REST APIs. Each IoA is associated with a unique attack ID. By default all the IoAs are enabled for detection. You can enable or disable detection of a specific IoA, using the **Enable/Disable Attacks** feature of **Attack Management**.

Before you begin

- Make sure you have admin user privileges to enable or disable the IoAs on APIs.

## Steps

- To access the feature click on **SETTINGS** tab and then click **Enable/Disable Attacks** on the left pane.

The screenshot shows the 'Enable / Disable Attacks' configuration page in the PingIntelligence dashboard. The left sidebar has 'Enable / Disable Attacks' selected. The main content area displays a list of attacks, each with a toggle switch and a 'Filters' icon. The attacks listed are:

Attack Name	Last Enabled Date	Status	Filters
Data Exfiltration	Tue Jun 08 16:32:16 UTC 2021	Enabled	⌵
Credential Stuffing	Tue Jun 08 16:32:36 UTC 2021	Enabled	⌵
Multi Client Login	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Stolen Cookie Attack	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Memory Attack - PUT	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Memory Attack - POST	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Cookie DoS	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Client Probing	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
DDoS Attack	Mon May 31 09:55:19 UTC 2021	Enabled	⌵
Extreme Client Activity		Enabled	⌵

**Note:** The PingIntelligence for APIs dashboard interacts with the API Behavioral Security (ABS) AI Engine, when you enable or disable an attack. If you disable an attack while the ABS AI engine is processing data, ABS may still report attacks for a few minutes. The attack type would be disabled when the next batch of data is processed. When you enable an attack from the disabled state, ABS takes a few minutes to report the API attacks. For more information, see [Enable or disable attacks in ABS](#).

- Use the toggle  button to enable or disable an IoA type. The toggle button will not be present if an IoA cannot be disabled. For example, the following attack IDs cannot be disabled as these are real-time attacks reported by ASE:
  - Attack ID 13: API DDoS Attack Type 2
  - Attack ID 100: Decoy Attack. This attack ID must be disabled from ASE.
  - Attack ID 101: Invalid API Activity. This attack ID must be disabled from ASE.
- Click on icon to know details such as the time the attack was enabled or disabled and so on. The following screenshot shows the attack details displayed.


The screenshot shows the details for the 'Data Exfiltration' attack. The details are as follows:

ATTACK ID:	1
ATTACK NAME:	Data Exfiltration
ATTACK DESCRIPTION:	Client extracted an abnormal amount of data.
ENABLED TIME:	Tue Jun 08 16:32:16 UTC 2021
IS ENABLED:	true


You will always be prompted with a confirmation notification before enabling or disabling an IoA. For example when you try to disable an IoA, you will be prompted with the following notification. Click




**Submit** to confirm. You should see a success notification whenever an attack type is enabled or disabled.



- Sort the attack types based on attack ID or Is Enabled status.



- Search based on attack name or attack ID within enabled or disabled attacks.



## Determining the training status of an API

The AI engine must be trained on an API before it can detect Indicators of Attack (IoA). Whenever a new API is added to your environment, the AI engine automatically trains on the new API before looking for any Indicators of Attack (IoAs) on it. You can view the training status of an API through PingIntelligence for APIs Dashboard.

Before you begin

- Confirm you have admin user privileges to view the Training status dashboard.
- If you're accessing PingIntelligence through PingOne platform, make sure that PingOne API Intelligence service is activated. For more information, see [Getting started with PingOne API Intelligence](#)

About this task

Check the training status of the AI engine for a given API from the Training status dashboard. When the training is complete, the AI engine will be ready to detect attacks on the API.

Steps

- Click **Training Status** on the left pane, to view the training status for an API. By default you will reach the Per API dashboard. Select the API from the drop-down list. The dashboard displays the list of Indicators of Attack (IoAs) with their training status for the selected API.


**Note:** A **Trained** status indicates that the machine learning models for the IoA are built and the AI engine can detect the IoA on the API. For more information, see [Per API attacks](#).

- Click **Download Attack Thresholds** to download the file of attack thresholds in a JSON format. For more information, see [Threshold range for Tn and Tx](#) on page 460.

The following is a sample snippet of the JSON file.

```
{
  "company" : "ping identity",
  "name" : "api_threshold",
  "description" : "This report contains threshold settings for the
specified API/Attack ID",
  "api_name" : "api1",
  "threshold" : [ {
    "id" : 1,
    "type" : "data_exfiltration_attack",
    "system" : {
      "A" : {
        "tn" : "-1",
        "tx" : "-1"
      },
      "B" : {
        "tn" : "-1",
        "tx" : "-1"
      },
      "C" : {
        "tn" : "-1",
        "tx" : "-1"
      }
    }
  }
}, <pi-thresholds.json continues..>
```


- Click the expand icon  to review further details, such as attack ID, attack description, and so on.




The screenshot shows the 'Training Status for API : api1' page in the PingIntelligence dashboard. The interface includes a sidebar with navigation options like 'Dashboard', 'APIs', 'Discovered APIs', 'Attack Management', 'License', and 'Training Status'. The main content area shows a dropdown menu for 'api1' and a 'Download Attack Thresholds' button. Below this, there is a search bar and a table of attack types with their training status.

Attack Type	Training Status	Expand Icon
ASE API DDoS Attack	Trained	⌵
Decoy API Accessed	Trained	⌵
ASE Pattern Enforcement	Trained	⌵
API DoS Attack	Trained	⌵
Unauthorized Client Attack	Trained	⌵
Header Manipulation	Trained	⌵
Query Manipulation Attack	Trained	⌵
Data Exfiltration	Untrained	⌵


- You can sort the attack types based on **Attack ID** or **Is Trained** status as shown in the the following screenshot.



- You can search and know the training status based on attack name or attack ID within attack types.



- Click the **Across API** tab for the across API training status. The status indicates if the AI engine is ready to detect attack types, which span across multiple APIs. For more information, see [Across API attacks](#). To download the attack thresholds for Across API attacks, click **Download Attack Thresholds**.



## Configuring training settings

AI training depends on a set of training parameters in the AI engine. You can configure training variables or reset the trained APIs in the AI engine from the Dashboard.

Before you begin

- Make sure you have admin user privileges to configure the training settings.
- If you're accessing PingIntelligence through PingOne platform, make sure that the PingOne API Intelligence service is activated. For more information, see [Getting started with PingOne API Intelligence](#).

### About this task

The following steps provide an overview of the different training parameters that can be configured through the Dashboard. It is recommended that you review the variables and configure the best values for your environment.

### Steps

- Click **Settings -> Training Settings** as shown in the following screenshot. By default you will reach the **Global Configuration** page.

The screenshot shows the PingIntelligence dashboard interface. At the top, there is a navigation bar with 'MAIN' and 'SETTINGS' (highlighted with a yellow box). The user is logged in as 'Administrator'. On the left sidebar, 'Training Settings' is highlighted with a yellow box. The main content area is titled 'Training Settings' and contains two tabs: 'Global Configuration' and 'Reset Training'. Under the 'Global Configuration' tab, there are two settings: 'TRAINING PERIOD' with a value of 6 and unit 'hours', and 'TRAINING UPDATE INTERVAL' with a value of 1 and unit 'hours'.

**Note:** You need admin user privileges to update the Training settings.

- You can configure the following two settings in the **Global Configuration** page.
  - TRAINING PERIOD**- The number of hours to train the AI model before it moves to attack detection mode. It is recommended that you configure the training for at least a week's duration, in a production environment.
  - TRAINING UPDATE INTERVAL**- The time interval at which continuous learning model thresholds are updated in ABS AI engine.

These variables are specified in **hours** with an allowable range of 1 to 10000. Click **Save** on the bottom-left to reflect the changes.

This screenshot is similar to the previous one but shows the 'Global Configuration' tab selected. An orange arrow points from the 'Global Configuration' tab in the sidebar to the 'Global Configuration' tab in the main content area. The settings are now: 'TRAINING PERIOD' set to 1 and unit 'hour', and 'TRAINING UPDATE INTERVAL' set to 1 and unit 'hour'.

- You can reset the training of an API or multiple APIs from the **Reset Training** page. To reset the training, select the APIs in **RESET TRAINING** and click **Go**.

**Note:** If there are any pending jobs in the ABS AI engine, the reset will fail with an error notification. You can re-run resetting after a few minutes. If the reset fails multiple times, follow the steps explained in [Resetting trained APIs in ABS](#) to manually reset the API.

The screenshot shows the 'Training Settings' page in the PingIntelligence for APIs interface. The sidebar on the left has 'Training Settings' selected. The main content area has two tabs: 'Global Configuration' and 'Reset Training'. A yellow arrow points to the 'Reset Training' tab. Below the tabs, there is a 'RESET TRAINING' section with a text input field and a 'Go' button.

#### Related links:

- [Training the ABS model](#) on page 338
- [AI Engine training variables](#) on page 339
- [Update the training variables](#) on page 341
- [Resetting trained APIs](#) on page 346

## PingIntelligence Integrations

You can integrate PingIntelligence with a variety of API platforms.

For information about integrating PingIntelligence with an API gateway, see:

- [Akana API gateway sideband integration](#) on page 558
- [PingIntelligence Apigee integration](#) on page 581
- [PingIntelligence AWS API Gateway Integration](#) on page 601
- [Axway sideband integration](#) on page 616
- [Azure APIM sideband integration](#) on page 640
- [PingIntelligence - CA API gateway sideband integration](#) on page 649
- [F5 BIG-IP PingIntelligence integration](#) on page 658
- [IBM DataPower Gateway sideband integration](#) on page 670
- [PingIntelligence - Kong API gateway integration](#) on page 677
- [Mulesoft sideband integration](#) on page 684
- [NGINX sideband integration](#) on page 698

- [NGINX Plus sideband integration](#) on page 714
- [PingAccess sideband integration](#) on page 747
- [PingFederate sideband integration](#) on page 758
- 
- [PingIntelligence WSO2 integration](#) on page 764

## Akana API gateway sideband integration

This integration guide discusses the deployment of PingIntelligence for APIs in a sideband configuration with Akana API Gateway. PingIntelligence for APIs in a sideband deployment mode integrates with Akana API Gateway to provide in-depth analytics on API traffic. A PingIntelligence policy is installed in the Policy Manager component of Akana API Gateway to pass API metadata to PingIntelligence for detailed API activity reporting and attack detection. For more information on sideband deployment, see [Sideband ASE](#) on page 160 .

PingIntelligence for APIs provides JavaScript policy that extracts API metadata from a request and response processed by Akana API Gateway. The API metadata is passed to API Security Enforcer (ASE). Here are a few highlights of the integration solution:

- Support for SSL connectivity through a valid CA signed certificate.
- Support for connection keep alive between Akana gateway and ASE, for faster processing of request and response data.
- Support for ASE-failover by provisioning a secondary ASE.
- OAuth attribute extraction and username support for OAuth enabled APIs.
- Interception of OAuth tokens sent as part of query parameters.

**Note:** Akana Gateway does not support self-signed certificates.

### PingIntelligence policies:

Three policies are made available to support the integration. They are packaged in **pi-api-akana-policy-4.x.x.tar.gz** file. The following diagram shows the directory structure for reference.

```
pingidentity
├── akana-policy
│   ├── pi_policy.js
│   ├── retain-header-policy.js
│   ├── config.js
│   └── version.txt
```


**pi\_policy.js:** This is the main PingIntelligence policy. It extracts the metadata for each API call, formats it into JSON and makes API calls to pass the metadata to ASE.

**retain-header-policy.js:** After validating a token with the OAuth server, Akana gateway deletes the incoming Authorization header. As a result, this header does not get forwarded to ASE. The retainHeader.js remedies this by capturing the deleted Authorization header and passes it to pi\_policy.js for metadata extraction. The retainHeader.js policy gets executed before pi\_policy.js.

**config.js:** This script takes ASE configuration as input from the user. The script then connects the ASE nodes and the policy.

**Note:** The retain-header.js policy needs to be attached to all OAuth enabled APIs, to ensure user information is extracted from API requests.

The following diagram shows the logical setup of PingIntelligence for APIs components and Akana API Gateway:



The traffic flow through the Akana API gateway and PingIntelligence for APIs components is explained below :

1. Client sends an incoming request to Akana API gateway.
2. PingIntelligence policy deployed on Akana API gateway is executed on the request to extract the metadata from the incoming request.
3. Akana API gateway makes an API call to send the request metadata to API Security Enforcer (ASE). The ASE checks the client identifiers such as usernames, tokens against the blacklist. If all checks pass, ASE returns a 200-OK response to the Akana API gateway. If not, a different response code is sent to Akana API gateway (400 or 403). The request information is also logged by ASE and sent to the Ping Intelligence API Behavioral Security (ABS )AI Engine for processing.
4. The Akana API gateway forwards the API requests to the backend server after the ASE processes it. If the gateway receives a 403-Forbidden response from ASE, it blocks the client. Otherwise it forwards the request to the backend server.
5. The response from the backend server is received by Akana API Gateway.
6. The PingIntelligence policy is again applied on the response to extract the metadata from the server response.
7. Akana API gateway makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing. ASE sends a 200-OK to API gateway.
8. Akana API gateway sends the response received from the backend server to the client.

## Prerequisites

Complete the following prerequisites before deploying PingIntelligence policy on Akana API gateway.

**Install PingIntelligence software:** PingIntelligence software should be installed and configured. Refer to [Automated deployment](#) or [Manual deployment](#).

**Verify that ASE is in sideband mode:** Check that ASE is in sideband mode by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

**Enable sideband authentication:** For a secure communication between Akana gateway and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

Ensure SSL is configured in ASE for client side connection using CA-signed certificate. Please refer to [Configure SSL for external APIs](#) on page 142 for more details.

**Generate sideband authentication token:** To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

**Enable connection keepalive between gateway and ASE-** Navigate to `/opt/pingidentity/ase/config/`. Set the value of `enable_sideband_keepalive` to `true` in `ase.conf` file. If the ASE is running stop it, before making the change. Start ASE after setting the value. For more information on ASE configuration, see [Sideband ASE configuration - ase.conf](#) on page 162

## Add PingIntelligence ASE APIs

This section explains the steps to add a primary and secondary ASE nodes to Akana API gateway.

**i Important:** The primary and secondary ASE APIs should **not be** exposed to external API clients. For more details on securing ASE APIs, see [Secure PingIntelligence ASE APIs](#) on page 564.

To add ASE APIs to Akana API gateway:

1. Login to **Akana portal** and click **Add API** from the **APIs** drop down list.
2. Select **I want to design my API from scratch(REST) only**.



3. Enter the following details for ASE:
  - a. Name of the API in **Name**.
  - b. Enter the Endpoint-<http/https>://<ASE-Hostname or IP>/ase.
  - c. Enable **Advanced Options**.
  - d. Enter API version in **Version ID**.
  - e. Select Pattern **Proxy** in the **Pattern** section.
  - f. Select an **Implementation**.
  - g. Select **Deployment Zones**.
4. Click **Save** after entering the details.

akana Dashboard APIs Apps More

## Add API

All APIs  
My APIs  
Add API

I want to design my API from scratch (REST only)

Name: \*  
PingIntelligence ASE

Endpoint (if known):  
https://ase.example.com

I have an OAS3/Swagger/RAML/WSDL/WADL document

Advanced Options

Version ID:  
Enter API Version

Pattern:  
 Proxy  
 Orchestration  
 Physical Service

Implementation:  
Default

5. Add 2 resources under **Resources**, one to post request metadata to ASE and another to post response metadata to ASE.

To add a resource to ASE API, open API Designer by performing below 3 steps.

- a. Navigate to the Overview page of the API.
- b. Choose **Details** from the left menu pane. The summary of the API is displayed in the details.
- c. In the **Design** section, click **Edit** to enter API Designer.

The screenshot shows the API Designer interface for the PING-ASE-PS API. The left sidebar contains 'Details', 'Documentation', and 'Admins'. The main content area is divided into sections: 'Summary' (API Description: PING-ASE-PS. Represents Ping Intelligence ASE physical endpoint.), 'Version' (v1), 'Version Notes' (PING-ASE-PS), 'Organization' (Tenant - amshargi), and 'Pattern' (Physical Service). Below this is the 'Design' section, which shows a table of resources:

Verb	Path	Operation ID	Summary
POST	/request		Post request meta data to Ping Intelligence ASE (Uday team Insta
POST	/response		Post request meta data to Ping Intelligence ASE (Uday team Insta

To add the Request resource to API

The screenshot shows the API Designer interface in the 'Resources' section. The 'Resources' table is empty, and the 'Models' section shows 'You have not created any models.'

Verb	Path	Operation ID	Summary
GET	/{path..+}	Default_Operation	

- a. Click **Add Resource** to open the **Edit Resource** window.
- b. Enter `/request` in the **Path** to post request metadata to ASE.
- c. Choose the **Verb** `POST`.
- d. Enter **Operation ID**. If the user does not provide the value, a random value is generated for Operation ID.
- e. Click **Finish** after updating the other non mandatory details like Description, Summary, and Tags.
- f. Click **Save** to reflect the changes.

**Edit Resource** [X]

Path: \*  
/request

Description:  
Post request metadata to ASE

Verb:  
POST

Operation ID: \*  
Changing the OperationID deletes the operation and creates a new operation. Any activities relating to the old operation are lost once you save.  
postRequestMetadata

Summary:  
Post request metadata to ASE

Tags:  
Enter tags here, separated by commas  
Enter tags here, separated by commas

Cancel Finish

**Note:** A default resource is created when an API is added to Akana API Gateway. This resource can be edited to add the first resource.

To add the Response resource to API

- a. Click **Add Resource** to open the **Edit Resource** window.
- b. Enter `/response` in the **Path** to post request metadata to ASE.
- c. Choose the **Verb** `POST`.
- d. Enter **Operation ID**. If the user does not provide the value, a random value is generated for Operation ID.
- e. Click **Finish** after updating the other non mandatory details like Description, Summary, and Tags.
- f. Click **Save** to reflect the changes.

**Edit Resource** [X]

Path: \*  
/response

Description:  
Post response metadata to ASE

Verb:  
POST

Operation ID: \*  
Changing the OperationID deletes the operation and creates a new operation. Any activities relating to the old operation are lost once you save.  
postResponseMetadata

Summary:  
Post response metadata to ASE

Tags:  
Enter tags here, separated by commas  
Enter tags here, separated by commas

Cancel Finish


6. Repeat steps 1- 5, and add the secondary (back-up) ASE node.

## Secure PingIntelligence ASE APIs



The primary and secondary ASE APIs, added in Akana API Gateway, should be secured from unauthorized access of external clients. To ensure this, secure the ASE APIs using the **API Consumer Application Security operational policy**. The policy allows control on the clients attempting to access the ASE APIs. Add the policy to both primary and secondary ASEs in the Akana gateway.

Complete the following steps to add API Consumer Application Security operational policy to ASE APIs::


1. Login to **Akana Policy Manager**, navigate to the **Tenant** and select the **ASE API**.
2. Click **+** to expand and select **Policies**. Click **Operational Policies** and then click **Add Policy** on the bottom-right.




3. In the **Add Policy Wizard**, select **API Consumer Application Security Policy** from **Add Policy**. Enter a **Policy Name**, click **Next** and then click **Finish** to save the policy.




4. The policy appears under **Policies** in ASE API. Click the policy. Click **Modify** in **API Consumer Application Security Policy** section.




5. Click **Apply** on the next screen without making any changes.




6. Next click **Activate Policy**.




7. Select the ASE API and click **Manage** in **Policy Attachments** section.



8. Click **Attach** on the next page, to attach the policy to ASE API.



9. In the **Attach Organization Policies** window, select the policy added from **Policies** window, and select the **<Policy Name>** checkbox in front of it. Click **Apply**.



10. Click **Close**.

11. Repeat steps 1-10, and add the policy to secondary ASE API.

## Capture ASE details

This section elaborates the steps involved to capture details of Service name, Interface name, Operation name for primary and secondary ASE nodes. The Service QName, Interface Name, and Operation Name are used in **config.js**.

To capture the above values:

1. Login to **Akana Policy Manager**, navigate through the **Organization Tree** on the left and select the **Tenant** and then the **ASE API**.

## 2. Expand the **Services** and click on the **API**.

### a. Capture Service QName.

The screenshot shows the Policy Manager interface. On the left, the Organization Tree is expanded to show the Services folder, with the service `pi-as-ase-primary_0.0.0_Sandbox` selected. On the right, the details for this service are displayed:

- Description:** pi-as-ase-primary
- Organization:** pi-as-ase-primary\_1579158781392
- Status:** Normal
- Lifecycle Stage:** -
- Version:** -
- Alerts:** 0
- User Name:** i4sUiNXVZLLJULOUJx7yeA==
- Descriptor URL:** <https://console.apiportal-smoke.akana.com:443/rest/services/uddi%3a9f5bbfb0-382f-11ea-abc0-c3dea8925eb9/defin>
- Service QName:** `{pi-as-ase-primary_0.0.0}svc_314492f1-ecdc-4184-93a0-57ee2258154b.smshargi.sandbox`
- Proxy For:** `pi-as-ase-primary_0.0.0_Sandbox_Target (uddi:9e5e9bf5-382f-11ea-abc0-c3dea8925eb9)`

Below the details, there are sections for **Advanced Properties**, **Binding Identifiers**, **Identity Profiles**, **Interfaces and Bindings**, and **Policy Attachments**.

### b. Capture Interface Name.

This screenshot is identical to the previous one, but the **Service QName** field is highlighted in blue. The value is `{pi-as-ase-primary_0.0.0}svc_314492f1-ecdc-4184-93a0-57ee2258154b.smshargi.sandbox`.

### c. Click **Operations** tab on the menu, and capture Operations Name.

The screenshot shows the Akana Policy Manager interface. On the left is the 'Organization Tree' with a list of API resources. On the right, a table displays details for the selected API 'pi-as-ase-primary\_0.0.0\_Sandbox'.

Name	Interface
postRequestMetadata	pi-as-ase-primary_Po
postResponseMetadata	pi-as-ase-primary_Po

Below the table, navigation controls show 'Page 1 of 1'.

**Note:** Repeat the above steps to capture the Service Qname, Interface Name, and Operation Name details for Secondary ASE API.

## Deploy PingIntelligence policies

Deploying PingIntelligence policies in Akana API gateway is divided into three parts:

- Adding an input script (config.js).
- Adding PingIntelligence policy and applying the policy to APIs.
- Adding RetainerHeader policy and applying the policy to APIs.

Complete the following steps to download and extract the PingIntelligence policy:

1. Download the PingIntelligence policy.
2. Extract the policies by using the following command.

```
# tar -zxvf <<file name>>
```

For example,

```
# tar -zxvf pi-api-akana-policy-4.1.1.tar.gz
```

Add Input script

Complete the following steps to add input script to API gateway:

1. Login to **Akana Policy Manager**, navigate to the **Tenant** and click **Scripts**.



2. Click **Add Script**.
3. Enter **Script Name** and **Script Description**, and click **Next**.



**POLICY MANAGER™**

### Specify Script Details

The **Add Script Wizard** allows you to build scripts for automating common tasks you may want to execute in Policy Manager.

You can build a library of reusable scripts that can be imported into a **Process** definition (via the Script Activity) or used in a **QoS** or **Operational Script Policy**.

The script configuration process involves specifying a **Script Name** and **Script Description** in the **Script Details** section, and configuring your script on the **Script Editor** page.


To continue, specify the script information and click **Next**.

**Script Details**

Script Name: ASE-Input-Parameters

Script Description: Helper Script for PingIntelligence p

4. Select **JavaScript** as **Language** from the list.
5. Copy the contents of **config.js** script provided by PingIntelligence and paste them into the **Source**.



**POLICY MANAGER™**

### Script Editor

The **Script Editor** provides the ability to define a script that can be later imported into a Process **Script Activity** or used in a **QoS** or **Operational Script** languages available in the drop-down list.

You can import an existing script by importing it to the current script definition via the **Imports** section. To accomplish this, in the **Available Scripts** section, click the script to copy it to the **Imported Scripts** section. After the script is imported it can then be referenced in the script source (e.g., samplescript(value1,value2);).

Note that only scripts that match the language type will be available for selection in the tree. The script does not return a value.

You can author **Process** related scripts using the **Policy Manager Scripting API**. Here you will find interfaces for adding alert reporting, logging capabilities, triggering process execution, and classes for holding transport header information (name/values) and holding transport headers for a message.

From the script workspace, to use a pre-defined method, type CTRL+Space, choose from the list, and then type a period (.) after the method.

When you are ready to save your script, click **Finish**.

6. Substitute the values of 'Service\_QName', 'Interface\_Name', and 'Operation\_Name' that were captured in Capture ASE details step. This needs to be performed for both primary and secondary ASE nodes. The below table lists the variables in **config.js** that needs to be populated.

Variable	Purpose
ase_token	Variable to hold ASE sideband authentication token.
primary_ase_service	Service QName for primary ASE.
primary_ase_interface	Interface name for primary ASE.
primary_ase_request_operation	Operation Name for posting Request Metadata in primary ASE.
primary_ase_response_operation	Operation Name for posting Response Metadata in primary ASE.
secondary_ase_service	Service QName for secondary ASE
secondary_ase_interface	Interface name for secondary ASE
secondary_ase_request_operation	Operation Name for posting Request Metadata in secondary ASE.
secondary_ase_response_operation	Operation Name for posting Response Metadata in secondary ASE.

Here is a sample substitution snippet for reference:

```
var ase_token = "ASE-Token-123";
/*Primary ASE Configuration*/
var primary_ase_service = "{pi-as-ase-primary_0.0.0}svc_314492f1-ecdc-4184-93a0-57ee2258154b.smshargi.sandbox";
var primary_ase_interface = "{pi-as-ase-primary_0.0.0}pi-as-ase-primary_PortType_0";
var primary_ase_request_operation = "postRequestMetadata";
var primary_ase_response_operation = "postResponseMetadata";
/*****/
/*Secondary ASE Configuration*/
var secondary_ase_service = "{pi-as-ase-primary_0.0.0}svc_314492f1-ecdc-4184-93a0-57ee2258154b.smshargi.sandbox";
var secondary_ase_interface = "{pi-as-ase-primary_0.0.0}pi-as-ase-primary_PortType_0";
var secondary_ase_request_operation = "postRequestMetadata";
var secondary_ase_response_operation = "postResponseMetadata";
```

7. Click **Finish**, and then click **Close**.

Add PingIntelligence policy

Complete the following steps to add a PingIntelligence policy to Akana gateway:

1. Login to **Akana Policy Manager** and navigate to the **Tenant**. Under **Policies** click **Operational Policies**.

2. Select **Add Policy** option. Select Policy Type as **Private Operational Script Policy** from the list and click **Next**.

**POLICY MANAGER™**

### Select Policy Creation Option

The "Select Policy Creation Option" screen allows you to add or import policies used to govern web services that are managed in Policy Manager.

Two options are provided. The "Add Policy" option allows you to add Policy Manager governance policies. The "Import Policy" option allows you to import an XML file with a standard WS-Policy format. Imported policies are used for interoperability. XML files that contain multiple policy entries will be imported as a Policy Manager "Aggregate" policy.

Click the radio button of the policy import option you would like to configure. For the "Add Policy" option, select a policy name from the "Type" drop-down list box. For the "Import Policy" option, click "Browse." The "Choose File To Upload" dialog displays. Select a file to upload and click "Open."

After you have completed your entries, click "Next."

**Policy Creation Options**

- Add Policy:**
  - select policy type -
  - API Consumer Application Security Policy
  - API User Security Policy
  - Aggregate Policy
  - Anti Virus Policy
  - Auditing Message Policy
  - Auditing Service Policy
  - Authentication Policy
  - Authorization Policy
  - CORS Policy
  - Cross Site Scripting Detection Policy
  - HTTP Caching Policy
  - HTTP Malicious Pattern Detection Policy
  - HTTP Message Validation Policy
  - HTTP Security Policy
  - JOSE Security Policy v2 (Unencoded Payload Support)
  - Message Threat Policy
  - Metrics Policy
  - OAuth Client Policy
  - OAuth Security Policy
  - OAuth10a Trusted Token Security Policy
  - Open Banking Client Validation Policy
  - Paging Policy
  - Pipeline Policy
  - Private Operational Script Policy**
  - Public Operational Script Policy
  - SPNEGO Policy
  - Schema Validation Policy
  - WS-Addressing Policy
  - WS-Auditing Message Policy
  - WS-Auditing Service Policy
  - WS-Auditing Transaction Tracking Policy
  - WS-Malicious Pattern Detection Policy
  - WS-Schema Validation Policy
  - WS-Security Asymmetric Binding Policy
  - WS-Security Message Policy
  - WS-Security Supporting Tokens Policy
  - WS-Security Symmetric Binding Policy
  - WS-Security Transport Binding Policy
  - XML Policy
  - Unknown key: siteminder.header.policy.name
  - Unknown key: siteminder.impersonation.policy.name
  - Unknown key: siteminder.login.process.policy.name
- Import Policy:**
- Choose File To Upload:**

3. Provide **Policy Name** and **Description**, click **Finish** and then click **Close**.

**POLICY MANAGER™**

### Specify Policy Details

The "Specify Policy Details" screen is used to define the following policy information:

The "Policy Details" section is used to define the "Policy Name," "Policy Key," "Description," and "Type."

The "Policy Key" field allows you to enter a custom field value. If left blank, a system value is automatically assigned.

The "Type" field displays the policy type previously selected on the "Select Policy Creation Option" screen.

Specify the policy information. After you have completed your entries, click "Finish" to continue.

**Policy Details**

<b>Category:</b>	Operational Policy
<b>Policy Name:</b>	PingIntelligence
<b>Policy Key:</b>	<input type="text"/>
<b>Description:</b>	<i>If you do not provide this field value, a system value is assigned.</i> PingIntelligence Policy
<b>Type:</b>	Private Operational Script Policy

4. Navigate to **Workbench**.

5. In the **Private Operational Script Policy** section, select the policy name and click **Modify**.

6. Click on **Imports**. Select the script added in Add Input Script step above and import it by clicking <<.
7. Select **JavaScript** as language **Language** from the list.
8. Copy the contents of **pi\_policy.js** script and paste them into **Expression** in **Source**.

**Modify Script Policy**

The **Modify Script Policy** screen allows you to update a policy using a defined script language. The script can be written in any of the languages available in the drop-down list.

You can import an existing script by importing it to the current script definition via the **Imports** section. To accomplish this, in the **Available Scripts** section select a script from the tree, then use the left arrow to copy it to the **Imported Scripts** section. After the script is imported it can then be referenced in the script source (e.g., `samplescript(value1,value2);`).

Note that only scripts that match the language type will be available for selection in the tree. The script does not return a value.

Several predefined functions and variables are available to build a policy expression that is evaluated at runtime.

From the script workspace, to use a pre-defined method, type CTRL+Space, choose from the list, and then type a period (.) after the method.

When you are ready to save your script, click **Finish**.

**Script Policy Details**

**Name:** PingIntelligence  
**Description:**

**Script Policy**

**Imports**

**Source**

**Script Language:** JavaScript

**Expression:**

```

790 Last Modified: 29-Oct-2019
791 Imports: n/a
792 Input: message (non-normalized)
793 Returns: array containing all extracted p
800 */
801
802 function getProperties(msg) {
803
804 //TEST - inspect exchange properties
805 /*var exc = messageContext.getExchange();
806 var eprops = exc.getPropertyNames();
807 for ( var eprop in Iterator(eprops) ) {
808     auditLog.debug("exchange prop: " + eprop);
809 }*/
810
811 var properties = {};
812
813 //auditLog.debug("Number of properties: " + msg.
814
815 var iterator = msg.getPropertyNames().iterator();
816 while(iterator.hasNext()) {
817     var propertyName = iterator.next();
818     properties[String(propertyName)] = String(msg.g
819 //auditLog.debug("TEMP: found property " + pr
820     msg.getProperty(propertyName) + ".");
821 }
822
823     return properties;
824
825

```

**Function:** -- Select --

9. Click **Finish** and then click **Close**.
10. In the **WorkFlow Actions** click **Activate Policy** to activate the PingIntelligence policy.


Apply the PingIntelligence policy to APIs

The PingIntelligence Policy can be applied at tenant level, org level and at individual API level. The following steps explain the process of adding a policy at API level.


1. Login to **Akana Portal**.

2. To apply policy at per API level:

- a. Click on the API name.
- b. In the left window pane, click **Implementation** on the left pane.



- c. Click **API implementation name** icon. Possible values for API implementation could be (Live/Sandbox/Development).
- d. Click **Edit** in **Policies** section.



- e. Find the PingIntelligence Policy in **Available Policies** pane Click **Attach** under **PingIntelligence** policy.
- f. Click **Save**.

# pi-ak-test-api1 - Live - Edit Policies

Filter By Category:

All

## Available Policies



**AtmosphereApplicationSecurityPolicy**

Operational Policy



**BasicAuditing**

Operational Policy



**CORSAllowAll**

Operational Policy

Add RetainHeader policy

Complete the following steps to add RetainHeader Policy to Akana Gateway:

1. Login to **Akana Policy Manager** and navigate to the **Tenant**. Under **Policies** click **Operational Policies**.
2. Select **Add Policy** option. Select Policy Type as **Private Operational Script Policy** from the list and click **Next**.

**POLICY MANAGER™**

**Select Policy Creation Option**

The "Select Policy Creation Option" screen allows you to add or import policies used to govern web services that are managed in Policy Manager.

Two options are provided. The "Add Policy" option allows you to add Policy Manager governance policies. The "Import Policy" option allows you to import an XML file with a standard WS-Policy format. Imported policies are used for interoperability. XML files that contain multiple policy entries will be imported as a Policy Manager "Aggregate" policy.

Click the radio button of the policy import option you would like to configure. For the "Add Policy" option, select a policy name from the "Type" drop-down list box. For the "Import Policy" option, click "Browse." The "Choose File To Upload" dialog displays. Select a file to upload and click "Open."

After you have completed your entries, click "Next."

**Policy Creation Options**

**Add Policy:**

Type  - select policy type -

Imp

Ch

- API Consumer Application Security Policy
- API User Security Policy
- Aggregate Policy
- Anti Virus Policy
- Auditing Message Policy
- Auditing Service Policy
- Authentication Policy
- Authorization Policy
- CDRS Policy
- Cross Site Scripting Detection Policy
- HTTP Caching Policy
- HTTP Malicious Pattern Detection Policy
- HTTP Message Validation Policy
- HTTP Security Policy
- JOSE Security Policy v2 (Unencoded Payload Support)
- Message Threat Policy
- Metrics Policy
- OAuth Client Policy
- OAuth Security Policy
- OAuth2a Trusted Token Security Policy
- Open Banking Client Validation Policy
- Paging Policy
- Pipeline Policy
- Private Operational Script Policy**
- Public Operational Script Policy
- SPNEGO Policy
- Schema Validation Policy
- WS-Addressing Policy
- WS-Auditing Message Policy
- WS-Auditing Service Policy
- WS-Auditing Transaction Tracking Policy
- WS-Malicious Pattern Detection Policy
- WS-Schema Validation Policy
- WS-Security Asymmetric Binding Policy
- WS-Security Message Policy
- WS-Security Supporting Tokens Policy
- WS-Security Symmetric Binding Policy
- WS-Security Transport Binding Policy
- XML Policy
- Unknown key: siteminder.header.policy.name
- Unknown key: siteminder.impersonation.policy.name
- Unknown key: siteminder.login.process.policy.name

3. Provide **Policy Name** and **Description**, click **Finish** and then click

**POLICY MANAGER™**

**Specify Policy Details**

The "Specify Policy Details" screen is used to define the following policy information:

The "Policy Details" section is used to define the "Policy Name," "Policy Key," "Description," and "Type." The "Policy Key" field allows you to enter a custom field value. If left blank, a system value is automatically assigned.

The "Type" field displays the policy type previously selected on the "Select Policy Creation Option" screen.

Specify the policy information. After you have completed your entries, click "Finish" to continue.

**Policy Details**

**Category:** Operational Policy

**Policy Name:**

**Policy Key:**

*If you do not provide this field value, a system value will automatically be assigned.*

**Description:**

**Type:** Private Operational Script Policy

**Close.**

4. Navigate to **Workbench**.

5. In the **Private Operational Script Policy** section, select the policy name and click **Modify**.



**RetainHeaderValue (Draft)****version:**

v2 - 10/02/2020 07:30:29

**Policy Overview****Information** | [Modify](#)

<b>Type:</b>	Private Operational Script Policy
<b>Policy Name:</b>	RetainHeaderValue <i>(urn:uuid:b7d5e23b-0d00-11ea-a91b-9d6dbab54157)</i>
<b>Version:</b>	2
<b>Description:</b>	Retains value for Authorization header and copies to X_Au
<b>State:</b>	Draft

**Private Operational Script Policy****Options** | [Modify](#)

<b>Function:</b>	Pre-policy Auditing
<b>Script Language:</b>	JavaScript
<b>Expression:</b>	

```
/* v4 Imports none. */ var msg = messageContext.getMessage(); var headerName
vHeader = msg.getTransportHeaders().get(headerName); if (vHeader) { var vHe
(vHeaderValue != "") { msg.getTransportHeaders().add("X_" + headerName, vHe
auditLog.debug("***WARNING**": no value found for header " + headerName); } }
```

6. Select **JavaScript** as language in **ScriptLanguage** from the list.
7. Copy the contents of **retain-header-policy.js** script and paste them into **Expression**.
8. Select **Pre-policy auditing** from

**Modify Script Policy**

The **Modify Script Policy** screen allows you to update a policy using a defined script language. The script can be written in any of the languages available in the drop-down list.

You can import an existing script by importing it to the current script definition via the **Imports** section. To accomplish this, in the **Available Scripts** section select a script from the tree, then use the left arrow to copy it to the **Imported Scripts** section. After the script is imported it can then be referenced in the script source (e.g., `samplescript(value1,value2)`).

Note that only scripts that match the language type will be available for selection in the tree. The script does not return a value.

Several predefined functions and variables are available to build a policy expression that is evaluated at runtime.

From the script workspace, to use a pre-defined method, type CTRL+Space, choose from the list, and then type a period (.) after the method.

When you are ready to save your script, click **Finish**.

**Script Policy Details**

Name: akretainheader-exp  
Description:

**Script Policy**

Imports

Source

Script Language: JavaScript

Expression:

```

1  /*
2  3  */
4  /* Imports none.
5  6  */
7  var msg = messageContext.getMessage();
8  var headerName = "Authorization";
9  switch(messageContext.getParameterType()) {
10 case 0:
11     auditLog.debug("Request message.");
12
13     var vHeader = msg.getTransportHeaders().get(headerName);
14     if (vHeader)
15         var vHeaderValue = new String(vHeader.getValue());
16         auditLog.debug("INFO found headerValue: " + vHeaderValue);
17
18         if (vHeaderValue != "") {
19             msg.getTransportHeaders().add("X_" + headerName, vHeaderValue);
20             auditLog.debug("INFO X_ + headerName + header added to request.");
21         } else {
22             auditLog.debug("**WARNING**: no value found for header " + headerName);
23         }
24     } else {
25         var http_request_line = new String(msg.getProperty("http-request:line"));
26         var tokenIndex = http_request_line.indexOf("access_token=");
27         if(tokenIndex == -1) {

```

Function: Pre-policy Auditing

Function.

9. Click **Finish** and then click **Close**.
10. In the **WorkFlow Actions** click **Activate Policy** to activate the RetainHeader policy.

Apply the RetainHeader policy to APIs

The RetainHeader Policy can be applied at tenant level, org level and at individual API level. The following steps explain the process of adding a policy at API level.

1. Login to **Akana Portal**.

2. To apply policy at per API level:

- a. Click on the API name.
- b. In the left window pane, click **Implementation** on the left pane.

The screenshot shows the Akana API Gateway interface. The top navigation bar includes 'Dashboard', 'APIs', 'Apps', and 'More'. The left sidebar is expanded to 'Implementations'. The main content area displays the details for 'pi-ak-test-api1'. A 'Live' implementation is shown with a green icon and the following endpoints:

- Endpoints
- https://api56370live.mtl.gateway-smoke.akana.com:443/
- https://api56370live.gateway-smoke.akana.com:443/
- http://api56370live.gateway-smoke.akana.com:80/

- c. Click **API implementation name** icon. Possible values for API implementation could be (Live/Sandbox/Development).
- d. Click **Edit** in **Policies** section.

The screenshot shows the Akana API Gateway interface. The top navigation bar includes 'Dashboard', 'APIs', 'Apps', and 'More'. The left sidebar is expanded to 'Details'. The main content area displays the details for 'pi-ak-test-api1'. The 'Implementation Name' section includes the following fields:

- Implementation Name: Live
- Description: pi-ak-test-api1
- Pattern: Proxy - [Modify target endpoints](#)
- Allow Anonymous Access: Yes
- Approval Required: No
- Debug Mode:

The 'Deployments' section shows a world map with a green dot indicating an enabled zone. Below the map, it states: "You have 1 deployment zone enabled. Enabled Zone".

The 'Policies' section shows two policies:

- DetailedAuditing Operational Policy**
- PingIntelligence Operational Policy**: Private operational script policy that is responsible for sending an incoming request and, conditionally, returned response to Ping Intelligence ASE instance for AI analysis.

- e. Find the RetainHeader Policy in **Available Policies** pane Click **Attach** under **RetainHeader** Policy.
- f. Click **Save**.

# pi-ak-test-api1 - Live - Edit Policies

Filter By Category:

All

## Available Policies



**AtmosphereApplicationSecurityPolicy**

Operational Policy



**BasicAuditing**

Operational Policy



**CORSAllowAll**

Operational Policy


## PingIntelligence Apigee integration

PingIntelligence provides a shared flow to integrate Apigee Edge with PingIntelligence for APIs platform.

The two mechanisms of calling shared flows are flow hook and flow callout policies. A flow hook in Apigee Edge applies the PingIntelligence shared flow globally to all APIs in an environment in an organization. The FlowCallout policy in Apigee Edge applies the PingIntelligence shared flow on a per API basis in an environment in an organization.

PingIntelligence provides an automated tool to deploy both flow hook and flow callout policies.

The following diagram shows the logical setup of PingIntelligence API Security Enforcer (ASE) and Apigee Edge.



Traffic flows through the Apigee Edge and PingIntelligence for APIs components as follows:

1. Incoming request to Apigee Edge from a client.
2. Apigee Edge makes an API call to send the request information to ASE.
3. ASE checks the request against a registered set of APIs and checks the origin IP, cookie, OAuth2 token or API key against the Blacklist. If all checks pass, ASE returns a 200-OK response to the Apigee Edge. If not, a different response code (403) is sent to Apigee Edge. The request information is also logged by ASE and sent to the ABS AI Engine for processing.
4. If Apigee Edge receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, the gateway optionally blocks the client. In synchronous mode, the gateway waits for a response from ASE before forwarding the request to backend server. However, if asynchronous mode is enabled, the gateway forwards the request to the backend server without waiting for the response from ASE. The ASE passively logs the request and forwards it to ABS for attack analysis. It performs attack detection without blocking of attacks.
5. Apigee Edge receives the response from the backend server.
6. Apigee Edge makes a second API call to pass the response information to ASE, which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to Apigee Edge.
8. Apigee Edge sends the response received from the backend server to the client.

## Prerequisites to deploying PingIntelligence shared flow

Confirm that the following prerequisites are met before using the PingIntelligence Apigee tool.

Confirm that the following prerequisites are met before using the PingIntelligence Apigee tool.

### Prerequisite:

- **Apigee version** - PingIntelligence 4.0 and later works with Apigee Edge Cloud 18.12.04
- The machine where the PingIntelligence Apigee tool is installed has anyone of OpenJDK versions between 11.0.2 to 11.0.6 installed.
- **PingIntelligence software installation**

PingIntelligence4.0 or later software are installed and configured. For installation of PingIntelligencesoftware, see the manual or platform specific automated deployment guides.

- **Verify that ASE is in sideband mode**

Make sure that in ASE is in `sideband` mode by running the following command in the ASE command line:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as `sideband` and start ASE.

- **Enable sideband authentication:** For a secure communication between Apigee Edge and ASE, enable sideband authentication by entering the following command in the ASE command line:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for Apigee Edge to authenticate with ASE. This token is generated in ASE and configured in the `apigee.properties` file of PingIntelligence automated policy tool. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

- **Verify the certificate in `ase.pem` in case of self-signed certificates**

Make sure that the certificate applied for ASE data port matches with the certificate present in the `ase.pem` certificate file to prevent SSL issues after policy deployment. Run the following command to obtain the certificate used in ASE data port. If the certificates do not match, paste the correct certificate in the `/opt/pingidentity/pi/apigee/certs/ase.pem` file.

```
# openssl s_client -showcerts -connect <ASE IP address>:<port no> </dev/
null 2>/dev/null | openssl x509 -outform PEM > ase.pem
```

## Downloading and installing the automated policy tool

The automated policy tool deploys both flow hook and flow callout policies.

About this task

To download and install the PingIntelligence policy tool:

Steps

1. [Download](#) the PingIntelligence policy tool to the `/opt` directory.
2. Untar the policy tool:
  - a. At the command prompt, run the following command.

```
tar -zxvf <filename>
```

The following example shows what this command could look like in your instance.

```
tar -zxvf pi-apigee-4.1.tar.gz
```

- b. To verify that the tool successfully installed, run the `ls` command at the command prompt.

You see the Ping Identity directories and the build `.tgz` file.

The following table lists the available directories.

Directory	Description
<code>bin</code>	Contains the following scripts: <ul style="list-style-type: none"> <li>▪ <code>deploy.sh</code>: The script to deploy the PingIntelligence policy.</li> <li>▪ <code>undeploy.sh</code>: The script to undeploy the PingIntelligence policy.</li> <li>▪ <code>status.sh</code>: Reports the deployment status and configured Apigee credentials.</li> </ul>
<code>certs</code>	Contains the certificate <code>ase.pem</code> file that is shipped by default with ASE. Make sure that the certificate applied for the ASE data port matches with the certificate present in the <code>ase.pem</code> certificate file for self-signed certificates.  For more information, see <a href="#">Prerequisites to deploying PingIntelligence shared flow</a> on page 582.
<code>lib</code>	<code>.jar</code> files and various dependencies. Do not edit the contents of this directory.
<code>policy</code>	Contains the shared flows: <ul style="list-style-type: none"> <li>▪ <code>request_shared_flow_custom.zip</code></li> <li>▪ <code>request_shared_flow_kvm.zip</code></li> <li>▪ <code>response_shared_flow_custom.zip</code></li> <li>▪ <code>response_shared_flow_kvm.zip</code></li> </ul>
<code>config</code>	Contains the <code>apigee.properties</code> file.
<code>logs</code>	Contains the log and status files.

- To configure the PingIntelligence policy tool after installation, edit the `apigee.properties` file and set the necessary properties.

For more information, see [About Apigee properties file configuration](#) on page 584.

## About Apigee properties file configuration

The `apigee.properties` file is required for all sideband Apigee configurations.

The properties file is used to set properties for the PingIntelligence policy tool after installation. You can optionally configure it to capture user information. You can find the file in the `/pingidentity/apigee/config/` directory.

The following tables describe the variables in the file.

### General variables

Variable	Description
<code>configuration_store</code>	Where to store the ASE token. The possible values are <code>kvm</code> and <code>custom</code> . The default is <code>custom</code> . When <code>custom</code> is chosen, the ASE token is configured inside the PingIntelligence policy and uploaded to Apigee Edge directly. When <code>kvm</code> is chosen, the ASE token is stored in the KVM store.
<code>apigee_url</code>	URL to connect to Apigee Edge.  <b>Note:</b> If your Apigee installation is on a private cloud, change the URL to the one that matches your Apigee management server API IP:Port or hostname with protocol.
<code>apigee_username</code>	The username to connect to Apigee Edge.
<code>apigee_password</code>	The password to connect to Apigee Edge.
<code>apigee_environment</code>	The target environment for the PingIntelligence shared flow.
<code>apigee_organization</code>	The target organization for the PingIntelligence shared flow.
<code>ase_host_primary</code>	The ASE primary host IP address and port or hostname and port.



Variable	Description
ase_host_secondary	<p>The ASE secondary host IP address and port or hostname and port.</p> <p><b>Note:</b> This field cannot be left empty. In a testing environment, you can provide the same IP address for primary and secondary ASE host.</p>
ase_ssl	Enable or disable SSL communication between Apigee Edge and ASE. The default value is <code>true</code> .
ase_sideband_token	Configure the ASE token generated during the <a href="#">prerequisite</a> step.

### Configuration properties to extract user information

Variable	Description
enable_oauth_policy	<p>Choose whether to use the PingIntelligence OAuth Policy to extract <code>user_info</code> or not. Possible values are <code>true</code> or <code>false</code>. The default value is <code>false</code>.</p> <ul style="list-style-type: none"> <li>When set to <code>true</code>, the PingIntelligence OAuthPolicy is executed and <code>user_info</code> is sent to ASE.</li> <li>When set to <code>false</code>, the PingIntelligence OAuthPolicy is not executed. The <code>user_info</code> is captured from an existing custom OAuthPolicy, if available, and sent to ASE.</li> </ul> <p>In both the cases, even if authorization token is deleted by the gateway, <code>user_info</code> and token information are still sent to ASE.</p> <p>For more information on PingIntelligence OAuth Policy, see <a href="#">Extract user information from access tokens</a> on page 589.</p>
enable_async	<p>Choose synchronous or asynchronous mode between the gateway and ASE. In synchronous mode, the gateway waits for a response from ASE before forwarding the request to backend server.</p> <p>If asynchronous mode is enabled, the gateway forwards the request to the backend server without waiting for the response from ASE. The ASE passively logs the request and forwards it to ABS for attack analysis. It performs attack detection without blocking of attacks. Possible values are <code>true</code> or <code>false</code>.</p>

Variable	Description
access_token_position	<p>Location of access_token in the API request. Possible values are header or queryparam. The default value is header. It is used in the OAuthPolicy.</p> <pre>access_token_position=queryparam</pre> <p><b>Note:</b> At present, Apigee supports only the Bearer prefix in an authorization header.</p>
access_token_variable	<p>A variable to hold access_token value, as shown in the following example.</p> <pre>access_token_variable=access_token =&gt; -H "access_token: Rft3dqrs56Blirls56a"</pre> <p>The default value is Authorization. It is used in the OAuthPolicy.</p>
username_key_mapping	<p>This is used in the PingIntelligence policy to set the key of username attribute in access_token info. The default value is username.</p>
client_id_key_mapping	<p>This is used in the PingIntelligence policy to set the key of client_id attribute in access_token info. The default value is client_id.</p>

### Timeout configurations

Variable	Description
connect_timeout	<p>Connection timeout in milliseconds between Apigee API gateway and PingIntelligence ASE.</p>
io_timeout	<p>Read timeout in milliseconds between Apigee API gateway and PingIntelligence ASE.</p>

Variable	Description
keepalive_timeout	<p>Connection keepalive timeout between Apigee API gateway and PingIntelligence ASE. Make sure that enable_keepalive to true in ase.conf for the keepalive configuration to take effect.</p> <div data-bbox="873 359 1468 667" style="border: 1px solid black; padding: 5px;"> <p><b>Note:</b></p> <p>Make sure that the enable_sideband_keepalive is set to true in ase.conf file for keepalive connection between Apigee API gateway and ASE.</p> <p>For more information, see <a href="#">Sideband ASE configuration - ase.conf</a> on page 162.</p> </div>

**Note:**

Backslashes (\) are not supported in username and client\_id values.

The following is a sample apigee.properties file.

```
# Copyright 2020 Ping Identity Corporation. All Rights Reserved.
# Ping Identity reserves all rights in The program as delivered.
# Unauthorized use, copying,
# modification, reverse engineering, disassembling, attempt to discover any
# source code or
# underlying ideas or algorithms, creating other works from it, and
# distribution of this
# program is strictly prohibited. The program or any portion thereof may not
# be used or
# reproduced in any form whatsoever except as provided by a license without
# the written
# consent of Ping Identity. A license under Ping Identity's rights in the
# Program may be
# available directly from Ping Identity.

# KVM Mode kvm/custom
configuration_store=custom
# Apigee management server URL
apigee_url=https://api.enterprise.apigee.com
# Apigee management server username
apigee_username=
# Apigee management server password
apigee_password=
# Apigee environment to which it should be deployed
apigee_environment=prod
# Apigee organization name
apigee_organization=

# ASE Primary Host <IP/Host>:<port>
ase_host_primary=
# ASE Secondary Host <IP/Host>:<port>
ase_host_secondary=
# ASE SSL status
ase_ssl=true
# ASE sideband authentication token
ase_sideband_token=none
```

```

# Enable OAuth Policy (allowed values: true | false)

enable_oauth_policy=false
# Enable async (allowed values: true | false)
enable_async=true

# Position of Access Token (allowed values: header | queryparam)
access_token_position=header
# access_token_position=header, access_token_variable=Authorization => -H
"Authorization: Bearer Rft3dqrs56Blirls56a"
# access_token_position=header, access_token_variable=access_token => -H
"access_token: Rft3dqrs56Blirls56a"
# access_token_position=queryparam, access_token_variable=access_token
=> ...?access_token=Rft3dqrs56Blirls56a
access_token_variable=Authorization

# username key mapping in access_token. This is the key of username in
access_token attributes
username_key_mapping=username
# client_id key mapping in access_token. This is the key of client_id in
access_token attributes
client_id_key_mapping=client_id

# connection timeout between Apigee and ASE. Value is in milliseconds
connect_timeout=5000
# read timeout between Apigee and ASE. Value is in milliseconds
io_timeout=5000
# keepalive timeout between Apigee and ASE. Value is in milliseconds
# set enable_keepalive to true in ase.conf for the below configuration to
take effect
keepalive_timeout=30000

```

**Note:**

If `configuration_store` is set to `custom`, the configuration will be embedded into the PingIntelligence policy.

If `configuration_store` is set to `kvm`, the configuration is pushed to a key-value map store while deploying the policy and is retrieved during policy execution.

## Resetting timeout configurations

You can reset the timeout configurations after you have deployed the PingIntelligence policy.

About this task

There are two ways to reset the timeout configurations:

- Undeploy the policy and reset the values in the `apigee.properties` file and redeploy the PingIntelligence policy.


For more information on undeploying the policy, see [Changing the deployed policy mode](#) on page 597.

- Update the values in the Apigee Edge Management UI.

To update the timeout configurations in the Apigee Edge Management UI:

## Steps

1. In the Apigee Edge Management UI, go to the **Sharedflows** page.
2. On the **Sharedflows** page, open **PingIntelligence-Request-SharedRule**.
3. In the left navigation pane, under **Policies**, click **ASE Service Callout-Request**.
4. Click the **Develop** tab as shown in the screenshot. .



5. Change the timeout values under **HTTPTargetConnection** and save the changes.
6. Repeat steps 4 and 5 for **PingIntelligence-Response-Shared-Rule**.

## Extract user information from access tokens

PingIntelligence for APIs provides the `OAuthPolicy.xml` policy to capture user information from the requests sent to Apigee gateway.

The policy verifies the access token from the bundled Apigee OAuth server and extracts details like username and client ID and other request metadata. It can verify access tokens provided as part of a request header or a query parameter.

The `OAuthPolicy` extracts request metadata tagged to an access token. The policy should be executed before the PingIntelligence policy that builds the ASE request message, which captures the username and client ID from the metadata extracted by `OAuthPolicy`.

The `OAuthPolicy` can be attached using a flow hook or a flow callout. For more information, see [Deploying the PingIntelligence policy for flow hook](#) on page 590 and [Deploying the PingIntelligence policy for Flow Callout](#) on page 592.

You should deploy the `OAuthPolicy.xml` using a Flow CallOut policy to leverage the flexibility of applying on a per API basis. For more information, see [Configuring PingIntelligence Flow Callout in Apigee](#) on page 593.

The following screen capture illustrates the PingIntelligence shared flow with `OAuthPolicy`.

Shared Flows > | [Project Name]

Overview > 1

Project: [Project Name] Save Revision 1 Deployment: [Deployment Name] Help for Selected Shared Flow

Navigator: PingIntelligence-Request-SharedRule

Shared Flow: default

Property Inspector: default

SharedFlow

Step	Name
Step	Key-Value-Map-Operations-Request
Step	Encrypted-Key-Value-Map-Operations-Request
Step	OAuthPolicy
Step	JavaScript-Callout-Build-Headers-Callout
Step	BuildRequestDetailMessage-Assign
Step	ASE-Service-Callout-Request

```

1 <?xml version="1.0" encoding="UTF-8" standalone="yes"?>
2 <OAuthV2 async="false" continueOnError="true" enabled="true" name="OAuthPolicy">
3   <DisplayName>OAuthPolicy</DisplayName>
4   <Properties/>
5   <Attributes/>
6   <ExternalAuthorization>false</ExternalAuthorization>
7   <Operation>VerifyAccessToken</Operation>
8   <AccessToken>request.header.access_token</AccessToken>
9   <SupportedGrantTypes/>
10  <GenerateResponse enabled="false"/>
11  <Tokens/>
12 </OAuthV2>

```

**Note:**

At present, the OAuthPolicy supports extraction of user information from access tokens generated by Apigee bundled OAuth server only.

### Configure apigee.properties file to capture the user information

Additionally set the configuration properties in `apigee.properties` file to extract the user information using the PingIntelligence OAuthPolicy. For more information, see [Configure apigee.properties file to extract user information](#).

**Note:**

If a custom OAuth policy is used in place of PingIntelligence OAuthPolicy, then configure the `enable_oauth_policy` variable in `apigee.properties` to false.

## Deploying the PingIntelligence policy

Use the PingIntelligence automated policy tool to deploy the shared flow.

Using the PingIntelligence automated policy tool, you deploy the shared flow either by the flow hook or the flow callout policy, which is configured in the command line. Choose either the included ASE self-signed certificate or a certificate authority (CA)-signed certificate.

### Deploying the PingIntelligence policy for flow hook

About this task

With a flow hook, the PingIntelligence shared flow is applied to all APIs in the environment of an organization.

## Steps

### 1. Deploy the shared flow:

- **Deploy with self-signed certificate:** To deploy the PingIntelligence policy with self-signed certificate, run the following command.

```
/opt/pingidentity/pi/apigee/bin/deploy.sh -fh
Checking Apigee connectivity
Apigee connectivity ... success
Generating policies

Deploying PI Apigee policy Flow Hook

1) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
2) PingIntelligence-Config-KVM status ... not-applicable
3) ASE Server status ... deployed
4) Truststore status ... deployed
5) Upload pem file status ... deployed
6) Cache status ... deployed
7) Request policy upload status ... deployed
8) Response policy upload status ... deployed
9) Request policy deployment status ... deployed
10) Response policy deployment status ... deployed
11) Preproxy Flow hook status ... deployed
12) Postproxy Flow hook status ... deployed

Deployment of PI Policy finished successfully
```

- **Deploy with CA-signed certificate:** To deploy the PingIntelligence policy with CA-signed certificate, run the following command.

```
/opt/pingidentity/pi/apigee/bin/deploy.sh -fh -ca

Checking Apigee connectivity
Apigee connectivity ... success
Generating policies

Deploying PI Apigee policy Flow Hook

1) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
2) PingIntelligence-Config-KVM status ... not-applicable
3) ASE Server status ... deployed
4) Truststore status ... not-applicable - running using CA signed
certificate
5) Upload pem file status ... not-applicable - running using CA signed
certificate
6) Cache status ... deployed
7) Request policy upload status ... deployed
8) Response policy upload status ... deployed
9) Request policy deployment status ... deployed
10) Response policy deployment status ... deployed
11) Preproxy Flow hook status ... deployed
12) Postproxy Flow hook status ... deployed

Deployment of PI Policy finished successfully
```

2. After you deploy the flow hook using the PingIntelligence tool, to verify the status of the deployment, run the following command.

```
/opt/pingidentity/pi/apigee/bin/status.sh
Checking Apigee connectivity
Apigee connectivity ... success
```

```
Checking the PI Apigee Policy Flow Hook deployment status
```

- 1) PingIntelligence-Config-KVM status ... not applicable
- 2) PingIntelligence-Encrypted-Config-KVM status ... not applicable
- 3) ASE target status ... deployed
- 4) Cache status ... deployed
- 5) Truststore status ... deployed
- 6) Request Policy status ... deployed
- 7) Response Policy status ... deployed
- 8) Preproxy hook status ... deployed
- 9) Postproxy hook status ... deployed

```
PI Apigee Policy is already installed
```

## Deploying the PingIntelligence policy for Flow Callout

### About this task

In the Flow Callout, the PingIntelligence policy is applied on a per API basis in the environment of an organization.

### Steps

#### 1. Deploy the shared flow:

- **Deploy with self-signed certificate:** To deploy the PingIntelligence policy with self-signed certificate, run the following command.

```
/opt/pingidentity/pi/apigee/bin/deploy.sh -fc
Checking Apigee connectivity
Apigee connectivity ... success
Generating policies

Deploying PI Apigee policy Flow Call Out

1) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
2) PingIntelligence-Config-KVM status ... not-applicable
3) ASE Server status ... deployed
4) Truststore status ... deployed
5) Upload pem file status ... deployed
6) Cache status ... deployed
7) Request policy upload status ... deployed
8) Response policy upload status ... deployed
9) Request policy deployment status ... deployed
10) Response policy deployment status ... deployed
11) Preproxy Flow call out status ... deployed
12) Postproxy Flow call out status ... deployed

Deployment of PI Policy finished successfully
```

- **Deploy with CA-signed certificate:** To deploy the PingIntelligence policy with CA-signed certificate, run the following command.

```
bin/deploy.sh -fc -ca

Checking Apigee connectivity
Apigee connectivity ... success
Generating policies

Deploying PI Apigee policy Flow Call Out
```



```

1) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
2) PingIntelligence-Config-KVM status ... not-applicable
3) ASE Server status ... deployed
4) Truststore status ... not-applicable - running using CA signed
  certificate
5) Upload pem file status ... not-applicable - running using CA signed
  certificate
6) Cache status ... deployed
7) Request policy upload status ... deployed
8) Response policy upload status ... deployed
9) Request policy deployment status ... deployed
10) Response policy deployment status ... deployed
11) Preproxy Flow call out status ... deployed
12) Postproxy Flow call out status ... deployed

```

Deployment of PI Policy finished successfully

2. After deploying the Flow Call Out using the PingIntelligence tool, to verify the status of the deployment, run the following command.

```

/opt/pingidentity/pi/apigee/bin/status.sh
Checking Apigee connectivity
Apigee connectivity ... success

Checking the PI Apigee Policy Flow Call Out deployment status

1) PingIntelligence-Config-KVM status ... not applicable
2) PingIntelligence-Encrypted-Config-KVM status ... not applicable
3) ASE target status ... deployed
4) Cache status ... deployed
5) Truststore status ... deployed
6) Request Policy status ... deployed
7) Response Policy status ... deployed
8) Preproxy call out status ... deployed
9) Postproxy call out status ... deployed

PI Apigee Policy is already installed

```

## Configuring PingIntelligence Flow Callout in Apigee

After deploying the Flow Callout policy using PingIntelligence, configure the PingIntelligence for APIs shared flow.


About this task

**Note:**


The following steps are the same for Flow Callout for both request and response.

## Steps

1. Sign on to your Apigee Edge account and select the API Proxy.




2. Click the API name for which you want to apply the policy.




The **Develop** page opens.

3. On the **Develop** page, click the **Develop** tab.




4. On the **Develop** tab, under **Proxy Endpoints**, select **PreFlow**, and click **+ Step** for request.




The **Add Step** page opens.

- On the **Add Step** page, select **Flow Callout**.
- In the **Shared Flow** list, select the **Request** rule and click **Add**.




- On the **Develop** tab, under **Proxy Endpoints**, select **PreFlow**, and click **+ Step** for response.



The **Add Step** page opens.


- On the **Add Step** page, select **Flow Callout**.

9. In the **Shared Flow** list, select the **Response** rule and click **Add**.



The request and response rules are added.

10. Click **Save**.



11. Click **default** and enter the following lines in the `<HTTPTargetConnection>` tag.

```
<Properties>
  <Property name="success.codes">1xx,2xx,3xx,4xx,5xx</Property>
```

</Properties>

Revision 1 saved  
Additional changes have been made to the revision since it was saved.

Project: shop > Develop > 1

Target Endpoint: default

Name: [ ]

Description: [ ]

HTTP Target: http://httpbin.org

Code default

```

1 <?xml version="1.0" encoding="UTF-8" standalone="yes"?>
2 <TargetEndpoint name="default">
3   <Description/>
4   <FaultRules/>
5   <PreFlow name="PreFlow">
6     <Request/>
7     <Response/>
8   </PreFlow>
9   <PostFlow name="PostFlow">
10    <Request/>
11    <Response/>
12  </PostFlow>
13  <Flows/>
14  <HTTPTargetConnections/>
15  <Properties>
16    <Property name="success_codes">1xx,2xx,3xx,4xx,5xx</Property>
17  </Properties>
18  <URL>http://httpbin.org/</URL>
19  </HTTPTargetConnections/>
20 </TargetEndpoint>

```

Property Inspector: default

Property	Value
name	default
Description	
FaultRules	
PreFlow	
Request	PreFlow
Response	
PostFlow	
name	PostFlow
Request	
Response	
Flows	
HTTPTargetConnections	
Properties	
Property	1xx,2xx,3xx,4xx,5xx
name	success_codes
URL	http://httpbin.org

12. Save the revision.

## Save Revision

Saving the revision will update all deployments, including the deployment in the prod environment. Are you sure you want to save the revision, changing the prod deployment?

Cancel
Save

## Changing the deployed policy mode

You can change the type of policy deployed from Flow Hook to Flow Callout or Flow Callout to Flow Hook using the PingIntelligencePingIntelligence policy tool.

About this task

To change the type of policy.

### Tip:

Using the following steps, you can also change the use of security certificate from self-signed to certificate authority (CA)-signed or from CA-signed to self-signed.

Steps

1. To undeploy the deployed policy, run one of the following command based on the policy and certificate used:

- Undeploy a Flow Hook policy using a self-signed certificate.

```

/opt/pingidentity/pi/apigee/bin/undeploy.sh -fh
Checking Apigee connectivity

```

```

Apigee connectivity ... success

Undeploying PI Apigee policy Flow Hook

1) Preproxy hook status ... undeployed
2) Postproxy hook status ... undeployed
3) Request policy undeployment status ... undeployed
4) Response policy undeployment status ... undeployed
5) Request policy deleting status ... deleted
6) Response policy deleting status ... deleted
7) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
8) PingIntelligence-Config-KVM status ... not-applicable
9) ASE Primary target server status ... undeployed
10) ASE Secondary target server status ... undeployed
11) Truststore status ... undeployed
12) Cache status ... undeployed

Undeployment of PI Policy finished successfully

```

- **Undeploy a Flow Hook policy using a CA-signed certificate.**

```

opt/pingidentity/pi/apigee/bin/deploy.sh -fh -ca

Checking Apigee connectivity
Apigee connectivity ... success

Undeploying PI Apigee policy Flow Hook

1) Preproxy hook status ... undeployed
2) Postproxy hook status ... undeployed
3) Request policy undeployment status ... undeployed
4) Response policy undeployment status ... undeployed
5) Request policy deleting status ... deleted
6) Response policy deleting status ... deleted
7) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
8) PingIntelligence-Config-KVM status ... not-applicable
9) ASE Primary target server status ... undeployed
10) ASE Secondary target server status ... undeployed
11) Truststore status ... not-applicable - running using CA signed
    certificate
12) Cache status ... undeployed

Undeployment of PI Policy finished successfully

```

- **Undeploy a Flow Callout policy using a self-signed certificate.**

```

/opt/pingidentity/pi/apigee/bin/undeploy.sh -fc
Checking Apigee connectivity
Apigee connectivity ... success

Undeploying PI Apigee policy Flow Call Out

1) Preproxy hook status ... undeployed
2) Postproxy hook status ... undeployed
3) Request policy undeployment status ... undeployed
4) Response policy undeployment status ... undeployed
5) Request policy deleting status ... deleted
6) Response policy deleting status ... deleted
7) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
8) PingIntelligence-Config-KVM status ... not-applicable
9) ASE Primary target server status ... undeployed

```

```

10) ASE Secondary target server status ... undeployed
11) Truststore status ... undeployed
12) Cache status ... undeployed

```

```

Undeployment of PI Policy finished successfully

```

- Undeploy a Flow Callout policy using a CA-signed certificate.

```

opt/pingidentity/pi/apigee/bin/deploy.sh -fc -ca

```

```

Checking Apigee connectivity
Apigee connectivity ... success

```

```

Undeploying PI Apigee policy Flow Call Out

```

```

1) Preproxy hook status ... undeployed
2) Postproxy hook status ... undeployed
3) Request policy undeployment status ... undeployed
4) Response policy undeployment status ... undeployed
5) Request policy deleting status ... deleted
6) Response policy deleting status ... deleted
7) PingIntelligence-Encrypted-Config-KVM status ... not-applicable
8) PingIntelligence-Config-KVM status ... not-applicable
9) ASE Primary target server status ... undeployed
10) ASE Secondary target server status ... undeployed
11) Truststore status ... not-applicable - running using CA signed
    certificate
12) Cache status ... undeployed

```

```

Undeployment of PI Policy finished successfully

```

2. To deploy the other policy, see [Flow Hook](#) or [Flow Call Out](#).

## Add API definitions to ASE

---

Add the API definition files to help ASE extract metadata from API traffic, set decoys to trap intruding attacks, perform health checks on backend servers, and so on. The API definitions also help the AI Engine to build AI models to detect any Indicators of Attacks (IoAs) on APIs.

After the policy has been deployed to Apigee using the PingIntelligence automated policy tool, add APIs to ASE. For more information on defining APIs, see:

- [API naming guidelines](#) on page 169
- [Defining an API using API JSON configuration file in inline mode](#) on page 219

For more information on ASE sideband deployment, see [Sideband ASE](#) on page 160.

## Undeploying the PingIntelligence policy

---

Using the PingIntelligence automated policy tool, you can undeploy the shared flow either by Flow Hook or the Flow Callout policy.

## Undeploying the PingIntelligence policy for Flow Hook

### Steps

- Undeploy the PingIntelligence policy:
  - Undeploy with self-signed certificate: Run the following command to undeploy the PingIntelligence policy with self-signed certificate.

```
/opt/pingidentity/pi/apigee/bin/undeploy.sh -fh
```

- Undeploy with certificate authority (CA)-signed certificate: Run the following command to undeploy the PingIntelligence policy with a CA-signed certificate.

```
/opt/pingidentity/pi/apigee/bin/undeploy.sh -fh -ca
```

## Undeploying the PingIntelligence policy for Flow Callout

### Steps

- Undeploy the PingIntelligence policy:
  - Undeploy with self-signed certificate: Run the following command to undeploy the PingIntelligence policy with self-signed certificate.

```
/opt/pingidentity/pi/apigee/bin/undeploy.sh -fc
```

- Undeploy with certificate authority (CA)-signed certificate: Run the following command to undeploy the PingIntelligence policy with CA-signed certificate.

```
/opt/pingidentity/pi/apigee/bin/undeploy.sh -fc -ca
```

## Troubleshooting mismatch of self-signed certificates

If the ASE certificate is changed after the deployment of PingIntelligence policy and it doesn't match with the certificate present in the `ase.pem` certificate file, you might encounter SSL related issues.

### About this task

To resolve these issues:

### Steps

1. Undeploy the PingIntelligence policy by following either of the two options as applicable:
  - [Undeploy PingIntelligence policy for Flow Hook with self-signed certificate](#)
  - [Undeploy PingIntelligence policy for Flow Call Out with self-signed certificate](#)
2. To obtain the correct certificate to match what's in the `ase.pem` file, run the following command.

```
# openssl s_client -showcerts -connect <ASE IP address>:<port no> </dev/
null 2>/dev/null | openssl x509 -outform PEM > ase.pem
```

3. Paste the correct certificate in the `/opt/pingidentity/pi/apigee/certs/ase.pem` file.



4. Redeploy the PingIntelligence policy by following either of the two options as applicable:

- [Deploy PingIntelligence policy for Flow Hook with self-signed certificate](#)
- [Deploy PingIntelligence policy for Flow Call Out with self-signed certificate](#)

**Note:**

Make sure that the `ase_ssl` parameter in `/pingidentity/pi/apigee/config/apigee.properties` file is set to `true`.

## AWS API gateway integration

---

### PingIntelligence AWS API Gateway Integration

---

This integration guide discusses the deployment of PingIntelligence for APIs in a sideband configuration with AWS API Gateway through CloudFront.

PingIntelligence for APIs provides a sideband policy that can be installed in CloudFront. The policy uses AWS Lambda functions to pass API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking.


PingIntelligence for APIs provides an automated tool to deploy a the policy, which is implemented using the AWS Lambda functions. The policy requires AWS CloudFront to be present with all caching disabled. AWS Lambda functions must be initially deployed in the US-East-1 region, and the policy definition is pushed to any region with your API Gateways after the PingIntelligence policy is added.

The PingIntelligence sideband policy requires a CloudFront instance, which can be an existing or new instance.

**Important:**

The default AWS Lambda memory is sufficient for up to 1000 QPS. For a larger QPS, contact PingIdentity support. See the [aws.properties](#) file for default origin response value.

The following diagram shows the logical setup of PingIntelligence ASE (API Security Enforcer) and CloudFront.



The traffic flow through the CloudFront and PingIntelligence for APIs components is as follows:

1. An incoming API client request destined for the API Gateway arrives at CloudFront.
2. A PingIntelligence AWS Lambda policy makes an API call to send the request metadata to PingIntelligence ASE.
3. ASE checks the request against a registered set of APIs and looks for the origin IP, cookie, OAuth2 token, or API key in the ABS (API Behavioral Security) AI engine generated blacklist. If all checks pass, ASE returns a 200-OK response to AWS Lambda. If the checks don't pass, ASE sends a 403 response code to AWS Lambda. The request information is also logged by ASE and sent to the ABS AI Engine for processing.
4. If CloudFront receives a 200-OK response from ASE, it forwards the client request to the backend server. Otherwise, the CloudFront blocks the client when blocking is enabled for the API.
5. CloudFront receives the response from the backend server.
6. The Lambda response function makes a second API call to pass the response information to ASE.
7. ASE receives the response information and sends a 200-OK to AWS Lambda. The response information is also logged by ASE and sent to the ABS AI Engine for processing.
8. CloudFront sends the response received from the backend server to the client.

## Prerequisites

Complete the following before running the PingIntelligence AWS policy tool.

### Prerequisite:

- Install OpenJDK 11 on the system running the PingIntelligence policy tool.
- **Install PingIntelligence software**

PingIntelligence should be installed and configured. Refer to the PingIntelligence deployment guide for your environment.

- **AWS admin account:** To deploy the PingIntelligence sideband policy, an AWS admin account is required.

**Note:** Make sure that AWS cross-account is **not** used to deploy PingIntelligence policy.

- **Update CloudFront configuration:** Verify the following options are configured correctly:
  - **Disable Caching:** The PingIntelligence policy deployment tool requires that CloudFront be available with caching disabled for all CloudFront behaviors. Select **None (Improves Caching)** from the **Cache Based on Selected Request Headers** drop-down list.
  - **TTL:** Confirm that **Minimum TTL**, **Maximum TTL**, and the **Default TTL** are set to 0
  - **Forward Cookies:** Select **All** from the drop-down list
  - **Query String Forwarding and Caching:** Select **Forward all, cache based on all** from the drop-down list

## Edit Behavior

Allowed HTTP Methods  GET, HEAD  GET, HEAD, OPTIONS  GET, HEAD, OPTIONS, PUT, POST, PATCH, DELETE ?

Field-level Encryption Config  ?

Cached HTTP Methods  GET, HEAD (Cached by default)  OPTIONS ?

Cache Based on Selected Request Headers  ?  
[Learn More](#)

Object Caching  Use Origin Cache Headers  Customize ?  
[Learn More](#)

Minimum TTL  ?

Maximum TTL  ?

Default TTL  ?

Forward Cookies  ?

Query String Forwarding and Caching  ?

Smooth Streaming  Yes  No ?

Restrict Viewer Access (Use Signed URLs or Signed Cookies)  Yes  No ?

Compress Objects Automatically  Yes  No ?  
[Learn More](#)

- **Lambda function:** PingIntelligence policy tool requires viewer request and origin response Lambda functions. Make sure that there is no viewer request or origin response Lambda function defined in the caching behavior.
- **Verify that ASE is in sideband mode**

Check if ASE is in `sideband` mode by running the following command in the ASE command line:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
```

```
abs : enabled, ssl: enabled
abs attack : disabled
audit : enabled
sideband authentication : disabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40 MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

- **Enable sideband authentication:** For a secure communication between CloudFront and ASE, enable sideband authentication by entering the following command in the ASE command line:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for CloudFront to authenticate with ASE. This token is generated in ASE and configured in the `aws.properties` file of PingIntelligence automated policy tool. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

**Note:** For improved performance, you can optionally set the `enable_sideband_keepalive` parameter to `true` in `ase.conf` file. For more information, see [Sideband ASE configuration - ase.conf](#) on page 162.

## Configure automated policy tool

### Download

Complete the following steps to download and install the PingIntelligence policy tool:

1. [Download](#) the PingIntelligence policy tool to the `/opt` directory.
2. Complete the following steps to untar the policy tool:
  - a. At the command prompt, type the following command to untar the policy tool file:

```
tar -zxvf <filename>
```

#### For example:

```
tar -zxvf pi-aws-4.0.tar.gz
```

- b. To verify that the tool successfully installed, type the `ls` command at the command prompt. This should list the `pingidentity` directory and the `build.tgz` file.

The following table lists the directories:

Directory	Description
-----------	-------------

bin	Contains the following scripts: <ul style="list-style-type: none"> <li>▪ <code>deploy.sh</code>: The script to deploy the PingIntelligence policy.</li> <li>▪ <code>undeploy.sh</code>: The script to undeploy the PingIntelligence policy.</li> <li>▪ <code>status.sh</code>: Reports the deployment status of IAM role and Lambda function.</li> </ul>
lib	Jar files and various dependencies. Do not edit the contents of this directory.
policy	Contains the request and response Lambda functions: <ul style="list-style-type: none"> <li>▪ <code>request_lambda.zip</code></li> <li>▪ <code>response_lambda.zip</code></li> </ul>
config	Contains the <code>aws.properties</code> file.
logs	Contains the log and status files.

#### Configure the automated tool

Configure the `aws.properties` file available in the `/pingidentity/pi/aws/config/` directory. The following table describes the variables in the `aws.properties` file:

Variable	Description
mode	Choose the authentication mode between <code>keys</code> and <code>role</code> <p><b>Note:</b> If you running the PingIntelligence policy tool from your local machine, use the <code>keys</code> mode. If you are running the tool from an EC2 instance, use the <code>rolemode</code>.</p>
access_key	AWS access key. This is applicable when the mode is set to <code>keys</code>
secret_key	AWS secret key. This is applicable when the mode is set to <code>keys</code>
aws_lambda_memory	AWS Origin Response Lambda memory in MB. Default value is 1024 MB. The memory can be configured in multiple of 64. Minimum and maximum value are 128 and 3008 respectively. For more information, see <a href="#">AWS Lambda Pricing</a>
cloudfront_distribution_id	The CloudFront distribution ID.
ase_host_primary	The ASE primary host IP address and port or hostname and port

ase_host_secondary	<p>The ASE secondary host IP address and port or hostname and port. ASE secondary host receives traffic only when the primary ASE host is unreachable.</p> <p><b>Note:</b> This field cannot be left blank. In a testing environment, enter the same IP address for primary and secondary ASE host.</p> <p>If both the ASE hosts are unreachable, the request is directly sent to the backend API server.</p>
ase_ssl	<p>Enable or disable SSL communication between Lambda functions and ASE. The default value is true.</p>
ase_sideband_token	<p>Enter the ASE token generated during the <a href="#">prerequisite</a> step.</p>

Following is a sample `aws.properties` file:

```
# Copyright 2019 Ping Identity Corporation. All Rights Reserved.
# Ping Identity reserves all rights in The program as delivered.
# Unauthorized use, copying,
# modification, reverse engineering, disassembling, attempt to discover any
# source code or
# underlying ideas or algorithms, creating other works from it, and
# distribution of this
# program is strictly prohibited. The program or any portion thereof may not
# be used or
# reproduced in any form whatsoever except as provided by a license without
# the written
# consent of Ping Identity. A license under Ping Identity's rights in the
# Program may be
# available directly from Ping Identity.

#Authentication mode access-key & secret-key / role based access. Values can
# be keys or role.
mode=keys
#AWS access key
access_key=AKIAID7MDWSCUUVHMTNA
#AWS secret key
secret_key=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
#AWS Lambda memory in MB. It should be a multiple of 64. Minimum and maximum
# value are 128 and 3008 respectively.
aws_lambda_memory=1024
#Cloudfront distribution ID
cloudfront_distribution_id=EGQ9OEG3ZDABP

#ASE Primary Host <IP/Host>:<port>
ase_host_primary=test.elasticbeam.com
#ASE Secondary Host <IP/Host>:<port>
ase_host_secondary=test.elasticbeam.com
#ASE SSL status
ase_ssl=true
#ASE sideband authentication token
ase_sideband_token=283ded57cd5f48e6bcd8fa3ba9d2888d
```

## Create Role

If you have set the authentication mode as `role` in the `aws.properties` file, create a role for the EC2 instance. This role is required for the PingIntelligence policy deployment tool. Complete the following steps to create and configure.


1. Select EC2 as service and click on **Next: Permissions** button:

The screenshot shows the AWS IAM console 'Create role' wizard. The top navigation bar includes the AWS logo, 'Services', 'Resource Groups', and a search icon. The main heading is 'Create role' with a progress indicator showing four steps, with step 1 being the current step. Below the heading is the section 'Select type of trusted entity' with four options: 'AWS service' (selected), 'Another AWS account', 'Web identity', and 'SAML 2.0 federation'. Below this is the section 'Choose the service that will use this role' with a list of services. 'EC2' is selected. At the bottom right, there are 'Cancel' and 'Next: Permissions' buttons.


**1** **2** **3** **4**

### Create role


#### Select type of trusted entity




**AWS service**  
EC2, Lambda and others



**Another AWS account**  
Belonging to you or 3rd party



**Web identity**  
Cognito or any OpenID provider



**SAML 2.0 federation**  
Your corporate directory

Allows AWS services to perform actions on your behalf. [Learn more](#)

#### Choose the service that will use this role

**EC2**  
Allows EC2 instances to call AWS services on your behalf.

**Lambda**  
Allows Lambda functions to call AWS services on your behalf.

API Gateway	CodeBuild	EKS	Lambda	SMS
AWS Backup	CodeDeploy	EMR	Lex	SNS
AWS Support	Config	ElastiCache	License Manager	SWF
Amplify	Connect	Elastic Beanstalk	Machine Learning	SageMaker
AppSync	DMS	Elastic Container Service	Macie	Security Hub
Application Auto Scaling	Data Lifecycle Manager	Elastic Transcoder	MediaConvert	Service Catalog
Application Discovery Service	Data Pipeline	ElasticLoadBalancing	OpsWorks	Step Functions
Auto Scaling	DataSync	Glue	RAM	Storage Gateway
Batch	DeepLens	Greengrass	RDS	Transfer
CloudFormation	Directory Service	GuardDuty	Redshift	Trusted Advisor
CloudHSM	DynamoDB	Inspector	Rekognition	VPC
CloudTrail	EC2	IoT	S3	WorkLink
CloudWatch Events	EC2 - Fleet	Kinesis		

**\* Required** Cancel **Next: Permissions**

2. Choose the following three Policies and provide a name for each role (for example, PIDeploymentToolRole):

- IAMFullAccess
- AWSLambdaFullAccess
- CloudFrontFullAccess
- AmazonEC2FullAccess

After providing the name, click on **Create role**.

aws
Services ▾
Resource Groups ▾
🔔

## Create role

1
2
3
4

### Review

Provide the required information below and review this role before you create it.

**Role name\***

Use alphanumeric and '+,=,@-\_' characters. Maximum 64 characters.

**Role description**

Maximum 1000 characters. Use alphanumeric and '+,=,@-\_' characters.

**Trusted entities** AWS service: ec2.amazonaws.com

**Policies**

- 📦 [IAMFullAccess](#) ↗
- 📦 [CloudFrontFullAccess](#) ↗
- 📦 [AWSLambdaFullAccess](#) ↗
- 📦 [AmazonEC2FullAccess](#) ↗

**Permissions boundary** Permissions boundary is not set

The new role will receive the following tag

Key	Value
PI	PIAWS

**\* Required**

Cancel
Previous
Create role



- In the Summary page of the role that you created in step 2, click on the **Trust relationships** tab and then click on **Edit trust relationship** button:

The screenshot displays the AWS IAM console interface. At the top, the AWS logo is on the left, and navigation menus for 'Services' and 'Resource Groups' are on the right. A search bar labeled 'Search IAM' is positioned above a vertical sidebar containing navigation links: Dashboard, Groups, Users, Roles (highlighted with an orange bar), Policies, Identity providers, Account settings, Credential report, and Encryption keys. The main content area shows the breadcrumb 'Roles > PIDeploymentToolRole' followed by the 'Summary' heading. Below the heading, there are tabs for 'Permissions', 'Trust relationships' (which is active and highlighted with an orange bar), and 'Tags'. A blue button labeled 'Edit trust relationship' is prominently displayed. Underneath, the 'Trusted entities' section is introduced with the text 'The following trusted entities can assume this role.' A yellow highlighted box contains the heading 'Trusted entities' and lists two entities: 'The identity provider(s) ec2.amazonaws.com' and 'The identity provider(s) lambda.amazonaws.com', each separated by a dashed line.

4. In the **Edit Trust Relationship** page, enter the following lines and click on **Update Trust Policy**:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Effect": "Allow",
      "Principal": {
        "Service": "ec2.amazonaws.com"
      },
      "Action": "sts:AssumeRole"
    },
    {
      "Effect": "Allow",
      "Principal": {
        "Service": "lambda.amazonaws.com"
      },
      "Action": "sts:AssumeRole"
    }
  ]
}
```

```
}
```



Services ▾

Resource Groups ▾



## Edit Trust Relationship


## Edit Trust R

You can customize trust

### Policy Document

```
1 {  
2   "Versio  
3   "Statem  
4   {  
5     "Ef  
6     "Pr  
7     "  
8     },  
9     "Ac  
10  },  
11  {  
12     "Ef  
13     "Pr  
14     "  
15     },  
16     "Ac  
17  }  
18 ]  
19 }
```

5. Configure the **IAM role**, as the role that you created (for example,


Services ▾
Resource Groups ▾

1. Choose AMI
2. Choose Instance Type
3. Configure Instance Details

## Step 3: Configure Instance Details

Configure the instance to suit your requirements. You can launch

<b>Number of instances</b> ⓘ	<input type="text" value="1"/>
<b>Purchasing option</b> ⓘ	<input type="checkbox"/> Request Spot Instance
<b>Network</b> ⓘ	<input type="text" value="vpc-5e1115"/>
<b>Subnet</b> ⓘ	<input type="text" value="No preference"/>
<b>Auto-assign Public IP</b> ⓘ	<input type="text" value="Use subnet"/>
<b>Placement group</b> ⓘ	<input type="checkbox"/> Add placement group
<b>Capacity Reservation</b> ⓘ	<input type="text" value="Open"/>
<b>IAM role</b> ⓘ	<input style="border: 2px solid blue;" type="text" value="PIDeploymentRole"/>
<b>Shutdown behavior</b> ⓘ	<input type="text" value="Stop"/>
<b>Enable termination protection</b> ⓘ	<input type="checkbox"/> Protect against accidental termination
<b>Monitoring</b> ⓘ	<input type="checkbox"/> Enable CloudWatch Agent <a href="#">Additional configuration</a>
<b>Tenancy</b> ⓘ	<input type="text" value="Shared - Run instances on hardware shared with other users"/> <a href="#">Additional configuration</a>
<b>Elastic Inference</b> ⓘ	<input type="checkbox"/> Add an Elastic Inference Accelerator <a href="#">Additional configuration</a>

## Deploy PingIntelligence Policy for AWS

Using the PingIntelligence AWS policy tool, deploy the PingIntelligence policy in AWS @Lambda in the North Virginia (US-East-1) region. The Lambda function pushes the PingIntelligence policy to the Amazon CloudFront in the local AWS instances. The PingIntelligence Lambda policy communicates with PingIntelligence ASE to pass request and response metadata and check whether the client request should be blocked or passed to the AWS gateway.

**Note:** At present, the policy must be initially deployed in North Virginia (US-East-1) region.

To deploy the PingIntelligence policy, run the following command:

```
/opt/pingidentity/pi/aws/bin$ deploy.sh -ca

Deploying PI AWS Policy with CA-signed certificate

1) Create IAM Role named PI-Role - status... done
2) Create a policy named LambdaEdgeExecution-PI - status... done
3) Attach LambdaEdgeExecution-PI Policy to Role PI-Role... done
4) Generating policy... done
5) Deploying PI-ASE-Request Lambda... done
6) Fetching PI-ASE-Request Lambda version... done
7) Deploying PI-ASE-Response Lambda... done
8) Fetching PI-ASE-Response Lamda version... done
9) Deploying PI-ASE-Request Lamda CloudFront... done
10) Deploying PI-ASE-Response Lambda CloudFront... done

Successfully deployed PI AWS Policy.
```

When the `deploy.sh` script is run without `ca` option, the policy is deployed using the self-signed certificate which is included in the PingIntelligence policy. By the running the policy tool, the following two policies are deployed:

- Request Lambda
- Response Lambda

**Check the status of deployment:** To check the status of the PingIntelligence policy deployment, run the `status.sh` command:

```
/opt/pingidentity/pi/aws/bin$ status.sh
Checking the PI AWS Policy deployment status

1) IAM Role named PI-Role deployment - status... deployed
2) IAM Policy named LambdaEdge-PI deployment - status... deployed
3) PI-ASE-Request Lamda deployment - status... deployed
4) PI-ASE-Response Lamda deployment - status... deployed
5) PI-ASE-Request Lamda CloudFront deployment - status... deployed
6) PI-ASE-Response Lamda CloudFront deployment - status... deployed

PI AWS Policy is already installed.
```

### API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.

## Next steps - Integrate into your API environment

After the policy deployment is complete, refer to the following topics for next steps:

It is recommended to read the following admin guide topics apart from reading the [ASE](#) and [ABS](#) Admin Guides:

- [ASE port information](#)
- [API naming guidelines](#)
- Adding APIs to ASE in [Sideband ASE](#). You can add individual APIs or you can configure a [global API](#).
- [Connect ASE and ABS](#)

After adding APIs to PingIntelligence, the API model needs to be trained. The training of an API model is executed in the ABS AI engine.. The following topics provide a high level view of the process.

- [Train your API model](#)
- [Generate and view the REST API reports using Postman](#)
- [View PingIntelligence for APIs Dashboard](#).

## Uninstall CloudFront sideband policy

Remove the PingIntelligence AWS policy with the undeploy tool, which detaches the policy from CloudFront. To undeploy the policy, run the following command:

```
/opt/pingidentity/pi/aws/bin$ undeploy.sh
Undeploying PI AWS Policy

1) Fetching PI-ASE-Request Lambda version... done
2) Fetching PI-ASE-Response Lamda version... done
3) Undeploy PI-ASE-Request Lamda CloudFront... done
4) Undeploy PI-ASE-Response Lamda CloudFront... done
5) Undeploy PI-ASE-Request Lamda... done
6) Undeploy PI-ASE-Response Lamda... done
7) Detaching IAM Role named PI-Role from policy LambdaEdgeExecution-PI -
  status... done
8) Deleting IAM Role named PI-Role - status... done
9) Deleting policy named LambdaEdgeExecution-PI - status... done

Successfully undeployed PI AWS Policy.
```

**Note:** The time required to detach the policy from CloudFront varies depending on the CloudFront region where the policy is deployed. It is common to encounter intermediate error messages like the following during the course of uninstallation.

```
Lambda was unable to delete lambda:us-east-1:377367197819:function:PI-ASE-Request-E2PLLTN1FCYDB3:5 because it is a replicated function.
Please see our documentation for Deleting Lambda@Edge Functions and Replicas.
```

If such error occurs then re-execute the `undeploy.sh` after a gap of 30 minutes.

You can use the `cloud_front_id` from the [aws.properties](#) file to search and verify the deletion of PingIntelligence Lambda functions.

# Axway API gateway integration

---


## Axway sideband integration

---

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with an Axway API Gateway. A PingIntelligence policy is installed in the Axway API Gateway and passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking. PingIntelligence 4.0 software adds support for reporting and attack detection based on usernames captured from token attributes.

The following diagram shows the complete deployment:





Here is the traffic flow through Axway and PingIntelligence for APIs components.

1. Client sends an incoming request to Axway
2. Axway makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and checks the origin IP, cookie, API Key, or OAuth2 token in the PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to the Axway. If not, a different response code is sent to Axway. The request information is also logged by ASE and sent to the AI Engine for processing.
4. If Axway receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, the Gateway optionally blocks the client.
5. The response from the backend server is received by Axway.
6. Axway makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to Axway.
8. Axway sends the response received from the backend server to the client.

## Prerequisites

Complete the following before configuring the Axway API Gateway:

- **Confirm the Axway version** PingIntelligence 4.0 works with Axway 7.5.3 or

## Editing API, My API

*Editing virtualized API. Make your changes and click "Save" to commit*

← Save

Apply

Cancel

Inbound

Outbound

API

API Methods

Security



My API

### OAuth Security De

General

Authoriz

\*Acc

\*Scop

Remove crede

- **OAuth token store:** If you wish to detect username based attacks, make sure that OAuth token store is configured in Axway.

- **Install PingIntelligence software**

PingIntelligence should be installed and configured. Refer to the PingIntelligence deployment guide for your environment.

- **Verify that ASE is in sideband mode**

Check that ASE is in sideband mode by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

- **Enable sideband authentication:** For a secure communication between Axway and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for Axway to authenticate with ASE. To generate the token in ASE, enter the following ASE command:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

- **Port for AAD**

If you are using [AAD](#) to automate API definition updates on PingIntelligence, open the following ports:

- Open the management port to fetch API definitions from Axway. The default port is 8075.
- Open port 8010 in ASE for AAD to add API definitions.

To connect PingIntelligence ASE with Axway API Gateway, complete the following steps:

- Import the Axway Policy in Axway Policy Studio
- Deploy the Axway Policy
- Import the APIs from the Management VM to Axway API Manager.


## Deploy PingIntelligence policy

Deploying PingIntelligence policy requires completing the following two parts:


- [Configuring Axway Policy Studio](#)
- [Configure persistent connection for ASE keep-alive](#)
- [Configuring Axway API Manager](#)

## Axway Policy Studio configuration

1. Launch Axway Policy Studio and create a new project from an **API Gateway instance**:



2. In the **New Project** pop-up window, enter the details and click **Next**:




3. Enter **Host** details, **Username**, and **Password** of the API Gateway to connect and click **Next**:

The screenshot shows the 'New Project' dialog box in Axway Policy Studio. The dialog is titled 'New Project' and has a subtitle 'Open connection'. Below the subtitle is the instruction 'Specify the destination you want to connect to'. The dialog is divided into several sections:


- Saved Sessions:** A dropdown menu labeled 'Session:' is set to 'Admin Node Manager - localhost'.
- Connection Details:** Three input fields are present:
  - Host:** 'vortex-135'
  - Username:** 'admin'
  - Password:** '\*\*\*\*\*' (masked)
- Advanced:** A collapsed section indicated by a right-pointing arrow.

At the bottom of the dialog, there are three buttons: 'Help', '< Back', and 'Next >'. The 'Next >' button is highlighted in orange.

4. Click **Import configuration fragment** from the **File** sub menu in the menu bar




From the pop-up window, import the Axway Policy from the directory where it was saved. Select the policy and click **OK**:




5. After the Axway Policy is imported, click on **Policies > ASESecurity > ASE Request Handler > Access Token Information**. Double click on




Access Token Information box in the ASE Request Handler window.




- a. In the **Configure "Access Token Information"** pop-up window, enter your OAuth token store information and click the ... button.




- b. In the **Select OAuth Cache** pop-up window, select the OAuth token store.




6. After the Axway Policy is imported, click **Environment Settings** in the left-hand column and Click **Add HTTP Header**. In the HTTP Header Value field, enter the ASE authentication token that was created.



7. After the Axway Policy is imported, click **Environment Settings** in the left-hand column and click **Connect to ASE Request** under **ASE\_Request\_Connector**. Enter the IP address or the hostname of your ASE in the **URL** field as shown in the screen shot:




8. In the **Environment Settings** in the left-hand column, click **Connect to ASE Response** under **ASE\_Response\_Connector**. Enter the IP address or the hostname of your ASE in the **URL** field as shown in the screen shot:




9. In the left pane of the window, click **Server Settings**.
10. In the Server Settings window, double-click **Request Policies** under **API Manager**

11. In the **Add Request Policy** pop-up window, check the **ASE Request Handler** and click **OK**



12. Click **Add** and then **Save**



13. Repeat step 9-10 for Response Policies. 

14. Deploy the Policies by clicking **Deploy**.

## Configure ASE persistent connection

You can optionally configure TCP keep-alive connections in the `ase.conf` file of ASE. Following is a snippet of `ase.conf` displaying the `enable_sideband_keepalive` variable. The default value is set to `false`.

```
; enable connection keepalive for requests from gateway to ase.  
; This setting is applicable only in sideband mode.  
; Once enabled ase will add 'Connection: keep-alive' header in response  
; Once disabled ase will add 'Connection: close' header in response  
enable_sideband_keepalive=false
```

If this variable is set to `true`, then you must configure persistent connections in Axway Policy Studio by completing the following steps:

1. Click on **Environment Configuration**
2. Under **Environment Configuration**, click **Listeners > API Gateway**.
3. Click On your ASE IP address in **Sample Services**
4. In the **Remote Host Settings** pop-up window, un-check **Allow HTTP 1.1**
5. Check **Include Content Length in request**. Make sure all other options are not selected.
6. Click **OK** and Deploy the policy

The screenshot displays the Axway API Manager configuration interface. The left pane shows a tree view of the configuration hierarchy under 'pi [API Gateway]'. The selected item is '34.212.173.5 : 8000'. The right pane shows the 'Remote host settings' for this host, including an 'Edit' link and a 'Child Items' section. A 'Remote host settings' dialog box is open on the right, showing fields for 'Host alias', 'Host name', and 'Port', along with checkboxes for 'Allow HTTP', 'Include CORS', 'Send Server', and 'Verify server'.

### Axway API Manager configuration

Complete the following steps to configure Axway API Manager:

1. Login to the Axway API Manager.

2. In the Axway API Manager, click **Frontend API** and **Create new API**

The screenshot shows the 'Manage frontend API' interface in Axway API Manager. On the left, there is a sidebar with 'API' selected, and sub-items for 'Frontend API', 'Backend API', and 'API Catalog'. The main area displays a table of APIs:

Name	Version	Service Type	Organization	Frontend URL	State	Tags	Created on
decoy	1.0	REST	API Development	https://172.17.0.1:8065/decoy	Published		8 March 2018 00:19
demoshop	1.0	REST	API Development	https://172.17.0.1:8065/app	Unpublished		9 March 2018 01:11
shop	1.0	REST	API Development	https://shopapi/shopapi	Published		7 March 2018 23:04
shop-books	1.0	REST	API Development	https://books/shopapi-books	Published		8 March 2018 00:18
shop-electronics	1.0	REST	API Development	https://172.17.0.1:8065/shopapi-electronics	Unpublished		8 March 2018 00:19

Below the table is a 'Create new API' dialog box with a dropdown menu labeled '\*Select existing backend API:' and 'OK' and 'Cancel' buttons.

3. Click **Outbound** tab and enter Backend Service URL (your backend application server) and Request

The screenshot shows the 'Editing API, test' interface in Axway API Manager. The 'Outbound' tab is selected, and the configuration is shown for the 'API Gateway' pointing to a 'test' backend. The configuration details are as follows:

- Outbound authentication profile:** No authentication
- Backend service URL:** http://vortex-136:2200
- Request policy:** ASE Request Handler
- Default method routing:** API Proxy
- Response policy:** ASE Response Handler

Below the configuration is a section for '\* PER-METHOD OVERRIDE'.

Policy details:

**Configuration for capturing OAuth:** To capture OAuth token based attacks, complete the following steps:

1. In the API Manager, click on **Frontend API > Inbound** tab.



2. From the **Inbound security** drop-down list, select **OAuth** and click

**Edit.**

3. In the **OAuth Security Device** window, disable **Remove credentials on success** radio

#### OAuth Security Device

**OK** **Cancel**

button.

## API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.

### Axway API Manager configuration for PingIntelligence Dashboard

The PingIntelligence Dashboard pulls the API definition from Axway API Manager and converts them to a JSON format compatible with ASE. The Dashboard needs certain tags to be configured in Axway API Manager for it to import the normal and decoy API definitions. The following topics provide more information on configuring tags in Axway API Manager and configuring tags for the decoy API:

- [Configure tags in API Manager](#)
- [Configure tags for decoy API](#)

## Configure tags in API Manager

Tags are a medium to let ASE know which APIs from the API ecosystem need to be processed for monitoring and attack detection. Tags are also required for cookie and login URL parameters to be captured by PingIntelligence Dashboard for adding to ASE API JSON definition.

### Tagging the API for AI processing:

You need to configure `ping_ai` tag for all the APIs for which you want the traffic to be processed using the AI engine. For example, if you have 10 APIs in your ecosystem and you want only 5 APIs traffic to be processed using the AI engine, then apply the `ping_ai` tag on those 5 APIs.

In the Axway API Manager, click on **Frontend API > API** tab. In the API tab, navigate to Tags section and add the following tag and value:

- `ping_ai` – Set it to true if you want the traffic for API to be processed by PingIntelligence
- `ping_blocking` – This parameter defines whether the `enable_blocking` in ASE API JSON is set to `true` or `false` when the PingIntelligence Dashboard fetches the API definition from Axway. The default value is `true`. If you want to disable blocking in ASE, set it to `false`.

### Tags for Cookie and Login URL (Optional)

If your APIs use a cookie or log in URL then configure the following two tags and values for a cookie and login URL. In the Axway API Manager, click **Frontend API > API** tab. In the API tab, navigate to Tags section and add the following tag and value:

- `ping_cookie` – JSESSIONID
- `ping_login` – yourAPI/login

**Note:** If the API has API Key or OAuth2 token configured, the PingIntelligence Dashboard automatically learns it and adds it to the API JSON definition. You do not need to configure any tags for API Key and OAuth2 token.

The following illustration shows the tags to be added:



# Axway API Manager



API



**Frontend API**



Backend API



API Catalog

## Viewing API, shop

*The following API is read-only and cannot be m*

← Save

Apply

Cancel

Inbound

Outbound

**API**

### General

**Documentation**

## Configure tags for decoy API

You can configure Decoy APIs in Axway API Manager. A Decoy API is an API for which the traffic does not reach the backend API servers. The Decoy API is deployed to gather information about potential threats that your API ecosystem may face. Traffic directed to Decoy API configured in Axway API Gateway is redirected to ASE which functions as the backend server. ASE sends a preconfigured response, like 200 OK, for requests sent to a Decoy API.

You need to configure the following **TAGS** and **VALUES** in the **API** tab for **Frontend API** in Axway API Manager:

- `ping_ai - true`
- `ping_decoy - true`

The screenshot shows the Axway API Manager interface. The left sidebar contains navigation options: API, Frontend API, Backend API, API Catalog, and a settings icon. The main content area is titled 'API' and has tabs for Inbound, Outbound, API, API Methods, Security Profiles, Authentication Profiles, and CORS Profiles. The 'API' tab is active, showing the 'General' section with fields for Image, \*API name (decoy), API version (1.0), Service type (REST), API summary, State (Published), Created By (API Manager Administrator), and Created on (14 May 2018, 17:47). Below this is the 'Documentation' section with a Description dropdown set to 'Use original API description'. The 'Tags' section is highlighted with a green box and contains a table with two rows: 'ping\_ai' and 'ping\_decoy', both with a value of 'true'.

TAG:	VALUES
ping_ai	true
ping_decoy	true

**API JSON for decoy API:** The converted API JSON will have the decoy section configured as highlighted in the following JSON file:

```
{
```

```

"api_metadata": {
  "protocol": "https",
  "url": "/decoy",
  "hostname": "*",
  "cookie": "",
  "cookie_idle_timeout": "",
  "logout_api_enabled": false,
  "cookie_persistence_enabled": false,
  "oauth2_access_token": false,
  "apikey_qs": "",
  "apikey_header": "",
  "enable_blocking": true,
  "login_url": "",
  "api_mapping": {
    "internal_url": ""
  },
  "api_pattern_enforcement": {
    "protocol_allowed": "",
    "http_redirect": {
      "response_code": "",
      "response_def": "",
      "https_url": ""
    },
    "methods_allowed": [],
    "content_type_allowed": "",
    "error_code": "",
    "error_def": "",
    "error_message_body": ""
  },
  "flow_control": {
    "client_spike_threshold": "0/second",
    "server_connection_queueing": false
  },
  "api_memory_size": "64mb",
  "health_check": false,
  "health_check_interval": 60,
  "health_retry_count": 4,
  "health_url": "/",
  "server_ssl": false,
  "servers": [],
  "decoy_config": {
    "decoy_enabled": true,
    "response_code": 200,
    "response_def": "OK",
    "response_message": "OK",
    "decoy_subpaths": []
  }
}
}

```

### Axway XFF policy for decoy APIs

PingIntelligence provides an XFF policy for your decoy APIs. The XFF policy adds an 'X-Forwarded-For' to the backend only if it is not present in the original incoming request. If the 'X-Forwarded-For' header is already present in the incoming request, the policy takes no action.

Follow the steps 1-4 of [Axway Policy Studio configuration](#) to import the XFF policy. Deploy the XFF policy after importing.

The screenshot shows the navigation menu of the Axway API Gateway management console. At the top, there is a search bar with the text 'type filter text' and a search icon. Below the search bar, the main navigation menu is displayed under the heading 'Apr\_29 [API Gateway]'. The menu items are as follows:

- APIs
- Policies
  - Enable-xff (highlighted)
  - Generated Policies
  - OAuth 2.0
  - Policy Library
  - QuickStart
  - Sample Policies
- Resources
- Environment Configuration
- Server Settings

### OAuth2 Token and API Keys

If you have configured the API Key in Request Header or in Query String, the PingIntelligence Dashboard reads and converts these values to `apikey_qs` or `apikey_header` values in the ASE API JSON. PingIntelligence's AI engine considers API Key values only in request headers or the query string.

Similarly, if you have configured OAuth2 token, the PingIntelligence Dashboard marks the value of `oauth2_access_token` as `true` in the ASE API JSON.

**Note:** You do not need to configure any tags for API Keys or OAuth2 token.

Following API JSON file shows the converted parameters. The `protocol`, `url`, and `hostname` are picked from the values that you configure in **Resource path** when you create the Frontend API.

The screenshot displays the Axway API Manager interface. On the left, a sidebar contains navigation icons and labels: 'API', 'Frontend API' (highlighted), 'Backend API', and 'API Catalog'. The main area is titled 'Editing API, shop' and includes a subtitle: 'Editing virtualized API. Make your changes and click "Save" to commit them, or "Cancel" to discard them.' Below the title are buttons for 'Save', 'Apply', and 'Cancel'. A horizontal tab bar shows 'Inbound', 'Outbound', 'API' (selected), 'API Methods', 'Security Profiles', and 'Authentication'. The 'API' tab displays a diagram of a mobile phone and a laptop connected to a server, labeled 'shop'. Below this, the 'Resource path' is set to 'https://192.168.11.103/shop' and 'Inbound security' is set to 'Pass Through'.

```
{
  "api_metadata": {
    "protocol": "https",
    "url": "/shop",
    "hostname": "192.168.11.103",
    "cookie": "JSESSIONID",
    "cookie_idle_timeout": "",
    "logout_api_enabled": false,
    "cookie_persistence_enabled": false,
    "oauth2_access_token": true,
    "apikey_qs": "Keyld",
    "apikey_header": "",
    "enable_blocking": true,
    "login_url": "/shop/login",
    "api_mapping": {
      "internal_url": ""
    }
  },
  "api_pattern_enforcement": {
    "protocol_allowed": "",
    "http_redirect": {
      "response_code": "",
      "response_def": "",
      "https_url": ""
    },
    "methods_allowed": [],
    "content_type_allowed": "",
    "error_code": "",
    "error_def": "",
    "error_message_body": ""
  }
}
```

```

    },
    "flow_control": {
      "client_spike_threshold": "0/second",
      "server_connection_queueing": false
    },
    "api_memory_size": "64mb",
    "health_check": false,
    "health_check_interval": 60,
    "health_retry_count": 4,
    "health_url": "/",
    "server_ssl": false,
    "servers": [],
    "decoy_config": {
      "decoy_enabled": false,
      "response_code": 200,
      "response_def": "",
      "response_message": "",
      "decoy_subpaths": []
    }
  }
}

```

## Azure API gateway integration

---

### Azure APIM sideband integration

---


This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with Azure API Manager (APIM). A PingIntelligence policy is installed in APIM and passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking. PingIntelligence policy for Azure also supports detecting attacks based on the username.

The APIM PingIntelligence policy works in the following two configurable mode:

- **Asynchronous mode:** When the PingIntelligence policy is configured in the Asynchronous mode, APIM does not wait for a response from PingIntelligence ASE before sending the API client request to the backend API server. In this mode PingIntelligence deployment passively logs the API request and response. It performs detailed API activity reporting and attack detection without blocking of attacks.
- **Synchronous mode:** When the PingIntelligence policy is configured in the Synchronous mode, Azure API gateway waits for a response from PingIntelligence ASE before sending the request to the backend API server or blocking it. In this mode, PingIntelligence actively logs and responds to the API requests and response. It performs detailed API activity reporting with attack detection and blocking of attacks.



The following diagram shows the logical setup of PingIntelligence ASE and



Here is the traffic flow through the Azure and PingIntelligence for APIs components.

1. Client sends an incoming request to APIM
2. APIM makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and looks up the origin IP, cookie, OAuth2 token or API key on the PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to APIM. If not, a different response code is sent to APIM. The request information is also logged by ASE and sent to the AI Engine for processing.
4. If APIM receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, if it receives a 403-forbidden response, the APIM blocks the client when blocking is enabled for the API.
5. The response from the backend server is received by APIM.
6. APIM makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to Azure.
8. APIM sends the response received from the backend server to the client.

## Prerequisites

---

Complete the following prerequisites before deploying the PingIntelligence policy on APIM:

**Prerequisite:**

- Confirm that the Azure API Management Service is available
- **Version** : The PingIntelligence policy supports Azure APIM Q2CY2020 version. If you are using any other version, contact Ping Identity support.
- Confirm that the APIs to which you want to apply the PingIntelligence policy are available

- **Configure CA certificate in APIM:** If you want to use the ASE self-signed certificate, then configure the CA certificate from the **Security -> CA certificates**

The screenshot displays the Azure portal interface. On the left is a dark navigation pane with various service icons and labels. The main area on the right is light-colored and contains a search bar at the top right. Below the search bar, there are two sections: 'API Management' and 'Security'. The 'Security' section is expanded, showing a list of security-related services. The 'CA certificates' item is highlighted with a light blue background.

**Navigation Pane (Left):**

- Home
- Dashboard
- All services
- ★ FAVORITES
- All resources
- Resource groups
- App Services
- Function Apps
- SQL databases
- Azure Cosmos DB
- Virtual machines
- Load balancers
- Storage accounts
- Virtual networks
- Azure Active Directory
- Monitor
- Advisor
- Security Center
- Cost Management + Billing
- Help + support

**Main Content Area (Right):**

Search (Ctrl+ /)

**API Management**

- Quickstart
- APIs
- Products
- Named values
- Tags
- Analytics (preview)
- Users
- Subscriptions
- Groups
- Notifications
- Notification templates
- Issues
- Repository
- Management API

**Security**

- Identities
- OAuth 2.0
- OpenID Connect
- CA certificates**
- Client certificates

- **PingIntelligence policy application**

Select one of the following four levels to apply the PingIntelligence policy: .

- For all the APIs
- For a group of APIs, that is, at the product level
- For individual APIs
- For a specific operation in the API

- **PingIntelligence software installation**

Install and configure PingIntelligence software. Refer to the PingIntelligence deployment guide for your environment.

- **Verify that ASE is in sideband mode**

Check that ASE is in `sideband` mode by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband

http/ws                : port 80
https/wss              : port 443
firewall              : enabled
abs                   : disabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.61 MB, free 102.39
MB
google pubsub         : disabled
log level             : debug
timezone              : local (UTC)
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set `mode` as `sideband` and start ASE.

- **Enable sideband authentication:** For a secure communication between APIM and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for APIM to authenticate with ASE. To generate the token in ASE, enter the following ASE command:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

## Deploy PingIntelligence policy

---

PingIntelligence provides an XML policy file to integrate PingIntelligence and Azure API Management Service. This policy can be applied at an individual API level, for all the APIs, to a group of APIs, or for an operation of an API.

PingIntelligence recommends that the PingIntelligence policy be the first policy in the Azure policy XML. This ensures that all the traffic is captured by ASE and sent to PingIntelligence AI engine for analysis.

Complete the following steps to deploy the PingIntelligence policy:

1. [Download](#) the PingIntelligence policy XML file from the Sideband Integration section of the download page
2. Login to your Azure account and create the following **Named value** in your API Management service
  - **ase-primary**: The primary ASE node.
  - **ase-secondary**: The secondary ASE node. The traffic is redirected to the secondary ASE node if the primary ASE node is not reachable.

**Note:** Make sure that the ASE primary and secondary IP address is followed by a /.

- **ase-token**: The authentication token for secure communication between Azure API Management service and ASE.
- **connection-timeout**: The number of seconds for which the API Management Service waits for ASE to respond.
- **enable-async-mode**: Set the value to **true** to enable asynchronous mode between APIM and ASE. When the asynchronous mode is enabled, the Azure gateway does not wait for a response from ASE and sends the request to the backend server. The ASE performs detailed API activity reporting and attack detection without blocking of attacks. If you do not want to enable asynchronous mode, set the value to **false**. In this case, the Azure gateway does not send the API request to the backend server, until it receives a response from ASE.
- **oauth2-jwt-username-claim**: JWT claim name for username.
- **oauth2-token-qs-name**: The name of the query string parameter that contains the OAuth token. If you choose not to intercept the OAuth tokens coming as part of query string, then set the value to `@(null)`.


**Note:** The PingIntelligence policy extracts the OAuth token from the query string, configured in **oauth2-token-qs-name**. A new Authorization header- `Authorization: Bearer <OAuth token>` is added to the metadata sent to ASE. If there is an existing Authorization header, the token is prepended so that ABS AI engine can analyse it. If the query string has multiple query parameters with the same name, the first parameter is intercepted by the policy.





















- **retry-count**: The number of times APIM tries to connect to ASE.






If you change any of the **Named Values** after the policy is operational, it takes 60-seconds for the change to be applicable. For example, if you change the ase-primary node IP address, the new IP address would take effect only after 60-seconds.

Display name	Value	Tags
ase-primary	https://...../	
ase-secondary	https://...../	
ase-token	.....	
connection-timeout	60	
enable-async-mode	true	
oauth2-jwt-username-claim	username	
oauth2-token-qs-name	@(null)	
retry-count	2	














3. Open the downloaded PingIntelligence policy XML file and copy the policy at the desired level: **All APIs**, individual APIs, operation level, or Group of APIs. Click on **Policies** in the **Inbound processing** UI box and paste the policy.

 **Note:** The PingIntelligence policy does not validate the authenticity of a JWT. Configure the PingIntelligence policy after <validate-jwt> policy.

-  Home
-  Dashboard
-  All services
-  **FAVORITES**
-  All resources
-  Resource groups
-  App Services
-  Function Apps
-  SQL databases
-  Azure Cosmos DB
-  Virtual machines
-  Load balancers
-  Storage accounts
-  Virtual networks
-  Azure Active Directory
-  Monitor
-  Advisor
-  Security Center
-  Cost Management + Billing
-  Help + support

-  Overview
-  Activity log
-  Access control (IAM)
-  Tags
-  Diagnose and solve problems

## API Management

-  Quickstart
-  APIs
-  Products
-  Named values
-  Tags
-  Analytics (preview)
-  Users
-  Subscriptions
-  Groups
-  Notifications
-  Notification templates
-  Issues
-  Repository

4. Click on the **Save** button to save the

The image shows the Azure portal interface. On the left is a dark navigation pane with the following items:

- Home
- Dashboard
- All services
- FAVORITES**
- All resources
- Resource groups
- App Services
- Function Apps
- SQL databases
- Azure Cosmos DB
- Virtual machines
- Load balancers
- Storage accounts
- Virtual networks
- Azure Active Directory
- Monitor
- Advisor
- Security Center
- Cost Management + Billing
- Help + support

On the right is the main content area, titled 'API Management service'. It features a search bar with the placeholder text 'Search (Ctrl+/)'. Below the search bar is a list of navigation items:

- Overview
- Activity log
- Access control (IAM)
- Tags
- Diagnose and solve problems
- API Management**
- Quickstart
- APIs** (highlighted)
- Products
- Named values
- Tags
- Analytics (preview)
- Users
- Subscriptions
- Groups
- Notifications
- Notification templates
- Issues
- Repositories



**i Attention:** If an existing policy is deployed, copy and paste the <inbound> section of the PingIntelligence policy into the <inbound> section of your existing policy. Similarly, replace the <outbound> section of the policy. It is recommended that the PingIntelligence policy be the first policy that is executed.

## API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.

## Integrate PingIntelligence

---

After the policy deployment is complete, refer to the following topics for next steps:

It is recommended to read the following topics (part of the admin guides) apart from reading the [ASE](#) and [ABS AI Engine](#) Admin Guides:

- [Customizing ASE ports](#) on page 124
- [API naming guidelines](#) on page 169
- Adding APIs in [Sideband ASE](#) on page 160. You can add individual APIs or you can configure a global API. For more information, see [API discovery and configuration](#) on page 347.
- [Configure ASE to ABS connectivity](#) on page 194

After you have added your APIs in ASE, the API model needs to be trained. The training of an API model is executed in the ABS AI engine. The following topics provide information on important topics, however it is a good practice to read the entire ABS Admin Guide.

- [AI Engine training](#) on page 338
- [API reports using Postman](#) on page 413
- [Access PingIntelligence Dashboard](#) on page 20

## Configure ASE persistent connection

---

You can optionally configure TCP keep-alive connections in the `ase.conf` file of ASE. Following is a snippet of `ase.conf` displaying the `enable_sideband_keepalive` variable. The default value is set to `false`.

```
; enable connection keepalive for requests from gateway to ase.
; This setting is applicable only in sideband mode.
; Once enabled ase will add 'Connection: keep-alive' header in response
; Once disabled ase will add 'Connection: close' header in response
enable_sideband_keepalive=false
```

## CA API gateway integration

---


### PingIntelligence - CA API gateway sideband integration

---

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with CA API gateway. You can attach the PingIntelligence for APIs integration to your APIs in the CA API

Gateway by incorporating the Encapsulated Assertions to a subset of or to each API policies. When these Encapsulated Assertions are executed inside an API Gateway policy, the gateway passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking.

The following diagram shows the logical setup of PingIntelligence for APIs and CA API



gateway:

Here is the traffic flow through the CA API gateway and PingIntelligence for APIs components.

1. Incoming API Client request arrives at the CA API Gateway
2. A PingIntelligence assertion running on the CA API Gateway makes an API call to send the request metadata to PingIntelligence ASE
3. ASE checks the request against a registered set of APIs and looks for the origin IP, cookie, OAuth2 token or API key in the PingIntelligence Blacklist. If all checks pass, ASE returns a 200-OK response to CA. If the client is on the blacklist and blocking is enabled a 403 response is sent to CA. The request information is also logged by ASE and sent to the AI Engine for processing.
4. If CA receives a 200-OK response from ASE, then it forwards the client request to the backend server. Otherwise, the CA blocks the client when a 403 response is received.
5. The response from the backend server is received by CA.
6. CA makes a second API call to pass the response information to ASE.
7. ASE receives the response information and immediately sends a 200-OK to CA. The response information is also logged by ASE and sent to the AI Engine for processing.
8. CA sends the response received from the backend server to the client.

PingIntelligence encapsulated assertions include capabilities for enhanced sideband performance and availability including:

- **Persistent SSL sessions** - Support for flowing sideband calls across a persistent SSL session between the API Gateway and PingIntelligence.

**Note:** Requires enabling `enable_sideband_keepalive` parameter in the PingIntelligence ASE `ase.conf` file.

- **Redundant PingIntelligence nodes** - optional redundant PingIntelligence ASE nodes can be configured in the encapsulated assertion to bypass a node failure.

## Prerequisite

---

Confirm that the following prerequisites are met before deploying the PingIntelligence integration.

### Prerequisite:

- **CA API Gateway Policy Manager** - PingIntelligence was developed with and qualified with CA API Gateway 9.4 (contact PingIdentity for other supported releases). Use the included Policy Manager to configure the gateway..

- **PingIntelligence software installation**

PingIntelligence 4.0 software is installed and configured. For installation of PingIntelligence software, refer to the [manual](#) or [automated](#) deployment guides.

- Java must be installed on the system from where the bundle is imported into the CA API gateway
- **Verify that ASE is in sideband mode** Confirm that ASE is operating in `sideband` mode by running the following command in the ASE command line:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                 : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack             : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set `mode` as `sideband` and start ASE.

- **Enable sideband authentication:** For a secure communication between CA and ASE, enable sideband authentication by entering the following command in the ASE command line:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for CA to authenticate with ASE. This token is generated in ASE and configured in the policy XML file. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

## Install and configure the PingIntelligence bundle

---

Installing and configuring the PingIntelligence bundle for CA API gateway consists of following steps:

1. Configure properties in `pingintelligence-properties.bundle` file.
2. Import the bundle file and the properties file into the CA API gateway using the import script.
3. Configure a certificate and the ASE token using CA API Policy Manager

## Configure PingIntelligence bundle

Complete the following steps to configure the CA API gateway PingIntelligence policy:

1. Download the PingIntelligence policy files from the [download](#) site. The downloaded package will have the following files and properties:

- **ASE Check Request:** The assertion used to analyze API requests.
- **ASE Check Response:** The assertion used to analyze API responses.
- **Cluster-wide Properties:**
  - `ase_host_https`: The default is <https://ase-server.example.com>
  - `ase_host2_https`: The default is <https://ase-server-2.example.com>
  - `ase_path_request` and `ase_path2_request`: The default path is </ase/request>
  - `ase_path_response` and `ase_path2_response`: The default path is </ase/response>
- **API examples:**
  - `/shop` - Example API that may be called by an external client. The API shows how to support both failing and non-failing policies.
  - `/shop/backend` - An example shop-backend for demo purposes.

2. Untar the package

3. Edit the `pingintelligence-properties.bundle` to configure the following properties:

- `ase_host_https` and `ase_host2_https`: Primary and secondary PingIntelligence ASE IP address and port number. If the primary ASE is not available, the request is sent to the secondary ASE.
- `ase_request_connection_timeout`: The time in milliseconds for which API gateway waits to establish a TCP connection for the client request with ASE. After the timeout period, the request is directly sent to the backend server. The default value is 30,000 milliseconds.
- `ase_request_read_timeout`: The time in milliseconds for which API gateway waits to get a response from ASE for the request. After the timeout period, the request is directly sent to the backend server. The default value is 60,000 milliseconds.
- `ase_response_connection_timeout`: The time in milliseconds for which API gateway waits to establish a TCP connection with ASE for the response from the backend server. After the timeout period, the response is directly sent to the client. The default value is 30,000 milliseconds.
- `ase_response_read_timeout`: The time in milliseconds for which API gateway waits to get a response from ASE for the request. After the timeout period, the request is directly sent to the backend server. The default value is 60,000 milliseconds.
- `ase_path_request` and `ase_path2_request`: Use default value in sample file.
- `ase_path_response` and `ase_path2_response`: Use default value in sample file.

Following is a sample `pingintelligence-properties.bundle` file:

```
<?xml version="1.0" encoding="UTF-8"?><l7:Bundle xmlns:l7="http://
ns.l7tech.com/2010/04/gateway-management">
  <l7:References>
    <l7:Item>
      <l7:Name>ase_host_https</l7:Name>
      <l7:Id>f33082fa66314439b5d7e8703ac0963a</l7:Id>
      <l7:Type>CLUSTER_PROPERTY</l7:Type>
      <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
      <l7:Resource>
        <l7:ClusterProperty
id="f33082fa66314439b5d7e8703ac0963a" version="1">
          <l7:Name>ase_host_https</l7:Name>
          <l7:Value>https://your-ase-host-and-port</l7:Value>
        </l7:ClusterProperty>
      </l7:Resource>
```

```

</l7:Item>
<l7:Item>
  <l7:Name>ase_path_request</l7:Name>
  <l7:Id>f33082fa66314439b5d7e8703ac09636</l7:Id>
  <l7:Type>CLUSTER_PROPERTY</l7:Type>
  <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
  <l7:Resource>
    <l7:ClusterProperty
id="f33082fa66314439b5d7e8703ac09636" version="0">
      <l7:Name>ase_path_request</l7:Name>
      <l7:Value>/ase/request</l7:Value>
    </l7:ClusterProperty>
  </l7:Resource>
</l7:Item>
<l7:Item>
  <l7:Name>ase_path_response</l7:Name>
  <l7:Id>f33082fa66314439b5d7e8703ac09633</l7:Id>
  <l7:Type>CLUSTER_PROPERTY</l7:Type>
  <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
  <l7:Resource>
    <l7:ClusterProperty
id="f33082fa66314439b5d7e8703ac09633" version="0">
      <l7:Name>ase_path_response</l7:Name>
      <l7:Value>/ase/response</l7:Value>
    </l7:ClusterProperty>
  </l7:Resource>
</l7:Item>
<l7:Item>
  <l7:Name>ase_request_connection_timeout</l7:Name>
  <l7:Id>07b5ecd6fc3baca9518885b71dbcee8e</l7:Id>
  <l7:Type>CLUSTER_PROPERTY</l7:Type>
  <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
  <l7:Resource>
    <l7:ClusterProperty
id="07b5ecd6fc3baca9518885b71dbcee8e" version="0">
      <l7:Name>ase_request_connection_timeout</l7:Name>
      <l7:Value>30000</l7:Value>
    </l7:ClusterProperty>
  </l7:Resource>
</l7:Item>
<l7:Item>
  <l7:Name>ase_request_read_timeout</l7:Name>
  <l7:Id>07b5ecd6fc3baca9518885b71dbcee90</l7:Id>
  <l7:Type>CLUSTER_PROPERTY</l7:Type>
  <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
  <l7:Resource>
    <l7:ClusterProperty
id="07b5ecd6fc3baca9518885b71dbcee90" version="0">
      <l7:Name>ase_request_read_timeout</l7:Name>
      <l7:Value>60000</l7:Value>
    </l7:ClusterProperty>
  </l7:Resource>
</l7:Item>
<l7:Item>
  <l7:Name>ase_response_connection_timeout</l7:Name>
  <l7:Id>07b5ecd6fc3baca9518885b71dbcee92</l7:Id>
  <l7:Type>CLUSTER_PROPERTY</l7:Type>
  <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
  <l7:Resource>

```

```

        <l7:ClusterProperty
id="07b5ecd6fc3baca9518885b71dbcee92" version="0">
          <l7:Name>ase_response_connection_timeout</l7:Name>
          <l7:Value>30000</l7:Value>
        </l7:ClusterProperty>
      </l7:Resource>
    </l7:Item>
  <l7:Item>
    <l7:Name>ase_response_read_timeout</l7:Name>
    <l7:Id>07b5ecd6fc3baca9518885b71dbcee94</l7:Id>
    <l7:Type>CLUSTER_PROPERTY</l7:Type>
    <l7:TimeStamp>2019-07-09T20:18:03.316Z</l7:TimeStamp>
    <l7:Resource>
      <l7:ClusterProperty
id="07b5ecd6fc3baca9518885b71dbcee94" version="0">
        <l7:Name>ase_response_read_timeout</l7:Name>
        <l7:Value>60000</l7:Value>
      </l7:ClusterProperty>
    </l7:Resource>
  </l7:Item>
  <l7:Item>
    <l7:Name>ase_path2_response</l7:Name>
    <l7:Id>753f4df53a2f3daf040f9807a4f9a126</l7:Id>
    <l7:Type>CLUSTER_PROPERTY</l7:Type>
    <l7:TimeStamp>2019-07-18T17:04:41.043Z</l7:TimeStamp>
    <l7:Resource>
      <l7:ClusterProperty
id="753f4df53a2f3daf040f9807a4f9a126" version="0">
        <l7:Name>ase_path2_response</l7:Name>
        <l7:Value>/ase/response</l7:Value>
      </l7:ClusterProperty>
    </l7:Resource>
  </l7:Item>
  <l7:Item>
    <l7:Name>ase_path2_request</l7:Name>
    <l7:Id>753f4df53a2f3daf040f9807a4f9a124</l7:Id>
    <l7:Type>CLUSTER_PROPERTY</l7:Type>
    <l7:TimeStamp>2019-07-18T17:04:41.043Z</l7:TimeStamp>
    <l7:Resource>
      <l7:ClusterProperty
id="753f4df53a2f3daf040f9807a4f9a124" version="0">
        <l7:Name>ase_path2_request</l7:Name>
        <l7:Value>/ase/request</l7:Value>
      </l7:ClusterProperty>
    </l7:Resource>
  </l7:Item>
  <l7:Item>
    <l7:Name>ase_host2_https</l7:Name>
    <l7:Id>753f4df53a2f3daf040f9807a4f9a122</l7:Id>
    <l7:Type>CLUSTER_PROPERTY</l7:Type>
    <l7:TimeStamp>2019-07-18T17:04:41.043Z</l7:TimeStamp>
    <l7:Resource>
      <l7:ClusterProperty
id="753f4df53a2f3daf040f9807a4f9a122" version="1">
        <l7:Name>ase_host2_https</l7:Name>
        <l7:Value>https://your-second-ase-host-and-port</l7:Value>
      </l7:ClusterProperty>
    </l7:Resource>
  </l7:Item>

```

```
</17:Item>
</17:References>
```

## Import PingIntelligence policy

---

After the PingIntelligence bundle is configured, import it into the CA API gateway. PingIntelligence provides a script to import the policy. Complete the following steps to import the bundle:

1. Open the `import_pingintelligence.sh` file in an editor.
2. Configure the following values:
  - `GW`: API gateway hostname and port
  - `GW_user admin:password`: API gateway username
  - `GW_PASS_B64`: A base64 encoded password used to encrypt/decrypt secure passwords
3. Run the `import_pingintelligence.sh` script. After the import script is run, the PingIntelligence policy is installed in the API gateway.

**Verify the policy import:** Connect to the API gateway using the CA API Gateway Policy Manager. Verify the **PingIntelligence** folder is visible in the lower left-hand side window.

Following is a sample `import_pingintelligence.sh` script:

```
#!/usr/bin/env bash

# Configure the gateway host and port and user credentials
#
GW=localhost:8443
GW_USER=admin:password
GW_PASS_B64=*****=

# Import the folder 'PingIntelligence'
#
curl -k -u $GW_USER -X PUT -H "Content-Type: application/xml" -H "L7-key-
passphrase: $GW_PASS_B64" "https://$GW/restman/1.0/bundle" -d @../docker-
build/add-ons/ssg/policies/pingintelligence.bundle

# Import cluster properties that configure the PingIntelligence bundle
#
# ase_host_https
# ase_path_request
# ase_path_response
# ase_host2_https
# ase_path2_request
# ase_path2_response
# ase_request_connection_timeout
# ase_request_read_timeout
# ase_response_connection_timeout
# ase_response_read_timeout
#
curl -k -u $GW_USER -X PUT -H "Content-Type: application/xml" "https://
$GW/restman/1.0/bundle" -d @../docker-build/add-ons/ssg/policies/
pingintelligence-properties.bundle
```

## Configure ASE token and certificate

---

After the bundle is imported into the CA API gateway, configure the certificate and ASE token using the CA API Policy Manager.

**Configure the certificate:** Complete the following steps to configure the certificate using CA API Policy Manager:

1. In CA API Policy Manager, navigate to **Tasks > Certificate, Keys and Secrets > Manage Certificates**
2. Click **Add** and complete the steps on the GUI to add a certificate.
3. In the **Specify Certificate Options** step (step 3 in GUI), select the **Outbound SSL Connections** checkbox and click **Next**.
4. In the **Configure Validation** step (step 4 in GUI), select the **Certificate is a Trust Anchor** checkbox and click **Finish**.

**Configure ASE token:** Complete the following steps in the CA API Policy Manager to configure the ASE token that was generated as part of [Prerequisite](#) on page 651.

1. In the CA API Policy Manager, navigate to **Tasks > Certificate, Keys and Secrets > Manage Stored Passwords**
2. Select **ase\_token** and click on **properties**.
3. In the **Stored Password Properties** pop-up window, click on **Change Password**.
4. In the **Enter Password** pop-up window, enter the ASE token and click **Ok**.

## Apply PingIntelligence policy

The bundle includes ASE check request and check response encapsulated assertions. Apply these assertions to each API that you want to monitor using PingIntelligence. You can include these assertions in global policies if you want each incoming API call to automatically be checked by PingIntelligence or you can attach those assertions in service-level policies.

For service-level policies, each API will add two assertions, ASE Check Request and ASE Check Response. ASE Check Request is applied before routing the request to the backend. Whereas ASE Check Response is used after a call to the downstream endpoint (which is on line 25 in the screenshot below):

```

17 | > Comment: -
18 | ASE Check Request // create an ASE validation request for the
19 | Comment: *
20 | Comment: * Example for 'continue processing'
21 | ▶ [X] At least one assertion must evaluate to true // Audit a message
24 | Comment: *
25 | Route via HTTPS to https://localhost:8443/shop/backend // si
26 | ASE Check Response // create an ASE validation request for the

```

The ASE Check Request assertion is configured with the following:

ASE check request

### ASE Check Request:

Property	Value
Username (optional) (string):	{request.http.parameter.username}
CorrelationID (optional, not required by default) (string):	
Custom data as (optional) additional input for customizations (string):	
'true' to enable auditing of ASE messages (for development only!) (string):	true



If you do not configure the properties, the assertion extracts all required details by itself. This includes:

- Retrieving all the request headers
- Generating a correlationId (used as X-CorrelationID)
- Retrieving the ASE Token
- Retrieving the ASE HTTPS host
- Retrieving the ASE request path
- Sending a message to ASE

PingIntelligence recommends adding `username` to capture the user name when it is available. Examples of username variables include:

- `${request.http.parameter.username}` - The username variable included in the incoming request HTTP header.
- `${session.subscriber_id}` - The username variable when authenticating users with the OAuth Toolkit (OTK)
- `${request.username}` – The username variable in the case of HTTP Basic authentication

The variable name to use in this case will often be very implementation-specific. Use what you already defined as part of your CA API Gateway implementation.

You should change other if you are customizing to accommodate special use cases.

- **CorrelationID:** Optional – used if you want to override the `correlationId` which will otherwise automatically be assigned.
- **Custom data:** Optional - used to modify the internal of that assertion.
- **true:** Useful for users developing an API for debugging or auditing purposes.

The assertion has an output which is the generated `correlationId:ase.correlationId` that is utilized by the ASE check response assertion.

#### ASE check response

This ASE Check Response assertion must be configured for each API with the following variables:

- **Correlation-ID:** The ASE request and response correlation IDs, if specified, must match. Otherwise, keep `ase.correlationId`
- **All service response headers:** The default value is `${response.http.allheadervalues}`. This variable is created by the routing assertion that executed the backend call. If it is customized, for example, `myresponse`, then the updated variable should be used.
- **Response code:** The HTTP response status of the backend call.
- **Response status:** This value is ignored and hard coded to OK.
- **Username (optional):** This should match the username variable setting in the ASE Check Request assertion. The screenshot shows an example where the username is being extracted from the incoming HTTP request.
- **Custom data (optional):** Used by customers who would like to modify the internals of an assertion.
- **true:** Useful for users developing an API for debugging or auditing purposes.

## API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.

## Integrate PingIntelligence

---

After the policy deployment is complete, refer to the following topics for next steps:

It is recommended to read the following topics (part of the admin guides) apart from reading the [ASE](#) and [ABS AI Engine](#) Admin Guides:

- [Customizing ASE ports](#) on page 124
- [API naming guidelines](#) on page 169
- Adding APIs in [Sideband ASE](#) on page 160. You can add individual APIs or you can configure a global API. For more information, see [API discovery and configuration](#) on page 347.
- [Configure ASE to ABS connectivity](#) on page 194

After you have added your APIs in ASE, the API model needs to be trained. The training of an API model is executed in the ABS AI engine. The following topics provide information on important topics, however it is a good practice to read the entire ABS Admin Guide.

- [AI Engine training](#) on page 338
- [API reports using Postman](#) on page 413
- [Access PingIntelligence Dashboard](#) on page 20

## F5 BIG-IP integration


---

### F5 BIG-IP PingIntelligence integration

---

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with F5 BIG-IP. A PingIntelligence policy is installed in F5 BIG-IP and passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking. PingIntelligence software includes support for reporting and attack detection based on usernames captured from JSON Web Token (JWT).

This diagram depicts the architecture of PingIntelligence for APIs components along with F5 BIG-



IP:

Following is a description of the traffic flow through F5 BIG-IP and PingIntelligence ASE:

1. Client sends an incoming request to F5 BIG-IP
2. F5 BIG-IP makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and looks for the origin IP, cookie, OAuth2 token or API key in PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to the F5 BIG-IP. If not, a different response code is sent to F5 BIG-IP. The request information is also logged by ASE and sent to the AI Engine for processing.
4. F5 BIG-IP receives a 200-OK response from ASE, then it forwards the request to the backend server. A request is blocked only when ASE sends a 403 error code.
5. The response from the backend server is received by F5 BIG-IP.
6. F5 BIG-IP makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to F5 BIG-IP.
8. F5 BIG-IP sends the response received from the backend server to the client.

## Prerequisites

F5 BIG-IP and PingIntelligence sideband integration was tested with F5 BIG-IP TMOS with node.js v6.9.1. If you are using any other version of F5, contact Ping Identity support for help.

### F5 prerequisites:

- F5 BIG-IP with v13.1.0.8 software.
- Knowledge of iRules LX in F5. Refer the F5 documentation for information on iRules.
- A Virtual Server is configured to front-end the incoming traffic. Make sure to apply HTTP profile to the virtual server.
- A valid F5 BIG-IP license and iRules LX is enabled in your setup.

**PingIntelligence prerequisites:**

This section assumes that you have installed and configured PingIntelligence software. For more information on PingIntelligence installation, see [PingIntelligence setup](#) on page 46 or [PingIntelligence manual deployment](#) on page 84

- Download the PingIntelligence policy from the [download](#) site.
- **Verify that ASE is in sideband mode:** Log in to your ASE machine and check that ASE is in sideband mode by running the following `status` command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

- **Enable sideband authentication:** For secure communication between F5 BIG-IP and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p admin
```

- **Generate sideband authentication token**

A token is required for BIG-IP to authenticate with ASE. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use in [Import and configure PingIntelligence policy](#) on page 660

## Deploy PingIntelligence policy

---

Deploying PingIntelligence policy for F5 BIG-IP consists of the following steps:


1. Import and configure PingIntelligence policy
2. Create an LX plugin
3. (Optional step) Add server pools for the backend and add virtual server for the frontend. If you already have frontend virtual servers and backend server pool, skip to next step.
4. Add iRule to the virtual server

The PingIntelligence policy is specific to an ASE cluster. If you have more than one ASE cluster, then add the policy to a new workspace and create a new plugin. When you import the PingIntelligence policy, it is imported to an LX workspace and opens in a Nodejs editor.

### Import and configure PingIntelligence policy


Complete the following steps to import PingIntelligence policy in F5:

## 1. Login to your F5 UI and navigate to **Local Traffic > iRules > LX**




### Workspaces.

In the **Workspaces** tab, click on **import**.



2. A Workspace import page is displayed. Enter the **Name** and choose the PingIntelligence policy that you downloaded from Ping Identity download site. Click on **Import**.



3. Clicking on **Import** creates an LX Workspace

4. Open the Workspace by clicking on it. The policy is pre-loaded with extension named `oi_ext`. Edit the ASE configuration by clicking on **ASEConfig.js** file. It opens the PingIntelligence policy in the editor:

The screenshot shows the F5 Management Center interface. The top navigation bar indicates 'ONLINE (ACTIVE) Standalone'. The breadcrumb trail is 'Local Traffic » iRules : LX Workspaces » pi\_workspace'. The left sidebar contains various configuration categories like Statistics, iApps, DNS, Local Traffic, Acceleration, Device Management, Network, and System. The main area is divided into 'General Properties' and 'Workspace Files'. The 'General Properties' section shows details for 'pi\_workspace', including its name, partition, node.js version (6.9.1), and associated plugin (pi\_plugin). The 'Workspace Files' section shows a tree view of files, with 'ASEConfig.js' selected. The editor displays the following JavaScript code:

```

1 - class ASEConfig {
2
3 - constructor() {
4   this.ase_primary = "172.16.40.156";
5   this.ase_primary_port = 4443;
6   this.ase_secondary = "172.16.40.156";
7   this.ase_secondary_port = 4443;
8   this.is_ase_ssl = true;
9   this.ase_token = "eyJhbGciOiJIUzI1NiIsInR5cCI6IkpXVCJ9.eyJ1cm91ciI6ImFkb2luZXN0IiwiaWF0IjoiMTY5MzU0MzU0In0.41fc";
10  this.ase_ca = "4.1.pem";
11  this.use_ca = false;
12  this.APIPaths = ["/"];
13
14  //configure below parameters for JWT tokens
15  this.enable_oauth = true;
16  this.is_access_token_in_header = true;
17  this.access_token_variable = "access_token";
18  this.authorization_header_prefix = "Bearer";
19  this.user_key_mapping = "Username";
20  this.clientid_key_mapping = "client_id_name";
21
22  // Parameters to be used internally. Don't change values for these variable
23  this.correlationheader = "X-CorrelationID";
24  this.aseheader = "ASE-Token";
25
26  }
27
28 - getAPIPaths() {
29   return this.APIPaths;
30 }

```

The following table describes the ASE variables:

Variable	Description
<code>ase_primary</code>	IP address of primary ASE node
<code>ase_primary_port</code>	Port number of primary ASE node
<code>ase_secondary</code>	IP address of secondary ASE node
<code>ase_secondary_port</code>	Port number of secondary ASE node
<code>is_ase_ssl</code>	Set to <code>true</code> if traffic to ASE is sent over HTTPS
<code>ase_token</code>	The ASE sideband authentication token that was generated as part of prerequisites
<code>use_ca</code>	Set to <code>true</code> if ASE is using a CA-signed certificate
<code>include_paths</code>	Provide the list of paths that the policy should process. If <code>/</code> is provided as path, then all the traffic is monitored. The maximum number of subpaths in path is 3. For example, <code>/a/b/c/</code> .
<code>enable_auth</code>	Set to <code>true</code> if traffic contains access token in authorization header or querystring.
<code>is_access_token_in_header</code>	Set to <code>true</code> if access token is present in authorization header.


Variable	Description
access_token_variable	If the access token is present in <code>querystring</code> , then specify the key used for token.
authorization_header_prefix	If the access token is present in <code>authorization</code> header, then specify the prefix used for access token.
user_key_mapping	The location of <code>username</code> in JSON payload of JWT access token.
clientid_key_mapping	The location of client ID in JSON payload of JWT access token

## Create LX plugin

After importing and configuring the PingIntelligence policy, create an LX plugin with name **pi\_plugin**.


Complete the following steps to create an LX plugin:

### 1. Navigate to **Local Traffic > iRules > LX Plugins**:





- In the New Plugin page, click on **Create** to create a new plugin with name **pi\_plugin**. Select the workspace that you created earlier from the **From Workspace** drop-down list and click on **Finished**.



### (Optional) Create backend server pool and frontend virtual server


It is optional to create a backend server pool and frontend virtual server if you already have those set up. If you have existing backend server pool and frontend virtual server that you want to use, continue with the steps to [Add PingIntelligence policy](#) on page 668

Complete the following steps if you do not have a backend server pool and frontend virtual server.


#### Add backend server pool

Complete the following steps to create a backend server pool:


## 1. Navigate to Local Traffic > Pools > Pool List and click on Create:



## 2. In the configuration page for the pool, configure the fields and add a new node for the backend



- Click on **Finished**. This creates a backend server pool which is accessed from clients connecting to the frontend virtual




server

### Add frontend virtual server

Complete the following steps to add a frontend virtual server:

- Navigate to **Local Traffic > Virtual Server > Virtual Server List** and click on **Create**



2. Configure the frontend virtual server details. At a minimum, configure the following values:

- **Destination Address:** This is the virtual IP address that is used for the frontend.
- **SSL Profile (Client):** Configure if the frontend is SSL
- **SSL Profile (Server):** Configure if the backend is SSL

The screenshot shows the configuration page for a virtual server. The 'General Properties' section includes fields for Name (Frontend), Description, Type (Standard), Source Address, Destination Address/Mask (172.16.40.100), Service Port (443), Notify Status to Virtual Address (checked), and State (Enabled). The 'Configuration' section is set to 'Basic' and includes dropdowns for Protocol (TCP), Protocol Profile (Client) (tcp), Protocol Profile (Server) (tcp), HTTP Profile (http), HTTP Proxy Connect Profile (None), FTP Profile (None), RTSP Profile (None), SSL Profile (Client) (clientsl), and SSL Profile (Server) (ajm-default-serverssl). There are also 'Selected' and 'Available' lists for SSL profiles.

3. Click on **Finished**

4. Under **Resource** tab, add backend pool to virtual server and click on

The screenshot shows the 'Resources' tab for the virtual server. The 'Load Balancing' section has a Default Pool dropdown set to 'Backend'. Below this are sections for 'iRules' and 'Policies', both showing 'No records to display' and 'Manage...' buttons. The top of the interface shows the device is 'ONLINE (ACTIVE)' and the user is 'admin'.

Update

## Add PingIntelligence policy

The imported PingIntelligence policy must be tied to a virtual server. Add the PingIntelligence policy to the existing or recently created virtual server..

Complete the following steps to add the PingIntelligence policy to the virtual server:

1. Navigate to **Local Traffic > Virtual Servers > Virtual Server List**
2. Select the virtual server to which you want to add the PingIntelligence policy
3. Click on the **Resources** tab
4. In the **iRules** section, click on the **Manage** button.

5. Choose the iRule under the **pi\_plugin** that you want to attach to the virtual server.

The screenshot shows the F5 BIG-IP GUI with the 'Resource Management' window open for a virtual server. The 'Available' list contains the following iRules:

- \_sys\_auth\_ssl\_ocsp
- \_sys\_auth\_tacacs
- svs\_https\_redirect
- /Common/pi\_plugin** (highlighted)
- pi\_irule** (highlighted)

6. Move the **pi\_irule** to the **Enabled** window and click on **Finished**.

The screenshot shows the F5 BIG-IP GUI with the 'Resource Management' window open. The 'Enabled' list now contains the following iRules:

- /Common/pi\_plugin** (highlighted)
- pi\_irule** (highlighted)

The 'Available' list contains the following iRules:


- \_sys\_auth\_ssl\_cc\_idap
- \_sys\_auth\_ssl\_crdp
- \_sys\_auth\_ssl\_ocsp
- \_sys\_auth\_tacacs
- \_sys\_https\_redirect

# IBM DataPower gateway integration

## IBM DataPower Gateway sideband integration

This integration guide discusses the deployment of PingIntelligence for APIs in a sideband configuration with IBM DataPower Gateway. PingIntelligence for APIs provides policy assembly components that extract the API metadata from a request or response processed by IBM DataPower Gateway. The API metadata is passed to PingIntelligence for APIs for detailed API activity reporting and attack detection. For more information on sideband deployment, see [Sideband ASE](#) on page 160.


The PingIntelligence policy assembly components are added using API Manager in IBM API Connect. The following diagram shows the implementation steps of the PingIntelligence policy assembly components in the IBM API ecosystem.



### Note:

The PingIntelligence policy assembly components get deployed on a per API basis. You must configure them for an individual API to extract the request and response metadata for the API.

The following diagram shows the logical setup of PingIntelligence for APIs and IBM DataPower Gateway.



The traffic flow through the IBM DataPower Gateway and PingIntelligence for APIs components is explained below:

1. A client sends an incoming request to the IBM DataPower Gateway.

2. PingIntelligence policy component is executed on the request to extract the metadata from the incoming request.
3. IBM DataPower Gateway makes an API call to send the request metadata to API Security Enforcer (ASE). The ASE checks the client identifiers such as usernames, tokens against the blacklist. If all checks pass, ASE returns a 200-OK response to the IBM DataPower Gateway. If the checks do not pass, ASE sends different response code (403) to the IBM DataPower Gateway. In both cases, ASE logs the request information and sends it to the Ping Intelligence API Behavioral Security (ABS) AI Engine for processing.
4. If the ASE sends a 200-OK response to the IBM DataPower Gateway, it forwards the API requests to the backend server. If the gateway receives a 403-Forbidden response from ASE, it blocks the client.
5. IBM DataPower Gateway receives the response from the backend server.
6. PingIntelligence policy component is applied on the response to extract the metadata from the server response.
7. IBM DataPower Gateway makes a second API call to pass the response information to ASE, which sends the information to the ABS AI engine for processing.
8. IBM DataPower API Gateway sends the response received from the backend server to the client.

## Prerequisites

---

Complete the following prerequisites before deploying the PingIntelligence policy.

**Confirm the versions-** The PingIntelligence policy is validated only for the following versions of IBM APIC and DataPower:

- IBM APIC v5.0.8.7
- IBM DataPower Gateway 2018.4.10

**Verify User permissions-** To configure PingIntelligence policy, the user must have permissions to edit and publish APIs in the API Manager.

**Install PingIntelligence software-** PingIntelligence software should be installed and configured. For more information on PingIntelligence deployment, see [PingIntelligence setup](#) on page 46 and [PingIntelligence manual deployment](#) on page 84.

**Verify that ASE is in sideband mode-** Check that ASE is in sideband mode by running the following ASE command.

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status           : started
mode             : sideband
http/ws         : port 80
https/wss       : port 443
firewall        : enabled
abs             : enabled, ssl: enabled
abs attack      : disabled
audit           : enabled
sideband authentication : disabled
ase detected attack : disabled
attack list memory : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as `sideband` and start ASE. For more information on starting ASE, see [Start and stop ASE](#) on page 126.

**Enable sideband authentication-** For a secure communication between IBM DataPower Gateway and ASE, enable sideband authentication by entering the following ASE command.

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

Ensure SSL is configured in ASE for client side connection using self-signed certificate. For more information on configuring self-signed certificate, see [Configure SSL for external APIs](#) on page 142.

**Enable connection keepalive between gateway and ASE-** Navigate to `/opt/pingidentity/ase/config/`. Set the value of `enable_sideband_keepalive` to `true` in `ase.conf` file. If the ASE is running stop it, before making the change. Start ASE after setting the value. For more information on ASE configuration, see [Sideband ASE configuration - ase.conf](#) on page 162

**Generate sideband authentication token-** To generate the token in ASE, enter the following command in the ASE command line.

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use. The token is required for IBM DataPower Gateway to authenticate with ASE. It is set as a runtime variable in ASE config set-variable policy. For more information, see [Configure PingIntelligence policy components](#) on page 675.

## Deploy PingIntelligence policy

---

PingIntelligence for APIs provides `pi_policy.yaml` file for IBM DataPower Gateway sideband integration. The policy has the following three policy assembly components:

- **ASE Config-** This assembly component configures the ASE connection and authentication parameters. It implements a set-variable policy that configures the parameters as runtime variables.
- **ASE Request-** This assembly component extracts the API metadata from a request processed by the IBM DataPower Gateway. It implements a gateway script policy in the DataPower Gateway.
- **ASE Response-** This assembly component extracts the API metadata from a response processed by the IBM DataPower Gateway. It implements a gateway script policy in the DataPower Gateway.

IBM API Connect provides different policy types to control specific aspects of processing by the DataPower Gateway. For example, to configure a capability, for logging, for security, and so forth. The **set-variable** policy type helps to add or set a runtime variable. The **gateway script** policy gives built-in access to the DataPower Gateway to execute a specified DataPower Gateway script program.

The deployment of PingIntelligence policy involves:

- Step1- [Add PingIntelligence policy components](#) on page 672.
- Step2- [Configure PingIntelligence policy components](#) on page 675.

**Note:** The PingIntelligence policy does not support payload with a DELETE request. When the policy is deployed, if a DELETE request comes with a payload, the payload will not reach the backend API server.

## Add PingIntelligence policy components

Complete the following steps before adding the PingIntelligence policy to your API:

1. Download the PingIntelligence policy from the [ping identity download site](#).



2. Extract the policy by using the following command.


```
# tar -zxvf <<file name>>
```

For example,


```
# tar -zxvf pi-api-ibm-policy-4.1.0.tar.gz
```

Complete the following steps to add the PingIntelligence policy components to your API in IBM API Manager:


1. Log in to API Manger.




2. Click the **Menu** ☰ icon on the top-left corner, to open navigation pane.




3. Click **Drafts** in the navigation pane.




4. Click the **APIs** tab.



5. Click on your API under **TITLE** list or enter the API name in **Search APIs** dialog box and select the API.



6. Click **Source** tab to edit your API definition.



7. Copy and paste the content of PingIntelligence policy into the **Assembly** block of your API definition at three places as illustrated:

- a. Open the pi\_policy.yaml file, copy the content of the **set-variable:** block having **ASE Config component** and paste it in the next line after **execute:** block in your API.

```
assembly:
  execute:
    - set-variable:
      version: 1.0.0
      title: ASE Config
      actions:
        - set: ase-master-url
```



- b. Next, copy the content of the **gateway script:** block containing **ASE Request component** from pi\_policy.yaml file and paste it after the immediate last line of **ASE Config component**, that was copied in step 8.1.

```
- set: ase-slave-url
  value:
- set: ase-token
  value:
- gatewayscript:
  version: 1.0.0
  title: ASE Request
  source: |2-
    var urlopen =
    var asetoken =
```


- c. Copy the content of the **gateway script:** block containing **ASE Response component** from pi\_policy.yaml file and paste it as the last component of your API..

```
username:
- gatewayscript:
  version: 1.0.0
  title: ASE Response
  source: |2-
    var urlopen = re
    var asetoken =
```

**Note:** The assembly component **ASE Reponse** should **always** be the last component of your policy assembly.

8. Click the **Validate**  icon to validate your changes. Click the **Save**  icon after completing the validation.


- Click the **Assemble** tab to open the **Assemble** view. Verify the sequence of the components ASE Config, ASE Request, and ASE Response in the Policy Assembly. The order must match as highlighted in the red boxes of the following image.




## Configure PingIntelligence policy components


After adding the PingIntelligence policy to an API, complete the following steps to configure ASE parameters:

- Click **Assemble** tab. In the main window click **ASE Config** component to open the **property sheet** on the right.



2. Configure the values for ASE master URL, ASE slave URL, and ASE token. Click the **Save**  icon on the top-right corner.

**Note:** The following format is applicable for ASE master and slave URLs-<http/https>://<ASE-Host name or IP address>.




Action \*  
**Set**  
Set, Add, or Clear a runtime variable.

Set  
**ase-master-url**  
The name of the variable to be set.

Type \*  
**string**  
The type of the value to set. This can be string, number or boolean.

Value  
[Redacted]  
The value that the variable will be set to.

**Remove**




Action \*  
**Set**  
Set, Add, or Clear a runtime variable.

Set  
**ase-slave-url**  
The name of the variable to be set.

Type \*  
**string**  
The type of the value to set. This can be string, number or boolean.

Value  
[Redacted]  
The value that the variable will be set to.

**Remove**



Action \*  
**Set**  
Set, Add, or Clear a runtime variable.

Set  
**ase-token**  
The name of the variable to be set.

Type \*  
**string**  
The type of the value to set. This can be string, number or boolean.

Value  
[Redacted]  
The value that the variable will be set to.

**Remove**

3. Publish your API after completing step 2 to make the PingIntelligence policy components part of your API definition.


# Kong API gateway integration

## PingIntelligence - Kong API gateway integration

This guide describes the deployment of the PingIntelligence plugin for Kong 1.5.0 community version API gateway. Install the plugin on all the Kong nodes that you want to integrate with PingIntelligence. You can apply the plugin at the global level or a per-service level for both db-less and database mode of Kong API gateway. For more information on Kong's db-less and database mode, see [Kong documentation](#). Following is a high-level list of features of the PingIntelligence plugin:

- You can apply the plugin at the global or per-service level for both database and db-less mode.
- The plugin supports keepalive connections.
- You can configure ASE primary and secondary nodes for failover. If both the primary and secondary nodes are not available, the plugin routes the connection to the backend servers.

The following diagram shows the logical setup of PingIntelligence and Kong API



gateway:

Here is the traffic flow through Kong API gateway and PingIntelligence for APIs components.

1. Client sends an incoming request to Kong
2. Kong makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and looks up the client identifier on the PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to

Kong. If not, a different response code is sent to Kong. The request information is also logged by ASE and sent to the AI Engine for processing.

4. If Kong receives a 200-OK response from ASE, then it forwards the request to the backend server. A request is blocked only when ASE sends a 403 error code to Kong.
5. The response from the backend server is received by Kong.
6. Kong makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to Kong.
8. Kong sends the response received from the backend server to the client.

## Prerequisites

---

Complete the following prerequisites for PingIntelligence and Kong API gateway before deploying the PingIntelligence plugin:

### PingIntelligence prerequisites

- **PingIntelligence software:** Make sure that PingIntelligence software is already installed. For more information on PingIntelligence for APIs installation, see [Automated deployment guide](#) or [Manual deployment guide](#).
- **Verify ASE mode:** Make sure that ASE is deployed in `sideband` mode. Run the `status` command to check the ASE mode:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                 : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set `mode` as `sideband` and start ASE. For more information on `ase.conf` file, see [Sideband ASE configuration - ase.conf](#) on page 162

- **Enable sideband authentication** - Enable sideband authentication if you want secure communication between Kong and ASE by entering the following command in the ASE command line:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

### Generate sideband authentication token

A token is required for Kong to authenticate with ASE. This token is generated in ASE and configured in the `kong.yml` file of PingIntelligence plugin. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

- **Configure keepalive in ase.conf** - If you want to keep alive the connections between Kong and ASE, set the value of `enable_sideband_keepalive` to `true`. If ASE is already running, stop ASE, edit

the `ase.conf` file and then start ASE. For more information on keepalive parameter, see [Sideband ASE configuration - ase.conf](#) on page 162.

### Kong Prerequisites

- Kong API gateway is already installed
- Luarocks, the Lua package manager, is installed on all the Kong nodes where you want to deploy the PingIntelligence module.

## Deploy PingIntelligence policy

---

Complete the following steps to deploy PingIntelligence plugin for Kong API gateway:

1. [Download](#) the PingIntelligence plugin for Kong and copy to `/opt/` directory on all the Kong nodes where you want to deploy PingIntelligence plugin.
2. Untar the plugin file by entering the following command:

```
$ untar pi-api-kong-policy-4.1.0.tar.gz
```

3. Change directory to `/opt/pingidentity/kong-policy`

```
$ cd /opt/pingidentity/kong-policy
```

4. Run the luarocks command to deploy the PingIntelligence plugin

```
$ luarocks make *.rockspec
```

This command installs the PingIntelligence plugin files at `/usr/local/share/lua/5.1/kong/plugins/pingintelligence/` location. This location may be different based on the version of Luarocks.

5. Configure `/opt/pingidentity/kong-policy/examples/kong.conf` to provide the plugin name. The default plugin name is `pingintelligence`. The plugin name that you configure in `kong.conf` is used in `kong.yml` file. Following is a sample `kong.conf` file.

**Note:** Edit your existing `kong.conf` file by copying the `plugins = bundled,pingintelligence` section.

```
#-----
# Kong sample configuration file
# -----

log_level = debug
plugins = bundled,pingintelligence

proxy_listen = 0.0.0.0:8000
admin_listen = 0.0.0.0:8001
database = off
declarative_config = /opt/pingidentity/kong-policy/examples/kong.yml
lua_ssl_trusted_certificate = /opt/pingidentity/kong-policy/certs/cacert.pem
lua_package_path = ./?.lua;./?/init.lua;
```

6. **db-less mode:** If you are running Kong in db-less mode, configure the `kong.yml` file for deploying the PingIntelligence plugin. The following table explains the variables of the file:

Variable	Description
<b>services</b> <ul style="list-style-type: none"> <li>▪ <code>name</code></li> <li>▪ <code>url</code></li> <li>▪ <code>routes</code></li> </ul>	<ul style="list-style-type: none"> <li>▪ <code>name</code> Name of the service or API</li> <li>▪ <code>url</code> The URL where the service or API is hosted</li> <li>▪ <code>routes</code> The subpaths of the service. A maximum of 3-subpaths are supported</li> </ul>
<b>plugins:</b> In this section, define the ASE specific variables for a service or API. <ul style="list-style-type: none"> <li>▪ <code>name</code></li> <li>▪ <code>service</code></li> </ul>	<ul style="list-style-type: none"> <li>▪ <code>name:</code> The name of the plugin. This name was configured in <code>kong.conf</code> file.</li> <li>▪ <code>service:</code> The name of the service API. If you want to apply the plugin to more than one service, create a service section for each service as shown in the example <code>kong.yml</code> file. For example, if you have three services or APIs, your <code>kong.yml</code> file should have three <code>service</code> sections, one for each service. The example <code>kong.yml</code> file has two sample service names configured.</li> </ul>
<b>config</b> <ul style="list-style-type: none"> <li>▪ <code>ase_primary_host</code></li> <li>▪ <code>ase_secondary_host</code></li> <li>▪ <code>ase_port</code></li> <li>▪ <code>ase_token</code></li> <li>▪ <code>ase_timeout</code></li> <li>▪ <code>ase_keepalive</code></li> <li>▪ <code>access_token</code></li> <li>▪ <code>use_tls</code></li> <li>▪ <code>sni_name</code></li> <li>▪ <code>tls_verify</code></li> </ul>	<ul style="list-style-type: none"> <li>▪ <code>ase_primary_host:</code> IP address of primary ASE node</li> <li>▪ <code>ase_secondary_host:</code> IP address of the secondary ASE node.</li> <li>▪ <code>ase_port:</code> Port number of the ASE node</li> <li>▪ <code>ase_token:</code> The sideband ASE token that was generated as part of the prerequisites</li> <li>▪ <code>ase_timeout:</code> The time in milliseconds for which Kong waits for ASE to respond before trying the other host. The default value is 5,000 ms</li> <li>▪ <code>ase_keepalive:</code> The time in milliseconds for the keepalive connection. The default value is 60,000 ms.</li> <li>▪ <code>access_token:</code> If OAuth token is part of the query string, the <code>access_token</code> field allows you to set the query param key that holds OAuth token in the query string</li> <li>▪ <code>use_tls:</code> Configures a TLS connection between the API gateway and ASE. The default value is <code>false</code>.</li> <li>▪ <code>sni_name:</code> Fully qualified domain name (FQDN) of the certificate applied to ASE data port</li> <li>▪ <code>tls_verify:</code> When set to <code>true</code>, the API gateway verifies the certificate. If the certificate validation fails, the connection is closed. When set to <code>false</code>, the API gateway does not verify the certificate, however, the connection between the API gateway and ASE is encrypted..</li> </ul>

- **Apply plugin at a per-service level:** Configure the `kong.yml` file as described in the table above with the service name of all the API or services to which you want to apply the plugin. Following is a sample `kong.yml` file:

```
#
-----
# This is an example file to get you started with using
# declarative configuration in Kong.
```



```

#
-----

# Metadata fields start with an underscore (_)
# Fields that do not start with an underscore represent Kong entities
  and attributes

# _format_version is mandatory,
# it specifies the minimum version of Kong that supports the format

_format_version: "1.1"

# Each Kong entity (core entity or custom entity introduced by a plugin)
# can be listed in the top-level as an array of objects:

services:
  - name: shop-books
    url: <your_service_url>
    routes:
      - name: shop-books-route
        paths:
          - /shopapi-books

  - name: shop-electronics
    url: <your_service_url>
    routes:
      - name: shop-electronics-route
        paths:
          - /shopapi-electronics

plugins:
  - name: pingintelligence
    service: shop-books
    _comment: "An example configuration of pingintelligence plugin"
    config:
      ase_primary_host: localhost
      ase_secondary_host: localhost

      ase_port: "8000"
      ase_token: 1ebd5fde1b0b4373a1ad8b8724d13813
      ase_timeout: "5000"
      ase_keepalive: "60000"
      access_token: access_token
      use_tls: false
      sni_name: test.ase.pi
      tls_verify: false
    tags:
      - api_security

  - name: pingintelligence
    service: shop-electronics
    _comment: "An example configuration of pingintelligence plugin"
    config:
      ase_primary_host: 172.16.40.220
      ase_secondary_host: 172.16.40.220
      ase_port: "8000"
      ase_token: 1ebd5fde1b0b4373a1ad8b8724d13813
      ase_timeout: "5000"
      ase_keepalive: "60000"
      access_token: access_token
      use_tls: false
      sni_name: test.ase.pi
      tls_verify: false
    tags:

```

```
- api_security
```

- **Apply plugin at the global level:** To apply the plugin at the global level, remove the `service` name from the `kong.yml` file as shown in the sample file below.

```
#
# -----
# This is an example file to get you started with using
# declarative configuration in Kong.
#
# -----
# Metadata fields start with an underscore (_)
# Fields that do not start with an underscore represent Kong entities
# and attributes
#
# _format_version is mandatory,
# it specifies the minimum version of Kong that supports the format
_format_version: "1.1"
#
# Each Kong entity (core entity or custom entity introduced by a plugin)
# can be listed in the top-level as an array of objects:
services:
  url: <your_service_url>
  routes:
    paths:

plugins:
  - name: pingintelligence
    _comment: "An example configuration of pingintelligence plugin"
    config:
      ase_primary_host: localhost
      ase_secondary_host: localhost

      ase_port: "8000"
      ase_token: 1ebd5fde1b0b4373a1ad8b8724d13813
      ase_timeout: "5000"
      ase_keepalive: "60000"
      access_token: access_token
      use_tls: false
      sni_name: test.ase.pi
      tls_verify: false
    tags:
      - api_security
```

7. Start the API gateway after the plugin has been deployed.

```
$ kong start -c kong.conf
```

**Note:** By default, Kong is configured to run its services on 8000 port and admin API on 8001 port. You can change these default ports in `kong.conf` file.

### Database mode

You can also optionally configure Kong to work in the database mode. If you are running Kong in the database mode, use the following `curl` commands to apply the plugin at a per-service level or global level. You can refer the config section in step-6 above for more details on the parameters sent as part of

the request in the `curl` commands. Make sure that Kong is running when you are applying the plugin in database mode.

- **Apply plugin at service level:** Run the following command to apply the plugin at a per service level:

```
curl --location --request POST '<kong_ip>:<kong_admin_port>/services/
<service_name>/plugins' \
--header 'Content-Type: application/json' \
--data-raw '{
  "name": "pingintelligence",
  "config": {
    "tls_verify": ,
    "sni_name": "",
    "ase_port": "",
    "ase_primary_host": "",
    "ase_token": "",
    "ase_timeout": "",
    "ase_keepalive": "",
    "ase_secondary_host": "",
    "access_token": "",
    "use_tls":
  }
}'
```

- **Apply plugin at the global level:** Run the following `curl` command to apply the plugin at the global level.

```
curl --location --request POST '<kong_ip>:<kong_admin_port>/plugins' \
--header 'Content-Type: application/json' \
--data-raw '{
  "name": "pingintelligence",
  "config": {
    "tls_verify": ,
    "sni_name": "",
    "ase_port": "",
    "ase_primary_host": "",
    "ase_token": "",
    "ase_timeout": "",
    "ase_keepalive": "",
    "ase_secondary_host": "",
    "access_token": "",
    "use_tls":
  }
}'
```

## Extracting user information when OIDC plugin is used

You can extract the user attributes from JWTs when OpenID Connect (OIDC) plugin is installed in Kong gateway. To do this, capture the header value assigned to `upstream_introspection_header` parameter in the OIDC plugin configuration. Assign this value to the location key in the `jwt` object of the API JSON file. ASE will extract the user information from the JWT.

If `upstream_introspection_header` is not configured in the OIDC plugin, then complete the following configuration and assign `x_introspection` to the location key in the `jwt` object of the API JSON file.

```
http patch :8001/plugins/$PLUGIN_ID config:=@patch.json
cat patch.json
{
  "upstream_introspection_header": "x_introspection"
}
```

The following is a snippet of JWT object from a sample API JSON file.

```
"jwt": {
  "location": "h:x_introspection",
  "username": "username",
  "clientid": "client_id"
}
```

For more information on configuring the API JSON file, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.


## Mulesoft API gateway integration

### Mulesoft sideband integration

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with Mulesoft API Gateway. A PingIntelligence policy is installed in the Mulesoft API Gateway and it passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking.

The PingIntelligence policy works with APIs that are configured with basic endpoint and also with APIs that are configured with proxy endpoint. The policy is simpler to deploy when applied to APIs that are configured with the endpoint with proxy option since more API metadata is already accessible by the policy.

#### Traffic flow for Mulesoft integration without user information




Here is the traffic flow through the Mulesoft and PingIntelligence for APIs components.

1. Client sends an incoming request to Mulesoft.
2. The PingIntelligence policy running in Mulesoft collects API metadata and token attributes.
3. Mulesoft makes an API call to send the request information to ASE. ASE checks the request against a registered set of APIs and checks the origin IP, cookie or OAuth2 token against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the Mulesoft. If not, a different response code is sent to Mulesoft. The request information is also logged by ASE and sent to the AI Engine for processing.

4. If Mulesoft receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, the Gateway optionally blocks the client.
5. The response from the backend server is received by Mulesoft. Mulesoft sends the response received from the backend server to the client.
6. Mulesoft makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing. ASE receives the response information and sends a 200-OK to Mulesoft.
7. Mulesoft sends the response to the client.

### Traffic flow for Mulesoft integration with user information

Here is the traffic flow through the Mulesoft and PingIntelligence for APIs components. PingFederate is used as the OAuth server to gather the user



information.

1. Client requests and receives an access token from PingFederate.
2. Client sends a request with the access token received from PingFederate.
3. Mulesoft verifies the authenticity of the access token with PingFederate.
4. If the token is invalid, Mulesoft returns a 401-unauthorized message to the client.
5. If the token is valid, the PingIntelligence policy running in Mulesoft collects API metadata and token attributes.
6. Mulesoft makes an API call to send the request information to ASE. ASE checks the request against a registered set of APIs and checks the origin IP, cookie or OAuth2 token against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the Mulesoft. If not, a different response code is sent to Mulesoft. The request information is also logged by ASE and sent to the AI Engine for processing.
7. If Mulesoft receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, the Gateway optionally blocks the client.
8. The response from the backend server is received by Mulesoft. Mulesoft sends the response received from the backend server to the client.

9. Mulesoft makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing. ASE receives the response information and sends a 200-OK to Mulesoft.
10. Mulesoft sends the response to the client.

## Prerequisites

Complete the following prerequisites before deploying PingIntelligence policy on MuleSoft:

### Prerequisite:

- **Versions** The PingIntelligence policy supports the 3.9.x and 4.x versions of MuleSoft. If you are using any other version, contact Ping Identity support.

**Note:** Due to a known bug in Mulesoft 4.2.2, you can encounter a 502 error response when the PingIntelligence policy is deployed with MuleSoft 4.2.2. Refer to the following [MuleSoft documentation](#) for more information about the issue and its resolution.

- **Install PingIntelligence software**

PingIntelligence software should be installed and configured. For more information, see [PingIntelligence manual deployment](#) on page 84 or [PingIntelligence automated deployment](#)

- **Verify that ASE is in sideband mode**

Check that ASE is in `sideband` mode by running the following ASE command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                 : sideband

http/ws                : port 80
https/wss              : port 443
firewall               : enabled
abs                    : disabled, ssl: enabled
abs attack             : disabled
audit                  : enabled
sideband authentication : disabled
ase detected attack    : disabled
attack list memory     : configured 128.00 MB, used 25.61 MB, free 102.39
  MB
google pubsub          : disabled
log level               : debug
timezone                : local (UTC)
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set `mode` as `sideband` and start ASE.

- **Enable sideband authentication:** For a secure communication between Mulesoft Anypoint and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for Mulesoft Anypoint to authenticate with ASE. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

Prerequisites to gather the user information

Complete this optional prerequisite to gather user information from PingFederate. To integrate PingFederate with Mulesoft follow the instructions detailed in [Configure Client Management PingFederate](#). This will enable PingFederate OAuth Token Enforcement policy. This policy should be applied before the PingIntelligence policy in the **Anypoint platform API Manager** as shown in the following screenshot.

Name	Category	Fulfills	Requires
> PingFederate access token enforcement ⓘ	Security	OAuth 2.0 protected	<a href="#">API Specification snippet</a>
> PingIntelligence ⓘ	Security	Message protection	

Currently the PingIntelligence policy supports PingFederate as authorization server.

## Deploy PingIntelligence policy

PingIntelligence provides a policy to deploy PingIntelligence 4.3 with Mulesoft 3.9 and 4.0. The policy package has the following two files:

- `pi_policy.yaml`
- `pi_policy.xml`

Follow the steps to deploy PingIntelligence policy based on the version of Mulesoft API gateway. For PingIntelligence to detect attacks based on username, make sure that the **PingFederate access token**

**enforcement** policy is the first policy deployed. PingIntelligence policy should be the second policy.

The screenshot shows the Mulesoft API Manager interface for the 'userinfo-mule39 v1' API. The API is active and has an asset version of 1.0.0 (Latest). A 'Configuration Detail' modal is open, showing the following configuration for the 'PingFederate access token enforcement' policy:

Policy	Configuration
PingFederate access token enforcement	
Scopes	openid profile email
Skip Client Id Validation	true

Below the modal, the 'API level policies' section shows a table of policies:

Name	Category	Fulfills						
PingFederate access token enforcement	Security	OAuth 2.0 protected						
<table border="1"> <thead> <tr> <th>Order</th> <th>Method</th> <th>Resource URI</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>All API Methods</td> <td>All API Resources</td> </tr> </tbody> </table>			Order	Method	Resource URI	1	All API Methods	All API Resources
Order	Method	Resource URI						
1	All API Methods	All API Resources						
PingIntelligence	Security	Message protection						

## PingIntelligence for Mulesoft 3.9


Before applying the PingIntelligence policy, make sure that the API to which you want to apply the policy is defined. The steps mentioned below use an API named PingIntelligenceAPI for illustration purpose.

### Deploying PingIntelligence policy to Mulesoft Anypoint


1. Log in to your Mulesoft Anypoint account.



2. Open API Manager by expanding the menu on the left-hand side.




3. In the API Administration page, click on Custom



Policies.

4. In the Custom policies page, click on Add custom



policy:

5. In the Add custom policy pop-up window, add the policy name, for example, PingIntelligence policy and upload the `pi_policy.yaml` and `pi_policy.xml` files.

Add custom policy
✕

**Mule Version**

Policy for runtimes older than Mule 4
  Policy for Mule 4 or later

**Name \***

|

PingIntelligence Policy

A YAML file defining the configuration parameters for the policy.

Choose File No file chosen

**Policy configuration \***

The Mule configuration XML for the policy implementation. Learn more [here](#).

Choose File No file chosen

Cancel

Add

PingIntelligence policy is added as shown below.

API Manager

Custom Policies

SANDBOX

API Administration

Automated Policies

Client Applications

Custom Policies

Analytics

**Custom policies**

Create [custom policies](#) that will be available to all APIs in your organization.

The policies listed on this page were created for **Mule 3.9, and earlier**.

In Mule 4 and later, policies are stored as assets in Exchange. Therefore, instead of API Manager, you have to go to Exchange to create policies. For more information, see [MuleSoft documentation](#).

Add custom policy

Name	Files	Fulfills	Requires	
PingIntelligence Policy	<a href="#">YAML</a> <a href="#">XML</a>	Message protection		Delete

## PingIntelligence for Mulesoft 4.x

Complete the following steps to deploy PingIntelligence policy for Mulesoft 4.x.

1. Create a project directory by following the instructions explained in [Getting started with Custom Policies development](#) link. The following screenshot shows an illustrative sample of a project directory structure.

```

my-custom-policy/
├── my-custom-policy.yaml
├── mule-artifact.json
├── pom.xml
├── src
│   └── main
│       └── mule
│           └── template.xml

```

2. PingIntelligence policy package provides three files for 4.x :

- `policy.xml`- Contains the actual logic of the policy.
- `policy.yaml`- Has details that render policy configuration UI.
- `pom.xml`- Specifies dependencies for policy compilation.

When the project's directory structure is created, replace the contents of `my-custom-policy.yaml` with that of `policy.yaml` file and the contents of `template.xml` with that of `policy.xml`. Similarly, replace the contents of `pom.xml` with that of `pom.xml` file provided in PingIntelligence policy package.

```

my-custom-policy/
├── my-custom-policy.yaml ← Copy the contents of policy.yaml
├── mule-artifact.json
├── pom.xml ← Copy the contents of pom.xml
├── src
│   └── main
│       └── mule
│           └── template.xml ← Copy the contents of policy.xml

```

Edit the `pom.xml` file to enter your organization's `groupId`:

```

<?xml version="1.0" encoding="UTF-8"?>
<project xmlns="http://maven.apache.org/POM/4.0.0"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://
maven.apache.org/xsd/maven-4.0.0.xsd">
  <modelVersion>4.0.0</modelVersion>

  <groupId>7a0f5884-ba26-4929-a681-66ca288a6992</groupId>

  <artifactId>PingIntelligence</artifactId>
  <version>1.2.0</version>
  <name>PingIntelligence</name>
  <description>ASE Sideband Policy for mule 4 with username info</
description>

```

- From the command line in your project' folder, run the following command. This packages the PingIntelligence policy and creates a deployable JAR file.

```
> mvn clean install
```

**Note:** You require license to MuleSoft Enterprise Repository for compiling the policy.

- Upload the PingIntelligence policy to **Exchange** by following the instructions under [Deploying a Policy Created Using the Maven Archetype](#).

The PingIntelligence policy is now available to apply to your APIs. For more information, see [Apply PingIntelligence policy](#) on page 692.

## Apply PingIntelligence policy

Complete the following steps to attach the PingIntelligence policy to your API:

**Note:** If you are applying the PingIntelligence policy in Mulesoft 3.9 and there is an earlier version of the policy already applied to your API, then remove the policy before applying PingIntelligence 4.3 policy. To remove the policy, follow the steps explained in [Remove existing PingIntelligence policy](#) on page 696.

- Log in to your Mulesoft Anypoint account.
- Navigate to the API manager and click on the **Version** of the API to which you want to attach the PingIntelligence policy.

The screenshot shows the MuleSoft API Manager interface. The main content area displays a table of API versions. The table has columns for API Name, Version, Status, Client Applications, and Creation Date. Two rows are visible: one for 'decoy' and one for 'PingIntelligenceAPI'. The 'PingIntelligenceAPI' row is highlighted with a yellow border. The 'decoy' row shows version v1, status Active, 0 client applications, and creation date 01-29-2019 13:38. The 'PingIntelligenceAPI' row shows version v1, status Active, 0 client applications, and creation date 01-30-2019 12:29.

API Name	Version	Status	Client Applications	Creation Date
decoy	v1	Active	0	01-29-2019 13:38
PingIntelligenceAPI	v1	Active	0	01-30-2019 12:29

3. On the API page, click on **Policies** as shown in the following illustration.

The screenshot shows the Mulesoft API Manager interface. The top navigation bar includes the Mulesoft logo and 'API Manager'. Below it, the breadcrumb trail is 'API Administration (Sandbox) > PingIntelligenceAPI (v1) - Settings'. The left sidebar contains a menu with 'SANDBOX' at the top, followed by 'API Administration', 'Alerts', 'Contracts', 'Policies' (highlighted with a yellow box), 'SLA Tiers', and 'Settings'. The main content area displays the details for 'PingIntelligenceAPI v1'. It shows 'API Status: Active', 'Asset Version: 1.0.0 Latest', 'Type: HTTP', and 'Implementation URL: https://...'. There is a '+ Add consumer endpoint' button. Below this, there are two columns: 'API Instance' with ID '15625345' and 'Autodiscovery' with API Name 'groupId:479b784e-68b3-4bb5-841d-017134ea013a:assetId:pingintelligenceapi'. The 'Label' is '+ Add a label' and the 'API Version' is 'v1:15625345'. A 'Proxy' section shows 'Proxy Application: PingIntelligenceAPI' and 'Proxy URL: pingintelligenceapi.us-e2.cloudhub.io'.

The Policies page supports applying the PingIntelligence policy to the API. Click on **Apply New**:

The screenshot shows the Mulesoft API Manager interface for the 'Policies' page. The breadcrumb trail is 'API Administration (Sandbox) > PingIntelligenceAPI (v1) - Policies'. The left sidebar menu is the same as in the previous screenshot, but 'Policies' is now highlighted with a blue bar. The main content area displays the details for 'PingIntelligenceAPI v1', including 'API Status: Active', 'Asset Version: 1.0.0 Latest', 'Type: HTTP', and 'Implementation URL: https://somebackend.com/'. There is a '+ Add consumer endpoint' button. Below this, there is a section titled 'API level policies' with a blue button labeled 'Apply New Policy' (highlighted with a yellow box). At the bottom of the page, there is a light blue box containing the text 'There are no applied policies.'

4. In the **Select Policy** pop-up window, select the PingIntelligence Policy and click on **Configure**

Policies	Requires
<input type="radio"/> Client ID enforcement ⓘ	—
<input type="radio"/> HTTP basic authentication ⓘ	Security manager
<input type="radio"/> IP blacklist ⓘ	—
<input type="radio"/> IP whitelist ⓘ	—
<input type="radio"/> JSON threat protection ⓘ	—
<input type="radio"/> LDAP security manager ⓘ	—
<input type="radio"/> OAuth 2.0 access token enforcement using external provider ⓘ	—
<input checked="" type="radio"/> PingIntelligence Policy Custom ⓘ	—

#### Policy.

5. In the Apply policy page, enter the following values:

- ASE Token that was generated as part of [prerequisite](#).
- ASE primary and secondary host and port. The traffic is sent to the ASE secondary host only when the primary ASE node is unreachable.
- Enable SSL for a secure HTTPS connection between Mulesoft and PingIntelligence ASE.
- Check the **Allow self-signed certificate** check-box to enable Mulesoft to accept a self-signed certificate from ASE.
- Configure the **Connection Timeout** and **Read Timeout**. The behavior of the API gateway is governed by Connection Timeout and Read Timeout, in the event of API Gateway not able to connect to ASE or the response from ASE is delayed.

Timeout parameter	Description
Connection Timeout	It governs the time the API gateway waits to establish a connection with ASE, following which it sends the client request to the backend server.

Timeout parameter	Description
Read Timeout	It governs the time the API Gateway waits for ASE's response before sending the request to the backend server.

The default value is 5000 milliseconds or Five-seconds. It is a good practice to configure a small value to limit the delay in case ASE is not reachable or unresponsive.

### Apply PingIntelligence policy

ASE sideband policy for Mule 4.X APIs deployed on Mule Cloudhub from Ping Identity

#### ASE TOKEN

ASE sideband authentication token

#### ASE Primary Host \*

Hostname or IP:Port

#### ASE Secondary Host \*

Hostname or IP:Port for failover

Enable SSL

If enabled, Mulesoft will connect to ASE over HTTPS

Allow self-signed certificate

If enabled, Mulesoft will accept self-signed certificate from ASE

#### Connection Timeout \*

Connection timeout in milliseconds

#### Read Timeout \*

Read timeout in milliseconds

#### USERNAME KEY

The key that holds the configured username in PingFederate

#### CLIENT ID KEY

The key that holds the configured client id in PingFederate

Cancel

Apply

### Note:

If there are any changes to the ASE endpoints, repeat the process explained in step-five and redeploy the configuration.

6. Navigate to your API and click on version number as described in step-one. In the API page, scroll down to the **Deployment Configuration** section and click on

Deployment Configuration ▾

Runtime version:

3.9.x ▾

Proxy application name: ⓘ

PingIntelligenceAPI

.cloudhub.io

Redeploy

### Redeploy.

Extracting response metadata for APIs with Basic endpoint

If your API is configured with Basic endpoint on Mulesoft version 3.9.x, then add the following properties in your Mule application.

- `http.status`
- `http.reason`
- `content-type`
- `content-length`

You can use `set-property` element to configure these properties in the Mule application. If required, you can also set other response side headers to send more information to the PingIntelligence policy. The following is a sample configuration of setting response side details. For more information on setting the properties in a Mule application, see [property transformer](#).

```
<set-property propertyName="http.status" value="200" doc:name="Property"/>
<set-property propertyName="http.reason" value="OK" doc:name="Property"/>
<set-property propertyName="content-type" value="application/json"
  doc:name="Property"/>
<set-property propertyName="content-length" value="21" doc:name="Property"/>
<set-property propertyName="set-cookie" value="PHPSESSIONID=CookieValue"
  doc:name="Property"/>
```


## Remove existing PingIntelligence policy

Remove earlier versions of PingIntelligence policy applied on your APIs, before applying PingIntelligence 4.3 policy. Complete the following steps to remove an existing policy from your API:

1. Log in to your Mulesoft Anypoint account.




- Navigate to the API manager. On the API Administration page, click on the **Version** of the API for which you want to remove the PingIntelligence




policy.

- On the API page, click on **Policies**. Click and expand the **PingIntelligence policy** and from the **Actions** list, select **Remove**.



4.



Click **Remove** to confirm the policy removal.

Once you remove the exiting policy from the API, follow the steps explained in [Apply PingIntelligence policy](#) on page 692 and apply the new PingIntelligence 4.3 policy.

## Next steps - Integration

---

After the policy deployment is complete, refer the following topics for next steps:

It is recommended to read the following topics (part of the admin guides) apart from reading the [ASE](#) and [ABS](#) Admin Guides:

- [ASE port information](#)
- [API naming guidelines](#)
- Adding APIs to ASE in [Sideband ASE](#). You can add individual APIs or you can configure a global API. For more information, see [API discovery and configuration](#) on page 347.
- [Connect ASE and ABS](#)

After you have added your APIs in ASE, the API model needs to be trained. The training of API model is completed in ABS. The following topics give a high level view, however it is a good practice to read the entire ABS Admin Guide.

- [Train your API model](#)
- [Generate and view the REST API reports using Postman.](#)
- [View PingIntelligence for APIs Dashboard.](#)

### API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.


## NGINX integration

---

### NGINX sideband integration

---

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with NGINX. PingIntelligence policy modules are installed in the NGINX and pass API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking.



Here is the traffic flow through NGINX and PingIntelligence for APIs components.

1. Client sends an incoming request to NGINX
2. NGINX makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and looks for the origin IP, cookie, OAuth2 token or API key in PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to the NGINX. If not, a different response code is sent to NGINX. The request information is also logged by ASE and sent to the AI Engine for processing.
4. If NGINX receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, NGINX optionally blocks the client.
5. The response from the backend server is received by NGINX.
6. NGINX makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to NGINX.
8. NGINX sends the response received from the backend server to the client.

## Prerequisites

Prerequisite is divided in three sections. Prerequisite for PingIntelligence applies to both RHEL 7.6 and Ubuntu 16.04. Complete the prerequisite based on your operating system.

- [Prerequisites for PingIntelligence](#)
- [Prerequisite for RHEL 7.6](#)
- [Prerequisite for Ubuntu 16.04](#)

## Prerequisite for PingIntelligence

The prerequisites are divided in the three sections:

This section assumes that you have installed and configured PingIntelligence software. For more information on PingIntelligence installation, see [PingIntelligence setup](#) on page 46 or [PingIntelligence manual deployment](#) on page 84

- **Verify that ASE is in sideband mode:** Log in to your ASE machine and check that ASE is in sideband mode by running the following `status` command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                 : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

- **Enable sideband authentication:** For secure communication between NGINX and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for NGINX to authenticate with ASE. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use in [Configure NGINX for PingIntelligence](#) on page 703

## Prerequisites for RHEL 7.6

Complete the following prerequisites before deploying PingIntelligence policy on NGINX:

- **NGINX version:** The PingIntelligence policy modules are compiled for NGINX 1.14.2. If you have a different version of NGINX, contact Ping Identity support.
- **RHEL version:** RHEL 7.6. Verify your RHEL version by entering the following command on your machine:

```
$ cat /etc/redhat-release
Red Hat Enterprise Linux Server release 7.6 (Maipo)
```

- **OpenSSL version:** OpenSSL 1.0.2k-fips on your RHEL 7.6 machine. You can check the OpenSSL version using the `openssl version` command.

```
$ openssl version
OpenSSL 1.0.2k-fips 26 Jan 2017
```

- **Extract ASE certificate:** Complete the following steps to extract the ASE certificate:
  1. Make sure that ASE is running. If ASE is not running, run the following command on ASE command line to start ASE:

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.0.2...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

For more information on starting ASE, see [Start and stop ASE](#) on page 126

2. Run the following command:

```
openssl s_client -connect <ASE_IP>:<ASE_PORT> 2>/dev/null </dev/null |
sed -ne '/-BEGIN CERTIFICATE-/,/-END CERTIFICATE-/p' > test.ase.pi
```

This command extract the ASE certificate and appends in `test.ase.pi` file. Copy the certificate file to the NGINX machine and configure the certificate path in `nginx.conf` file.

- **Download dependencies for RHEL:** Run the following command to download RHEL dependencies for compiling NGINX:

```
# yum install pcre-devel.x86_64 openssl-devel.x86_64 zlib-devel.x86_64
wget gcc
```

**ⓘ Important:** The PingIntelligence modules for NGINX 1.14.2 are specifically compiled for RHEL 7.6 and OpenSSL 1.0.2k-fips. If you do not have these specific versions of RHEL and OpenSSL, contact Ping Identity support.

#### Prerequisites for Ubuntu 16.0.4 LTS

Complete the following prerequisites before deploying PingIntelligence policy on NGINX:

- **NGINX version:** The PingIntelligence policy modules are compiled for NGINX 1.14.2. If you have a different version of NGINX, contact Ping Identity support.
- **Ubuntu version:** Ubuntu 16.04 LTS. Run the following command to check your Ubuntu version:

```
$ cat /etc/os-release
NAME="Ubuntu"
VERSION="16.04.6 LTS (Xenial Xerus)"
ID=ubuntu
ID_LIKE=debian
PRETTY_NAME="Ubuntu 16.04.6 LTS"
VERSION_ID="16.04"
HOME_URL="http://www.ubuntu.com/"
SUPPORT_URL="http://help.ubuntu.com/"
BUG_REPORT_URL="http://bugs.launchpad.net/ubuntu/"
VERSION_CODENAME=xenial
UBUNTU_CODENAME=xenial
```

- **OpenSSL version:** OpenSSL 1.0.2g. You can the check the OpenSSL version using the `openssl version` command:

```
$ openssl version
OpenSSL 1.0.2g 26 Jan 2017
```

- **Extract ASE certificate:** Complete the following steps to extract the ASE certificate:
  1. Make sure that ASE is running. If ASE is not running, run the following command on ASE command line to start ASE:

```
/opt/pingidentity/ase/bin/start.sh
Starting API Security Enforcer 4.0.2...
please see /opt/pingidentity/ase/logs/controller.log for more details
```

For more information on starting ASE, see [Start and stop ASE](#) on page 126

2. Run the following command:

```
openssl s_client -connect <ASE_IP>:<ASE_PORT> 2>/dev/null </dev/null |
sed -ne '/-BEGIN CERTIFICATE-/,/-END CERTIFICATE-/p' > test.ase.pi
```

This command extract the ASE certificate and appends in `test.ase.pi` file. Copy the certificate file to the NGINX machine and configure the certificate path in `nginx.conf` file.

- **Download dependencies for Ubuntu:** Run the following command to download Ubuntu dependencies for compiling NGINX:

```
# apt-get -yq install make g++ gcc libpcre3 libpcre3-dev apt-utils zlib1g
zlib1g-dev curl openssl libssl-dev
```

**i Important:** The PingIntelligence modules are specifically compiled for Ubuntu 16.0.4 and OpenSSL 1.0.2g. If you do not have these specific versions of Ubuntu and OpenSSL, contact Ping Identity support.

## NGINX for RHEL 7.6

To compile NGINX Community Edition 1.14.2 for PingIntelligence for APIs, complete the following steps:

1. Download the NGINX community version:

```
# wget https://nginx.org/download/nginx-1.14.2.tar.gz
```

2. Untar the NGINX file:

```
# tar -xvzf nginx-1.14.2.tar.gz
```

3. Change directory to `nginx-1.14.2`

```
# cd nginx-1.14.2
```

4. Compile and install NGINX by running the following command: Note that these options for compiling NGINX are in addition to your environment specific options.

```
# ./configure --with-compat --with-http_ssl_module
```

`--with-compat:` This option enables NGINX to load dynamic modules.

`--with_http_ssl_module:` This flag is used configure SSL support in NGINX.

5. Run the `make` command to compile NGINX:

```
# make
```

6. Run the `make install` command to install NGINX:

```
# sudo make install
```

7. Verify the compilation by entering the following command:

```
# sudo /usr/local/nginx/sbin/nginx -V
```

The output of the above command should display `--with-compat` and `--with_http_ssl_module` flags.

## Configure NGINX for PingIntelligence

Configure the `nginx.conf` setup NGINX and PingIntelligence sideband integration. Following is a summary of steps to configure NGINX for PingIntelligence:

1. Create `modules` directory inside NGINX
2. Download PingIntelligence modules
3. Copy PingIntelligence modules in the `modules` directory
4. Edit `nginx.conf` for PingIntelligence

### Create `modules` directory and download PingIntelligence modules

1. Create a `modules` directory in NGINX:

```
# mkdir /usr/local/nginx/modules
```

2. Download the NGINX - PingIntelligence modules from the [download](#) site
3. Untar the downloaded file.

```
# tar -xvzf rhel_modules_1.14.2.tgz
modules/
modules/nginx-oss-list.txt
modules/nginx_ase_integration_module.so
modules/nginx_http_ase_integration_response_module.so
modules/nginx_http_ase_integration_request_module.so
```

The three PingIntelligence modules are:

- a. `nginx_ase_integration_module.so`
  - b. `nginx_http_ase_integration_request_module.so`
  - c. `nginx_http_ase_integration_response_module.so`
4. Copy the three PingIntelligence modules files for RHEL to the `modules` directory of NGINX.

```
# cp nginx_ase_integration_module.so /usr/local/nginx/modules
# cp nginx_http_ase_integration_request_module.so /usr/local/nginx/modules
# cp nginx_http_ase_integration_response_module.so /usr/local/nginx/modules
```

Configure `nginx.conf`:

Complete the following steps to configure `nginx.conf` for PingIntelligence. Make sure that the PingIntelligence module and other configurations are added at the correct place in `nginx.conf` as shown in the sample file at the end of the section.

1. **Load PingIntelligence modules:** Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence modules:

```
worker_processes 1;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;
```

```

pid                /usr/local/nginx/pid/nginx.pid;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;

events {
    worker_connections 1024;
}

http {
    keepalive_timeout 65;
    upstream pi.ase {
        server IP:PORT max_fails=1 max_conns=1024 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=1024 fail_timeout=10 backup;
        keepalive 32;
    }
}
truncated nginx.conf

```

IP:PORT is the IP address of primary and secondary ASE.

2. Add primary and secondary ASE hosts in `nginx.conf` in the upstream section. Following is a snippet of `nginx.conf` file with an ASE primary and secondary host configuration:

```

http {
    keepalive_timeout 65;
    upstream pi.ase {
        server 192.168.11.12:443 max_fails=3 max_conns=1024 fail_timeout=10;
        server 192.168.11.13:443 max_fails=3 max_conns=1024 fail_timeout=10 backup;
        keepalive 32;
    }
}

```

### 3. Configure SSL certificate:

Configure a SSL certificate location and ASE sideband authentication token in `nginx.conf`. ASE certificate was extracted from ASE in [Prerequisites](#) on page 699. Copy the certificate to `/usr/local/nginx/ssl/test.ase.pi` on the NGINX machine and configure the certificate path in `nginx.conf` file.

The sideband authentication token was created as part of the [Prerequisites](#) in the PingIntelligence section. Following is a snippet the showing certificate location and sideband authentication token:

```

#Certificate location of ASE
set $certificate /usr/local/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <YOUR ASE SIDEBAND TOKEN>;

```

**Note:** You can also use your own SSL certificate by providing the path to the certificate in `set $certificate`. Make sure that ASE has the updated certificate.

4. **Configure ASE request and response:** Configure ASE request and response API endpoints in `nginx.conf`. Following snippet of `nginx.conf` shows ASE request and response:

```

#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
}

```



```

ase_integration_http_version 1.1;
ase_integration_ase_token $ase_token;
ase_integration_correlation_id $correlationid;
ase_integration_host pi.ase;
ase_integration_ssl_trusted_certificate /usr/local/nginx/ssl/
test.ase.pi;
ase_integration_ssl_verify off;
ase_integration_ssl_verify_depth 1;
ase_integration_ssl_server_name on;
ase_integration_ssl_name test.ase.pi;
ase_integration_next_upstream error timeout non_idempotent;

#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host pi.ase;
    ase_integration_ssl_trusted_certificate /usr/local/nginx/ssl/
test.ase.pi;
ase_integration_ssl_verify off;
ase_integration_ssl_verify_depth 1;
ase_integration_ssl_server_name on;
ase_integration_ssl_name test.ase.pi;
ase_integration_next_upstream error timeout non_idempotent;

```

**Note:** `ase_integration_ssl_verify` is optional for non-SSL ASE connection.

- 5. Apply PingIntelligence policy:** Apply PingIntelligence modules for APIs by configuring location in `nginx.conf`. `ase_integration_request` should be the first and a `ase_integration_response` should be the last.

```

location / {
    ase_integration_request;
    proxy_pass http://localhost:8080/;
    ase_integration_response;
}

```

If you have more than more than one API, configure a `location` for each API as shown above.

- 6. Verify:** Verify that `nginx.conf` is syntactically correct by running the following command:

```

# sudo /usr/local/nginx/sbin/nginx -t
nginx: the configuration file /usr/local/nginx/conf/nginx.conf syntax is
ok
nginx: configuration file /usr/local/nginx/conf/nginx.conf test is
successful

```

- 7. Restart:** Restart NGINX by entering the following command:

```

# sudo /usr/local/nginx/sbin/nginx -s stop
# sudo /usr/local/nginx/sbin/nginx

```

- 8. Run the following command to verify if `--with-compat` and `--with-http_ssl_module` is in the list of flags under configured arguments.**

```

# sudo /usr/local/nginx/sbin/nginx -V
nginx version: nginx/1.14.2

```

```

built by gcc 5.4.0 20160609 (Ubuntu 5.4.0-6ubuntu1~16.04.11)
built with OpenSSL 1.0.2g 1 Mar 2016
TLS SNI support enabled
configure arguments: --with-compat --with-http_ssl_module

```

9. Verify that NGINX has restarted by entering the following command:

```
# netstat -tulpn | grep 4443
```

Following is a sample `nginx.conf` for reference:

```

worker_processes 1;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;

events {
    worker_connections 1024;
}

http {
    keepalive_timeout 65;
    upstream pi.ase {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
    }
}

server {
    # remove "ssl" from the below line for a non-SSL frontend
    listen 4443 ssl bind;
    server_name localhost;

    # Comment out the next 5-lines for a non-SSL frontend
    ssl_certificate /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
    ssl_password_file /usr/local/nginx/ssl/password_file;
    ssl_protocols TLSv1.2;
    ssl_ciphers HIGH:!aNULL:!MD5;

    #root /usr/share/nginx/html;
    #charset koi8-r;
    #access_log /var/log/nginx/host.access.log main;
    resolver 8.8.8.8 ipv6=off;

    #The following location configuration is to configure your application.
    A corresponding API JSON should be present in ASE.
    location / {
        ase_integration_request;
        proxy_pass http://localhost:8080/;
        ase_integration_response;
    }
}

```

```

    }

    #The following configuration is a Ping Intelligence configuration and do
    not edit
    set $correlationid $pid-$request_id-$server_addr-$remote_addr-
    $remote_port-$request_length-$connection;

# ASE token must be configured
# ASE certificate must be copied under /usr/local/nginx/ssl/ and update the
set $certificate to the # certificate file path
#Certificate location of ASE
set $certificate /usr/local/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <YOUR ASE SIDEBAND TOKEN HERE>;
#Host header which should be send to ASE
set $ase_host pi.ase;
#SNI value to use for ASE
set $ase_ssl_host pi.ase;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
}

```

## NGINX for Ubuntu 16.04

---

To compile NGINX Community Edition 1.14.2 for PingIntelligence for APIs, complete the following steps:

1. Download the NGINX community version:

```
# wget https://nginx.org/download/nginx-1.14.2.tar.gz
```

**2. Untar the NGINX file:**

```
# tar -xvzf nginx-1.14.2.tar.gz
```

**3. Change directory to nginx-1.14.2**

```
# cd nginx-1.14.2
```

**4. Compile and install NGINX by running the following command: Note that these options for compiling NGINX are in addition to your environment specific options.**

```
# ./configure --with-compat --with-http_ssl_module
```

--with-compat: This option enables NGINX to load dynamic modules.

--with\_http\_ssl\_module: This flag is used configure SSL support in NGINX.

**5. Run the `make` command to compile NGINX:**

```
# make
```

**6. Run the `make install` command to install NGINX:**

```
# sudo make install
```

**7. Verify the compilation by entering the following command:**

```
# sudo /usr/local/nginx/sbin/nginx -V
```

The output of the above command should display `--with-compat` and `--with_http_ssl_module` flags.

## Configure NGINX for PingIntelligence

Configure the `nginx.conf` setup NGINX and PingIntelligence sideband integration. Following is a summary of steps to configure NGINX for PingIntelligence:

1. Create `modules` directory inside NGINX
2. Download PingIntelligence modules
3. Copy PingIntelligence modules in the `modules` directory
4. Edit `nginx.conf` for PingIntelligence

**Create `modules` directory and download PingIntelligence modules****1. Create a `modules` directory in NGINX:**

```
# mkdir /usr/local/nginx/modules
```

2. Download the NGINX - PingIntelligence modules from the [download](#) site
3. Untar the downloaded file.

```
tar -xvzf ubuntu_modules_1.14.2.tgz
modules/
modules/nginx-oss-list.txt
modules/nginx_ase_integration_module.so
modules/nginx_http_ase_integration_response_module.so
```

```
modules/nginx_http_ase_integration_request_module.so
```

The three PingIntelligence modules are:

- a. ngx\_ase\_integration\_module.so
- b. ngx\_http\_ase\_integration\_request\_module.so
- c. ngx\_http\_ase\_integration\_response\_module.so

4. Copy the three PingIntelligence modules for Ubuntu to the `modules` directory of NGINX.

```
# cp ngx_ase_integration_module.so /usr/local/nginx/modules
# cp ngx_http_ase_integration_request_module.so /usr/local/nginx/modules
# cp ngx_http_ase_integration_response_module.so /usr/local/nginx/modules
```

Configure `nginx.conf`:

Complete the following steps to configure `nginx.conf` for PingIntelligence. Make sure that the PingIntelligence module and other configurations are added at the correct place in `nginx.conf` as shown in the sample file at the end of the section.

1. **Load PingIntelligence modules:** Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence modules:

```
worker_processes 1;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;

load_module modules/ngx_ase_integration_module.so;
load_module modules/ngx_http_ase_integration_request_module.so;
load_module modules/ngx_http_ase_integration_response_module.so;

events {
    worker_connections 1024;
}

http {
    keepalive_timeout 65;
    upstream pi.ase {
        server IP:PORT max_fails=1 max_conns=1024 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=1024 fail_timeout=10 backup;
        keepalive 32;
    }
}
truncated nginx.conf
```

IP:PORT is the IP address of primary and secondary ASE.

2. Add primary and secondary ASE hosts in `nginx.conf` in the upstream section. Following is a snippet of `nginx.conf` file with an ASE primary and secondary host configuration:

```
http {
    keepalive_timeout 65;
    upstream pi.ase {
        server 192.168.11.12:443 max_fails=3 max_conns=1024 fail_timeout=10;
        server 192.168.11.13:443 max_fails=3 max_conns=1024 fail_timeout=10 backup;
        keepalive 32;
    }
}
```

```
}

```

### 3. Configure SSL certificate:

Configure a SSL certificate location and ASE sideband authentication token in `nginx.conf`. ASE certificate was extracted from ASE in [Prerequisites](#) on page 699. Copy the certificate to `/usr/local/nginx/ssl/test.ase.pi` on the NGINX machine and configure the certificate path in `nginx.conf` file.

The sideband authentication token was created as part of the [Prerequisites](#) in the PingIntelligence section. Following is a snippet the showing certificate location and sideband authentication token:

```
#Certificate location of ASE
set $certificate /usr/local/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <YOUR ASE SIDEBAND TOKEN>;
```

**Note:** You can also use your own SSL certificate by providing the path to the certificate in `set $certificate`. Make sure that ASE has the updated certificate.

### 4. Configure ASE request and response: Configure ASE request and response API endpoints in `nginx.conf`. Following snippet of `nginx.conf` shows ASE request and response:

```

#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host pi.ase;
    ase_integration_ssl_trusted_certificate /usr/local/nginx/ssl/
test.ase.pi;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name on;
    ase_integration_ssl_name test.ase.pi;
    ase_integration_next_upstream error timeout non_idempotent;
}

#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host pi.ase;
    ase_integration_ssl_trusted_certificate /usr/local/nginx/ssl/
test.ase.pi;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name on;
    ase_integration_ssl_name test.ase.pi;
    ase_integration_next_upstream error timeout non_idempotent;
}

```

**Note:** `ase_integration_ssl_verify` is optional for non-SSL ASE connection.

- 5. Apply PingIntelligence policy:** Apply PingIntelligence modules for APIs by configuring location in `nginx.conf`. `ase_integration_request` should be the first and `ase_integration_response` should be the last.

```
location /shop {
    ase_integration_request;
    proxy_pass http://localhost:8000/;
    ase_integration_response;
}
```

If you have more than one API, configure a location for each API as shown above.

- 6. Verify:** Verify that `nginx.conf` is syntactically correct by running the following command:

```
# sudo /usr/local/nginx/sbin/nginx -t
nginx: the configuration file /usr/local/nginx/conf/nginx.conf syntax is
ok
nginx: configuration file /usr/local/nginx/conf/nginx.conf test is
successful
```

- 7. Restart:** Restart NGINX by entering the following command:

```
# sudo /usr/local/nginx/sbin/nginx -s stop
# sudo /usr/local/nginx/sbin/nginx
```

- 8. Run the following command to verify if `--with-compat` and `--with-http_ssl_module` is in the list of flags under configured arguments.**

```
# sudo /usr/local/nginx/sbin/nginx -V
nginx version: nginx/1.14.2
built by gcc 5.4.0 20160609 (Ubuntu 5.4.0-6ubuntu1~16.04.11)
built with OpenSSL 1.0.2g 1 Mar 2016
TLS SNI support enabled
configure arguments: --with-compat --with-http_ssl_module
```

- 9. Verify that NGINX has restarted by entering the following command:**

```
# netstat -tulpn | grep 4443
```

Following is a sample `nginx.conf` for reference:

```
worker_processes 1;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;

events {
    worker_connections 1024;
```

```

}

http {
    keepalive_timeout 65;
    upstream pi.ase {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
    }
}

server {
    # remove "ssl" from the below line for a non-SSL frontend
    listen          4443 ssl bind;
    server_name     localhost;

    # Comment out the next 5-lines for a non-SSL frontend
    ssl_certificate     /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
    ssl_password_file   /usr/local/nginx/ssl/password_file;
    ssl_protocols       TLSv1.2;
    ssl_ciphers         HIGH:!aNULL:!MD5;

    #root            /usr/share/nginx/html;
    #charset koi8-r;
    #access_log /var/log/nginx/host.access.log  main;
    resolver 8.8.8.8 ipv6=off;

    #The following location configuration is to configure your application.
    A corresponding API JSON should be present in ASE.
    location / {
        ase_integration_request;
        proxy_pass http://localhost:8080/;
        ase_integration_response;
    }

    #The following configuration is a Ping Intelligence configuration and do
    not edit
    set $correlationid $pid-$request_id-$server_addr-$remote_addr-
    $remote_port-$request_length-$connection;

    # ASE token must be configured
    # ASE certificate must be copied under /usr/local/nginx/ssl/ and update the
    set $certificate to the # certificate file path
    #Certificate location of ASE
    set $certificate /usr/local/nginx/ssl/test.ase.pi;
    #ASE Token for sideband authentication
    set $ase_token <YOUR ASE SIDEBAND TOKEN HERE>;
    #Host header which should be send to ASE
    set $ase_host pi.ase;
    #SNI value to use for ASE
    set $ase_ssl_host pi.ase;
    #ASE Request Proxy Configuration
    location = /ase/request {
        internal;
        ase_integration https://pi.ase;
        ase_integration_method "POST";
        ase_integration_http_version 1.1;
        ase_integration_ase_token $ase_token;
        ase_integration_correlation_id $correlationid;
        ase_integration_host $ase_host;
        ase_integration_ssl_trusted_certificate $certificate;
        ase_integration_ssl_verify off;
    }
}

```



```

ase_integration_ssl_verify_depth 1;
ase_integration_ssl_server_name off;
ase_integration_ssl_name $ase_ssl_host;
ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://pi.ase;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
}

```

## Next steps - integration

---

After the policy deployment is complete, refer the following topics for next steps:

It is recommended to read the following topics (part of the admin guides) apart from reading the [ASE](#) and [ABS Admin Guides](#):

- [Customizing ASE ports](#) on page 124
- [API naming guidelines](#) on page 169
- Adding APIs to ASE in [Defining an API using API JSON configuration file in sideband mode](#) on page 170. You can add individual APIs or you can configure a global API. For more information on global API, see [API discovery and configuration](#) on page 347.
- [ABS AI-based security](#) on page 193

After you have added your APIs in ASE, the API model needs to be trained. The training of API model is completed in ABS. The following topics give a high level view, however it is a good practice to read the entire ABS Admin Guide.

- [Training the ABS model](#) on page 338
- [API reports using Postman](#) on page 413 .
- [Access PingIntelligence Dashboard](#) on page 20 .

### API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. APIs are discovered when a global API JSON is defined in the ASE. For more information, see [API discovery and configuration](#) on page 347 . You can edit the discovered API's JSON definition in Dashboard before adding them to ASE. For more information on editing and configuring API discovery, see [Discovered APIs](#) on page 540.


# NGINX Plus integration

## NGINX Plus sideband integration

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with NGINX Plus. A PingIntelligence sideband policy is installed in NGINX Plus and passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking. PingIntelligence software adds support for reporting and attack detection based on usernames captured from token attributes.

### Traffic flow for NGINX Plus integration without user information

Here is the traffic flow through NGINX and PingIntelligence for APIs components.




1. Client sends an incoming request to NGINX
2. NGINX makes an API call to send the request metadata to ASE
3. ASE checks the request against a registered set of APIs and looks for the origin IP, cookie, OAuth2 token or API key in PingIntelligence AI engine generated Blacklist. If all checks pass, ASE returns a 200-OK response to the NGINX. If not, a different response code is sent to NGINX. The request information is also logged by ASE and sent to the AI Engine for processing.
4. If NGINX receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, NGINX optionally blocks the client.

5. The response from the backend server is received by NGINX.
6. NGINX makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing.
7. ASE receives the response information and sends a 200-OK to NGINX.
8. NGINX sends the response received from the backend server to the client.

### Traffic flow for NGINX Plus integration with user information

Here is the traffic flow through the NGINX Plus and PingIntelligence for APIs components. PingFederate is used as the OAuth server to gather the user information:



1. Client requests and receives an access token from PingFederate.
2. Client sends a request with the access token received from PingFederate.
3. NGINX Plus verifies the authenticity of the access token with PingFederate.
4. If the request is invalid, ASE sends a 403 error and NGINX Plus drops the connection request.
5. If the token is valid, the PingIntelligence policy running in NGINX Plus collects API metadata and token attributes. In case of an invalid token, the request is allowed, however, without user information.
6. NGINX Plus makes an API call to send the request information to ASE. ASE checks the request against a registered set of APIs and checks the origin IP, cookie or OAuth2 token against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the NGINX Plus. If not, a different response code is sent to NGINX Plus. The request information is also logged by ASE and sent to the AI Engine for processing.
7. If NGINX Plus receives a 200-OK response from ASE, then it forwards the request to the backend server. Otherwise, the Gateway optionally blocks the client.
8. The response from the backend server is received by NGINX Plus. NGINX Plus sends the response received from the backend server to the client.
9. NGINX Plus makes a second API call to pass the response information to ASE which sends the information to the AI engine for processing. ASE receives the response information and sends a 200-OK to NGINX Plus.
10. NGINX Plus sends the response to the client.

## Prerequisites

Prerequisite is divided in three sections. Prerequisite for PingIntelligence applies to both RHEL 7.6 and Ubuntu 16.0.4. Complete the prerequisite based on your operating system. The prerequisite section is divided in the following four sections:

- [Prerequisites for PingIntelligence](#) on page 716
- [Prerequisites for RHEL 7.6](#) on page 716
- [Prerequisites for Ubuntu 16.0.4](#) on page 717
- [Prerequisites for Debian 9](#) on page 718

### Prerequisites for PingIntelligence

This section assumes that you have installed and configured PingIntelligence software. For more information on PingIntelligence installation, see [PingIntelligence setup](#) on page 46 or [PingIntelligence manual deployment](#) on page 84

- **Verify that ASE is in sideband mode:** Log in to your ASE machine and check that ASE is in sideband mode by running the following `status` command:

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                 : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : enabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.60 MB, free 102.40
MB
```

If ASE is not in sideband mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as sideband and start ASE.

- **Enable sideband authentication:** For secure communication between NGINX and ASE, enable sideband authentication by entering the following ASE command:

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p admin
```

- **Generate sideband authentication token**

A token is required for NGINX to authenticate with ASE. To generate the token in ASE, enter the following command in the ASE command line:

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use in [Configure NGINX Plus for RHEL 7.6](#) or [Configure NGINX Plus for Ubuntu 16.0.4](#).

### Prerequisites for RHEL 7.6

Complete the following prerequisites before deploying PingIntelligence policy on NGINX Plus:

- **NGINX Plus version:** The PingIntelligence policy modules are compiled for NGINX Plus R16. If you have a different version of NGINX Plus, contact Ping Identity support.

- **RHEL version:** RHEL 7.6. Verify your RHEL version by entering the following command on your machine:

```
$ cat /etc/redhat-release
Red Hat Enterprise Linux Server release 7.6 (Maipo)
```

- **OpenSSL version:** OpenSSL 1.0.2k-fips on your RHEL 7.6 machine. You can check the OpenSSL version using the `openssl version` command.

```
$ openssl version
OpenSSL 1.0.2k-fips 26 Jan 2017
```

**i Important:** The PingIntelligence modules for NGINX Plus have been specifically compiled for RHEL 7.6 and OpenSSL 1.0.2k-fips. If you have different versions of these components, contact Ping Identity support.

- **Configure NGINX Plus certificates:** Complete the following steps to configure certificate for NGINX Plus:

1. Create a directory for SSL certificates:

```
# sudo mkdir -p /etc/ssl/nginx
```

2. Login to NGINX customer portal and download `nginx-repo.key` and `nginx-repo.crt` to `/etc/ssl/nginx`

For more information, see [Installing NGINX Plus](#)

- **Download dependencies for RHEL:** Run the following command to download dependencies for RHEL:

```
# yum install wget ca-certificates
```

#### Prerequisites for Ubuntu 16.0.4

Complete the following prerequisites before deploying PingIntelligence policy on NGINX Plus:

- **NGINX version:** The PingIntelligence policy modules are compiled for NGINX Plus R16. If you have a different version of NGINX Plus, contact Ping Identity support.
- **Ubuntu version:** Ubuntu 16.04 LTS. Run the following command to check your Ubuntu version:

```
$ cat /etc/os-release
NAME="Ubuntu"
VERSION="16.04 LTS (Xenial Xerus)"
ID=ubuntu
ID_LIKE=debian
PRETTY_NAME="Ubuntu 16.04.6 LTS"
VERSION_ID="16.04"
HOME_URL="http://www.ubuntu.com/"
SUPPORT_URL="http://help.ubuntu.com/"
BUG_REPORT_URL="http://bugs.launchpad.net/ubuntu/"
VERSION_CODENAME=xenial
UBUNTU_CODENAME=xenial
```

- **OpenSSL version:** OpenSSL 1.0.2g. You can check the OpenSSL version using the `openssl version` command:

```
$ openssl version
OpenSSL 1.0.2g 26 Jan 2017
```

- **Download dependencies for Ubuntu:** Run the following command to download dependencies for Ubuntu:

```
# sudo apt-get install apt-transport-https lsb-release ca-certificates
```

- **Configure NGINX Plus certificates:** Complete the following steps to configure certificate for NGINX Plus:

1. Create a directory for SSL certificates:

```
# sudo mkdir -p /etc/ssl/nginx
```

2. Login to NGINX customer portal and download `nginx-repo.key` and `nginx-repo.crt` to `/etc/ssl/nginx`

For more information, see [Installing NGINX Plus](#)

**i Important:** The PingIntelligence modules are specifically compiled for Ubuntu 16.0.4 and OpenSSL 1.0.2g. If you do not have these specific versions of Ubuntu and OpenSSL, contact Ping Identity support.

### Prerequisites for Debian 9

Complete the following prerequisites before deploying PingIntelligence policy on NGINX Plus:

- **NGINX version:** The PingIntelligence policy modules are compiled for NGINX Plus R19. If you have a different version of NGINX Plus, contact Ping Identity support.
- **Debian version:** Debian 9 (stretch). Run the following command to check your Debian version:

```
$ cat /etc/os-release
PRETTY_NAME="Debian GNU/Linux 9 (stretch)"

NAME="Debian GNU/Linux"
VERSION_ID="9"
VERSION="9 (stretch)"
VERSION_CODENAME=stretch
ID=debian
HOME_URL="https://www.debian.org/"
SUPPORT_URL="https://www.debian.org/support"
BUG_REPORT_URL="https://bugs.debian.org/"
```

- **OpenSSL version:** OpenSSL 1.1.01. You can check the OpenSSL version using the `openssl version` command:

```
$ openssl version
OpenSSL 1.1.01 10 Sep 2019
```

- **Configure NGINX Plus certificates:** Complete the following steps to configure certificate for NGINX Plus:

1. Create a directory for SSL certificates:

```
# sudo mkdir -p /etc/ssl/nginx
```

2. Login to NGINX customer portal and download `nginx-repo.key` and `nginx-repo.crt` to `/etc/ssl/nginx`

For more information, see [Installing NGINX Plus](#)

## NGINX Plus for RHEL 7.6

---

Complete the following steps to install NGINX Plus:

1. Download NGINX Plus R16 repository:

```
# sudo wget -P /etc/yum.repos.d https://cs.nginx.com/static/files/nginx-plus-7.4.repo
```

2. Complete the following steps to install Lua modules:

- a. Check whether the Lua version `16+0.10.13-1.el7_4.ngx` is available in the list

```
# sudo yum list nginx-plus-module-lua --showduplicates
```

- b. Install Lua module:

```
# sudo yum install nginx-plus-module-lua-16+0.10.13-1.el7_4.ngx
```

3. Install NGINX Plus:

- a. Check whether NGINX Plus version `nginx-plus-16-1.el7_4.ngx` is available in the list

```
# sudo yum list nginx-plus --showduplicates
```

- b. Install NGINX Plus:

```
# sudo yum install nginx-plus-16-1.el7_4.ngx
```

## Configure NGINX Plus for PingIntelligence

Configure the `nginx.conf` to setup NGINX Plus and PingIntelligence sideband integration. Following is a summary of steps to configure NGINX Plus for PingIntelligence:

1. Create `modules` directory inside NGINX
2. Download PingIntelligence modules
3. Copy PingIntelligence modules in the `modules` directory
4. Edit `nginx.conf` for PingIntelligence

### Create `modules` directory and download PingIntelligence modules

1. Create a `modules` directory in NGINX Plus:

```
# mkdir /etc/nginx/modules
```

2. Download the NGINX Plus - PingIntelligence modules from the [download](#) site
3. Untar the downloaded file.

```
# tar -xvzf pi-api-nginx-plus-policy-4.3.tar.gz
```

The three PingIntelligence modules are:

- `ngx_ase_integration_module.so`
- `ngx_http_ase_integration_request_module.so`
- `ngx_http_ase_integration_response_module.so`

The `pi-pf.conf` file has the OAuth policy details.

- Copy the three PingIntelligence modules files for RHEL to the `modules` directory of NGINX Plus and `pi-pf.conf` file to `/usr/local/nginx/conf/` directory.

```
# cp ngx_ase_integration_module.so /etc/nginx/modules
# cp ngx_http_ase_integration_request_module.so /etc/nginx/modules
# cp ngx_http_ase_integration_response_module.so /etc/nginx/modules
# cp pi-pf.conf /usr/local/nginx/conf/
```

- Change to `root` user:

```
# sudo su
```

- Export client credentials as environment variables:

```
# export PF_ID=<ID>
# export PF_SECRET=<SECRET>
```

Here `PF_ID` and `PF_SECRET` are PingFederate client ID and secret.

Configure `nginx.conf` file

Complete the following steps to configure `nginx.conf` for PingIntelligence. Make sure that the PingIntelligence module and other configurations are added at the correct place in `nginx.conf` as shown in the sample file at the end of the section.

- Load PingIntelligence modules:** Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence modules:

```
worker_processes 4;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/ngx_ase_integration_module.so;
load_module modules/ngx_http_ase_integration_request_module.so;
load_module modules/ngx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/ngx_http_lua_module.so;

events {
    worker_connections 1024;
}
truncated nginx.conf file
```

- Configure ASE primary and secondary node:** Configure ASE primary and secondary node IP address by replacing `IP:PORT` in the `nginx.conf` file snippet show below:

```
http {

    keepalive_timeout 65;
    upstream ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
        #keepalive_timeout 3600s; # NOT allowed < 1.15.3
    }
}
```



```
}
```

*truncated nginx.conf file*

- 3. Configure introspect server IP address:** Configure introspect server IP address by replacing IP:PORT in the `nginx.conf` file snippet show below:

```
upstream introspect_server {
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    keepalive 32;
}
```

*truncated nginx.conf file*

- 4. Configure username and client ID key:** Configure the username and client ID keys in `nginx.conf`. These are the keys for username and client ID that you have configured in PingFederate.

```
set $oauth_username_key Username;
set $oauth_client_id_key ClientID;
```

*truncated nginx.conf file*

- 5. Configure token parameter name:** Configure the token parameter name after `$arg_` and in `ase/` request:

```
# Set the token parameter name below after $arg_ and inside /ase/request.
set $oauth_key_param $arg_access_token;
set $oauth_token_param $arg_access_token;
```

```
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
```

*truncated nginx.conf file*

- 6. Configure introspection URL:** Configure the URL of the introspection server:

```
# Set introspection URL
set $oauth_url https://introspect_server/as/introspect.oauth2;
```

*truncated nginx.conf file*

- 7. Configure ASE Sideband token:** The sideband authentication token was created as part of the [Prerequisites](#) on page 716 in the PingIntelligence section. Following is a snippet showing sideband authentication token:

```
#ASE Token for sideband authentication
set $ase_token <ASE_TOKEN>;
```

- 8. Configure ASE request and response:** Configure ASE request and response API endpoints in `nginx.conf`. Following snippet of `nginx.conf` shows ASE request and response:

```
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}

truncated nginx.conf file
```

- 9. Apply PingIntelligence policy:** You can apply PingIntelligence policy at the global level, that is, for all the APIs in your environment or for an individual API.

**Note:** If the authorization header in the request has multiple tokens, the PingIntelligence policy extracts only the first valid bearer token from the authorization header.

- Apply PingIntelligence policy globally:** To apply PingIntelligence policy globally, add `ase_integration_request` and `ase_integration_response` in the `server` section of `nginx.conf` as shown below:

```
server {
    listen          4443 ssl bind;
    server_name     localhost;
    ssl_certificate /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
```

```

ssl_password_file /usr/local/nginx/ssl/password_file;
ssl_protocols TLSv1.2;
ssl_ciphers HIGH:!aNULL:!MD5;
resolver 8.8.8.8 ipv6=off;
ase_integration_request;
ase_integration_response;

```

```
# Set OAuth Client details
```

*truncated nginx.conf file*

- **Apply PingIntelligence policy for a specific API:** Apply PingIntelligence modules for APIs by configuring `location` in `nginx.conf`. `ase_integration_request` should be the first and a `ase_integration_response` should be the last.

**Note:** Comment-out the `ase_integration_request` and `ase_integration_response` that was configured to apply PingIntelligence policy globally.

```

location / {
    include /usr/local/nginx/conf/pi-pf.conf;
    ase_integration_request;
    proxy_pass http://localhost:8080/;
    ase_integration_response;
}

```

*truncated nginx.conf file*

**10. Verify syntactical correctness of nginx.conf:** To verify the syntactical correctness of `nginx.conf`, run the following command:

```

# /usr/local/nginx/sbin/nginx -t
nginx: the configuration file /usr/local/nginx/conf/nginx.conf syntax is
ok
nginx: configuration file /usr/local/nginx/conf/nginx.conf test is
successful

```

**Final configuration steps:** Complete the following steps to configure PingIntelligence policy for NGINX Plus:

1. Restart NGINX by entering the following command:

```

# /usr/local/nginx/sbin/nginx -s stop
# /usr/local/nginx/sbin/nginx

```

2. Run the following command to verify if `--with-compat` and `--with-http_ssl_module` is in the list of flags under configured arguments.

```

# sudo /usr/local/nginx/sbin/nginx -V
nginx version: nginx/1.15.2 (nginx-plus-r16)
built by gcc 5.4.0 20160609 (Ubuntu 5.4.0-6ubuntu1~16.04.9)
built with OpenSSL 1.0.2g 1 Mar 2016
TLS SNI support enabled
configure arguments: --with-compat --with-http_ssl_module

```

3. Verify that NGINX has restarted by entering the following command:

```
# netstat -tulpn | grep 4443
```

Following is a sample `nginx.conf` file:

```
worker_processes 4;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/nginx_http_lua_module.so;

events {
    worker_connections 1024;
}

http {
    keepalive_timeout 65;
    upstream test.ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
#        keepalive_timeout 3600s; # NOT allowed < 1.15.3
    }

    upstream introspect_server {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
    }

    lua_shared_dict cache_dict 128m;

server {
    listen 4443 ssl bind;
    server_name localhost;
    ssl_certificate /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
    ssl_password_file /usr/local/nginx/ssl/password_file;
    ssl_protocols TLSv1.2;
    ssl_ciphers HIGH:!aNULL:!MD5;
    resolver 8.8.8.8 ipv6=off;
    ase_integration_request;
    ase_integration_response;

    # Set OAuth Client details

    # Set env variable PF_ID &PF_SECRET
    set_by_lua $client_id 'return os.getenv("PF_ID")';
    set_by_lua $client_secret 'return os.getenv("PF_SECRET")';

    # Uncomment next 2 lines to set client credentials here.
    # set $client_id nginx_client;
    # set $client_secret nginx_secret;

    set $oauth_username_key Username;
```

```

set $oauth_client_id_key ClientID;

# Set the token parameter name below after $arg_ and inside /ase/
request.
set $oauth_key_param $arg_access_token;
set $oauth_token_param $arg access_token;
# Set cache lifetime, default is 120s.
set $oauth_cache_timeout 120;

# Set introspection URL
set $oauth_url https://introspect_server/as/introspect.oauth2;

location /introspect {
    internal;
    proxy_method    POST;
    if ($arg_auth_token) {
        set $auth_token $arg_auth_token;
    }
    if ($http_authorization ~* .*?(bearer) (\s+) ([-a-zA-Z0-9._~+/]) (, |
\s|$\)) {
        set $auth_token $3;
    }
    proxy_set_header    Content-Type "application/x-www-form-urlencoded";
    proxy_set_body      "client_id=${client_id}&client_secret=
${client_secret}&token=${auth_token}";
    proxy_pass_request_body off;
    proxy_http_version 1.1;
    proxy_set_header    Connection "";
    proxy_pass           $oauth_url;
}

location /shop {
    include /usr/local/nginx/conf/pi-pf.conf;
    proxy_pass http://18.209.173.37:4100/shop;
}

#DO NOT EDIT BELOW VARIABLE
set $correlationid $pid-$request_id-$server_addr-$remote_addr-
$remote_port-$request_length-$connection;
#Certificate location of ASE
set $certificate /usr/local/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <ASE_TOKEN>;
#Host header which should be send to ASE
set $ase_host test.ase.pi;
#SNI value to use for ASE
set $ase_ssl_host test.ase.pi;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
}

```

```

    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
}
}

```

## Configuring NGINX Plus with PingAccess agent for PingIntelligence

You can install PingIntelligence sideband policy on NGINX Plus R22 or R23 systems with PingAccess agent.

Before you begin

Make sure the following prerequisites are complete before you configure NGINX Plus with PingIntelligence policy:

- API Security Enforcer (ASE) is installed, and the pre-conditions listed under [prerequisites for PingIntelligence](#) are met.
- PingAccess and PingFederate are installed.
- PingAccess agent is installed and configured on NGINX. For more information, see [PingAccess Agent for NGINX](#).
- PingAccess is configured to use PingFederate as a token provider and token introspection is enabled on PingAccess. For more information, see [Configure PingFederate as the token provider for PingAccess](#).

About this task

Configure the `nginx.conf` to setup NGINX Plus and PingIntelligence sideband policy. Complete the following steps to integrate the sideband policy:

Steps

1. Download the NGINX Plus - PingIntelligence modules from the [download](#) site
2. Untar the downloaded file.

```
# tar -xvzf pi-api-nginx-plus-policy-5.0.tar
```

3. Copy the PingIntelligence modules files for RHEL to the modules directory of NGINX Plus and `pi-pf.conf` file to `/nginx/conf/` directory.
4. Change to root user.

```
# sudo su
```

## 5. Configure the `nginx.conf` file. Complete the following steps to configure `nginx.conf` for PingIntelligence:

- Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence module.

```

user  nginx;
worker_processes  auto;
error_log  /var/log/nginx/error.log debug;
pid       /var/run/nginx.pid;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;
load_module modules/nginx_http_paa_module.so;

events {
    worker_connections  1024;
}

```

**Note:** Make sure the modules are loaded in the order highlighted above.

- Configure ASE primary and secondary node IP address by replacing IP:PORT in the `nginx.conf` file as shown in the following snippet.

```

http {
    upstream test.ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
        # keepalive_timeout 3600s; # NOT allowed < 1.15.3
    }
}

```

- Configure the following ASE parameters in `nginx.conf` file:

Parameter	Description
<code>certificate</code>	Certificate location of ASE
<code>ase_token</code>	ASE Token for sideband authentication
<code>ase_host</code>	Host header that should be send to ASE
<code>ase_ssl_host</code>	SNI value to use for ASE

```

#DO NOT EDIT BELOW VARIABLE
set $correlationid $pid-$request_id-$server_addr-$remote_addr-$remote_port-$request_length-$connection;
#Certificate location of ASE
set $certificate /etc/ssl/nginx/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token 76748f33353940efab31e9fbe15d930a;
#Host header which should be send to ASE
set $ase_host test.ase.pi;
#SNI value to use for ASE
set $ase_ssl_host test.ase.pi;

```

## 6. Add PingIntelligence sideband policy

- To apply PingIntelligence policy globally, add `ase_integration_request` and `ase_integration_response` in the server section of `nginx.conf` as shown in the following snippet:

```
server {
    listen          44444 ssl bind;
    server_name     localhost;
    ssl_certificate /etc/nginx/ssl/cert.pem;
    ssl_certificate_key /etc/nginx/ssl/key.pem;
    ssl_protocols  TLSv1.2;
    ssl_ciphers    HIGH:!aNULL:!MD5;
    add_header Allow "GET, POST, HEAD" always;
    ase_integration_request;

    ase_integration_response;
}
```

*truncated nginx.conf file*

- To apply PingIntelligence sideband policy for a specific API, configure location in `nginx.conf` as shown in the following snippet:

```
location / {
    include /usr/local/nginx/conf/pi-pf.conf;
    ase_integration_request;
    proxy_pass http://localhost:8080/;
    ase_integration_response;
}
```

*truncated nginx.conf file*

Note: When configuring the policy for individual APIs, comment-out `ase_integration_request` and `ase_integration_response` that are added to apply PingIntelligence policy globally.

## 7. Run the following command and verify syntactical correctness of `nginx.conf` file.

```
# /usr/local/nginx/sbin/nginx -t
nginx: the configuration file /usr/local/nginx/conf/nginx.conf syntax is
ok
nginx: configuration file /usr/local/nginx/conf/nginx.conf test is
successful
```

## 8. Restart NGINX by entering the following command.

```
# /usr/local/nginx/sbin/nginx -s stop
# /usr/local/nginx/sbin/nginx
```

### Next steps

- Verify that NGINX has restarted by entering the following command.

```
# netstat -tulpn | grep <NGINX port number>
For example : # netstat -tulpn | grep 4443
```

- Configure API JSON file as explained in [Configuring API JSON to extract user information](#) on page 731.

**Sample `nginx.conf` file** - Following is a sample `nginx.conf` file.

```
user nginx;
worker_processes auto;
```



```

error_log /var/log/nginx/error.log debug;
pid /var/run/nginx.pid;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;
load_module modules/nginx_http_paa_module.so;

events {
    worker_connections 1024;
}

http {
    include /etc/nginx/paa/http.conf;
    log_format main '$remote_addr - $remote_user [$time_local] "$request" '
        '$status $body_bytes_sent "$http_referer" '
        '"$http_user_agent" "$http_x_forwarded_for"';
    access_log /var/log/nginx/access.log main;

    sendfile on;
    #tcp_nopush on;

    keepalive_timeout 65;
    upstream test.ase.pi {
        server 127.1.1.1:8443 max_fails=1 max_conns=100 fail_timeout=10;
        server 127.1.1.1:8443 max_fails=1 max_conns=100 fail_timeout=10
    }
    backup;
    # keepalive_timeout 3600s; # NOT allowed < 1.15.3
}

server {
    listen 44444 ssl bind;
    server_name localhost;
    ssl_certificate /etc/nginx/ssl/cert.pem;
    ssl_certificate_key /etc/nginx/ssl/key.pem;
    ssl_protocols TLSv1.2;
    ssl_ciphers HIGH:!aNULL:!MD5;
    add_header Allow "GET, POST, HEAD" always;
    location /todo/api-only {
        ase_integration_request;
        proxy_pass https://172.16.40.38:8443/todo/api-only;
        proxy_ssl_verify off;
        ase_integration_response;
    }
    location /shopapi {
        proxy_pass https://172.16.40.70:4100/shopapi;
        proxy_ssl_verify off;
    }
    #DO NOT EDIT BELOW VARIABLE
    set $correlationid $pid-$request_id-$server_addr-$remote_addr-$remote_port-$request_length-$connection;
    #Certificate location of ASE
    set $certificate /etc/ssl/nginx/test.ase.pi;
    #ASE Token for sideband authentication
    set $ase_token 76748f33353940efab31e9f9f9e15d930a;
    #Host header which should be send to ASE
    set $ase_host test.ase.pi;
    #SNI value to use for ASE
    set $ase_ssl_host test.ase.pi;
}

```

```

#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}

location /introspect {
    internal;
    proxy_method POST;
    if ($arg_auth_token) {
        set $auth_token $arg_auth_token;
    }
    if ($http_authorization ~* .*?(bearer) (\s+) ([-a-zA-Z0-9._~+/]+) (, |
\s|$)) {
        set $auth_token $3;
    }
    #proxy_set_header Content-Type "application/x-www-form-urlencoded";
    proxy_pass_request_body off;
    proxy_http_version 1.1;
    proxy_set_header Connection "";
    proxy_pass $oauth_url;
    proxy_read_timeout 60;
    proxy_set_header authorization "";
}
}

include /etc/nginx/conf.d/*.conf;
}

```

## Configuring API JSON to extract user information

This topic discusses the process to extract user attributes from signed JWT (JSON Web Token).

To extract the user information from the JWT identity mapping, capture the value assigned to **HEADER NAME**. It's the name of the header to use when sending the signed JWT to the ASE

Assign the value of Header Name to the location key in the jwt object of the API JSON file. For more information on configuring the API JSON file, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.

```
"jwt": {
    "location": "h:X-Identity",
    "username": "username",
    "clientid": "client_id"
}
```

### Related links

- [Creating a JWT identity mapping](#)
- [Defining an API using API JSON configuration file in sideband mode](#) on page 170

## NGINX Plus for Ubuntu 16.0.4

Complete the following steps to install NGINX Plus:

1. Download NGINX Plus R16 repository:

```
# printf "deb https://plus-pkgs.nginx.com/ubuntu `lsb_release -cs` nginx-
plus\n" | sudo tee /etc/apt/sources.list.d/nginx-plus.list
# sudo wget -q -O /etc/apt/apt.conf.d/90nginx https://cs.nginx.com/static/
files/90nginx
# sudo apt-get update
```

2. Complete the following steps to install NGINX Plus with Lua modules:

a. Check whether 16-1~xenial is available in the list

```
# sudo apt-cache show nginx-plus | grep "Version"
```

b. Install NGINX Plus:

```
# sudo apt-get install nginx-plus=16-1~xenial
# sudo apt-get install nginx-plus-module-ndk=16+0.3.0-1~xenial
# sudo apt-get install nginx-plus-module-lua=16+0.10.13-2~xenial
```

## Configure NGINX Plus for PingIntelligence

Configure the `nginx.conf` to setup NGINX Plus and PingIntelligence sideband integration. Following is a summary of steps to configure NGINX Plus for PingIntelligence:

1. Create `modules` directory inside NGINX working directory
2. Download PingIntelligence modules
3. Copy PingIntelligence modules in the `modules` directory
4. Edit `nginx.conf` for PingIntelligence

### Create `modules` directory and download PingIntelligence modules

1. Create a `modules` directory in NGINX Plus:

```
# mkdir /etc/nginx/modules
```

2. Download the NGINX Plus - PingIntelligence modules from the [download](#) site

3. Untar the downloaded file.

```
# tar -xvzf pi-api-nginx-plus-policy-4.3.tar.gz
```

The three PingIntelligence modules are:

- `ngx_ase_integration_module.so`
- `ngx_http_ase_integration_request_module.so`
- `ngx_http_ase_integration_response_module.so`

The `pi-pf.conf` file has the OAuth policy details.

4. Copy the three PingIntelligence modules files for Ubuntu to the `modules` directory of NGINX Plus and `pi-pf.conf` file to `/usr/local/nginx/conf/` directory.

```
# cp ngx_ase_integration_module.so /etc/nginx/modules
# cp ngx_http_ase_integration_request_module.so /etc/nginx/modules
# cp ngx_http_ase_integration_response_module.so /etc/nginx/modules
# cp pi-pf.conf /usr/local/nginx/conf/
```

5. Change to `root` user:

```
# sudo su
```

6. Export client credentials as environment variables:

```
# export PF_ID=<ID>
# export PF_SECRET=<SECRET>
```

Here `PF_ID` and `PF_SECRET` are PingFederate client ID and secret.

Configure `nginx.conf` file

Complete the following steps to configure `nginx.conf` for PingIntelligence. Make sure that the PingIntelligence module and other configurations are added at the correct place in `nginx.conf` as shown in the sample file at the end of the section.

- 1. Load PingIntelligence modules:** Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence modules:

```
worker_processes 4;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/nginx_http_lua_module.so;

events {
    worker_connections 1024;
}
truncated nginx.conf file
```

- 2. Configure ASE primary and secondary node:** Configure ASE primary and secondary node IP address by replacing `IP:PORT` in the `nginx.conf` file snippet show below:

```
http {
    keepalive_timeout 65;
    upstream ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
        #keepalive_timeout 3600s; # NOT allowed < 1.15.3
    }
}
truncated nginx.conf file
```

- 3. Configure introspect server IP address:** Configure introspect server IP address by replacing `IP:PORT` in the `nginx.conf` file snippet show below:

```
upstream introspect_server {
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    keepalive 32;
}
truncated nginx.conf file
```

- 4. Configure username and client ID key:** Configure the username and client ID keys in `nginx.conf`. These are the keys for username and client ID that you have configured in PingFederate.

```
set $oauth_username_key Username;
```

```
set $oauth_client_id_key ClientID;
```

*truncated nginx.conf file*

- 5. Configure token parameter name:** Configure the token parameter name after \$arg\_ and in ase/request:

```
# Set the token parameter name below after $arg_ and inside /ase/request.
set $oauth_key_param $arg_access_token;
set $oauth_token_param $arg_access_token;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}

truncated nginx.conf file
```

- 6. Configure introspection URL:** Configure the URL of the introspection server:

```
# Set introspection URL
set $oauth_url https://introspect_server/as/introspect.oauth2;
```

*truncated nginx.conf file*

- 7. Configure ASE Sideband token:** The sideband authentication token was created as part of the [Prerequisites](#) on page 716 in the PingIntelligence section. Following is a snippet the showing certificate location and sideband authentication token:

- 8. Configure ASE request and response:** Configure ASE request and response API endpoints in nginx.conf. Following snippet of nginx.conf shows ASE request and response:

```
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
```

```
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
```

*truncated nginx.conf file*

- 9. Apply PingIntelligence policy:** You can apply PingIntelligence policy at the global level, that is, for all the APIs in your environment or for an individual API.

**Note:** If the authorization header in the request has multiple tokens, the PingIntelligence policy extracts only the first valid bearer token from the authorization header.

- **Apply PingIntelligence policy globally:** To apply PingIntelligence policy globally, add `ase_integration_request` and `ase_integration_response` in the serversection of `nginx.conf` as shown below:

```
server {
    listen          4443 ssl bind;
    server_name     localhost;
    ssl_certificate /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
    ssl_password_file /usr/local/nginx/ssl/password_file;
    ssl_protocols  TLSv1.2;
    ssl_ciphers    HIGH:!aNULL:!MD5;
    resolver 8.8.8.8 ipv6=off;
    ase_integration_request;
    ase_integration_response;

    # Set OAuth Client details
```

*truncated nginx.conf file*

- **Apply PingIntelligence policy for a specific API:** Apply PingIntelligence modules for APIs by configuring location in `nginx.conf`. `ase_integration_request` should be the first and a `ase_integration_response` should be the last.

**Note:** Comment-out the `ase_integration_request` and `ase_integration_response` that was configured to apply PingIntelligence policy globally.

```
location / {
    include /usr/local/nginx/conf/pi-pf.conf;
    ase_integration_request;
    proxy_pass http://localhost:8080/;
    ase_integration_response;
}
```

```
truncated nginx.conf file
```

**10. Verify syntactical correctness of nginx.conf:** To verify the syntactical correctness of nginx.conf, run the following command:

```
# /usr/local/nginx/sbin/nginx -t
nginx: the configuration file /usr/local/nginx/conf/nginx.conf syntax is
ok
nginx: configuration file /usr/local/nginx/conf/nginx.conf test is
successful
```

**Final configuration steps:** Complete the following steps to configure PingIntelligence policy for NGINX Plus:

1. Restart NGINX by entering the following command:

```
# /usr/local/nginx/sbin/nginx -s stop
# /usr/local/nginx/sbin/nginx
```

2. Run the following command to verify if `--with-compat` and `--with-http_ssl_module` is in the list of flags under configured arguments.

```
# sudo /usr/local/nginx/sbin/nginx -V
nginx version: nginx/1.15.2 (nginx-plus-r16)
built by gcc 5.4.0 20160609 (Ubuntu 5.4.0-6ubuntu1~16.04.9)
built with OpenSSL 1.0.2g 1 Mar 2016
TLS SNI support enabled
configure arguments: --with-compat --with-http_ssl_module
```

3. Verify that NGINX has restarted by entering the following command:

```
# netstat -tulpn | grep 4443
```

Following is a sample nginx.conf file:

```
worker_processes 4;

error_log /usr/local/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /usr/local/nginx;

pid /usr/local/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/ngx_ase_integration_module.so;
load_module modules/ngx_http_ase_integration_request_module.so;
load_module modules/ngx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/ngx_http_lua_module.so;

events {
    worker_connections 1024;
}

http {

    keepalive_timeout 65;
    upstream test.ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    }
    keepalive 32;
```



```

#     keepalive_timeout 3600s; # NOT allowed < 1.15.3
}

upstream introspect_server {
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    keepalive 32;
}

lua_shared_dict cache_dict 128m;

server {
    listen          4443 ssl bind;
    server_name     localhost;
    ssl_certificate /usr/local/nginx/ssl/cert.pem;
    ssl_certificate_key /usr/local/nginx/ssl/key.pem;
    ssl_password_file /usr/local/nginx/ssl/password_file;
    ssl_protocols   TLSv1.2;
    ssl_ciphers     HIGH:!aNULL:!MD5;
    resolver 8.8.8.8 ipv6=off;
    ase_integration_request;
    ase_integration_response;

    # Set OAuth Client details

    # Set env variable PF_ID & PF_SECRET
    set_by_lua $client_id 'return os.getenv("PF_ID")';
    set_by_lua $client_secret 'return os.getenv("PF_SECRET")';

    # Uncomment next 2 lines to set client credentials here.
    # set $client_id nginx_client;
    # set $client_secret nginx_secret;

    set $oauth_username_key Username;
    set $oauth_client_id_key ClientID;

    # Set the token parameter name below after $arg_ and inside /ase/
request.
    set $oauth_key_param $arg_access_token;
    set $oauth_token_param $arg_access_token;

    # Set cache lifetime, default is 120s.
    set $oauth_cache_timeout 120;

    # Set introspection URL
    set $oauth_url https://introspect_server/as/introspect.oauth2;

    location /introspect {
        internal;
        proxy_method POST;
        if ($arg_auth_token) {
            set $auth_token $arg_auth_token;
        }
        if ($http_authorization ~* .*?(bearer) (\s+) ([-a-zA-Z0-9._~+/]) (, |
\s|$)) {
            set $auth_token $3;
        }
        proxy_set_header Content-Type "application/x-www-form-urlencoded";
        proxy_set_body "client_id=${client_id}&client_secret=
${client_secret}&token=${auth_token}";
        proxy_pass_request_body off;
        proxy_http_version 1.1;
        proxy_set_header Connection "";

```

```

    proxy_pass      $oauth_url;
}

location /shop {
    include /usr/local/nginx/conf/pi-pf.conf;
    proxy_pass http://18.209.173.37:4100/shop;
}
#DO NOT EDIT BELOW VARIABLE
set $correlationid $pid-$request_id-$server_addr-$remote_addr-
$remote_port-$request_length-$connection;
#Certificate location of ASE
set $certificate /usr/local/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <ASE_TOKEN>;
#Host header which should be send to ASE
set $ase_host test.ase.pi;
#SNI value to use for ASE
set $ase_ssl_host test.ase.pi;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
}
}

```

## NGINX Plus for Debian 9

---

Complete the following steps to install NGINX Plus:

## 1. Download NGINX Plus R19 repository

```
# printf "deb https://plus-pkgs.nginx.com/debian `lsb_release -cs` nginx-  
plus\n" | sudo tee /etc/apt/sources.list.d/nginx-plus.list  
# sudo wget -q -O /etc/apt/apt.conf.d/90nginx https://cs.nginx.com/static/  
files/90nginx  
# sudo apt-get update
```

## 2. Complete the following steps to install NGINX Plus:

### a. Check whether 19-1~stretch is available in the list

```
# sudo apt-cache show nginx-plus | grep "Version"
```

### b. Install NGINX Plus and related modules:

```
# sudo apt-get install nginx-plus=19-1~stretch  
# sudo apt-get install nginx-plus-module-ndk=19+0.3.0-1~stretch  
# sudo apt-get install nginx-plus-module-lua=19+0.10.15-1~stretch
```

## Configure NGINX Plus for PingIntelligence

Complete the following steps to configure the `nginx.conf` to setup NGINX Plus and PingIntelligence sideband integration:

### Create `modules` directory and download PingIntelligence modules

#### 1. Create a `modules` directory in NGINX Plus, if it is not existing already.


```
# mkdir /etc/nginx/modules
```

#### 2. Download the NGINX Plus - PingIntelligence modules from the [download](#) site

### 3. Untar the downloaded file.

```
# tar -xvzf pi-api-nginx-plus-policy-4.3.tar.gz
```

The following is the directory structure.



### 4. Copy the three PingIntelligence modules files for Debian to the `/etc/nginx/modules/` directory of NGINX Plus and `pi-pf.conf` file to `/etc/nginx/` directory. The `pi-pf.conf` file has the OAuth policy details.

```
# cp ngx_ase_integration_module.so /etc/nginx/modules/
# cp ngx_http_ase_integration_request_module.so /etc/nginx/modules/
# cp ngx_http_ase_integration_response_module.so /etc/nginx/modules/
# cp pi-pf.conf /etc/nginx/
```

### 5. Change to root user:

```
# sudo su
```

### 6. Export client credentials as environment variables:

```
# export PF_ID=<ID>
# export PF_SECRET=<SECRET>
```

Here `PF_ID` and `PF_SECRET` are PingFederate client ID and secret.

Configure `nginx.conf` file

Complete the following steps to configure `nginx.conf` for PingIntelligence. Make sure that the PingIntelligence module and other configurations are added at the correct place in `nginx.conf` as shown in the sample file at the end of the section.

- 1. Load PingIntelligence modules:** Edit the `nginx.conf` file to load the PingIntelligence modules. Following is a snippet of `nginx.conf` file showing the loaded PingIntelligence modules:

```
worker_processes 4;

error_log /etc/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /etc/nginx;

pid /etc/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/nginx_ase_integration_module.so;
load_module modules/nginx_http_ase_integration_request_module.so;
load_module modules/nginx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/nginx_http_lua_module.so;

events {
    worker_connections 1024;
}
truncated nginx.conf file
```

- 2. Configure ASE primary and secondary node:** Configure ASE primary and secondary node IP address by replacing `IP:PORT` in the `nginx.conf` file snippet show below:

```
http {
    keepalive_timeout 65;
    upstream test.ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
        #keepalive_timeout 3600s; # NOT allowed < 1.15.3
    }
}
truncated nginx.conf file
```

- 3. Configure introspect server IP address:** Configure introspect server IP address by replacing `IP:PORT` in the `nginx.conf` file snippet show below:

```
upstream introspect_server {
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    keepalive 32;
}
truncated nginx.conf file
```

- 4. Configure username and client ID key:** Configure the username and client ID keys in `nginx.conf`. These are the keys for username and client ID that you have configured in PingFederate.

```
set $oauth_username_key Username;
```

```
set $oauth_client_id_key ClientID;
```

*truncated nginx.conf file*

- 5. Configure token parameter name:** Configure the token parameter name after \$arg\_ and in ase/request:

```
# Set the token parameter name below after $arg_ and inside /ase/request.
set $oauth_key_param $arg_access_token;
set $oauth_token_param $arg_access_token;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}

truncated nginx.conf file
```

- 6. Configure introspection URL:** Configure the URL of the introspection server:

```
# Set introspection URL
set $oauth_url https://introspect_server/as/introspect.oauth2;
```

*truncated nginx.conf file*

- 7. Configure ASE Sideband token:** The sideband authentication token was created as part of the [Prerequisites](#) on page 716 in the PingIntelligence section. Following snippet in step-8 shows the certificate location and sideband authentication token:

- 8. Configure ASE request and response:** Configure ASE request and response API endpoints in nginx.conf. Following snippet of nginx.conf shows ASE request and response:

```
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
```

```
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
```

*truncated nginx.conf file*

- 9. Apply PingIntelligence policy:** You can apply PingIntelligence policy at the global level, that is, for all the APIs in your environment or for an individual API.

**Note:** If the authorization header in the request has multiple tokens, the PingIntelligence policy extracts only the first valid bearer token from the authorization header.

- **Apply PingIntelligence policy globally:** To apply PingIntelligence policy globally, add `ase_integration_request` and `ase_integration_response` in the `server` section of `nginx.conf` file as shown below:

```
server {
    listen          4443 ssl bind;
    server_name     localhost;
    ssl_certificate /etc/nginx/ssl/cert.pem;
    ssl_certificate_key /etc/nginx/ssl/key.pem;
    ssl_password_file /etc/nginx/ssl/password_file;
    ssl_protocols  TLSv1.2;
    ssl_ciphers    HIGH:!aNULL:!MD5;
    resolver 8.8.8.8 ipv6=off;
    ase_integration_request;
    ase_integration_response;
}
```

# Set OAuth Client details

*truncated nginx.conf file*

- **Apply PingIntelligence policy for a specific API:** Apply PingIntelligence modules for specific APIs by configuring `location` in `nginx.conf`. `ase_integration_request` should be the first and `ase_integration_response` should be the last, as shown in the following snippet.

**Note:** When applying the policy to a specific API, comment-out the `ase_integration_request` and `ase_integration_response`, that are configured in the `server` section of the `nginx.conf` file to apply PingIntelligence policy globally.

```
location / {
    include /etc/nginx/pi-pf.conf;
    ase_integration_request;
    proxy_pass http://localhost:8080/;
    ase_integration_response;
}
```

```
truncated nginx.conf file
```

**10. Verify syntactical correctness of nginx.conf:** To verify the syntactical correctness of nginx.conf, run the following command:

```
# /usr/sbin/nginx -t
nginx: the configuration file /etc/nginx/nginx.conf syntax is ok
nginx: configuration file /etc/nginx/nginx.conf test is successful
```

**Final configuration steps:** Complete the following steps to configure PingIntelligence policy for NGINX Plus:

1. Restart NGINX by entering the following command:

```
# /usr/sbin/nginx -s stop
# /usr/sbin/nginx
```

2. Run the following command to verify if `--with-compat` and `--with-http_ssl_module` is in the list of flags under configured arguments.

```
# sudo /usr/sbin/nginx -V
nginx version: nginx/1.17.3 (nginx-plus-r19)
built by gcc 6.3.0 20170516 (Debian 6.3.0-18+deb9u1)
built with OpenSSL 1.1.0j 20 Nov 2018 (running with OpenSSL 1.1.0l 10 Sep 2019)
TLS SNI support enabled
```

3. Verify that NGINX has restarted by entering the following command:

```
# netstat -tulpn | grep 4443
```

Following is a sample nginx.conf file:

```
worker_processes 4;

error_log /etc/nginx/logs/error.log debug;
worker_rlimit_core 500M;
working_directory /etc/nginx;

pid /etc/nginx/pid/nginx.pid;
env PF_ID;
env PF_SECRET;

load_module modules/ngx_ase_integration_module.so;
load_module modules/ngx_http_ase_integration_request_module.so;
load_module modules/ngx_http_ase_integration_response_module.so;
load_module modules/ndk_http_module.so;
load_module modules/ngx_http_lua_module.so;

events {
    worker_connections 1024;
}

http {
    keepalive_timeout 65;
    upstream test.ase.pi {
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
        server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
        keepalive 32;
    }
    # keepalive_timeout 3600s; # NOT allowed < 1.15.3
}
```



```

upstream introspect_server {
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10;
    server IP:PORT max_fails=1 max_conns=100 fail_timeout=10 backup;
    keepalive 32;
}

lua_shared_dict cache_dict 128m;

server {
    listen          4443 ssl bind;
    server_name     localhost;
    ssl_certificate /etc/nginx/ssl/cert.pem;
    ssl_certificate_key /etc/nginx/ssl/key.pem;
    ssl_password_file /etc/nginx/ssl/password_file;
    ssl_protocols  TLSv1.2;
    ssl_ciphers    HIGH:!aNULL:!MD5;
    resolver 8.8.8.8 ipv6=off;
    ase_integration_request;
    ase_integration_response;

    # Set OAuth Client details

    # Set env variable PF_ID &PF_SECRET
    set_by_lua $client_id 'return os.getenv("PF_ID")';
    set_by_lua $client_secret 'return os.getenv("PF_SECRET")';

    # Uncomment next 2 lines to set client credentials here.
    # set $client_id nginx_client;
    # set $client_secret nginx_secret;

    set $oauth_username_key Username;
    set $oauth_client_id_key ClientID;

    # Set the token parameter name below after $arg_ and inside /ase/
    request.
    set $oauth_key_param $arg_access_token;
    set $oauth_token_param $arg_**access_token;

    # Set cache lifetime, default is 120s.
    set $oauth_cache_timeout 120;

    # Set introspection URL
    set $oauth_url https://introspect_server/as/introspect.oauth2;

    location /introspect {
        internal;
        proxy_method POST;
        if ($arg_auth_token) {
            set $auth_token $arg_auth_token;
        }
        if ($http_authorization ~* .*?(bearer) (\s+) ([-a-zA-Z0-9._~/+]) (, |
\s|$)) {
            set $auth_token $3;
        }
        proxy_set_header Content-Type "application/x-www-form-urlencoded";
        proxy_set_body "client_id=${client_id}&client_secret=
${client_secret}&token=${auth_token}";
        proxy_pass_request_body off;
        proxy_http_version 1.1;
        proxy_set_header Connection "";
        proxy_pass $oauth_url;
    }
}

```

```

location /shop {
    include /etc/nginx/pi-pf.conf;
    proxy_pass http://18.209.173.37:4100/shop;
}
#DO NOT EDIT BELOW VARIABLE
set $correlationid $pid-$request_id-$server_addr-$remote_addr-
$remote_port-$request_length-$connection;
#Certificate location of ASE
set $certificate /etc/nginx/ssl/test.ase.pi;
#ASE Token for sideband authentication
set $ase_token <ASE_TOKEN>;
#Host header which should be send to ASE
set $ase_host test.ase.pi;
#SNI value to use for ASE
set $ase_ssl_host test.ase.pi;
#ASE Request Proxy Configuration
location = /ase/request {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    # set token key here.
    ase_integration_token_key access_token;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
#ASE Response Proxy Configuration
location = /ase/response {
    internal;
    ase_integration https://test.ase.pi;
    ase_integration_method "POST";
    ase_integration_http_version 1.1;
    ase_integration_ase_token $ase_token;
    ase_integration_correlation_id $correlationid;
    ase_integration_host $ase_host;
    ase_integration_ssl_trusted_certificate $certificate;
    ase_integration_ssl_verify off;
    ase_integration_ssl_verify_depth 1;
    ase_integration_ssl_server_name off;
    ase_integration_ssl_name $ase_ssl_host;
    ase_integration_next_upstream error timeout non_idempotent;
}
}
}

```


# PingAccess API gateway integration

## PingAccess sideband integration

This guide describes the deployment of PingIntelligence for APIs in a sideband configuration with PingAccess. A PingIntelligence policy is installed in PingAccess and passes API metadata to PingIntelligence for detailed API activity reporting and attack detection with optional client blocking.

The PingIntelligence sideband policy supports interception of OAuth Tokens that come as part of a query string. It also supports optional enablement of Asynchronous mode to API Security Enforcer (ASE).

The following diagram depicts the architecture of PingIntelligence for APIs components along with PingAccess and PingFederate.



Here is the traffic flow through the PingAccess and PingIntelligence for APIs components.

1. Client requests and receives an access token from PingFederate.
2. Client sends a request with the access token received from PingFederate.
3. PingAccess verifies the authenticity of the access token with PingFederate.
4. If the token is invalid, PingAccess returns a 401-unauthorized message to the client.
5. If the token is valid, the PingIntelligence policy running in PingAccess collects API metadata and token attributes.
6. PingAccess makes an API call to send the request information to ASE. ASE checks the request against a registered set of APIs and checks the client identifiers such as IP addresses, cookies against the AI generated Blacklist. If all checks pass, ASE returns a 200-OK response to the PingAccess. If not, a 403- forbidden response code is sent to PingAccess. The request information is also logged by ASE and sent to the API Behavioral Security (ABS) AI Engine for processing.
7. If PingAccess receives a 200-OK response from ASE, it forwards the request to the backend server. Otherwise, the gateway optionally blocks the client. In synchronous mode, the gateway waits for a

response from ASE before forwarding the request to backend server. However, if asynchronous mode is enabled, the gateway forwards the request to the backend server without waiting for the response from ASE. The ASE passively logs the request and forwards it to ABS for attack analysis. It performs attack detection without blocking of attacks.

8. The response from the backend server is received by PingAccess. PingAccess sends the response received from the backend server to the client.
9. PingAccess makes a second API call to pass the response information to ASE which sends the information to the ABS AI engine for processing. ASE receives the response information and sends a 200-OK to PingAccess.
10. PingAccess sends the response to the client.

## Prerequisites

Complete the following before configuring PingAccess:

- **Confirm the PingAccess version** - The PingIntelligence policy supports PingAccess versions 5.x and 6.x. If you are using any other version, contact Ping Identity support.
- **Install PingIntelligence software**

PingIntelligence software should be installed and configured. For more information on PingIntelligence deployment, see [PingIntelligence setup](#) on page 46 and [PingIntelligence manual deployment](#) on page 84 .

- **Verify that ASE is in sideband mode**

Check ASE is in sideband mode by running the following command in ASE command line.

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : disabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.61 MB, free 102.39
  MB
google pubsub         : disabled
log level              : debug
timezone              : local (UTC)
```

If ASE is not in `sideband` mode, then stop ASE and change the mode by editing the `/opt/pingidentity/ase/config/ase.conf` file. Set mode as `sideband` and start ASE.

- **Enable sideband authentication**

For secure communication between PingAccess and ASE, enable sideband authentication by entering the following ASE command.

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for PingAccess to authenticate with ASE. To generate the token, enter the following ASE command.

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```

Save the generated authentication token for further use.

## Configure PingFederate to extract token attributes

You need to configure PingFederate for PingIntelligence policy to be able to extract the username from the incoming token. Complete the following steps to configure PingFederate to extract token attributes:

1. While configuring **Access Token Management** in PingFederate, add all the attributes that should be exposed for the token. PingFederate provides these attribute values to PingAccess for OAuth tokens.
2. Click **Access Token Attribute Contract** under **Access token management Instance** and add the required attributes. Make sure to at least add

The screenshot displays the PingFederate configuration interface. On the left, a sidebar menu includes 'MAIN' (with 'Identity Provider' and 'OAuth Server' options) and 'SETTINGS' (with 'Security' and 'System' options). The 'OAuth Server' option is selected. The main content area is titled 'Access Token Management | Create Access Token Management Instance'. It features a tabbed interface with four tabs: 'Type', 'Instance Configuration', 'Session Validation', and 'Access Token Attribute Contract'. The 'Access Token Attribute Contract' tab is active, showing a list of attributes: 'email', 'group', 'org', and 'Username'. The 'Username' attribute is highlighted, and its 'Subject Attribute Name' is set to 'USER\_KEY'. Below the attribute list, there is a text input field for 'Username' and a dropdown menu for 'Subject Attribute Name' with 'USER\_KEY' selected.

username.

3. After Adding the required attributes, configure the attribute sources:

- a. Click **Access Token Mapping**
- b. Select the relevant **Context**
- c. Click **Contract Fulfilment**

The screenshot shows the PingFederate Admin Console interface. The left sidebar contains navigation options: MAIN (Identity Provider, OAuth Server) and SETTINGS (Security, System). The main content area is titled 'Access Token Attribute Mapping | Access Token Mapping' and features four tabs: 'Attribute Sources & User Lookup', 'Contract Fulfillment', 'Issuance Criteria', and 'Summary'. The 'Contract Fulfillment' tab is selected. Below the tabs, a message reads: 'Select a Source and Value to map into each item in the Contract list.' A table with two columns, 'Contract' and 'Source', is displayed. The rows are: 'Username' with 'Persistent Grant', 'email' with 'Text', 'group' with 'Text', and 'org' with 'Context'.

## Deploying the PingIntelligence policy

About this task

To integrate PingAccess with PingIntelligence components, complete the following steps in PingAccess:


**Note:** We recommend that you increase the default heap size in PingAccess before deploying the PingIntelligence policy for PingAccess 6.x. Refer to the instructions explained in [Modifying the Java heap size](#) for changing the default heap size. For more information, contact PingIdentity support.

## Steps

1. Download the PingIntelligence policy from the [Ping Identity download site](#) and unzip it. The zip file contains three policy files based on the JDK version. Use the policy based on your deployment environment.

```
pingidentity /
├── pingaccess-policy
│   ├── openjdk11
│   │   └── pingIntelligence.jar
│   ├── oraclejdk11
│   │   └── pingIntelligence.jar
│   ├── oraclejdk8
│   │   └── pingIntelligence.jar
└── version.txt
```


2. Copy the `PingIntelligence.jar` file into the `lib` directory in `PA_home`.
3. Restart PingAccess.
4. Log in to PingAccess.



**Note:** To support fail-over, a secondary ASE is provisioned. Complete the following steps for both Primary and Secondary ASEs.

5. Add the Primary ASE as a Third-Party Service:

- a. In the left pane click **Sites**. Navigate to **THIRD-PARTY SERVICES** and click **+ Add Third-Party Service** to add the Primary




ASE.

- b. In the **New Third-Party Service** page, enter a name that identifies the Primary ASE in **NAME** and enter the endpoint used to reach the Primary ASE in **TARGET**.

**Note:** Select options under **SECURE** to connect PingAccess to PingIntelligence ASE using HTTPS.

- c. Click **Save**.



6. Repeat step-5 to add the Secondary ASE as a Third-Party Service. Enter the Name and endpoint specific to the Secondary ASE.

7. Add PingIntelligence sideband rule :

- a. In the left pane click **Rules**. In the new Rule page, in the **NAME** field, enter the name of the rule for PingIntelligence.
- b. In the **TYPE** drop-down list, select **PingIntelligence**. This appears in the drop-down list after adding PingIntelligence.jar in PA\_HOME in step 3.
- c. Select the ASE Endpoint for Primary ASE in **PINGINTELLIGENCE ASE ENDPOINT** drop-down list.
- d. Select the ASE Endpoint for Secondary ASE in **PINGINTELLIGENCE ASE ENDPOINT-BACKUP** drop-down list.

**Note:** If the Secondary ASE is not installed, you can choose Primary ASE Endpoint in **PINGINTELLIGENCE ASE ENDPOINT-BACKUP** drop-down list.

- e. In the **PINGINTELLIGENCE ASE TOKEN** field, enter ASE sideband token that is generated for authentication between PingAccess and ASE.
- f. If an OAuth token comes as part of a query string, enter the name of the query string in the **PINGINTELLIGENCE QS OAUTH** field.

**Note:** The PingIntelligence policy extracts the OAuth token from the query string, configured in **PINGINTELLIGENCE QS OAUTH**. A new Authorization header- `Authorization: Bearer`



<OAuth token> is added to the metadata sent to ASE. If there is an existing Authorization header, the token is prepended so that ABS AI engine can analyse it. If the query string has multiple query parameters with the same name, the first parameter is intercepted by the policy.

- g. Select the **ENABLE ASYNC MODE** to choose Asynchronous mode between PingAccess and ASE.

**Note:** The PingIntelligence policy supports both synchronous and asynchronous modes of communication between PingAccess and ASE. By default, the communication mode is synchronous. When the asynchronous mode is enabled, the PingAccess gateway does not wait for a response from ASE and sends the request to backend server. ASE performs attack detection without blocking of attacks in asynchronous mode.


The screenshot displays the PingAccess management console interface. The left sidebar shows the navigation menu with 'Rules' selected. The main content area is titled 'PingIntelligence' and shows the configuration for a specific rule. The configuration includes:

- NAME:** PingIntelligence
- TYPE:** PingIntelligence
- PINGINTELLIGENCE ASE ENDPOINT:** ASE ENDPOINT1
- PINGINTELLIGENCE ASE ENDPOINT - BACKUP:** ASE ENDPOINT2
- PINGINTELLIGENCE ASE TOKEN:** [Redacted]
- PINGINTELLIGENCE QS OAUTH:** [Redacted]
- ENABLE ASYNC MODE:**
- Show Advanced:** [Dropdown arrow]


Copyright © 2003-2020 Ping Identity Corporation All rights reserved

## 8. Apply the rule by completing the following steps :

- a. Edit the existing application.
- b. In the edit application page, click on **API Policy**.
- c. Under **Available Rules**, Click the **+** sign for the PingIntelligence rule.
- d. After clicking on the **+** sign, the PingIntelligence rule moves under the **API APPLICATION POLICY** as shown in the screen capture below.



- e. Click **Save** to save the rule.



**Note:** You can selectively apply the PingIntelligence sideband rule to individual Resources as well. To apply the sideband rule, click the **RESOURCES** tab and move the rule from **AVAILABLE RULES** onto the policy bar. For more information, see [Applying rules to applications and resources](#)

## Configure ASE persistent connection

You can optionally configure TCP keep-alive connections in the `ase.conf` file of ASE. Following is a snippet of `ase.conf` displaying the `enable_sideband_keepalive` variable. The default value is set to `false`.

```
; enable connection keepalive for requests from gateway to ase.
; This setting is applicable only in sideband mode.
; Once enabled ase will add 'Connection: keep-alive' header in response
; Once disabled ase will add 'Connection: close' header in response
enable_sideband_keepalive=false
```

## API discovery

PingIntelligence API discovery is a process to discover, and report APIs from your API environment. The discovered APIs are reported in PingIntelligence Dashboard. Complete the following two steps to automatically capture API definitions from PingAccess:

- Configure API discovery in PingIntelligence Dashboard
- Configure API discovery in PingAccess

Configure API discovery in PingIntelligence Dashboard

Configure the discovery parameters in the Dashboard as explained in [Configure API discovery](#) on page 541.

**Note:** Make sure that the ASE mode is configured to *sideband* in `webgui.properties`, and it matches the configuration in `/pingidentity/ase/config/ase.conf` file in ASE.

Ensure the following configurations specific to PingAccess are set:

**Set Discovery source** - Dashboard can discover APIs from three sources, ABS AI engine, PingAccess, and Axway API gateway. The discovery source is configured in the `/pingidentity/webgui/config/webgui.properties` file. Set the `pi.webgui.discovery.source` to `pingaccess`. Following is a snippet of the `webgui.properties` file for configuring the discovery source.

```
### api discovery properties
# discovery source
# valid values: abs, axway and pingaccess
# for axway and pingaccess, see config/discovery.properties
pi.webgui.discovery.source=pingaccess
```

**Set Credentials** - When the API discovery source is PingAccess, configure the gateway management URL and credentials in the `/pingidentity/webgui/config/discovery.properties` file. Following is a snippet of the `discovery.properties` file for configuring the credentials.

```
### PingAccess config. Only valid if pi.webgui.discovery.source=pingaccess
# Admin URL
pingaccess.management.url=https://127.0.0.1:9000/
# Admin username
pingaccess.management.username=Username
# Admin password
pingaccess.management.password=Password
```

Configure API discovery in PingAccess

For PingIntelligence Dashboard to automatically discover the APIs, include the following parameters in the **DESCRIPTION** section of an existing Application or while you add a new Application in PingAccess. The Application Type must be API.

```
{
  "ping_ai": true,
  "ping_host": "",
  "ping_url": "",
  "ping_login": "",
  "ping_cookie": "JSESSIONIDTEST",
  "apikey_qs": "X-API-KEY",
  "apikey_header": "",
  "ping_decoy": false,
  "oauth2_access_token": false,
  "ping_blocking": true
}
```

```
}

```

The following table describes the parameters captured when PingIntelligence Dashboard fetches the API definition from PingAccess and adds it to ASE.


Parameter	Description
ping_ai	When <code>true</code> , PingIntelligence processing is applied to this API. Set to <code>false</code> for no PingIntelligence processing. Default value is <code>true</code> .
ping_host	Hostname of the API. You can configure * as <code>hostname</code> to support any hostname.
ping_url	The base URL of the managed API, for example, <code>/shopping</code> . This field cannot be empty.
ping_login	Login URL for the API. The field can be empty.
ping_cookie	Cookie name for the API. The field can be empty.
apikey_qs	When API Key is sent in the query string, ASE uses the specified parameter name to capture the API key value. This field can be empty.
apikey_header	When API Key is part of the header field, ASE uses the specified parameter name to capture the API key value. This field can be empty.
ping_decoy	When <code>true</code> , API is a decoy API. The values can be <code>true</code> or <code>false</code> .
oauth2_access_token	When <code>true</code> , PingIntelligence expects an OAuth token. The values can be <code>true</code> or <code>false</code> .
ping_blocking	When <code>true</code> , enable PingIntelligence blocking when attack are detected on the API. The default value is <code>true</code> . To disable blocking for the API, set to <code>false</code> .

#### Related links


- [Discovered APIs](#) on page 540
- [API discovery and configuration](#) on page 347
- [Defining an API using API JSON configuration file in sideband mode](#) on page 170

## Handle exceptions

This topic discusses exception handling by PingIntelligence policy when ASE is unavailable. To ensure High-Availability the policy supports Primary and Secondary ASEs. In the event of an exception the gateway processes the current request or response to the corresponding destination. From the subsequent request or response a switch happens between the ASEs and the metadata is routed to the other ASE. The following diagram shows, the flow when an exception occurs.



You can configure an **Availability profile** to define the way PingAccess manages network requests. For more information, see [Availability profiles](#)



## PingFederate integration

### PingFederate sideband integration


You can deploy PingIntelligence for APIs in a sideband configuration with PingFederate server. PingIntelligence provides a sideband policy that extracts metadata from an authentication request or response processed by PingFederate. This metadata is passed to PingIntelligence to detect anomalous behavior and attacks by the client. PingIntelligence provides key metrics and forensics around such attacks. It also gives insights into normal traffic patterns by providing detailed client activity reports

The PingIntelligence policy for PingFederate is executed when a client requests an access token or refresh token from PingFederate. The policy secures the token endpoint `/as/token.oauth2`. For more information on the OAuth endpoints exposed by PingFederate, see [PingFederate OAuth 2.0 endpoints](#).

The PingIntelligence policy supports attack detection and reporting based on IP addresses of the clients. It is deployed in PingFederate as a servlet filter. It supports both OIDC and SAML V2 standards. The policy deployment does not require any reconfiguration of password credential validator (PCV).

The following diagram shows the architecture of PingIntelligence for APIs components and the interaction flow with PingFederate. The LDAP directory component in the diagram is used for illustrative purpose. PingFederate also supports other directories and user

data-stores through PCVs. For more information, see [Password Credential Validators](#).



The traffic flow through the PingFederate and PingIntelligence for APIs components is as follows:

1. A client sends a request with its authorization grant to PingFederate to obtain an access or refresh token.
2. The PingIntelligence for APIs policy deployed in PingFederate intercepts this request and extracts metadata such as origin IP address, and so on.
3. PingFederate makes an API call to send the metadata to API Security Enforcer (ASE). The ASE checks the client identifiers such as IP addresses against its blacklist. A blacklist is a list of client identifiers that were detected executing an attack. If all checks pass, ASE returns a `200-OK` response to PingFederate. If the checks do not pass, ASE sends a `403-Forbidden` response code to PingFederate and optionally blocks the client. In both the cases, ASE logs the request information and sends it to the API Behavioral Security (ABS) AI Engine to analyze the traffic patterns.
4. PingFederate forwards the client authentication request to the supported directory server.
5. PingFederate receives the response from the server.
6. The Ping Intelligence for APIs policy intercepts the response and extracts the metadata.
7. PingFederate makes a second API call to pass the response information to ASE, which sends the information to the ABS AI engine for processing.
8. PingFederate sends the requested token to the client.

Related links

- [Sideband ASE](#) on page 160
- [ABS AI Engine](#)
- [PingIntelligence for APIs Dashboard](#)

## Prerequisites

Complete the following prerequisites before deploying PingIntelligence policy on PingFederate:

- **Verify versions supported**

The PingIntelligence policy is qualified with the following combination.

PingFederate Version	JDK version	Password Credential Validator (PCV)
PingFederate 9.3.3	Oracle JDK8.0.u261	<ul style="list-style-type: none"> <li>▪ OpenLDAP-2.4.44</li> <li>▪ Simple Username Password Credential Validator</li> </ul>

If you are using any other versions of PingFederate or JDK, or any other PingFederate supported PCV, contact the Ping Identity support team for deployment support.

- **Install PingIntelligence software**

PingIntelligence software should be installed and configured. For more information on PingIntelligence deployment, see [PingIntelligence automated deployment](#) or [PingIntelligence manual deployment](#) on page 84.

- **Verify that API Security Enforcer (ASE) is in sideband mode**

Check that ASE is in sideband mode by running the following ASE command.

```
/opt/pingidentity/ase/bin/cli.sh status
API Security Enforcer
status                : started
mode                  : sideband
http/ws               : port 80
https/wss             : port 443
firewall              : enabled
abs                   : disabled, ssl: enabled
abs attack            : disabled
audit                 : enabled
sideband authentication : disabled
ase detected attack   : disabled
attack list memory    : configured 128.00 MB, used 25.61 MB, free 102.39
  MB
google pubsub         : disabled
log level              : debug
timezone              : local (UTC)
```

If ASE is not in sideband mode, complete the following steps:

1. Stop ASE if it is running. For more information, see [Start and stop ASE](#) on page 126.
2. Navigate to `/opt/pingidentity/ase/config/`.
3. Edit the `ase.conf` file and set mode parameter to `sideband`.
4. Start ASE. For more information, see [Start and stop ASE](#) on page 126.

- **Enable sideband authentication**

For a secure communication between PingFederate and ASE, enable sideband authentication by entering the following ASE command.

```
# ./bin/cli.sh enable_sideband_authentication -u admin -p
```

- **Generate sideband authentication token**

A token is required for PingFederate to authenticate with ASE. To generate the token in ASE, enter the following command in the ASE command line. Save the generated authentication token for further use.

```
# ./bin/cli.sh -u admin -p admin create_sideband_token
```



- **Enable connection keepalive between PingFederate and ASE**
  1. Stop ASE if it is running. For more information, see [Start and stop ASE](#) on page 126.
  2. Navigate to `/opt/pingidentity/ase/config/`.
  3. Edit the `ase.conf` file and set `enable_sideband_keepalive` parameter to `true`.
  4. Start ASE. For more information, see [Start and stop ASE](#) on page 126.

## Deploying the PingIntelligence policy

---

Deploy the PingIntelligence for APIs policy in PingFederate and complete the required configurations.

About this task

To deploy the PingIntelligence policy:

Steps

1. Download the PingIntelligence for APIs policy file from the [Sideband Integrations](#) section of the PingIntelligence download page and copy it to the node hosting PingFederate server.

**Note:**

If the PingFederate server is deployed in a cluster, then copy the policy to all the runtime engine nodes of the cluster.

2. Extract the policy file by entering the following command.

```
$ untar pi-api-pf-policy-4.3.tar.gz
```

3. Stop PingFederate. For more information, see [Start and stop PingFederate](#).
4. Copy the policy to the `pingfederate/server/default/deploy` directory.

```
$ cp pingidentity/pf-policy/pf-pi4api-filter.jar <pf_install>/pingfederate/server/default/deploy/
```

5. Complete the following configurations:
  - [Configuring PingIntelligence servlet filter](#) on page 761
  - [Configure API JSON in ASE](#)
6. Start PingFederate. For more information, see [Start and stop PingFederate](#).

### Configuring PingIntelligence servlet filter

Configure the servlet filter for PingIntelligence policy in the `webdefault.xml` file in PingFederate.

About this task

To define the PingIntelligence for APIs servlet filter:

## Steps

1. Add the the following filter configuration to the `<pf_install>/pingfederate/etc/webdefault.xml` file. Add the filter configuration within the `<web-app></web-app>` element.

**Note:**

If there are multiple filters in the `webdefault.xml` file, then place `pi4APIFilter` at the end.

```
<filter>
  <filter-name>pi4APIFilter</filter-name>
  <filter-class>com.pingidentity.pi.servlets.PI4APIServletFilter</
filter-class>
  <init-param>
    <param-name>ASE-Primary-URL</param-name>
    <param-value>https://<IP address of primary ASE>:<Port number></
param-value>
  </init-param>
  <init-param>
    <param-name>ASE-Secondary-URL</param-name>
    <param-value>https://<IP address of secondary ASE>:<Port number></
param-value>
  </init-param>
  <init-param>
    <param-name>ASE-Token</param-name>
    <param-value><ASE authentication token></param-value>
  </init-param>
  <init-param>
    <param-name>Enable-Blocking</param-name>
    <param-value>false</param-value>
  </init-param>
</filter>
<filter-mapping>
  <filter-name>pi4APIFilter</filter-name>
  <url-pattern>/as/token.oauth2</url-pattern>
</filter-mapping>
```

2. Make sure the following configurations are set correctly:

- The `filter-class` element is configured to `com.pingidentity.pi.servlets.PI4APIServletFilter`.
- The `pi4APIFilter` is mapped to the token endpoint URL of PingFederate by configuring the `url-pattern` element to `/as/token.oauth2`.
- The `filter-name` element in both the `<filter>` and `<filter-mapping>` blocks is `pi4APIFilter`.

3. Substitute the actual values for the `init` parameters in the `pi44APIFilter` filter.

The following table explains the `PI4API` `init` parameters in detail. They control the communication with API Security Enforcer (ASE). You can contact PingIdentity support team for the actual values of these parameters.

Parameter name	Description
ASE-Primary-URL	The URL or IP address of the ASE primary host.
	<p><b>Note:</b></p> <p>To support high availability, PingIntelligence provides ASE primary and secondary nodes.</p>

Parameter name	Description
ASE-Secondary-URL	The URL or IP address of the ASE secondary host.
ASE-Token	The ASE sideband authentication token. You can obfuscate the sideband authentication token using one of the following utilities available in the PingFederate <code>&lt;pf_install&gt;/pingfederate/bin/</code> directory: <ul style="list-style-type: none"> <li>On Windows: <code>obfuscate.bat</code></li> <li>On Linux: <code>./obfuscate.sh</code></li> </ul> If you need further assistance in using the utility, contact Ping Identity support.
Enable-Blocking	You can optionally block a client that has been detected executing an attack. To block the client, you need to enable blocking in ASE by setting the Enable-Blocking to <code>true</code> . The default value is <code>false</code> .

## Configuring API JSON

Configure the API JSON file in API Security Enforcer (ASE).

About this task

The API JSON file parameters define the connectivity to the token endpoint.

To configure the API JSON file:

Steps

1. Navigate to the `/pingidentity/ase/config/` directory.
2. Edit the `sideband_api.json.example` file, and set the value of `url` parameter to `/as` and `login_url` parameter to `/as/token.oauth2`.

**Note:**

`/as/token.oauth2` is the token endpoint of PingFederate authorization server.

3. Rename the `sideband_api.json.example` file to `pf.json`.
4. After configuring the API JSON file, add it to ASE by executing the following command.

```
/opt/pingidentity/ase/bin/cli.sh -u admin -p admin add_api pf.json
```

The following is a sample configuration of the API JSON file.

```
{
  "api_metadata": {
    "protocol": "http",
    "url": "/as",
    "hostname": "*",
    "cookie": "",
    "oauth2_access_token": false,
    "apikey_qs": "",
    "apikey_header": "",
    "login_url": "/as/token.oauth2",
```

```

"enable_blocking": true,
"api_memory_size": "128mb",
"decoy_config": {
  "decoy_enabled": false,
  "response_code": 200,
  "response_def": "",
  "response_message": "",
  "decoy_subpaths": []
}
}
}

```

**Note:**

For more information on configuring API JSON parameters, see [Defining an API using API JSON configuration file in sideband mode](#) on page 170.

## WSO2 API gateway integration

---

### PingIntelligence WSO2 integration

---

PingIntelligence for APIs in a sideband deployment integrates with WSO2 API gateway to provide in depth analytics on API traffic. In the deployment WSO2 API Gateway is the primary component that intercepts API requests and applies various types of policies. Each policy is executed using something we call an “API Handler”. The API gateway architecture allows users to add specific handlers to perform various tasks in different stages of the request flow. This implementation comes with a handler that allows users to perform sideband calls to the Ping ASE. With these sideband calls, it publishes API request metadata to Ping and checks the validity of the request. It does the same for the response as well. With the provided request metadata Ping ASE can detect abnormal access patterns. It also builds a knowledge base using API request data sent to it.

For more information on PingIntelligence - WSO2 integration, see [Artificial Intelligence Based API Security with WSO2 and PingIntelligence for APIs](#).

## PingIntelligence Docker toolkit

---

PingIntelligence for APIs provides a Docker toolkit to create Docker images of PingIntelligence components and MongoDB. The Docker toolkit can be run on either RHEL or Ubuntu machines. The supported versions are, RHEL 7.9 or Ubuntu 18.0.4 LTS.

The Docker toolkit provides information on environment variables available for the PingIntelligence components, and an example Kubernetes `.yaml` file for automated deployment of PingIntelligence in Kubernetes environments. For more information on using the `.yaml` file, see [PingIntelligence Kubernetes PoC](#) on page 34.

#### Prerequisites

[Download](#) the following PingIntelligence components, tools, and open source modules:

- Download products:
  - PingIntelligence ASE 5.0
  - PingIntelligence ABS 5.0
  - PingIntelligence Dashboard 5.0
  - MongoDB 4.2.0
  - OpenJDK 11.0.2 to 11.0.6
  - Kibana 6.8.1
  - Elasticsearch 6.8.1
- License:

Obtain valid PingIntelligence for APIs license files from Ping Identity sales team.

**Note:**

- Download the correct ASE binary based on the base image you want to create.
- Download the correct MongoDB 4.2.0 binary based on the Docker image you want to build.

## Untar the Docker toolkit

To use the Docker toolkit, you need to untar the toolkit. Run the following command to untar the toolkit:

```
tar -zxvf pi-api-docker-toolkit-5.0.tar.gz
```

Untarring the Docker toolkit, creates the directory structure as shown in the following table:

Directory	Description
bin	Contains the <code>build.sh</code> script to build the Docker images
config	Contains the <code>docker.conf</code> file to configure the base image name and the base image operating system
certs/webgui	Contains the PingFederate public certificate file, <code>webgui-ss-oidc-provider.crt</code> . PingIntelligence Dashboard Docker image can be generated by optionally packaging it with the PingFederate public certificate.
data	For internal use
external	Contains the third-party software: <ul style="list-style-type: none"> <li>▪ MongoDB 4.2.0</li> <li>▪ Elasticsearch 6.8.1</li> <li>▪ Kibana 6.8.1</li> <li>▪ OpenJDK 11.0.2 to 11.0.6</li> </ul>
images	Contains the created Docker images using the <code>build.sh</code> script
lib	For internal use
license	Contains the PingIntelligence license file. <p><b>Note:</b> You can build the images without adding the license file to the <code>license</code> directory. If you build the Docker images without the license file in <code>license</code> directory, then you need to map or mount the license file in the <code>/config/</code> directory.</p>

logs	Contains the log files
software	Contains PingIntelligence ASE, ABS, and Dashboard

### Configure docker.conf

Navigate to the `config` directory and edit the `docker.conf` file for base image name and base image operating system. Following is a sample `docker.conf` field:

```
# Base image name using which all the PingIntelligence images are created
base_image=registry.access.redhat.com/rhel7:7.9

# Operating system of the base image. The valid values are ubuntu or rhel
base_image_os=rhel

# Define the username for images. This user is added to the Docker
# images. Containers created from these Docker images use the configured #
# user to run PingIntelligence software
user_name=pinguser
```

**Note:** Do not set the `user_name` as `root` in `docker.conf` file.

## Build the PingIntelligence Docker images

Use the `build.sh` script available in the `bin` directory to build the Docker images. You can build all the following Docker images at once or you can choose to build the images individually. The following Docker images are built:

- ASE
- ABS
- Dashboard
- MongoDB

It is a good practice to obfuscate the various keys and password in ASE, ABS, and Dashboard before building the Docker images. For more information on obfuscating keys and passwords, see the following topics:

- ASE - [Obfuscate keys and passwords](#)
- ABS - [Obfuscate passwords](#)
- Dashboard - [Obfuscate keys and passwords](#) on page 473

Complete the following steps to build the Docker images:

1. Configure the base image name and base image operating system details in the `config/docker.conf` file.
2. Download the following PingIntelligence software in to the `software` directory:
  - ASE
  - ABS
  - PingIntelligence Dashboard
3. Download OpenJDK 11.0.2, Kibana 6.8.1, Elasticsearch 6.8.1 and MongoDB 4.2.0 in the `external` directory and save them with the name as shown in the following table:

Software	File name
Elasticsearch	elasticsearch.tar.gz

OpenJDK 11.0.2	openjdk11.tar.gz
Kibana	kibana.tar.gz
MongoDB	mongodb.tgz

**Note:** Make sure that MongoDB is as per the base image configured in `docker.conf` file.

4. Run the `build.sh` script to build the Docker images:

```
docker-setup# ./bin/build.sh all
Base image os: rhel
Creating build context for ASE
Creating Image
Image created with tag pingidentity/ase:5.0
Image saved to /home/ubuntu/docker-setup/images/pingidentity_ase.tar
Creating build context for abs
Creating Image
Image created with tag pingidentity/abs:5.0
Image saved to /home/ubuntu/docker-setup/images/pingidentity_abs.tar
Creating build context for dashboard
Creating Image
Image created with tag pingidentity/dashboard:5.0
Image saved to /home/ubuntu/docker-setup/images/pingidentity_dashboard.tar
Creating build context for mongo
Creating Image
Image created with tag pingidentity/mongo:4.2.0
Image saved to /home/ubuntu/docker-setup/images/pingidentity_mongo.tar
root@ip-172-31-25-146:/home/ubuntu/docker-setup# vim lib/dashboard/
context/entrypoint.sh
```

The other options that you can give with `build.sh` are: `ase`, `abs`, `dashboard`, and `mongo`.

5. Verify that the images are created by checking the local registry. Run the following command:

```
sudo docker image ls | grep pingidentity
pingidentity/dashboard          5.0          4c2b1378bec0
 38 minutes ago                2.07GB
pingidentity/mongo              4.2.0       fcf3986eab34
 3 days ago                     781MB
pingidentity/abs                5.0         feced8848a28
 3 days ago                     910MB
pingidentity/ase                5.0         5ab75d3180ed
 3 days ago                     595MB
```

6. Verify that the Docker images are saved in the `images` directory:

```
docker-setup# ls -ltra images/
total 3437116
drwxr-xr-x 11 root root          4096 Sep 18 18:39 ..
-rw----- 1 root root 782182400 Sep 21 10:18 pingidentity_abs.tar
-rw----- 1 root root 495038976 Sep 21 10:20 pingidentity_mongo.tar
-rw----- 1 root root 339437568 Sep 23 06:57 pingidentity_ase.tar
-rw----- 1 root root 1302484480 Sep 23 08:08 pingidentity_dashboard.tar
drwxr-xr-x 2 root root          4096 Sep 23 08:08 .
```

**Note:** The Docker images do not install any additional packages like `vi` editor and so on.

## Environment variables exposed in Docker images

Environment variables are exposed in the Docker images. If you do not set the environment variable, the default values are used. The following tables list the environment variables for ASE, ABS, Dashboard, and MongoDB.

**ASE Environment Variables:** The following table lists the ASE environment variables and the values:

Environment	Value	Usage
MODE	inline/ sideband	ASE can be deployed either in inline mode or sideband mode. For more information, see the <a href="#">ASE admin guide</a> .
TIMEZONE	string	Set the timezone of ASE to either <code>local</code> or <code>UTC</code> . Default value is <code>utc</code> .  <i>ⓘ</i> <b>Note:</b> Make sure TIMEZONE is set to the same value in ASE, ABS, and Dashboard.
ENABLE_CLUSTER	True/false	Set the value to <code>true</code> to enable ASE cluster.
ENABLE_ABS	true/false	Set the value to <code>true</code> to enable ABS.
PEER_NODE	<IP or hostname>:port	ASE cluster peer node's IP address and port number
ASE_SECRET_KEY	string	Set the value of the ASE secret key.  <i>ⓘ</i> <b>Note:</b> ASE access key cannot be changed. Its value always remains <code>admin</code> .
ABS_ENDPOINT	<IP or hostname>:port	IP address or host name of the ABS endpoint
ABS_ACCESS_KEY	string	Access key to connect to ABS
ABS_SECRET_KEY	string	Secret key to connect to ABS
ADMIN_LOG_LEVEL	EL-5	1-5 (FATAL, ERROR, WARNING, INFO, DEBUG)
ENABLE_SIDEBAND_CLIENT_AUTHENTICATION	True/False	Enable client side authentication. This setting is applicable only in sideband mode. Once enabled, ASE authenticates requests using ASE authentication tokens.
ENABLE_SIDEBAND_CONNECTION_KEEPALIVE	True/False	Set the value to <code>true</code> to enable connection keepalive for requests from gateway to ASE. This configuration is applicable only in sideband mode.
ENABLE_ASE_HEALTH_CHECK	True/false	Set the value to <code>true</code> to enable ASE health check module.
ENABLE_GOOGLE_PUBSUB	True/False	Google Pub/Sub configuration
GOOGLE_PUBSUB_CONNECTION	string	
GOOGLE_PUBSUB_CONCURRENCY	number	Number of concurrent connections to Google Pub/Sub Minimum: 1, Default: 1000, Maximum: 1024
GOOGLE_PUBSUB_RATE	number	Number of messages published per second. Minimum: 1, Default: 1000, Maximum: 10000



GOOGLE_PUBSUB_API_KEY	string	Google service account API key (Optional)
CACHE_QUEUE_SIZE	number	Maximum number of messages buffered in memory. If queue is full, messages are written to <code>logs/google_pubsub_failed.log</code> Minimum: 1, Default: 300, Maximum: 10000
GOOGLE_PUBSUB_TIMEOUT	number	Timeout in seconds to publish a message to Google Pub/Sub. Minimum: 10, Default: 30, Maximum: 300
DEPLOYMENT_TYPE	string	Indicates ABS deployment type to ASE. Supported values are <code>onprem</code> or <code>cloud</code> .
GATEWAY_CREDENTIALS	string	The obfuscated gateway credentials that are generated at cloud portal. ASE parses these gateway credentials to get OAuth URL and URL for ABS API calls.  Populate this value when <code>DEPLOYMENT_TYPE</code> is set to <code>cloud</code> .

**ABS Environment Variables:** The following table lists the ABS environment variables and the values:

Environment	Value	Usage
MONGO_RS	<code>mongodb://&lt;IP or hostname&gt;:&lt;port&gt;,&lt;IP or hostname&gt;:&lt;port&gt;, &lt;IP or hostname&gt;:&lt;port&gt;</code>	MongoDB replica set IP addresses or host names and port numbers.
MONGO_USERNAME	string	MongoDB username
MONGO_PASSWORD	string	MongoDB password
ABS_LOG_LEVEL	string	Log levels (ALL > DEBUG > INFO > WARN > ERROR > FATAL > OFF) Default is INFO
MONGO_SSL	true/false	Set to true if MongoDB instance is configured in SSL mode. By default, ABS will try to connect to MongoDB using non-SSL connection. Default is false
IS_DASHBOARD_NODE	true/false	Setting as true makes an ABS node for dashboard engine query only and does not participate in ABS cluster for log processing
ENABLE_EMAILS	true/false	Enable (true) or disable (false) ABS email notifications.
SENDER_EMAIL	string	Email address used for sending email alerts and reports.

SENDER_EMAIL_PASSWORD	string	<p>Password of sender's email account.</p> <p><b>Note:</b> You can leave this field blank if your SMTP server does not require authentication.</p>
RECEIVER_EMAIL	string	Email address notified about alerts and reports. If you want more than one person to be notified, use an email alias.
ABS_CLI_ADMIN_PASSWORD	string	Set the ABS CLI admin password.
ABS_JKS_PASSWORD	string	Set the ABS Java keystore password.
MONGO_CERTIFICATE_VERIFY	boolean/false	<p>Set to true if you want to enable verification of MongoDB SSL server certificate.</p> <p>By default, ABS will try to connect to MongoDB without verifying SSL connection. Default is false</p>
TIMEZONE	string	<p>Set the timezone of ABS to either <code>local</code> or <code>UTC</code>. Default value is <code>utc</code>.</p> <p><b>Note:</b> Make sure TIMEZONE is set to the same value in ASE, ABS, and Dashboard.</p>
ABS_ACCESS_KEY	string	The access key for the ABS admin user. For more information, see <a href="#">ABS users</a>
ABS_SECRET_KEY	string	The secret key for the ABS admin user. For more information, see <a href="#">ABS users</a>
ABS_ACCESS_KEY_RU	string	The access key for the restricted user. For more information on restricted user, see <a href="#">ABS users</a> .
ABS_SECRET_KEY_RU	string	The secret key for the restricted user. For more information on restricted user, see <a href="#">ABS users</a> .
ATTACK_INITIAL_TRAINING	Integer	The attack training period
ATTACK_UPDATE_INTERVAL	Integer	Attack threshold uphold interval
API_DISCOVERY	true/false	Set the value to true to enable API discovery in ABS. For ABS to discover APIs, a global API JSON must be configured in ASE. For more information, see <a href="#">API discovery and configuration</a> on page 347.
API_DISCOVERY_INITIAL_PERIOD	Integer	The initial period set in hours in which ABS has to be discover APIs. It is a good practice to keep the API discovery interval period less than the initial attack training interval.

API_DISCOVERY_UPDATE_INTERVAL	integer	The time period in hours in which ABS reports the newly discovered APIs
API_DISCOVERY_SUBPATH	integer	The number of subpaths that are discovered in an API. The maximum value is 3.
POC_MODE	string	Sets the mode in which ABS trains its API models. Set it to <code>true</code> for running ABS in POC mode. For more information, see <a href="#">ABS POC mode</a> on page 313

**MongoDB Environment Variables:** The following table lists the MongoDB environment variables and the values:

Environment	Value	Usage
MONGO_USERNAME	string	MongoDB username
MONGO_PASSWORD	string	MongoDB password
MULTI_NODE_REPLICA_SET	boolean	Set it to <code>true</code> if you want to run multiple MongoDB nodes in MongoDB replica set. The default value is <code>false</code> . If you have set it to <code>true</code> , then manually add MongoDB nodes into replica set. Run <code>abs_init.js</code> script from the primary MongoDB node.
WIRED_TIGER_CACHE_SIZE_GB	integer	Memory in GB to be used by MongoDB cache.
MONGO_SSL	string	Configures whether MongoDB uses SSL. Default values is <code>false</code> .

**Dashboard Environment Variables:** The following table lists the Dashboard environment variables and the values:

Environment	Value	Usage
DISCOVERY_SOURCE	string	Source of API discovery. Values can be <code>abs</code> , <code>pingaccess</code> , or <code>axway</code> .
PINGACCESS_URL	string	URL of PingAccess if you set the discovery source as <code>pingaccess</code> .
PINGACCESS_USERNAME	string	PingAccess username for API discovery.
PINGACCESS_PASSWORD	string	PingAccess password for API discovery.
AXWAY_URL	string	URL of Axway if you set the discovery source as <code>axway</code> .
AXWAY_USERNAME	string	Axway username for API discovery.
AXWAY_PASSWORD	string	Axway username for API discovery.
DISCOVERY_MODE	string	Mode in which Dashboard publishes APIs to ASE. Values can be <code>auto</code> or <code>manual</code> . For more information, see <a href="#">Discovered APIs</a> on page 540
DISCOVERY_MODE_AUTO_POLLING_INTERVAL	integer	If the <code>DISCOVERY_MODE</code> is set as <code>auto</code> , set the polling interval at which Dashboard polls the discovery source for APIs. It is recommended to have minimum value of 10-minutes.
DISCOVERY_MODE_AUTO_DELETE	boolean	If the <code>DISCOVERED_API</code> is set as <code>auto</code> , you can choose to retain or delete APIs in ASE which are added manually. Set it to <code>true</code> , if you want to delete the APIs that are manually added in ASE.

ASE_MODE	string	Sets the mode in which ASE is deployed. Values can be either <code>inline</code> or <code>sideband</code> . Make sure this value is same as that set in ASE.
ABS_ACCESS_KEY	string	The access key for the ABS admin user. For more information, see <a href="#">ABS users</a>
ABS_SECRET_KEY	string	The secret key for the ABS admin user. For more information, see <a href="#">ABS users</a>
ABS_HOST	string	IP address of ABS host
ENABLE_XPACK	string	Configures whether x-pack is installed. Default value is <code>true</code> . If the variable is set to <code>false</code> , the Web GUI protocol should be HTTP.
ENABLE_SYSLOG	string	Configures whether Dashboard sends syslog messages to the syslog server. The default value is <code>false</code> .  <div style="border: 1px solid black; padding: 5px;"> <p><b>i Important:</b> <code>ENABLE_SYSLOG</code> and <code>ENABLE_UI</code> both cannot be <code>false</code> at the same time.</p> </div> <p>When <code>ENABLE_SYSLOG</code> environment variable is passed to the container, <code>SYSLOG_HOST</code> and <code>SYSLOG_PORT</code> should also be passed. These are to configure the syslog server and port number.</p>
ABS_RESTRICTED_USER_ACCESS	boolean	Set to true if you want to use ABS restricted user. For more information on restricted user, see <a href="#">ABS users</a> .
ABS_URL	string	The URL should be in the form of <code>https://&lt;IP&gt;:&lt;port&gt;</code> . The URL is used by Web GUI to connect to ABS.
ASE_URL	string	The URL should be in the form of <code>https://&lt;IP&gt;:&lt;port&gt;</code> . The URL is used by Web GUI to connect to ASE.
ASE_ACCESS_KEY	string	Access key of the ASE admin user
ASE_SECRET_KEY	string	Secret key of the ASE admin user
DASHBOARD_URL	string	The URL should be in the form of <code>https://&lt;IP&gt;:&lt;port&gt;</code> . The URL is used by Web GUI to connect to dashboard. IP and port number are of Kibana.
H2_DB_PASSWORD	string	Password for H2 database
H2_DB_ENCRYPTION_PASSWORD	string	Password to change encryption method of H2 database
WEBGUI_ADMIN_PASSWORD	string	Password for admin user of Web GUI
WEBGUI_PING_USER_PASSWORD	string	Password for <code>ping_user</code> of Web GUI
SESSION_MAX_AGE	6h	Defines the maximum time for a session. The configured values should be in the form of <code>&lt;number&gt;&lt;duration_suffix&gt;</code> . Duration should be <code>&gt; 0</code> . Allowed <code>duration_suffix</code> values: <code>m</code> for minutes, <code>h</code> for hours, and <code>d</code> for days.
MAX_ACTIVE_SESSIONS	50	Defines the maximum number of active UI sessions at any given time. The value should be greater than 1.
AUTHENTICATION_MODE	local or sso	Set the value to <code>sso</code> to authenticate Dashboard with PingFederate

SSO_OIDC_CLIENT_ID	string	Client ID value in configured in the Identity provider.
SSO_OIDC_CLIENT_SECRET	SECRET	Client Secret configured for the corresponding Client ID.
SSO_OIDC_CLIENT_AUTHENTICATION_MODE	BASIC, POST, and NONE	OIDC Client authentication mode. The valid values are BASIC, POST, or NONE
SSO_OIDC_PROVIDER_ISSUER_URI	string	PingFederate URI that is required by webgui to establish SSO. The default value is <code>https://127.0.0.1:9031</code> .  <i>Note:</i> PingIntelligence Dashboard Docker image can be generated by packaging it with PingFederate public certificate. For doing this the certificate needs to be placed in <code>certs/webgui</code> directory with the name <code>webgui-ssoidc-provider.crt</code> .
SSO_OIDC_PROVIDER_USER_UNIQUE_ID	string	Claim name for unique ID of the user in UserInfo response. A new user is provisioned using this unique ID value.
SSO_OIDC_PROVIDER_USER_FIRST_NAME	string	Claim name for first name of the user in UserInfo response. Either first name or last name can be empty, but both should not be empty.
SSO_OIDC_PROVIDER_USER_LAST_NAME	string	Claim name for last name of the user in UserInfo response. Either first name or last name can be empty, but both should not be empty
SSO_OIDC_PROVIDER_USER_ROLE	string	Claim name for role of the user in UserInfo response. Valid values for roles are ADMIN and REGULAR.
SSO_OIDC_PROVIDER_ADDITIONAL_SCOPES	string	Additional scopes in authorization request. Multiple scopes should be comma (,) separated values. OpenID, profile scopes are always requested.
TIMEZONE	string	Set the timezone of Dashbord to either <code>local</code> or <code>UTC</code> . Default value is <code>utc</code> .  <i>Note:</i> Make sure TIMEZONE is set to the same value in ASE, ABS, and Dashboard.

## ILM policy configuration in Dashboard

The Index Lifecycle Management (ILM) policy allows for an automatic rollover of index based on time or size of data. The `ilm.json` file contains the configurations of the policy. The following table lists the variables that you can set in the `ilm.json` file. For more information on `ilm.json` configuration, see [Automatic rollover index](#) on page 504.

Variable	Description
<code>max_size</code>	Defines the maximum size of the Elasticsearch rollover index. When the index size reaches the defined value, it roll over. <code>max_size</code> value should be a positive non-zero number. Allowed units are MB and GB.

Variable	Description
max_age	Defines the maximum age of the Elasticsearch rollover index configuration. <code>max_age</code> value should be a positive non-zero number. Allowed units are <code>h</code> for hours and <code>d</code> for the number of days. If both <code>max_size</code> and <code>max_age</code> are configured, then the index rolls over based on the value which is achieved first.
min_age	Defines the minimum age, after which the Elasticsearch rollover index enters into a different phase. Allowed units are <code>h</code> for hours and <code>d</code> for the number of days. Every index starts from <code>hot</code> phase. For more information on the phases in an index life cycle, see <a href="#">Automatic rollover index</a> on page 504.
priority	Defines the sequence in which, indices are reloaded back into memory when Elasticsearch restarts. Use a positive integer number to set the priority.

Following is snippet of a sample `ilm.json` file.

```
{
  "policy": {
    "phases": {
      "hot": {
        "actions": {
          "rollover": {
            "max_size": "7GB",
            "max_age": "7d"
          },
          "set_priority": {
            "priority": 100
          }
        }
      },
      "warm": {
        "min_age": "30d",
        "actions": {
          "set_priority": {
            "priority": 50
          }
        }
      },
      "cold": {
        "min_age": "90d",
        "actions": {
          "freeze": {},
          "set_priority": {
            "priority": 0
          }
        }
      }
    }
  }
}
```

## Using environment variables - example

The following sections show example of using environment variables to create containers. The containers must be created in the following order:

1. MongoDB
2. ABS
3. ASE
4. Dashboard

**Launch MongoDB container:** Run the following command with some sample environment variables to launch the MongoDB container:

```
docker run -d --name mongo --hostname mongo -e
  MONGO_USERNAME="new_mongo_user" \
-e MONGO_PASSWORD="new_mongo_password" \
-e WIRED_TIGER_CACHE_SIZE_GB="1.8" \
-e MONGO_SSL="true" pingidentity/mongo:4.2.0
```

Running this command creates the MongoDB container with settings in environment variable provided. If any of the environment variable is not used, then the container is launched with default values.

**Launch ABS container:** Run the following command with some sample environment variables to launch the ABS container:

```
docker run -d --name abs --hostname abs --link mongo:mongo -e
  MONGO_RS=mongodb://mongo:27017 \
-e MONGO_USERNAME="new_mongo_user" \
-e MONGO_PASSWORD="new_mongo_password" -e MONGO_SSL="true" \
-e ABS_ACCESS_KEY="new_abs_ak" \
-e ABS_SECRET_KEY="new_abs_sk" -e ABS_ACCESS_KEY_RU="new_abs_ak_ru" \
-e ABS_SECRET_KEY_RU="new_abs_sk_ru" \
-e ATTACK_INITIAL_TRAINING="24" \
-e API_DISCOVERY="true" -e API_DISCOVERY_INITIAL_PERIOD="6" \
-e API_DISCOVERY_UPDATE_INTERVAL="1" \
-e API_DISCOVERY_SUBPATH="3" \
pingidentity/abs:5.0
```

**Launch ASE container:** Run the following command with some sample environment variables to launch the ASE container:

```
docker run -d --name ase --link abs:abs --hostname ase -e MODE="inline" \
-e ENABLE_CLUSTER="true" -e ENABLE_ABS="true" -e ABS_ENDPOINT="abs:8080" \
-e ABS_ACCESS_KEY="new_abs_ak" -e ABS_SECRET_KEY="new_abs_sk" --shm-size=1g
pingidentity/ase:5.0
```

**Launch the second ASE node in ASE cluster:** Run the following command with some sample environment variables to launch the ASE node in a cluster:

```
docker run -d --name ase1 --link abs:abs --link ase:ase --hostname ase1 \
-e MODE="inline" -e ENABLE_CLUSTER="true" \
-e PEER_NODE="ase:8020" -e ENABLE_ABS="true" \
-e ABS_ENDPOINT="abs:8080" -e ABS_ACCESS_KEY="new_abs_ak" \
-e ABS_SECRET_KEY="new_abs_sk" --shm-size=1g pingidentity/ase:5.0
```

**Launch Dashboard:** Run the following command with some sample environment variables to launch the Dashboard container:

```
docker run -d --name webgui --link abs:abs --link ase:ase --hostname webgui \
-e ABS_RESTRICTED_USER_ACCESS="false" \
-e ABS_ACCESS_KEY="new_abs_ak" -e ABS_SECRET_KEY="new_abs_sk" -e \
ABS_HOST="abs" \
-e ABS_URL="https://abs:8080" -e ASE_URL="https://ase:8010" \
-e DASHBOARD_URL="https://localhost:5601" -e \
WEBGUI_ADMIN_PASSWORD="new_webgui_admin_password" \
-e WEBGUI_PING_USER_PASSWORD="new_webgui_pinguser_password" \
-p 8030:8030 pingidentity/dashboard:5.0
```

### Port mapping

When the containers are created, the exposed ports are not mapped. To map the ports, you need to complete port mapping using the `-p` option in the `docker run` command. The following table lists the ports that should be exposed in the container.

Component	Port number	Usage
ASE	8080	HTTP data plane
	8443	HTTPS data plane
	8010	Management port number
	8020	Cluster port number
ABS	8080	API server port number
Dashboard	8030	Dashboard port number
MongoDB	27017	MongoDB port number

## PingIntelligence Hardening Guide

---

### PingIntelligence security hardening guide

---

The hardening document provides administrators with a single point of reference for configurations and best practices available to harden their platform. To avoid duplication, this document does not include the detailed configuration instructions. Instead, it refers readers to information on hardening the PingIntelligence platform.

#### Ping security overview

One of the key security principles we follow at Ping is to make configurations secure by default. However, it is not always possible to create one-size-fits-all security configurations. This document contains recommendations on how PingIntelligence administrators can further harden their platform based on their individual needs.

The recommendations are grouped by different PingIntelligence functional components. When administrators work on deploying a component in PingIntelligence, they can look up the corresponding section in this document.



Accessing the document

Click on [PingIntelligence security hardening guide](#), to access this document. You must have a registered account to the [PingIdentity support and community portal](#), for accessing it. If you need any further assistance, contact Ping sales team.

## PingIntelligence Monitoring Guide

---

This guide discusses steps to monitor the performance and health of your PingIntelligence deployment.

The document explains different methods to conduct health checks on PingIntelligence components. It provides recommendations on resource-utilization thresholds and patterns. It also discusses trouble shooting tips.

### PingIntelligence Health Check Guide

---

This document provides administrators with a list of commands that can be used to perform health checks on different PingIntelligence components.

There are multiple methods explained for each component. You can automate the steps or use them in manual mode. The document also captures information on log files, PID details, and port details of following PingIntelligence component:

#### Perform health checks on ASE

This section discusses the commands that can be used to check the health status of ASE. You can use the following options to conduct a health check on ASE nodes :

- **Health check URL**

Enable the ASE health check URL in the `/pingidentity/ase/config/ase.conf` file. To do this set the `enable_ase_health` config property to `true`. The default value of `enable_ase_health` is `false`.

If the configuration is modified on a running ASE node, restart the node after modifying the configuration. For more information, see [Start and stop ASE](#) on page 126. In a clustered ASE environment, stop the ASE cluster and update the `ase.conf` file of the primary node and restart the other ASE nodes. For more information, see [Restart ASE cluster](#) on page 139.

Once the `enable_ase_health` is set to `true`, hit the following URLs and do a health check. If ASE is receiving the traffic, the response will be `200 OK`.

```
http://<ase-hostname/ip>:<http_port>/ase
https://<ase-hostname/ip>:<https_port>/ase
```

- **Status command**

Use the following CLI command to know the status of an ASE process, the running status of http or https process, and port number. It also gives basic configuration information.

```
$/bin/cli.sh status
```

- **ABS Info command**

This command shows the status of communication between ABS and all the ASE nodes in a cluster. It shows last log upload and attack fetch information from ABS. If ASE is having any issues in uploading logs to ABS or connecting to ABS it will be reported in the output of the `abs_info` command.

```
$ ./bin/cli.sh -u admin -p admin abs_info
```

- **Process status**

If ASE is running as a `systemctl` service, use the following command to check the status of the service.

```
$ systemctl status pi-ase.service
```

## Perform health checks on ABS AI Engine

This section discusses the commands that can be used to check the health status of ABS AI Engine. You can use the following options to conduct a health check :

- **ABS Admin API**

Use the ABS [Admin REST API](#) on page 418 either from the Postman Collection or use curl command.

```
$ curl -k -X GET 'https://<ABS Hostname/IP:8080/v4/abs/admin' -H 'x-abs-ak: <ABS access key>' -H 'x-abs-sk: <ABS ssecret key>'
```

- **Process status**

If ABS AI Engine is running as a `systemctl` service, use the following command to check the status of the service.

```
$ systemctl status pi-abs.service
```

- **Check ABS log for job failures**

Use the following command to check the ABS log for any job failures. If any failures are detected, reach out to Ping Identity support team.

```
$ grep allocated logs/abs/abs.log | grep failure
```

- **Check ABS log for MongoDB heartbeat**

The `/logs/abs/abs.log` file reports the status of MongoDB heart beats at regular intervals. This is a good indicator to check ABS to MongoDB connectivity issues.

## Perform health checks on PingIntelligence Dashboard

This section discusses the commands that can be used to check the health status of PingIntelligence Dashboard and its components..

Dashboard data engine

- **Status command**

This command shows the status of the dashboard process.

```
$ ./bin/cli.sh status
```

It returns the status as Running or Not Running.

- **Process status**

If the dashboard data engine is running as a `systemctl` service, use the following command to check the status of the service.

```
$ systemctl status pi-dashboard.service
```

- **Check dashboard log file for errors or exceptions**

To detect the connectivity issues between dashboard data engine and ABS or Elasticsearch verify the `/pingidentity/dashboard/logs/dashboard.log` file.

```
$ tail logs/dashboard.log
```

## Web GUI

- **Health check URL**

The following URL provides a `200 OK` response if WebGUI component is up and running. You can use `curl` command or browser to check the status.

```
https://<WebGUI Hostname/IP>:<port>/status
```

```
$ curl -k -o /dev/null -s -w "%{http_code}\n" https://<webgui>:8030/status
200
```

- **Status command**

The following command shows the status of the WebGUI process.

```
$ ./bin/cli.sh status
```

- **Process status**

If the WebGUI is running as a `systemctl` service, use the following command to check the status of the service.

```
$ systemctl status pi-webgui.service
```

- **Check WebGUI admin log file for errors or exceptions**

To detect the connectivity issues between WebGUI and ABS or Elasticsearch verify the `/pingidentity/webgui/admin/logs/admin.log` file.

```
$ tail logs/admin/admin.log
```

## Elasticsearch

- **Health check URL**

There are three ways to check the health of Elasticsearch using a health check URL

- Using anonymous access - To enable access for anonymous user, add the following line to the `elasticsearch.yaml`.

```
xpack.security.authc.anonymous.roles: monitoring_user
```

You can update this during initial setup or later. You must restart Elasticsearch if you are making the change on a running instance. After updating the `elasticsearch.yaml` hit the following URL

to check the status of Elasticsearch. You can use curl command or browser. A 200 OK response indicates a running Elasticsearch.

```
https://<Elasticsearch Hostname/IP>:9200/
```

```
$ curl -k -o /dev/null -s -w "%{http_code}\n" https://<Elasticsearch Hostname/IP>:9200/
```

- Using a health check user- Add a health check user to Elasticsearch using the following command.

```
curl -u elastic:<elastic user password> -k -X POST "https://localhost:9200/_xpack/security/user/<health_check_user>?pretty" -H 'Content-Type: application/json' -d '{
  "password" : "<password for health_check_user>",
  "roles": ["monitoring_user"]
}'
```

After adding the health check user, hit the following URL to check the status of Elasticsearch. You can use curl command or browser. A 200 OK response indicates a running Elasticsearch.

```
https://<health_check_user>:<password>@<Elasticsearch hostname/IP>:9200/
```

```
$ curl -k -o /dev/null -s -w "%{http_code}\n" https://<health_check_user>:<password>@<Elasticsearch hostname/IP>:9200/
```

**Note:** This approach doesn't require an Elasticsearch restart.

- Using Elasticsearch username and password - You can query the health status of Elasticsearch using the elastic user and its password to see a more comprehensive output, which also reports the state of the cluster. Use the following curl command.

```
$ curl -XGET -k -H 'content-type: application/json; charset=UTF-8' -u "elastic:<password>" 'https://<elasticsearch hostname/IP>:9200/_cluster/health?pretty'
```

- **Process status**

If Elasticsearch is running as a `systemctl` service, use the following command to check the status of the service.

```
$ systemctl status pi-elasticsearch.service
```

- **Check Elasticsearch log for errors or exceptions**

Verify the Elasticsearch log for any exceptions or errors.

```
$ tail logs/elasticsearch.log
```

## Kibana

- **Health check URL**

There are two ways to check the health of Kibana using a health check URL

- Using anonymous access - To enable access, add the following line to the `kibana.yaml`.

```
status.allowAnonymous: true
```

You can update this during initial setup or later. You must restart Kibana if you are making the change on a running instance. After updating the `kibana.yaml` hit the following URL to check the status. You can use curl command or browser. A 200 OK response indicates a running Kibana instance.

```
https://<Kibana Hostname/IP>:5601/pi/ui/dashboard/api/status
```

```
$ curl -k -o /dev/null -s -w "%{http_code}\n" https://<Kibana Hostname/IP>:5601/pi/ui/dashboard/api/status
```

- Using health check user - Add a health check user to Kibana with the following command

```
curl -u elastic:<elastic user password> -k -X POST "https://localhost:9200/_xpack/security/user/<health_check_user>?pretty" -H 'Content-Type: application/json' -d '{
  "password" : "<password for health_check_user>",
  "roles": ["monitoring_user"]
}'
```

After adding the health check user, hit the following URL to check the status of Kibana. You can use curl command or browser. A 200 OK response indicates a running Kibana.

```
https://<health_check_user>:<password>@<Kibana hostname/IP>:5601/pi/ui/dashboard/api/status
```

```
$ curl -k -o /dev/null -s -w "%{http_code}\n" https://<health_check_user>:<password>@<Kibana hostname/IP>:5601/pi/ui/dashboard/api/status
```

- **Process Status**

If Kibana is running as a `systemctl` service, use to check the status of the service.

```
$ systemctl status pi-kibana.service
```

- **Check Kibana log for errors or exceptions**

Verify the Kibana log for any exceptions or errors.

```
$ tail logs/kibana.log
```

## Logs, port numbers, PIDs

This section covers supplementary information like log file details, important port numbers, and PID information of PingIntelligence for APIs components.

### Log files

The following table shows the main log files of PingIntelligence components.

ASE	ABS AI Engine	PingIntelligence Dashboard
<a href="#">ASE management, access and audit logs</a> on page 150	<p><a href="#">ABS logs</a> on page 326</p> <p><b>Note:</b> <code>abs.log</code> must be the first place for debugging any issues on the ABS. The log has information about each machine learning job on the host. All incoming communication from ASE or PingIntelligence Dashboard or REST API requests are logged in this file. It also has a periodic log on heartbeat to MongoDB.</p>	<ul style="list-style-type: none"> <li>Dashboard data engine : /pingidentity/ dashboard/logs/ dashboard.log</li> <li>WebGUI: /pingidentity/ webgui/logs/admin.log and /pingidentity/ webgui/logs/sso.log</li> <li>Elasticsearch: / pingidentity/ elasticsearch/logs/ elasticsearch.log</li> <li>Kibana: /pingidentity/ kibana/logs/kibana.log</li> </ul>

### Port numbers

The following table shows important port numbers used by PingIntelligence components.

ASE	ABS AI Engine	PingIntelligence Dashboard
<a href="#">ASE ports</a>	<a href="#">ABS ports</a> on page 318	<ul style="list-style-type: none"> <li>PingIntelligence Dashboard server: 8030. Port number 8030 should be exposed to public internet. Make sure that your organization's firewall allows access to this port.</li> <li>Elasticsearch: 9200</li> <li>Kibana: 5601</li> <li>H2 database: 9092. H2 database is installed and runs as a part of PingIntelligence Dashboard.</li> </ul>

### PID information

All the PingIntelligence components have their respective PID files. Refer these files for monitoring or for getting the PID information of the processes.

ASE	ABS AI Engine	PingIntelligence Dashboard
The ASE PID file contains the PID for the controller process and the http balancer and https balancer processes. /pingidentity/ase/logs/ase.pid	The /pingidentity/abs/data/abs.pid file contains the PID for the main ABS process.	There are separate PID files for the different components of PingIntelligence Dashboard. <ul style="list-style-type: none"> <li>• /pingidentity/dashboard/data/dashboard.pid</li> <li>• /pingidentity/webgui/logs/webgui.pid</li> <li>• /pingidentity/elasticsearch/logs/elasticsearch.pid</li> <li>• /pingidentity/kibana/logs/kibana.pid</li> </ul>

## PingIntelligence Troubleshooting Guide

Basic troubleshooting tips are provided here to help you overcome common difficulties with PingIntelligence.

### Troubleshooting issues between on-premise ASE and PingOne API Intelligence

This document discusses common error scenarios that you might encounter while working with on-premise ASE (API Security Enforcer) and PingOne API Intelligence. It also suggests the corrective steps for these issues.

ASE sends email alerts in the event of connectivity or authentication issues. You can verify the emails for preliminary error details.

#### Common error scenarios between on-premise ASE and PingOne

Problem	Solution
ASE is not starting after updating gateway credential in <code>abs.conf</code> file.	<p>Gateway credential is generated in PingOne. ASE parses gateway credentials and uses the information to connect with PingOne. Make sure the gateway credential is properly configured in the <code>abs.conf</code> file.</p> <p>Verify the <code>controller logs</code> located under /&lt;ASE installation&gt;/pingidentity/ase/logs/ directory.</p> <p>If the errors indicate incorrect gateway credential configuration, it is recommended to generate the gateway credentials from PingOne and reconfigure <code>abs.conf</code> file. For more information, see <a href="#">Generating a credential in PingOne</a>.</p>

Problem	Solution
PingOne is not authenticating ASE consistently.	<ol style="list-style-type: none"> <li>Run the <code>abs_info</code> CLI command and know the reason for failure. To do this: <ol style="list-style-type: none"> <li>Navigate to <code>/&lt;ASE install path&gt;/bin/</code> directory.</li> <li>Run the following command: <pre># /cli.sh -uadmin -padmin abs_info</pre> </li> </ol> </li> <li>If the failure is associated with gateway validation, it is recommended to regenerate the gateway credentials and reconfigure the <code>abs.conf</code> file. For more information, see <a href="#">Generating a credential in PingOne</a>. For other issues, contact Ping Identity support team.</li> </ol>
Experiencing constant slow log upload speeds.	ASE keeps a queue of logs to be uploaded to PingOne and uploads them on a first-come-first-serve basis. A slow upload or a blockage indicates connectivity issues. Verify your network for any disruptions. If the issue still persists, contact Ping Identity support team for resolution.

## PingIntelligence Upgrade Guide

The guide covers upgrading your PingIntelligence from version 4.4.1 to 5.0 and other third-party components like MongoDB, Elasticsearch, and Kibana.

### Prerequisites

Complete the following prerequisites before proceeding with upgrade:

- Download PingIntelligence for APIs 5.0 binaries from [Ping download site](#).
- Access to PingIntelligence for APIs upgrade package - `pi-api-upgrade-5.0.tar.gz`. Contact Ping Identity Sales team for the latest upgrade script package.
- Host machine with RHEL 7.9 or Ubuntu 18.04 LTS. PingIntelligence 5.0 supports RHEL 7.9 or Ubuntu 18.04 LTS operating systems.
- OpenJDK 11.0.2 to OpenJDK 11.0.6.
- Set `JAVA_HOME` by adding the following command in `~/ .bashrc` file.

```
export JAVA_HOME="/a/b/java"
```

- Disable ABS on all ASE nodes by entering the following command on ASE nodes.

```
./cli.sh -u admin -p admin disable_abs
```

- To minimize the impact to live traffic, stop ASE.

**Note:** Upgrade will be done in-place for all the components. The process will need components to be taken out of live traffic processing till the upgrade is completed.



### Common upgrade steps

- Extract the PingIntelligence for APIs upgrade package `pi-api-upgrade-5.0.tar.gz` into a temporary directory on the host machine that has either ASE or ABS AI Engine or PingIntelligence Dashboard installed.

```
# mkdir ~/pi-tmp
# cp pi-api-upgrade-5.0.tar.gz ~/pi-tmp/
# cd ~/pi-tmp/
# tar -xvf pi-api-upgrade-5.0.tar.gz
```

The following image shows the directory structure.

```
pingidentity/
├── __upgrade
│   ├── __ase
│   │   ├── __ase-upgrade.sh
│   │   └── __abs
│   │       ├── __abs-upgrade.sh
│   │       ├── __dashboard
│   │       ├── __bin
│   │       │   ├── __upgrade.sh
│   │       │   ├── __config
│   │       │   └── __upgrade.properties
│   │       └── __lib
│   └── __mongo
│       └── __mongo-upgrade.sh
└── __version.txt
```

**Note:** You can copy the upgrade package onto the host machine using utilities like SCP, rsync, SFTP, or curl.

- Upgrade the components in the following order
  - [Step-1 Upgrading MongoDB](#) on page 785
  - [Step-2 Upgrading ABS AI Engine](#) on page 787
  - [Step-3 Upgrading PingIntelligence Dashboard](#) on page 788
  - [Step-4 Upgrading ASE](#) on page 793

**Note:** The upgrade scripts should be run from a user who has read, write, and execute permissions in the installation directories.

## Step-1 Upgrading MongoDB

This section discusses the steps to upgrade the MongoDB.

Before you begin

Make sure the following prerequisites are met:

- All the MongoDB nodes in the replica set must be online and reachable.
- It is recommended to retain only 10-days of data in order to facilitate fast upgrade process.
- MongoDB binary must be added to the PATH variable.

```
export PATH=$PATH:<path to mongo binary>
```

- All ABS instances connected to this replica set must be stopped and there should be no reads or writes occurring during the upgrade.
- Extract the upgrade scripts from the PingIntelligence upgrade package as explained in [Common upgrade tasks section](#).

### About this task

Complete the following steps to upgrade MongoDB:

### Steps

1. Navigate to `~/pi-tmp/pingidentity/upgrade/mongo/` and copy the `mongo-upgrade.sh` script and place it in MongoDB Primary node.

```
# cd ~/pi-tmp/pingidentity/upgrade/mongo/
# cp mongo-upgrade.sh /<ABS 4.4.1 installation path>/pingidentity/mongo/
util/
```

2. Stop ABS on all nodes by entering the following command.

```
# /<ABS installation path>/pingidentity/abs/bin/stop.sh
```

For example:

```
# /home/pi-user/pingidentity/abs/bin/stop.sh
```

If ABS is running as a service, then run the following command.

```
# systemctl stop pi-abs.service
```

3. Navigate to the `/<ABS 4.4.1 installation path>/pingidentity/mongo/util/` directory and run the mongo upgrade script.

```
# ./mongo-upgrade.sh -u <abs-mongo-user> -p <abs-mongo-password>
```

For example:

```
# ./mongo-upgrade.sh -u absuser -p absxxx --port 27017
please make sure that there is no ABS process running before running the
mongo-upgrade script.
are you sure you want to continue? (yes/no): yes
progress will be logged in ./pi-abs-upgrade/mongo-upgrade.log
```

**i Important:** The `mongo-upgrade.sh` script must be executed only on the MongoDB Primary node. If the upgrade process fails due to any reason, compress the `pi-abs-upgrade` directory and send it to Ping Identity support for troubleshooting.

4. Verify the indexes created on MongoDB collections to make sure the upgrade is successful. For more information, see [Verifying MongoDB indexes](#) on page 794.

### Next steps

Proceed to [Step-2 Upgrading ABS AI Engine](#) on page 787.

**i Important:** Only after successful upgrade of MongoDB, proceed with ABS upgrade.

## Step-2 Upgrading ABS AI Engine

This section discusses the steps to upgrade ABS 4.4.1 to 5.0

Before you begin

- Extract the upgrade scripts from the PingIntelligence upgrade package as explained in [Common upgrade tasks section](#)

About this task

Complete the following steps on all the ABS nodes in a cluster.

Steps

1. Download the ABS 5.0 binary. Copy the binary to a temporary directory and extract it.

```
# cp pi-api-abs-5.0.tar.gz ~/pi-tmp/
# cd ~/pi-tmp/
# tar -xvf pi-api-abs-5.0.tar.gz
```

2. Navigate to `~/pi-tmp/pingidentity/upgrade/abs/` and copy the ABS upgrade script to the `~/pi-tmp/pingidentity/abs/util/` directory in the temporary directory.

```
# cd ~/pi-tmp/pingidentity/upgrade/abs/
# cp abs-upgrade.sh ~/pi-tmp/pingidentity/abs/util
```

3. Navigate to `~/pi-tmp/pingidentity/abs/util/` directory and run the upgrade script.

**i Attention:** : Only after successful upgrade of MongoDB, proceed with ABS upgrade.

```
# cd ~/pi-tmp/pingidentity/abs/util/
# ./abs-upgrade.sh <ABS 4.4.1 installation path>
```

For example:

```
# ./abs-upgrade.sh /home/pi-user/pingidentity/abs
Upgrading ABS to version 5.0
are you sure you want to continue? (yes/no): yes
making the configuration changes and copying new binaries
configuration for smtp_ssl field is already configured
configuration for mongo_ssl field is already configured
configuration for mongo_auth_mechanism field is already configured
upgrade to ABS 5.0 is successful
please start ABS using: /home/pi-user/pingidentity/abs//bin/start.sh
if systemctl service present, run command: systemctl restart pi-
abs.service
```

4. Verify that the upgrade was successful by entering the following command.

```
# cat /<ABS installation path>/pingidentity/abs/version.txt
```

For eexample:

```
# cat /home/pi-user/pingidentity/abs/version.txt
```

5. Update the license file in `/pingidentity/abs/config` directory to the new PingIntelligence 5.0 license file.

## 6. Start all ABS nodes.

**Note:** Start the ABS nodes only after completing the MongoDB upgrade as detailed in [Step-1 Upgrading MongoDB](#) on page 785.

```
# /<ABS installation path>/pingidentity/abs/bin/start.sh
```

For example:

```
# /home/pi-user/pingidentity/abs/bin/start.sh
```

If ABS is running as a service, then run the following command.

```
# systemctl start pi-abs.service
```

Next steps

Proceed to [Step-3 Upgrading PingIntelligence Dashboard](#) on page 788.

## Step-3 Upgrading PingIntelligence Dashboard

---

Before you begin

Extract the upgrade scripts from the PingIntelligence upgrade package as explained in [Common upgrade tasks section](#)

About this task

Complete the following steps to upgrade PingIntelligence for APIs Dashboard from version 4.4.1 to 5.0:

Steps

1. Download the PingIntelligence Dashboard for APIs 5.0 binary. Copy the binary to a temporary directory and extract it.

```
# cp pi-api-dashboard-5.0.tar.gz ~/pi-tmp/
# cd ~/pi-tmp/
# tar -xvf pi-api-dashboard-5.0.tar.gz
```

2. Change the following variables in the `upgrade.properties` config file available in the `~/pi-tmp/pingidentity/upgrade/dashboard/config/` directory.

**Note:** If Elasticsearch component is running on AWS, then make sure the value of Elasticsearch distribution type is set to `aws` in both `WebGUI.properties` and `dashboard.properties`. For more information see, [Configure WebGUI properties - webgui.properties](#) on page 479 and [Configure Dashboard properties - dashboard.properties](#) on page 476.

- When Elasticsearch component is on the same host.

```
source.dashboard.dir=<dashboard installation path for 4.4.1>
upgrade.dashboard.binary=<path of 5.0 binary>
```

For example:

```
# vim ~/pi-tmp/pingidentity/upgrade/dashboard/config/
dashboard.properties
```

```
source.dashboard.dir= /home/pi-user/pingidentity/
upgrade.dashboard.binary= ~/pi-tmp/pi-api-dashboard-5.0.tar.gz
.
.
```

**Note:** When the Elasticsearch component is on a remote host, set the value of `upgrade.elasticsearch.url` with the Elasticsearch URL on the remote host. If the Elasticsearch component is on the same host as PingIntelligence Dashboard, do not populate it.

- When Elasticsearch component is on a remote host.

```
source.dashboard.dir=<dashboard installation path for 4.4.1>
upgrade.dashboard.binary=<path of 5.0 binary>
upgrade.elasticsearch.url= <remote ES URL>
upgrade.elasticsearch.username= <elasticsearch username>
```

For example:

```
# vim ~/pi-tmp/pingidentity/upgrade/dashboard/config/
dashboard.properties
source.dashboard.dir= /home/pi-user/pingidentity/
upgrade.dashboard.binary= ~/pi-tmp/pi-api-dashboard-5.0.tar.gz
upgrade.elasticsearch.url= https://255.255.255.255:9200/
upgrade.elasticsearch.username= changeme
```

**Note:** Do not set the value of `upgrade.elasticsearch.username`, if Elasticsearch on the remote host doesn't support authentication. If authentication is supported, then enter the password for Elasticsearch when prompted at the terminal of the remote host.

### 3. Stop all the 4.4.1 components in the following order:

- Stop WebGUI by entering the following command.

```
# /<PI Dashboard installation path>/pingidentity/webgui/bin/stop.sh
```

For example

```
# /home/pi-user/pingidentity/webgui/bin/stop.sh
```

If WebGUI is running as a service, then run the following command.

```
# systemctl stop pi-webgui.service
```

- Stop Dashboard data engine by entering the following command.

```
# /<PI Dashboard installation path>/pingidentity/dashboard/bin/stop.sh
```

For example

```
# /home/pi-user/pingidentity/dashboard/bin/stop.sh
```

If Dashboard data engine is running as a service, then run the following command.

```
# Systemctl stop pi-dashboard.service
```

- Stop Kibana by entering the following commands

```
# kill -15 `ps -ef | grep node | grep cli | grep -v grep | awk '{print $2}'`
```

If Kibana is running as a service, then run the following command.

```
# Systemctl stop pi-kibana.service
```

- Stop Elasticsearch by entering the following commands.

```
# kill -15 `ps -ef | grep elasticsearch| grep java| grep -v grep | awk '{print $2}'`
```

If Elasticsearch is running as a service then use the following command.

```
# Systemctl stop pi-elasticsearch.service
```

**Note:** Ignore the step if Elasticsearch is hosted on a remote machine.

### 4. After the components are stopped, back up the listed directories using following commands:

- WebGUI

```
# mkdir ~/pi-tmp/webgui_bkup
# cd ~/pi-tmp/webgui_bkup
# cp -R ~/pingidentity/webgui/config ~/pi-tmp/webgui_bkup
# cp -R ~/pingidentity/webgui/data ~/pi-tmp/webgui_bkup
# cp -R ~/pingidentity/webgui/logs ~/pi-tmp/webgui_bkup
```

- Dashboard data engine

```
# mkdir ~/pi-tmp/dashboard_bkup
```

```
# cd ~/pi-tmp/dashboard_bkup
# cp -R ~/pingidentity/dashboard/config ~/pi-tmp/dashboard_bkup
# cp -R ~/pingidentity/dashboard/logs ~/pi-tmp/dashboard_bkup
```

- Kibana

```
# mkdir ~/pi-tmp/kibana_bkup
# cd ~/pi-tmp/kibana_bkup
# cp -R ~/pingidentity/kibana/config ~/pi-tmp/kibana_bkup
```

- Elasticsearch

```
# mkdir ~/pi-tmp/elasticsearch_bkup
# cd ~/pi-tmp/elasticsearch_bkup
# cp -R ~/pingidentity/elasticsearch/config ~/pi-tmp/elasticsearch_bkup
# cp -R ~/pingidentity/elasticsearch/data ~/pi-tmp/elasticsearch_bkup
```

5. Navigate to `~/pi-tmp/pingidentity/upgrade/dashboard/bin` and execute the `upgrade.sh` script.

```
# cd ~/pi-tmp/pingidentity/upgrade/dashboard/bin
# ./upgrade.sh
```

6. Verify that the upgrade was successful by entering the following command.

```
# cat /<PingIntelligence Dashboard installation path>/pingidentity/
dashboard/version.txt

# cat /<PingIntelligence Dashboard installation path>/pingidentity/webgui/
version.txt
```

For example

```
# cat /home/pi-user/pingidentity/dashboard/version.txt
# cat /home/pi-user/pingidentity/webgui/version.txt
```

**Note:** The `upgrade.sh` script upgrades all the Dashboard components along with data and configuration parameters.

7. Start the dashboard components in the following order:

- Start Elasticsearch by executing the following command

```
#!/bin/elasticsearch -d -p logs/elasticsearch.pid
```

Run the following command to verify the status.

```
# curl -XGET -k https://127.0.0.1:9200/_cluster/health?pretty -u
elastic:<elastic password>
```

**Note:** Ignore the step if Elasticsearch is hosted on a remote machine.

- Start the Dashboard data engine by executing the following commands.

```
# /<PI Dashboard installation path>/pingidentity/dashboard/bin/start.sh
```

For example

```
# cd /home/pi-user/pingidentity/dashboard
```

```
# ./bin/start.sh
```

If Dashboard data engine, is running as a service, then run the following command

```
# systemctl start pi-dashboard.service
```

To verify the successful start of dashboard service run the following command.

```
# ls -al data/dashboard.touch
```

- Start Kibana.

```
# cd /home/pi-user/pingidentity/kibana
# ./bin/kibana > logs/kibana.log 2>&1 &
```

If Kibana is running as a service, then

```
# Systemctl start pi-kibana.service
```

- Start WebGUI

```
# /<PI Dashboard installation path>/pingidentity/webgui/bin/start.sh
```

For example

```
# cd ../webgui/
# ./bin/start.sh
# https://<ip>:8030/
```

If WebGUI is running as a service, then run the following command

```
# systemctl start pi-webgui.service
```

If the upgrade process fails due to timeout or any other reason halt the ongoing process, restore the backups, and restart the process by completing the following steps:

1. Stop the dashboard components as explained in step-3.
2. Restore the backed up files into the component directories.

**i Important:** Delete any existing residual data before restoring the backed up Elasticsearch data.

```
# cd /home/pi-user/pingidentity/elasticsearch
# rm -rf data/*
# cp ~/pi-tmp/elasticsearch_bkup/data/* data/
```

3. Resume the upgrade process from step-5.

**i Note:** It is recommended to not populate the `pi.webgui.ase.url` parameter in the `WebGUI.properties` file, if ASE is not reachable from WebGUI. For more information, see [Configure WebGUI properties - webgui.properties](#) on page 479.

Next steps

Proceed to [Step-4 Upgrading ASE](#) on page 793



## Step-4 Upgrading ASE

Complete the following steps on all the ASE nodes in a cluster to upgrade to upgrade ASE 4.4.1 to 5.0.

Before you begin

- Extract the upgrade scripts from the PingIntelligence upgrade package as explained in [Common upgrade tasks section](#)
- Run the following command and stop ASE.

```
# /<ASE installation path>/pingidentity/ase/bin/stop.sh -u <username> -p
<password>
```

For example:

```
# /home/pi-user/pingidentity/ase/bin/stop.sh -u admin -p pswd
```

If ASE is running as a service, then run the following command.

```
# systemctl stop pi-ase.service
```

- Make sure all the access logs are uploaded. Navigate to /<ASE 4.4.1 installation path>/pingidentity/ase/log and run the following command.

```
$ ls -lrt | sed -r "s/(.+\.s+\.+\.s+\.+\.s+0\s+.)//g" | grep "http\|
decoy"
```

About this task

Complete the following steps on all the ASE nodes in a cluster to upgrade to upgrade ASE 4.4.1 to 5.0.

Steps

1. Download the ASE 5.0 binary. Copy the binary to a temporary directory and extract it.

```
# cp pi-api-ase-rhel-5.0.tar.gz ~/pi-tmp/
# cd ~/pi-tmp/
# tar -xvf pi-api-ase-rhel-5.0.tar.gz
```

2. Navigate to ~/pi-tmp/pingidentity/upgrade/ase/ and copy the ASE upgrade script to the ~/pi-tmp/pingidentity/ase/util/ directory in the temporary directory.

```
# cd ~/pi-tmp/pingidentity/upgrade/ase/
# cp ase-upgrade.sh ~/pi-tmp/pingidentity/ase/util/
```

3. Navigate to the /<ASE 4.4.1 installation path>/pingidentity/ase/config/ directory, and remove the existing ASE license from the directory.
4. Copy the new PingIntelligence 5.0 license into /<ASE 4.4.1 installation path>/pingidentity/ase/config/ directory.
5. Navigate to the ~/pi-tmp/pingidentity/ase/util/ directory and run the upgrade script.

```
# cd ~/pi-tmp/pingidentity/ase/util/
# ./ase-upgrade.sh <ASE 4.4.1 installation path>
```

For example:

```
# ./ase-upgrade.sh /home/pi-user/pingidentity/ase
```

```
4.4.1 is not running
Copying new binaries for ASE 5.0
Upgrade to ASE 5.0 is successful
Please start ASE using: /home/pi-user/pingidentity/ase/bin/start.sh
If systemctl service present, run command: systemctl restart pi-
ase.service
.
.
```

**Note:** The `ase-upgrade.sh` script upgrades the Balancer and Controller binaries in ASE.

6. Run the following command and verify the successful upgrade of the ASE node.

```
# /<ASE installation path>/pingidentity/ase/bin/cli.sh version
```

For example:

```
# /home/pi-user/pingidentity/ase/bin/cli.sh version
```

7. Start ASE nodes in a cluster setup one after the other.

```
# /<ASE installation path>/pingidentity/ase/bin/start.sh
```

For example:

```
# /home/pi-user/pingidentity/ase/bin/start.sh
```

If ASE is running as a service, then run the following command.

```
# systemctl start pi-ase.service
```

8. Run the following command to check the status and verify the successful start of ASE node.

```
# /<ASE installation path>/pingidentity/ase/bin/cli.sh status
```

For example.

```
# /home/pi-user/pingidentity/ase/bin/cli.sh status
```

Next steps

Enter the following command and enable ABS on ASE node.

```
# pingidentity/ase/bin/cli.sh -u admin -p <password> enable_abs
```

## Verifying MongoDB indexes

This section discusses the checks you can perform on MongoDB collections to verify a successful upgrade.

About this task

To check successful creation of indexes on the primary and the secondary MongoDB nodes, run the following commands.

## Steps

1. Run the following command to verify indexes on `real_time_ioc` collection. The command lists out three indexes as shown in the example.

```
mongo --quiet -u <abs-mongo-user> -p <abs-mongo-password>
--authenticationDatabase=admin <IP address>:27017/abs_data --eval
'db.real_time_ioc.getIndexes()' | grep name
```

For example :

```
mongo --quiet -u admin -p abs-mongo-password
--authenticationDatabase=admin 127.1.1.1:27017/abs_data --eval
'db.real_time_ioc.getIndexes()' | grep name
"name" : "_id_",
"name" : "start_date_1_end_date_1","api_name" : 1
"name" : "session_id_1_api_name_1",
```

2. Run the following command to verify indexes on `log_nodes` collection. The command lists out two indexes as shown in the example.

```
mongo --quiet -u <abs-mongo-user> -p <abs-mongo-password>
--authenticationDatabase=admin <IP address>:27017/abs_data --eval
'db.log_nodes.getIndexes()' | grep name
```

For example:

```
mongo --quiet -u admin -p abs-mongo-password
--authenticationDatabase=admin 127.1.1.1:27017/abs_mldata --eval
'db.log_nodes.getIndexes()' | grep name
"name" : "_id_",
"name" : "logs.log_ids.id_1",
```

# PingIntelligence Usecases

---

## Converting SSL certificates to ASE compatible format

---

About this task

This topic discusses the commands involved in converting your SSL (Secure Sockets Layer) certificates to make them compatible with ASE's (API Security Enforcer) SSL certificate format. When PingIntelligence for APIs is deployed in sideband mode, ensure that the SSL certificates used by the gateway in `.pem` format. You can use OpenSSL for converting the certificates.

**Converting a `.crt` extension to `.pem` extension** -Complete the following steps to convert your SSL certificate from `.crt` extension to `.pem` extension.

## Steps

1. Run the following command to get ASE certificate details.

```
# openssl s_client -showcerts -connect <ASE-IP>:<SSL-PORT>
```

For example

```
openssl s_client -showcerts -connect 127.1.1.1:8443
```

2. Create a temporary certificate file `ase.crt` using the contents of ASE certificate.

① **Note:** Make sure to include the content starting from "-----BEGIN CERTIFICATE-----" to "-----END CERTIFICATE-----" in the temporary `ase.crt` file.

3. Run the following command to convert the `ase.crt` certificate into `.pem` file.

```
# openssl x509 -in ase.crt -out ase.pem
```