

# PingFederate Server



# Contents

|   |           |
|---|-----------|
| <b>PingFederate.....</b>                                | <b>9</b>  |
| <b>Release Notes.....</b>                               | <b>9</b>  |
| PingFederate 11.1.10 (April 2024).....                  | 10        |
| PingFederate 11.1.9 (November 30).....                  | 10        |
| PingFederate 11.1.8 (August 2023).....                  | 10        |
| PingFederate 11.1.7 (May 2023).....                     | 11        |
| PingFederate 11.1.6 (February 2023).....                | 11        |
| PingFederate 11.1.5 (February 2023).....                | 11        |
| PingFederate 11.1.4 (February 2023).....                | 11        |
| PingFederate 11.1.3 (December 2022).....                | 12        |
| PingFederate 11.1.2 (October 2022).....                 | 12        |
| PingFederate 11.1.1 (July 2022).....                    | 13        |
| PingFederate 11.1 (June 2022).....                      | 14        |
| PingFederate 11.0.8 (August 2023).....                  | 21        |
| PingFederate 11.0.7 (February 2023).....                | 22        |
| PingFederate 11.0.6 (February 2023).....                | 22        |
| PingFederate 11.0.5 (October 2022).....                 | 22        |
| PingFederate 11.0.4 (August 2022).....                  | 22        |
| PingFederate 11.0.3 (May 2022).....                     | 23        |
| PingFederate 11.0.2 (March 2022).....                   | 23        |
| PingFederate 11.0.1 (January 2022).....                 | 23        |
| PingFederate 11.0 (December 2021).....                  | 24        |
| Previous releases.....                                  | 32        |
| <b>Introduction to PingFederate.....</b>                | <b>33</b> |
| About identity federation and SSO.....                  | 33        |
| Service providers and identity providers.....           | 33        |
| Federation hub.....                                     | 34        |
| Supported standards.....                                | 34        |
| Federation roles.....                                   | 35        |
| Terminology.....  | 35        |
| Browser-based SSO.....                                  | 37        |
| Web services standards.....                             | 53        |
| OAuth 2.0.....  | 55        |
| System for Cross-domain Identity Management (SCIM)..... | 64        |
| Transport and message security.....                     | 65        |
| Integration overview.....                               | 65        |
| Bundled adapters and authenticators.....                | 65        |
| Additional integrations.....                            | 68        |
| SSO integration concepts.....                           | 70        |
| Identity provider integration.....                      | 70        |
| Service provider integration.....                       | 72        |
| Security token service.....                             | 74        |
| OAuth authorization server.....                         | 75        |
| User account management.....                            | 76        |
| Enterprise deployment features.....                     | 76        |

|  |            |
|--|------------|
| Additional features.....   | 77         |
| Key concepts.....  | 78         |
| WS-Trust STS.....  | 80         |
| About OAuth.....   | 83         |
| Bundled adapters and authenticators.....                         | 92         |
| Security infrastructure.....                                     | 95         |
| Hierarchical plugin configurations.....                          | 99         |
| Identity mapping.....  | 100        |
| User attributes.....   | 101        |
| User provisioning.....   | 106        |
| Customer identity and access management.....                     | 108        |
| Federation hub use cases.....                                    | 108        |
| Federation planning checklist.....                               | 113        |
| <b>Installing and uninstalling PingFederate.....</b>             | <b>117</b> |
| System requirements.....   | 119        |
| Compatible database drivers.....                                 | 124        |
| Port requirements.....   | 125        |
| Installing Java.....   | 129        |
| Installing PingFederate 11.1.....                                | 130        |
| Installing PingFederate on Linux systems.....                    | 130        |
| Installing the PingFederate service on Linux manually.....       | 131        |
| Installing PingFederate on Windows.....                          | 134        |
| Installing the PingFederate service on Windows manually.....     | 135        |
| Uninstalling PingFederate.....                                   | 136        |
| Uninstalling PingFederate from a Windows server.....             | 136        |
| Uninstalling PingFederate from a Linux server.....               | 137        |
| <b>Upgrading PingFederate.....</b>                               | <b>138</b> |
| Downloading PingFederate.....                                    | 139        |
| Preparing to upgrade PingFederate.....                           | 139        |
| Upgrade considerations.....                                      | 140        |
| Upgrade considerations introduced in PingFederate 10.x.....      | 144        |
| Upgrade considerations introduced in PingFederate 9.x.....       | 146        |
| Upgrade considerations introduced in PingFederate 8.x.....       | 147        |
| Upgrade considerations introduced in PingFederate 7.x.....       | 149        |
| Upgrade considerations introduced in PingFederate 6.x.....       | 151        |
| Upgrading PingFederate installations.....                        | 152        |
| Upgrading PingFederate on Linux systems.....                     | 152        |
| Upgrading PingFederate on Windows using the Upgrade Utility..... | 155        |
| Upgrading PingFederate on Windows using the installer.....       | 157        |
| Custom mode in the Upgrade Utility.....                          | 158        |
| Post-upgrade tasks.....  | 158        |
| Reviewing administrative users.....                              | 159        |
| Copying customized files or settings.....                        | 159        |
| Reviewing database changes.....                                  | 162        |
| Logging configurations.....                                      | 164        |
| Migrating other components.....                                  | 164        |
| Resetting files and variable for HSM.....                        | 166        |
| Verifying the new installation.....                              | 166        |
| Updating to the latest maintenance release.....                  | 167        |
| <b>Getting Started with PingFederate.....</b>                    | <b>168</b> |

|   |            |
|---|------------|
| Starting and stopping PingFederate.....                 | 168        |
| Starting and stopping PingFederate on Windows.....      | 168        |
| Starting and stopping PingFederate on Linux.....        | 169        |
| Opening the PingFederate administrative console.....    | 170        |
| Setting up PingFederate.....                            | 170        |
| PingFederate administrative console.....                | 171        |
| Navigation tabs and menus.....                          | 172        |
| Customizing shortcuts.....                              | 175        |
| Tasks and steps.....                                    | 175        |
| Console buttons.....                                    | 176        |
| Third-party cryptographic solutions.....                | 177        |
| Supported hardware security modules.....                | 177        |
| Supported software security package.....                | 187        |
| <br>  |            |
| <b>Server Clustering Guide.....</b>                     | <b>189</b> |
| Overview of clustering.....                             | 189        |
| Cluster protocol architecture.....                      | 191        |
| Runtime state-management architectures.....             | 192        |
| Adaptive clustering.....                                | 192        |
| Directed clustering.....                                | 196        |
| Runtime state-management services.....                  | 201        |
| Inter-Request State-Management (IRSM) Service.....      | 202        |
| IdP Session Registry Service.....                       | 203        |
| SP Session Registry Service.....                        | 203        |
| LRU memory management schemes.....                      | 204        |
| Assertion Replay Prevention Service.....                | 204        |
| Artifact-Message Persistence and Retrieval Service..... | 205        |
| Back-Channel Session Revocation Service.....            | 206        |
| Account Locking Service.....                            | 207        |
| Other services.....                                     | 207        |
| Deploying cluster servers.....                          | 208        |
| Dynamic cluster discovery.....                          | 214        |
| Deploying provisioning failover.....                    | 221        |
| Configuration synchronization.....                      | 223        |
| Console configuration push.....                         | 223        |
| Configuration-archive deployment.....                   | 223        |
| <br>  |            |
| <b>Administrator's Reference Guide.....</b>             | <b>224</b> |
| Attribute mapping expressions.....                      | 225        |
| Enabling and disabling expressions.....                 | 225        |
| Construct OGNL expressions.....                         | 226        |
| Using the OGNL edit window.....                         | 230        |
| Authentication policies.....                            | 231        |
| Selectors.....  | 233        |
| Policies.....   | 251        |
| Policy fragments.....                                   | 285        |
| Policy contracts.....                                   | 286        |
| Adapter Mappings.....                                   | 289        |
| Sessions.....   | 292        |
| Bundled adapters.....                                   | 299        |
| Composite Adapter.....                                  | 300        |
| HTML Form Adapter.....                                  | 305        |
| HTTP Basic Adapter.....                                 | 325        |
| Identifier First Adapter.....                           | 328        |

|   |     |
|---|-----|
| Kerberos Adapter.....   | 335 |
| OpenToken Adapter.....  | 342 |
| Configuring a Passthrough IdP Adapter.....                        | 350 |
| Configuring a Reference ID Adapter.....                           | 351 |
| Configuring an X.509 Certificate IdP Adapter.....                 | 354 |
| Customer IAM configuration.....                                   | 357 |
| Setting up PingDirectory for customer identities.....             | 357 |
| Managing local identity profiles.....                             | 359 |
| Configuring local identity profiles.....                          | 359 |
| Configuring the HTML Form Adapter for customer identities.....    | 370 |
| Setting up self-service registration.....                         | 371 |
| Enabling third-party identity providers without registration..... | 387 |
| Customizing assertions and authentication requests.....           | 390 |
| Message types and available variables.....                        | 391 |
| Sample customizations.....  | 394 |
| Fulfillment by datastore queries.....                             | 397 |
| Attribute mapping with multiple data sources.....                 | 397 |
| Datastore query configuration.....                                | 398 |
| IdP-to-SP bridging.....   | 408 |
| Adapter-to-adapter mappings.....                                  | 408 |
| Token translator mappings.....                                    | 414 |
| Identity provider SSO configuration.....                          | 419 |
| IdP application integration settings.....                         | 420 |
| IdP protocol endpoints.....                                       | 437 |
| SP connection management.....                                     | 440 |
| SP affiliations.....  | 515 |
| OAuth configuration.....  | 518 |
| Configuring OAuth use cases.....                                  | 518 |
| Configuring authorization server settings.....                    | 519 |
| Scopes and scope management.....                                  | 531 |
| Adding virtual issuers for OpenID Connect.....                    | 542 |
| Configuring client settings.....                                  | 542 |
| Managing Client Registration Policy instances.....                | 563 |
| Managing OAuth clients.....                                       | 565 |
| Grant contract mapping.....                                       | 582 |
| Token mapping.....  | 603 |
| Client Initiated Backchannel Authentication (CIBA).....           | 635 |
| OAuth attribute mapping using a datastore.....                    | 649 |
| OAuth client session management.....                              | 650 |
| OAuth token exchange.....   | 651 |
| Security management.....  | 656 |
| Certificate and key management.....                               | 657 |
| System integration.....   | 693 |
| Account lockout protection.....                                   | 699 |
| Password spraying prevention.....                                 | 700 |
| Implementing a MasterKeyEncryptor using AWS KMS.....              | 701 |
| Self-service user account management.....                         | 703 |
| Configuring self-service password management.....                 | 703 |
| Configuring self-service account recovery.....                    | 705 |
| Configuring self-service user name recovery.....                  | 711 |
| Service provider SSO configuration.....                           | 712 |
| SP application integration settings.....                          | 712 |
| Federation settings.....  | 720 |
| Managing IdP connections.....                                     | 724 |
| OpenID Connect Relying Party support.....                         | 805 |
| Configuring IdP discovery using a persistent cookie.....          | 819 |

|   |             |
|---|-------------|
| System administration.....  | 820         |
| Configuring PingFederate properties.....  | 820         |
| Configuring size limits.....  | 825         |
| PingFederate log files.....   | 828         |
| Alternative console authentication.....   | 848         |
| Configuring automatic connection validation.....                                | 860         |
| Automating configuration migration.....   | 861         |
| Outbound provisioning CLI.....  | 866         |
| Customizable user-facing pages.....   | 869         |
| Customizable email notifications.....   | 882         |
| Customizable text message.....  | 889         |
| Localizing messages for end users.....  | 889         |
| Configuring a password policy.....  | 891         |
| Managing cipher suites.....   | 892         |
| Manage externally stored authentication sessions.....                           | 893         |
| OAuth persistent grants cleanup.....  | 898         |
| Specifying the domain of the PF cookie.....                                     | 903         |
| Specifying the domain of the PF.PERSISTENT cookie.....                          | 903         |
| Extending the lifetime of the PingFederate cookie.....                          | 904         |
| Configuring forward proxy server settings.....                                  | 905         |
| Adding custom HTTP response headers.....  | 905         |
| Configuring validation for the AudienceRestriction element.....                 | 906         |
| Customizing the OpenID Provider configuration endpoint response.....            | 906         |
| Customizing the heartbeat message.....  | 907         |
| Customizing the favicon for application and protocol endpoints.....             | 908         |
| Configuring the behavior of searching multiple datastores with one mapping..... | 908         |
| System settings.....  | 909         |
| Server.....   | 909         |
| Metadata.....   | 930         |
| Monitoring and notifications.....   | 935         |
| Datastores.....   | 936         |
| Password Credential Validators.....   | 980         |
| Active Directory and Kerberos.....  | 992         |
| External systems.....   | 997         |
| Configuring general settings.....   | 1023        |
| Troubleshooting.....  | 1024        |
| Enabling debug messages and console logging.....                                | 1024        |
| Resolving startup issues.....   | 1027        |
| Troubleshooting data store issues.....  | 1027        |
| Resolving URL-related errors.....   | 1027        |
| Resolving service-related errors.....   | 1028        |
| Troubleshooting authentication policy issues.....                               | 1029        |
| Troubleshooting registration and profile management issues.....                 | 1031        |
| Troubleshooting runtime errors.....   | 1031        |
| Troubleshooting OAuth transactions.....   | 1035        |
| Other runtime issues.....   | 1039        |
| Collecting support data.....  | 1040        |
| WS-Trust STS configuration.....   | 1041        |
| Server settings.....  | 1041        |
| Identity provider STS configuration.....  | 1043        |
| Service provider STS configuration.....   | 1066        |
| <b>Performance Tuning Guide.....</b>  | <b>1079</b> |
| Logging.....  | 1079        |
| Operating system tuning.....  | 1080        |

|   |             |
|---|-------------|
| Linux tuning.....   | 1080        |
| Windows tuning.....   | 1081        |
| Concurrency.....  | 1082        |
| Tuning the acceptor queue size.....                               | 1082        |
| Tuning the server thread pool.....                                | 1083        |
| Configuring connection pools to datastores.....                   | 1084        |
| Snapshot isolation for high-volume transactions.....              | 1085        |
| Memory.....   | 1085        |
| JVM heap.....   | 1085        |
| Garbage collectors.....   | 1086        |
| Young generation bias.....  | 1087        |
| The memoryoptions utility.....                                    | 1088        |
| Hardware security modules.....                                    | 1096        |
| Configuration at scale.....                                       | 1096        |
| References.....   | 1096        |
| <br>  |             |
| <b>PingFederate Monitoring Guide.....</b>                         | <b>1096</b> |
| Resource metrics.....   | 1097        |
| Runtime monitoring using JMX.....                                 | 1097        |
| Connecting with JMX.....  | 1099        |
| Liveliness and responsiveness.....                                | 1100        |
| Monitoring.....   | 1104        |
| Thread pool.....  | 1109        |
| Logging, reporting, and troubleshooting.....                      | 1110        |
| Creating an error-only server log.....                            | 1111        |
| Splunk dashboards and audit logs.....                             | 1112        |
| <br>  |             |
| <b>SDK Developer's Guide.....</b>                                 | <b>1115</b> |
| SDK directory structure.....                                      | 1117        |
| Developing your own plugin.....                                   | 1117        |
| Implementation guidelines.....                                    | 1118        |
| Shared plugin interfaces.....                                     | 1119        |
| Developing IdP adapters.....                                      | 1120        |
| Developing authentication API-capable adapters and selectors..... | 1123        |
| Developing SP adapters.....                                       | 1132        |
| Developing token processors.....                                  | 1133        |
| Developing token generators.....                                  | 1134        |
| Developing authentication selectors.....                          | 1134        |
| Developing data source connectors.....                            | 1135        |
| Developing password credential validators.....                    | 1137        |
| Developing identity store provisioners.....                       | 1137        |
| Developing notification publishers.....                           | 1143        |
| Building and deploying with Ant.....                              | 1144        |
| Building and deploying manually.....                              | 1145        |
| Log messages.....   | 1146        |
| <br>  |             |
| <b>Developer's Reference Guide.....</b>                           | <b>1146</b> |
| OAuth 2.0 endpoints.....  | 1146        |
| Authorization endpoint.....                                       | 1147        |
| Client-initiated backchannel authentication endpoint.....         | 1154        |
| Token endpoint.....   | 1161        |
| Introspection endpoint.....                                       | 1171        |
| Token revocation endpoint.....                                    | 1176        |

|  |             |
|--|-------------|
| Grant-management endpoint.....                           | 1178        |
| Dynamic client registration endpoint.....                | 1178        |
| Device authorization endpoint.....                       | 1182        |
| User authorization endpoint.....                         | 1185        |
| OpenID Provider configuration endpoint.....              | 1186        |
| UserInfo endpoint.....                                   | 1190        |
| Pushed authorization requests endpoint.....              | 1191        |
| OAuth Playground.....                                    | 1193        |
| Web service interfaces and APIs.....                     | 1193        |
| Connection Management Service.....                       | 1195        |
| SSO Directory Service.....                               | 1198        |
| SOAP request and response examples.....                  | 1200        |
| OAuth Client Management Service.....                     | 1201        |
| OAuth Access Grant Management Service.....               | 1227        |
| OAuth Persistent Grant Management API.....               | 1230        |
| Session Management API by session identifiers.....       | 1233        |
| Session Management API by user identifiers.....          | 1236        |
| Session Revocation API endpoint.....                     | 1239        |
| PingFederate administrative API.....                     | 1241        |
| Application endpoints.....                               | 1249        |
| IdP endpoints.....                                       | 1250        |
| SP endpoints.....  | 1256        |
| System-services endpoints.....                           | 1269        |
| Authentication API.....                                  | 1273        |
| Exploring the authentication API.....                    | 1275        |
| Mobile application authentication through REST APIs..... | 1277        |
| Device authorization through mobile applications.....    | 1281        |
| <b>Index.....</b>  | <b>1282</b> |



# PingFederate

---

PingFederate is an enterprise federation server that enables user authentication and single sign-on (SSO). It serves as a global authentication authority that lets your customers, employees, and partners securely access applications.



## Release Notes

- [Current](#)



## Get Started with PingFederate

- [Introduction to PingFederate](#) on page 33
- [Installing and uninstalling PingFederate](#) on page 117
- [PingFederate administrative console](#) on page 171



## Use PingFederate

- [Administrator's Reference Guide](#) on page 224
- [Developer's Reference Guide](#) on page 1146
- [SDK Developer's Guide](#) on page 1115
- [Integrations](#)



## Troubleshoot PingFederate

- [Enabling debug messages and console logging](#)
- [Resolving startup issues](#)
- [Troubleshooting data store issues](#)
- [Resolving URL-related errors](#)
- [Resolving service-related errors](#)
- [Troubleshooting authentication policy issues](#)
- [Troubleshooting registration and profile management issues](#)
- [Troubleshooting runtime errors](#)
- [Troubleshooting OAuth transactions](#)
- [Other runtime issues](#)
- [Collecting support data](#)



## Learn More

- [Community](#)
- [Support](#)
- [PingFederate customer training](#) (existing customers only)
- [Partner Portal](#) (partners)

## Release Notes

---

These release notes summarize the changes in current and previous product updates.

PingFederate enables outbound and inbound solutions for single sign-on (SSO), federated identity management, mobile identity security, API security, social identity integration, and customer identity and access management (CIAM). PingFederate extends employee, customer, and partner identities across

domains without passwords, using only standard identity protocols: SAML, WS-Federation, WS-Trust, OAuth, and SCIM.

## PingFederate 11.1.10 (April 2024)

---

**Rest datastore security vulnerability** PF-34720 **Security**

Fixed a JSON injection vulnerability in REST datastores described in security advisory [SECADV044](#).

**Runtime nodes security vulnerability** PF-34896 **Security**

Fixed a path traversal vulnerability in Runtime nodes described in security advisory [SECADV044](#).

**OpenID Connect policy management editor security vulnerability** PF-35081 **Security**

Fixed a Cross-Site Scripting vulnerability in the OpenID Connect Policy Management Editor described in security advisory [SECADV044](#).

**Slow log consumption affects performance** PF-33368 **Fixed**

Fixed a defect that caused performance issues for PingFederate when third-party logging services were slow to consume logging events.

## PingFederate 11.1.9 (November 30)

---

Enhancements and resolved issues in PingFederate 11.1.9.

**Outbound provisioning performance improvement** PF-33466 **Fixed**

You can now turn off server-side sorting for LDAP requests related to outbound provisioning, which can improve performance in some environments.

Configure this option using the `ProvisionWithServerSort` parameter in the `com.pingidentity.common.util.ldap.LDAPUtil.xml` file.

**Updating OAuth clients with dynamic client registration** PF-34146 **Fixed**

Fixed a defect where an OAuth client created with dynamic client registration (DCR) couldn't be updated with DCR after it was modified with the administrative console.

**Resolved a vulnerability in the Initial Setup Wizard** PF-34646 **Security**

Fixed a Server-Side Request Forgery vulnerability in the Initial Setup Wizard described in security advisory [SECADV041](#).

## PingFederate 11.1.8 (August 2023)

---

Enhancements and resolved issues in PingFederate 11.1.8.

**Potential security vulnerability** PF-33449 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV037](#).

**Binary attributes handled incorrectly when using PingOne LDAP gateway datastores** PF-33637 **Fixed**

Now when PingFederate retrieves a binary attribute from a PingOne LDAP gateway datastore, it correctly converts the attribute value to the specified format (base64, SID, hex).

**Potential security vulnerability** PF-34017 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV037](#).

## PingFederate 11.1.7 (May 2023)

---

Enhancements and resolved issues in PingFederate 11.1.7.

### Logging validation

PF-32764 **Fixed**

We've improved logging validation.

### Resource Owner (RO) Password Credentials flow

PF-33359 **Fixed**

We've improved the error messaging around the Resource Owner (RO) Password Credentials flow.

### Requested Authentication Context Selector

PF-33549 **Fixed**

The Requested Authentication Context Selector no longer throws a Null Pointer Exception (NPE) during callback.

## PingFederate 11.1.6 (February 2023)

---

Enhancements and resolved issues in PingFederate 11.1.6.

### Potential security vulnerability

PF-32748 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV035](#).

### Log improvements

PF-33017 **Fixed**

In order to reduce re-encryption and file scanning log verbosity, when a configuration is imported or replicated to a cluster, PingFederate no longer scans files in the `etc` directory.

### Other improvements

**New**

- We also updated the following bundled components and third-party dependencies:
  - PingID Integration Kit 2.24
  - PingID Adapter 2.13.2
  - PingID PCV (with integrated RADIUS server) 3.0.3

## PingFederate 11.1.5 (February 2023)

---

Enhancements and resolved issues in PingFederate 11.1.5.

### Server log warnings

PF-33037 **Fixed**

We've added a warning to server logs if the `ds-pwp-state-json` attribute is not present in PingDirectory's LDAP Response. This warning appears in the log every time a user interacts with the profile management page. Please enable this attribute to adhere to PingDirectory's security configuration best practices. PingDirectory version 8.1 and later supports this attribute, and customers running older versions are encouraged to upgrade to a supported version as soon as possible.

## PingFederate 11.1.4 (February 2023)

---

Enhancements and resolved issues in PingFederate 11.1.4.

### OAuth client management

PF-32790 **Fixed**

When managing OAuth clients, we've resolved a defect where selecting the **Require JWT Secured Authorization Response Mode** text toggled the incorrect check box.

### Potential security vulnerability

PF-32805 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV033](#).

### Informing adapters of end policy result

PF-32890 **Fixed**

When processing policy fragments, all adapters invoked in the fragment now correctly execute their respective post-processing step (if applicable) to inform the adapter of the end policy result.

**Managing certificates within Metadata Export** PF-32965 Fixed

Managing certificates within the **Metadata Export** flow no longer displays or saves an empty list of certificates, clearing out existing ones in the process. For more information, see [Metadata export](#).

**Cluster data replication** PF-32983 Fixed

We've resolved a defect where cluster data replication could remove keys from engine node's `pf.jwk` file instead of merging and retaining the keys.

## PingFederate 11.1.3 (December 2022)

---

Enhancements and resolved issues in PingFederate 11.1.3.

**Improvements to custom revocation checker** PF-32395 Fixed

We've improved PingFederate's custom revocation checker, ensuring that when the server returns stapled Online Certificate Status Protocol (OCSP) responses, PingFederate invokes the checker. Previously, PingFederate used the default revocation checker to validate these responses, which could cause single sign-on (SSO) failures with BCFIPS mode enabled. For more information, see [Configuring certificate revocation](#) on page 682.

**Cluster replication notifications** PF-32398 Fixed

We've improved notifications to signal to administrators that in the event of a replication failure or any changes to cluster configuration require replication. For more information, see [Cluster management](#) on page 926.

**Null pointer exception during dependency error detection** PF-32553 Fixed

During PingFederate dependency error detection, OGNL expressions in adapter-to-adapter mappings no longer raise a null pointer exception (NPE).

**PingFederate updates to HSM ordering** PF-32556 Fixed

We've updated the recommended security provider ordering for the Thales Luna Network hardware security module (HSM) to address an issue where temporary keys and sessions could accumulate on the HSM, eventually resulting in resource exhaustion. A limitation of the new ordering is that EC certificates can no longer operate as SSL server certificates. For details on the new order, see [Integrating with Thales Luna Network HSM](#) on page 181.

## PingFederate 11.1.2 (October 2022)

---

Enhancements and resolved issues in PingFederate 11.1.2.

**Bulk import for IdP connections** PF-31870 Fixed

Resolved an issue where bulk import fails for identity provider (IdP) connections that fulfill Persistent Grant Extended Attributes.

**Connection failures on external LDAP authentication login** PF-32001 Fixed

PingFederate now recovers from initial connection failure when logging into the administrative console using external LDAP authentication.

**Hiding user information from authentication API responses** PF-32028 Fixed

You can now configure the setting `IncludeUserInfoInResponses` in the `<install_dir>/server/default/data/config-store/org.sourceid.saml20.domain.mgmt.impl.AuthnApiManagerImpl.xml` file to hide user information from authentication API responses.

**Errors on policy fragments configured to handle failures locally** PF-32073 **Fixed**

When an error occurs on policies containing fragments and configured to handle failures locally, PingFederate no longer redirects a user to the service provider (SP) error page on SP-initiated single sign-on (SSO).

**Outbound TLS connection failures** PF-32199 **Fixed**

The certificate path-building algorithm now uses PingFederate's custom revocation checker. This fix resolves a bug where outbound TLS connections failed for servers that presented out-of-order certificate chains.

**PingDirectory user registration** PF-32241 **Fixed**

During user registration, PingFederate now sends all passwords to PingDirectory, resolving an issue where passwords consisting of only spaces would not properly register a PingDirectory password.

**Configurations with no connection type in Kerberos realm** PF-32274 **Fixed**

When reading the `pingfederate-kerberos-realms.xml` file, PingFederate no longer raises an error for configurations with no connection type in the Kerberos realm.

## PingFederate 11.1.1 (July 2022)

---

Enhancements and resolved issues in PingFederate 11.1.1.

**Administrative API enhancement** **Info**

Improved the administrative API to manage the System for Cross-domain Identity Management (SCIM) inbound provisioning settings in identity provider (IdP) connections.

**Message customization enhancement** **Info**

Enhanced PingFederate message customization by adding the following FedHub-specific context variables:

- `FedHubSpConnApplicationName`
- `FedHubSpConnName`
- `FedHubOAuthClientId`
- `FedHubOAuthClientName`

**Cluster management enhancement** **Info**

Revised the **Cluster Management** window to make it more obvious when changes to the configuration on the administrative node have not been replicated to the engine nodes.

**Security around password expiration PingDirectory** PF-29706 **Fixed**

Improved the security around password expiration when using PingDirectory as a user store.

**Issuance criteria in authentication policy contracts** PF-31485 **Fixed**

Issuance criteria in authentication policy contracts no longer cause the logs to indicate invalid XML errors. This issue did not cause runtime errors.

**HTTP header for client IP addresses** PF-31735 **Fixed**

Resolved an issue that sometimes occurred when IPV6 addresses were specified in the **HTTP Header for Client IP Addresses** field on the **Incoming Proxy Settings** window.

**Error descriptions** PF-31753 **Fixed**

PingFederate error descriptions no longer disclose details of java classes.

**MasterKeyEncryptor failure during cluster replication** PF-31795 **Fixed**

When PingFederate is using a custom MasterKeyEncryptor that relies on an SSL call to an external service, cluster replication no longer causes cascading failures because PingFederate is unable to open Java key store files.

**Updating the client secret with the OAuth client management service** PF-31851 Fixed

When updating the client secret with the OAuth client management service, PingFederate now correctly creates the secondary secrets.

**OAuth authorization requests with `response_mode=pi.flow`** PF-31942 Fixed

Now when PingFederate receives an OAuth authorization request with `response_mode=pi.flow`, password change and account recovery flows using an authentication policy work correctly.

**Provisioning parameter failure** PF-31180 Fixed

We've fixed a defect that caused provisioning to fail when the `modifyTimestamp` parameter is included in the provisioning request.

`modifyTimestamp` is capitalized differently depending on the identity provider. For more information, see [Modifying source settings](#) on page 504.

## PingFederate 11.1 (June 2022)

---

New features and improvements in PingFederate 11.1.

**PingOne integration** PingOne New

We've added Kerberos authentication via PingOne and the PingOne LDAP Gateway Data Store. This new capability allows PingFederate in the cloud, without a direct connection to Active Directory, to complete Kerberos authentication for browser-based SSO requests and STS transactions through PingOne.

**JWT Secured Authorization Response Mode (JARM)** New

We're proud to support [JWT Secured Authorization Response Mode](#) (JARM) in version 11.1. JARM allows authorization servers to transmit authorization responses in JSON web tokens (JWTs), providing digital signature and encryption, sender authentication, and audience restriction. As JARM becomes a requirement in FAPI 2, you can deploy open banking solutions confidently.

**JWT Response for OAuth Token Introspection** New

We're also introducing support for [JWT Response for OAuth Token Introspection](#), a draft specification on track to become one of the authorization server requirements in the FAPI 2 Advanced Profile. JWT-secured introspection responses provide stronger assurance to the introspection requesters, most relevant when the requester, such as a resource server, expects to receive verified claims from the authorization server.

**Client secret management** New

Seamless client secret rotation no longer requires real-time coordination between PingFederate administrators and the application development teams. You can now configure PingFederate to retain previous secrets for a configurable period, during which the application teams can work on updating the client secrets in their apps. This enhancement drastically lowers the costs of securing applications that use client secrets for authentication. For more information, see "Client Secret Retention Period" in the topic [Managing client configuration defaults](#) on page 555.

**API support for Device Authorization Grant** New

In addition to template-driven user experience, the user authorization step from Device Authorization Grant supports API now. You can also decide whether PingFederate should check the device activation code before or after authentication. These new capabilities enable you to build applications with the desired user experience for input-constrained devices, such as smart TVs or telepresence equipment.

**Amazon DynamoDB for grants** New

You can store OAuth persistent grants in Amazon DynamoDB, which allows you to take advantage of a NoSQL database where it matters most: delivering responsive experiences to globally distributed users and offering high availability at ease.

### Revocation of self-contained access tokens


**New**

You can optionally enable direct revocation for self-contained access tokens (JWT access tokens). This flexibility provides a secure way to invalidate access tokens without revoking the underlying refresh tokens or persistent grants. For more information, see [Configuring JSON token management](#) on page 606 and its description of the **Enable Token Revocation** check box.

### A new alert system

**New**

PingFederate 11.1 centralizes alerts, such as the reminder to replicate configuration, under the new bell icon in the top menu. You can review important alerts from any configuration window.



### Copy-and-paste authentication policies and fragments

**New**

Previously, if you wanted to update an authentication policy or a reusable policy fragment midstream, they had to reconfigure all downstream paths, which can take some effort. With PingFederate 11.1, you can copy a subtree of policy paths before removing a step (such as an IdP adapter), adding a new step (such as a selector or another IdP adapter), and then pasting the subtree back to the policy. This new capability applies to reusable policy fragments and between authentication policies and reusable policy fragments.

### Administrative API to move individual policies

**New**

You can use the administrative API to move an individual policy to a specific location. This enhancement makes re-organizing policies by API requests easier and safer.

### Cluster configuration management

**New**

PingFederate engine nodes now capture common configuration replication issues in their server logs and send replication status back to the console node. The **Cluster Management** window provides live updates when you select **Replicate Configuration** in the **Cluster Management** window. If an error occurs, you can act on it immediately and recover from potential outages faster.

### Passthrough IdP Adapter

**New**

You can now associate authentication sessions with user identities passed through the new Passthrough Identity Provider (IdP) Adapter. By placing the Passthrough IdP Adapter downstream from an IdP connection in a policy tree, you can take advantage of additional capabilities associated with defining a user key. For example, you can use the user key to query or revoke a user's authentication sessions.

### Kerberos authentication and ObjectSID

**New**

The Kerberos Adapter and the Kerberos Token Processor now return the `ObjectSID` attribute value. Because `ObjectSID` uniquely identifies the user in Active Directory, leveraging it helps streamline the **Attribute Source & Lookup** configuration.

### Kerberos authentication and re-authentication

**New**

You can configure the Kerberos Adapter to fail when the service provider asks for re-authentication by including `ForceAuthn=true` (SAML 2.0) or `prompt=login` (OpenID Connect) in their authentication requests. For example, suppose user interactions are required when the partners ask for re-authentication. In that case, you can add the HTML Form Adapter to the **Fail** policy path of the Kerberos Adapter.

**More error handling options****New**

- You now can configure individual authentication policies to handle authentication failures locally without redirecting to the service providers or returning error messages to the OAuth clients. This flexibility addresses the scenario where an IdP-oriented end-user experience is desirable.
- PingFederate now includes error results from issuance criteria in error responses. Partners can use the error results to resolve issues as needed. If the invoked policy is configured to handle failures locally, you can do the same to improve the end-user experience.
- You can now optionally configure the HTML Form Adapter not to return control to PingFederate when an account lockout occurs. Instead, PingFederate returns a “please try again later” message to the browser or the authentication API application.

**Extended properties for end-user interactions****New**

You can now leverage extended properties in Velocity templates when customizing template-driven end-user interactions. You can reference extended properties in the templates instead of creating multiple `If/ElseIf/Else` directives, significantly reducing the initial effort. New and updated experiences can be inherited from extended property values from the OAuth client records and Browser SSO connections, eliminating most of the maintenance costs. PingFederate also passes extended property values to authentication API applications. As a result, application developers who create and maintain end-user UX for customer identities will benefit from this new enhancement.

**Better documentation in Velocity templates****New**

We’ve also improved inline documentation in our Velocity templates. Moving forward, we will maintain variable names and their definitions consistently to communicate changes, such as introducing new variables.

**Enhancements in Thales HSM integration****New**

Both Java 11 and 8 environments are supported when integrating with Thales Luna Cloud Hardware Security Module (HSM) Services or Luna Network HSMs. For more information about Thales Luna HSM Client, see the [Luna Cloud HSM Service Client Guide](#) and [Luna Network HSM Documentation Archive](#).

**Secondary signing certificate****New**

You can now add a secondary signing certificate to your connections. If configured, PingFederate includes it in both the metadata exports and the metadata URL responses. This flexibility allows you to notify your partners about upcoming changes more easily through metadata.

**Administrative API improvements****New**

We improved the PingFederate administrative API to manage the following configurations:

- JIT provisioning settings in IdP connections
- **System # Data & Credential Stores # Identity Store Provisioners**
- **System # Server # General Settings**
- **System # Server # WS-Trust Settings**

**Other improvements****New**

- We significantly improved our metrics exposed through HTTP (at the heartbeat endpoint) and JMX to help you detect and diagnose performance issues. Both channels include HTTP response code counts, data source response time statistics, and Jetty queue size information; these metrics help troubleshoot latency issues associated with datastores or traffic volume.
- PingFederate now uses OCSP to obtain certificate revocation status by default on new installations. As part of this enhancement, PingFederate uses the OCSP responder URL provided in the certificate first, followed by the now optional Default OCSP Responder URL, and lastly, CRL, making the certificate validation process more efficient.
- The administrative console now provides guidance when you attempt to import a configuration archive obtained from a different version of PingFederate.



- PingFederate 11.1 supports Amazon IAM roles for service accounts, which increases security posture with credential isolation and auditability.
- PingOne Verify is now part of the PingFederate distribution .zip file and Windows installer.
- We also updated the following bundled components and third-party dependencies:
  - PingID Integration Kit 2.17
  - PingOne Fraud Integration Kit 1.0
  - PingOne Protect Integration Kit 1.2
  - Jackson-Databind 2.12.7
  - Log4j2 2.17.2
  - Spring Framework 5.3.20

## **H2 database engine upgrade** PF-21198 **Fixed**

Upgraded the H2 database engine to version 2.1.210.

## **A username in the URL during change password flows** PF-24501 **Fixed**

The username no longer appears in the URL during change password flows.

## **Guava upgrade** PF-28932 **Fixed**

Upgraded the Guava dependency to version 30.1.1.

## **OAuth client Issuer DN** PF-29368 **Fixed**

If the administrative API was used to create an OAuth client that has the Client Certificate authentication type, and the client's Issuer DN does not have a normalized DN value, the administrative console's **Client** window no longer fails to show the Issuer DN as the default value. This issue didn't affect runtime behavior.

## **Time stamp for last update** PF-29761 **Fixed**

When a user record in a datastore mistakenly has a future date for the last update time, PingFederate no longer uses that date as the value of `attrib_last_timestamp` in the `channel_variable` table. Instead, PingFederate sets the value to the maximum time stamp that is not in the future.

## **Number and Boolean data types in JSON responses from REST API data source lookups** PF-29835 **Fixed**

The JSON response from REST API data source lookups now retains number and Boolean data types instead of converting them to strings.

## **NotYetConnectedException warning messages from JGroup in the server.log** PF-30075 **Fixed**

Resolved an issue that caused the `NotYetConnectedException` warning message to repeatedly appear in the `server.log` when using `AWS_PING` for dynamic cluster discovery.

## **Matching OAuth client's redirection URIs** PF-30146 **Fixed**

If the OAuth client's redirection URI contains a wild card in the authority part of the URI, and the `redirect_uri` parameter of the token request contains userinfo in the authority part, then PingFederate will no longer consider the redirection URI a match.

## **Potential security vulnerability** PF-30255 **Fixed**

Resolved a potential security vulnerability.

## **Logging invalid assertion errors** PF-30495 **Fixed**

In a specific case, when PingFederate logs an invalid assertion error, the error message no longer fails to include a remark about why the assertion or response is invalid.

## **Null pointer exception in authentication API password reset flow** PF-30558 **Fixed**

When an OAuth client is performing a password reset through the authentication API, if PingFederate does not find any session attributes, now PingFederate logs an error state instead of a null pointer exception.

## **Determining authentication instants for flows** PF-30770 **Fixed**

Resolved an issue that prevented PingFederate from correctly determining the authentication instant for the flow when the initial OIDC authorization request specifies a `max_age`, the flow falls through to legacy authentication source selection (policies are disabled or no policy applies), and the user chooses an upstream OIDC IdP connection.

**Templates for PingOne MFA 1.6.1** PingOne MFA PF-30806 Fixed

PingFederate now includes all the templates for PingOne MFA 1.6.1.

**Dependency errors for SAML token processors and generators** PF-31054 Fixed

When saving SAML token processors or generators, PingFederate now correctly handles dependency errors caused by misconfigured settings on the **Protocol Settings** window's **Federation Info** tab.

**Preserving the order of map type configurations** PF-31145 Fixed

Now PingFederate preserves the order of map type configurations under `<pf_install>/pingfederate/server/default/data/config-store` when performing a bulk export or a GET operation at the `/configStore` administrative API endpoint.

**Warning about using the administrative console in multiple tabs** PF-31280 Fixed

Now if you use the PingFederate administrative console in multiple tabs on one browser, it warns you that doing so might cause inconsistent behavior which could corrupt its configuration.

**Saving authorization server settings overwrites scope.whitelist** PF-31304 Fixed

Resolved an issue that caused PingFederate to overwrite the `scope.whitelist` in the `\data\config-store\org.sourceid.oauth20.domain.AuthzServerManagerImpl.xml` file when you save the authorization server settings.

**OAuth client IDs added to admin.log entries** PF-31561 Fixed

Now OAuth client MODIFY, CREATE, and DELETE event log entries in the `admin.log` include the client ID.

**Honoring the property for maximum HTTP request body size** PF-31575 Fixed

Now PingFederate honors the value of `http.maxRequestBodySize` in the `run.properties` file, which specifies the maximum HTTP request body size of any incoming request to PingFederate's web services and administrative API.

**PingID password credential validator with integrated RADIUS server** Issue

PingFederate versions 11.1.4, 11.1.5, 11.2.1, and 11.2.2 contain version 3.0.2 of the PingID password credential validator (PCV). That version of the PCV has known issues that you should review before upgrading. For more information, see [Known issues in PingID RADIUS PCV 3.0.2](#).

**Administrative console and administrative API** Issue

- `/bulk`: Only resource types currently supported by the administrative API are included in the exported data. We don't intend to introduce administrative API support to the following areas:
  - [SAML 2.0 IdP Discovery](#)
  - [SAML 2.0 SP Affiliation](#)
  - [SMS Provider](#)
- Previously, the administrative API did not accurately reflect a **Persistent Grant Max Lifetime** setting of 29 days (or shorter) with the selection of the **Grants Do Not Timeout Due To Inactivity** option. As a result, if you have configured such OAuth authorization server settings and have generated a bulk export in version 10.0 through 10.0.2, we recommend that you re-generate a new bulk export after upgrading to version 10.0.3 (or a more recent version). The newly exported data does not contain the aforementioned flaw, and you can safely import it to version 10.0.3 (or a more recent version).
- When enabling mutual TLS certificate-based authentication, administrators often configure a list of acceptable client certificate issuers. When you use a browser to access the console or the administrative API documentation, PingFederate returns to the browser the list of acceptable

issuers as part of the TLS handshake. If the browser's client certificate store contains multiple client certificates, the browser often presents you only the certificates whose issuer matches one of the acceptable issuers. However, when PingFederate runs in a Java 11 environment, Chrome presents you all its configured client certificates, regardless of whether the issuer matches one of the acceptable issuers or not.

- Prior to toggling the status of a connection with the administrative API, you must ensure that any expired certificates or no longer available attributes are replaced with valid certificates or attributes; otherwise, the update request fails.
- When creating or updating a child instance of a hierarchical plugin, the administrative API retains objects with an `"inherited": false` name/value pair (or without such name/value pair altogether), ignores those with a value of `true`, and returns a 200 HTTP status code. No error messages are returned for the ignored objects.
- Using the browser's navigation mechanisms (for example, the **Back** button) causes inconsistent behavior in the administrative console. Use the navigation buttons provided at the bottom of windows in the PingFederate console.
- Using the PingFederate console in multiple tabs on one browser might cause inconsistent behavior which could corrupt its configuration.
- If authenticated to the PingFederate administrative console using certificate authentication, a session that has timed out might not appear to behave as expected. Normally (when using password authentication), when a session has timed out and a user attempts some action in the console, the browser is redirected to the sign-on page, and then back to the administrative console after authentication is complete. Similar behavior applies for certificate authentication, in principle. However, because the browser might automatically resubmit the certificate for authentication, the browser might redirect to the administrative console and not the sign on page.

### TLsv1.3

### Issue

For Java versions that don't support TLsv1.3 (meaning versions earlier than 8u261), PingFederate fails on start up with a `NoSuchAlgorithmException` exception. To resolve this error, remove `TLsv1.3` from the following settings in the `run.properties` file:

- `pf.tls.client.protocols`
- `pf.tls.runtime.server.protocols`
- `pf.tls.admin.server.protocols`

### TLS cipher suite customization

### Issue

PingFederate's TLS cipher suites can be customized by modifying `com.pingidentity.crypto.SunJCEManager.xml` (or a similarly-named file if BCFIPS or a hardware security module (HSM) is configured). After updating the file and replicating, all cluster nodes must be restarted for the change to take effect.

### Java

### Issue

- As of PingFederate 11.1, BC-FIPS and HSMs are not supported when using Java 17.
- Updating Java version 8 to version 11 results in an error when PingFederate is already installed and running. To work around this issue, uninstall and reinstall the PingFederate Windows service by running the `UninstallPingFederateService.bat` and `InstallPingFederateService.bat` files located in `<pf_install>/pingfederate/sbin/wrapper`.

### Hardware security modules (HSMs)

### Issue

- For Entrust HSMs and Thales HSMs, it is not possible to use an elliptic curve (EC) certificate as an SSL server certificate.
- For Entrust HSMs or AWS CloudHSM, PingFederate must be deployed with Oracle Server JRE 8 or Amazon Corretto 8.
- For keys stored in AWS CloudHSMs, JWT token signing fails when using RSASSA-PSS SHA-512.

- For Thales and Entrust HSMs, JWT token decryption using ECDH-ES may fail. This issue only arises if PingFederate is configured with static OAuth and OpenID Connect keys, a static key is stored on the HSM, and PingFederate is consuming a token encrypted with this key.
- For Entrust HSMs, JWT token decryption using RSAES OAEP may fail. This issue only arises if PingFederate is configured with static OAuth and OpenID Connect keys, a static key is stored on the HSM, and PingFederate is consuming a token encrypted with this key.
- For Entrust HSMs, SAML assertion decryption using RSA OAEP may fail when the decryption key is stored on the HSM.
- TLS 1.3 is not currently supported with any HSM.

## SSO and SLO

**Issue**

- When consuming SAML metadata, PingFederate does not report an error when neither the `validUntil` nor the `cacheDuration` attribute is included in the metadata. Note that PingFederate does reject expired SAML metadata as indicated by the `validUntil` attribute value, if it is provided.
- The anchored-certificate trust model cannot be used with the Single log off (SLO) redirect binding because the certificate cannot be included with the logout request.
- If an IdP connection is configured for multiple virtual server IDs, PingFederate will always use the default virtual server ID for IdP Discovery during an SP-initiated SSO event.

## Composite Adapter configuration

**Issue**

SLO is not supported when users are authenticated through a Composite Adapter instance that contains another instance of the Composite Adapter.

## Self-service password reset

**Issue**

Passwords can be reset for Microsoft Active Directory user accounts without the permission to change password.

## OAuth

**Issue**

PingFederate does not support a case-sensitive naming convention for OAuth client ID values when client records are stored in a directory server. For example, after creating a client with an ID value of `sampleClient`, PingFederate does not allow the creation of another client with an ID value of `SampleClient`.

Although it's possible to create clients using the same ID values with different casings when client records are stored in XML files, a database server, or custom storage, we recommend not doing so to avoid potential record migration issues.

## Customer identity and access management

**Issue**

Some browsers display a date-picker user interface for fields that have been designed for date-specific inputs. Some browsers do not. If one or more date-specific fields are defined on the registration page or the profile management page (or both), end users must enter the dates manually if their browsers do not display a date-picker user interface for those fields.

## Provisioning

**Issue**

- LDAP referrals return an error and cause provisioning to fail if the `user` or `group` objects are defined at the DC level, and not within an OU or within the Users CN.
- The `totalResults` value in SCIM responses indicates the number of results returned in the current response, not the total number of estimated results on the LDAP server.

## Logging

**Issue**

- If a source attribute has been configured for masking in an IdP adapter or IdP connection and the source attribute is mapped to OAuth's persistent grant `USER_KEY` attribute, the `USER_KEY` attribute will not be masked in the server logs. Other persistent grant attributes will be masked.
- Even if a source attribute has been configured for masking in an IdP adapter and the source attribute is mapped as the adapter's unique user key, the user key attribute is not masked in the server or audit logs.

**Database logging****Issue**

- If a source attribute has been configured for masking in an IdP adapter or IdP connection and the source attribute is mapped to OAuth's persistent grant **USER\_KEY** attribute, the **USER\_KEY** attribute will not be masked in the server logs. Other persistent grant attributes will be masked.
- Even if a source attribute has been configured for masking in an IdP adapter and the source attribute is mapped as the adapter's unique user key, the user key attribute is not masked in the server or audit logs.

**RADIUS NAS-IP-Address****Issue**

The RADIUS NAS-IP-Address is only included in Access-Request packets when the `pf.bind.engine.address` is set with an IPv4 address. IPv6 is not supported.

**Microsoft Internet Explorer 11****Info**

Ping Identity commits to deliver the best experience for administrators and users. As we continue to improve our products, we encourage you to migrate off of Microsoft Internet Explorer 11. Starting with PingFederate 11.0, Internet Explorer 11 is no longer included in the PingFederate qualification process for administrators or users. For a list of supported browsers, see [System requirements](#) on page 119.

**Configcopy tool, Connection Management Service, SSO Directory Service****Info**

As of PingFederate 10.2, these features have been deprecated and will be removed in a future release.

**Oracle Directory Server Enterprise Edition****Info**

As Oracle ended its Premier Support for Oracle Directory Server Enterprise Edition (ODSEE 11g) in December 2019, we no longer include ODSEE as part of the PingFederate qualification process (starting with PingFederate 10.2). We continue to qualify against [Oracle Unified Directory](#) ([www.oracle.com/middleware/technologies/unified-directory.html](http://www.oracle.com/middleware/technologies/unified-directory.html)) and other supported directory servers. For a full list, see [System requirements](#) on page 119.

**SNMP****Info**

Starting with PingFederate 10.2, monitoring and reporting through the Simple Network Management Protocol (SNMP) has been removed.

**Roles and protocols****Info**

Starting with PingFederate 10.1, roles and protocols are always enabled and no longer configurable through the administrative console and API.

**S3\_PING discovery protocol****Info**

Starting with PingFederate 10.1, the S3\_PING discovery protocol has been deprecated. Customers running on AWS infrastructure should instead use NATIVE\_S3\_PING.

**Red Hat Enterprise Linux install script****Info**

Starting with PingFederate 10.0, the Red Hat Enterprise Linux install script is no longer available. To install PingFederate 10.0 for Linux, you must download and extract the product distribution `.zip` file.

## PingFederate 11.0.8 (August 2023)

---

Enhancements and resolved issues in PingFederate 11.0.8.

**Logging validation**PF-34017 **Fixed**

We've improved logging validation.

**Potential security vulnerability**PF-33449 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV037](#).

**Potential security vulnerability**PF-34017 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV037](#).

## PingFederate 11.0.7 (February 2023)

---

Enhancements and resolved issues in PingFederate 11.0.7.

### Server log warnings

PF-33037 **Fixed**

We've added a warning to server logs if the *ds-pwp-state-json* attribute is not present in PingDirectory's LDAP Response. This warning appears in the log every time a user interacts with the profile management page. Please enable this attribute to adhere to PingDirectory's security configuration best practices. PingDirectory version 8.1 and later supports this attribute, and customers running older versions are encouraged to upgrade to a supported version as soon as possible.

## PingFederate 11.0.6 (February 2023)

---

New features and improvements in PingFederate 11.0.6.

### Potential security vulnerability

PF-32805 **Fixed**

We've resolved a potential security vulnerability that is described in security advisory [SECADV033](#).

## PingFederate 11.0.5 (October 2022)

---

PingFederate 11.0.5 is a cumulative maintenance release for PingFederate 11.0. For a summary of the features introduced in the 11.0 release, see [PingFederate 11.0 - December 2021](#).

### IPV6 address issue

PF-31735 **Fixed**

Resolved an issue that sometimes occurred when IPV6 addresses were specified in the **HTTP Header for Client IP Addresses** field on the **Incoming Proxy Settings** window.

### Administrative console login

PF-32001 **Fixed**

PingFederate now recovers from initial connection failure when logging into the administrative console using external LDAP authentication.

### User registration defect resolution

PF-32241 **Fixed**

During user registration, PingFederate now sends all passwords to PingDirectory, resolving an issue where passwords consisting of only spaces would not properly register a PingDirectory password.

## PingFederate 11.0.4 (August 2022)

---

New features and improvements in PingFederate 11.0.4.

### MasterKeyEncryptor and cluster replication

PF-31795 **Fixed**

When PingFederate uses a custom MasterKeyEncryptor that relies on an SSL call to an external service, cluster replication no longer causes cascading failures because PingFederate cannot open Java key store files.

### Rule matching for fragment nodes and NullPointerException

PF-31929 **Fixed**

When using rule matching for fragment nodes, PingFederate no longer raises a NullPointerException (NPE) if a fragment fails.

### Zero byte archives

PF-31966 **Fixed**

Resolved an issue that caused PingFederate to generate a zero byte archive when it couldn't read a file in the `<pf_install>/pingfederate/server/default/data` directory.

### JWT access token lifetimes

PF-31989 **Fixed**

When using centralized and dynamically rotating keys for OAuth and OpenID Connect, PingFederate now prevents you from setting the JWT access token lifetime to be longer than the `dynamic-rotation-`

period-in-days specified in `<pf_install>/pingfederate/server/default/data/config-store/jwks-endpoint-configuration.xml`.

## PingFederate 11.0.3 (May 2022)

---

New features and improvements in PingFederate 11.0.3.

**Intermittent failure to respond after restart caused by LDAP SDK** PF30776 **Fixed**

To resolve an issue in which PingFederate occasionally stopped responding after a restart, the UnboundID LDAP SDK for Java was updated to version 6.0.4.

**TLS 1.3 for outbound connections** PF-31303 **Fixed**

PingFederate now supports TLS 1.3 for outbound connections when running on Java 8 versions 8u261 and newer.

**Updated Spring Framework** PF-31169 **Info**

Updated Spring Framework to version 5.3.18.

## PingFederate 11.0.2 (March 2022)

---

New features and improvements in PingFederate 11.0.2.

**Updated PingOne MFA adapter** PingOne MFA **Info**

Updated the bundled PingOne MFA adapter to version 1.6.

**LDAP connections** PF-30804 **Fixed**

Resolved an issue that caused LDAP connections to periodically fail during provisioning.

**Bulk export** PF-30863 **Fixed**

Bulk export no longer fails to include all XML OAuth clients in the response payload.

**Single sign-on from browsers on iOS** PF-31057 **Fixed**

Resolved an issue that caused single sign-on from browsers on iOS to fail when an authentication policy terminates on Kerberos Adapter fallback that has an existing session.

**nCipher mode** PF-31064 **Fixed**

When running PingFederate in nCipher mode, now the administrative API successfully generates elliptic curve (EC) keys when the optional signatureAlgorithm field is not provided.

**TLS 1.3 for inbound connections** PF-31112 **Fixed**

PingFederate now supports TLS 1.3 for inbound connections when running on Java 8 versions 8u261 and newer.

**Symantec VIP Adapter** PF-31123 **Fixed**

Resolved an issue that prevented PingFederate from using the Symantec VIP Adapter.

**LDAP-related performance** PF-31146 **Fixed**

Resolved an LDAP-related performance issue.

**Signature verification for certificate revocation lists** PF-31159 **Fixed**

Resolved an issue where signature verification for certificate revocation lists could take more than 10 seconds on Windows. When LDAP-based authentication was enabled in the administrative console, this could prevent administrative users from signing on.

## PingFederate 11.0.1 (January 2022)

---

New features and improvements in PingFederate 11.0.1.

**Rolling grace period for refresh tokens** **Improved**

When PingFederate rotates a refresh token, if the client fails to get the new token, now PingFederate can accept the previous token for the short period that you specify with the **Refresh Token Rolling Grace Period** setting.

**Performance improvement** **Info**

Improved performance of the administrative console when a large number of OAuth clients are stored in LDAP or JDBC datastores.

**URL region of the PingOne home button** PingOne **Info**

When configuring the URL of the PingOne home button in the PingFederate administrative console, now `pf.pingone.admin.url.region` in `run.properties` supports Canada as a region.

#### **AWS CloudHSM client**

**Info**

PingFederate can be successfully integrated with AWS CloudHSM client version 3.4.4.

#### **Resolved a potential security vulnerability**

PF-30450 **Security**

Resolved a potential security vulnerability that is described in security bulletin [SECBL021](#).

#### **Updated Apache Log4j2**

PF-30536 **Security**

Resolved a potential security vulnerability by updating Apache Log4j2 to version 2.17.1.

#### **Authenticating PingDirectory users** PingDirectory

PF-30557 **Fixed**

Resolved an issue that allowed PingDirectory users to authenticate with expired passwords.

#### **Certificate revocation list checks**

PF-30637 **Fixed**

Resolved an issue that caused certificate revocation list (CRL) checks to return "issuer not found in trusted CAs store" even though the issuer certificate is present.

## **PingFederate 11.0 (December 2021)**

---

New features and improvements in PingFederate 11.0.

#### **PingOne LDAP Gateway datastore** PingOne

**New**

PingFederate in the cloud can now connect to on-premise directory servers through the [PingOne LDAP Gateway](#). This new capability reduces the complexity of moving to the cloud, while maintaining connectivity to on-premise end-user data.

#### **PingOne unified admin integration** PingOne

**New**

Administrators can now open the PingOne unified admin from any configuration window in the PingFederate administrative console. To activate the new Home icon, enter the PingOne region and the environment ID in the `run.properties` file.

#### **Management of configuration encryption keys**

**New**

PingFederate maintains a set of configuration encryption keys to encrypt sensitive configuration information provided by the administrators and decrypt them later as needed. While we continue recommending customers to protect their configuration encryption keys by [AWS KMS](#) or custom solutions based on the PingFederate SDK (the `MasterKeyEncryptor` interface), we are introducing two enhancements in this area.

- **Key rotation:** Administrators or key-management processes can now insert a new configuration encryption key into the system with one click in the administrative console or a single administrative API request. Once rotated, PingFederate starts using this new encryption key when it needs to encrypt sensitive configuration data.
- **Re-encryption of configuration data:** Version 11 also comes with a new `configkeymgr` command-line utility. Administrators can optionally scan, review, re-encrypt, and delete older configuration encryption keys in their systems. Furthermore, administrators can now choose to re-encrypt sensitive information when importing an archive from a different environment; this is most useful when administrators do not want to share configuration encryption keys between the two environments.

#### **Secret Managers**

**New**

The new Secret Managers support allows customers to store certain credentials, such as data store credentials, in external secret management systems and have PingFederate retrieve them as needed. It helps customers comply with internal IT policies or meet and exceed their industry standards. Version 11 integrates out-of-the-box with CyberArk Credential Provider. Customers can also develop custom solutions based on the PingFederate SDK (the `SecretManager` interface), to connect to other secret management systems.

#### **FAPI 1 Advanced Final certifications**

**New**

Ping Identity remains a solid contributor to the financial-grade API initiatives from the OpenID Foundation. We're proud that PingFederate is a certified implementation of various FAPI 1 Advanced Final profiles,



including all profiles under Australia CDR and UK Open Banking and four profiles under Brazil Open Banking. Deploy Open Banking solutions with confidence and rest assured that we will continue to invest in OAuth, OpenID Connect, and FAPI specifications. For more information about OpenID certifications, visit [https://openid.net/certification/#FAPI\\_OPs](https://openid.net/certification/#FAPI_OPs).

### Flexibility in ID token issuance

**New**

When processing an OpenID Connect hybrid flow, in addition to issuing an ID token from the token endpoint, PingFederate may also return an ID token from the authorization endpoint, depending on the requested response type. Administrators now have the flexibility to separate these two ID token issuances and configure their fulfillment differently. These enhancements allow our customers to comply with the regulatory requirements and open standards set by the Australian CDR and FAPI specifications.

### Encrypted request objects

**New**

PingFederate now supports encrypted request objects that OAuth clients send to its [Authorization endpoint](#) and the [Pushed Authorization Requests \(PAR\) endpoint](#). As needed, administrators can make encrypted request objects mandatory. This new capability further secures the confidentiality of authentication request parameters.

### Authorization server issuer identification

**New**

The OAuth 2.0 Authorization Server Issuer Identification [draft specification](#) intends to mitigate the scenario where mix-up attacks are a potential threat to all OAuth clients interacting with multiple authorization servers. As needed, administrators can enable this optional capability.

### Better private key JWT validation

**New**

In the context of OAuth client authentication, when processing private key JWTs from applications, PingFederate now ensures that the issuer (`iss`) claim value matches the client ID. This enhancement removes the need to use issuance criteria to enforce this validation requirement.

### Message customization in OIDC IdP connection

**New**

PingFederate 11 can now take the request parameters from the SAML 2.0 SP or the OpenID Connect relying party (OIDC RP) into account when building its OIDC authentication request to the third-party OpenID Provider (OP). This capability allows administrators to selectively configure the values in the outbound OIDC authentication requests if their use cases or the third-party OPs have the need to gather more information from the originating SP or RP.

### Multi-valued attribute format

**New**

Administrators can optionally indicate that PingFederate should always return an array for an attribute value regardless of whether the attribute contains one or multiple values. This flexibility simplifies the logic required to consume attribute values from access tokens or ID tokens.

### Streamlined initial setup experience

**New**

We're pleased to introduce a brand new initial setup experience, where administrators can finish their initial setup in as little as four steps, rapidly making our rock-solid capabilities available after starting PingFederate for the first time.

### Individual policy management by API

**New**

Administrators can now focus solely on one policy without including other policies as part of the API request when managing an individual authentication policy through the administrative API. This simplification improves the API experience and eliminates the risk of making unexpected changes in other authentication policies.

### Console heartbeat

**New**

Monitoring the status of the console node is now more straightforward with the addition of the `/pf/heartbeat.ping` heartbeat endpoint to the administrative port. Like its runtime counterpart, the administrative heartbeat endpoint is also capable of returning additional information. If administrators want

detailed information in the responses, set the `pf.heartbeat.system.monitoring` property to `true` in the `run.properties` file.

### Datastore enhancements

**New**

- We expanded the REST API datastore with HTTP POST support. Administrators can connect to data repositories that prefer or require the HTTP POST method.
- Administrators can add attribute options in their LDAP directory searches. This enhancement expands what PingFederate can retrieve from the directory servers that support attribute options, PingDirectory being one of them.
- When configuring an LDAP search filter that uses one or more variables, an administrator can optionally specify default values for them, most useful in the scenarios where these variables may not contain any values at runtime.

### Migration of templates

**New**

Our upgrade tools now copy customized default templates from the previous installation to the new one. This improvement preserves the end-user experience and branding, making it easier to verify and move forward with version 11 and beyond.

### New configuration for dynamic discovery settings

**New**

Previously, administrators could only define dynamic discovery settings to discover cluster membership in the `server/default/conf/tcp.xml` file. Version 11 provides a new configuration file for these settings, `jgroups.properties` in the `bin` directory. This new approach streamlines future upgrade experiences. For new installations, we recommend defining dynamic discovery settings in the `jgroups.properties` file. While upgraded environments will continue to look for dynamic discovery settings from the `tcp.xml` file, we recommend performing a one-time migration to ease the upgrade experiences in the future.

### Email ownership verification by OTP

**New**

For customer identities, in addition to email ownership verification by one-time link, administrators can now enable email ownership verification by one-time passcode (OTP). This new option offers a modern verification experience. It also helps customers who prefer not to send hyperlinks via email to their consumers.

### Request context to authentication API applications

**New**

Administrators can optionally configure PingFederate to pass contextual information, such as the OAuth client ID or tracked HTTP parameters, from the sign-on requests to the authentication API applications. This allows developers to build applications that offer tailored experiences and satisfy branding requirements from their organizations based on contextual information from the sign-on requests.

### Kerberos authentication improvement

**New**

Administrators can now ensure Kerberos authentication remains functional for service tickets associated with older Kerberos service account passwords after updating the **Domain/Realm Password** field with a new password in PingFederate. This optional capability increases productivity because workforce identities are no longer required to restart their Windows sessions in order to authenticate via Kerberos.

### Contextual information in Session Management API responses

**New**

The Session Management API now includes IP address and User-Agent information in its responses. Clients with access to this API can learn more about their users and provide suitable offerings based on this new insight.

### Security enhancements

**New**

- PingFederate now supports Amazon EC2 Instance Metadata Service version 2 (IMDSv2) when `AWS_PING` is the chosen dynamic discovery method. No PingFederate configuration changes are required, and IMDSv1 remains supported.
- PingFederate now records administrative timed-out events in the administrator audit log (`admin.log`).

- The **Change Password** and **Password Reset** end user-facing pages now time out after 30 minutes. This is the new default behavior for new and upgraded installations. As needed, administrators can configure a different **Password Update Timeout** value per HTML Form Adapter instance to suit the needs of their organizations.

### Other improvements

**New**

- PingFederate now includes HTTP/2 support for inbound requests for better performance.
- Administrators can optionally configure PingFederate to mask values obtained from tracked parameters in the server log. Look for the **MaskTrackedParams** setting in the `org.sourceid.saml20.domain.mgmt.impl.TrackedHttpParamManagerImpl.xml` file.
- Administrators are free to enable the refresh token grant type independently on a per-client basis regardless of whether session validation is enabled in any Access Token Managers.
- Administrators can optionally configure PingFederate to redirect end-users back to the **Sign On** page after successfully updating their soon-to-expire password as part of their SSO requests.
- The **Reuse Existing Persistent Access Grants for Grant Types** authorization server setting is now overridable per client.
- PingFederate now supports RSAES OAEP using SHA-256 and MGF1 with SHA-256 (RSA-OAEP-256) when minting outbound ID tokens or processing inbound encrypted request objects
- Administrators can optionally restrict access to the redirectless mode per authentication API application. Additionally, administrators can further limit each application to an OAuth client to improve security around the redirectless mode of the authentication API.
- We upgraded the framework of our administrative API documentation to Swagger 2.0.
- PingFederate now preserves line breaks and indentations of OGNL expressions.
- The following templates now share the following Velocity template variables, which makes branding end-user experiences easier.

| Templates  | Variables   |
|--|---|
| <ul style="list-style-type: none"> <li>▪ <code>identifier.first.template.html</code></li> <li>▪ <code>html.form.login.challenge.template.html</code></li> <li>▪ <code>html.form.login.template.html</code></li> <li>▪ <code>html.form.message.template.html</code></li> <li>▪ <code>html.form.password.expiring.notification.template.html</code></li> </ul> | <ul style="list-style-type: none"> <li>▪ <code>\$client_id</code> - The ID of the OAuth client used by the request</li> <li>▪ <code>\$entityId</code> - The entity ID of the SP connection used by the request</li> <li>▪ <code>\$connectionName</code> - The name of the SP connection used by the request</li> <li>▪ <code>\$baseUrl</code> - The base URL of PingFederate instance</li> <li>▪ <code>\$adapterId</code> - The IdP adapter ID used by the request</li> <li>▪ <code>\$spAdapterId</code> - The SP adapter ID used by the request</li> </ul> |

- Updated the following bundled components and third-party dependencies:
  - Jetty 9.4.44
  - JGroups 4.2.16
  - jose4j 0.7.9
  - Log4j 2.16.0
  - PingFederate Agentless Integration Kit 2.0.4
  - PingID Integration Kit 2.15.0
  - PingOne Integration Kit 2.4.1
  - Spring Framework 5.3.5

### Cluster dynamic OAuth/OpenID Connect keys

PF-20709 **Fixed**

Resolved an issue that sometimes caused a cluster's dynamic OAuth/OpenID Connect keys to fail to synchronize when a node restarts.

- Provisioning** PF-27519 **Fixed**  
 Resolved an issue that prevented a PingFederate provisioner from using a group of GUIDs as the source to detect new and removed records.
- Configuring the `favicon.ico` URL** PF-28074 **Fixed**  
 Now PingFederate correctly applies customizations of `response-header-runtime-config.xml` to the `favicon.ico` URL.
- Retrieving OAuth clients from Oracle databases** PF-28842 **Fixed**  
 Reduced the time it takes for PingFederate to retrieve OAuth clients from Oracle databases.
- Unnecessary dependency error banners** PF-29189 **Fixed**  
 Unnecessary dependency error banners no longer appear in the administrative console when you use the administrative API to modify selectors or service provider adapters.
- Localizing end user messages from the authentication API** PF-29202 **Fixed**  
 Now you can localize end user messages from the authentication API for registration failure scenarios.
- Device authorization flow using IdP connection OAuth attribute mapping** PF-29294 **Fixed**  
 Resolved an issue that stopped PingFederate from completing a device authorization flow when using IdP connection OAuth attribute mapping.
- Multiple Sign-On Delay template redirects** PF-29318 **Fixed**  
 When a proxy is in front of PingFederate, the Multiple Sign-On Delay template now redirects to the correct port.
- Logging `XMLCipher::decryptElement called without a key and unable to resolve`** PF-29350 **Fixed**  
 As a service provider (SP), when PingFederate can't decrypt an assertion using the primary encryption certificate, it now logs the following message at the WARN level instead of the ERROR level:  
`"XMLCipher::decryptElement called without a key and unable to resolve"`.
- Security vulnerability** PF-29381 **Fixed**  
 Resolved a potential security vulnerability caused by web server URI mishandling.
- Response headers for `/pf-ws` and `/pf-scim` endpoints** PF-29392 **Fixed**  
 Introduced the ability to add response headers to the `/pf-ws` and `/pf-scim` endpoints.
- Upgrade utility** PF-29470 **Fixed**  
 Fixed the upgrade utility so that, in non-interactive mode, it retains cipher related settings that are different from the default settings in the source version. PingFederate changes to new default settings on upgrade only if the settings have not been changed from the defaults in the source install.
- Custom template specified for the HTML Form Adapter** PF-29509 **Fixed**  
 Resolved an issue that caused PingFederate to render the default `forgot-password-error.html` template instead of the custom template specified in the **Password Reset Error Template** field for the HTML Form Adapter.
- Partial matches for resource URIs with OAuth 2.0 Token Exchange** PF-29668 **Fixed**  
 Resolved an issue that prevented the use of partial matches for resource URIs with OAuth 2.0 Token Exchange and produced the error message: `"Unable to find a token generation policy instance to issue a token"`.
- Adding attributes to data source lookups** PF-29795 **Fixed**  
 Now, when administrators add an attribute to a data source lookup but do not use the attribute anywhere, such as for contract mapping or issuance criteria, the attribute persists in the administrative console and API.

**Microsoft Active Directory LDIF script for persistent grant storage** PF-29847 **Fixed**

The Microsoft Active Directory LDIF script for persistent grant storage now creates an index for the `accessGrantGuid` attribute.

**Notification publisher** PF-29870 **Fixed**

Resolved the following notification publisher issues:

- When the SMTP server queues a message but has not sent it yet, the log now indicates that the message was queued, not that it was sent.
- PingFederate now respects the **Connection Timeout** setting for the notification publisher's SMTP server.
- Deprecated the **Retry Attempt** and **Retry Delay** fields for the notification publisher's SMTP server and removed them from the administrative console. PingFederate can still handle API configurations with those fields but they do nothing.

**Target resources that don't start with `http://` or `https://`** PF-30002 **Fixed**

Now target resources that don't start with `http://` or `https://` are also available for mapping and issuance criteria.

**Response code for an invalid transport method** PF-30039 **Fixed**

Now various endpoints return `400 Bad Request` instead of `500 Internal Server Error` when they receive requests with an invalid transport method. For example, calling the ACS endpoint with a `GET` instead of a `POST` now returns `400 Bad Request`.

**Custom IDP adapters that use the class for filterable dropdown controls** PF-30232 **Fixed**

The administrative console no longer shows an error message when you try to create an instance of a custom IDP adapter that uses the class for filterable dropdown controls, `ConnectionSelectionFieldDescriptor`.

**Memory usage during certificate revocation list (CRL) parsing** PF-30272 **Fixed**

Reduced memory usage during certificate revocation list (CRL) parsing, which speeds up CRL retrieval and avoids memory exhaustion in the case of very large CRLs.

**Administrative console and administrative API** **Issue**

- `/sp/idpConnections`: For identity provider (IdP) connections, the administrative API connection support is limited to Browser SSO, WS-Trust STS, and OAuth Assertion Grant connections. As a result, when updating an IdP connection using the administrative API, it is possible to lose inbound provisioning settings previously configured using the administrative console.
- `/bulk`: Only resource types currently supported by the administrative API are included in the exported data. Resources not yet supported include:
  - Identity Store Provisioners
  - Inbound provisioning settings from IdP connections
  - SMS Provider settings
- Previously, the administrative API did not accurately reflect a **Persistent Grant Max Lifetime** setting of 29 days (or shorter) with the selection of the **Grants Do Not Timeout Due To Inactivity** option. As a result, if you have configured such OAuth authorization server settings and have generated a bulk export in version 10.0 through 10.0.2, we recommend that you re-generate a new bulk export after upgrading to version 10.0.3 (or a more recent version). The newly exported data does not contain the aforementioned flaw, and you can safely import it to version 10.0.3 (or a more recent version).
- When enabling mutual TLS certificate-based authentication, administrators often configure a list of acceptable client certificate issuers. When an administrator uses a browser to access the console or the administrative API documentation, PingFederate returns to the browser the list of acceptable issuers as part of the TLS handshake. If the browser's client certificate store contains multiple client certificates, the browser often presents to the user only the certificates whose issuer matches one of the acceptable issuers. However, when PingFederate runs in a Java 11 environment, Chrome

presents to the administrator all its configured client certificates, regardless of whether the issuer matches one of the acceptable issuers or not.

- Prior to toggling the status of a connection with the administrative API, an administrator must ensure that any expired certificates or no longer available attributes are replaced with valid certificates or attributes; otherwise, the update request fails.
- When creating or updating a child instance of a hierarchical plugin, the administrative API retains objects with an `"inherited": false` name/value pair (or without such name/value pair altogether), ignores those with a value of `true`, and returns a 200 HTTP status code. No error messages are returned for the ignored objects.
- Using the browser's navigation mechanisms (for example, the **Back** button) causes inconsistent behavior in the administrative console. Use the navigation buttons provided at the bottom of windows in the PingFederate console.
- Using the PingFederate console in multiple tabs on one browser might cause inconsistent behavior which could corrupt its configuration.
- If authenticated to the PingFederate administrative console using certificate authentication, a session that has timed out might not appear to behave as expected. Normally (when using password authentication), when a session has timed out and a user attempts some action in the console, the browser is redirected to the login page, and then back to the administrative console after authentication is complete. Similar behavior applies for certificate authentication, in principle. However, because the browser might automatically resubmit the certificate for authentication, the browser might redirect to the administrative console and not the login page.

### TLsv1.3

**Issue**

For Java versions that don't support TLsv1.3 (meaning versions earlier than 8u261), PingFederate fails on start up with a `NoSuchAlgorithmException` exception. To resolve this error, remove `TLsv1.3` from the following settings in the `run.properties` file:

- `pf.tls.client.protocols`
- `pf.tls.runtime.server.protocols`
- `pf.tls.admin.server.protocols`

### TLS cipher suite customization

**Issue**

PingFederate's TLS cipher suites can be customized by modifying `com.pingidentity.crypto.SunJCEManager.xml` (or a similarly-named file if BCFIPS or a hardware security module (HSM) is configured). After updating the file and replicating, all cluster nodes must be restarted for the change to take effect.

### Updating Java 8 to Java 11

**Issue**

Updating Java version 8 to version 11 results in an error when PingFederate is already installed and running. To work around this issue, uninstall and reinstall the PingFederate Windows service by running the `UninstallPingFederateService.bat` and `InstallPingFederateService.bat` files located in `<pf_install>/pingfederate/sbin/wrapper`.

### Hardware security modules (HSM)

**Issue**

- For Entrust HSMs or AWS CloudHSM, PingFederate must be deployed with Oracle Server JRE 8 or Amazon Corretto 8.
- For Entrust HSMs, it is not possible to use an elliptic curve (EC) certificate as an SSL server certificate.
- For keys stored in Thales HSMs, JWT token decryption fails when using RSAES OAEP with AES-CBC-192 or AES-CBC-256. This issue only arises if PingFederate is configured with static OAuth and OpenID Connect keys and is consuming a token encrypted with one of these keys.
- When PingFederate is configured in hybrid mode with a Thales HSM, it is not possible to export a locally-stored EC key pair.
- When PingFederate is configured in hybrid mode with a Thales HSM, JWT token decryption using ECDH-ES may fail. This issue only arises if PingFederate is configured with static OAuth and OpenID

Connect keys, a static key is stored locally, and PingFederate is consuming a token encrypted with this key.

- TLS 1.3 is not currently supported with any HSM.

## SSO and SLO

Issue

- When consuming SAML metadata, PingFederate does not report an error when neither the `validUntil` nor the `cacheDuration` attribute is included in the metadata. Note that PingFederate does reject expired SAML metadata as indicated by the `validUntil` attribute value, if it is provided.
- The anchored-certificate trust model cannot be used with the SLO redirect binding because the certificate cannot be included with the logout request.
- If an IdP connection is configured for multiple virtual server IDs, PingFederate will always use the default virtual server ID for IdP Discovery during an SP-initiated SSO event.

## Composite Adapter configuration

Issue

SLO is not supported when users are authenticated through a Composite Adapter instance that contains another instance of the Composite Adapter.

## Self-service password reset

Issue

Passwords can be reset for Microsoft Active Directory user accounts without the permission to change password.

## OAuth

Issue

PingFederate does not support a case-sensitive naming convention for OAuth client ID values when client records are stored in a directory server. For example, after creating a client with an ID value of `sampleClient`, PingFederate does not allow the creation of another client with an ID value of `SampleClient`.

Although it's possible to create clients using the same ID values with different casings when client records are stored in XML files, a database server, or custom storage, we recommend not doing so to avoid potential record migration issues.

## Customer identity and access management

Issue

Some browsers display a date-picker user interface for fields that have been designed for date-specific inputs. Some browsers do not. If one or more date-specific fields are defined on the registration page or the profile management page (or both), end users must enter the dates manually if their browsers do not display a date-picker user interface for those fields.

## Provisioning

Issue

- LDAP referrals return an error and cause provisioning to fail if the `user` or `group` objects are defined at the DC level, and not within an OU or within the Users CN.
- The `totalResults` value in SCIM responses indicates the number of results returned in the current response, not the total number of estimated results on the LDAP server.

## Logging

Issue

- If a source attribute has been configured for masking in an IdP adapter or IdP connection and the source attribute is mapped to OAuth's persistent grant `USER_KEY` attribute, the `USER_KEY` attribute will not be masked in the server logs. Other persistent grant attributes will be masked.
- Even if a source attribute has been configured for masking in an IdP adapter and the source attribute is mapped as the adapter's unique user key, the user key attribute is not masked in the server or audit logs.

## Database logging

Issue

- If a source attribute has been configured for masking in an IdP adapter or IdP connection and the source attribute is mapped to OAuth's persistent grant `USER_KEY` attribute, the `USER_KEY` attribute will not be masked in the server logs. Other persistent grant attributes will be masked.

- Even if a source attribute has been configured for masking in an IdP adapter and the source attribute is mapped as the adapter's unique user key, the user key attribute is not masked in the server or audit logs.

### **RADIUS NAS-IP-Address**

**Issue**

The RADIUS NAS-IP-Address is only included in Access-Request packets when the `pf.bind.engine.address` is set with an IPv4 address. IPv6 is not supported.

### **Microsoft Internet Explorer 11**

**Info**

Ping Identity commits to deliver the best experience for administrators and users. As we continue to improve our products, we encourage our customers to migrate off of Microsoft Internet Explorer 11. Starting with PingFederate 11.0, Internet Explorer 11 is no longer included in the PingFederate qualification process for administrators or users. For a list of supported browsers, see [System requirements](#) on page 119.

### **Configcopy tool, Connection Management Service, SSO Directory Service**

**Info**

As of PingFederate 10.2, these features have been deprecated and will be removed in a future release.

### **Oracle Directory Server Enterprise Edition**

**Info**

As Oracle ended its Premier Support for Oracle Directory Server Enterprise Edition (ODSEE 11g) in December 2019, we no longer include ODSEE as part of the PingFederate qualification process (starting with PingFederate 10.2). We continue to qualify against [Oracle Unified Directory](http://www.oracle.com/middleware/technologies/unified-directory.html) (www.oracle.com/middleware/technologies/unified-directory.html) and other supported directory servers. For a full list, see [System requirements](#) on page 119.

### **SNMP**

**Info**

Starting with PingFederate 10.2, monitoring and reporting through the Simple Network Management Protocol (SNMP) has been removed.

### **Roles and protocols**

**Info**

Starting with PingFederate 10.1, roles and protocols are always enabled and no longer configurable through the administrative console and API.

### **S3\_PING discovery protocol**

**Info**

Starting with PingFederate 10.1, the S3\_PING discovery protocol has been deprecated. Customers running on AWS infrastructure should instead use NATIVE\_S3\_PING.

### **Red Hat Enterprise Linux install script**

**Info**

Starting with PingFederate 10.0, the Red Hat Enterprise Linux install script is no longer available. To install PingFederate 10.0 for Linux, you must download and extract the product distribution `.zip` file.

## **Previous releases**

---

For information about enhancements and issues resolved in previous releases of PingFederate, follow the links below to their release notes.


- [10.3 June 2021](#)
- [10.2 December 2020](#)
- [10.1 June 2020](#)
- [10.0 December 2019](#)
- [9.3 June 2019](#)
- [9.2 December 2018](#)
- [9.1 June 2018](#)
- [9.0 December 2017 and previous releases](#)



# Introduction to PingFederate

PingFederate is an enterprise federation server and identity bridge for user authentication and standards-based single sign-on (SSO) for employee, partner, and customer identity types.

PingFederate enables outbound and inbound solutions for SSO, federated identity management, customer identity and access management, mobile identity security, API security, and social identity integration. Browser-based SSO extends employee, customer, and partner identities across domains without passwords using standard identity protocols, such as SAML, WS-Federation, WS-Trust, OAuth, OpenID Connect, and System for Cross-domain Identity Management (SCIM).



## About identity federation and SSO

Federated identity management, or identity federation, allows enterprises to exchange identity information securely across domains, providing browser-based single sign-on (SSO).

Identity federation also integrates access to applications across distinct business units within a single organization. As organizations grow through acquisitions, or when business units maintain separate user repositories and authentication mechanisms across applications, a federated solution to browser-based SSO is desirable.

This cross-domain, identity-management solution provides numerous benefits, ranging from increased end user satisfaction and enhanced customer relations to reduced cost and greater security and accountability.


For complete information about identity federation and the standards that support it, see [Supported standards](#) on page 34.

## Service providers and identity providers

Identity federation standards identify two operational roles in an SSO transaction: the identity provider (IdP) and the service provider (SP).

An IdP might be an enterprise that manages accounts for a large number of users who need secure access to the web-based applications or services of customers, suppliers, and business partners. An

SP might be a SaaS provider or a business-process outsourcing (BPO) vendor wanting to simplify client access to its services.



### Secure single sign-on

Identity federation allows both types of organizations to define a trust relationship whereby the SP provides access to users from the IdP. The IdP continues to manage its users, and the SP trusts the IdP to authenticate them.

A single instance of PingFederate provides complete support for both roles even when a single organization's business processes encompass both SP and IdP use cases.

### Federation hub


As a federation hub, PingFederate can bridge browser-based SSO between IdPs and SPs, reducing administrative overhead.

Identity federation refers to the negotiation and management of federation settings with partners. Supporting different federation protocols can hinder application development and SSO implementation.

Configuring PingFederate as a federation hub:

- Allows you to simplify application development and SSO implementation by extending federated access across partners supporting different federation standards
- Provides a centralized console to simplify SSO administration

Bridging IdPs and SPs through a federation hub allows you to multiplex a single connection for multiple partners.



### Supported standards

PingFederate supports a variety of federation roles, protocols, and standards.

PingFederate provides flexible, integrated support for the SAML protocols, WS-Federation, OAuth, OpenID Connect, and WS-Trust. In addition, PingFederate supports System for Cross-domain Identity Management (SCIM) for inbound and outbound provisioning.

## Federation roles

A variety of federation roles work together in an identity federation partnership.

The most recent sets of standards, SAML 2.0 and WS-Federation, define two roles in an identity federation partnership: an identity provider (IdP) and a service provider (SP).



### Note:

Earlier SAML 1.x specifications used the terms asserting party (for IdP) and relying party (for SP). For consistency and clarity, PingFederate adopts the later terms IdP and SP across all specifications.

A third role, defined in the SAML 2.0 specifications and available in PingFederate, is that of an IdP Discovery provider.

OAuth 2.0 and OpenID Connect 1.0 can configure PingFederate as an authorization server (AS), an OpenID provider (OP), and a relying party (RP).

### Identity provider

An IdP, also called the SAML authority, is a system entity that authenticates a user, or SAML subject, and transmits referential identity information based on the authentication.



### Note:

The SAML subject may be a person, a web application, or a web server. Since the SAML subject is often a person, our documentation employs the term "user" throughout.

### Service provider

An SP is the consumer of identity information provided by the IdP. Based on trust, technical agreements, and verification of adherence to protocols, SP applications and systems determine how to use information contained in an SSO token: a SAML assertion, a JSON Web Token (JWT), or an OAuth access token in conjunction with an ID token.

### IdP Discovery provider

This role provides an IdP look-up service that can be incorporated into the implementation of either an IdP or an SP, or employed as a standalone server.

### Authorization server

An OAuth authorization server issues access tokens and refresh tokens to OAuth clients after the resource owner fulfills the authentication requirement.

### OpenID provider

An OpenID provider (OP) is an AS that is capable of authenticating the resource owner and providing claims (user attributes) to an RP about the authentication event and the user.

## Terminology

Definitions for the list of SAML specifications that provide a system of building blocks and support components for achieving secure data exchange in an identity federation.

The list of SAML specifications includes:

- Assertions
- Bindings

- Profiles
- Metadata
- Authentication Context

## Assertions

Assertions are XML documents sent from an identity provider (IdP) to a service provider (SP). Each assertion contains identifying information about a user who has initiated a single sign-on (SSO) request.

## Bindings

A SAML binding describes the way transport protocols exchange messages. PingFederate supports the following bindings:

### HTTP POST

Describes how to transport SAML messages in HTML form-control content, which uses a base-64 format.

### HTTP Artifact

Describes how to use an artifact to represent a SAML message. An HTML form control or a query string in the URL transports the artifact.

### HTTP Redirect (SAML 2.0)

Describes how to transport SAML messages using HTTP 302 status-code response messages.

### SOAP (SAML 2.0)

Describes how to transfer SAML messages across the back channel.

## Profiles

Profiles describe processes and message flows combining assertions, request/response message specifications, and bindings to achieve a specific desired functionality or use case. Profiles define the application of the specifications and play a large part in PingFederate.

## Metadata

SAML 2.0 defines an XML schema to standardize metadata to facilitate the exchange of configuration information among federation partners, such as profile and binding support, connection endpoints, and certificate information.

Whether you publish or consume metadata, PingFederate supports the use of XML digital signatures to ensure the integrity of the data.

## Authentication context

Before allowing access to a protected resource, an SP might want information about the assertion and the user's original authentication by the IdP. The SP uses this information for an access control decision or to provide an audit trail for regulatory or security-policy compliance.

The SAML 2.0 specification provides an XML schema whereby partners create authentication-context declarations. Partners might choose to reference a URI to implement a set of classes provided by the specification to help categorize and simplify context interpretation (see the OASIS document: [Authentication Context for the OASIS Security Assertion Markup Language \(SAML\) V2.0](#)). However, it is up to partners to decide if they require additional authentication context and if these classes supply an adequate description. For SAML 1.x, if using the authentication context, called AuthenticationMethod, the context must appear as a URI (see [oasis-sstc-saml-core-1.1.pdf](#)).

An administrator can configure PingFederate, acting as an IdP, to include a specific authentication context in assertions for browser SSO or WS-Trust.

Several PingFederate integration kits provide methods for the developer to insert authentication context from external IdP applications into the assertion. The SP developer has the option to:

- Call methods for extracting authentication context from an assertion.
- Work with the application to create access control or other processing based on the context.

## Browser-based SSO

Browser-based single sign-on (SSO) includes [SAML 1.x profiles](#) on page 37, [SAML 2.0 profiles](#) on page 40, [WS-Federation](#) on page 50, and [OpenID Connect](#) on page 91 and provides standards-based SSO, single logout (SLO), attribute query and X.509 attribute sharing profile (XASP), and the WS-Federation Passive Requestor Profile for service provider (SP)-initiated SSO.


### SAML 1.x profiles

SAML 1.0 and 1.1 profiles provide for browser-based single sign-on (SSO), initiated by an identity provider (IdP), using either the POST or artifact bindings.

The SAML 1.x specifications provide for a non-normative service provider (SP)-initiated scenario called “destination-first.” This scenario lets web developers create applications that enable a user to initiate SSO from the SP site.

### SSO—Browser-POST

In this scenario, a user logged on to the identity provider (IdP) attempts to access a resource on a remote service provider (SP) server. HTTP POST transports the SAML assertion to the SP.



### SSO—Browser-POST profile

### Processing steps

1. A user logs on to the IdP.  
If a user is not logged on for some reason, the IdP challenges them to do so at step 2.
2. The user clicks a link or otherwise requests access to a protected SP resource.
3. Optionally, the IdP retrieves attributes from the user data source.
4. The IdP's SSO service returns an HTML form to the browser with a SAML response containing the authentication assertion and any additional attributes. The browser automatically posts the HTML form back to the SP.




#### Note:

SAML specifications require digitally-signed POST responses.

5. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

### SSO—Browser-Artifact

In this scenario, the identity provider (IdP) sends a SAML artifact to the service provider (SP) through either HTTP POST or a redirect. The SP uses the artifact to obtain the associated SAML response from the IdP.



### SSO—Browser-Artifact profile


#### Processing steps

1. A user logs on to the IdP.  
If a user is not logged on for some reason, the IdP challenges them to do so at step 2.
2. The user clicks a link or otherwise requests access to a protected SP resource.
3. Optionally, the IdP retrieves attributes from the user datastore.

4. The IdP federation server generates an assertion, creates an artifact, and sends an HTTP redirect containing the artifact through the browser to the SP's Assertion Consumer Service (ACS).
5. The ACS extracts the Source ID from the SAML artifact and sends an artifact-resolve message to the identity federation server's Artifact Resolution Service (ARS).
6. The ARS sends a SAML artifact response message containing the previously-generated assertion.
7. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

### SP-initiated (destination-first) SSO

In service provider (SP)-initiated, destination-first transactions, the user connects to an SP site and attempts to access a protected resource in the SP domain. The user might have an account at the SP site, but according to the federation agreement, the identity provider (IdP) manages authentication. The SP sends an authentication request to the IdP.



### SP-initiated SSO

#### Processing steps

1. The user requests access to a protected SP resource. The request redirects to the federation server to handle authentication.
2. The federation server sends a SAML request for authentication to the IdP's single sign-on (SSO) service, also called the Intersite Transfer Service.
3. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.
4. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
5. The IdP's Intersite Transfer Service returns an artifact representing the SAML response to the SP.
6. The SP's artifact handling service sends a SOAP request with the artifact to the IdP's artifact resolver endpoint.
7. The IdP resolves the artifact and returns the corresponding SAML response with the SSO assertion.

8. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

## SAML 2.0 profiles

PingFederate supports the following major profiles defined under the SAML 2.0 standard:

- [Single sign-on](#) on page 40 (SSO)
- [Single logout](#) on page 49 (SLO)
- [Attribute Query and XASP](#) on page 49
- [Standard IdP Discovery](#) on page 50

## Single sign-on

Pairing service provider (SP)- and identity provider (IdP)-initiated protocols with transport-binding specifications results in eight practical SSO scenarios.


Enabling SP-initiated transactions through SAML 2.0 increases the number of possible SSO profile variations. The following profile variations each illustrate a specific scenario:

- [SP-initiated SSO—POST-POST](#) on page 40 A user attempts to access a protected resource directly on an SP website without logging on. The user does not have an account on the SP site but does have a third-party IdP-federated account. The SP sends an authentication request to the IdP. The user's browser sends both the request and the returned SAML assertion through HTTP POST.
- [SP-initiated SSO—Redirect-POST](#) on page 42 The SP sends an HTTP redirect message to the IdP containing an authentication request. The IdP returns a SAML response with an assertion to the SP via HTTP POST
- [SP-initiated SSO—Artifact-POST](#) on page 43 The SP sends a SAML artifact to the IdP through an HTTP redirect. The IdP uses the artifact to obtain an authentication request from the SP's SAML artifact resolution service. The IdP returns a SAML response to the SP via HTTP POST.
- [SP-initiated SSO—POST-Artifact](#) on page 44 the SP sends an authentication request to the IdP through HTTP POST. The returned SAML assertion is redirected through the user's browser. The response contains a SAML artifact.
- [SP-initiated SSO—Redirect-Artifact](#) on page 45 The SP sends an HTTP redirect message to the IdP containing a request for authentication. The IdP returns an artifact through HTTP redirect. The SP uses the artifact to obtain the SAML response.
- [SP-initiated SSO—Artifact-Artifact](#) on page 46 The SP sends a SAML artifact to the IdP through an HTTP redirect. The IdP uses the artifact to obtain an authentication request from the SP, and then the IdP sends another artifact to the SP, which the SP uses to obtain the SAML response.
- [IdP-initiated SSO—POST](#) on page 47 A user is logged on to the IdP and attempts to access a resource on a remote SP server. The SAML assertion is transported to the SP through HTTP POST.
- [IdP-initiated SSO—Artifact](#) on page 48 The IdP sends a SAML artifact to the SP through an HTTP redirect. The SP uses the artifact to obtain the associated SAML response from the IdP.

### *SP-initiated SSO—POST-POST*

In this scenario, a user attempts to access a protected resource directly on a service provider (SP) website without logging on. The user does not have an account on the SP site but does have a third-party identity provider (IdP)-federated account. The SP sends an authentication request to the IdP. The user's browser sends both the request and the returned SAML assertion through HTTP POST.





### SP-initiated SSO—POST-POST

#### Processing steps

1. The user requests access to a protected SP resource. The request redirects to the federation server to handle authentication.
2. The federation server sends an HTML form back to the browser with a SAML request for authentication from the IdP. The HTML form automatically posts to the IdP's SSO service.
3. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.
4. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
5. The IdP's SSO service returns an HTML form to the browser with a SAML response containing the authentication assertion and any additional attributes. The browser automatically posts the HTML form back to the SP.


 **Note:**

SAML specifications require digitally-signed POST responses.

6. (Not shown) If the signature and the assertion, or the JSON Web Token, are valid, the SP establishes a session for the user and redirects the browser to the target resource.

*SP-initiated SSO—Redirect-POST*

In this scenario, the service provider (SP) sends an HTTP redirect message to the identity provider (IdP) containing an authentication request. The IdP returns a SAML response with an assertion to the SP through HTTP POST.

**SP-initiated SSO: redirect/POST**

## Processing steps

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request redirects to the federation server to handle authentication.
2. The SP returns an HTTP redirect code, 302 or 303, containing a SAML request for authentication through the user's browser to the IdP's single sign-on (SSO) service.
3. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.
4. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
5. The IdP's SSO service returns an HTML form to the browser with a SAML response containing the authentication assertion and any additional attributes. The browser automatically posts the HTML form back to the SP.


**Note:**

SAML specifications require digitally-signed POST responses.

6. (Not shown) If the signature and the assertion, or the JSON Web Token, are valid, the SP establishes a session for the user and redirects the browser to the target resource.

*SP-initiated SSO—Artifact-POST*

In this scenario, the service provider (SP) sends a SAML artifact to the identity provider (IdP) through an HTTP redirect. The IdP uses the artifact to obtain an authentication request from the SP's SAML artifact resolution service (ARS), and the IdP returns a SAML response to the SP through HTTP POST.

**SP-initiated SSO—Artifact-POST**

## Processing steps

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request redirects to the federation server to handle authentication.
2. The SP generates an authentication request and creates an artifact. The SP sends an HTTP redirect containing the artifact through the user's browser to the IdP's single sign-on (SSO) service.

**Note:**

The artifact contains the source ID of the SP's artifact resolution service and a reference to the authentication.

3. The SSO service extracts a source ID from the SAML artifact and sends a SAML artifact-resolve message over SOAP containing the artifact to the SP's ARS.

**Note:**

The federation agreement made prior to this action maps the SP and IdP's source IDs and remote ARS.

4. The SP's ARS returns a SAML message containing the previously-generated authentication request.
5. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.

6. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
7. The IdP's SSO service returns an HTML form to the browser with a SAML response containing the authentication assertion and any additional attributes. The browser automatically posts the HTML form back to the SP.


**Note:**

SAML specifications require digitally-signed POST responses.

8. (Not shown) If the signature and the assertion, or the JSON Web Token, are valid, the SP establishes a session for the user and redirects the browser to the target resource.

**SP-initiated SSO—POST-Artifact**

In this single sign-on (SSO) scenario, the service provider (SP) sends an authentication request to the identity provider (IdP) through HTTP POST. The returned SAML assertion redirects through the user's browser, and the response contains a SAML artifact.


**SP-initiated SSO—POST-Artifact****Processing steps**

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request redirects to the federation server to handle authentication.
2. The federation server sends an HTML form back to the browser with a SAML request for authentication from the IdP. The HTML form automatically posts to the IdP's SSO service.
3. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.

4. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
5. The IdP federation server generates an assertion, creates an artifact, and sends an HTTP redirect containing the artifact through the browser to the SP's Assertion Consumer Service (ACS).
6. The ACS extracts the source ID from the SAML artifact and sends an artifact-resolve message to the federation server's Artifact Resolution Service (ARS).
7. The ARS sends a SAML artifact response message containing the previously-generated assertion.
8. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

#### SP-initiated SSO—Redirect-Artifact

In this scenario, the service provider (SP) sends an HTTP redirect message to the identity provider (IdP) containing a request for authentication. The IdP returns an artifact through HTTP redirect, and the SP uses the artifact to obtain the SAML response.



#### SP-initiated SSO—Redirect-Artifact


##### Processing steps

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request redirects to the federation server to handle authentication.
2. The SP returns an HTTP redirect, either code 302 or 303, containing a SAML request for authentication through the user's browser to the IdP's single sign-on (SSO) service.
3. If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.
4. The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.

5. The IdP federation server generates an assertion, creates an artifact, and sends an HTTP redirect containing the artifact through the browser to the SP's Assertion Consumer Service (ACS).
6. The ACS extracts the Source ID from the SAML artifact and sends an artifact-resolve message to the identity federation server's Artifact Resolution Service (ARS).
7. The ARS sends a SAML artifact response message containing the previously-generated assertion.
8. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

#### SP-initiated SSO—Artifact-Artifact

In this scenario, the service provider (SP) sends a SAML artifact to the identity provider (IdP) through an HTTP redirect. The IdP uses the artifact to obtain an authentication request from the SP, then the IdP sends another artifact to the SP, which the SP uses to obtain the SAML response.



#### SP-initiated SSO—Artifact-Artifact

##### Processing steps

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request redirects to the federation server to handle authentication.
2. The Assertion Consumer Service (ACS) generates an authentication request and creates an artifact. It sends an HTTP redirect containing the artifact through the user's browser to the IdP's single sign-on (SSO) service.

##### Note:

The artifact contains the source ID of the SP's Artifact Resolution Service (ARS) and a reference to the authentication request.

- The SSO service extracts the source ID from the SAML artifact and sends a SAML artifact resolve message containing the artifact to the SP's artifact resolution service.




**Note:**

The federation agreement maps the SP and IdP's source IDs and remote artifact resolution services prior to this action.

- The SP's artifact resolution service sends back a SAML artifact response message containing the previously-generated authentication request.
- If the user is not already logged on to the IdP site or needs to re-authenticate, The IdP asks for credentials, such as ID and password, and the user logs on.
- The user data store can provide additional information about the user for inclusion in the SAML response. The federation agreement between the IdP and the SP predetermines these attributes. See [User attributes](#) on page 101.
- The IdP federation server generates an assertion, creates an artifact, and sends an HTTP redirect containing the artifact through the browser to the SP's Assertion Consumer Service (ACS).
- The ACS extracts the Source ID from the SAML artifact and sends an artifact-resolve message to the identity federation server's Artifact Resolution Service (ARS).
- The ARS sends a SAML artifact response message containing the previously-generated assertion.
- (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

*IdP-initiated SSO—POST*

In this scenario, a user is logged on to the identity provider (IdP) and attempts to access a resource on a remote service provider (SP) server. HTTP POST transports the SAML assertion to the SP.



**IdP-initiated SSO--POST**

## Processing steps

1. A user logs on to the IdP.

If a user is not yet logged on for some reason, he or she is challenged to do so at step 2.

2. The user requests access to a protected SP resource.
3. After the user requests access, the IdP might also retrieve attributes from the user datastore..
4. The IdP's SSO service returns an HTML form to the browser with a SAML response containing the authentication assertion and any additional attributes. The browser automatically posts the HTML form back to the SP.


**Note:**

SAML specifications require digitally-signed POST responses.

5. (Not shown) If the signature and the assertion, or the JSON Web Token, are valid, the SP establishes a session for the user and redirects the browser to the target resource.

*IdP-initiated SSO—Artifact*

In this single sign-on (SSO) scenario, the identity provider (IdP) sends a SAML artifact to the service provider (SP) through an HTTP redirect. The SP uses the artifact to obtain the associated SAML response from the IdP.

**IdP-initiated SSO--Artifact**

## Processing steps

1. A user logs on to the IdP.

If a user has not yet logged on for some reason, he or she is challenged to do so at step 2.

2. The user clicks a link or otherwise requests access to a protected SP resource.
3. After the user requests access, the IdP might also retrieve attributes from the user datastore.



4. The IdP federation server generates an assertion, creates an artifact, and sends an HTTP redirect containing the artifact through the browser to the SP's Assertion Consumer Service (ACS).
5. The ACS extracts the Source ID from the SAML artifact and sends an artifact-resolve message to the identity federation server's Artifact Resolution Service (ARS).
6. The ARS sends a SAML artifact response message containing the previously-generated assertion.
7. (Not shown) If the IdP returns a valid SAML assertion to the SP, a session is established on the SP and the browser is redirected to the target resource.

### Single logout

The single logout (SLO) profile enables users to log out of all participating sites in a federated session from any site.

The associated identity provider (IdP) federation deployment manages all logout requests and responses for participating sites. If a participating site returns an error, other participating sites might not receive their logout requests. In this scenario, PingFederate returns an error message to the end users.

The logout messages can be transported using any combination of bindings described for SSO (POST, artifact, or redirect). See the diagrams under [SAML 2.0 profiles](#) on page 40 for illustrations of these message flows.

#### About session cleanup

When a service provider (SP) receives an SLO request from an IdP, the session creation adapters must handle any session clean-up involving the local application.

### Attribute Query and XASP

The SAML 2.0 Attribute Query profile allows a service provider (SP) to request user attributes from an identity provider (IdP) in a secure transaction separate from single sign-on (SSO). The X.509 Attribute Sharing Profile (XASP) defines a specialized extension of the general Attribute Query profile.

The IdP, acting as an attribute authority, accepts attribute queries, performs a datastore lookup into a user repository such as an LDAP directory, provides values to the requested attributes, and generates an attribute response back to the originating SP requester. The SP then returns the attributes to the requesting application.



#### Tip:

When privacy is required for sensitive attributes, you can configure PingFederate to obfuscate, or mask, their values in the server and transaction logs.

Web SSO is distinct from the Attribute Query use case. You can configure PingFederate servers to implement either of these profiles without regard to the other.

The XASP specification enables organizations with an investment in Public Key Infrastructure (PKI) to issue and receive Attribute Queries based on user-certificate authentication.

Under XASP a user authenticates directly with an SP application by providing their X.509 certificate. After the user is authenticated, the SP application requests additional user attributes by contacting the SP PingFederate server. A portion of the user's X.509 certificate is included in the request and can be used to determine the correct IdP to use as the source of the requested attributes. Finally, the SP generates an Attribute Query and transmits it to the IdP over the SOAP back channel.

Because the user arrives at the SP server already authenticated, no PingFederate adapter is used in this case.

### Standard IdP Discovery

SAML 2.0 identity provider (IdP) Discovery provides a cookie-based look-up, when the IdP is not otherwise specified, to dynamically identify a user's IdP during a service provider (SP)-initiated single sign-on (SSO) event.

This mechanism is helpful in cases where an SP is a hub for several IdPs in an identity federation.



#### Tip:

In addition to supporting standard IdP Discovery, PingFederate provides a cross-protocol, proprietary mechanism that allows an SP server to write a persistent browser cookie. The cookie contains a reference to the previous IdP-authentication partner for SSO. For more information, see [Configuring IdP discovery using a persistent cookie](#) on page 819.

In the standard scenario, when a user requests access to a protected resource on the SP, common-domain browser cookies are used to determine where a user has previously authenticated. Using this information, a PingFederate server can determine which IdP connection to use for sending an authentication request.

PingFederate can serve in up to three different IdP Discovery provider roles: common domain server, common domain cookie writer, and common domain cookie reader. Each of these roles is necessary to support IdP Discovery. The roles can be distributed across multiple servers at different sites.

#### Common domain server

In this role, the PingFederate server hosts a domain that its federation partners share in common. The common domain server allows partners to manipulate browser cookies that exist within that common domain. PingFederate can serve in this role exclusively or as part of either an IdP or an SP federation role, or both.

#### Common domain cookie writer

When PingFederate is acting in an IdP role and authenticates a user, it can write an entry in the common domain cookie, including its federation entity ID. An SP can look up this information on the common domain (not the same location as the common domain server described above).

#### Common domain cookie reader

When PingFederate is acting as an SP and needs to determine past IdP authentications, it reads the common domain cookie. Based on the information contained in the cookie, PingFederate can then initiate an SSO authentication request using the correct IdP connection.

### WS-Federation

PingFederate supports the WS-Federation Passive Requestor Profile for service provider (SP)-initiated single sign-on (SSO), enabling interoperability with Microsoft's Active Directory Federation Service (ADFS).

This profile allows for straightforward redirects and HTTP GET and POST methods to transport SAML assertions or JSON web tokens (JWTs) as security tokens for SSO and logout request and response messages for single logout (SLO).




#### Note:

Unlike SAML, WS-Federation consolidates the endpoints for SLO and SSO. When you set up a WS-Federation connection in PingFederate, both types of transactions are available to an SP web application that supports them both.

For more information about WS-Federation and the Passive Requestor Profile, see [web services Federation Languages](#).

### Passive Requestor profile

This profile permits a user's browser, the passive requestor, to request a security token from an identity provider (IdP) when the user requests access to a protected web service or other resource at an SP.



### WS-Federation SSO

Processing steps:

1. A user requests access to a protected SP resource. The user is not logged on to the site. The request is redirected to the federation server to handle authentication.
2. The SP generates a security token request and redirects the browser to the identity provider's WS-Federation implementation.
3. If the user is not already logged on to the IdP site or if re-authentication is required, the IdP asks for credentials, such as ID and password, and the user logs on.
4. Additional information about the user can be retrieved from the user datastore for inclusion in the SAML response. These attributes are predetermined as part of the federation agreement between the IdP and the SP. For more information, see [User attributes](#) on page 101.
5. The federation server creates a response containing a signed SAML assertion, or a JSON Web Token, and returns it to the SP through POST.
6. (Not shown) If the signature and the assertion, or the JWT, are valid, the SP establishes a session for the user and redirects the browser to the target resource.


Single logout using WS-Federation is handled in much the same way as with SAML. For more information, see [Single logout](#) on page 49. However, HTTP GET/POST is always used as the transport mechanism.

### About account linking

Account linking provides a means for a user to log on to disparate sites with just one authentication when the user has established accounts and credentials at each site.

All protocols support this method of interconnecting accounts across domains.

Account linking involves a persistent name identifier associated with accounts at each participating site. The assertion conveys the name identifier, which can be an opaque pseudonym. Once established locally, the service provider (SP) can use the account link to look up the user and provide access without re-authentication.



### Account linking

#### Processing steps

1. David Smith logs on to Site A as *dauidsmith*. He then decides to access his account on Site B through Site A.
2. Optionally, the federation server looks up additional attributes from the datastore.
3. The Site A federation server sends a persistent name identifier to Site B, along with any other attributes.

#### Note:

When using a pseudonym and sending other attributes, be careful not to send attributes that could identify the subject.

4. The federation server on Site B uses the information to associate the pseudonym with the existing account of *dsmith* and optionally might ask David to provide consent to the linking.

Once the link has been established, Site B stores the information so that David only has to log on to Site A to access Site B.

## Web services standards

The PingFederate WS-Trust security token service (STS) interoperates with many different web-service environments that support varying standards.

PingFederate supports multiple versions of SOAP and WS-Trust specifications and operates with any combination of these standards simultaneously.

PingFederate supports namespace aliasing to eliminate common trailing-slash inconsistencies for WS-Trust 1.3. The server does not support namespace aliasing for WS-Trust 2005.

The following table lists supported SOAP/WS-Trust versions and corresponding namespaces.

### SOAP/WS-Trust versions

| Spec     | Version | Namespace   |
|----------|---------|---|
| SOAP     | 1.1     | http://schemas.xmlsoap.org/soap/envelope/         |
|          | 1.2     | http://www.w3.org/2003/05/soap-envelope           |
| WS-Trust | 2005    | http://schemas.xmlsoap.org/ws/2005/02/trust/      |
|          | 1.3     | http://docs.oasis-open.org/ws-sx/ws-trust/200512/ |

### Web Services Security

Web Services Security (WSS or WSSE) is a set of specifications defined by the OASIS Web Services Security (WSS) Technical Committee..

WSS defines XML extensions used to secure web service invocations, providing a standard way for partners to add message integrity and confidentiality to web service interactions. The WSS-defined token profiles describe standard ways of binding security tokens to these messages, enabling a variety of additional capabilities. Defined profiles include SAML assertions, Username, Kerberos, X.509, and other existing security tokens. SSL/TLS is often used in conjunction with deployments of WSS. For more information see [https://www.oasis-open.org/committees/tc\\_home.php?wg\\_abbrev=wss](https://www.oasis-open.org/committees/tc_home.php?wg_abbrev=wss).



#### Note:

The implementation of WSS in the deployment of web services identity federations is outside the scope of PingFederate, which provides a standalone, standard means of handling the tokens needed for such federations. See [WS-Trust](#) on page 54.



### WSS token transfer

#### Processing steps

1. A user requests content from an application.
2. The web service client sends a web service request to the WSP, including the SAML assertion in a WSS header.

3. The WSP responds to the request and sends an SSL/TLS token back to the application.
4. The web service client returns an HTML page to the user.

### WS-Trust

WS-Trust comprises a protocol that systems and applications use when requesting a service to issue, validate, and exchange security tokens.

Organizations can leverage WS-Trust to centralize their security-token processing. The WS-Trust specification defines the role of a Security Token Service (STS) as the entity responsible for responding to requests using the protocol. In this role, the STS creates new security tokens, validates existing security tokens, exchanges security tokens of one type for those of another, or any combination of these.

The WS-SX (Secure Exchange) technical committee manages the WS-Trust specification through its contribution to the OASIS standards organization. For more information, see [www.oasis-open.org/committees/tc\\_home.php?wg\\_abbrev=ws-sx](http://www.oasis-open.org/committees/tc_home.php?wg_abbrev=ws-sx).


### Request types

The WS-Trust protocol defines two request types in securing web services: Issue and Validate, often associated with the web service client (WSC) and web service provider (WSP), respectively.

- The WSC requests that a security token service (STS) issue a SAML token to convey information between the WSC and the WSP.
- The WSP sends the STS a request to validate the incoming token. Optionally, the WSP can request that the STS issue a local token for the service provider (SP) domain.

When issuing and validating security tokens, PingFederate enforces security policies, defined by administrators, generating the token types that are required for a web service request to pass between two security domains (whether these domains are within the same organization or in separate organizations).

### Token exchange (example)



### Processing steps

1. A user requests content from an application.

2. The application acts as a WSC to respond to the user's request. The application calls PingFederate, passing the existing user security token to exchange it for the appropriate SAML assertion.
3. PingFederate verifies the existing security token, creates a new SAML assertion representing the user, and returns it to the requesting application.
4. The application sends a web service request to the WSP, including the SAML assertion in a WS-Security header.
5. The WSP retrieves the SAML assertion from the WS-Security header in the incoming request and sends a message to its own deployment of PingFederate to determine if the assertion is valid.
6. PingFederate validates the SAML assertion, creates a new security token for the local domain, and returns the new token to the WSP.
7. The WSP responds to the request according to its policy for the user.
8. The web application returns an HTML page to the user.



**Note:**

This example shows PingFederate deployed in both the WSC and WSP sides of the interaction. However, other deployment options are also supported.

## OAuth 2.0 and PingFederate AS

OAuth 2.0 defines a protocol for securing application access to protected resources by issuing access tokens to clients of REST APIs and non-REST APIs.

Instead of the client directly authenticating to the API using credentials, or the credentials of a user, OAuth enables the client to authenticate by presenting a previously-obtained token. The token represents or contains a set of attributes, policies, or both appropriate to the client and the user. Using these tokens is more secure than using passwords directly on the API call. The attributes are used by the API to authenticate the call and authorize access.

### Participants

#### Client

Wants access to a resource protected by a resource server and interacts with an authorization server to obtain access tokens.

#### Resource server (RS)

Hosts and protects resources and makes them available to authenticated and authorized clients.

#### Authorization server (AS)

Issues access tokens and refresh tokens to clients on behalf of the resource servers.

#### Resource owner (RO)

Denies, grants, or revokes authorization to a client requesting access to resources protected by the resource servers.

### Tokens

#### Access token

Allows clients to authenticate to a resource server and claim authorizations for accessing particular resources. Access tokens have specific authorization scope and duration.

#### Refresh token

Allows clients to obtain a fresh access token without re-obtaining authorization from the resource owner. A refresh token is a long-lived token that a client can trade in to an authorization server to

obtain a new short-lived access token with the same attached authorizations as the existing access token.


## PingFederate OAuth AS

Based on the Internet Engineering Task Force (IETF) [OAuth 2.0 Authorization Framework](#), the OAuth AS in PingFederate supports several interaction models for different types of clients such as servers, desktop applications, or mobile applications. Administrators can also enable Cross-origin Resource Sharing (CORS) support for OAuth endpoints.

### Web redirect flow

The web redirect flow process takes place between the user, website, PingFederate authorization server (AS), and resource server (RS).

In this scenario, a user attempts to access a protected resource through a third-party web server client. The client sends an authorization request to the resource server, and receives an authorization code back through a HTTP redirect. The client trades the authorization code for an access token, and uses the token in an API call to obtain data.



### Web redirect flow

#### Processing steps

1. User navigates to an OAuth client website and requests access to protected resources from another website. Flow chart depicting the process of web redirect flow between the User/Browser, Website (client), PingFederate AS and RS.

#### Note:

To reduce the risk of code interception attack, the OAuth client can optionally include the parameter `code_challenge` with or without `code_challenge_method`. For more information, see step 3 and



*Flow chart depicting the process of web redirect flow between the User/Browser, Proof Key for Code Exchange by (PKCE) OAuth Public Clients.*

- The browser is redirected to the PingFederate OAuth AS with a request for authorization.

If the user is not logged on, the OAuth AS challenges the user to authenticate. The OAuth AS authenticates the user and prompts for authorization. After the user authorizes, the OAuth AS redirects the browser to the requesting site with an authorization code. If the user does not authenticate, the OAuth AS returns an error rather than the authorization code.

- The requesting site makes a HTTPS request to the OAuth AS to exchange the authorization code for an access token.

 **Note:**

If the OAuth client has provided the optional parameter `code_challenge` in step 1, it must submit the corresponding `code_verifier` in this request.


The OAuth AS validates the grant and user data associated with the code and then returns an access token.

- The requesting site uses the access token in an API call to request user data.
- The RS asks PingFederate for verification that the token is valid and has not expired. PingFederate returns data about the user, the granted scope, and the client ID.
- Once verified, the RS returns the requested data to the requesting site.
- The requesting site displays data from the API call to the user.

### Device authorization grant

The device authorization grant process takes place between the user, device, PingFederate authorization server (AS), and resource server (RS).

In this scenario, a user attempts to access a protected resource through a device client that lacks a browser or has limited user-input capabilities, such as a smart TV, digital picture frame, or printer. The OAuth device authorization grant type allows a user to grant authorization to the device client using a browser on a second device, such as a smart phone or computer. For more information about the grant type, see the [OAuth 2.0 Device Authorization Grant](#) specification.



### OAuth device authorization grant

## Processing steps

1. The device sends a device authorization request to PingFederate, the authorization server (AS), at its device authorization endpoint.
2. PingFederate returns a device authorization response. Among other parameters, the response contains a device code, a user code, a user authorization endpoint, and a user authorization endpoint with the user code in a query parameter.
3. The device provides the user authorization endpoint with the user code in a query parameter, the user code, and instructions to the user, as in the following example.

```
Using a browser on another device, visit:
https://www.example.com/authorizeDevice
```

```
Enter the code:
HVF7-B4KW
```

4. The device starts sending device access token requests to PingFederate at its token endpoint to poll whether the user has completed the authorization process.

The device access token request must include the device authorization grant type, `urn:ietf:params:oauth:grant-type:device_code`, the device code, and the user code.

For each device access token request it receives, PingFederate returns a device access token response. The payload varies depending on the authorization status.

5. The user completes the authorization process by performing the following actions:
  - a. Goes to the user authorization endpoint on a second device that has a browser, such as a smartphone or a computer.
  - b. Fulfills the authentication requirements.
  - c. Enters the user code or confirms a pre-populated user code.
  - d. Approves or denies the scope of permissions requested by the device.
6. The device continues polling PingFederate for an authorization status.
7. PingFederate validates the user code and provides the device with an access token in the device access token response.

If the user denies the scope of permissions, PingFederate provides the device with a relevant error message in the device access token response.

8. The device provides the access token to the RS to access protected resources.
9. The RS validates the access token.
10. The RS provides the requested data to the device.

## CIBA grant


Client Initiated Backchannel Authentication (CIBA) is an extension to OpenID Connect that improves the end-user experience during authentication and authorization in a federated environment.

Like OpenID Connect, CIBA is an authentication flow, governing how clients are identified and granted access. With CIBA, user consent can be requested through an out-of-band flow. For example, when making an online purchase, CIBA improves user experience because the customer's browser will not have to redirect to a financial institution for authorization. Instead, the customer receives a push notification from the financial institution's mobile app to complete authorization. This allows the customer to avoid confusing browser redirects.

## CIBA by poll

The OAuth Client Initiated Backchannel Authentication (CIBA) grant by poll process takes place between the client, user, authentication device, PingFederate, and resource server (RS).

After receiving an authentication request acknowledgment, the client starts polling the OpenID Provider (OP)'s token endpoint on a regular interval to obtain the authorization results. When the OP receives the authorization granted by the user through the authentication device, it returns an access token to the client.



## OAuth CIBA grant by poll

### Processing steps

1. The client sends an authentication request to PingFederate at its client-initiated backchannel authentication endpoint. The client must include in its authentication request the desired scope of permissions and one identity hint for PingFederate to identify the user. When providing an identity hint, the client has three options:

- `login_hint`
- `login_hint_token`
- `id_token_hint`

The client can include a user code using the `user_code` parameter in the authentication request, transmit all request parameters of the authentication request in a signed request object, or do both.

2. PingFederate validates the authentication request and identifies the user based on the hint provided by the client.
3. PingFederate returns an authentication request acknowledgement to the client. The response contains the identifier, `auth_req_i`, that PingFederate assigns to the authentication request.
4. The client starts polling PingFederate at its token endpoint to check whether the user has completed the authorization process.

The client must include in its token request the CIBA grant type, `urn:openid:params:grant-type:ciba`, and the corresponding `auth_req_id` value.

For each token request it receives, PingFederate returns a token response. The payload varies depending on the authorization status.

5. PingFederate invokes a CIBA authenticator based on the applicable CIBA request policy to reach out to the user with the information (for example, the requested scopes) that the user needs to obtain authorization.
6. The authentication device presents the information and works with the user to obtain authorization.

7. The user reviews the information presented by the authentication device and then approves or denies the scopes requested by the client.
8. The authentication device sends the authorization result back to PingFederate.
9. The client continues polling PingFederate for an authorization result.
10. PingFederate returns an access token in a token response to the client.


If the user denies the requested scopes, PingFederate provides the client with a relevant error message in the token response.

11. The client provides the access token to the RS to access protected resources.
12. The RS validates the access token.
13. The RS provides the requested data to the client.

### CIBA by ping

The OAuth Client Initiated Backchannel Authentication (CIBA) grant by ping process takes place between the client, user, authentication device, PingFederate, and resource server (RS).

After receiving an authentication request acknowledgment, the client waits for a ping callback message from the OpenID Provider (OP). When the OP receives the authorization granted by the user through the authentication device, it sends a ping callback message to the client's notification endpoint. The client then sends a token request to retrieve an access token.



### OAuth CIBA grant by ping

## Processing steps

1. The client sends an authentication request to PingFederate at its client-initiated backchannel authentication endpoint.

The client must include in its authentication request the desired scope of permissions, one identity hint for PingFederate to identify the user, and a bearer token that PingFederate can use to authenticate the ping callback message. When providing an identity hint, the client has three options:

- `login_hint`
- `login_hint_token`
- `id_token_hint`

For the bearer token, the client must follow the syntax as defined in [RFC 6750, section 2.1](#) and transmit it using the `client_notification_token` parameter.

The client can include a user code using the `user_code` parameter, transmit all request parameters of the authentication request in a signed request object, or do both.

The authentication request can be signed or unsigned.

2. PingFederate validates the authentication request and identifies the user based on the hint provided by the client.
3. PingFederate returns an authentication request acknowledgment to the client. The response contains the identifier, `auth_req_id`, that PingFederate assigns to the authentication request.
4. PingFederate invokes a CIBA authenticator based on the applicable CIBA request policy to reach out to the user with the information (for example, the requested scopes) that the user needs to obtain authorization.
5. The authentication device presents the information and works with the user to obtain authorization.
6. The user reviews the information presented by the authentication device and then approves or denies the scopes requested by the client.
7. The authentication device sends the authorization result back to PingFederate.
8. PingFederate sends a ping callback message using the HTTP POST method to the client at its notification endpoint.

Per specification, PingFederate includes the `client_notification_token` value in the Authorization HTTP request header and the `auth_req_id` value in the message body.

9. The client sends a token request to PingFederate at its token endpoint.

The client must include in its token request the CIBA grant type, `urn:openid:params:grant-type:ciba`, and the corresponding `auth_req_id` value.

10. PingFederate returns an access token in a token response to the client.

If the user denies the requested scopes, PingFederate provides the client with a relevant error message in the token response.

11. The client provides the access token to the RS to access protected resources.
12. The RS validates the access token.
13. The RS provides the requested data to the client.

## Token exchange grant

You can configure the PingFederate OAuth server to support the token exchange grant type.


This feature uses the protocol defined in the OAuth 2.0 token exchange specification RFC 8693. For information about the protocol, see [OAuth 2.0 Token exchange](#). For information about configuring the OAuth server for token exchange, see [OAuth token exchange](#) on page 651.

An OAuth token exchange begins when an OAuth client sends a token exchange request to the PingFederate OAuth server. The request contains the token exchange grant type parameter, a subject token, and a subject token type parameter. For impersonation use cases, the request also contains an actor token and actor token type parameter. The request might also contain resource, audience, scope, and requested token type parameters.

The optional resource parameter identifies an Access Token Management (ATM) instance or token generator instance. The optional audience parameter identifies another client that will use the new token to get access to a resource. If a request includes an audience parameter, the OAuth server will select the ATM instance specified in the audience client's configuration as seen in step 2.

A successful token exchange ends when the OAuth server sends the client a message containing the requested token. The response also contains an issued token type parameter and a token type parameter.

To function as the authorization server, PingFederate requires at least one Token Exchange Processor Policy (TEPP) in order to utilize the token exchange grant type. For more information, see [Defining token exchange processor policies](#) on page 653. A TEPP includes a map of subject token types to token processor instances and a map of attributes from the request and other sources to a TEPP attribute contract. You must assign a default TEPP to the OAuth server. Optionally, you can assign a TEPP to OAuth clients that need to exchange tokens.




When the OAuth server receives a token exchange request from an OAuth client:

1. The OAuth server selects a TEPP and fulfills the TEPP attribute contract as follows:
  - If the OAuth client's configuration specifies a TEPP, the OAuth server selects that TEPP. Otherwise, the OAuth server selects the default OAuth server TEPP.
  - The OAuth server uses the TEPP's map of subject token types to select a token processor instance. The token processor then uses the TEPP's attribute map to produce a TEPP attribute contract.
2. The OAuth server selects a token generator instance or ATM instance as follows:
  - If the request does not have an audience or resource parameter, the OAuth server selects the default OAuth server ATM instance.
  - If the request includes resource parameters, audience parameters, or both, and if the OAuth server determines that they identify a single ATM or token generator instance, the OAuth server selects it.
  - If the request includes resource parameters, audience parameters, or both, and if the OAuth server determines that they do not identify a single ATM or token generator instance, the OAuth server returns an error.
3. The token generator or ATM uses the attribute contract to generate the token as follows:
  - The default token type is generated if the request does not include a requested token type parameter.
  - If the request includes a requested token type parameter, that type of token is generated.
  - If the request includes a requested token type but the token generator or ATM does not support that token type, the OAuth server returns an error.
4. The OAuth server sends the client a response containing the requested token.

### Assertion grant profile for OAuth 2.0 authorization grants

The assertion grant profile process takes place between the user or requesting application, client application, PingFederate identity provider (IdP), PingFederate authorization server (AS) and resource server (RS).

In this scenario, a client obtains an assertion, either a SAML 2.0 bearer assertion or a JSON Web Token (JWT) bearer token, and makes an HTTP request to the PingFederate OAuth AS to exchange the assertion for an access token. The OAuth AS validates the assertion and returns an access token. The client uses the token in an API call to the RS to obtain data.



### Assertion grant profile

#### Processing steps

1. A user-initiated or client-initiated event, such as a mobile application or a scheduled task, requests access to software as a service (SaaS) protected resources from an OAuth client application.
2. The client application obtains an assertion from an IdP.



#### Note:

When using SAML assertions as authorization grants, client applications must obtain assertions that meet the requirements defined in RFC7522. Do not use SAML assertions acquired through browser single sign-on (SSO) profiles here.

3. The client application makes an HTTP request to the PingFederate OAuth AS to exchange the assertion for an access token. The OAuth AS validates the assertion and returns the access token.
4. The client application adds the access token to its API call to the RS. The RS returns the requested data to the client application.

### OpenID Connect support

As an extension of OAuth capabilities, PingFederate supports an optional configuration for OpenID Connect.

OpenID Connect is a modern protocol for secure, lightweight transfer of authentication and user attributes. For more information, see [openid.net/connect](https://openid.net/connect).

PingFederate can be deployed as an OpenID Provider (OP), a Relying Party (RP), or both. PingFederate supports both the Basic Client and the Implicit Client profiles.

### Client management

PingFederate provides features that support OAuth client management.

provides administrators the flexibility to manage OAuth clients using the following interfaces:

- The administrative console
- The administrative API
- The OAuth Client Management Service

Additionally, supports dynamic client registration based on the OAuth 2.0 Dynamic Client Registration Protocol specification.

## System for Cross-domain Identity Management (SCIM)

PingFederate supports the SCIM 1.1 protocol for outbound and inbound provisioning.

At an identity provider (IdP) outbound site, you have the option to automatically provision and maintain user accounts at service provider (SP) sites that have implemented SCIM. When you have PingFederate configured as an SP inbound site, you can automatically provision and manage user accounts and groups for your own organization using the standard SCIM protocol. For a brief summary of supported features, see the following table.

| Feature   | Outbound provisioning   | Inbound provisioning   |
|---|---|--|
| SCIM specification  | SCIM 1.1  | SCIM 1.1   |
| Data format   | JSON  | JSON   |
| User and group create, read, update, and delete (CRUD) operations | Yes   | Yes  |
| Custom schema support   | Yes   | Yes  |
| List/query and filtering support                                  | Not applicable  | Yes  |
| PATCH   | Yes   | No   |
| Authentication method   | HTTP Basic and OAuth Resource Owner Password Credentials grant type     | HTTP Basic and client certificate (mutual TLS)   |
| Source data stores  | PingDirectory, Microsoft Active Directory, and Oracle Unified Directory | Not applicable   |
| Target data stores  | Not applicable  | Active Directory and other data stores via the Identity Store Provisioner Java SDK interface |

For detailed information about SCIM, see [www.simplecloud.info](http://www.simplecloud.info).



## Transport and message security

Two main ways of securing interactions are Secure Sockets Layer with Transport Level Security (SSL/TLS) and digital signatures.

Use SSL/TLS in environments that require both message confidentiality and integrity. For SAML messaging, digital signatures ensure the identity of both parties involved in the transaction and validate that a particular partner received a message. To achieve increased privacy, PingFederate also lets you encrypt SAML 2.0 messages, including SAML metadata files, as well as WS-Trust STS assertions.

For more information, see [Security and Privacy Considerations for the OASIS Security Assertion Markup Language \(SAML\) V2.0](#).

## Integration overview

---

As a standalone server, PingFederate must be programmatically integrated with end-user applications and identity management (IdM) systems to complete the “first- and last-mile” implementation of a federated identity network for browser-based single-sign-on (SSO).

PingFederate supports identity and access management (IAM) integrations with a wide range of cloud, mobile, Software as a Service (SaaS), APIs, and on-premises applications.

For an identity provider (IdP), the first mile of this integration process involves providing a mechanism through which PingFederate looks up a user's current authenticated session data, such as a cookie, or authenticates a user without such a session. For a service provider (SP), the last mile involves enabling PingFederate to supply information needed by the target application to set a valid session cookie or other application-specific security context for the user.

To enable both sides of this integration, PingFederate provides bundled and separately available integration kits, which include adapters that plug into the PingFederate server and agent toolkits that interface with local IdM systems or applications, as needed.

In addition, PingFederate provides plugin authentication selectors, which enable dynamic selection of authentication sources based on administrator-specified criteria.

For integrations that are included with PingFederate, see [Bundled adapters and authenticators](#). For an overview of the various types of integrations that are available, see [Additional integrations](#).

Visit the Ping Identity [Integration Directory](#) to explore 1800+ integrations and find links to downloads and documentation.

## Bundled adapters and authenticators

PingFederate comes bundled with the following adapters and authenticators to enable common deployment scenarios.

### Bundled adapters

#### Composite Adapter

Allows multiple configured IdP adapters to execute in sequence. Depending on the authentication context, use this capability, called adapter chaining, for either single-adapter usage or to support multi-factor authentication through a series of adapters. For more information, see [Composite Adapter](#) on page 300.

#### HTML Form Adapter

Used in conjunction with Password Credential Validators. These adapters provide integration with user-datastores in directory servers or locally. For more information, see [HTML Form Adapter](#) on page 305.

#### HTTP Basic Adapter

Used in conjunction with Password Credential Validators. These adapters provide integration with user-data stores in directory servers or locally. For more information, see [HTTP Basic Adapter](#) on page 325.

#### Identifier First Adapter

When a variety of user types authenticate at , it is often better to ask the user for their identifier first, determine their user population, and prompt the user with the desired authentication requirements and experience. The Identifier First Adapter is designed to handle this use case. For more information, see [Identifier First Adapter](#) on page 328.

#### Kerberos Adapter

Provides a seamless desktop SSO experience for Windows environments and supports authentication mechanism assurance from the Active Directory domain service. For new configurations and as a simpler alternative to the separately-available IWA Integration Kit, use this adapter. For more information, see [Kerberos Adapter](#) on page 335.

#### OpenToken Adapter

Provides a generic interface for integrating with various applications, including Java- and .NET-based applications. For more information, see [OpenToken Adapter](#) on page 342.

#### Passthrough IdP Adapter

The Passthrough IdP Adapter allows a user key to be associated with a user's authentication sessions. By placing the Passthrough IdP Adapter downstream from an IdP connection in a policy tree, you can take advantage of additional capabilities associated with defining a user key. For more information, see [Configuring a Passthrough IdP Adapter](#) on page 350.

#### PingID Adapter

PingID is a cloud-based authentication service that binds user identities to their devices, making it an effective multi-factor authentication solution. For more information, see the [PingID documentation](#).

#### PingOne Fraud Adapter

Allows PingFederate to use the PingOne Fraud service. For more information, see [PingOne Fraud Integration Kit](#).

#### PingOne MFA Adapter

Allows PingFederate to use the PingOne MFA service for multi-factor authentication (MFA). For more information, see [PingOne MFA Integration Kit](#).

#### PingOne Protect Adapter

When a user signs on through PingFederate, the adapter sends the transaction information to the PingOne Risk service and retrieves a risk evaluation and other information about the user's current and previous transactions. For more information, see [PingOne Risk Kit](#).

#### PingOne Verify Adapter

Allows PingFederate to use the PingOne Verify service to trigger an identity verification challenge as part of the PingFederate authentication policy or registration flow. For example, you can use this adapter for personal identity verification based on a government issued photo ID. For more information, see [PingOne Verify Integration Kit](#).

#### Bundled authentication selectors

PingFederate provides plugin authentication selectors, which enable dynamic selection of authentication sources based on administrator-specified criteria. Along with the Composite Adapter and token authorization, the selectors enable dynamic integration with an organization's authentication or authorization policies, also known as adaptive federation.

**Tip:**

To select subsequent selectors or authentication sources for handling complex hierarchical access-policy decisions, use the results of authentication-selection criteria evaluation. For more information, see [Authentication policies](#) on page 231.

#### CIDR Authentication Selector

Provides a means of choosing authentication sources or other authentication sources at runtime based on whether an end-user's IP address falls within specified ranges using Classless Inter-Domain Routing notation. This selector allows administrators to determine, for example, whether an SSO request originates inside or outside the corporate firewall and use different authentication integration accordingly. For more information, see [Configuring the CIDR Authentication Selector](#) on page 234.

#### Cluster Node Authentication Selector

Provides a means of picking authentication sources or other authentication sources at runtime based on the PingFederate cluster node that is servicing the request. For example, you can configure this selector to choose whether PingFederate attempts Integrated Windows Authentication based on the PingFederate cluster node with which a Key Distribution Center is associated. For more information, see [Configuring the Cluster Node Authentication Selector](#) on page 236.

#### Connection Set Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on a match found between the target SP connection used in an SSO request and SP connections configured within PingFederate. For example, administrators with different requirements for SP connections can override connection adapter selection on an individual connection basis. For more information, see [Configuring the Connection Set Authentication Selector](#) on page 237.

#### Extended Property Authentication Selector

Enables PingFederate to choose configured authentication sources or other selectors based on a match found between a selector result value and an extended property value from the invoking browser-based SSO connections or OAuth client. For more information, see [Configuring the Extended Property Authentication Selector](#) on page 237.

#### HTTP Header Authentication Selector

Provides a means of choosing authentication sources or other authentication sources at runtime based on a match found using wildcard expressions in an HTTP header. This selector allows administrators to determine, for example, authentication behavior based on the type of browser. For more information, see [Configuring the HTTP Header Authentication Selector](#) on page 239.

#### HTTP Request Parameter Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on query parameter values in the HTTP request. For more information, see [Configuring the HTTP Request Parameter Authentication Selector](#) on page 241.

#### OAuth Client Set Authentication Selector

Enables PingFederate to choose configured authentication sources or other selectors based on a match found between the client information in an OAuth request and the OAuth clients configured in the PingFederate OAuth authorization server (AS). This selector allows you to override client authentication selection on an individual client basis in one or more authentication policies. For more information, see [Configuring the OAuth Client Set Authentication Selector](#) on page 243.

#### OAuth Scope Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on a match found between the scopes of an OAuth authorization request and scopes configured in the PingFederate OAuth authorization server (AS). For example, if a client requires write access to a resource, administrators can configure the selector to choose an adapter that offers a stronger form of authentication such as the X.509 client certificate rather than username and password. For more information, see [Configuring the OAuth Scope Authentication Selector](#) on page 244.

#### Requested AuthN Context Authentication Selector

Provides a means of picking authentication sources or other authentication sources at runtime based on the authentication context requested by an SP, for SP-initiated SSO. Configured authentication sources are mapped either to SAML-specified contexts or any ad-hoc context agreed upon between the IdP and SP partners. For more information, see [Configuring the Requested AuthN Context Authentication Selector](#) on page 245.

#### Session Authentication Selector

Enables PingFederate to choose a policy path at runtime based on whether the user already has a PingFederate authentication session for a particular source. For more information, see [Configuring the Session Authentication Selector](#) on page 246.



#### Note:

Authentication selectors rely on HTTP requests, HTTP headers, POST data, or a combination of them. Ensure that standard security measures are in place when using these selectors.

#### Software development kit (SDK)

The PingFederate SDK provides a flexible means of creating custom adapters to integrate federated identity management into your system environment. For more information, see the PingFederate [SDK Developer's Guide](#) on page 1115.

## Additional integrations

In addition to the bundle integrations and authenticators, Ping Identity provides identity and access management (IAM) integrations with a wide range of cloud, mobile, software as a service (SaaS), APIs, and on-premises applications.

To discover integrations, including downloads and documentation, visit the Ping Identity [Integration Directory](#).

The following describes our most common types of integrations:

#### Single sign-on (SSO)

Integration kits allow PingFederate to coordinate SSO for a variety of platforms and applications, such as Atlassian and Citrix.

For select platforms, [configuration guides](#) are provided to help you configure SSO without any additional downloads.

#### User and group provisioning

Connectors allow PingFederate to provision and synchronize users and groups from an attached datastore to a directory in a cloud service, such as PingOne, Salesforce, or Zoom.

Connectors also let you set up optional SSO between PingFederate and the cloud service.

These typically include a connection template for the PingFederate provisioning engine.

### Multi-factor authentication (MFA)

MFA integrations allow PingFederate to include third-party MFA providers, such as PingOne MFA and RSA SecurID, as part of the sign-on flow.

### Mobile device management

Mobile device management integrations allow PingFederate to adjust the sign-on flow based on device information from services such as MobileIron and AirWatch.

These typically include an IdP adapter.

### Risk-based intelligent authentication

Risk intelligence integration kits allows PingFederate to retrieve a security risk assessment from third parties, such as PingOne Protect and ThreatMetrix, when a user signs on. You can use this information to dynamically adjust authentication requirements based on the risk level for each sign-on event.

These typically include an IdP adapter.

### Custom application integration

The [Agentless Integration Kit](#) can integrate any application with PingFederate for SSO. This uses API calls with no need for agent software. We provide sample code for a variety of programming languages.

Specific integrations are available for the language your application uses, such as Java, .NET, and PHP. These include an IdP and SP adapter, an agent file, and sample code.

### Web server agents

PingFederate to extend single sign-on abilities to applications running on web servers, such as Apache and IIS.

### Social sign-on

Cloud identity connectors (CIC) allow PingFederate to coordinate SSO by using third-party services as identity providers (IdP). This allows a user to access a service provider (SP), such your web application, by signing into a popular service, such as LinkedIn, Google, or Facebook.

These typically include a PingFederate IdP adapter.

### Checking user credentials

Password credential validator (PCV) integrations let PingFederate validate user credentials against a directory service, such as PingOne and Azure, when a user signs on.

These include a PCV add-on for PingFederate.

### Converting identity tokens

Token translators allow PingFederate to convert or validate IdP tokens in a variety of formats, such as the WS-Trust security token service (STS).

These typically include token processor and token generator files.

### Custom integrations

PingFederate also includes an SDK that software you can use to write custom interfaces for specific systems. For more information, see the [SDK Developer's Guide](#) on page 1115.

### Specific use cases

To explore comprehensive guides for specific use cases, see [Use Case Guides](#).


## SSO integration concepts

PingFederate supports both identity provider (IdP) and service provider (SP) integration.

For an IdP, the first step in the integration process involves sending identity attributes from an authentication service or application to PingFederate. PingFederate uses those identity attributes to generate a SAML assertion. For information about SAML, see [Supported standards](#) on page 34. IdP integration typically provides a mechanism through which PingFederate looks up a user's current authenticated session data, such as a cookie, or authenticate a user without such a session.

For an SP, the last step of the integration process involves sending identity attributes from PingFederate to the target application. PingFederate extracts the identity attributes from the incoming SAML assertion and sends them to the target application to set a valid session cookie or other application-specific security context for the user.

The following diagram illustrates the basic concepts of integration with PingFederate.




## Identity provider integration

Identity provider (IdP) integration involves retrieving user-identity attributes from the IdP domain and sending them to the PingFederate server.

An IdP is a system entity that authenticates a user, or “SAML subject,” and transmits referential identity attributes based on that authentication to PingFederate. Typically, the IdP retrieves the identity attributes from an authenticated user session. Depending on the IdP deployment/implementation environment, a number of attribute-retrieval approaches are used for IdP integration. Ping Identity offers a broad range of commercial integration kits that address various IdP scenarios, such as custom-application integration, integration with a commercial identity management (IdM) product, or integration with an authentication system.

**Tip:**

For IdPs implementing single sign-on (SSO) to selected software as a service (SaaS) providers such as Google Apps and Salesforce, PingFederate also provides automated user provisioning.



### Custom applications

Many applications use their own authentication mechanisms, typically through a database or LDAP repository, and are responsible for their own user-session management. Custom-application integration is necessary when there is limited or no access to the web or application server hosting the application. Integration with these custom applications is handled by application-level integration kits, which allow software developers to integrate their applications with a PingFederate server acting as a service provider (SP).

With these integration kits, PingFederate sends the identity attributes from the SAML assertion to the SP application, which then uses them for its own authentication and session management. As for the IdP, application-specific integration kits include an SP agent, which resides with the SP application and provides a simple programming interface to extract the identity attributes sent from the PingFederate server. PingFederate can use this information to start a session for the SP application.

Ping Identity provides custom-application integration kits for a variety of programming environments, including:

- Java
- .NET
- PHP

Ping Identity provides an Agentless Integration Kit, which allows developers to use direct HTTP calls to the PingFederate server to temporarily store and retrieve user attributes securely, eliminating the need for an agent interface.

### IdM systems

An IdP enterprise that uses an IdM system expands the reach of the IdM domain to external partner applications through integration with PingFederate. IdM integration kits typically use the IdM agent API to access identity attributes in the IdM proprietary session cookie and transmit those attributes to the PingFederate server.

IdM integration kits do not require any development; the PingFederate administrative console accomplishes all integrations.

Ping Identity provides integration kits for many of the leading IdM systems, such as Oracle Access Manager.

### Authentication systems

An authentication application or service normally handles initial user authentication outside of the PingFederate server. To access applications outside the security domain, PingFederate authentication-system integration kits leverage this local authentication.

Authentication integration kits do not require any development; the PingFederate administrative console accomplishes all integrations with PingFederate. Ping Identity offers integration kits for authentication systems including:

- X.509 Certificate
- RSA SecurID Integration Kit
- Symantec VIP Integration Kit


PingFederate also packages two IdP adapters, an HTML Form Adapter and an HTTP Basic Adapter, which delegate user authentication to plugin password credential validators (PCVs). Supplied validators use either an LDAP directory, RADIUS server, or a simple username/password verification system maintained by PingFederate. Customized validators can also be developed. When the PingFederate IdP server receives an authentication request for SP-initiated SSO or a user clicks a link for IdP-initiated SSO, PingFederate invokes the implemented adapter and prompts the user for credentials, if the user is not already logged on.

## Service provider integration

Service provider (SP) integration involves passing the identity attributes from PingFederate to the target SP application.

An SP is the consumer of identity attributes provided by the identity provider (IdP) through a SAML assertion. The SP application uses this information to set a valid session or other security context for the user, represented by the identity attributes. Session creation involves a number of approaches. For the IdP, Ping Identity offers commercial integration kits that address the various SP scenarios. Most SP scenarios involve custom-application integration, server-agent integration, integration with an identity management (IdM) product, or integration with a commercial application.





### Custom applications

Many applications use their own authentication mechanisms, typically through a database or LDAP repository, and are responsible for their own user-session management. Custom-application integration is necessary when there is limited or no access to the web or application server hosting the application. Application-level integration kits handle integration with these custom applications and allow software developers to integrate their applications with a PingFederate server acting as an SP.

With these integration kits, PingFederate sends the identity attributes from the SAML assertion to the SP application, which can then use them for its own authentication and session management. As for the IdP, application-specific integration kits include an SP agent, which resides with the SP application and provides a simple programming interface to extract the identity attributes sent from the PingFederate server. PingFederate can use this information to start a session for the SP application.

Ping Identity provides custom-application integration kits for a variety of programming environments, including:

- Java
- .NET
- PHP

In addition, Ping Identity provides an Agentless Integration Kit, which allows developers to use direct HTTP calls to the PingFederate server to temporarily store and retrieve user attributes securely, eliminating the need for an agent interface.

### Server agents

Server-agent integration with PingFederate allows SP enterprises to accept SAML assertions and provide single sign-on (SSO) to all applications running on that web or application server; there is no need to integrate each application. Since integration occurs at the server level, server-agent integration maximizes

ease of deployment and scalability. Applications running on the web or application server must delegate authentication to the server. If the application employs its own authentication mechanism, integration must occur at the application level.

With server-agent integration kits, PingFederate sends the identity attributes from the SAML assertion to the server agent, which is typically a web filter or Java Authentication and Authorization Service (JAAS) Login Module. The server agent extracts the identity attributes, which the server then uses to authenticate and create a session for the user.

SP server-integration kits do not require any development work: the PingFederate administrative console accomplishes all integrations with PingFederate.

Ping Identity provides integration kits for many web and application servers, including:

- Internet Information Services (IIS)
- Apache (Red Hat)
- Apache (Windows)
- NetWeaver
- WebSphere

#### IdM systems

IdM integration with PingFederate allows an SP enterprise to accept SAML assertions and provide SSO to applications protected by the IdM domain. IdM integration kits typically use the IdM agent API to create an IdM proprietary session token based on the identity attributes received from PingFederate.

IdM integration kits do not require any development; the PingFederate administrative console and the IdM administration tool accomplish integration with PingFederate.

Ping Identity provides integration kits for leading IdM systems, such as Oracle Access Manager.

#### Commercial applications and SaaS

Commercial-application integration with PingFederate allows an SP enterprise to accept SAML assertions and provide SSO to those commercial applications.

These integration kits do not require any development; the PingFederate administrative console accomplishes all integrations.

Ping Identity offers integration kits to many commercial applications and SaaS vendors, including:

- Citrix
- SharePoint
- Box
- Google
- Office 365
- Salesforce
- Slack
- Workday
- Zendesk

## Security token service


---

The PingFederate WS-Trust Security Token Service (STS) allows organizations to extend single sign-on (SSO) identity management (IdM) to web services.

The STS shares the core functionality of PingFederate, including console administration, identity and attribute mapping, and certificate security management. With PingFederate, web services identify the end user who has initiated a transaction across domains, providing enhanced service while simultaneously

ensuring appropriate information access and regulatory accountability. For information about WS-Trust and the role of an STS, see [Web services standards](#) on page 53.

You can use PingFederate in many different scenarios to address different identity and security problems as they relate to web services, service-oriented architecture (SOA), and Enterprise Service Buses. All of these scenarios share a recommended architectural approach that uses a SAML assertion as the standard security token shared between security domains. For more information, see [WS-Trust STS](#) on page 80.



## WS-Trust Security Token Service SSO

### OAuth authorization server

PingFederate can act as an OAuth authorization server (AS), allowing a resource owner to grant authorization to a client requesting access to resources protected by a resource server (RS).

The OAuth AS issues tokens to clients on behalf of a resource for use in authenticating a subsequent API call—typically, but not exclusively a REST API. The PingFederate OAuth AS issues tokens to clients in several different scenarios, including:

- A web application wants access to a protected resource associated with a user and needs the user's consent.
- A native application client on a mobile device or tablet wants to connect to a user's online account and needs the user's consent.
- An enterprise application client wants to access a protected resource hosted by a business partner, customer, or software as a service (SaaS) provider.

For information about OAuth and the role of an AS, see [OAuth 2.0 and PingFederate AS](#).

You can configure the PingFederate OAuth AS independently or in conjunction with security token service (STS) and browser-based single sign-on (SSO) for either an identity provider (IdP) or a service provider (SP) deployment. For more information, see [About OAuth](#) on page 83.

 **Note:**

OAuth AS capabilities might require additional licenses. For more information, contact [sales@pingidentity.com](mailto:sales@pingidentity.com).

## User account management

---

Typically, the identity provider (IdP) repository maintains user accounts in an identity federation. However, a service provider (SP) often has its own set of user accounts, which might not always correspond to IdP users.

The SP might need to establish and maintain parallel accounts for remote single sign-on (SSO) users to enforce authorization policy, customize user experience, comply with regulations, or a combination of such purposes.

PingFederate provides two kinds of user provisioning for browser-based SSO to facilitate cross-domain account management, one designed for an IdP, and one for an SP:

- At an IdP site, an administrator automatically provisions and maintains user accounts for partner SPs who have implemented the System for Cross-domain Identity Management (SCIM) or, when using optional plugin software as a service (SaaS) connectors, for selected hosted-software providers..
- At an SP site, an administrator provisions accounts within the organization automatically from SCIM-enabled IdPs or uses information from SAML assertions received during SSO events.

For more information, see [User provisioning](#) on page 106.

## Enterprise deployment features

---


PingFederate's enterprise-deployment architecture provides one location to manage your environment, eliminating the need to maintain redundant copies of these configurations and trust relationships.

One-time configuration, available everywhere

PingFederate houses all protocol definitions, public key infrastructure (PKI) keys, policies, and profiles in a single location. You can add new protocols, profiles, or use cases, and then make them available to your entire organization.

Improved security

PingFederate improves security by creating a single “doorway” through which all your identity information is exchanged. The same doorway is used regardless of who the users are or in which direction information is shared, such as internal users accessing external applications and external users accessing internal systems.



### Load balancers and reverse proxies

To enhance performance and security, you can deploy PingFederate behind an application load balancer (ALB), a network load balancer (NLB), a reverse proxy, or a similar network traffic management solution on-premise or in the cloud.

#### Important:

PingFederate can benefit from knowing the originating IP addresses of incoming requests. Before you deploy PingFederate in the cloud or behind a load balancer, to avoid unexpected behaviors, work with your network team and configure PingFederate's **Incoming Proxy Settings** accordingly. For more information, see [Configuring incoming proxy settings](#) on page 697.

### Extensive audit and logging capabilities

With PingFederate's extensive auditing and logging capabilities, you can complete logging-related compliance and service-level requirements, without having to acquire and consolidate disparate logs from throughout your organization.

### Business use case driven configuration

The PingFederate administrative console supports various protocol, while reducing complexity and learning curves. You are guided through configuration steps applicable only to the business use cases you need to support.

## Additional features

PingFederate's lightweight, standalone architecture allows server integration and partnering with existing home-grown and commercial identity management (IdM) systems and applications providing standards-based single sign-on (SSO) and API security integration benefits.


### PingOne

The PingOne Cloud Platform offers one platform for unifying all your digital identities and allowing your users and devices to securely access cloud, mobile, SaaS and on-premises applications and APIs. With

PingFederate, you can leverage these services to accelerate the digital transformation of your environment for better security and compliance.

### Integration kits

Use PingFederate's software development kit (SDK) for creating custom integrations with existing authentication services and target applications as well as quick connections to various partners. For more information, see [Bundled adapters and authenticators](#) on page 65. Download PingFederate integration kits from the Ping Identity [Downloads](#) website.



### Multiple security-domain, multi-protocol federation

#### Token translators

Ping Identity offers special token processors for an IdP and token generators for a SP that enable the WS-Trust security token service (STS) to validate and issue a variety of token types. These plug-ins supplement built-in SAML token processing and generation and handle the local identity tokens required in many security contexts. For more information, see [Token processors and generators](#) on page 81.

#### SaaS connectors

SaaS connectors offer a streamlined approach for browser-based SSO to selected SaaS providers, including automatic user provisioning and deprovisioning. The connector packages include quick-connection templates, which automatically configure endpoints and other connection information for each provider. For more information, see [Outbound provisioning for IdPs](#) on page 106.

#### Cloud identity connectors

Offer your users the option to login, register, and access your cloud-based applications with their social identity from sites like Apple, Facebook, Google, LinkedIn, Microsoft, and Twitter.

## Key concepts

This section provides background information and preparation to help administrators understand and use PingFederate.

### Connection Types

PingFederate features an integrated administrative console for configuring connections to identity-federation partners. The four connection types include:

- Browser-based single sign-on (SSO) – Called Browser SSO in the administrative console, this term refers to standards-based secure SSO, which generally depends on a user's browser to transport identity assertions and other messaging between partner endpoints. For more information, see [Supported standards](#) on page 34.
- WS-Trust security token service (STS) – Employs the PingFederate STS, which enables web service clients (WSCs) and web service providers (WSPs) to extend SSO to identity-enabled web services at provider sites. For more information, see the [WS-Trust STS](#) on page 80. These standards, including WS-Trust, do not rely on the user's browser for message transport.

- OAuth Assertion Grant – Exchanges a SAML assertion or a JSON Web Token for an OAuth access token with the PingFederate authorization server (AS). For more information, see [About OAuth](#) on page 83.
- Provisioning – Provides automated cross-domain inbound and outbound user management. For more information, see [User provisioning](#) on page 106.

You can configure the types of connections together for the same partner or independently.

### WS-Trust STS

PingFederate WS-Trust STS allows organizations to extend SSO identity management (IdM) to web services. For more information see, [About WS-Trust STS](#).

### OAuth

You can configure PingFederate to act as an OAuth authorization server (AS), allowing a resource owner to grant authorization to an OAuth client requesting access to resources hosted by a resource server (RS). For more information, see [About OAuth](#).

### SSO integration kits and adapters

PingFederate provides bundled and separate integration kits that include adapters that plug into the PingFederate server and agent toolkits that interface with local IdM systems or applications as needed. For more information, see [SSO integration kits and adapters](#).

### Security infrastructure

PingFederate security infrastructure supports encrypted messaging, certificates, and digital signing. For more information, see [Security infrastructure](#).

### Hierarchical plugin configuration

PingFederate allows you to use a configuration of an adapter, as well as certain other PingFederate plugins, as a parent instance from which you can create child instances. For more information, see [Hierarchical plugin configurations](#).

### Identity mapping

PingFederate enables identity mapping between domains for browser-based SSO and WS-Trust STS. For more information, see [Identity mapping](#).

### User attributes

Federation transactions require the transmission of a unique piece of information that identifies the user for identity mapping between security domains. For more information, see [User attributes](#).

### User provisioning

PingFederate provides cross-domain user provisioning and account management. For more information, see [User provisioning](#).

### Customer identity and access management

PingFederate empowers administrators to deliver a secure and easy-to-use customer authentication, registration, and profile management solution. For more information, see [Customer identity and access management](#).

### Federation hub use cases

As a federation hub, PingFederate can bridge browser-based SSO between IdPs and SPs. For more information, see [Federation hub use cases](#).

### Federation planning

An essential first step in establishing an identity federation involves discussions and agreements between you and your connection partners. For more information, see the [Federation planning checklist](#).

## WS-Trust STS

The PingFederate WS-Trust Security Token Service (STS) allows organizations to extend single-sign on (SSO) identity management (IdM) to web services.

You can configure the WS-Trust STS for partner connections independently or in conjunction with browser-based SSO for either an identity provider (IdP) or a service provider (SP) deployment. The STS is bundled with separate plug-ins for standard SAML token processing and generation.

For information about WS-Trust and the role of an STS, see [Web services standards](#) on page 53.

### Connection-based policy

PingFederate employs a partner-connection configuration for both IdP and SP roles, which enables the association of web services authentication policies with federation partners. For more information, see [Connection-based policy](#).

### Token processor and generator

PingFederate provides support for a variety of security-token formats through token processors and generators. For more information, see [Token processors and generators](#).

### WSC and WSP support

Ping Identity provides the Java client software development kit (SDK) for enabling web service applications to interact with the PingFederate STS. For more information, see [WSC and WSP support](#).

### STS OAuth integration

PingFederate STS provides several ways to facilitate the use of issued tokens with an OAuth authorization server (AS). For more information, see [STS OAuth integration](#).

### Connection-based policy

For both the identity provider (IdP) and service provider (SP) roles, PingFederate employs a partner-connection configuration, which enables the association of web services authentication policies with federation partners.

For Security Token Service (STS) processing, these policies define configurations for handling WS-Trust requests and transferring identity information between security domains. For more information, see [Web services standards](#) on page 53.

### IdP configuration

Use the administrative console in an IdP role to configure WS-Trust request-processing policy for your SP partner including:

- The type of SAML token to create in response to an issue request from a web service client (WSC) application
- The mapping of attributes to include within the issued SAML token
- The key used to create a digital signature for the issued SAML token



## SP configuration

Use the administrative console in an SP role to configure WS-Trust request-processing policy for your IdP partner including:

- Whether to validate the incoming SAML token only, or to validate the incoming token and also issue a local token
- The mapping of attributes to include in the locally issued token when applicable
- The certificate used to verify the digital signature for the incoming SAML token
- The key used to decrypt the incoming SAML token when needed

## Token processors and generators

PingFederate provides support for a variety of security-token formats through token processors and generators.

These token processors and generators plug into the PingFederate server and deploy similarly to browser-based single sign-on (SSO) adapters. For more information, see [Bundled adapters and authenticators](#) on page 65.

For an identity provider (IdP), token processors provide a mechanism through which PingFederate can validate an incoming token from a web service client (WSC) and map attributes to be included in the issued SAML token.

For a service provider (SP), token generators provide a mechanism through which PingFederate can generate a local token based upon the incoming SAML token from a WSP and map attributes to be included in that token.

PingFederate only generates SAML 1.1 or 2.0 token when it is configured as an IdP for sending across trust boundaries to a federate SP partner. PingFederate only accepts SAML tokens when configured as an SP. Token plug-ins allow a modular approach for validating and producing the token types used by different applications or systems within a conceptual trust domain. PingFederate provides bundled and separately available token plug-ins.



### Tip:

For direct security token service (STS) token exchange within the same domain or trust boundary, use the PingFederate STS to exchange one token type for another directly, without generating a transitional SAML token. For more information, see [Token translator mappings](#) on page 414.

PingFederate allows you to use a configuration of a token processor or generator as a parent instance from which you create child instances. For more information, see [Hierarchical plugin configurations](#) on page 99.

## Bundled token plug-ins

PingFederate comes installed with token processors for an IdP configuration that accept and validate SAML 1.1 or 2.0 tokens, OAuth bearer access tokens, JSON web tokens (JWT), username tokens, and Kerberos tokens. For more information, see [Token models and management](#) on page 84. SAML tokens are issued on the IdP side through built-in browser-based SSO capabilities.

For an SP configuration, PingFederate provides token generators for issuing local SAML 1.1 or 2.0 tokens. PingFederate validates incoming SAML tokens using built-in capabilities.

## Commercial token plug-ins

Ping Identity provides token plug-ins called token translators to work with various authentication systems and identity management (IdM) systems. You can download the available plug-ins from the Downloads website.

## WSC and WSP support

Ping Identity provides the Java client software development kit (SDK) for enabling web service applications to interact with the PingFederate security token service (STS).

For web service client (WSC) STS clients, PingFederate provides built-in protocol support for Windows Identity Foundation (WIF) applications based on the Windows Communication Foundation (WCF) framework.



### Note:

The WIF framework includes WS-\* protocol support and can interact natively with PingFederate.

## Client SDK

The STS Java client SDK provides interfaces that create the WS-Trust Request Security Token (RST) and Request Security Token Response (RSTR) messaging to interact with the PingFederate STS endpoints. Using the SDK library, applications are not responsible for forming these WS-Trust protocol messages, and instead interact only with the tokens themselves.

The SDK is available for download on the Ping Identity Downloads website.

## Windows Identity Foundation clients

PingFederate natively supports STS clients using claims-based WIF technology. Claims-based federated identity for web services is a part of the WS-Trust standard that permits client applications to make access-policy decisions, when specifically categorized user attributes are sent in the security token. For more information, see [Attribute contracts](#) on page 101.

The PingFederate STS supports the following bindings in the .NET federated-security scenarios with WS-Trust:

- `WSFederationHttpBinding`
- `WS2007FederationHttpBinding`

Additionally, the PingFederate STS supports the following bindings for RST and RSTR interactions with .NET. Support for these bindings is limited to the Username, x509, SAML 1.1, and SAML 2.0 token types:

- `WSHttpBinding`
- `WS2007HttpBinding`



### Note:

For token types such as Kerberos, where customizing default bindings might be necessary, the PingFederate STS supports the use of `customBinding`.

For more information about bindings, see Microsoft's [System-Provided Bindings](#).

To expedite configuring their applications, PingFederate provides metadata for developers. PingFederate offers two varieties of metadata, which work together to arrive at functional WSC and web service provider (WSP) configurations:

- STS Metadata Exchange, which contains connection details relating to the SP partner. See the `/pf/sts_mex.ping` section in [System-services endpoints](#) on page 1269.
- Federation Metadata, which contains details on the PingFederate public signing certificate and other information required to establish the trust relationship. See the `/pf/federation_metadata.ping` section in [System-services endpoints](#) on page 1269.

For more information about claim-based federated identity, see Microsoft's [A Guide to Claims-based Identity and Access Control](#).

## STS OAuth integration

PingFederate security token service (STS) provides several ways to facilitate the use of issued tokens with an OAuth authorization server (AS).

### OAuth token processor

This token processor provides a mechanism through which PingFederate STS can validate an incoming OAuth Bearer access token. The token processor reads and validates the access token and returns any additional user attributes defined.

### JWT bearer token grant type

```
urn:ietf:params:oauth:grant-type:jwt-bearer
```

This token request returns a JSON Web Token (JWT) that a web service client (WSC) can use to request OAuth access tokens from any OAuth AS that supports using JWTs as authorization grants, as defined in [JSON Web Token \(JWT\) Profile for OAuth 2.0 Client Authentication and Authorization Grants](#) specification.

### OAuth access token with JWT bearer token grant type

```
oauth-v2:access:token:response|via|urn:ietf:params:oauth:grant-type:jwt-bearer
```

This proprietary token request is similar to the JWT Bearer Token grant type but returns an OAuth access token directly. Acting as an identity provider (IdP), PingFederate generates the intermediate JWT and requests an access token from the OAuth AS on behalf of the WSC. The AS endpoint is obtained from the **AppliesTo** element of the WS-Trust request security token (RST) message.

### SAML 2.0 bearer assertion grant type

```
urn:ietf:params:oauth:grant-type:saml2-bearer
```

This token request returns an encoded SAML assertion that a WSC can use to request OAuth access tokens from any OAuth AS that supports the [SAML 2.0 Profile for OAuth 2.0 Client Authentication and Authorization Grants](#) specification.

### OAuth access token with SAML 2.0 bearer assertion grant type

```
oauth-v2:access:token:response|via|urn:ietf:params:oauth:grant-type:saml2-bearer
```

This proprietary token request is similar to the SAML 2.0 Bearer Assertion grant type but returns an OAuth access token directly. Acting as an IdP, PingFederate generates the intermediate, encoded SAML assertion and requests an access token from the OAuth AS on behalf of the WSC. The AS endpoint is obtained from the **AppliesTo** element of the WS-Trust RST message.

These capabilities bridge the WS-Trust client-STs relationship and the trust relationship the same client with an OAuth AS, allowing the client to obtain additional resources on behalf of already-authenticated users in follow-on transactions.

## About OAuth

Configuring PingFederate as an OAuth authorization server (AS) allows a resource owner (RO), typically an end user, to grant authorization to an OAuth client requesting access to the resource server (RS).

The OAuth AS issues tokens to clients on behalf of an RO for use in authenticating a subsequent API call to the RS, typically, but not exclusively, a REST API call.



### Tip:

If your PingFederate license does not include the OAuth AS capabilities, contact [sales@pingidentity.com](mailto:sales@pingidentity.com).

You can configure the PingFederate OAuth AS independently or in conjunction with security token service (STS) or browser-based single sign-on (SSO) for either an identity provider (IdP) or a service provider (SP) deployment.

In an IdP deployment, an IdP adapter is used to authenticate and provide user information for the access token. In an SP deployment, the inbound SAML assertion is used to provide authentication information about the user associated with the access token through an OAuth attribute mapping in the IdP connection.

For an STS IdP, PingFederate provides an OAuth token processor that validates incoming OAuth Bearer access tokens.

### **Delegated access types**

To enhance access control, PingFederate supports both explicit and implicit delegation of transaction approval.

#### Explicit delegation

This is the most common OAuth use case, which involves a resource owner (RO) who explicitly delegates the authority to a client to make API calls to a resource server (RS) and is asked to approve the transaction. This is the type of delegation inherent in web redirect flow.

#### Implicit delegation

Implicit delegation also generally involves a client who calls an API on behalf of a user. However, the client's authority is implied by the nature of the transaction, and the user is not specifically asked to approve the transaction.

### **Token models and management**

Successful OAuth transactions require an OAuth authorization server (AS) to issue tokens characterized by both security model and data model for use in authenticating an API call.

#### Token security model

A token security model refers to the conditions that must be met by a client to use a token on an API call. The currently supported model is a Bearer Token. A client's presentation of the token – for example, as a parameter on the API call – to the resource server (RS) is interpreted as providing sufficient proof to the RS that the client received the same token from the OAuth AS.

#### Token data model

A token data model refers to whether the token carries identity and security information or acts as a pointer to the information.

#### Self-contained tokens (JSON Web Tokens)

Contain identity and security information and attributes in a transport format such as JSON, signed by the AS and verified directly by the RS.

#### Reference tokens (Internally Managed Reference Tokens)

Serve as a reference to some set of attributes. The RS must de-reference the token for the corresponding identity and security information at the OAuth AS that issued it.

#### Token management

PingFederate supports multiple access token management instances, providing flexibility for enterprises where deployments require different token data models, token lifetimes, attribute contracts, token validation rules, or any combination of them for various clients.

## Grant types

To obtain an access token, a client interacts with an OAuth authorization server (AS), sending a request for an access token that includes an access grant. An access grant is also used when a resource server (RS) requests validation of an access token from the AS.

### Primary grant types

OAuth defines several different access grant types. Each grant type reflects different authorization mechanisms.

#### Authorization code

```
authorization_code
```

An authorization code is returned to the client through a browser redirect after the resource owner (RO) gives consent to the AS. The client subsequently exchanges the authorization code for an access token and often a refresh token. RO credentials are never exposed to the client.

#### Resource owner password credentials

```
password
```

The client collects the RO's password and exchanges it at the AS for an access token and often a refresh token. This grant type is suitable in cases where the RO has a trust relationship with the client, such as its computer operation system or a highly-privileged application because the client must discard the password after using it to obtain the access token.

#### Refresh token

```
refresh_token
```

A refresh token often returns with an access token. Once the original access token expires, the corresponding refresh token sends to the AS to obtain a fresh access token without requiring the RO to re-authenticate. This allows short-lived access tokens to exist between the client and the resource server and long-lived tokens between the client and the AS.

The refresh token grant type only works in conjunction with either the authorization code or RO password credentials grant type.

#### Implicit

```
implicit
```

A browser redirect responds to the RO authorization request, rather than an intermediate authorization code, and returns an access token to the client. This grant type works for clients incapable of keeping client credentials confidential for use in authenticating with the AS, such as client applications implemented in a browser using a scripting language like JavaScript.

#### Client credentials

```
client_credentials
```

The client presents its own credentials to the AS to obtain an access token. This access token is either associated with the client's own resources, and not a particular RO, or with a RO for whom the client is otherwise authorized to act.

### Extension grant types

OAuth provides an extension mechanism for defining new extension grant types to support additional clients or to provide a bridge between OAuth and other trust frameworks. An OAuth client uses an extension grant type by specifying an absolute URI as the value of the **grant\_type** parameter and by adding any additional parameters necessary when contacting the token endpoint at `/as/token.oauth2`.

PingFederate supports the following extension grant types:

## Assertion grants

### JWT Bearer

```
urn:ietf:params:oauth:grant-type:jwt-bearer
```

The client obtains a JSON web token (JWT) and uses it to request an access token from the AS. This grant type allows a client to use an existing trust relationship, expressed through a JWT, without a direct user approval step at the AS.

### SAML 2.0 Bearer

```
urn:ietf:params:oauth:grant-type:saml2-bearer
```

The client obtains a SAML 2.0 Bearer assertion and uses it to request an access token from the AS. Similar to the JWT Bearer grant type, this grant type allows a client to use an existing trust relationship, expressed through a SAML assertion, without a direct user approval step at the AS.



#### Note:

The SAML assertion used for this grant type generally cannot be a browser-based SSO assertion. To ensure its validity, the assertion must be associated with WS-Trust security token service (STS) processing.

## Client-initiated backchannel authentication (CIBA) grant

```
urn:openid:params:grant-type:ciba
```

The client presents an identity hint to the AS. The AS identifies the RO based on the hint provided and then authenticates and obtains authorization from the RO through an out-of-band flow. Depending on the setup, the client either polls the AS for the authorization result or wait for a signal from the AS to return to the AS for the authorization result. If the RO approves the authentication request, the AS returns an access token to the client. Otherwise, the AS returns an error message per the specification.

## Device authorization grant

```
urn:ietf:params:oauth:grant-type:device_code
```

The client presents a device code and user code to the AS to identify the device-authorization session and obtain an access token. This access token is associated with a RO for whom the client is otherwise authorized to act.

## token exchange grant

```
urn:ietf:params:oauth:grant-type:token-exchange
```

The client presents a security token to the AS. In exchange, the AS returns another kind of security token to the client. The new token might be an access token that is more narrowly scoped for a downstream service or it could be an entirely different kind of token. This grant type supports subject and actor tokens employing impersonation and delegation.

## Validation grant

```
urn:pingidentity.com:oauth2:grant_type:validate_bearer
```

This proprietary PingFederate OAuth extension enables an RS to act as a client in the request/response exchange with PingFederate as the AS in this scenario. The grant type allows an RS to check with PingFederate on the validity of a bearer access token received from a client making a protected-resources call.

## Scopes

In addition to OAuth, PingFederate supports the use of scopes to constrain and define access privileges.

OAuth provides a mechanism to constrain the privileges associated with an access token, whereas scopes provide a way to more specifically define the privileges requested and granted. Generally, a client specifies the desired scopes when sending an authorization request to the authorization server. If the user approves, the authorization server issues an access token with these scopes.

Scopes are configured globally using the **System # OAuth Settings # Scope Management** configuration wizard. Once defined, you can manage the availability of scopes on a client-by-client basis.

### Static scopes and dynamic scopes

As an authorization server, supports the concepts of static scopes and dynamic scopes. To define a static scope, use a text value such as `read_bank_account`. To define a dynamic scope, use a text value with a variable component represented by a wildcard, such as `read_bank_account_txn:*`. As illustrated, dynamic scopes allow clients to request authorization using scope values with a variable component from one request to another.

## Consent approval

With Authorization Code, Implicit, and Device Authorization grant types, an authorization server (AS) prompts the user to grant authorization to share user information. Once granted, the AS issues an access token to the client who uses it to access information from the resource server (RS).

### Default consent user interface

PingFederate handles the consent approval process by presenting the **Request for Approval** window to the user by default. This window displays a list of requested permissions, **scopes**, along with their descriptions as configured in PingFederate. It is up to the user to approve or deny individual scopes.

### External consent user interface

As use cases evolve towards giving users more control over their data, it becomes more important to provide detailed information about the requests. While the scope description can help, PingFederate also supports the use of an external web application to prompt for authorization consent. This approach opens up the opportunity to retrieve additional information specific to the users. For example, the web application can be written in such a way that when a client requests the **read\_bank\_account** scope, the web application retrieves the user's customer information file and gives the user the ability to choose which accounts to make available to the client.

## Client management and storage

OAuth clients interact with an authorization server (AS) to obtain access tokens and optionally refresh tokens to access protected resources on resource servers.

provides administrators the flexibility to manage OAuth clients using the following interfaces:

- The administrative console
- The administrative API
- The OAuth Client Management Service

Additionally, supports dynamic client registration based on the OAuth 2.0 Dynamic Client Registration Protocol specification.

Storing client records in XML files by default allows administrators to manage clients using the administrative console and the administrative API. It also allows developers to submit client creation requests based on the Dynamic Client Registration protocol specification. The configuration archive contains client records.

Alternatively, because the OAuth Client Management Service requires external storage of client records, PingFederate supports configuration to store client records externally on a database server, a directory

server, or some other storage medium through the use of the PingFederate SDK. Under this configuration, the configuration archive does not include client records.

### Client authentication schemes

Most OAuth and OpenID Connect use cases require the client application to authenticate successfully before its requests can be processed further.

As an OAuth authorization server (AS), PingFederate supports the following client authentication schemes:

- Client secret for HTTP Basic authentication
- Client TLS certificate for mutual TLS authentication
- Private key JWT for the `private_key_jwt` client authentication method, as defined in the OpenID Connect specification
- None when authentication is not required

When deployed as an OpenID Connect Relying Party (RP), PingFederate authenticates through client secret and private key JSON web tokens (JWT). It also handles the scenario where authentication is not required.

### Dynamic client registration

As an OAuth provider, PingFederate supports a number of OAuth protocols.

PingFederate supports dynamic client registration based on the [OAuth 2.0 Dynamic Client Registration Protocol](#) specification. When enabled, it allows developers to register OAuth clients through an API based on open standards.

### Transient grants and persistent grants

There are two types of OAuth authorization grants: transient grants and persistent grants.

#### Transient grants

Transient grants are valid only for the lifetime of their respective access tokens. Transient authorizations include those obtained by OAuth clients in the following manners:

- Grants obtained by using the authorization code, resource owner credentials, or device authorization grant type, without the refresh token grant type
- Grants obtained by using client credential, JWT bearer, SAML 2.0 bearer assertion, or token exchange grant type

Transient grants are not preserved.

#### Persistent grants

Persistent grants typically bear a longer lifetime than their respective access tokens do. Persistent authorizations include those obtained by OAuth clients in the following ways:

- Grants obtained or updated using the authorization code, resource owner credentials, or device authorization grant type, in conjunction with the refresh token grant type



#### Note:

If the use cases involve mapping attributes from authentication sources, such as IdP adapter instances or IdP connections, or password credential validator (PCV) instances to the access tokens, directly or through persistent grant-extended attributes, storing these attributes from authentication sources and their values along with the persistent grants maintains them for reuse when clients subsequently present refresh tokens for new access tokens.



- Grants obtained or updated by using the implicit grant type, for which is configured to reuse existing persistent grants



**Note:**

If the use cases involve mapping attributes from authentication sources or PCV instances to the access tokens, runtime procedures obtain attribute values for each token request, but persistent grants do not store with attributes or their values.

#### Persistent grant lifetime and maintenance

Persistent grants and any associated attributes and their values remain valid until the grants expire or until explicitly revokes or cleans them up.

Grants persist without any expiration information. Grants also persist with an idle timeout window, a maximum lifetime, or both. If you configure an idle timeout value, the idle timeout window slides when a persistent grant updates. When you have an idle timeout value configured without a maximum lifetime, persistent grants remain valid until they expire due to inactivity or until the grant storage revokes or removes them. When you have an idle timeout value configured with a maximum lifetime, persistent grants remain valid until they expire due to inactivity or lifetime expiration or until the grant storage removes them.

removes expired grants and the associated attributes from the grant datastore once a day. The frequency and the size of the cleanup batch are configurable. Optionally, caps the number of persistent grants on a basis of the combination of user, client, and grant type.

#### Persistent grant storage

Support for persistent grants requires the use of a database server or a directory server for long-term storage. PingFederate also supports other storage solutions through the PingFederate SDK. For more information, see [OAuth grant datastores](#) on page 963.

PingFederate uses a built-in HSQLDB database as its grant datastore after the initial setup.



**CAUTION:**

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

#### Grant storage and management

PingFederate uses a built-in HSQLDB database as its persistent grant datastore after the initial setup.



**CAUTION:**

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

Persistent grants and any associated attributes and their values remain valid until the grants expire or until explicitly revokes or cleans them up.

removes expired grants and the associated attributes from the grant datastore once a day. The frequency and the size of the cleanup batch are configurable. Optionally, caps the number of persistent grants on a basis of the combination of user, client, and grant type.

For revocation, PingFederate provides two endpoints.

#### Token revocation endpoint

The token revocation endpoint allows clients to notify the authorization server that they no longer need a previously-obtained refresh or access token. The revocation request invalidates the actual token and possibly other tokens based on the same authorization grant.

#### Grant-management endpoint

The grant-management endpoint allows resource owners to view and optionally revoke the persistent access grants they have authorized.

Intended for OAuth clients, the token revocation endpoint is the endpoint to which clients send their token revocation requests. The grant-management endpoint is for resource owners. It displays a list of grants the resource owners have made. Resource owners can view and optionally revoke one or more grants as they see fit.

### Mapping OAuth attributes

Mapping OAuth attributes is a two-stage processing workflow.


The two stages of mapping OAuth attributes include:

- The first stage: map from authentication sources, such as IdP adapter instances or IdP connections, authentication policy contracts, or Password Credential Validator instances (for resource owner credentials) to persistent grants.
- The second stage: map from persistent grants, authentication sources, authentication policy contracts, authentication context, or Password Credential Validator instances to access tokens.



#### Note:

This two-stage mapping workflow is different from other mapping scenarios in PingFederate, which involve just a one-phase configuration.



#### The first stage

To accomplish the first stage, setting up persistent grants requires mapping, including a user key and all extended attributes.

The mappings use attributes obtained during initial authentication events within PingFederate, namely attributes from IdP adapter instances, attributes from assertions through IdP connections, attributes from authentication policy contracts, or attributes returned by password credential validator instances. Configure data store queries to accomplish different tasks, such as retrieving the user identifier from an LDAP directory server as the user key.

**Important:**

The **USER\_KEY** attribute values must be unique across all end users, because the **USER\_KEY** attribute is the user identifier to store and to retrieve persistent grants. For example, the **sAMAccountName** attribute value of an end user in one domain might match that of another end user in another domain. In this case, you can map the **subject DN** attribute to the **USER\_KEY** attribute.

The second stage

The second mapping configuration involves mapping from persistent grants the user keys, any extended attributes derived from the first stage, or both into OAuth access tokens.

When the authentication context matches specific mappings between the authentication sources, authentication policy contracts, or password credential validators, the attributes map into access tokens. The **HTTP Request** Java object retrieves the authentication method that a client uses, or the private key JWT for client authentication if the client uses the `private_key_jwt` authentication method. The **HTTP Request** Java object maps it into the access tokens.

Data stores used here retrieve any required user attributes.

Runtime processing

At runtime, the first time a client requests an OAuth token, the process employs the two mapping sequences. Every time an existing persistent grant requests a new access token, the process invokes the second mapping.

**OAuth user-facing windows**

The PingFederate OAuth authorization server (AS) presents five windows to end users during OAuth transactions.

The windows include:

- One prompting for approval of the requested scopes
- One providing a means of revoking persistent access grants
- Three others displaying information for the purpose of connecting OAuth-capable internet of things (IOT) based on the [OAuth 2.0 Device Authorization Grant](#) specification

Administrators can customize these windows as needed.

**OpenID Connect**

As an extension of OAuth capabilities, PingFederate supports an optional configuration for OpenID Connect, a modern protocol for secure, lightweight transfer of authentication and user attributes.

OpenID Provider support

As an OpenID Provider (OP), PingFederate supports both the Basic Client and Implicit Client profiles defined in the standard. In both profiles, the end result releases an ID token and an OAuth access token; however, depending on associated grant types, PingFederate might also release a refresh token.

The ID token is an integrity-secured, self-contained token in JSON Web Token (JWT) format containing claims about the user. A client uses the ID token to identify the user accessing the client application through an OP. A client may subsequently use the OAuth access token to retrieve additional claims about the user, such as a complete profile containing full name, email, phone, and other schema elements defined in an OpenID Connect policy from the Userinfo endpoint (`/idp/userinfo.openid`).

For session management, PingFederate provides a front-channel endpoint for OAuth clients using the OpenID Connect protocol to close other associated sessions at `/idp/startSLO.ping` and a back-channel web service for clients to revoke end-user sessions at `/pfws/rest/sessionMgmt/revokedSris`.

As an OP, PingFederate optionally accepts request parameters through self-contained, signed JWTs. This capability enables PingFederate to validate the integrity of the request parameters it receives before processing the request further. PingFederate also includes a state hash (`s_hash`) in the ID token to protect the integrity of the `state` parameter.

### Relying Party support

As a Relying Party (RP), PingFederate is capable of leveraging identities from OPs to complete browser-based SSO requests. In this use case, PingFederate is the requesting OAuth client application.

The setup involves establishing an IdP connection to the OP. PingFederate retrieves identity information from the OP and passes the end-user claims, which are user attributes in an ID token, to one or more target applications. This configuration allows administrators to take advantage of their existing last-mile integration and expand the horizon of their applications to additional partners using the OpenID Connect protocol.

PingFederate is also capable of sending request parameters through self-contained, signed JWTs, thus adding a layer of security to the transmission of the request parameters. Additionally, if the ID token contains a state hash, PingFederate validates it.

### CORS support for OAuth endpoints

PingFederate supports cross-origin resource sharing (CORS) for several OAuth endpoints.

The supported OAuth endpoints include:

- `/as/token.oauth2`
- `/as/revoke_token.oauth2`
- `/idp/userinfo.openid`
- `/pf-ws/rest/oauth/grants/`
- `/pf/JWKS`
- `/.well-known/openid-configuration`
- `/as/bc-auth.ciba`

As needed, administrators can add or remove allowed origins using the administrative console on the **Authentication Application** page. For instructions on how to add and remove allowed origins, see [Configuring authentication applications](#) on page 434.

Once configured, client-side web applications from the trusted origins are allowed to make requests to the authorization server for the purpose of accessing protected resources, such as obtaining or renewing access tokens with refresh tokens, presenting access tokens for revocation, querying additional claims (user attributes), and retrieving OpenID Provider configuration information and JSON Web Key Sets.

## Bundled adapters and authenticators

PingFederate comes bundled with the following adapters and authenticators to enable common deployment scenarios.

### Bundled adapters

#### Composite Adapter

Allows multiple configured IdP adapters to execute in sequence. Depending on the authentication context, use this capability, called adapter chaining, for either single-adapter usage or to support multi-factor authentication through a series of adapters. For more information, see [Composite Adapter](#) on page 300.

#### HTML Form Adapter

Used in conjunction with Password Credential Validators. These adapters provide integration with user-datastores in directory servers or locally. For more information, see [HTML Form Adapter](#) on page 305.

## HTTP Basic Adapter

Used in conjunction with Password Credential Validators. These adapters provide integration with user-data stores in directory servers or locally. For more information, see [HTTP Basic Adapter](#) on page 325.

## Identifier First Adapter

When a variety of user types authenticate at , it is often better to ask the user for their identifier first, determine their user population, and prompt the user with the desired authentication requirements and experience. The Identifier First Adapter is designed to handle this use case. For more information, see [Identifier First Adapter](#) on page 328.

## Kerberos Adapter

Provides a seamless desktop SSO experience for Windows environments and supports authentication mechanism assurance from the Active Directory domain service. For new configurations and as a simpler alternative to the separately-available IWA Integration Kit, use this adapter. For more information, see [Kerberos Adapter](#) on page 335.

## OpenToken Adapter

Provides a generic interface for integrating with various applications, including Java- and .NET-based applications. For more information, see [OpenToken Adapter](#) on page 342.

## Passthrough IdP Adapter

The Passthrough IdP Adapter allows a user key to be associated with a user's authentication sessions. By placing the Passthrough IdP Adapter downstream from an IdP connection in a policy tree, you can take advantage of additional capabilities associated with defining a user key. For more information, see [Configuring a Passthrough IdP Adapter](#) on page 350.

## PingID Adapter

PingID is a cloud-based authentication service that binds user identities to their devices, making it an effective multi-factor authentication solution. For more information, see the [PingID documentation](#).

## PingOne Fraud Adapter

Allows PingFederate to use the PingOne Fraud service. For more information, see [PingOne Fraud Integration Kit](#).

## PingOne MFA Adapter

Allows PingFederate to use the PingOne MFA service for multi-factor authentication (MFA). For more information, see [PingOne MFA Integration Kit](#).

## PingOne Protect Adapter

When a user signs on through PingFederate, the adapter sends the transaction information to the PingOne Risk service and retrieves a risk evaluation and other information about the user's current and previous transactions. For more information, see [PingOne Risk Kit](#).

## PingOne Verify Adapter

Allows PingFederate to use the PingOne Verify service to trigger an identity verification challenge as part of the PingFederate authentication policy or registration flow. For example, you can use this adapter for personal identity verification based on a government issued photo ID. For more information, see [PingOne Verify Integration Kit](#).

## Bundled authentication selectors

PingFederate provides plugin authentication selectors, which enable dynamic selection of authentication sources based on administrator-specified criteria. Along with the Composite Adapter and token

authorization, the selectors enable dynamic integration with an organization's authentication or authorization policies, also known as adaptive federation.

**Tip:**

To select subsequent selectors or authentication sources for handling complex hierarchical access-policy decisions, use the results of authentication-selection criteria evaluation. For more information, see [Authentication policies](#) on page 231.

#### CIDR Authentication Selector

Provides a means of choosing authentication sources or other authentication sources at runtime based on whether an end-user's IP address falls within specified ranges using Classless Inter-Domain Routing notation. This selector allows administrators to determine, for example, whether an SSO request originates inside or outside the corporate firewall and use different authentication integration accordingly. For more information, see [Configuring the CIDR Authentication Selector](#) on page 234.

#### Cluster Node Authentication Selector

Provides a means of picking authentication sources or other authentication sources at runtime based on the PingFederate cluster node that is servicing the request. For example, you can configure this selector to choose whether PingFederate attempts Integrated Windows Authentication based on the PingFederate cluster node with which a Key Distribution Center is associated. For more information, see [Configuring the Cluster Node Authentication Selector](#) on page 236.

#### Connection Set Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on a match found between the target SP connection used in an SSO request and SP connections configured within PingFederate. For example, administrators with different requirements for SP connections can override connection adapter selection on an individual connection basis. For more information, see [Configuring the Connection Set Authentication Selector](#) on page 237.

#### Extended Property Authentication Selector

Enables PingFederate to choose configured authentication sources or other selectors based on a match found between a selector result value and an extended property value from the invoking browser-based SSO connections or OAuth client. For more information, see [Configuring the Extended Property Authentication Selector](#) on page 237.

#### HTTP Header Authentication Selector

Provides a means of choosing authentication sources or other authentication sources at runtime based on a match found using wildcard expressions in an HTTP header. This selector allows administrators to determine, for example, authentication behavior based on the type of browser. For more information, see [Configuring the HTTP Header Authentication Selector](#) on page 239.

#### HTTP Request Parameter Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on query parameter values in the HTTP request. For more information, see [Configuring the HTTP Request Parameter Authentication Selector](#) on page 241.

#### OAuth Client Set Authentication Selector

Enables PingFederate to choose configured authentication sources or other selectors based on a match found between the client information in an OAuth request and the OAuth clients configured in the PingFederate OAuth authorization server (AS). This selector allows you to override client authentication selection on an individual client basis in one or more authentication policies. For more information, see [Configuring the OAuth Client Set Authentication Selector](#) on page 243.

### OAuth Scope Authentication Selector

Provides a means of selecting authentication sources or other authentication sources at runtime based on a match found between the scopes of an OAuth authorization request and scopes configured in the PingFederate OAuth authorization server (AS). For example, if a client requires write access to a resource, administrators can configure the selector to choose an adapter that offers a stronger form of authentication such as the X.509 client certificate rather than username and password. For more information, see [Configuring the OAuth Scope Authentication Selector](#) on page 244.

### Requested AuthN Context Authentication Selector

Provides a means of picking authentication sources or other authentication sources at runtime based on the authentication context requested by an SP, for SP-initiated SSO. Configured authentication sources are mapped either to SAML-specified contexts or any ad-hoc context agreed upon between the IdP and SP partners. For more information, see [Configuring the Requested AuthN Context Authentication Selector](#) on page 245.

### Session Authentication Selector

Enables PingFederate to choose a policy path at runtime based on whether the user already has a PingFederate authentication session for a particular source. For more information, see [Configuring the Session Authentication Selector](#) on page 246.



#### Note:

Authentication selectors rely on HTTP requests, HTTP headers, POST data, or a combination of them. Ensure that standard security measures are in place when using these selectors.

### Software development kit (SDK)

The PingFederate SDK provides a flexible means of creating custom adapters to integrate federated identity management into your system environment. For more information, see the PingFederate [SDK Developer's Guide](#) on page 1115.

## Security infrastructure

This section describes the PingFederate security infrastructure that supports encrypted messaging, certificates, and digital signing.

PingFederate's configuration windows integrate these functions to provide complete control over certificate generation and authentication verification.

### Digital signatures

A digital signature is a way to verify the identity of a person or entity who originates an electronic document and ensure that the message has not been altered.

Both SAML, including security token service (STS) tokens, and WS-Federation electronic documents use digital signatures.

Handling a digital signature involves message signing, signature and certificate validation, and signing-policy coordination between connection partners.

### Message signing

Certificates contain information about the certificate owner along with a public key. Applying a digital signature creates and encrypts a hash from the signing message using the private key.

PingFederate provides a choice of signature encryption algorithms when you require a stronger algorithm.

To ensure the integrity of SAML messages or security token service (STS) tokens, we recommend digital signing practices using public/private keypairs in conjunction with X.509 certificates.

**Note:**

Digital signatures do not encrypt the contents of a message; instead, messages use XML encryption when needed.

Ping Identity recommends a certificate signed by a certificate authority (CA); however, PingFederate will work with self-signed or untrusted third-party-signed certificates. After generating a keypair and a self-signed certificate, use PingFederate to create a certificate signing request (CSR) and send it to a CA for signing. After the CA has generated a CSR, import it into PingFederate's certificate management system. PingFederate's trusted store or the Java runtime `cacerts` store must contain the CA's certificate.

PingFederate enables signing and validation of requests and responses. Additionally, PingFederate provides for certificate generation, import and export functionality, CSR generation, and application of digital signatures. You have the option to create reusable global signing certificates across your federated connection base and import signature verification certificates for each partner. For more information, see [Manage digital signing certificates and decryption keys](#) on page 667.

**Note:**

Ping Identity recommends generating unique certificates for each connection, which limits exposure if the private key becomes compromised.

### Signature validation

After receiving a signed message, PingFederate verifies the signature using the public key that corresponds with the private key used to sign the message or token. Verification involves creating a hash of the received message, using the signing partner's public key to decrypt the hash sent with the original message, and verifying that both hash values are equal.

### Certificate validation

PingFederate always checks certificates to see if they have expired when they are initially imported. It also checks certificates at runtime when they are used to verify incoming signed assertions.

PingFederate also checks to see whether a certificate has been revoked, using either certificate revocation lists (CRLs) or the online certificate status protocol (OCSP). Depending on the content of the certificate in question and your requirements, the server will perform either of these checks during single sign-on (SSO) or single log-out (SLO) processing for the following cases:

- Signature verification
- Validation of a client certificate used for authentication to PingFederate when the server is handling direct client requests
- Validation of the server SSL certificate when PingFederate acts as the client making an HTTPS request to a separate server

If the system encounters an expired or revoked certificate, the associated SSO or SLO transaction fails at runtime and writes an error to the transaction log. In the administrative console, the Status column of the respective Certificate Management list identifies the expired or revoked certificate.

In PingFederate, by default, OCSP revocation checking is enabled and CRL revocation checking is disabled. However, you can configure PingFederate to use only CRL checking or as a backup to OCSP checking.

For more information, see [Configuring certificate revocation](#) on page 682.

### CRL revocation checking

CRL revocation checking involves querying a CRL distribution-point URL and ensuring that a certificate is not on the returned revocation list maintained at the site. The certificate specifies the URL.



## OCSP revocation checking

OCSP revocation checking provides a more centralized and potentially more reliable means of checking certificate status than CRL revocation checking provides. In this scenario, the incoming certificate embeds an OCSP Responder URL or a configured default URL to query the certificate status.

The primary difference between OCSP and CRL checking is how the verification occurs. CRL checking requires the requesting client to determine if the certificate has been revoked, or if any of the certificates in the chain of issuer certificates has been revoked, based on the returned CRL. With OCSP, the client sends the certificate itself, and the Responder server handles revocation checking to return the certificate status.

For more information about OCSP, see [tools.ietf.org/html/rfc2560](https://tools.ietf.org/html/rfc2560).

## Digital signing policy coordination

To coordinate digital signature policy, partners must first agree about whether they will sign SAML messages or tokens.

In some cases, such as SAML security token service (STS) tokens and single sign-on (SSO) assertions sent across the POST binding, the protocol specifications require signatures. The PingFederate administrative console and the runtime protocol engine enforce these requirements. Some partner connections specify other, optional uses of the digital signatures between partners.

If a trusted, self-signed certificate authority (CA) does not issue a digital-signing certificate, then the signing partner must send the public-key certificate out-of-band, such as through email, to the partner. The partner must import the certificate into PingFederate when configuring a connection to the signing partner for SSO, single log-out (SLO), or STS.

If a trusted CA signs the certificate and the signing partner chooses to embed the certificate in all signed messages, then the verifying partner uses the embedded certificate for signature verification, after validating it against the Subject Distinguished Name (DN) of the original certificate. Because validation only requires the Subject DN, the public-key certificate might not be sent out-of-band.



### Tip:

During the signature verification configuration, PingFederate extracts the Subject DN from the certificate when available.

The next section provides more information about the two alternative signature-verification trust models described above from the standpoint of the verifying partner.

## Trust models

For validating digital signatures, PingFederate provides a selection of trust models in the administrative console for each partner connection, based on the certificate categories listed below. For each trust model, PingFederate always verifies the currency of the certificate and the validity of the message in the certificate specified. Additional checks depend upon the trust model selected.

### Anchored certificate

In this case, certificates used for signature verification must be issued by a trusted CA, and the certificate chain must be verifiable recursively back to the root issuer. PingFederate validates the certificate, including recursive revocation checking (when enabled) back to the issuer, for all signed messages from the partner. By default, PingFederate also prompts for the Issuer DN of the certificates to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections.

In addition, when choosing the anchored trust model, the incoming message must include the verification certificate for the signature. PingFederate uses that certificate to verify signatures from the partner if its Subject DN matches the partner's public certificate (as specified in the administrative console), the Issuer DN (if specified) matches one of the issuers in the chain, and the

Issuer CA certificate is part of the trusted store. This feature provides a dynamic trust model that overcomes the problem of interrupting service to change out expired certificates.

### Unanchored Certificate

In the unanchored certificate model, incoming signature verification exclusively uses the certificates imported for a connection into PingFederate or a secondary, backup certificate, either self-signed or trusted CA-issued, when specified. This verification does not apply to the certificate chain. However, when enabled, existing chains receive revocation checking as far as available.

### Secure sockets layer

A certificate authority (CA)-signed SSL certificate identifies one or both ends of the federation. SSL/TLS provides an encrypted connection between the two parties to avoid exposing the content of a message. This promotes confidentiality and message integrity.

### SAML SSL and TLS scenarios

SSL/TLS should be used in association with the SOAP responder URL and Single Sign-on Service located at an identity provider (IdP) site. On the service provider (SP) side, the Artifact Resolution Service should also use SSL/TLS. Optionally, SSL/TLS can also be used to secure communication between internal data stores and PingFederate and between the PingFederate security token service (STS) and web service client or provider applications.

The SSL/TLS server-client handshake involves negotiating cipher suites to use for encryption and decryption on each side of a secured transaction. You can find cipher suites in the following configuration files:

- `com.pingidentity.crypto.SunJCEManager.xml`
- `com.pingidentity.crypto.AWSCloudHSMJCEManager.xml`
- `com.pingidentity.crypto.LunaJCEManager.xml`
- `com.pingidentity.crypto.NcipherJCEManager.xml`
- `com.pingidentity.crypto.BCFIPSJCEManager.xml`

These cipher-suite configuration files are located in the `<pf_install>/server/default/data/config-store` directory. These files comment out weaker cipher suites. To ensure the most secure transactions, retain this cipher-suite configuration.



#### Important:

Because of the import restrictions of some countries, Oracle Server Java SE Runtime Environment (JRE) 8 has built-in restrictions on available cryptographic strength (key size). To use larger key sizes, enable the Java Cryptography Extension (JCE) unlimited strength jurisdiction policy. For more information, see the Java 8 release notes in Oracle's documentation.

For Oracle Java SE Development Kit 11, the JCE jurisdiction policy defaults to unlimited strength. For more information, see the Oracle JDK Migration Guide in Oracle's documentation.

Starting with version 9.1, PingFederate selects cipher suites based on the order that they appear in the cipher-suite configuration file for new installations. For upgrades, enable the same selection mechanism. For more information, see [Managing cipher suites](#) on page 892.

### Authentication

PingFederate browser-based single sign-on (SSO) uses three methods to authenticate connection partners making SOAP requests. For STS client SOAP authentication, configure a separate option using either or both of the first two methods listed here. Partners must agree upon the selection of methods and synchronize within IdP and SP federation implementations.

### HTTP Basic authentication

Partners identify themselves by passing username and password credentials.

### SSL client certificate authentication

Partners use SSL client certificates presented during SOAP request transactions. Each partner needs to import the other partner's certificate out-of-band. For more information, see [Manage SSL client keys and certificates](#) on page 664.

### Digital signatures

Partners sign the XML message transmitted through the SSL/TLS connection. The receiver verifies the signatures based upon the certificates configured for that connection. Each partner should import the others' certificates out-of-band. For more information, see [Manage digital signing certificates and decryption keys](#) on page 667.

### Trusted certificates

PingFederate validates the trust of all certificates. PingFederate trusts certificates if the issuer's certificate is also in PingFederate's trusted certificate store. You must import the root certificate of the CA into PingFederate's trusted certificate store or into the Java runtime `cacerts` store.

### Encryption

PingFederate supports the optional SAML 2.0 specification allowing for encryption of assertions, including security token service (STS) SAML tokens, which further enhances confidentiality when required.

For SAML 2.0 single sign-on (SSO) connections, you can choose to encrypt entire assertions or individual user attributes, including the user's name identifier. You can use signature verification and signing keys to encrypt and decrypt messages, respectively.

## Hierarchical plugin configurations

PingFederate allows you to use a configuration of an adapter along with other PingFederate plugins as a parent instance for any created child instances.

After this, you can then modify the inherited configuration for child instances as needed. This feature provides easier management of adapter settings in cases where only small changes to an existing adapter or plugin configuration need to be made for a particular use case.

For example, different service provider (SP)-connection adapter instances might have their own identity provider (IdP) sign-on URLs, for branding or other application ownership reasons, while the majority of the other adapter configuration settings are the same. In this case, you might want to use a parent/child configuration to override the logon URLs.



#### Tip:

Override adapter instances as part of mapping them into either SP or IdP connections for cases where overridden settings apply only to one particular connection configuration.

Any changes to a parent configuration propagate to its child or connection-based configurations so long as the derived instance has not overridden the changes.

In addition to adapters, PingFederate allows you to create parent/child configurations for the following plugin types:

- Token Translators (see [Token processors and generators](#) on page 81)
- Access Token Management instances (see [Access token management](#) on page 603)
- Password Credential Validators (see [Password Credential Validators](#) on page 980)
- Identity Store Provisioners (see [Configuring Identity Store Provisioners](#) on page 717)

## Identity mapping

Identity mapping is at the core of identity federation. One of the primary goals of SAML is to provide a way for an identity provider (IdP) to send a secure token, called the assertion, containing user-identity information that a service provider (SP) translates or maps to local user stores.

For browser-based single sign-on (SSO), PingFederate enables two modes of identity mapping between domains: account linking and account mapping.

For WS-Trust security token service (STS), PingFederate uses account mapping.

See subsequent topics for more information about these identity mapping options.

### Account linking

Under the standards, use account linking for browser-based single sign-on (SSO) in cases where each domain maintains separate accounts for the same user.

Account linking uses the SAML assertion to create a persistent association between these distinct user accounts. The account link, or name identifier, such as an email address or identity provider (IdP)-generated pseudonym, identifies individual users. When privacy is a concern, use pseudonyms because they prevent tracing back to a user's identity at the partner site.

During the user's first SSO request, the service provider (SP) prompts for local credentials, which enables the SP to link the name identifier contained within the assertion—either an open attribute or a pseudonym—with the user's local account. Subsequent SSO events will not prompt the user to authenticate with the SP because the SP federation server keeps a table associating remote users' name identifiers with local user accounts. The SP associates the link to the user's corresponding local account and provides access to the account without separate authentication.



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

The name identifier optionally includes additional attributes. When using a pseudonym as the account link, take care to send only general attributes, such as a user's organizational role or department, that will not compromise privacy.

### Linking permission and defederation

The SAML specification also allows the SP application to build in user verification and approval of account linking and provides a means for the user to permanently cancel the linking, known as defederation. For more information, see [/sp/defederate.ping](#) on page 1259. A defederated user might later elect to re-associate with a local user account.

### SP affiliations

Under the SAML 2.0 specifications, an IdP configures PingFederate to enable a group of SPs, called an SP affiliation, to share the same persistent name identifier. For more information, see [SP affiliations](#) on page 515. An SP affiliation facilitates the use case where a number of business partners have an existing relationship and where sharing a single name identifier among all parties reduces the federation integration effort.

## Account mapping

Account mapping, also called attribute mapping, enables a service provider (SP) to use PingFederate to perform a user lookup and map a user's identity dynamically based on one or more attributes received in the assertion.

Looking up the user always exposes the attributes. In other words, both the identity provider (IdP) and the SP know these attributes, such as an email address.

Account mapping achieves one-to-one mapping where individual user accounts exist on both sides of a federated connection or many-to-few mapping where IdP users without accounts at destination sites map to guest accounts or to a role-based general account.

For browser-based single sign-on (SSO), transient identifiers provide an additional level of privacy—virtual anonymity—by generating a different opaque ID each time the user initiates SSO. Transient IDs are often used in conjunction with federation role mapping to map the user to a guest account or to a role-based account based on the user's association with the IdP organization rather than personal attributes.

As with pseudonyms, additional attributes might be sent with the transient identifier. Again, take care to preserve privacy.

In B-to-B or B-to-E use cases where an administrator might create a user lookup on behalf of the user, the administrator might implement account mapping.

## User attributes

Federation transactions require, at a minimum, the transmission of a unique piece of information, such as an email address, that identifies the user for identity mapping between security domains.

In addition to attributes used for identity mapping, the identity provider (IdP) can pass other user attributes in an assertion, including SAML tokens for web services. The service provider (SP) uses this supplemental information for several purposes. For example, the SP can use attributes to map and authorize the user into a specific role with associated site permissions or to customize the end application display for a more robust user experience.

The SP can also incorporate additional attributes prior to creating a session for the target application. This is common where the SP also maintains an account for the user and wants additional information for profiling or access-policy purposes.

Attributes must be carefully managed between IdPs and SPs. PingFederate facilitates the process by providing configuration steps that enable administrators to:

- Define and enforce `attribute_contract` for each partner connection.
- Define and retrieve attributes from the IdP adapter, authentication policy contracts, or security token service (STS) token processor to populate an attribute contract directly or use these attributes to look up additional attributes in IdP data stores.
- Define and enforce a set of required attributes needed by SP adapters or STS token generators to interface local systems or applications.
- Set up connections to local data stores.
- Configure specific attribute sources and lookups based on the data stores and map attributes into IdP assertions or into SP adapters or token generators used to interface target applications.
- Selectively mask attribute values recorded in transaction logs.

### Attribute contracts

An attribute contract represents an agreement between partners about user attributes sent in a SAML assertion, a JSON web token (JWT), or an OpenID Connect ID token.

The contract is a list of case-sensitive attribute names. Partners must configure attribute contracts to match.



**Tip:**

When privacy is required for sensitive attributes, you can configure PingFederate to mask their values in log files. For more information, see [Attribute masking](#) on page 104.

For an identity provider (IdP) or an OpenID Provider (OP), the attribute contract defines which attributes PingFederate sends in an assertion, a JWT, or an ID token. While all users authenticate to the partner through this fixed contract, the values used to fulfill the contract might differ from one user to the next. Relying on a combination of different data sources might also fulfill the attribute contract:

- The IdP adapter or security token service (STS) token processor
- An IdP attribute source, which identifies the location of individual attributes in a datastore
- Static text values for some attributes, or text values combined with variables
- Expressions (see [Attribute mapping expressions](#) on page 225)

For a service provider (SP) or an OpenID Connect Relying Party, the attribute contract defines the attributes PingFederate expects in a SAML assertion, an ID token, or from the UserInfo endpoint at the OP. To pass these attributes to the SP adapter or, for web services, to the SP token generator, configure PingFederate accordingly. For more information, see [Managing SP adapters](#) on page 713 or [Managing token generators](#) on page 1066. In addition, you can configure PingFederate to use attributes to look up additional attributes in local data stores, which often help start a user session or create a local security token for web services. For more information, see [Adapter contracts](#) on page 103 or [STS token contracts](#) on page 103.

The attribute contract always contains the user identifier **SAML\_SUBJECT** in a SAML assertion and **sub** in a JWT or an ID token unless you are using account linking for browser-based single sign-on (SSO). This attribute is automatically included when creating a new contract.



**Note:**

You create attribute contracts on a per-connection basis. For example, if an SP has deployed two session-creation adapters for two separate applications, the IdP connection partner creates a single attribute contract. This single contract supplies all the attributes required by both SP adapters.

#### Name formats

By agreement with an SP partner, an IdP might specify a format, such as email, associated with the **SAML\_SUBJECT**. The SP might further require this information to facilitate handling of the format.

The partner agreement might also include a requirement for the IdP to provide format specifications associated with other attributes.

PingFederate provides a means for an IdP administrator to select from among standard subject, attribute formats, or both, depending on the relevant SAML specifications. An administrator also defines a customized selection of additional attribute formats. For more information, see [Setting up an attribute contract](#) on page 456.



**Note:**

The designation of formats does not apply to SP administrators. The information about formats remains available in the incoming assertion to an SP application that needs the information for particular processing requirements.

For the WS-Trust IdP configuration, attribute-name formats remain unspecified. If needed however, an administrator might use a special variable in the attribute contract to set the subject-name format. For more information, see [Defining an attribute contract for IdP STS](#) on page 1054. Browser-based SSO attribute contracts also use the same variable, but the feature has deprecated.

## STS namespaces

By agreement with an SP partner for a WS-Trust STS connection, an IdP specifies an XML namespace to associate with an attribute, for example, to use claims-based authorization with WIF clients. For more information, see [WSC and WSP support](#) on page 82. The only attributes that allow specified namespaces belong to a WS-Trust IdP configuration using **SAML 1.1** or **SAML 1.1 for Office 365** as the default token type. For more information, see [Defining an attribute contract for IdP STS](#) on page 1054.

## Adapter contracts

An adapter contract represents an agreement between the PingFederate server and an external application.

In concert with the attribute contract between partners, adapter contracts specify the transfer of attributes. Adapter contracts consist of a list of case-sensitive attribute names.

On the identity provider (IdP) side of a federation, an IdP adapter supplies attributes to PingFederate for more information, see [Bundled adapters and authenticators](#) on page 65 and [Managing IdP adapters](#) on page 420.

On the service provider (SP) side, adapters require adapter contract attributes to start a session with an application. Each security domain requires at least one adapter type. Then, you must configure an adapter instance for each target application. For more information, see [Managing SP adapters](#) on page 713.

Attributes from the attribute contract fulfill the adapter contracts on the SP side, possibly enhanced with other attributes from local data stores. For example, if the same security context controls several target applications and provides the same set of attributes to start a session for the user, you would deploy an adapter type and configure an adapter instance for each protected application. For more information, see [Managing target session mappings](#) on page 739.

## Extended adapter contract

When PingFederate deploys an adapter type, it creates adapter contracts. Developing these adapters "hard-wires" them to look up or set a specific set of attributes. Attribute requirements might change after deployment. To streamline adjustment of adapter contracts, PingFederate allows an administrator to add additional attributes to the adapter instance through the administrative console, called extended adapter contracts.

## STS token contracts

Similar to an adapter contract for browser-based single sign-on (SSO), A security token service (STS) token-processor or token-generator contract represents an agreement between the PingFederate server and an external application in the context of a web services transaction.

In concert with the attribute contract between partners, token contracts specify the transfer of attributes, consisting of a list of case-sensitive attribute names.

On the identity provider (IdP) side of a federation, PingFederate receives token-processor attributes. For more information, see [Token processors and generators](#) on page 81 and [Managing token processors](#) on page 1043.

On the service provider (SP) side, a token generator requires token-generator contract attributes to pass identify information from the token to the web service client application. Each security domain requires at least one token generator type. Then a token-generator instance must be configured for each target application. For more information, see [Managing token generators](#) on page 1066. If several target applications are controlled by the same security context and can receive the same set of attributes for the user, you would deploy a token generator type and configure a token generator instance for each target application. For more information, see [Managing SP token generator mappings](#) on page 1070.

## Extended token generator contract

When PingFederate deploys a token-generator type, it creates token-generator contracts. When developed, these token generators are "hard-wired" to look up or set a specific set of attributes. After

deployment, your attribute requirements might change. To streamline adjustment of token-generator contracts, PingFederate allows an administrator to add additional attributes to the token-generator instance through the administrative console. These adjustments are called extended token-generator contracts.

### Datstores

Datstores represent external systems that store user attributes and other data.

Once defined, PingFederate configurations retrieve user attributes from datstores for contract fulfillment and token authorization in various use cases. Configurations write certain records or log messages to datstores. PingFederate supports a wide variety of database servers and directory servers. As needed, the SDK supports the creation of custom drivers for connecting to other types of data repositories, such as flat files or SOAP-connected databases. For more information, see the Javadoc for the `CustomDataSourceDriver` interface, the `SamplePropertiesDataStore.java` file for a sample implementation, and the [SDK Developer's Guide](#) on page 1115 for build and deployment information.



#### Tip:

The Javadoc for `CustomDataSourceDriver` and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

### Attribute masking

At runtime PingFederate logs user attributes. To preserve user privacy, you can mask the values of logged attributes.

For more information about log files, see [PingFederate log files](#) on page 828. PingFederate provides this masking capability at all points where the server logs attributes. These points include:

- Datstore lookup at either the identity provider (IdP) or service provider (SP) site. For more information, see [Datstores](#) on page 936.
- Retrieval of attributes from an IdP adapter or token processor. For more information, see [Setting pseudonym and masking options](#) on page 423 and [Setting attribute masking](#) on page 1049.
- SP-server processing of incoming attributes based on the single sign-on (SSO) attribute contract. For more information, see [Defining an attribute contract](#) on page 737.



#### Note:

The SAML Subject ID is not masked; the SAML specifications provide for either pseudonymous account linking or transient identification to support privacy for the Subject ID. For more information, see [Account linking](#) on page 100.

- SP-server processing of incoming attributes in response to an Attribute Request under X.509 Attribute Sharing Profile (XASP). For more information, see [Configuring security policy for Attribute Query](#) on page 763.

For information about XASP, see [Attribute Query and XASP](#) on page 49.



#### Important:

Many adapter implementations, along with other product extensions, can independently write unmasked attribute values to the PingFederate server log. PingFederate does not control these implementations. If using such a component raises a concern about sensitive attribute values, you can adjust the component's logging threshold in `log4j2.xml` to prevent the recording of attributes.



## Token authorization

PingFederate provides an optional configuration known as token authorization to evaluate user attributes as well as other runtime variables, such as authentication context, for authorization purposes.

Token authorization provides a way for administrators to extend access policy directly to many areas, such as browser single sign-on (SSO), security token service (STS), and OAuth events, by conditionally allowing or disallowing the issuance of relevant security tokens such as SAML assertions, STS tokens, OAuth access tokens, or session cookies. The option is also available for extending authorization policy to attribute-query responses, identity provider (IdP) adapter contracts, and authentication policy contracts.

Administrators can configure token authorization using Issuance Criteria windows immediately following the configuration of attribute mapping at all applicable points in the administrative console. See [Defining issuance criteria for IdP Browser SSO](#) on page 465 as an example.

### Issuance criteria

The token-authorization configuration consists of rules that evaluate attribute values against selected conditions. Depending on the type of configuration that contains the token-authorization setup, choose from among several sources for the attributes. The sources always consist of all of those available for attribute mapping, including configured data stores and runtime information related to the context of an event. In addition, the sources use values of mapped attributes to provide access to any plain-text mappings or the runtime results of any attribute mapping expressions.



#### Tip:

When more than one condition is configured, all are evaluated and all the conditions must be met at runtime (evaluated as true) for authorization to succeed and processing to continue. In cases where you might need “or” conditions or layered evaluations, you can create one or more attribute mapping expressions.



#### Note:

When authorization fails and a transaction halts, the system passes back a configurable `Error Result` code, potentially to an application layer or as a variable on a PingFederate user-facing template. How this code is interpreted depends on the use case and application integration.

### Single and multivalued conditions

Each token-authorization configuration provides a choice of conditions for evaluating attribute values:

- equal to
- equal to (case insensitive)
- equal to DN
- not equal to
- not equal to (case insensitive)
- not equal to DN
- multi-value contains
- multi-value contains (case insensitive)
- multi-value contains DN
- multi-value does not contain
- multi-value does not contain (case insensitive)
- multi-value does not contain DN



#### Note:

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions when you want to validate whether one of the attribute values matches or does not match the specified value. Using a single-value condition when an attribute has multiple values causes the criteria to fail consistently.

## User provisioning

PingFederate provides cross-domain user provisioning and account management.

User provisioning is an important aspect of identity federation. When organizations enable SSO for their users, they must ensure that some form of account synchronization is in place. Automated user provisioning features within free administrators from having to devise a manual strategy for this.

Provisioning support takes different forms, depending on what role PingFederate plays in an identity federation, and you can configure it either in conjunction with partner SSO connections or separately:

- IdP sites support automatic provisioning and maintaining user accounts at service provider (SP) sites that have implemented the system for cross-domain identity management (SCIM) or at selected software as a service (SaaS) providers. For more information, see the next section, [Outbound provisioning for IdPs](#) on page 106.

For information about SCIM, see [www.simplecloud.info](http://www.simplecloud.info).

- When PingFederate is configured as a SP, it supports provisioning and managing user accounts and groups for your own organization automatically by using the standard SCIM protocol or by using identity information received during SSO events from SAML assertions. For more information, see [Provisioning for SPs](#) on page 107.

### Outbound provisioning for IdPs

For identity provider (IdP) sites, PingFederate provides built-in automated provisioning and user-account management to system for cross-domain identity management (SCIM)-enabled services providers and to selected software as a service (SaaS) providers through their proprietary provisioning APIs.

User provisioning is an important aspect of identity federation. When organizations enable SSO for their users, they must ensure that some form of account synchronization is in place. Automated user provisioning features within free administrators from having to devise a manual strategy for this.


Outbound provisioning also provides an automated means of account disabling or deprovisioning, which might be of key importance to system auditors.



#### Tip:

Support for provisioning for SaaS applications, including quick-connection templates to expedite the configuration effort, is available separately. Contact [sales@pingidentity.com](mailto:sales@pingidentity.com) for more information.

With outbound provisioning enabled, the PingFederate runtime engine, the provisioner, polls the IdP organization's user store periodically. The server uses a separate database to monitor the state of the user store and keeps user data synchronized between the organization and the target service provider, as illustrated in the following diagram.



### LDAP user store

PingFederate provides built-in support for PingDirectory, Microsoft Active Directory, Oracle Unified Directory; pre-configuration of many provisioning settings uses templates. Although Ping Identity has only formally tested these datastores for support, other LDAP datastores will likely work as well.

### Internal datastore

PingFederate is tested with Amazon Aurora (MySQL and PostgreSQL), Microsoft SQL Server, Oracle Database, Oracle MySQL, and PostgreSQL as internal provisioning datastores. A demonstration-only, embedded HSQLDB database is installed by default. Scripts to aid setup are in the directory `<pf_install>/pingfederate/server/default/conf/provisioner/sql-scripts`.



### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

## Provisioning for SPs

PingFederate offers two provisioning options when configured as a service provider (SP).

User provisioning is an important aspect of identity federation. When organizations enable SSO for their users, they must ensure that some form of account synchronization is in place. Automated user provisioning features within free administrators from having to devise a manual strategy for this.

When configured as an SP, PingFederate offers two provisioning options:

### Inbound provisioning

SCIM inbound provisioning provides support for incoming SCIM messages containing requests to create, read, update, delete, or deactivate user and group records in Microsoft Active Directory datastores or custom user stores through the Identity Store Provisioners. supports SCIM attributes in the core schema and custom attributes through a schema extension. Configuring this provisioning feature has two options: by itself or in conjunction with SSO or other connection types.

In effect, inbound provisioning provides an organization with a dedicated SCIM service provider, which routes user-management requests to an organization's centralized user store. The requests usually originate from trusted applications within an organization, such as a human-resources on-boarding software as a service (SaaS) product, or from trusted partner identity providers (IdPs).

For setup information, see [Configuring SCIM inbound provisioning](#) on page 773. To integrate inbound provisioning with custom user stores, see [Configuring Identity Store Provisioners](#) on page 717. For application-development information about using PingFederate endpoints for SCIM provisioning, see [SCIM inbound provisioning endpoints](#) on page 1261.

### Just-in-time provisioning

At an SP site, creates and updates local user accounts in an external LDAP directory or Microsoft SQL Server as part of SSO processing, called Just-in-time (JIT) provisioning or, formerly, Express Provisioning. When provisioning requires local accounts, this feature allows SPs to maintain accounts for users who authenticate through IdP partners without having to provision accounts manually.

When configured, the SP server writes user information to the local user store using attributes from the incoming SAML assertion. For SAML 2.0 partner connections, supplement assertion attributes with user attributes returned from an Attribute Query.

also updates existing user accounts based on assertions. Using this option, adds or overwrites attributes for a local user account each time processes SSO for a user.

For information about enabling JIT Provisioning, see [Choosing IdP connection options](#) on page 728. For configuration information, see [Configuring just-in-time provisioning](#) on page 763.

## Customer identity and access management

PingFederate empowers administrators to deliver a secure and easy-to-use customer authentication, registration, and profile management solution.

This solution leverages the HTML Form Adapter to offer users the options to authenticate through third-party identity providers, self-register as part of the sign-on experience, and manage their accounts through a self-service profile management page. The registration and profile management pages are fully customizable and localizable, which allows administrators to present a consistent branding experience based on the needs of the users and the organizations.

## Federation hub use cases

Configuring PingFederate as a federation hub accomplishes two primary functions.

Configure PingFederate as a federation hub to:

- Bridge partners using different federation protocols to circumvent partner or application limitations.
- Multiplex a connection for multiple partners to reduce costs and expand use cases.

As a federation hub, PingFederate bridges browser-based single sign-on (SSO) between identity providers and service providers. It stands in the middle of the SSO and single log-out (SLO) flow, acting as the service provider (SP) for the identity providers and as the identity provider (IdP) for the service providers. The four use cases are:

- Bridging an IdP to an SP
- Bridging an IdP to multiple SPs
- Bridging multiple IdPs to an SP
- Bridging multiple IdPs to multiple SPs

PingFederate also supports protocol translation among SAML 1.0, 1.1, 2.0, OpenID Connect, and WS-Federation. For SAML-based connections, this also means it is possible to bridge between various bindings between identity providers and service providers.


The federation hub capability deploys alongside with other OAuth use cases, IdP connections, SP connections, or any combination of them, to your partners. This flexibility helps in streamlining your federation infrastructure and reducing operating costs.

## Bridging an IdP to an SP

PingFederate bridges single sign-on (SSO) and single log-out (SLO) transactions between an identity provider (IdP) and a service provider (SP).

### About this task

If you have a legacy IdP system only capable of sending SAML 1.1 assertions through POST and an SP that requires SAML 2.0 assertions through the artifact binding, configuring the federation hub allows PingFederate to consume inbound SAML 1.1 assertions by POST, translate them to SAML 2.0 assertions, and send them through the artifact binding the SP.



### Steps


1. Create a contract to bridge the attributes between the IdP and the SP. For more information, see [Federation hub and authentication policy contracts](#) on page 112.
2. Create an IdP connection between the IdP and PingFederate, the federation hub as the SP, and add the applicable authentication policy contracts to the IdP connection on the **Target Session Mapping** tab.
3. Create an SP connection between PingFederate, the federation hub as the IdP, and the SP and add to the SP connection the corresponding authentication policy contract on the **Authentication Source Mapping** window.
4. Work with the IdP to connect to PingFederate, the federation hub, as the SP.
5. Work with the SP to connect to PingFederate, the federation hub, as the IdP.

## Bridging an IdP to multiple SPs

PingFederate bridges single sign-on (SSO) and single log-out (SLO) transactions between an identity provider (IdP) and multiple service providers (SPs).

### About this task

For example, your company wants to route federation requests from a recently acquired subsidiary through its federation infrastructure. PingFederate multiplexes one IdP connection to multiple SP connections to the desired SPs. The federation hub consumes assertions from the subsidiary and creates new assertions to the respective SPs.



### Steps

1. For each SP, create a contract to the IdP. For more information, see [Federation hub and authentication policy contracts](#) on page 112. Because each SP likely requires a unique set of attributes, you will need to create multiple contracts.


2. Create an IdP connection between the IdP and PingFederate, the federation hub as the SP.
3. Add the applicable authentication policy contract(s) to the IdP connection on the **Target Session Mapping** window.
4. For each SP, create an SP connection between PingFederate, the federation hub as the IdP, and the SP.
5. Add the corresponding authentication policy contract to the SP connection on the **Authentication Source Mapping** window.
6. For each SP supporting the SAML IdP-initiated SSO profile, map the expected target resources to the corresponding SP connections on the **Applications # Integration # Target URL Mapping** window.
7. Work with the IdP to connect to PingFederate, the federation hub as the SP.
8. Work with each SP to connect to PingFederate, the federation hub as the IdP.

### Bridging multiple IdPs to an SP

With PingFederate, you can bridge single sign-on (SSO) and single log-out (SLO) transactions between multiple identity providers (IdPs) and a service provider (SP).

About this task

For example, you are tasked to provide federated access to resources on Microsoft SharePoint for various business partners. With PingFederate, you can multiplex one SP connection, to SharePoint, to multiple IdP connections for all your business partners. The federation hub can also, as needed, translate SAML assertions from the business partners to WS-Federation security tokens and send them over to SharePoint.



Steps

1. Create a contract to bridge the attributes between the IdPs and the SP. For more information, see [Federation hub and authentication policy contracts](#) on page 112.  
You likely need only one contract unless the SP requires a different set of attributes from each IdP.
2. For each IdP, create an IdP connection between the IdP and PingFederate, the federation hub as the SP.
3. On the **Target Session Mapping** window, add the applicable authentication policy contracts to the IdP connection.
4. On the **Selectors** window, configure an authentication selector. For example, see an instance of the [Identifier First Adapter](#) on page 328 to map each IdP to the corresponding IdP connection in an authentication policy.
5. Create an SP connection between PingFederate, the federation hub as the IdP, and the SP.
6. Add the corresponding authentication policy contract to the SP connection on the **Authentication Source Mapping** window.

#### Important:

PingFederate includes the Entity ID of the original IdP (**Authenticating Authority**) in SAML 2.0 assertions so that the SP can determine the original issuer of the assertions. This is especially

important when bridging multiple IdPs to one SP—the SP should take the information about the original issuer into consideration before granting access to protected resources.

For SAML 1.x assertions and WS-Federation security tokens, you can add an attribute on the **Attribute Contract** window and then map **Context: Authenticating Authority** as the attribute value on the **Attribute Contract Fulfillment** window.

For information about **Authenticating Authority**, see section [2.7.2.2 Element <AuthnContext>](#) in the SAML 2.0 specification.



**Note:**

If the SP does not take action based on **Authenticating Authority**, depending on the attributes from the IdPs, you can define validation rules on the **Issuance Criteria** window to protect against user impersonation between IdPs.


7. Work with each IdP to connect to PingFederate, the federation hub as the SP.
8. Work with the SP to connect to PingFederate, the federation hub as the IdP.

### Bridging multiple IdPs to multiple SPs

PingFederate can bridge single sign-on (SSO) and single log-out (SLO) transactions between multiple identity providers (IdPs) and service providers (SPs).

About this task

This PingFederate federation hub use case is a combination of [Bridging an IdP to multiple SPs](#) on page 109 and [Bridging multiple IdPs to an SP](#) on page 110.



### Steps

1. Create multiple contracts to bridge the attributes between the IdPs and the SPs. For more information, see [Federation hub and authentication policy contracts](#) on page 112.
2. For each identity provider, create an IdP connection between the IdP and PingFederate, the federation hub as the SP.
3. Add the applicable authentication policy contracts to the IdP connection in the **Target Session Mapping** window.
4. In the **Selectors** window, configure an authentication selector to map each IdP to the corresponding IdP connection in an authentication policy. For example, see an instance of the [Identifier First Adapter](#) on page 328.
5. For each service provider, create an SP connection between PingFederate, the federation hub as the IdP, and the SP.

6. Add the corresponding authentication policy contract to the SP connection in the **Authentication Source Mapping** window.



#### Important:

PingFederate includes the Entity ID of the original IdP, **Authenticating Authority**, in SAML 2.0 assertions so that the SP can determine the original issuer of the assertions. This is especially important when bridging multiple IdPs to one SP—the SP should take the information about the original issuer into consideration before granting access to protected resources.

In the **Attribute Contract** window, add an attribute for SAML 1.x assertions and WS-Federation security tokens. Then, in the **Attribute Contract Fulfillment**, map **Context: Authenticating Authority** as the attribute value.

For information about **Authenticating Authority**, see section [2.7.2.2 Element <AuthnContext>](#) in the SAML 2.0 specification.



#### Note:

If the SP does not take action based on **Authenticating Authority**, in the **Issuance Criteria** window, you can define validation rules to protect against user impersonation between IdPs.

7. For each SP supporting the SAML IdP-initiated SSO profile, map the expected target resources to the corresponding SP connections in the **Applications # Integration # Target URL Mapping** window.
8. Work with each IdP to connect to the federation hub as the SP.
9. Work with each SP to connect to the federation hub as the IdP.

### Federation hub and authentication policy contracts

PingFederate uses two connections to bridge an identity provider (IdP) to a service provider (SP). It fuses these two connections together by using an authentication policy contract as the medium to carry user attributes from the IdP to the SP.

The two connections are:

- An IdP connection where end users authenticate and PingFederate, the federation hub, is the SP
- An SP connection to the target application where PingFederate, the federation hub, is the IdP

Each authentication policy contract comes with one default attribute, **subject**. You can extend the contract to include additional attributes as needed. In most federation hub use cases, you configure PingFederate to pull attribute values from inbound assertions into the authentication policy contract in an IdP connection and to push those values from the authentication policy contract into the outbound assertions through an SP connection. For advanced use cases, you can configure the IdP connections, SP connections, or both, to look up values from multiple data store instances.

PingFederate can use OGNL expressions to customize authentication request and response messages from IdP connections before sending them to SPs. To customize messages, the expressions can use the variables `#FedHubIncomingAuthnResponse`, `#FedHubIncomingAuthnRequest`, and `#FedHubOutgoingAuthnRequest` in an SP connection when an authentication policy is used to select the IdP connection. For more information, see [Customizing assertions and authentication requests](#) on page 390 and [Message types and available variables](#) on page 391.

When bridging one IdP to one SP, you must create one authentication policy contract and associate the contract with both the IdP connection and the SP connection.

When bridging one IdP to multiple SPs, you need to create an authentication policy contract per SP because each SP likely requires a different set of attributes. In addition, you need to map all the authentication policy contracts into the IdP connection and add the respective authentication policy contracts to each SP connection to the SP.



When bridging multiple IdPs to one SP, you likely need only one contract unless the SP requires a different set of attributes from each IdP. In addition, you need to add the authentication policy contract to the SP connection and the applicable IdP connections.

You can manage authentication policy contracts on the **Policy Contracts** window (**Authentication # Policies # Policy Contracts**).

### Federation hub and virtual server IDs

PingFederate manages the federation hub differently based on how the server provider (SP) connection uses virtual server IDs.

PingFederate uses two connections to bridge an identity provider (IdP) to a SP:

- An IdP connection where end users authenticate and PingFederate, the federation hub, is the SP
- An SP connection to the target application where PingFederate, the federation hub, is the IdP

Generally speaking, PingFederate consumes assertions from the IdP through the IdP connection and generates new assertions to the SP through the SP connection.

If the SP connection does not use a virtual server ID, the issuer of the assertions to the SP is the ID defined for the protocol between PingFederate, the federation hub as the IdP, and the SP.

If the SP connection uses multiple virtual server IDs for the purpose of connecting to multiple environments serviced by the same partner using one connection, PingFederate automatically retains information about AuthnRequest messages sent to the virtual server ID specific endpoint for SP-initiated single sign-on (SSO). When the IdP returns the corresponding assertions to PingFederate as the SP, PingFederate retrieves the preserved information and uses that specific virtual server ID as the issuer in assertions sent to the SP. For IdP-initiated SSO, the issuer of the assertions to the SP is the default virtual server ID.

## Federation planning checklist

An essential first step in establishing an identity federation involves discussions and agreements between you and your connection partners. The sections below comprise a partial checklist of items that should be coordinated before you deploy PingFederate.

### Standards and specifications

Choose which federation protocols your deployment will support. For SAML single sign-on (SSO) configurations, decide which profiles and bindings will be used. For more information, see [Supported Standards](#).

### Signing and validation

Decide which SAML messages—assertions, responses, requests—will be digitally signed and how the messages will be verified by your federation partner. If messages are signed, decide how certificates will be exchanged, for example, secure email. For more information, see [Security infrastructure](#) on page 95.

### Back-channel security

Determine what type of SOAP channel authentication will be used: Basic or SSL/TLS. If SSL/TLS is used, determine whether server-only or both server and client certificates will be needed and how they will be managed. Also decide what level of security will be required for connections to back-end datastores or identity management systems.

### Trusted certificate management

Determine whether both partners are using SSL/TLS runtime certificates, signing certificates, or both that have been signed by a major certificate authority (CA). If self-signed certificates or nonstandard CAs are used, the signed certificates must be exchanged and imported into Trusted Certificate stores. Also, determine whether you want to adopt a trust model that uses embedded certificates. For more information, see [Digital signing policy coordination](#) on page 97.

## Deployment

Decide how PingFederate fits into your existing network. Also, determine whether high-availability, failover options, or both, are required. For more information, see the PingFederate [Server Clustering Guide](#) on page 189.

## Federation server identification

Determine how you and your partners will identify your respective federation deployments. Under federation standards, both the sender, the identity provider (IdP), and the receiver, service provider (SP), of an assertion must be uniquely identified within the identity federation. For more information, see [Configuration data exchange](#) on page 116.

With PingFederate, you define a unique ID for each supported protocol. For more information, see [Specifying federation information](#) on page 910. Optionally, you can also use a list of multiple virtual server IDs on a connection-by-connection basis. For more information, see [Multiple virtual server IDs](#) on page 115.



### Tip:

PingFederate also provides for virtual host names, which differ from virtual server IDs but are not mutually exclusive; they are intended for use when your network configuration is such that you receive federation messages under more than one domain name. For more information, see [Configuring virtual host names](#) on page 928.

## Server clock synchronization

Ensure that both the SP and IdP server clocks are synchronized. SAML messages and security token service (STS) tokens provide a time window that allows for small synchronization differentials. However, wide disparities will result in assertion or request time-outs.

## User data stores

Identify the type of datastore that contains user data when needed. For more information, see [Datastores](#) on page 104.

## Web application and session integration

Decide how PingFederate as an IdP receives subject identity information, either from an STS token or a user session.

For an SP, decide how PingFederate will forward user identity information to the destination web application or system to start a session. For more information, see [Bundled adapters and authenticators](#) on page 65 and [Token processors and generators](#) on page 81.

## Transaction logging

PingFederate provides basic transaction logging and monitoring. Decide whether transaction logging should be integrated with a systems management application and whether you have regulatory compliance requirements that affect your logging processes. For more information, see [PingFederate log files](#) on page 828.

## Identity mapping

For browser-based SSO, decide whether you will use PingFederate to link accounts on your respective systems using a persistent name identifier, or whether you will use account mapping. For more information, see [Identity mapping](#) on page 100.

### Attribute contract agreement

If your federation partnership will not use account linking, or will not use it exclusively, then you and your partner must agree on a set of attributes that the IdP will send in an assertion for either SSO or web service access. For more information, see [Attribute contracts](#) on page 101

### Metadata exchange

If you are using SAML, decide whether you will use the metadata standard to exchange XML files containing configuration information. PingFederate makes it easy to use this protocol, which provides a significant shortcut to setting up your partner connections.

### Multiple virtual server IDs

Virtual server IDs provide more configuration flexibility in cases where you need to identify your server differently when connecting to a partner in one connection for multiple environments or in multiple connections where the partner also supports multiple federation IDs.

#### Connecting to a partner in one connection

This is a use case where you need to connect to multiple environments serviced by the same partner using one federation ID, multiplexing one service provider (SP) connection to access multiple subdomain accounts in Microsoft Office 365.

Suppose both the marketing and the engineering departments of contoso.com, the identity provider (IdP), have their own departmental subdomains, marketing.contoso.com and engineering.contoso.com. They are both registered in Office 365, the SP, under the parent domain, contoso.com.

To include both marketing.contoso.com and engineering.contoso.com as the virtual server IDs in the Office 365 SP connection, configure the PingFederate IdP server. Each virtual server ID has its own set of protocol endpoints obtained in the connection metadata. For more information, see [Metadata export](#) on page 932 and [System-services endpoints](#) on page 1269.

After providing the protocol endpoints information to Office 365, when Office 365 sends login requests to PingFederate, PingFederate picks the correct IdP adapter to authenticate the end users based on the virtual server ID in the requests.

For each successful login, PingFederate builds an assertion with the issuer set to the corresponding virtual server ID. When Office 365 receives the assertion, it creates the end user session with the right subdomain settings based on the issuer value in the assertion.

#### Connecting to a partner in multiple connections

In this use case, you connect to your partner in multiple connections. In each connection, you identify yourself and your partner differently.

For example, you as the SP provide separate environments for the end users based on their regions. Your IdP operates in two regions, Europe (EU) and North America (NA). Their federation IDs are `eu.idp.local` and `na.idp.local` respectively.

In the PingFederate SP server, you can create two IdP connections to federate identities for end users from both regions as follows.

|                          | Partner's federation ID   | Your virtual server ID     |
|--------------------------|---------------------------|----------------------------|
| <b>IdP connection #1</b> | <code>eu.idp.local</code> | <code>idp-eu.sp.tld</code> |
| <b>IdP connection #2</b> | <code>na.idp.local</code> | <code>idp-na.sp.tld</code> |

Based on the issuer (the partner's federation ID) and the audience values (your virtual server ID), PingFederate determines at runtime which IdP connection the assertion is intended for, validates as per the connection settings, and passes attribute values to the SP adapter to create the end-user session.

## Working with multiple virtual server IDs

You can assign virtual server IDs either as an IdP during configuration of an SP connection or as an SP configuring an IdP connection for both Browser single sign-on (SSO) Profiles and WS-Trust security token service (STS) for access to identity-enabled web services. For more information, see [Identifying the SP](#) on page 449 and [Identifying the partner](#) on page 731.

If a connection has only one virtual server ID, it becomes the default virtual server ID for the connection. If the list contains several entries, you must specify one of them as the default virtual server ID for that connection. The connection uses the default virtual server ID when a request does not include virtual server ID information. For more information, see [IdP endpoints](#) on page 1250 for an IdP or [SP endpoints](#) on page 1256 for an SP.

In a connection with multiple virtual server IDs, you can restrict each adapter added to the connection to certain virtual server IDs to enhance the end-user experience. For more information, see [Restricting an authentication source to certain virtual server IDs](#) on page 462 and [Restricting a target session to certain virtual server IDs](#) on page 741.



### Tip:

Restrict each token processor or token generator added to a WS-Trust STS SP connection or IdP connection. For more information, see [Restricting a token processor to certain virtual server IDs](#) on page 1057 or [Restricting a token generator to certain virtual server IDs](#) on page 1072.



### Important:

To protect against unauthorized access, configure Issuance Criteria to verify virtual server ID in conjunction with other conditions, such as group membership information. For more information, see [Defining issuance criteria for IdP Browser SSO](#) on page 465 or [Defining issuance criteria for SP Browser SSO](#) on page 744.

## Configuration data exchange

If your partner's deployment does not produce or consume a metadata file that conforms to SAML metadata specifications, you might need to exchange connection information manually. If the deployment does not use metadata, some common configuration details must be exchanged.

### Identity provider (IdP) to service provider (SP)

If you are the IdP, your SP partner will need some or all of the following connection information, depending upon which profiles and bindings you configure:

- Unique ID—Identifies the IdP that issues an assertion or other SAML message. For SAML 2.0, the ID is the IdP entity ID; for SAML 1.x, it is the IdP issuer; for WS-Federation, it is the IdP realm.  
PingFederate also supports the optional use of virtual IDs. For more information, see [Federation planning checklist](#) on page 113.
- SOAP artifact resolution URL—The endpoint your site uses to receive an SP's SOAP requests when the artifact binding is used.
- Single logout (SLO) service URL—The destination of SLO request messages.
- Single sign-on (SSO) service URL—The endpoint where you receive and process assertions.

### SP to IdP

If you are the SP, your IdP partner will need some or all of the following connection information depending upon which profiles and bindings you configure:

- Unique ID—Identifies the SP. For SAML 2.0, the ID is the entity ID; for SAML 1.x, it is the SP's audience; for WS-Federation, it is the SP's realm.

PingFederate also supports the optional use of virtual IDs. For more information, see [Federation planning checklist](#) on page 113.

- SOAP artifact resolution service URL—The endpoint to use for SOAP requests when the artifact binding is used.
- Single logout service URL (SAML 2.0)—The destination of SLO request messages.
- Assertion consumer service URL—The location where the SP receives assertions.
- Target URLs—The URLs for the protected resources that a user is trying to access.

#### Mutual settings between parties

The parties must mutually determine the settings. These settings might include:

- Attributes—User information sent in an assertion. For more information, see [User attributes](#) on page 101.
- Signing certificates—SAML and WS-Federation protocols specify a number of conditions built into the PingFederate connection-setup windows that might or might not require digital signatures.
- SOAP connection type and authentication style—For SAML connections using the back channel, such as artifact binding, HTTP Basic authentication, SSL client certificate authentication, digital signatures, or some combination of the three is required. You and your partner must exchange the necessary credentials, certificates, and signing keys.

## Installing and uninstalling PingFederate

---

PingFederate operates as a standalone server based on Java EE application server technology. This section shows you how to properly install PingFederate.


A new installation involves:

- Determining the deployment architecture
- Reviewing [system](#) and [port](#) requirements
- [Installing a Java runtime environment](#)
- [Installing PingFederate](#)
- Completing the Initial Setup wizard

#### Deployment options


Depending on your needs and infrastructure capabilities, you can choose a standalone or proxy configuration. For information about configuring proxy settings, see [Configuring incoming proxy settings](#) on page 697 and [Configuring forward proxy server settings](#) on page 905.

The following diagram illustrates a standalone PingFederate deployment in a DMZ.



In this configuration, the users access PingFederate through a web application server, an enterprise identity management (EIM) system, or both. PingFederate then retrieves information from a datastore to use in processing the transaction.

You can also deploy PingFederate with a proxy server. The following diagram depicts a proxy-server configuration in which users and web browsers access the proxy. The proxy then communicates with PingFederate to request single sign-on (SSO).






## System requirements

PingFederate has the following recommended system versions and requirements.

Operating systems and virtualization

 **Note:**

PingFederate is tested with default configurations of operating-system components. If your organization customizes implementations or installs third-party plug-ins, deployment efforts might affect the PingFederate server.

| Component         | Supported versions  |
|-------------------|---|
| Operating systems | <ul style="list-style-type: none"> <li>▪ Amazon Linux 2 and 2022</li> <li>▪ Canonical Ubuntu 18.04 LTS and 20.04 LTS</li> <li>▪ Microsoft Windows Server 2012 R2, 2016, 2019, and 2022</li> <li>▪ Oracle Linux (Red Hat Compatible Kernel) 7.9 and 8.5</li> <li>▪ Red Hat Enterprise Linux ES 7.9 and 8.5</li> <li>▪ SUSE Linux Enterprise 12 SP5 and 15 SP3</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If you have a Windows Server 2012 R2 environment, you should upgrade to a later version. For more information, including the end of support for Windows Server 2012 R2 in July 2023, see <a href="#">Upgrade considerations introduced in PingFederate 10.x</a> on page 144.</p> </div>   |
| Docker support    | <ul style="list-style-type: none"> <li>▪ Docker version: 20.10.17</li> </ul> <p>View the PingFederate Docker image on <a href="#">DockerHub</a>. Visit Ping Identity's DevOps <a href="#">documentation</a> for more information. Note that only the PingFederate software is licensed under Ping Identity's end user license agreement, and any other software components contained within the image are licensed solely under the terms of the applicable open source or third-party license.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Ping Identity accepts no responsibility for the performance of any specific virtualization software and in no way guarantees the performance or interoperability of any virtualization software with its products.</p> </div> |
| Virtualization    | <p>Although Ping Identity does not qualify or recommend any specific virtual-machine (VM) or container products other than those already specified, PingFederate has run well on several, including Hyper-V, VMWare, and Xen.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The list of products is provided for example purposes only. We view all products in this category equally. Ping Identity accepts no responsibility for the performance of any specific virtualization software and in no way guarantees the performance, interoperability, or both of any VM or container software with its products.</p> </div>  |

#### Java environment

- Amazon Corretto 8, 11, and 17
- OpenJDK 11 and 17
- Oracle Java SE Development Kit 11 LTS and 17 LTS
- Oracle Java SE Runtime Environment (Server JRE) 8

 **Note:**



Ping Identity Java Support Policy applies. For more information, see Java Support Policy in the Ping Identity Knowledge Base.



**Important:**

PingFederate does not support any JDK 11 version prior to 11.0.4 due to an error covered in the [Oracle Java Bug Database](#).

### Browsers

| Server                | Supported browsers  |
|-----------------------|---|
| Runtime server        | <ul style="list-style-type: none"> <li>▪ Apple Safari</li> <li>▪ Google Chrome</li> <li>▪ Microsoft Edge</li> <li>▪ Mozilla Firefox</li> <li>▪ Apple iOS 15 (Safari)</li> <li>▪ Google Android 11 (Chrome)</li> </ul> |
| Administrative server | <ul style="list-style-type: none"> <li>▪ Google Chrome</li> <li>▪ Microsoft Edge</li> <li>▪ Mozilla Firefox</li> </ul>  |

### TLS protocol

Runtime server and administrative server

- TLS 1.2 and 1.3

### Datastore integration

| Functionality         | Supported versions  |
|-----------------------|---|
| User-attribute lookup | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Aurora MySQL 3.01.0 (compatible with MySQL 8.0.23)</li> <li>▪ Aurora PostgreSQL (compatible with PostgreSQL 13.6)</li> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Database 12c Release 2 and 19c</li> <li>▪ Oracle MySQL 8.0</li> <li>▪ Oracle Unified Directory 12c</li> <li>▪ PostgreSQL 11 and 13</li> <li>▪ Custom implementation through the PingFederate SDK</li> </ul> |

| Functionality   | Supported versions   |
|---|--|
| SaaS or SCIM outbound provisioning                      | Provisioning channel data source <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Oracle Unified Directory 12c</li> </ul> Provisioning internal datastore <ul style="list-style-type: none"> <li>▪ Aurora MySQL 3.01.0 (compatible with MySQL 8.0.23)</li> <li>▪ Aurora PostgreSQL (compatible with PostgreSQL 13.6)</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Database 12c Release 2 and 19c</li> <li>▪ Oracle MySQL 8.0</li> <li>▪ PostgreSQL 11 and 13</li> </ul>        |
| SCIM inbound provisioning                               | <ul style="list-style-type: none"> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Custom implementation through the PingFederate SDK</li> </ul>  |
| Just-in-time (JIT) inbound provisioning                 | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Unified Directory 12c</li> </ul>  |
| Account linking   | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Aurora MySQL 3.01.0 (compatible with MySQL 8.0.23)</li> <li>▪ Aurora PostgreSQL (compatible with PostgreSQL 13.6)</li> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Database 12c Release 2 and 19c</li> <li>▪ Oracle MySQL 8.0</li> <li>▪ Oracle Unified Directory 12c</li> <li>▪ PostgreSQL 11 and 13</li> </ul>  |
| OAuth client configuration and persistent grants        | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Aurora MySQL 3.01.0 (compatible with MySQL 8.0.23)</li> <li>▪ Aurora PostgreSQL (compatible with PostgreSQL 13.6)</li> <li>▪ Amazon DynamoDB (persistent grant only)</li> <li>▪ Microsoft Active Directory 2012 R2 and 2016</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Database 12c Release 2 and 19c</li> <li>▪ Oracle MySQL 8.0</li> <li>▪ Oracle Unified Directory 12c</li> <li>▪ PostgreSQL 11 and 13</li> <li>▪ Custom implementation through the PingFederate SDK</li> </ul> |
| Registration and profile management of local identities | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> </ul>  |

| Functionality                      | Supported versions   |
|------------------------------------|--|
| Persistent authentication sessions | <ul style="list-style-type: none"> <li>▪ PingDirectory 7.3, 8.2, 8.3, 9.0, 9.1</li> <li>▪ Aurora MySQL 3.01.0 (compatible with MySQL 8.0.23)</li> <li>▪ Aurora PostgreSQL (compatible with PostgreSQL 13.6)</li> <li>▪ Microsoft SQL Server 2016 SP2, 2017, and 2019</li> <li>▪ Oracle Database 12c Release 2 and 19c</li> <li>▪ Oracle MySQL 8.0</li> <li>▪ PostgreSQL 11 and 13</li> <li>▪ Custom implementation through the PingFederate SDK</li> </ul> |

**Note:**

If you have Microsoft Active Directory environments on the 2012 R2 functional level, you should upgrade to a later version. For more information, including the end of support for the 2012 R2 functional level in July 2023, see [Upgrade considerations introduced in PingFederate 10.x](#) on page 144.

**Note:**

was tested with vendor-specific JDBC drivers. For more information, see [Compatible database drivers](#) on page 124.

Secret manager (optional)

CyberArk Credential Provider 12

Hardware security modules (optional)

**Note:**

When integrating with AWS CloudHSM or Entrust nShield Connect hardware security modules (HSM), you must deploy with Oracle Server JRE (Java SE Runtime Environment) 8 or Amazon Corretto 8.

| Hardware security module                                  | Supported versions  |
|---|---|
| AWS CloudHSM  | <ul style="list-style-type: none"> <li>▪ Client software version: 3.4.4</li> </ul> <p>PingFederate must be deployed on one of the Linux operating systems supported by both AWS CloudHSM and PingFederate.</p>  |
| Entrust nShield Connect HSMs (in FIPS 140-2 Level 3 mode) | <ul style="list-style-type: none"> <li>▪ Host and Firmware version: 12.40.0</li> <li>▪ Client driver version: 12.40.2</li> <li>▪ Hardware Models: 6000+ and XC High</li> </ul>  |
| Thales Luna Cloud HSM Services and Luna Network HSM       | <ul style="list-style-type: none"> <li>▪ Luna HSM Client 10.5</li> </ul> <p>For more information about the Luna HSM Client, including compatible HSMs, HSM firmware, appliance software, and client software, see the <a href="#">Luna Cloud HSM Service Client Guide</a> and the <a href="#">Luna Network HSM Documentation Archive</a>.</p> |

### Minimum hardware requirements

- Multi-core Intel Xeon processor or higher
  - 4 CPU/Cores recommended
- 4 GB of RAM
  - 1.5 GB available to PingFederate
- 1 GB of available hard drive space



#### Note:

Although it's possible to run PingFederate on less powerful hardware, the guidelines provided accommodate disk space for default logging, auditing profiles, and CPU resources for a moderate level of concurrent request processing.

## Compatible database drivers

PingFederate is compatible with the following vendor-specific Java database connectivity (JDBC) drivers.

| Database server                  | Driver information   |
|----------------------------------|--|
| Amazon Aurora (MySQL 5.7) 2.10.0 | <p>Driver version information</p> <p><code>mysql-connector-java version 8.0.29</code></p> <p>Driver class</p> <p><code>com.mysql.cj.jdbc.Driver</code></p> <p>JDBC URL</p> <p><code>jdbc:mysql://databaseservername/databasename</code></p> <p>Database location</p> <p>Regional</p> <p>Database features</p> <p>One writer and multiple readers</p> |
| Amazon Aurora (PostgreSQL 13.6)  | <p>Driver version information</p> <p><code>postgresql version 42.3.6</code></p> <p>Driver class</p> <p><code>org.postgresql.Driver</code></p> <p>JDBC URL</p> <p><code>jdbc:postgresql://databaseservername/databasename</code></p> <p>Database features</p> <p>One writer and multiple readers</p>  |

| Database server                               | Driver information  |
|---|---|
| Microsoft SQL Server 2016 SP2, 2017, and 2019 | <p>Driver version information</p> <p>sqljdbc version 9.4.1</p> <p>Driver class</p> <p><code>com.microsoft.sqlserver.jdbc.SQLServerDriver</code></p> <p>JDBC URL</p> <p><code>jdbc:sqlserver://databaseservername;databaseName=databasename</code></p> |
| Oracle Database 12c Release 2 and 19c         | <p>Driver version information</p> <p>ojdbc8 version 21.5.0.0</p> <p>Driver class</p> <p><code>oracle.jdbc.OracleDriver</code></p> <p>JDBC URL</p> <p><code>jdbc:oracle:thin:@databaseservername:databasename</code></p>                               |
| Oracle MySQL 8.0                              | <p>Driver version information</p> <p>mysql-connector-java version 8.0.29</p> <p>Driver class</p> <p><code>com.mysql.cj.jdbc.Driver</code></p> <p>JDBC URL</p> <p><code>jdbc:mysql://databaseservername/databasename</code></p>                        |
| PostgreSQL 11 and 13                          | <p>Driver version information</p> <p>postgresql version 42.3.6</p> <p>Driver class</p> <p><code>org.postgresql.Driver</code></p> <p>JDBC URL</p> <p><code>jdbc:postgresql://databaseservername/databasename</code></p>                                |

For additional information about these drivers, contact the respective vendors.

## Port requirements

The following table summarizes the ports and protocols that PingFederate uses to communicate with external components. This information provides guidance for firewall administrators to ensure the correct ports are available across network segments.



**Note:**

Direction refers to the direction of the initial requests relative to PingFederate. Inbound refers to requests PingFederate receives from external components. Outbound refers to requests PingFederate sends to external components.

### PingFederate required ports and protocols

| Service                | Protocol, direction, transport, default port | Source  | Destination           | Description   |
|------------------------|--|---|-----------------------|---|
| Administrative console | HTTPS, inbound, TCP, 9999                    | Browsers accessing the administrative console, REST calls to the administrative API, web service calls to the Connection Management Service.<br><br>Applicable to the console node in a clustered PingFederate environment. | Administrative node   | Used for incoming requests to the administrative console. Configurable in the <code>run.properties</code> file. |
| Administrative console | HTTPS, outbound, TCP, 443                    | Administrator accessing online documentation.<br><br>Applicable to the console node in a clustered PingFederate environment.  | docs.pingidentity.com | Used for accessing online documentation from the administrative console.  |

| Service                             | Protocol, direction, transport, default port       | Source  | Destination                                  | Description  |
|-------------------------------------|--|---|--|--|
| Runtime engine                      | HTTPS, inbound, TCP, 9031 (and 9032 if configured) | Browsers accessing the runtime server for SSO or SLO; web service calls to the SSO Directory Service; REST calls to the OAuth Client Management Service, the OAuth Access Grant Management Service, the Persistent Grant Management API, and the Session Revocation API.<br><br>Applicable to all runtime engine nodes in a clustered PingFederate environment. | Runtime engine nodes                         | Used for incoming requests to the runtime engine.<br><br>Configurable in the <code>run.properties</code> file.   |
| Cluster traffic                     | JGroups, inbound, TCP, 7600                        | PingFederate peer servers in a clustered PingFederate environment.  | Administrative node and runtime engine nodes | Used for communications between engine nodes in a cluster when the transport mode for cluster traffic is set to TCP (the default behavior).<br><br>Configurable in the <code>run.properties</code> file.                               |
| Cluster traffic                     | JGroups, inbound, TCP, 7700                        | PingFederate peer servers in a clustered PingFederate environment.  | Administrative node and runtime engine nodes | Used by other nodes in the cluster as part of the cluster's failure-detection mechanism when the transport mode for cluster traffic is set to TCP (the default behavior).<br><br>Configurable in the <code>run.properties</code> file. |
| PingOne connections (if configured) | HTTPS, outbound, TCP, 443                          | All nodes   | pingone.com                                  | The administrative node uses PingOne APIs to create connections to PingOne. Engine nodes use PingOne APIs to obtain access tokens and call PingOne services.   |

| Service   | Protocol, direction, transport, default port | Source  | Destination  | Description  |
|---|--|---|--|--|
| PingOne for Enterprise integration (if configured)        | HTTPS and secure WebSocket, TCP, 443         | PingFederate<br>Applicable to the console node in a clustered PingFederate environment. | pingone.com  | Used for communications between PingFederate and PingOne for Enterprise for establishing and maintaining a managed SP connection to PingOne for Enterprise, monitoring of PingFederate from the PingOne admin portal, authenticating end users against the PingOne for Enterprise Directory. |
| Cluster traffic (if configured)                           | JGroups, outbound, TCP, 443                  | PingFederate peer servers in a clustered PingFederate environment.                      | Amazon Simple Storage Service (Amazon S3) or an OpenStack Swift server | Used by all nodes when the optional dynamic discovery mechanism is enabled.  |
| Cluster traffic   | JGroups, inbound, UDP, 7601                  | PingFederate peer servers in a clustered PingFederate environment.                      | Administrative node and runtime engine nodes                           | Used for communications between engine nodes in a cluster when the transport mode for cluster traffic is set to UDP. By default, the transport mode is TCP.<br><br>Configurable in the <code>run.properties</code> file.   |
| Active Directory domains/ Kerberos realms (if configured) | Kerberos, outbound, TCP or UDP, 88           | PingFederate  | Windows domain controllers   | Used for communications between PingFederate and Windows domain controllers for the purpose of Kerberos authentication.  |
| reCAPTCHA (if configured)                                 | HTTPS, outbound, TCP, 443                    | PingFederate  | www.google.com/recaptcha/api/site/verify                               | Used by the HTML Form Adapter when invisible reCAPTCHA from Google is enabled to prevent automated attacks.  |
| Administration notification                               | SMTP, outbound, TCP, 25 (465 if SMTPS)       | All nodes   | SMTP server  | Used to send notification messages for various events. For more information, see <a href="#">Runtime notifications</a> on page 935.  |

**Note:**

For PingID integration, see [PingID required domains, URLs, and ports](#).



Depending on the integration kits deployed and the connecting third-party systems, such as email server or SMS service provider, additional ports might be required.

## Installing Java

---

PingFederate requires a Java runtime environment to be installed on your server.

About this task

PingFederate has been tested in the following Java environments:

- Amazon Corretto 8, 11, and 17
- OpenJDK 11 and 17
- Oracle Java SE Development Kit 11 LTS and 17 LTS
- Oracle Java SE Runtime Environment (Server JRE) 8



### Note:

Ping Identity Java Support Policy applies. For more information, see Java Support Policy in the Ping Identity Knowledge Base.



### Important:

PingFederate does not support any JDK 11 version prior to 11.0.4 due to an error covered in the [Oracle Java Bug Database](#).



### Important:

Because of the import restrictions of some countries, Oracle Server Java SE Runtime Environment (JRE) 8 has built-in restrictions on available cryptographic strength (key size). To use larger key sizes, enable the Java Cryptography Extension (JCE) unlimited strength jurisdiction policy. For more information, see the Java 8 release notes in Oracle's documentation.

For Oracle Java SE Development Kit 11, the JCE jurisdiction policy defaults to unlimited strength. For more information, see the Oracle JDK Migration Guide in Oracle's documentation.

Steps

1. Download and install a Java runtime.
2. Set the `JAVA_HOME` environment variable to the Java installation directory path and add its `bin` directory to the `PATH` environment variable.



### Note:

If you intend to use the PingFederate installer for Windows or run PingFederate as a service, you must set the `JAVA_HOME` environment variable and modify the `PATH` environment variable at the system

level. If you are not using the PingFederate installer or running PingFederate as a service, you can set the variables at either the system or user level.



#### CAUTION:

When running for Windows, switching the Java version from 8 to 11 (or the reverse) prevents the service from running, and you won't be able to start . The problem occurs because garbage collection logging configuration arguments that are used by Java 8 are incompatible with those used by Java 11.

To change Java versions:

- a. Run `<pf_install>\pingfederate\sbin\win-x86-64\uninstall-service.bat` to de-register the service.
- b. Install the new Java version and update the `JAVA_HOME` and `PATH` environment variables.
- c. Run `<pf_install>\pingfederate\sbin\win-x86-64\install-service.bat` to register the service.

## Installing PingFederate 11.1

You can install PingFederate on Windows and Linux operating systems.

Install PingFederate using the following methods:

- Install PingFederate on a Windows system by running the installer for Windows or by extracting the distribution .zip archive. Using the installer for Windows is the preferred method.
- Install PingFederate on a Linux system by extracting the distribution .zip archive.



#### Note:

This documentation refers to the installation directory path where the `pingfederate` directory is located as `<pf_install>`. For example, `<pf_install>/pingfederate/bin`.



#### Important:

To avoid future problems with automated upgrades, do not rename the installed `pingfederate` directory.

If you are installing multiple instances of PingFederate on the same machine, such as a console node and an engine node in a clustered environment, install each instance using a unique `<pf_install>` directory.

If you are upgrading an existing PingFederate environment, see [Upgrading PingFederate](#).

Click the corresponding tabs for your preferred installation method.

## Installing PingFederate on Linux systems

Before you begin

- See [System requirements](#) for a list of qualified Linux operating systems.
- Request a license key through the Ping Identity licensing website.
- Ensure you are signed on to your system with sufficient privileges to install and run an application. You must install and run PingFederate under a local user account.
- Verify that you have installed the Java Runtime Environment (JRE) and that you have set the required environment variables correctly. For more information, see [Installing Java](#) on page 129.

### About this task

To install PingFederate on a Linux system using the distribution `.zip` archive:

### Steps

1. Download the latest version of the PingFederate Server distribution `.zip` archive from the [Downloads website](#).
2. Extract the archive into the target installation directory.
3. Start PingFederate manually by running `<pf_install>/pingfederate/bin/run.sh`.

**Tip:**

To configure PingFederate to run as a service on Linux, install PingFederate on Linux manually.

### Result:

The startup process is complete when you see the following message.

```
PingFederate running...
```

### Next steps

If your organization plans to manage keys and certificates using a hardware security module (HSM), see [Supported hardware security modules](#).

## Installing the PingFederate service on Linux manually

### Before you begin

- Request a license key through the Ping Identity licensing website.
- Ensure you are signed on to your system with sufficient privileges to install and run an application.
- Verify that you have installed the Java Runtime Environment (JRE) and that you have set the required environment variables correctly. For more information, see [Installing Java](#) on page 129 in the PingFederate Server documentation.

### About this task

If you have not installed PingFederate on Linux using the distribution `.zip` archive, you can install it manually. To install the PingFederate service on Linux manually:

### Steps

1. Download the distribution `.zip` archive from the Ping Identity [website](#).
2. Extract the file into an installation directory, `<pf_install>`.
3. Create a new local user account for the PingFederate service, such as `pingfederate`.

**Note:**

The service account is referred to as `<pf_user>`.

4. Change the ownership of the PingFederate installation directory `<pf_install>` and update the read-write permissions by running the following commands:

```
chown -R <pf_user> <pf_install>
chmod -R 775 <pf_install>
```

5. If the operating system supports systemd, install the PingFederate unit file:
  - a. Edit the `<pf_install>/pingfederate/sbin/linux/pingfederate.service` systemd unit file.

Replace the following variables with information from your environment:

`${PF_VERSION}`

The version of PingFederate.

`${PF_USER}`

The local user account for the PingFederate service.

`${PF_HOME}`

The `<pf_install>/pingfederate` directory.

For example, if `<pf_install>` is `/opt/identity.fed`, replace `${PF_HOME}` with `/opt/identity.fed/pingfederate`.

`${PF_JAVA_HOME}`

The `<JAVA_HOME>` environment variable value (a directory).

- b. Copy the `pingfederate.service` file to the systemd unit files directory, for example, `/etc/systemd/system`.

 **Note:**

Depending on the operating system, the exact location might vary. Consult your system administrators as needed. The rest of the step assumes `/etc/systemd/system` is the systemd unit files directory.

- c. Run the following command to update the read-write permissions of the `pingfederate.service` systemd unit file:

```
chmod 664 /etc/systemd/system/pingfederate.service
```

- d. Run the following commands to load the new system configuration changes and start the PingFederate service:

```
systemctl daemon-reload ;\
systemctl start pingfederate
```

- e. Run the following commands to configure the PingFederate service to start automatically as the server boots:

```
systemctl enable pingfederate ;\
systemctl daemon-reload ;\
systemctl restart pingfederate
```

**Result:**

After setting up the PingFederate systemd unit file, you can run the following `systemctl` command to manage the PingFederate service:

```
systemctl start pingfederate
systemctl stop pingfederate
systemctl restart pingfederate
systemctl status pingfederate
```

6. If the operating system supports SysV initialization, follow these steps to install the PingFederate script.

- a. Edit the `<pf_install>/pingfederate/sbin/linux/pingfederate` script.

Replace the following statements with information from your environment:

```
PF_HOME=$PF_HOME
```

Replace `$PF_HOME` with the `<pf_install>/pingfederate` directory.

For example, if `<pf_install>` is `/opt/identity.fed`, replace `$PF_HOME` with `/opt/identity.fed/pingfederate`.

```
USER="pingfederate"
```

If the PingFederate service account is not `pingfederate`, replace `<pingfederate>` with the local user account for the PingFederate service.

For example, if `<pf_user>` is `pingfed`, replace `<pingfederate>` with `pingfed`.

Example:

Example (truncated)

If `<pf_install>` and `<pf_user>` are `/opt/identity.fed` and `pingfederate` respectively, the required modifications are:

```
...
PF_HOME=/opt/identity.fed/pingfederate
DIR="$PF_HOME/sbin"
USER="pingfederate"
...
```

- b. Copy the `pingfederate` script to the SysV initialization directory, for example, `/etc/rc.d/init.d`.

The exact location might vary, depending on the operating system. Consult your system administrators, as needed. The rest of the step assumes `/etc/rc.d/init.d` is the SysV initialization directory.

- c. Run the following command to update the read-write permissions of the `pingfederate` SysV initialization script:

```
chmod 755 /etc/rc.d/init.d/pingfederate
```

- d. Configure the operating system to start the PingFederate service at various runlevels.

On an RHEL server, you can use the **Service Configuration** utility to do so.

Alternatively, the initialization directories associated with various runlevels can accept manual symbolic links of the `pingfederate` script by running the `ln -s <source> <target>` command.

Example:

You can create the following symbolic links on an RHEL server where runlevels 2 and 4 are not used:

```
ln -s /etc/rc.d/init.d/pingfederate /etc/rc3.d/S84pingfederate
ln -s /etc/rc.d/init.d/pingfederate /etc/rc5.d/S84pingfederate
ln -s /etc/rc.d/init.d/pingfederate /etc/rc0.d/K15pingfederate
ln -s /etc/rc.d/init.d/pingfederate /etc/rc1.d/K15pingfederate
```

```
ln -s /etc/rc.d/init.d/pingfederate /etc/rc6.d/K15pingfederate
```

 **Note:**

Some operating systems might require a restart of the system to activate the new scripts. Consult your system administrators as needed.

### Next steps

After setting up the PingFederate SysV initialization script, you can use the **Service Configuration** utility or run the following **service** commands to manage the PingFederate service:

```
service pingfederate start
service pingfederate stop
service pingfederate restart
service pingfederate status
```

## Installing PingFederate on Windows

### Before you begin

- Request a license key through the Ping Identity licensing page.
- Ensure you are signed on to your system with sufficient privileges to install and run an application.
- Verify that you have installed the Java Runtime Environment (JRE) and that you have set the required environment variables correctly. For more information, see [Installing Java](#) on page 129.

### About this task

You can install PingFederate on a Windows system using the installer for Windows or the distribution .zip archive. Using the installer for Windows is the preferred method.

 **Tip:**

To configure PingFederate to run as a service on Windows, install PingFederate on Windows manually. For more information, see [Installing the PingFederate service on Windows manually](#) on page 135.

To install PingFederate:

## Steps

1. Install PingFederate using the installer for Windows or the distribution .zip archive:

Choose from:

- To install using the PingFederate installer for Windows:
  - a. Download the PingFederate installer for Windows from the Ping Identity [website](#).
  - b. Double-click the .msi file to open the PingFederate Setup Wizard, and follow the instructions to complete the installation.

PingFederate is configured to run as a service and starts automatically at the end of the installation process.



### Note:

The PingFederate installer for Windows installs only one instance of PingFederate on a Windows server. If you need additional PingFederate instances on the same Windows server, install them using the distribution .zip archive.

You must manually configure various port settings in the `<pf_install>/pingfederate/bin/run.properties` file for each instance to avoid port conflicts.

- To install PingFederate using the distribution .zip archive:
    - a. Download the distribution .zip archive from the Ping Identity [website](#). The distribution .zip archive is identical for both Windows and Linux.
    - b. Extract the file into an installation directory.
2. If you have installed PingFederate by extracting the distribution .zip archive, start PingFederate manually by running `<pf_install>/pingfederate/bin/run.bat`.

Wait for the script to finish. The startup process completes when you see the following message.

```
PingFederate running...
```



### CAUTION:

When running for Windows, switching the Java version from 8 to 11 (or the reverse) prevents the service from running, and you won't be able to start . The problem occurs because garbage collection logging configuration arguments that are used by Java 8 are incompatible with those used by Java 11.

To change Java versions:

- a. Run `<pf_install>\pingfederate\sbin\win-x86-64\uninstall-service.bat` to de-register the service.
- b. Install the new Java version and update the `JAVA_HOME` and `PATH` environment variables.
- c. Run `<pf_install>\pingfederate\sbin\win-x86-64\install-service.bat` to register the service.

## Next steps

If your organization plans to manage keys and certificates using a hardware security module (HSM), see [Supported hardware security modules](#).

## Installing the PingFederate service on Windows manually

### Before you begin

- Request a license key through the Ping Identity licensing website.

- Ensure you are signed on to your system with sufficient privileges to install and run an application.
- Verify that you have installed the Java Runtime Environment (JRE) and that you have set the required environment variables correctly. See [Installing Java](#) on page 129.

About this task



**Note:**

If you have installed PingFederate using the installer for Windows, skip these steps because PingFederate has already been configured to run as a service and to start automatically at the end of the installation process.

To install the PingFederate service manually:

Steps

1. Download the distribution .zip archive from the Ping Identity [website](#).  
The distribution .zip archive is identical for both Windows and Linux.
2. Extract the archive into an installation directory, `<pf_install>`.
3. Start PowerShell or Command Prompt as an administrator.
4. Run the `<pf_install>\pingfederate\sbin\win-x86-64\install-service.bat` file.
5. Go to **Control Panel # Administrative Tools # Services** to open the management console.
6. Right-click the **PingFederate** service and select **Start**.

Result

The PingFederate service starts automatically on reboot.

## Uninstalling PingFederate

---

Learn how to uninstall PingFederate from a Windows or Linux server.

Uninstalling PingFederate involves removing the previously-installed PingFederate service and the installation directory, `<pf_install>`.

Click the corresponding tabs for instructions on uninstalling from Windows or from Linux.

### Uninstalling PingFederate from a Windows server

Before you begin

- Ensure you are signed on to your system with sufficient privileges to uninstall an application.
- Optionally, make a backup copy of the PingFederate installation directory `<pf_install>`.

About this task

The method you use to uninstall PingFederate depends on whether you installed it using the installer for Windows or the distribution .zip file.



## Steps

1. Verify the installation medium in **Control Panel # Uninstall a Program**.



### Note:

The existence of a PingFederate entry indicates a previous installation of PingFederate using the Windows installer. If there is no existing PingFederate entry, the distribution .zip file was used to perform the installation.

2. Depending on the type of installation, uninstall PingFederate using one of the following methods: Choose from:
  - To uninstall PingFederate using the PingFederate installer for Windows, go to **Control Panel # Uninstall a Program**.  
Doing this removes the PingFederate service and the installation directory.
  - To uninstall PingFederate using the distribution .zip file:
    - a. Go to **Control Panel # Administrative Tools # Services** to open the management console.
    - b. Right-click the **PingFederate** service and select **Stop**.
    - c. Run `uninstall-service.bat` from the `<pf_install>\pingfederate\sbin` subdirectory that corresponds to your platform processor.
    - d. Optionally, remove the PingFederate installation directory `<pf_install>`.

## Uninstalling PingFederate from a Linux server

### Before you begin

- Ensure you are signed on to your system with sufficient privileges to uninstall an application.

### About this task

You can use the systemd service or the SysV initialization script to uninstall PingFederate from a Linux server.

## Steps

1. Uninstall PingFederate using one of the following methods: Choose from:
  - To uninstall PingFederate using the systemd service, use the following `systemctl` commands to stop and disable PingFederate:

```
systemctl stop pingfederate ;\
systemctl disable pingfederate ;\
```

```
systemctl daemon-reload
```

You can also remove the PingFederate systemd unit file `pingfederate.service` from the systemd unit files directory `/etc/systemd/system` before running the `systemctl daemon-reload` command.

- To uninstall PingFederate using the SysV initialization script:

Do one of the following:

- Use the **Service Configuration utility** to stop and disable the PingFederate service.
- Remove any symbolic links from various initialization directories to stop the PingFederate service.
- Remove the PingFederate SysV initialization script `pingfederate` from the SysV initialization directory `/etc/rc.d/init.d`.



**Note:**

Depending on the operating system, the exact directory locations might vary. Consult your system administrators as needed.

2. Optional: Remove the PingFederate installation directory, `<pf_install>`.

## Upgrading PingFederate

Use this section to learn how to upgrade your PingFederate environment to the latest version on Windows and Linux systems.

Depending on your PingFederate installation, you can upgrade by using the PingFederate installer for Windows or the Upgrade Utility, which automatically migrates existing PingFederate installations of 6.0 and later to the latest version. The Upgrade Utility is included with the software distribution.

For general information about upgrading Ping Identity products and an upgrade planning guide, see [Planning your upgrade](#).



**Important:**

Before upgrading your production environment, you should:

- Upgrade your test environment and verify that the new installation meets your expectations.
- Thoroughly retest the behavior of any customized components.

After you complete the upgrade process, you can create a backup of your previous installation and remove it from the server.

End users might experience service disruptions as you upgrade your PingFederate environment. As needed, schedule a maintenance window to perform the upgrade.

### Upgrade paths

| Operating system  | Source version   | Source installation medium         | Possible upgrade paths   |
|-------------------|------------------|------------------------------------|--|
| Microsoft Windows | 8.x through 11.x | PingFederate installer for Windows | PingFederate installer for Windows or PingFederate Upgrade Utility |

| Operating system | Source version   | Source installation medium                     | Possible upgrade paths       |
|------------------|------------------|--|------------------------------|
|                  | 6.x through 11.x | PingFederate product distribution .zip archive | PingFederate Upgrade Utility |
| Linux            | 6.x through 11.x | PingFederate product distribution .zip archive | PingFederate Upgrade Utility |

If you are upgrading from PingFederate 5.3 or earlier, contact [Support](#) for more information.

Both the PingFederate installer for Windows and the Upgrade Utility create a new installation based on the new product distribution .zip archive and then copy the relevant files and property values from the existing installation (the source) to the new installation (the target). As a result, neither tool affects the source installation.

#### Integration kits

Both upgrade tools also copy the program files for the deployed adapters, connectors, and token translators (the integration kits in general) from the source installation to the target installation. Although the tools don't upgrade the integration kits automatically, you can download newer versions from the Ping Identity Downloads website and upgrade the integration kits manually. For integration kit documentation, see the Ping Identity [website](#).

## Downloading PingFederate

You can download the latest version of PingFederate from the [PingFederate Downloads](#) website.

#### Steps

- Download PingFederate:  
Choose from:
  - The distribution .zip archive can be used to upgrade PingFederate on both Windows and Linux.
  - To download the PingFederate product distribution .zip archive, click **Product Distribution (ZIP)**.

#### Note:

The distribution .zip archive can be used to upgrade PingFederate on both Windows and Linux.

## Preparing to upgrade PingFederate

Prepare to upgrade PingFederate by completing a number of tasks.

#### Steps

- Review the PingFederate release notes for enhancements, upgrade considerations, deprecated features, and other known issues and limitations.
- Review the post-upgrade tasks.
- Review potential changes in system and port requirements.
- Obtain a new license key if needed.

- Update the Java runtime environment (JRE) to version 8 or 11 on your PingFederate servers if needed.

When you upgrade the JRE, modify the previously defined paths for the system `<JAVA_HOME>` and `<PATH>` environment variables.



#### Important:

PingFederate 7.2 and earlier will not start using the currently supported Java runtime. If you need to start the previous PingFederate version on the same server after the upgrade, retain the older Java installation and change environment variables back when needed.

- Complete any unfinished connections (Drafts) in the administrative console if you want to include them in the migration.

## Upgrade considerations

---

The following modifications since PingFederate 11.0 might affect existing deployments.

### Expired passwords and prompts to change passwords

When using PingDirectory 8.2 or later as the credential store, if a user's password has expired, the following settings ensure PingFederate doesn't direct the user to the Change Password form when they enter an invalid password:

- Set the **return-password-expiration-controls** setting in the PingDirectory password policy to **always**.
- Starting with PingFederate 11.1, when configuring an LDAP Username Password Credential Validator, select the **Expect Password Expired Control** checkbox in the advanced fields section of the **Instance Configuration** tab of the **Create Credential Validator Instance** window.

### Device authorization flows using the authentication API

Starting with PingFederate 11.1, the user code verification steps of the device authorization flow are API-enabled. Existing API applications will need to be updated to support the new API states. To disable the use of the API for the new states, set `enable-authn-api-for-user-code-validation` to `false` in `<pf_install>/pingfederate/server/default/config-store/oauth-device-flow.xml`. This will cause PingFederate to continue to render these states itself using the Velocity templates.

### Java 17

Starting with PingFederate 11.1, when using Java 17, the following JDKs are supported:

- Adoptium OpenJDK
- Oracle JDK
- Amazon Correto

If you upgrade to Java version 17 after you upgrade PingFederate:

- Remove `-XX:-UseParallelOldGC` from the `jvm-memory.options` file.
- Reinstall the Windows Service.

### Certificate revocation checking

Starting with PingFederate 11.1, when configured for certificate revocation list (CRL) or online certificate status protocol (OCSP) revocation checking, PingFederate now performs these checks in a broader range of flows. In particular, outbound TLS calls to retrieve JSON web key sets (JWKS) now perform revocation checks. Also, outbound TLS calls performed by plugins, such as adapters,

now perform revocation checks. To revert to the previous behavior where PingFederate doesn't perform these new checks, set `pf.tls.installRevocationCheckerGlobally` to `false` in the `run.properties` file.

 **Note:**

CRL-based revocation checks can consume large amounts of memory. If CRL checking is enabled, you should set PingFederate's maximum heap in the `jvm-memory.options` file to at least 4 GB. Alternatively, consider switching to OCSP revocation checking, which demands fewer resources.

When configured for CRL or OCSP revocation checking, PingFederate's validation of CRLs and OCSP responses is tighter than before. The following settings in the `revocation-checking-config.xml` file control the new validation checks:

- `crl-issuer-allow-any-trust-anchor`
- `crl-verify-issuing-distribution-point`
- `OCSP-enforce-responder-key-usage-check`

Although you should leave the new validation checks enabled, you can disable them for compatibility with existing deployments.

#### Custom `MasterKeyEncryptor` implementations

Starting with PingFederate 11.1, due to the revocation checking enhancements outlined above, a circular initialization dependency can arise if revocation checking is enabled and a custom `MasterKeyEncryptor` implementation makes API calls to an external service. To avoid this risk, you should disable revocation checking for any API calls made by the master key encryptor. Refer to the SDK documentation for more information on how to disable revocation checking in custom `MasterKeyEncryptor` implementations.

#### `run.sh` and `run.bat` files

In PingFederate 11.1, the `run.sh` and `run.bat` files were updated.

- A `startup` directory was added under the PingFederate installation. Its contents are now added to the classpath using a wildcard.
- References to `jetty-start.jar` were updated in `run.sh` and `run.bat` because `jetty-start.jar` was moved from the `bin` directory to the `startup` directory.
- References to `run.jar` were removed from `run.sh` and `run.bat` because `run.jar` was removed from the `bin` directory.

If your `run.sh` or `run.bat` files were customized, you must update your copy of these files accordingly.

#### Template `username.recovery.template.html`

Starting with PingFederate 11.1, the `username.recovery.template.html` template no longer includes the `$forgotPasswordUrl` variable.

 **Tip:**

The top of the template file documents which variables you can use.

#### Dynamic discovery settings

In versions preceding PingFederate 11.0, administrators could only define dynamic discovery settings to discover cluster membership in the `server/default/conf/tcp.xml` file. Now PingFederate provides a new configuration file for these settings, `bin/jgroups.properties`. This new approach streamlines future upgrade experiences. For new installations, we recommend defining dynamic discovery settings in the `jgroups.properties` file. While upgraded

environments will continue to look for dynamic discovery settings from the `tcp.xml` file, we recommend performing a one-time migration to ease the upgrade experiences in the future. For more information, see [Migrating cluster discovery settings](#) on page 219.

#### Velocity HTML templates

Starting with PingFederate 11.0, if any of the default Velocity HTML templates for user-facing windows were modified, the Upgrade Utility migrates them to the new installation and renames the corresponding default templates in the new installation with the following format: `<template_name>-default-<PF-version>.<ext>`. For more information, see [User-facing windows](#) on page 159.

#### Kerberos authentication

Starting with PingFederate 11.0, when the new **Retain Previous Keys on Password Change** check box on the **Manage Domain/Realm** window is selected, PingFederate saves the encryption keys associated with the password of the current Kerberos service account. The check box is selected by default.

#### Note:

PingFederate will not save the encryption keys until you re-save the configuration of the domain or realm. To facilitate seamless rotation of the service account password for existing domains, click **Save** on the **Manage Domain/Realm** window before you update the password in the domain controller. For more information, see [Adding Active Directory domains and Kerberos realms](#) on page 994.

#### IWA IdP adapter

PingFederate 11.0 and later no longer support the integrated Windows authentication (IWA) IdP adapter. The IWA integration kit for Kerberos has been replaced with a PingFederate adapter for Kerberos. See [Migrating from the Integrated Windows Authentication Integration Kit to the PingFederate Kerberos adapter](#).

#### Private key JSON web token authentication

When authenticating an OAuth client that uses the private key JSON web token (JWT) authentication scheme, PingFederate now validates that the issuer and subject claims in the JWT have the same value.

The following administrative API endpoint exposes the validation on/off switch:

```
https://{{pf_base_host_port}}/pf-admin-api/v1/configStore/oauth-credentials-validator/issuerMustBeEqualToClientId
```

To disable validation, send an HTTP POST request with the following body to the endpoint:

```
{
  "id": "issuerMustBeEqualToClientId",
  "stringValue": "false",
  "type": "STRING"
}
```

#### Authentication API applications

Starting with PingFederate 11.0, the new **Restrict Access to Redirectless Mode** check box on the **Authentication API Applications** window lets you restrict which authentication API applications can use redirectless mode. To avoid impacting existing deployments, this check box is not selected on upgrade. However, you should enable this setting. For more information, see [Managing authentication applications](#) on page 431.

## Jetty agent

Starting with PingFederate 11.0, if your PingFederate server is running on a Java version prior to 8u252, you must modify your `run.sh`, `run.bat`, or `PingFederateService.conf` script to include the new Jetty agent in PingFederate.

Add the following Java argument to the script:

```
-javaagent:/server/default/lib/jetty-alpn-agent.jar
```

Example for `run.sh`:

```
"$JAVA" $JAVA_OPTS \  
$ERROR_FILE \  
$HEAP_DUMP \  
${GC_FILE:+$GC_FLAG"$GC_FILE"$GC_OPTIONS} \  
$ENDORSED_DIRS_FLAG \  
-javaagent:$PF_HOME/server/default/lib/jetty-alpn-agent.jar \  
-Dlog4j2.AsyncQueueFullPolicy=Discard \  

```

Example for `run.bat`:

```
"%JAVA%" %PF_JAVA_OPTS% %JAVA_OPTS% %GC_OPTION% -javaagent:  
%PF_HOME%/server/default/lib/jetty-alpn-agent.jar -  
Dlog4j2.AsyncQueueFullPolicy=Discard
```

Example for `PingFederateService.conf` (note the extra `../` because this is located in `pingfederate/sbin/wrapper`):

```
# Java Additional Parameters  
wrapper.java.additional.1=-Dlog4j.configurationFile=../../server/  
default/conf/log4j2.xml  
  
..... (omitted lines 2-13 to save space) .....  
  
wrapper.java.additional.14=-javaagent:../../server/default/lib/jetty-  
alpn-agent.jar
```

## Specifying a maximum size for inbound runtime requests

Starting with PingFederate 11.0, if you have previously specified a value for `maxFormContextSize` in `jetty-runtime.xml`, you should now use `pf.runtime.http.maxRequestSize` in the `run.properties` file to control the maximum size for inbound runtime requests. For more information, see [Configuring PingFederate properties](#) on page 820.

## Java 8

As we continue to improve our products and hardware security module (HSM) integrations, you should migrate off of Java 8. We intend to remove Java 8 support from our qualification process in May 2023. For more information, including Java 11 support, see [System requirements](#) on page 119.

## Third-party integrations

As we continue to improve PingFederate, we intend to remove the following product releases from our qualification process after the release of PingFederate 11.3 in June 2023:

- Oracle Linux 7.9 (Red Hat-compatible Kernel)
- Red Hat Enterprise Linux 7.9
- Microsoft SQL Server 2016 SP2

- Oracle Database 12c Release 2
- Microsoft Windows Server 2012 R2
- Microsoft Active Directory 2012 R2

We encourage you to upgrade these products to more recent versions, such as:

- Oracle Linux 8.5 (Red Hat-compatible Kernel)
- Red Hat Enterprise Linux 8.5
- Microsoft SQL Server 2017
- Oracle Database 19c
- Microsoft Windows Server 2016
- Microsoft Active Directory 2016

For a more complete list of qualified third-party solutions, see [System requirements](#) on page 119.

## Upgrade considerations introduced in PingFederate 10.x

Several specific modifications since PingFederate 10.0 might affect existing deployments.

### Delayed heartbeat response due to archive import on startup

Starting with version 10.2, when you place an archive in the `<pf_install>/pingfederate/server/default/data/drop-in-deployer` directory on startup, the heartbeat endpoint will not return 200 until archive import completes. Depending on how long archive import and configuration loading takes, the first successful heartbeat response may be significantly delayed relative to earlier versions. If you have configured a health check or probe that can trigger a restart of the server, crash loop behavior can result. Review the configuration of these checks to ensure time thresholds are set appropriately.

### TLS 1.0 and 1.1 disabled

Starting with version 10.3, PingFederate disables TLS 1.0 and 1.1 for both inbound and outbound connections by default. As a result, clients using TLS 1.0 or 1.1 will no longer be able to connect to the administrative port or the runtime port. If you must re-enable TLS 1.0 or 1.1, add `TLSv1` or `TLSv1.1` to the `run.properties` file: look for the “TLS Protocol Settings” section and follow the inline instructions. Additionally, you might need to add back the weaker cipher suites, such as `TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA`, `TLS_ECDH_RSA_WITH_AES_128_CBC_SHA`, or `TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA`. For more information, see [Managing cipher suites](#) on page 892.

### Bouncy Castle FIPS mode

When upgrading an installation where Bouncy Castle FIPS mode is enabled, it is no longer necessary to place the `bc-fips` jar file in the `JAVA_HOME/jre/lib/ext` directory. It is also no longer necessary to modify the `JAVA_HOME/jre/lib/security/java.security` file. It is recommended to revert these changes to the Java environment.

### SameSite cookie configuration

As of PingFederate 10.3, the Jetty configuration uses the native servlet SameSite cookie configuration. This moves the SameSite specifier declaration to its own attribute in the Jetty configuration as follows:

- New format for `jetty-admin.xml` in the `DeploymentManager`:

```
<Call name="setContextAttribute">
  <Arg>org.eclipse.jetty.cookie.sameSiteDefault</Arg>
  <Arg>None</Arg>
</Call>
```



- New format for `jetty-runtime.xml` in the `WebAppContext`:

```
<Call name="setAttribute">
  <Arg>org.eclipse.jetty.cookie.sameSiteDefault</Arg>
  <Arg>None</Arg>
</Call>
```

- If you want to specify a default value for session management cookies, such as `JSESSIONID`, in servlets hosted in PingFederate, add a `<comment>` like the one in the following snippet to the existing `session-config` in the `web.xml` file:

```
<session-config>
  <session-timeout>30</session-timeout>
  <cookie-config>
    <http-only>true</http-only>
    <!--
      The following comment adds a default SameSite value
      to the JSESSIONID cookie in any servlet context.
      Available options are:
          __SAME_SITE_NONE__
          __SAME_SITE_LAX__
          __SAME_SITE_STRICT__
    -->
    <comment>__SAME_SITE_NONE__</comment>
  </cookie-config>
</session-config>
```

### Microsoft Internet Explorer 11

Ping Identity commits to deliver the best experience for administrators and users. As we continue to improve our products, we encourage our customers to migrate off of Microsoft Internet Explorer 11. We intend to remove Internet Explorer 11 from our qualification process in December 2021.

### Microsoft Windows Server 2012 R2 and Active Directory 2012

Because Microsoft will end extended support for Windows Server 2012 R2 in late 2023 (see [here](#)), you should upgrade your Windows servers and Active Directory to a later version, such as Windows Server 2019. For a full list, see [System requirements](#) on page 119. We intend to remove Windows Server 2012 R2 and Active Directory 2012 from our qualification process in July 2023.

### Authorization endpoint

Before version 10.2, PingFederate did not validate the `NumericDate` value of `exp` claims in a signed request object's JWT. To ensure the JWT does not expire too far in the future, PingFederate 10.2 and later do validate the value. PingFederate rejects any JWT that expires more than 720 minutes later. You can change that default value in `<pf_install>/pingfederate/server/default/data/config-store/jwt-request-object-options.xml`.



#### Note:

PingFederate interprets the `NumericDate` value as seconds, not milliseconds. So PingFederate 10.2 will reject a JWT that has the `NumericDate` value based on milliseconds, because PingFederate calculates the JWT to live more than 720 minutes.

### Configuration change necessary for MFA adapters

As of PingFederate 10.2, when you define policies using multi-factor authentication (MFA) adapters, you must select the **User ID Authenticated** check box in the **Incoming User ID** popup to allow users to register as a new MFA user. You should only select this check box if the previous authentication source has verified the **Incoming User ID**. You should not select the check box if the MFA adapter is part of a policy used for password reset or password change. For more information, see [Defining authentication policies](#) on page 254.

**Important:**

Administrators using the PingID adapter must review existing policies and select this check box if appropriate. Otherwise, the adapter will prevent new user registration.

**Expression Admin role**

When upgrading to PingFederate 10.1 or later from an earlier version, administrative users who were granted the Admin role in the earlier installation are granted the Expression Admin role automatically. You can achieve the same result by using the `/bulk/import` administrative API endpoint to bulk-import a configuration that was bulk-exported from PingFederate 10.0.

Additionally, all four administrative roles, namely User Admin, Admin, Expression Admin, and Crypto Admin, are required to access and make changes through the following services:

- The `/bulk`, `/configArchive`, and `/configStore` administrative API endpoints
- The **System # Server # Configuration Archive** window in the administrative console
- The **Connection Management** configuration item on the **Security # System Integration # Service Authentication** window

**Authentication session created after user registration**

As of PingFederate 10.1, an authentication session is automatically created for a user after registration, preventing the user from having to log in again during the next SSO transaction. This feature is enabled by default for all new and existing local identity profiles. However, if needed, you can disable it through the `/localIdentity/identityProfiles` administrative API endpoint by setting the `createAuthnSessionAfterRegistration` attribute to `false`.

**Template `html.form.login.template.html`**

Starting with PingFederate 10.0, the `html.form.login.template.html` template no longer includes the `$forgotPasswordUrl` variable.

**Upgrade considerations introduced in PingFederate 9.x****Gemalto SafeNet Luna HSM 6.3**

When integrating with Gemalto SafeNet Luna Network HSM 6 (hardware security module), PingFederate 9.2 requires firmware version of 6.3.0 and client driver version of 6.3. See [Integrating with Thales Luna Network HSM](#) on page 181 for setup information.

**Weaker cipher suites disabled**

Starting with PingFederate 9.1, weaker cipher suites `TLS_RSA_WITH_AES_128_CBC_SHA` and `TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA` are disabled in new installations and upgrades. As a result, the administrative and runtime servers support only TLS 1.2. If you must re-enable these cipher suites for legacy clients, refer to [Managing cipher suites](#) on page 892 for more information.

**LDAP service accounts on PingDirectory**

If PingFederate 9.3.1 or newer has an LDAP connection with PingDirectory, then add the config-read privilege to its service account in PingDirectory. Otherwise, users will not receive password expiry notifications. For more information, see [Assigning Privileges to Normal Users and Individual Root Users](#) in the PingDirectory documentation.

**Improved validation for `AudienceRestriction`**

If an IdP connection is configured with multiple virtual server IDs, the `AudienceRestriction` value in a SAML response must now match the virtual server ID information embedded in the protocol endpoint at which PingFederate receives the message. Otherwise the SSO attempt fails. To override this validation on a per-connection basis, see [Configuring validation for the `AudienceRestriction` element](#) on page 906.

### Custom authentication selector

If you have created a custom authentication selector that returns an IdP adapter instance ID or the connection ID of an IdP connection, you must update the associated descriptor instance. See [Updating the custom authentication selector](#) on page 164 for more information.

### Provisioning datastore reset

Upgrading to PingFederate 9.0 or 9.0.1 when using its outbound provisioning capability can result in user records being disabled at SaaS applications. The issue is resolved in version 9.0.2.

If you are upgrading from version 8.4.4 (or earlier) or from version 9.0.2, 9.0.3, and 9.0.4 to version 10.0, the upgrade process automatically resolves this issue. No further action is required.

If you are upgrading from version 9.0 or 9.0.1 to PingFederate 10.0, you must use the `provmgr` command-line tool to reset the provisioning datastore on the upgraded installation. See [Reviewing database changes](#) on page 162 for more information.

### Security enhancement in JDBC datastore queries

A security enhancement was made in PingFederate 9.0 to safeguard JDBC datastore queries against back-end SQL injection attacks. This protection is enabled for all new installations. For upgrades, see [Reviewing database changes](#) on page 162.

### Access token validation response

Starting with PingFederate 9.2, the access token validation response no longer includes the username and subject elements by default. Responses include them only if they were mapped in the issuing access token management instance.

## Upgrade considerations introduced in PingFederate 8.x

### `InterReqStateMgmtMapImpl.expiry.mins` renamed

The `InterReqStateMgmtMapImpl.expiry.mins` setting in the `size-limits.conf` file has been renamed in PingFederate 8.4.2. If you have previously modified the value of this setting, please refer to [Copying customized files or settings](#) on page 159 for more information.

### An improved index (`IDX_FIELD_NAME`) in the database table for OAuth clients

PingFederate 8.4 has modified an existing index (`IDX_FIELD_NAME`) in the `pingfederate_oauth_clients_ext` database table as a general improvement. For information about modifying this index in your existing table, see [Reviewing database changes](#) on page 162.

### Security enhancement to the OAuth token endpoint

Starting with version 8.3, a new PingFederate installation no longer allows OAuth clients to send access token validation requests to its token endpoint (`/as/token.oauth2`) by the HTTP GET method.

For upgrades, the Upgrade Utility applies this new behavior to the new installation as well unless the `<pf_install>/pingfederate/server/default/data/config-store/oauth-token-endpoint-binding.xml` file has been modified in the older version, in which case the Upgrade Utility preserves the modified configuration.

### SSLv2Hello disabled

Starting with PingFederate 8.3, SSLv2Hello is disabled. Customers are encouraged to update their applications to use TLSv1, TLSv1.1, or TLSv1.2 when establishing HTTPS connections with PingFederate.

As needed, SSLv2Hello can be re-enabled as needed. See [Enabling SSLv2Hello](#) for more information.

### License management simplification

Starting with version 8.2, PingFederate no longer maintains its license information in the `<pf_install>/pingfederate/server/default/data/.pingfederate.lic` file, which is known as the secondary license file in the previous versions of PingFederate. The `.pingfederate.lic`, if any, is ignored.

We recommend using the administrative console to simplify the license management aspect of a standalone PingFederate server or a clustered PingFederate environment.

#### Security enhancement for a clustered PingFederate environment

As of PingFederate 8.1, when encryption is enabled for the network traffic sent between nodes in a clustered PingFederate environment, you must provide an authentication password for the cluster as well; otherwise PingFederate aborts during its startup process.

For more information about the `pf.cluster.encrypt` and `pf.cluster.auth.pwd` properties, see [Deploying cluster servers](#) on page 208.

#### Metadata signing

Previously, when no signing certificate was chosen on the **Metadata Signing** tab on the **System # Protocol Metadata # Metadata Settings** window, the `/pf/sts_mex.ping` and `/pf/federation_metadata.ping` system-services endpoints provided signed WS-Trust and WS-Federation metadata using one of the certificates configured on the **Security # Certificate & Key Management # Signing & Decryption Keys & Certificates** window.

Starting with PingFederate 8.1, if no certificate is selected in the **Metadata Signing** menu, PingFederate provides unsigned metadata at both aforementioned endpoints. Select a certificate in the **Metadata Signing** window if signed metadata is desired.

#### Hostname verification for email server

For email notification using SSL or TLS, hostname verification of the certificate is available starting with PingFederate 8.1. This option is enabled automatically when the **Use SSL** or **Use TLS** check box is selected for a new configuration. When upgrading from a previous version of PingFederate, if email notification had already been configured to use SSL or TLS, the Upgrade Utility preserves the configuration without activating the hostname verification option for compatibility reasons. Administrators should consider activating this new option to improve security.

#### New login template file for the HTML Form Adapter

Previously, when multiple instances of the HTML Form Adapter are chained together (for example, in an instance of the Composite Adapter), the subsequent instance tried authenticating the end user with the credentials from the previous login, which might fail when the HTML Form Adapter instances were configured to use different password credential validators (PCVs). Although this use case is rare, PingFederate 8.1 has corrected the behavior. As a result, the login template file, `<pf_install>/pingfederate/server/default/conf/template/html.form.login.template.html`, has been modified.

If you have previously customized this login template file and if you have authentication use cases that chain multiple instances of the HTML Form Adapter, you should re-customize using the new `html.form.login.template.html` file.

#### New connection pool library

As of PingFederate 8.0, support for BoneCP as the JDBC connection pool library has been deprecated and replaced with Apache Commons DBCP 2, which requires JDBC 4.1 or later drivers.

Verify the database-driver JAR files, found in the `<pf_install>/pingfederate/server/default/lib` directory, meet the minimum version requirement. If you are using JDBC drivers of version 4.0 (or earlier), contact your vendors for the latest drivers and replace the older JDBC database-driver JAR files with the latest.

For more information, including re-enabling BoneCP as the JDBC connection pool library, see [Reviewing database changes](#) on page 162.

## Log4j 2 upgrade

PingFederate 8.0 has upgraded its logging framework from Log4j to Log4j 2.

If you have previously customized `<pf_install>/pingfederate/server/default/conf/log4j.xml`, you will need to manually migrate your changes to the new `log4j2.xml` in the same `conf` directory. See [Logging configurations](#) on page 164 for instructions.

### Note:

was tested with vendor-specific JDBC drivers. For more information, see [Compatible database drivers](#) on page 124. To obtain the database driver `.jar` file, contact your database vendor. Install the database driver file to the `<pf_install>/pingfederate/server/default/lib` directory, and then restart the server.

## Upgrade considerations introduced in PingFederate 7.x

### Hostname verification for LDAPS

For LDAP type datastores with LDAPS enabled, hostname verification of the certificate is enabled by default for all new datastores beginning with PingFederate 7.3. When upgrading from a previous version of PingFederate, this option is disabled for existing datastores for compatibility reasons. Administrators should consider activating this new option for greater security.

### Changes in a database table supporting nested group membership

Outbound provisioning of groups and nested group membership requires an update in the internal datastore. Follow the instructions in [Reviewing database changes](#) on page 162 to add or update the **group\_membership** table.

### SSLv3 disabled

To mitigate the POODLE attack, the SSLv3 protocol is disabled by default starting in PingFederate 7.3. It can be re-enabled by modifying the connector configuration in `jetty-runtime.xml` and `jetty-admin.xml` found in the `<pf_install>/pingfederate/etc` directory.

### New representation for multivalued attributes in WS-Federation assertions

Starting with PingFederate 7.3, multivalued attributes in WS-Federation assertions are now represented as multiple `AttributeValue` elements under a single `Attribute` element. Previously, they were represented as a series of `Attribute` elements with the same name. The new behavior was implemented for compatibility with ADFS 2.0. To revert to the previous behavior, a setting is available in `wstrust-global-settings.xml`.

### A new index (EXPIRESIDX) in the database table for OAuth persistent grants

PingFederate 7.3 added an index (EXPIRESIDX) for the `expires` column in the `pingfederate_access_grant` database table. For information on adding this index to your existing table, see [Reviewing database changes](#) on page 162.

### A new database table for OAuth persistent grant extended attributes

Starting with PingFederate 7.2 R2, a new database table needs to be created to support OAuth's persistent grant extended attributes. The database scripts to create this table can be found in `<pf_install>/pingfederate/server/default/conf/access-grant/sql-scripts/access-grant-attribute-<databaseServer>.sql`. See [Reviewing database changes](#) on page 162 for more information.

### LDAP filter syntax checking

Starting with PingFederate 7.2, LDAP filters only allow spaces in matched-against values.

Examples

`(|(sAMAccountName=${username})(employeeID=ID for ${username}))` is allowed; spaces in the matched-against value of “ID for \${username}” are valid.

`( |(sAMAccountName=${username})(employeeID=ID for ${username}) )` is not allowed because this filter contains spaces outside of matched-against values.

Invalid filters cause SSO runtime failures. Error messages logged to server.log include:

```
Caused by: javax.naming.NamingException: [LDAP: error code 87 -
Expected a closing parenthesis...
```

```
Caused by: javax.naming.NamingException: [LDAP: error code 87 -
Unexpected closing parenthesis found...
```

We recommend reviewing LDAP filters and removing spaces outside of matched-against values after upgrade.

### HTML Form Adapter enhancement

Starting with version 7.1 R3, PingFederate tracks login attempts in the HTML Form Adapter. When the number of login failures reaches the Challenge Retries threshold defined in the adapter, the user is locked out for one minute. See [HTML Form Adapter](#) on page 305 for more information.

### A new index (CLIENTIDIDX) in the database table for OAuth persistent grants

PingFederate 7.1 R3 added an index (CLIENTIDIDX) for the `client_id` column in the `pingfederate_access_grant` database table. For information on adding this index to your existing table, see [Reviewing database changes](#) on page 162.

### Requested (formerly SAML) AuthN Context authentication selector process order changed

In releases prior to 7.1 R2, when the Requested AuthN Context Authentication Selector received a list of authentication contexts, it used the last context that it could match, rather than the first. However, both the SAML and OpenID Connect specifications treat an authentication context list as appearing in order of preference. To align the Requested AuthN Context Authentication Selector with these specifications, the selection order was changed in 7.1 R2. With this release, the selector will use the first authentication context it can match, rather than the last.

### Multivalued LDAP attributes passed to outbound provisioning OGNL expressions

In releases before version 7.1, if an OGNL expression was used to populate a SaaS-partner field in outbound provisioning, only the first value of a selected multivalued LDAP attribute was used in the OGNL expression. As of PingFederate 7.1, this behavior was changed to use all values in the expression.



#### Note:

If this new behavior conflicts with existing deployments, it can be reverted via the `supportMultiValuesFromDirectory` property located in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.provisioner.mapping.OgnlFieldMapper.xml` file.

### OAuth clients reconfiguration

Neither the Upgrade Utility nor the platform-specific installers migrates OAuth clients that are created from 6.5 through 7.0. Use any of the following interfaces to reconfigure your OAuth clients:

- The **Clients** window (**Applications # OAuth # Clients**) in the administrative console.
- The `/oauth/clients` administrative API endpoint.
- The REST-based web service for OAuth client management at the `/pf-ws/rest/oauth/clients` and `/pf-ws/rest/oauth/clients/id` endpoints. This web service requires the client records to be stored in a database.

Note that has been storing OAuth clients in XML files since version 7.1; these clients are migrated to the new installation. In addition, if you have configured 6.8 (or a more recent version) to store OAuth clients in an external database, the new installation retains that configuration as well.

## Upgrade considerations introduced in PingFederate 6.x

### Cluster bind address required

Starting with PingFederate 6.11, the `pf.cluster.bind.address` property located in `<pf_install>/pingfederate/bin/run.properties` is required when running PingFederate in a cluster. The default value is `NON_LOOPBACK`.

### Decryption and digital signing policy changes

Potential security vulnerabilities have resulted in the following changes to PingFederate as of version 6.11. In some cases, these might impact interoperability with partners:

- When acting as an SP and using the POST binding, PingFederate decrypts an assertion only when the SAML response has been signed. An unsigned SAML response that contains an encrypted assertion is rejected.



#### Note:

Although strongly discouraged, this policy change can be reverted on a per-connection basis via the `EntityIdsToAllowAssertionDecryptionWithoutResponseSignature` list located in the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.saml20.profiles.sp.HandleAuthnResponse.xml` file.

- When acting as an IdP, PingFederate always signs a SAML response (even when the assertion is also signed) if it contains an encrypted assertion.



#### Note:

Although strongly discouraged, this policy change can be reverted on a per-connection basis via the `EntityIdsToOmitResponseSignatureOnSignedEncryptedAssertion` list located in the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.saml20.profiles.idp.HandleAuthnRequest.xml` file.

- When acting as an IdP, PingFederate decrypts an encrypted NameID in an Attribute Query only when the request has been signed or the client has authenticated with basic or mutual TLS.

### Key transport algorithm deprecated

Due to security risks associated with the RSA-v1.5 algorithm used for key transport, it is no longer available for new connections starting with PingFederate 6.11. Existing connections in which this algorithm is configured continue to support it. However, we recommend upgrading to use the newer RSA-OAEP algorithm. See [Selecting an encryption certificate](#) on page 494 for SP connections and [Choosing an encryption certificate \(SAML 2.0\)](#) on page 803 for IdP connections.

### OAuth persistent grants expiration

When upgrading to PingFederate 6.8 later, all persistent grants for any existing OAuth deployments using an Oracle MySQL database will expire. To address this issue, the `expires` column in the `pingfederate_access_grant` table should be set to null prior to the upgrade. If necessary, contact Ping Identity support for assistance.

### OAuth clients reconfiguration

Neither the Upgrade Utility nor the platform-specific installers migrates OAuth clients that are created from 6.5 through 7.0. Use any of the following interfaces to reconfigure your OAuth clients:

- The **Clients** window (**Applications # OAuth # Clients**) in the administrative console.
- The `/oauth/clients` administrative API endpoint.
- The REST-based web service for OAuth client management at the `/pf-ws/rest/oauth/clients` and `/pf-ws/rest/oauth/clients/id` endpoints. This web service requires the client records to be stored in a database.

Note that has been storing OAuth clients in XML files since version 7.1; these clients are migrated to the new installation. In addition, if you have configured 6.8 (or a more recent version) to store OAuth clients in an external database, the new installation retains that configuration as well.

#### OGNL library upgraded

The OGNL library has been upgraded in version 6.4. If you use OGNL expressions in versions prior to 6.4, we recommend retesting the expressions using the PingFederate administrative console or runtime tests.

## Upgrading PingFederate installations

---

When upgrading your PingFederate installation on Linux, you must use the Upgrade Utility. On Windows, you can use either the Upgrade Utility or the installer.

#### Before you begin

- Read [Upgrading PingFederate](#) on page 138 for an overview of the upgrade process.
- Ensure that you are signed on to your server with appropriate privileges to install and run an application.

#### About this task

Choose the relevant procedure for your system to upgrade PingFederate.



#### Tip:

If you are upgrading a clustered PingFederate environment, start with the console node, and then upgrade the engine nodes.



#### Important:

All nodes must use the same version of PingFederate.

## Upgrading PingFederate on Linux systems

You can use the Upgrade Utility on Linux servers to upgrade to the current version of PingFederate.

#### About this task

The Upgrade Utility migrates the existing versions of all PingFederate plugins by default. You can use the `-c` command line parameter to override the default behavior and install the latest versions of each plugin.

Upgrade results are contained in the `<pf_install_target>/pingfederate/upgrade/log/upgrade.log` file.

To use the Upgrade Utility on Linux servers to upgrade to the current version of PingFederate:



## Steps

1. Download the latest version of the PingFederate Server distribution .zip archive from the Ping Identity [website](#).
2. Extract the distribution .zip archive into the target installation directory.
3. Stop PingFederate.
4. On the command line, change the current directory to `<pf_install>/upgrade/bin` within the target installation and execute the following command:

```
./upgrade.sh <pf_install_source> [-l <newLicense>] [-c] [--release-notes-reviewed]
```

where:

`<pf_install_source>`

The full or relative path of the base `pingfederate` directory where the existing software is installed.

 **Note:**

The `pingfederate` directory must exist by that name for the Upgrade Utility to function correctly.

`<newLicense>`

The optional path and file name of the license to use for the upgraded version.

 **Note:**

If your current license is valid, the Upgrade Utility automatically copies it from the source installation to the target installation, and you don't need to specify the `<newLicense>` parameter.

If your license isn't valid, obtain a valid license file and specify its path and file name for this parameter.

`-c`

The optional parameter to run the tool in custom mode, which allows you to override newer default security settings (if any) and to upgrade to the newest version of each installed plugin.

`--release-notes-reviewed`

An optional parameter that indicates that you've already reviewed the release notes. This parameter prevents prompts during the upgrade that ask if you've read the release notes and the upgrade considerations.

## Result:

The command prompt displays messages indicating upgrade progress. The process is complete when the following message appears:

```
Upgrade completed with [N] errors and [N] warnings
```

If there are errors, scroll up the command window to see them and then correct the indicated problems. Errors during the upgrade should be rare but might include problems such as missing or malformed configuration files in the source installation. The messages are also logged to the `upgrade.log` file in the Upgrade Utility base directory.

5. If you're using an older version of the Amazon Web Services (AWS) CloudHSM client:
  - a. Update the CloudHSM client and the CloudHSM Software Library for Java to a supported version and restart the client.  
  
For more information, see [System requirements](#) on page 119.
  - b. Copy `<pf_install>/pingfederate/lib-ext/pf-aws-cloud-hsm-wrapper.jar` to the `JAVA_HOME/jre/lib/ext` directory.
  - c. Copy all of the files in the `/opt/cloudhsm/java` and `/opt/cloudhsm/lib` directories to the `JAVA_HOME/jre/lib/ext` directory.
6. If you're upgrading a clustered environment, repeat from step 1 to upgrade on each engine node.

**Note:**

End users might experience disruptions while you upgrade your environment.

7. Start the new installation.  
  
If you're upgrading a clustered environment, start the new instance on the console node.  
  
If you've configured single sign-on using OpenID Connect (OIDC) as the console authentication scheme and set the endpoint settings back to your environment, start the new instance on the console node and one of the engine nodes.
8. Open the administrative console and verify the new installation.
9. If you're upgrading a clustered PingFederate environment:
  - a. Start the new installation on each engine node, and then ensure all nodes are shown on the **System # Server # Cluster Management** page.
  - b. On the **Cluster Management** page, click **Replicate Configuration**.
10. If PingFederate is running as a service, reconfigure the PingFederate service:
  - a. Edit the `<pf_install>/pingfederate/sbin/linux/pingfederate.service` systemd unit file (see [step 5](#) in [Installing PingFederate > Installing on Linux manually](#)).
  - b. Edit the `<pf_install>/pingfederate/sbin/linux/pingfederate` SysV initialization script (see [step 6](#) in [Installing PingFederate > Installing on Linux manually](#)).
11. Although the upgrade utility automatically merges, migrates, and copies the language packs' `.properties` files into the upgraded PingFederate installation, verify the language packs in the upgrade installation by looking at the `.properties` files located in the upgraded `<pf_install>/pingfederate/server/default/conf/language-packs` directory.
  - **Standard** `.properties` files include `pingfederate-email-messages.properties`, `pingfederate-messages.properties`, and `pingfederate-sms-messages.properties`. During the upgrade, these files are migrated and merged into the upgraded PingFederate installation.
  - **Localized** `.properties` files (for example, `pingfederate-messages_fr_CA.properties`), are also migrated and merged into the upgraded PingFederate installation.
  - If the PingOne MFA or PingOne Protect integration kit was installed on PingFederate, you must manually migrate its `.properties` file after the upgrade.
  - All other `.properties` files in `<pf_install>/pingfederate/server/default/conf/language-packs` that don't fit the previous criteria are copied (not merged) into the upgraded PingFederate installation.

### Next steps

After upgrading PingFederate, perform the [Post-upgrade tasks](#) on page 158.

## Upgrading PingFederate on Windows using the Upgrade Utility

About this task

Upgrade results are contained in the `<pf_install_target>\pingfederate\upgrade\log\upgrade.log` file.



### Note:

If you used the server distribution `.zip` archive to install the previous version of PingFederate on Windows, you must use the Upgrade Utility to upgrade to the current version of PingFederate.

### Steps

1. Download the latest version of the PingFederate Server distribution `.zip` archive from the Ping Identity [website](#).



### Note:

The distribution `.zip` archive is identical for both Windows and Linux.

2. Extract the distribution `.zip` archive into the target installation directory.
3. Stop PingFederate.
4. At the command prompt, change the current directory to `<pf_install>\pingfederate\upgrade\bin` within the target installation and enter the following command:

```
upgrade <pf_install_source> [-l <newLicense>] [-c] [--release-notes-reviewed]
```

where:

`<pf_install_source>`

The full or relative path of the base `pingfederate` directory where the existing software is installed.



### Note:

The `pingfederate` directory must exist by that name for the Upgrade Utility to function correctly.

`<newLicense>`

The optional path and file name of the license to use for the upgraded version.



### Note:

If your current license is valid, the Upgrade Utility automatically copies it from the source installation to the target installation, and you don't need to specify the `<newLicense>` parameter.

If your license isn't valid, obtain a valid license file and specify its path and file name for this parameter.

-c

The optional parameter to run the tool in custom mode, which allows you to override newer default security settings (if any) and to upgrade to the newest version of each installed plugin.

```
--release-notes-reviewed
```

An optional parameter that indicates that you've already reviewed the release notes. This parameter prevents prompts during the upgrade that ask if you've read the release notes and the upgrade considerations.

#### Result:

The command prompt displays messages indicating upgrade progress. The process is complete when the following message appears:

```
Upgrade completed with [N] errors and [N] warnings
```

If there are errors, scroll up the command window to see them and then correct the indicated problems. Errors during the upgrade should be rare but might include problems such as missing or malformed configuration files in the source installation. The messages are also logged to the `upgrade.log` file in the Upgrade Utility base directory.

5. If you're upgrading a clustered environment, repeat from step 1 to upgrade on each engine node.



#### Note:

End users might experience disruptions while you upgrade your environment.

6. Start the new installation.

If you're upgrading a clustered environment, start the new instance on the console node.

If you've configured single sign-on using OpenID Connect (OIDC) as the console authentication scheme and set the endpoint settings back to your environment, start the new instance on the console node and one of the engine nodes.

7. Open the administrative console and verify the new installation.
8. If you're upgrading a clustered PingFederate environment:
  - a. Start the new installation on each engine node, and then go to **System # Server # Cluster Management** and ensure all nodes are shown.
  - b. On the **Cluster Management** page, click **Replicate Configuration**.
9. If PingFederate is running as a service, reinstall the service:
  - a. Remove the existing PingFederate service.
 

For more information, see [Uninstalling PingFederate from a Windows server](#) on page 136.
  - b. Install the new PingFederate service.
 

For more information, see [Installing the PingFederate service on Windows manually](#) on page 135.
  - c. For a clustered PingFederate environment, reinstall the PingFederate service on all nodes.
10. Although the upgrade utility automatically merges, migrates, and copies the language packs' `.properties` files into the upgraded PingFederate installation, verify the language packs in the upgrade installation by looking at the `.properties` files located in the upgraded `<pf_install>\pingfederate\server\default\conf\language-packs` directory.
  - **Standard .properties files include** `pingfederate-email-messages.properties`, `pingfederate-messages.properties`, and `pingfederate-sms-`

`messages.properties`. During upgrade, these files are migrated and merged into the upgraded PingFederate installation.

- Localized `.properties` files (for example, `pingfederate-messages_fr_CA.properties`), are also migrated and merged into the upgraded PingFederate installation.
- If the PingOne MFA or PingOne Protect integration kit was installed on PingFederate, you must manually migrate its `.properties` file after the upgrade.
- All other `.properties` files in `<pf_install>\pingfederate\server\default\conf\language-packs` that don't fit the previous criteria are copied (not merged) into the upgraded PingFederate installation.

Next steps

After upgrading PingFederate, perform the [Post-upgrade tasks](#) on page 158.

## Upgrading PingFederate on Windows using the installer

About this task



### Note:

If you used the PingFederate installer for Windows to install the previous version of PingFederate, you can use it to upgrade to the current version of PingFederate.

Upgrade results are contained in the `upgrade.log` file. If the upgrade succeeds, `upgrade.log` is located in `<pf_install_target>\pingfederate\upgrade\log`. If the upgrade fails, `upgrade.log` is located in `<pf_install_target>`.

The default location for `<pf_install_target>` is `C:\Program Files\Ping Identity`. You can change the location during the upgrade process.



### Note:

The PingFederate installer for Windows doesn't support custom mode. If you want to override the newer default security settings or upgrade the OpenToken Adapter, use the PingFederate Upgrade Utility.

Steps

1. Download the PingFederate installer for Windows from the Ping Identity [website](#).
2. Double-click the `pingfederate-<version>.msi` file to begin the upgrade.
3. Follow the instructions in the PingFederate Setup Wizard to upgrade PingFederate.

Result:

Errors are rare but might include problems, such as missing or malformed configuration files in the source installation. If the upgrade tool reports an error, review the error messages in the `upgrade.log` file.



### Note:

You can rerun the tool as many times as needed to correct any problems.

When the tool completes the upgrade, it automatically starts the new installation.

4. If you're upgrading a clustered environment, repeat from step 1 to upgrade on each engine node.



**Note:**

End users might experience disruptions while you upgrade your environment.

5. Open the administrative console and verify the new installation.
6. If you are upgrading a clustered PingFederate environment:
  - a. Go to **System # Server # Cluster Management** and ensure all nodes are shown.
  - b. On the **Cluster Management** page, click **Replicate Configuration**.

#### Next steps

After upgrading PingFederate, perform the [Post-upgrade tasks](#) on page 158.

## Custom mode in the Upgrade Utility

---

The custom-mode feature in the Upgrade Utility (invoked with the `-c` option on the command line) allows you to override several default security settings. In addition, if the installed OpenToken Adapter is out of date, running the tool in custom mode allows you to replace the adapter with the latest version.

#### Security defaults

Using the security defaults should not cause significant issues for most PingFederate installations. The more recent default security settings include:

- Disabling weaker cipher suites for both the SUN and LUNA Java Cryptography Extension (JCE) in PingFederate version 6.2 and later. To see which cipher suites are commented out, choose yes (y) when prompted on whether to use the new defaults. After the upgrade is complete, refer to one of the following configuration files in the new installation's `<pf_install>/pingfederate/server/default/data/config-store` directory:
  - `com.pingidentity.crypto.SunJCEManager.xml`
  - `com.pingidentity.crypto.AWSCloudHSMJCEManager.xml`
  - `com.pingidentity.crypto.LunaJCEManager.xml`
  - `com.pingidentity.crypto.NcipherJCEManager.xml`
  - `com.pingidentity.crypto.BCFIPSJCEManager.xml`

#### Adapter upgrade

Upgrading the OpenToken Adapter from an earlier version doesn't normally require any follow-on configuration changes.

- If your existing installation uses a version of the OpenToken Adapter earlier than 2.3, upgrading requires minor configuration modifications in the PingFederate console and redeployment of the agent configuration file.
- If you are upgrading from an OpenToken version earlier than 2.5.1, you should redeploy agent configuration files, if applicable, as well as any new agent libraries contained in recent versions of PingFederate integration kits and other plugins that use OpenToken.

## Post-upgrade tasks

---

Confirm your new PingFederate installation configurations and settings.

After upgrading PingFederate, you might need to:

- [Review administrative users](#)
- [Copy customized files or settings](#)
- [Review database changes](#)
- [Review the log configuration](#)
- [Migrate other components](#)
- [Reset files and variables for HSM](#)
- [Verify the new installation](#)

You should also perform runtime tests to ensure the new PingFederate installation fulfills your existing use cases.

## Reviewing administrative users

As of PingFederate 10.1, the use of expressions is enabled by default. Additionally, a new administrative role, Expression Admin, has been added.

When upgrading to the PingFederate 10.1 or later from a previous version, administrative users who were granted the Admin role in the earlier installation are granted the Expression Admin role automatically. You can achieve the same result by using the `/bulk/import` administrative API endpoint to bulk-import a configuration that was bulk-exported from PingFederate 10.0.

If preferred, administrators can disable the use of expressions by setting `evaluateExpressions` to `false` as described in [Enabling and disabling expressions](#) on page 225.

You can also go to **System # Server # Administrative Accounts** and remove the Expression Admin role from all Admin users. Doing this prevents Admin users from entering expressions into PingFederate if the `evaluateExpressions` element is set to `true` at a later time. For more information, see [Administrative accounts](#) on page 914.

## Copying customized files or settings

After you upgrade PingFederate, you must copy files that were customized in the previous release to the current installation.

### User-facing windows

If you modified any Velocity templates for user-facing windows, to preserve the customized user experience, some of your custom changes must be migrated manually to the new installation manually for each server node.

The templates are located in the `<pf_install>/pingfederate/server/default/conf/template` directory.

As of PingFederate 11.0, the Upgrade Utility migrates your modified Velocity HTML templates to the new installation. The default templates in the new installation that correspond to the modified templates are renamed with the following format: `<template_name>-default-<PF-version>.<ext>`.



### CAUTION:

Supporting CSS and image file names changed as of PingFederate 7.0. For each modified HTML template copied, add `.1` to the base name for each CSS file referenced in the header, for example, `<link rel="..." href="assets/css/window.1.css"/>`.

Add `.1` to any references in the copied templates to the installed image files contained in the `assets/images` directory, for example, ``.

### Email notifications

If you modified the email notification templates before PingFederate 9.2, manually migrate your custom changes to the new HTML-based templates for each server node.

The plain text templates (message-template-\*.txt) are located in `<pf_install>/pingfederate/server/default/conf` in the source installation. The new HTML-based templates are located in `<pf_install>/pingfederate/server/default/conf/template/mail-notifications` with the same file naming convention but an `.html` file extension.

As of PingFederate 11.0, the Upgrade Utility migrates your modified Velocity HTML templates to the new installation. The default templates in the new installation that correspond to the modified templates are renamed with the following format: `<template_name>-default-<PF-version>.<ext>`.

### Jetty or JBoss configuration

If you have modified any Jetty or JBoss settings that need to be carried forward, you must make the corresponding changes manually in the new PingFederate deployment.

If you are upgrading from PingFederate 6.9 or later, merge any changes in `<pf_install>/etc/jetty-runtime.xml` and `<pf_install>/etc/jetty-admin.xml` files into the corresponding files of the new deployment.



#### Note:

If only the values of the `minThreads`, `maxThreads`, and `acceptQueueSize` parameters were modified in those Jetty files, you should set those values in the new deployment's `<pf_install>/bin/run.properties` file instead of merging them into the Jetty files.

The advantage of setting those values in `run.properties` is that PingFederate can automatically merge `run.properties` customizations into new deployments, saving you time and preventing errors in future upgrades. For more information, see [Configuring PingFederate properties](#) on page 820.

If you are upgrading from PingFederate 6.0 through 6.8, first identify any changes made to the JBoss configuration, then make corresponding changes for the newer Jetty configuration.

For example, if you modified the `<pf_install>/pingfederate/server/default/deploy/jetty.sar/META-INF/jboss-service.xml` file before 6.9, identify the changes and make the same modifications at corresponding points in either the `jetty-admin.xml` or `jetty-runtime.xml` files located in the new Jetty configuration directory, `<pf_install>/pingfederate/etc`.

### The size-limits.conf file

Before PingFederate 8.4.2, the `InterReqStateMgmtMapImpl.expiry.mins` setting in the `<pf_install>/pingfederate/server/default/conf/size-limits.conf` file defines the lifetime of the Adapter session-state data and Inter-request state information data sets.

#### Adapter session-state data

The state information, along with the associated attributes and any of their values, maintained or used by the adapters.

#### Inter-request state information

The state information between the redirects to complete a request.

PingFederate 8.4.2 and later splits the `InterReqStateMgmtMapImpl.expiry.mins` settings into two settings, one setting for each data type.

| New settings   | Data type                       | Default value in minutes |
|--|---------------------------------|--------------------------|
| <code>InterReqStateMgmtMapImpl.expiry.mins.state-info</code> | Inter-request state information | 30                       |



| New settings  | Data type                  | Default value in minutes |
|---|----------------------------|--------------------------|
| <code>InterReqStateMgmtMapImpl.expiry.mins.att</code> | Adapter session-state data | 1440 (24 hours)          |

The new settings reduce the memory footprint of PingFederate by purging the inter-request state information after 30 minutes and retaining adapter session-state data during the day.

If you previously modified the value of the `InterReqStateMgmtMapImpl.expiry.mins` setting, when migrating your change to the latest version, adjust the value of the new settings based on your requirements.

### Cross-origin resource sharing (CORS) support for OAuth endpoints

If you previously edited the `<pf_install>/pingfederate/etc/webdefault.xml` file to enable CORS support for OAuth endpoints, instead of updating the `webdefault.xml` file, define the allowed origins manually using the PingFederate administrative console after the upgrade.

For more information, see [Configuring authorization server settings](#) on page 519.

### Configuration files in the config-store directory

If you added or replaced setting values in configuration files stored in the `<pf_install>/pingfederate/server/default/data/config-store` directory, the PingFederate upgrade tools copy these setting values to the new installation.



#### Note:

The upgrade tools do not copy comments from the existing installation to the new installation.

If you removed a setting or a block of settings from a configuration file in the `config-store` directory, the upgrade tool preserves your changes by removing the setting or block of settings from the new installation and records the removals in its log file.

To re-add a setting or block of settings to the new installation, compare the configuration file found in the new installation to the file found in the product distribution `.zip` archive and make your changes.

### Other configuration files

As of PingFederate 10.0, the upgrade process copies many files automatically. However, there are still some files that you must copy manually, which you can find in `<pf_install>/pingfederate/server/default/conf`.

The following files are copied automatically:

- Properties files with the `.conf` extension
- The `log4j2.db.properties` file
- The `jmx-remote-config.xml` file
- Non-default files located in the `template` directory

If you modified the default templates located in `<pf_install>/pingfederate/server/default/conf/template`, you must customize these templates in the new PingFederate installation.

If you modified versions of `tcp.xml`, `udp.xml`, and `log4j2.xml`, they are copied over intact. The default files are saved in the target directory with a different extension. To take advantage of the improvements in the default versions of these files, merge your changes into the current default files and then rename them appropriately.



#### Note:

If you are upgrading from 8.0 or earlier, PingFederate might not start until you have merged your changes into the current default files because of JGroups errors.

Other files, such as `jmx.remote.access`, are not copied to the new installation automatically. To preserve any custom settings, create a backup of the current configuration files and merge your changes to the current files.



#### Important:

If you previously customized Java virtual machine (JVM) options in the `run.bat` or `run.sh` files, instead of updating these files, manually merge your JVM options to the `<pf_install>/pingfederate/bin/jvm-memory.options` file. For more information, see [Fine-tuning JVM options](#) on page 1094 and [memoryoptions and upgrade](#) on page 1090.

## Reviewing database changes

Occasionally, PingFederate introduces database-related changes, such as adding a new table, modifying an existing table, or updating the connection pool library, for the purpose of product improvement.

Neither the Upgrade Utility nor the PingFederate installer for Windows migrates data maintained in the internal HSQLDB database or any external database. For instance, if outbound provisioning is enabled in the new PingFederate instance using the internal database, it's re-initialized from the provisioning source.



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

If your PingFederate environment connects to one or more database servers, review the following topics and make changes accordingly:

- [Provisioning datastore reset](#) on page 162
- [Enabling security enhancement in JDBC datastore queries](#) on page 163
- [An improved index in the database table for OAuth clients](#) on page 163

### Provisioning datastore reset

If you are upgrading from PingFederate 9.0.0 or 9.0.1, reset the provisioning datastore on the upgraded installation.

About this task

Use the `provmgr` command-line tool to reset the provisioning datastore on the upgraded installation.

The `provmgr` command-line tool is located in the `<pf_install>/pingfederate/bin` directory:

- Windows: `provmgr.bat`
- Linux: `provmgr.sh`

For more information about the `provmgr` command-line tool, see [Outbound provisioning CLI](#) on page 866.

## Steps

1. To obtain a list of provisioning channel IDs, run the following command:

```
provmgr --show-channels
```

2. Reset the provisioning datastore for a given channel by its ID:

```
provmgr -c <channel_id> --reset-all
```



### Note:

If you have multiple provisioning channels, run the command for each channel. The order of the parameters doesn't matter.

## Enabling security enhancement in JDBC datastore queries

Edit the `org.sourceid.common.SqlFilterManager.xml` file for stronger security protection in a JDBC datastore.

### About this task



### Note:

If you are upgrading from PingFederate 8.4.4 or earlier, modify the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.SqlFilterManager.xml` file to enable the safeguard for JDBC datastore queries against backend SQL injection attacks.

## Steps

1. Edit the `org.sourceid.common.SqlFilterManager.xml` file.
2. Set the `<item name="enableSqlFilters"/>` element value to `true`.

Example:

```
<?xml version="1.0" encoding="UTF-8"?>
<config xmlns="http://www.sourceid.org/2004/05/config">
  <item name="enableSqlFilters">true</item>
</config>
```

3. Save the file.
4. Restart PingFederate.
5. If you have a clustered PingFederate environment, push this change to all engine nodes:
  - a. On the administrative console, go to **System # Server # Cluster Management**.
  - b. Click **Replicate**.
6. Verify your use cases to make sure your search filters return the expected results.

## An improved index in the database table for OAuth clients

PingFederate 8.4 added the `value` column to an existing index (`IDX_FIELD_NAME`) in the `pingfederate_oauth_clients_ext` table as a general improvement.

This information is applicable only to customers who configured PingFederate to store OAuth clients on a database server.

You must modify the index in your existing `pingfederate_oauth_clients_ext` table.

Although there is no alter-table script provided, you can derive the setup from the new table-setup scripts in the `<pf_install>/pingfederate/server/default/conf/oauth-client-management/sql-scripts/oauth-client-management-<databaseServer>.sql` file.

## Logging configurations

PingFederate uses log4j2 to write log messages.

If the configuration file for Log4j 2 (or Log4j) has been modified in the source installation, manually merge the configuration changes into the upgraded environment.

### Merging custom logging configurations

About this task

The upgrade tools do not support automatic merging of customizations made to the existing logging configuration. Instead, these upgrade tools copy the modified `log4j2.xml` file to the new installation intact and rename the configuration file from the product `.zip` archive using the new PingFederate version number. Both configuration files are located in the same `conf` directory.



#### Note:

If the Upgrade Utility or the PingFederate installer for Windows determines that the `log4j2` configuration file ( `<pf_install>/pingfederate/server/default/conf/log4j2.xml` ) has changed since it was originally installed, new features are not activated.

To activate new features:

Steps

1. Review the new features by comparing the renamed `log4j2` configuration file against the `log4j2.xml` file.
2. Modify the `log4j2.xml` file to suit your needs.
3. If you have a clustered PingFederate environment, repeat step 2 for all applicable PingFederate nodes in the cluster.

## Migrating other components

Some custom and integrated components might require additional steps after upgrading PingFederate.

### Updating the custom authentication selector

Through the use of the PingFederate SDK, you can create a custom authentication selector by implementing the `AuthenticationSelector` interface.

Most implementations return `AuthenticationSelectorContext.ResultType.CONTEXT` as the result type, which requires no further action after an upgrade.

If your implementation returns either:

- `AuthenticationSelectorContext.ResultType.ADAPTER_ID`, an Identity Provider (IdP) adapter instance ID
- `AuthenticationSelectorContext.ResultType.IDP_CONN_ID`, the connection ID of an IdP connection

You must update the descriptor instance of your custom authentication selector to call the `setSelectAuthnSourceResultType` method with an input of `true`. For each authentication policy path that ends with an instance of such custom authentication selector, you must ensure that its action is set to **Done**.

For more information, see the Javadoc for the `AuthenticationSelector` interface and the `AuthenticationSelectorDescriptor` class.



**Tip:**

The Javadoc for is located in the `<pf_install>/pingfederate/sdk/doc` directory.

## Migrating to the integrated LDAP Username PCV

About this task

As of PingFederate 7.3, the integrated LDAP Username Password Credential Validator (PCV) can return additional attribute values upon successful validation.

If you have previously deployed the `LDAPExtendedAttributesPCV-<version>.jar` file from the PingID integration kit and created an instance of the LDAP PCV with Extended Attributes, migrate to the integrated LDAP Username PCV.

Steps

1. Create an instance of the integrated LDAP Username PCV:
  - a. Go to **System # Data & Credential Stores # Password Credential Validators** and click **Create New Instance**.
  - b. On the **Type** tab, enter the required information and select **LDAP Username Password Credential Validator** from the list.
  - c. On the **Instance Configuration** tab, select an LDAP datastore from the list, enter a search base and a search filter, and select the scope of the search.



**Tip:**

You can reuse the information from the existing LDAP PCV with Extended Attributes instance.

- d. On the **Extended Contract** tab, enter `memberOf` in the **Extend the Contract** section, and click **Add**.
  - e. On the **Summary** tab, review the setup and click **Done**.
  - f. On the **Manage Credential Validator Instances** page, click **Save**.
2. In the configuration where the LDAP PCV with Extended Attributes instance is used, replace it with the newly created LDAP Username Password Credential Validator instance.

For example, if you have created an instance of the PingID PCV (with integrated RADIUS server) instance and have selected an instance of the LDAP PCV with Extended Attributes as one of the delegate PCVs, remove the selection and add the newly created LDAP Username Password Credential Validator instance to the list.

3. After replacing the LDAP PCV with Extended Attributes instance, delete it from the **Password Credential Validators** page.
4. Remove the `<pf_install>/pingfederate/server/default/deploy/LDAPExtendedAttributesPCV-<version>.jar` file on all PingFederate servers.
5. Restart PingFederate on all PingFederate servers.

## Migrating to the integrated Username Token Processor

About this task

As of PingFederate 7.2, the Username Token Translator has been deprecated and replaced with an integrated Username Token Processor. Although the integrated Username Token Processor and the

deprecated Username Token Translator can be simultaneously deployed, you should migrate it to the new token processor.

#### Steps

1. Go to **Identity Provider # Token Processors**.
2. To create an instance of the integrated Username Token Processor, click **Create New Instance**.
  - a. On the **Type** page, select **Username Token Processor** from the list.



#### Tip:

If you have multiple WS-Trust STS SP connections, you can reuse the same Username Token Processor instance or create additional instances of the token processors as needed.

3. Map the new token processor instance to the applicable WS-Trust STS SP connection on the **IdP Token Processor Mapping** page.  
Repeat this step if you have multiple WS-Trust STS SP connections.
4. Test your WS-Trust STS SP connections using the instance of the integrated Username Token Processor.
5. Remove the token processor instance of the deprecated Username Token Translator from all WS-Trust STS SP connections on the **IdP Token Processor Mapping** page.
6. If you have set up token translator mappings, create new entries to replace those using instances of the deprecated Username Token Translator, test the new mapping entries, and delete the entries that use instances of the deprecated Username Token Translator.
7. Delete all token processor instances of the deprecated Username Token Translator on the **Identity Provider # Token Processors** page.
8. Remove the `pf-username-token-translator-<version>.jar` file from the `<pf_install>/pingfederate/server/default/deploy` directory on all PingFederate servers.
9. Restart PingFederate on all PingFederate servers.

### Resetting files and variable for HSM

Update your environmental variable in the `<pf_install>server/default/data/ncipher-kmdata-local` directory to point to the new location.

If your PingFederate installation is configured in a clustered environment with Entrust nShield Connect, you must copy the `<pf_install>server/default/data/ncipher-kmdata-local` directory to the new installation manually and update the environmental variable **NFAST\_KMLOCAL** to point to the new location.

### Verifying the new installation

Verify the functionality of your new PingFederate installation.

PingFederate integration kits and custom solutions might introduce third-party dependencies that could trigger runtime errors. You should perform runtime tests, verifying that the previously deployed use cases, including any OGNL expressions, are functional in the new PingFederate installation.

## Updating to the latest maintenance release

---

For PingFederate maintenance releases, you have the option to update your installation using the incremental update package. This in-place update method lets you replace and merge only the files that have changed.

Before you begin

- Ensure your installation is running PingFederate 11.1.x, where "x" represents an older maintenance release of 11.1.
- Make a backup copy of the PingFederate home directory.

About this task

You can incrementally update your PingFederate 11.1 installation to the latest 11.1 maintenance release. For example, if you are on PingFederate 11.1.1 and the latest maintenance release is version 11.1.4, you can use the in-place update method to update your installation to version 11.1.4.

The in-place update doesn't contain files from Ping Identity integration kits. You can upgrade an integration kit manually by downloading the latest kit from the [PingFederate Downloads](#) page's **Add-ons** tab and following the instructions provided by the kit's documentation.



### Important:

You cannot use the in-place update method to upgrade an older version of PingFederate, such as 9.3.3 or 10.3.2, to version 11.1.x. For those older versions, you must use the standard upgrade method for your platform described in [Upgrading PingFederate](#) on page 138.



### Note:

The in-place update method involves manual modification of PingFederate files. If you're not comfortable moving and editing these files, then instead use the standard upgrade method for your platform described in [Upgrading PingFederate](#) on page 138.

If your installation includes a cluster, perform the following procedure on each node starting with the administrative console node.

Steps

1. Go to the [PingFederate Downloads](#) page on the Ping Identity website.
2. In the **Maintenance Update** section, download the **In-place Update (ZIP)** file and extract its contents.
3. Stop PingFederate.
4. Copy the files in the in-place update's `pingfederate` directory and paste them into their corresponding locations in your current PingFederate installation, replacing the old files.  
For example, if the in-place update contains `pingfederate/server/default/lib/pf-protocolengine.jar`, copy the `pf-protocolengine.jar` file to the same location in your PingFederate installation: `<pf_install>/pingfederate/server/default/lib`.
5. Compare each file in the in-place update's `merge_required` directory with the version of the file in your current PingFederate installation and manually merge the changes into the file in your current installation.  
For example, if the in-place update contains `merge_required/pingfederate/server/default/conf/language-packs/pingfederate-messages.properties`, copy the changes

in the new version into the `pingfederate-messages.properties` file in your PingFederate installation.

6. Start PingFederate.

## Getting Started with PingFederate

---

This guide provides information about configuring PingFederate to deploy a secure Internet-identity platform, including single sign-on (SSO), based on the latest security and business standards.

### Starting and stopping PingFederate

---

Depending on the application mode and the operating system, the steps to start, stop, or restart PingFederate vary.

If you install or upgrade PingFederate using its platform-specific installer, PingFederate configures to run as a service. You can stop and disable the service and run PingFederate as a console application.

If you install or upgrade PingFederate manually by using the PingFederate product distribution file or the Upgrade Utility in command line, you can run PingFederate as a console application or install the PingFederate service manually and run it as a service.

### Starting and stopping PingFederate on Windows

#### Steps

- To start PingFederate on Windows, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Open a command prompt.
    2. Go to `<pf_install>/pingfederate/bin`.
    3. Run `run.bat`.
    4. Keep the command prompt open.
  - If PingFederate was installed as a Windows service:
    1. Go to **Control Panel # System and Security # Administrative Tools # Services**.
    2. Right-click on the PingFederate service and click **Start**.
- To stop PingFederate on Windows, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Locate the command prompt running PingFederate.
    2. Press CTRL+C to terminate PingFederate.
  - If PingFederate was installed as a Windows service:
    1. Go to **Control Panel # Administrative Tools # Services**.
    2. Right-click on the PingFederate service and click **Stop**.



- To restart PingFederate on Windows, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Locate the command prompt running PingFederate.
    2. Press CTRL+C to terminate PingFederate.
    3. When PingFederate stops, run `run.bat`.
    4. Keep the command prompt open.
  - If PingFederate was installed as a Windows service:
    1. Go to **Control Panel # Administrative Tools # Services**.
    2. Right-click on the PingFederate service and select **Restart**.

## Starting and stopping PingFederate on Linux

### Steps

- To start PingFederate on Linux, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Open a terminal window.
    2. Go to `<pf_install>/pingfederate/bin`.
    3. Run `run.sh`.
    4. Keep the terminal window open.
  - If PingFederate was installed as a service:
    1. Open a terminal window.
    2. Enter the system-dependent service command to start PingFederate.
- To stop PingFederate on Linux, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Locate the terminal window running PingFederate.
    2. Press CTRL+C to terminate PingFederate.
  - If PingFederate was installed as a service:
    1. Open a terminal window.
    2. Enter the system-dependent service command to stop PingFederate.
- To restart PingFederate on Linux, do one of the following:  
Choose from:
  - If PingFederate was installed as a console application:
    1. Locate the terminal window that is running PingFederate.
    2. Press CTRL+C to terminate PingFederate.
    3. When PingFederate stops, run `run.sh`.
    4. Keep the terminal window open.
  - If PingFederate was installed as a service:
    1. Open a terminal window.
    2. Enter the system-dependent service command to restart PingFederate.

## Opening the PingFederate administrative console

---

The PingFederate administrative console provides a wizard-like interface in which you configure your federation use cases.

About this task

To open the administrative console:

Steps

1. Start PingFederate. See [Starting and stopping PingFederate](#) on page 168.  
In a clustered PingFederate environment, start PingFederate on the console node.
2. Start a web browser.
3. Go to `https://<pf_host>:9999/`.



**Note:**

For PingFederate 10.1 and earlier, the administrative console is accessed at `https://<pf_host>:9999/pingfederate/app`.

`<pf_host>` is the network address of your PingFederate server. It can be an IP address, a host name, or a fully qualified domain name. It must be reachable from your computer.

9999 is the default value of the `pf.admin.https.port` property in the `run.properties` file.

## Setting up PingFederate

---

After [installing PingFederate](#), use the PingFederate setup wizard to configure the necessary initial settings.

About this task

The setup wizard guides you through the following steps:

1. Agree to the Terms and Conditions.
2. Enter the base URL used for communicating with your PingFederate environment.
3. Connect to PingOne. You can do this step later. For more information, see [Creating connections to PingOne](#) on page 998.
4. Upload your PingFederate license.
5. Create an administrator account.
6. Review and finish.



**Note:**


The wizard appears every time you open the PingFederate administrative console until you complete your initial setup.

If you exit the wizard before completing the setup, none of your information is saved.

Steps

1. Start the PingFederate server. For more information, see [Starting and stopping PingFederate](#) on page 168


- In your browser, go to `https://<pf_host>:9999/pingfederate/app`. The setup wizard opens.

 **Note:**

`<pf_host>` is the network address of your PingFederate server. It can be an IP address, a host name, or a fully qualified domain name. It must be reachable from your computer.

9999 is the default value of the `pf.admin.https.port` property in the `run.properties` file.

- Follow the instructions in the wizard.

 **Note:**

Click **Back** to return to a previous step.

Click **X** and close the browser tab to cancel your setup process.


Click **Restart** to start again from the beginning.



Result: After you complete the setup wizard's steps, the PingFederate administrative console opens. You can continue configuring PingFederate.






## PingFederate administrative console

The PingFederate administrative console provides windows and a wizard-like interface in which you configure your federation use cases.

The toolbar at the top of the administrative console provides controls mainly for navigating PingFederate. For more information about navigating PingFederate, see [Navigation tabs and menus](#) on page 172.



| Toolbar control   | Description  |
|---|--|
| PingOne home button  | If PingFederate is integrated with PingOne, this button opens the PingOne unified admin console.<br><br> <b>Note:</b><br>Configure the region and environment ID for your PingOne unified admin URL in the <code>run.properties</code> file, see <a href="#">Configuring PingFederate properties</a> on page 820. |
| PingFederate home link  | Opens the PingFederate administrative console's home window  |
| Authentication tab  | Opens the Authentication navigation window, which offers a menu pane and a shortcut pane   |

| Toolbar control  | Description  |
|--|--|
| Applications tab   | Opens the Applications navigation window, which offers a menu pane and a shortcut pane   |
| Security tab   | Opens the Security navigation window, which offers a menu pane and a shortcut pane   |
| System tab   | Opens the System navigation window, which offers a menu pane and a shortcut pane   |
| Search icon     | Opens a dialog box that lets you search for and open PingFederate windows  |
| Bell icon       | When a dot appears on the icon, clicking the icon opens a message about an important administrative issue. The messages also provide a link to the window where you can resolve the issue. |
|  |  <b>Note:</b><br>Some critical notifications appear on a banner above the toolbar.                        |
| Help icon      | Opens the Help menu, which provides access to context-sensitive online help, a tour of the console, endpoint information, and information about your version and license                   |
| Account icon  | Lets you sign on to, and off from, your PingFederate account   |

## Navigation tabs and menus

The PingFederate administrative console provides navigation tabs and menus. When you select a tab at the top of the console, the relevant menus appear on the left menu pane. When you select a menu, the menu items appear. When you select a menu item, the window with the same name appears. The menus and menu items depend on your permissions in PingFederate. For more information about permissions, see [Administrative accounts](#) on page 914.

### Each navigation tab provides access to multiple menus on the left menu pane

| Menus on the Authentication tab  | Menus on the Applications tab  | Menus on the Security tab  | Menus on the System tab   |
|--|--|--|---|
| <ul style="list-style-type: none"> <li>▪ Integration</li> <li>▪ Policies</li> <li>▪ OAuth</li> <li>▪ Token Exchange</li> </ul> | <ul style="list-style-type: none"> <li>▪ Integration</li> <li>▪ OAuth</li> <li>▪ Token Exchange</li> </ul> | <ul style="list-style-type: none"> <li>▪ Certificate &amp; Key Management</li> <li>▪ System Integration</li> </ul> | <ul style="list-style-type: none"> <li>▪ Data &amp; Credential Stores</li> <li>▪ Server</li> <li>▪ OAuth Settings</li> <li>▪ External Systems</li> <li>▪ Monitoring &amp; Notifications</li> <li>▪ Protocol Metadata</li> </ul> |

**Navigation tabs, menus, and menu items in alphabetical order**

| <b>Tabs</b>               | <b>Menus</b>                 | <b>Menu items and window names</b>       |
|---------------------------|------------------------------|--|
| Applications              | Integration                  | Adapter-to-Adapter Mappings              |
|                           |                              | Policy Contract Adapter Mappings         |
|                           |                              | SP Adapters                              |
|                           |                              | SP Connections                           |
|                           |                              | SP Default URLs                          |
|                           |                              | Target URL Mapping                       |
|                           | OAuth                        | Access Token Management                  |
|                           |                              | Access Token Mappings                    |
|                           |                              | CIBA Request Policies                    |
|                           |                              | Clients                                  |
|                           |                              | OpenID Connect Policy Management         |
|                           | Token Exchange               | Generator Groups                         |
|                           |                              | Processor Policies                       |
|                           |                              | Token Generator Mappings                 |
|                           |                              | Token Generators                         |
| Token Translator Mappings |                              |  |
| Authentication            | Integration                  | Authentication API Applications          |
|                           |                              | IdP Adapters                             |
|                           |                              | IdP Connections                          |
|                           |                              | IdP Default URL                          |
|                           | OAuth                        | CIBA Authenticators                      |
|                           |                              | IdP Adapter Grant Mapping                |
|                           |                              | Policy Contract Grant Mapping            |
|                           |                              | Resource Owner Credentials Grant Mapping |
|                           | Policies                     | Fragments                                |
|                           |                              | Local Identity Profiles                  |
|                           |                              | Policies                                 |
|                           |                              | Policy Contracts                         |
|                           |                              | Selectors                                |
|                           |                              | Sessions                                 |
|                           | Token Exchange               | STS Request Parameters                   |
| Token Processors          |                              |  |
| Security                  | Certificate & Key Management | Certificate Revocation Checking          |

| Tabs                   | Menus                      | Menu items and window names              |
|------------------------|----------------------------|--|
|                        |                            | OAuth & OpenID Connect Keys              |
|                        |                            | Partner Metadata URLs                    |
|                        |                            | Signing & Decryption Keys & Certificates |
|                        |                            | SSL Client Keys & Certificates           |
|                        |                            | SSL Server Certificates                  |
|                        |                            | System Keys                              |
|                        |                            | Trusted CAs                              |
|                        | System Integration         | Incoming Proxy Settings                  |
|                        |                            | Redirect Validation                      |
| Service Authentication |                            |  |
| System                 | Data & Credential Stores   | Active Directory Domains/Kerberos Realms |
|                        |                            | Data Stores                              |
|                        |                            | Identity Store Provisioners              |
|                        |                            | Password Credential Validators           |
|                        | External Systems           | CAPTCHA Settings                         |
|                        |                            | Connect to PingOne for Enterprise        |
|                        |                            | Notification Publishers                  |
|                        |                            | PingOne Connections                      |
|                        |                            | SMS Provider Settings                    |
|                        | Monitoring & Notifications | Runtime Notifications                    |
|                        |                            | Runtime Reporting                        |
|                        | OAuth Settings             | Authorization Server Settings            |
|                        |                            | Client Registration Policies             |
|                        |                            | Client Settings                          |
|                        |                            | Scope Management                         |
|                        | Protocol Metadata          | Attribute Requester Mapping              |
|                        |                            | File Signing                             |
|                        |                            | Metadata Export                          |
|                        |                            | Metadata Settings                        |
|                        |                            | SP Affiliations                          |
|                        | Server                     | Administrative Accounts                  |
|                        |                            | Cluster Management                       |
|                        |                            | Configuration Archive                    |
| Extended Properties    |                            |  |

| Tabs | Menus | Menu items and window names |
|------|-------|-----------------------------|
|      |       | General Settings            |
|      |       | License                     |
|      |       | Virtual Host Names          |

## Customizing shortcuts

Shortcuts allow you to access specific locations within the PingFederate administrative console immediately. You can customize which shortcuts you want to use by opening the **Shortcuts** customization menu available on the PingFederate main window.

About this task

Shortcuts are available for all PingFederate roles. You can customize up to ten shortcuts.

Steps

1. Click the **Pencil** icon beside **Shortcuts** to open the Shortcuts customization menu. The currently configured shortcuts are shown in the upper pane.
2. You can perform the following tasks.
  - To remove a current shortcut, click its icon in the upper pane. When you do this, the icon is displayed underneath **Recently Used**. Click the icon if you want to move it back to the list of current shortcuts.
  - To rearrange the current shortcuts, click and drag them to different positions in the upper pane.
  - To view the shortcuts that are available in every navigation section of the administrative console, click **Authentication**, **Applications**, **Security**, and **System**. Click a shortcut's icon or drag it into the upper pane to add it to the list of current shortcuts.
  - To restore the default shortcut settings, click **Restore Default**.
3. When you have finished customizing your shortcuts, click **Save**.

## Tasks and steps

Each task consists of a series of tabs. Each tab consists of a sequence of steps. The tasks and tabs appear in the top portion of the window.

## Sample tasks and steps

In this example, the primary task is managing one or more IdP adapter instances (**IdP Adapters**). The secondary task is creating an adapter instance (**Create Adapter Instance**). The current tab selects the type of adapter (**Type**). The subsequent tabs, which the administrator has not yet reached, are grayed out.

The administrator console displays a summary window at the end of every task, which offers the opportunity to review and make changes as needed.

Some steps provide buttons that branch to secondary tasks with multiple tabs. When the secondary tasks are complete, the administrative console returns to the primary task for the administrators to continue with the configuration.



#### Note:

Clicking **Cancel** or **Done** discards all unsaved changes for the tabs shown in the current task and returns you to the window from which you accessed the task.

#### Example

When creating a connection to a partner, the administrator might need to create a new digital signing certificate. The administrative console provides a button to begin creating a new signing certificate. When the administrator completes the task, the administrative console returns to the primary task of creating a connection to a partner.

## Console buttons

The buttons at the bottom of the administrative console change depending on where you are in the configuration process.

The following table describes these buttons.

| Button            | Description  |
|-------------------|--|
| <b>Save</b>       | Saves changes for all tabs in the current task and returns to the window from which the task or tab was accessed. This button is available only when the <b>Save</b> operation is valid.   |
| <b>Done</b>       | Marks all steps as complete for a current task, but does not save the configuration because further tasks or steps are necessary. To save your changes, click <b>Save</b> , or continue the configuration until you see a <b>Save</b> button. When creating a new service provider (SP) or identity provider (IdP) connection, click <b>Save Draft</b> . |
| <b>Save Draft</b> | Saves a connection's draft configuration.  |
| <b>Cancel</b>     | Discards all changes and returns to the window from which the current task was accessed.   |
| <b>Previous</b>   | Returns to the previous tab.   |
| <b>Next</b>       | Proceeds to the next tab if all required steps are complete in the current tab.  |



#### CAUTION:

Do not use the browser's **Back**, **Forward**, or **Refresh** buttons. Always use the navigation buttons in the PingFederate user interface, **Previous**, **Next**, or **Done**.



## Third-party cryptographic solutions

---

PingFederate can use third-party hardware and software cryptographic solutions.

You can configure to use a hardware security module (HSM) for cryptographic material storage and operations. When configured, private keys and their corresponding certificate are stored on the HSM. Related signing and decryption operations are processed there for enhanced security.

You can also integrate PingFederate with a third-party software cryptographic solution.

### Hardware security modules

When integrating with an HSM, PingFederate must be deployed with Oracle Server JRE 8. Oracle Java SE Development Kit 11 and OpenJDK 11 are not supported.

Typically, integrating with an HSM involves two steps:

1. Install and configure the HSM according to the manufacturer's documentation.
2. Follow the vendor-specific instructions to configure a new or existing PingFederate environment to use the HSM for key generation, storage, and operation.



#### Tip:

Use HSM hybrid mode to store each relevant key and certificate on the HSM or the local trust store. This allows you to transition the storage of keys and certificates to an HSM without needing to deploy a new PingFederate environment to mirror the setup. For more information, see [Transitioning to an HSM](#) on page 685.



#### Note:

Configuring PingFederate to use an HSM for cryptographic material storage and operations might impact performance. The level of impact depends on the performance of cryptographic functionality provided by the HSM and the network latency between PingFederate and the HSM. Consult with your HSM vendor for performance tuning if you plan to use an HSM in your PingFederate deployment.

### Software cryptographic solution

PingFederate supports Bouncy Castle FIPS as the provider of its Java keystore and cryptographic operations.

## Supported hardware security modules

PingFederate supports multiple configurations for secure material storage and processing.

PingFederate supports the following modules:

- AWS CloudHSM
- Thales Luna Network HSM
- Entrust nShield Connect HSM

### Integrating with AWS CloudHSM

PingFederate supports multiple hardware security modules (HSMs), including AWS CloudHSM.

Before you begin

Ensure Oracle Server JRE 8 is installed on the PingFederate server. For more information, see [Installing Java](#) on page 129.

Additionally, must be deployed on one of the Linux operating systems supported by both AWS CloudHSM and . For more information, see [System requirements](#) on page 119 and [Install and Configure the AWS CloudHSM Client \(Linux\)](#) in the AWS CloudHSM documentation.

## Steps

1. Request a crypto user (CU) account from your AWS CloudHSM administrator.



### Note:

You need this account's username and password for your PingFederate installation.

2. Install and configure your AWS CloudHSM client and tools.



### Note:

Commands vary depending on the operating system. For more information, see [Install the AWS CloudHSM Client and Command Line Tools](#) in the AWS CloudHSM documentation.

3. Install the AWS CloudHSM software library for Java.



### Note:

Commands vary depending on the Linux operating system. For instructions, see [Installing Java Library](#) in the AWS CloudHSM documentation.

4. Validate the AWS CloudHSM client installation.
  - a. Using the command line, export four environment variables.

```
$ export LD_LIBRARY_PATH=/opt/cloudhsm/lib
$ export HSM_PARTITION=PARTITION_1
$ export HSM_USER=<HSM username>
$ export HSM_PASSWORD=<password>
```

- b. To validate the AWS CloudHSM client installation, run the following Java program.

```
$ java -classpath "/opt/cloudhsm/java/*" org.junit.runner.JUnitCore
TestBasicFunctionality
```

### Result:

The result should be similar to the following output.

```
JUnit version 4.12
.2020-02-24 16:17:01,681 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:33) - Adding provider.
2020-02-24 16:17:01,749 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:42) - Logging in.
2020-02-24 16:17:01,749 INFO [main] cfm2.LoginManager
  (LoginManager.java:238) - Looking for credentials in
  HsmCredentials.properties
2020-02-24 16:17:01,750 INFO [main] cfm2.LoginManager
  (LoginManager.java:256) - Looking for credentials in
  System.properties
2020-02-24 16:17:01,750 INFO [main] cfm2.LoginManager
  (LoginManager.java:264) - Looking for credentials in System.env
2020-02-24 16:17:01,784 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:54) - Generating AES Key with key size
  256.
```

```
2020-02-24 16:17:01,995 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:63) - Encrypting with AES Key.
2020-02-24 16:17:02,005 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:84) - Deleting AES Key.
2020-02-24 16:17:02,006 DEBUG [main] TestBasicFunctionality
  (TestBasicFunctionality.java:92) - Logging out.
```

```
Time: 0.334
```

```
OK (1 test)
```

For more information, see [Validating the Installation](#) in the AWS CloudHSM documentation.

5. Update the `JAVA_HOME/jre/lib/security/java.security` file in your Java environment, and then add the `AWSCloudHSMProvider` line to the list of security providers immediately after the `sun.security.provider.Sun` provider.

Example:

```
# List of providers and their preference orders (see above):
security.provider.1=sun.security.provider.Sun
security.provider.2=com.pingidentity.crypto.AWSCloudHSMProvider
security.provider.3=sun.security.rsa.SunRsaSign
security.provider.4=sun.security.ec.SunEC
security.provider.5=com.sun.net.ssl.internal.ssl.Provider
security.provider.6=com.sun.crypto.provider.SunJCE
security.provider.7=sun.security.jgss.SunProvider
security.provider.8=com.sun.security.sasl.Provider
security.provider.9=org.jcp.xml.dsig.internal.dom.XMLDSigRI
security.provider.10=sun.security.smartcardio.SunPCSC
```

6. Configure a new PingFederate installation on the network interconnected to the HSM.



**Note:**

Go to the next step to integrate an existing PingFederate installation with your HSM.

7. To enable the Java interface and PingFederate integration, copy the following files to the `JAVA_HOME/jre/lib/ext` directory:

- `<pf_install>/pingfederate/lib-ext/pf-aws-cloud-hsm-wrapper.jar`
- `<pf_install>/pingfederate/server/default/lib/disruptor.jar`
- All files under the `/opt/cloudhsm/java` directory
- All files under the `/opt/cloudhsm/lib` directory

8. Update the `hivemodule.xml` file.

- a. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
- b. Go to the `<!-- Crypto provider -->` section.
- c. Update the `class` attribute value of the `construct` element for both the `JCEManager` and `CertificateService` service endpoint.

```
...
<!-- Crypto provider -->
<service-point id="JCEManager"
  interface="com.pingidentity.crypto.JCEManager">
  <invoke-factory>
    ...
    <construct class="com.pingidentity.crypto.AWSCloudHSMJCEManager" />
  </invoke-factory>
</service-point>
```

```

<service-point id="CertificateService"
  interface="com.pingidentity.crypto.CertificateService">
  <invoke-factory>
    ...
    <construct
      class="com.pingidentity.crypto.AWSCloudHSMCertificateServiceImpl"/>
    </invoke-factory>
  </service-point>
  ...

```

9. Update the `<pf_install>/pingfederate/bin/run.properties` file.
  - a. Change the value of the `pf.hsm.mode` property from `OFF` to `AWSCLOUDHSM`.
  - b. If you are setting up a new PingFederate installation, set the value of the `pf.hsm.hybrid` property to `false` to store newly-created or imported certificates on your HSM.
  - c. If you are configuring an existing PingFederate installation, set the value to `true` for the flexibility to store each relevant key and certificate on the HSM or the local trust store.

This allows you to transition the storage of keys and certificates to your HSM without deploying a new PingFederate environment. For more information, see [Transitioning to an HSM](#) on page 685.

10. Run the `<pf_install>/pingfederate/bin/hsmypass.sh` script for Linux.
  - a. Enter the password for the CU account when prompted. See [step 1](#).  
This procedure securely stores the password for communication to the HSM from PingFederate.

11. If the username of the CU account is not `crypto_user`, update the `com.pingidentity.crypto.AWSCloudHSM.xml` file.

- a. Edit the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.AWSCloudHSM.xml` file.

The unmodified version of the `com.pingidentity.crypto.AWSCloudHSM.xml` file follows.

```

<?xml version="1.0" encoding="UTF-8"?>
<con:config xmlns:con="http://www.sourceid.org/2004/05/config">
  <con:item name="Partition">PARTITION_1</con:item>
  <con:item name="CryptoUser">crypto_user</con:item>
</con:config>

```

- b. Replace `crypto_user` with the username of the CU account.

Example:

In the following example, the username of the CU account is `example_user`.

```

<?xml version="1.0" encoding="UTF-8"?>
<con:config xmlns:con="http://www.sourceid.org/2004/05/config">
  <con:item name="Partition">PARTITION_1</con:item>
  <con:item name="CryptoUser">example_user</con:item>
</con:config>

```

12. Repeat these steps on each node.
13. Start the new PingFederate server or restart the existing PingFederate server.

### AWS CloudHSM operational notes

When using a hardware security module (HSM), some restrictions apply to PingFederate.

- PingFederate requires Oracle Server JRE (Java SE Runtime Environment) 8 or Amazon Corretto 8 for deployment.
- PingFederate does not store public certificates on the hardware module for signature verification, encryption, and back-channel authentication. Instead, the local trust store on the file system stores these certificates.

- As an OpenID Provider, can use static or dynamically-rotating keys to sign ID tokens, JSON web tokens (JWTs) for client authentication, and OpenID Connect request objects. When using dynamically-rotating keys as part of the default configuration, the memory, not the HSM, stores short-term keys. The HSM can store static keys.
- Private keys are not exportable. When configured for use with the HSM, disables administrative-console options for this feature. Only the public portion of generated keys is exportable.
- When using the Configuration Archive feature, any keys, certificates, or objects generated and stored on the HSM prior to saving a configuration archive must continue to exist unaltered when the archive is restored. In other words, the user interface must execute any deletion or creation of objects on the HSM for proper operation.

For example, you create and save objects A, B, and C to the HSM and create a data archive that contains references to those objects. If you delete object C and attempt to recover it through the data archive, fails. Because the data archive contains a reference to the object and the object has been deleted from the HSM, you cannot use that data archive again.

- PingFederate limits cipher suites to those listed in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.AWSCloudHSMJCEManager.xml` file.



#### Note:

If the CloudHSM client daemon disconnects during runtime, PingFederate automatically attempts to reconnect to the daemon.

### Integrating with Thales Luna Network HSM

PingFederate supports multiple hardware security modules (HSMs), including Thales Luna Network HSMs.

#### Steps

1. Ensure that the PingFederate server has a supported Java virtual machine (JVM) installed.  
For more information, see [Installing Java](#).
2. Install and configure your Thales Luna Network HSM, including the optional JSP package for Java, according to Thales's instructions.  
This includes creating a partition, creating a Network Trust Link (NTL), and assigning a client to a partition.
  - a. Ensure the operation of the `vtl verify` command to indicate secure and proper communication with the HSM.
  - b. Delete any unnecessary keys or objects created while testing communication to the HSM from the host running PingFederate.
  - c. For your PingFederate installation, record the password used to open communication to the HSM through the NTL.
3. To enable the Java interface, copy the Luna library and program files to the Java installation as follows.

| Operating system | Steps  |
|------------------|--|
| Windows          | Copy the <code>LunaAPI.dll</code> and <code>LunaProvider.jar</code> files from the <code>LUNA_HOME/jsp/lib</code> directory to the <code>&lt;pf_install&gt;/pingfederate/startup</code> directory. |

| Operating system | Steps  |
|------------------|--|
| Linux            | Copy the <code>libLunaAPI.so</code> and <code>LunaProvider.jar</code> files from the <code>LUNA_HOME/jsp/lib</code> directory to the <code>&lt;pf_install&gt;/pingfederate/startup</code> directory. |

Prior to installing PingFederate, Thales provides sample Java applications to test that the Java HSM interface works. For more information, see the HSM documentation from Thales.

4. Update the `java.security` file in your Java environment by inserting `LunaProvider` after `SunJCE`, and then moving `SunRsaSign` and `SunEC` below `LunaProvider`. Ensure that the providers are numbered sequentially after your changes.
  - If the node uses Java 8, the `java.security` file is in the `JAVA_HOME/jre/lib/security` directory. Here's an example of an updated file for Java 8:

```
# List of providers and their preference orders (see above):
security.provider.1=sun.security.provider.Sun
security.provider.2=com.sun.net.ssl.internal.ssl.Provider
security.provider.3=com.sun.crypto.provider.SunJCE
security.provider.4=com.safenetinc.luna.provider.LunaProvider
security.provider.5=sun.security.rsa.SunRsaSign
security.provider.6=sun.security.ec.SunEC
security.provider.7=sun.security.jgss.SunProvider
security.provider.8=com.sun.security.sasl.Provider
security.provider.9=org.jcp.xml.dsig.internal.dom.XMLDSigRI
security.provider.10=sun.security.smartcardio.SunPCSC
```

- If the node uses Java 11, the `java.security` file is in the `JAVA_HOME/conf/security` directory. Here's an example of an updated file for Java 11:

```
# List of providers and their preference orders (see above):
security.provider.1=SUN
security.provider.2=SunRsaSign
security.provider.3=SunEC
security.provider.4=SunJSSE
security.provider.5=SunJCE
security.provider.6=com.safenetinc.luna.provider.LunaProvider
security.provider.7=SunJGSS
security.provider.8=SunSASL
security.provider.9=XMLDSig
security.provider.10=SunPCSC
security.provider.11=JdkLDAP
security.provider.12=JdkSASL
security.provider.13=SunPKCS11
```

5. On the network interconnected to the HSM, set up a new PingFederate installation.



**Note:**

To integrate an existing PingFederate installation with your HSM, skip to the next step.

6. Update the `hivemodule.xml` file.
  - a. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - b. Go to the `<!-- Crypto provider -->` section.
  - c. Update the `class` attribute value of the `construct` element for both the `JCEManager` and `CertificateService` service endpoint as follows.

...

```

<!-- Crypto provider -->
<service-point id="JCEManager"
  interface="com.pingidentity.crypto.JCEManager">
  <invoke-factory>
    ...
    <construct class="com.pingidentity.crypto.LunaJCEManager"/>
  </invoke-factory>
</service-point>

<service-point id="CertificateService"
  interface="com.pingidentity.crypto.CertificateService">
  <invoke-factory>
    ...
    <construct
      class="com.pingidentity.crypto.LunaCertificateServiceImpl"/>
  </invoke-factory>
</service-point>
...

```

7. In `com.pingidentity.crypto.LunaPartitions.xml`, configure `DefaultPartitionSlotOrLabel` with the slot number or label associated with the HSM partition you created in [step 2](#).
8. Update the `<pf_install>/pingfederate/bin/run.properties` file.
  - a. Change the value of `pf.hsm.mode` from `OFF` to `LUNA`.
  - b. To configure a new PingFederate installation, set the value of `pf.hsm.hybrid` to `false`. When set to `false`, the HSM stores newly created or imported certificates.
 

To configure an existing PingFederate installation, set the value to `true` for the flexibility to store each relevant key and certificate on the HSM or the local trust store. This allows you to transition the storage of keys and certificates to your HSM without deploying a new PingFederate environment. For more information, see [Transitioning to an HSM](#) on page 685.
9. From the `<pf_install>/pingfederate/bin` directory, run the `hsmpass.bat` batch file for Windows or the `hsmpass.sh` script for Linux.
  - a. Enter the NTL password when prompted. For more information, see [step 2](#).

This procedure securely stores the password for NTL communication to the HSM from PingFederate.

 **Note:**

The Thales Luna Network HSM supports configuration in a high-availability group. For more information, see the Thales distributed-installation instructions. To properly synchronize data, ensure that the `HAOnly` property is enabled using the `vt1 haAdmin -HAOnly -enable` command.

10. Repeat these steps on each node.
11. Start the new PingFederate server or restart the existing PingFederate server.

 **Important:**

Whenever you restart the Luna HSM, Thales recommends you also restart dependent processes such as PingFederate and all server nodes in a cluster.

### SafeNet Luna Network HSM operational notes

When using a hardware security module (HSM), some restrictions apply to PingFederate.

- PingFederate does not store public certificates on the hardware module for signature verification, encryption, and back-channel authentication. Instead, the local trust store on the file system stores these certificates.
- As an OpenID Provider, can use static or dynamically-rotating keys to sign ID tokens, JSON web tokens (JWTs) for client authentication, and OpenID Connect request objects. When using dynamically-rotating keys as part of the default configuration, the memory, not the HSM, stores short-term keys. The HSM can store static keys.
- Private keys are not exportable. When configured for use with the HSM, disables administrative-console options for this feature. Only the public portion of generated keys is exportable.
- When running in FIPS 140-2 level 3 compliance, also called strict FIPS mode, private keys cannot be imported. In this mode, administrative-console options for this feature are disabled.
- When using the Configuration Archive feature, any keys, certificates, or objects generated and stored on the HSM prior to saving a configuration archive must continue to exist unaltered when the archive is restored. In other words, the user interface must execute any deletion or creation of objects on the HSM for proper operation.

For example, you create and save objects A, B, and C to the HSM and create a data archive that contains references to those objects. If you delete object C and attempt to recover it through the data archive, fails. Because the data archive contains a reference to the object and the object has been deleted from the HSM, you cannot use that data archive again.

- PingFederate limits cipher suites to those listed in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.LunaJCEManager.xml` file.

### Integrating with Entrust nShield Connect HSM

PingFederate supports multiple hardware security modules (HSMs), including Entrust nShield Connect HSM.

#### Steps

1. Ensure the PingFederate server has Oracle Server JRE 8 installed.  
For more information, see [Installing Java](#) on page 129.
2. Install and configure your Entrust nShield Connect HSM client software.  
As part of the installation, install the optional Java Support (including KeySafe) and nCipherKM JCA/JCE provider classes components.
3. After your installation, see the HSM documentation from Entrust to make your PingFederate server a client of an HSM server.



#### Note:

PingFederate supports both Operator Card Set (OCS) protected keys and module-protected keys.

For OCS, note the password. You need the password for your installation of PingFederate.

For module-protected keys, edit the `pingfederate/server/default/data/config-store/com.pingidentity.crypto.NCipherSettings.xml` file to add the following entries:

```
<con:item name="protect">module</con:item>
<con:item name="ignorePassphrase">>true</con:item>
```

4. To enable the Java interface, copy the `NFAST_HOME/java/classes/nCipherKM.jar` file to the `JAVA_HOME/jre/lib/ext` directory.  
Prior to installing PingFederate, Entrust offers sample Java applications to test that the Java HSM interface works. For more information, refer to the HSM documentation from Entrust.



5. Update the `JAVA_HOME/jre/lib/security/java.security` file in your Java environment and add the `nCipherKM` line to the list of security providers, after the `sun` providers.

```
# List of providers and their preference orders (see above):
security.provider.1=sun.security.provider.Sun
security.provider.2=sun.security.rsa.SunRsaSign
security.provider.3=sun.security.ec.SunEC
security.provider.4=com.sun.net.ssl.internal.ssl.Provider
security.provider.5=com.sun.crypto.provider.SunJCE
security.provider.6=sun.security.jgss.SunProvider
security.provider.7=com.sun.security.sasl.Provider
security.provider.8=org.jcp.xml.dsig.internal.dom.XMLDSigRI
security.provider.9=sun.security.smartcardio.SunPCSC
security.provider.10=sun.security.mscapi.SunMSCAPI
security.provider.11=com.ncipher.provider.km.nCipherKM
```

6. Set up a new PingFederate installation on the network interconnected to the HSM.



**Important:**

Skip to the next step to integrate an existing PingFederate installation with your HSM.

7. Update the `hivemodule.xml` file.
  - a. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - b. Look for the `<!-- Crypto provider -->` section.
  - c. Update the `class` attribute value of the `construct` element for both the `JCEManager` and `CertificateService` service endpoint.

```
...
<!-- Crypto provider -->
<service-point id="JCEManager"
  interface="com.pingidentity.crypto.JCEManager">
  <invoke-factory>
    ...
    <construct class="com.pingidentity.crypto.NcipherJCEManager"/>
  </invoke-factory>
</service-point>

<service-point id="CertificateService"
  interface="com.pingidentity.crypto.CertificateService">
  <invoke-factory>
    ...
    <construct class="com.pingidentity.crypto.NcipherCertificateServiceImpl"/>
  </invoke-factory>
</service-point>
...
```

8. Update the `<pf_install>/pingfederate/bin/run.properties` file.
  - a. Change the value of `pf.hsm.mode` from `OFF` to `NCIPHER`.
  - b. If you are configuring a new PingFederate installation, set the value of `pf.hsm.hybrid` to `false` to store newly created or imported certificates on your HSM.
  - c. If you are configuring an existing PingFederate installation, set the value to `true`, which provides the flexibility to store each relevant key and certificate on the HSM or the local trust store. This capability allows you to transition the storage of keys and certificates to your HSM without the need to deploy a new PingFederate environment and to mirror the setup. For more information, see [Transitioning to an HSM](#) on page 685.

9. From the `<pf_install>/pingfederate/bin` directory, run the `hsmypass.bat` batch file for Windows or the `hsmypass.sh` script for Linux.

Enter the Operator Card Set password when prompted. See [step 3](#).

This procedure securely stores the password for communication to the HSM from PingFederate.

10. If you are setting up a new or configuring an existing PingFederate cluster, repeat these steps on each node.

When finished, use the following steps to replicate nShield data to the connected nodes in the cluster.

- a. On the console node, go to the `<pf_install>/pingfederate/server/default/data` directory and create a sub directory named `ncipher-kmdata-local`.
- b. Copy to the `ncipher-kmdata-local` directory all files from the `NFAST_KMDATA\local` directory, where `NFAST_KMDATA` is an environment variable created during the nShield Connect installation.

For example, `NFAST_KMDATA` could be set to `C:\ProgramData\NCipher\Key Management Data`.

- c. Create a new environment variable named `NFAST_KMLOCAL` and set it to `<pf_install>/pingfederate/server/default/data/ncipher-kmdata-local`.

 **Note:**

You must define this environment variable on all servers within the cluster.

- d. Restart the nShield Connect hardserver on all PingFederate servers in the cluster. For instructions on restarting the hardserver, see the HSM documentation from Entrust.
  - e. Sign on to the PingFederate administrative console and go to **System # Server # Cluster Management**.
  - f. To push the configuration changes, including the nShield data, to the engine nodes, click **Replicate Configuration**.
11. Start the new PingFederate server or restart the existing PingFederate server.

 **Important:**

Whenever you restart the nShield HSM, restart PingFederate and all server nodes in a cluster.

### nShield Connect HSM operational notes

Some restrictions apply to PingFederate when using a hardware security module (HSM).

- PingFederate requires Oracle Server JRE (Java SE Runtime Environment) 8 or Amazon Corretto 8 for deployment.
- When integrating PingFederate with Entrust nShield Connect on a platform with Oracle Server JRE 8u102, runtime errors might occur when handling certificates with a signing algorithm of RSA SHA256, SHA384, or SHA512. To resolve these runtime errors, upgrade to Oracle Server JRE 8u112.
- PingFederate only supports Operator Card Set (OCS) protected keys. If you use a standard, non-persistent OCS, removing the card from the smart card reader causes the HSM to remove the protected keys from its memory. Requests will likely fail because almost all requests require cryptographic processing. To resume operations, insert the card into the smart card reader and then restart PingFederate.

Alternatively, use a persistent OCS so that protected keys remain in memory even after the card is removed from the smart card reader. PingFederate will continue to process requests and to load keys and certificates from the HSM as needed. Until the card is inserted back into the HSM, the HSM will not support new key and certificate creation and storage. However, using a persistent OCS does not require a restart of PingFederate in this situation. For more information about persistent OCS, consult your HSM vendor.

- As an OpenID Provider, can use static or dynamically-rotating keys to sign ID tokens, JSON web tokens (JWTs) for client authentication, and OpenID Connect request objects. When using dynamically-rotating keys as part of the default configuration, the memory, not the HSM, stores short-term keys. The HSM can store static keys.
- Private keys are not exportable. When configured for use with the HSM, disables administrative-console options for this feature. Only the public portion of generated keys is exportable.
- When running in FIPS 140-2 level 3 compliance, also called strict FIPS mode, private keys cannot be imported. In this mode, administrative-console options for this feature are disabled.
- When using the Configuration Archive feature, any keys, certificates, or objects generated and stored on the HSM prior to saving a configuration archive must continue to exist unaltered when the archive is restored. In other words, the user interface must execute any deletion or creation of objects on the HSM for proper operation.

For example, you create and save objects A, B, and C to the HSM and create a data archive that contains references to those objects. If you delete object C and attempt to recover it through the data archive, fails. Because the data archive contains a reference to the object and the object has been deleted from the HSM, you cannot use that data archive again.

- PingFederate limits cipher suites to those listed in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.NcCipherJCEManager.xml` file.

## Supported software security package

PingFederate supports the Bouncy Castle FIPS provider software security package.

### Integrating with Bouncy Castle FIPS provider

In Bouncy Castle FIPS mode, all security-related cryptographic operations in PingFederate are handled by the Bouncy Castle FIPS security provider. Bouncy Castle FIPS is a FIPS 140-2 validated software cryptographic module. Operating in Bouncy Castle FIPS mode may be required if PingFederate is running as part of a FedRAMP-certified cloud service.

Third-party libraries deployed in PingFederate, such as JDBC drivers, are not guaranteed to operate in a FIPS-compliant fashion. When FIPS 140-2 compliance is a goal, you should confirm with the vendor before using any third-party libraries.

Plugins such as adapters and password credential validators need to be individually assessed for FIPS compliance. The FIPS status of a plugin is displayed in the Summary page inside its configuration. A warning is also logged on start-up for any configured plugins that are not FIPS-compliant or have not yet been assessed.

The integration of Bouncy Castle FIPS provider supports two phases:

- **Hybrid** to transition private keys from default keystore to the Bouncy Castle keystore.
- **Non-Hybrid** to start storing private keys only in the Bouncy Castle keystore.

Several properties in the `<pf_install>/pingfederate/bin/run.properties` file allow you to configure these phases as shown in the following table.

| Phase      | Properties  |
|------------|---|
| Hybrid     | <code>pf.hsm.mode=BCFIPS</code><br><code>pf.hsm.hybrid=true</code>  |
| Non-Hybrid | <code>pf.hsm.mode=BCFIPS</code><br><code>pf.hsm.hybrid=false</code> |

You can run either Java 8 or 11 when integrating with the BCFIPS provider. The setup steps are the same for both environments.

**Important:**

The only way to switch from BCFIPS mode back to non-BCFIPS mode is to roll back PingFederate with an archive.

**Setting up with Java 8 or Java 11**

This procedure describes how to integrate PingFederate with Bouncy Castle FIPS provider when you are running either Java 8 or 11.

**Steps**

1. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - a. Go go the `<!--Crypto provider -->` section.
  - b. Update the class attribute value of the construct element for both the JCEManager and CertificateService service endpoint.

```
<!-- Crypto provider -->
<service-point id="JCEManager"
  interface="com.pingidentity.crypto.JCEManager">
  <invoke-factory>
    ...
    <construct class="com.pingidentity.crypto.BCFIPSJCEManager"/>
  </invoke-factory>
</service-point>

<service-point id="CertificateService"
  interface="com.pingidentity.crypto.CertificateService">
  <invoke-factory model="autoreloadable">
    ...
    <construct
      class="com.pingidentity.crypto.BCFIPSCertificateServiceImpl"/>
    </invoke-factory>
  </service-point>
  ...
```

2. Edit the `<pf_install>/pingfederate/bin/run.properties` file.
  - a. Change the `pf.hsm.mode` property to BCFIPS.
  - b. If you are setting up a new PingFederate installation, set the value of the `pf.hsm.hybrid` property to `false` to store newly created or imported certificates on your HSM.
  - c. If you are configuring an existing PingFederate installation, set the `pf.hsm.hybrid` value to `true` for the flexibility to store each relevant key and certificate on the HSM or the local trust store.
 

This allows you to transition the storage of keys and certificates to your HSM without deploying a new PingFederate environment. For more information, see [Transitioning to an HSM](#) on page 685.
3. On Linux systems, the Bouncy Castle FIPS-approved secure random number generator may drain a large amount of entropy during initial seeding. If available entropy becomes too low, the PingFederate server or bundled command-line tools may stall on startup for long periods of time. If this occurs, then you will likely need to integrate with a hardware random number generator or install an entropy-supplementing daemon like `rngd`.

**Bouncy Castle operational notes**

When using the Bouncy Castle FIPS provider, some restrictions apply to PingFederate.

- As an OpenID Provider, PingFederate can use static or dynamically rotating keys to sign ID tokens, JSON web tokens (JWTs) for client authentication, and OpenID Connect request objects. When using

dynamically rotating keys as part of the default configuration, the memory, not the BCFIPS key stores, stores short-term keys. The HSM can store static keys.

- PingFederate limits cipher suites to those listed in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.BCFIPSJCEManager.xml` file.

## Server Clustering Guide

---

This section introduces the server clustering functionality of PingFederate.

Use this guide to learn the following concepts and tasks for deploying PingFederate server clusters:

- [Overview of clustering](#) on page 189
- [Cluster protocol architecture](#) on page 191
- [Runtime state-management architectures](#) on page 192
- [Runtime state-management services](#) on page 201
- [Deploying cluster servers](#) on page 208
- [Deploying provisioning failover](#) on page 221
- [Configuration synchronization](#) on page 223

### Overview of clustering

---

Server clustering lets you define a single configuration for multiple PingFederate servers and address single sign-on (SSO) and single logout (SLO) requests as a single system.

PingFederate includes clustering features that allow a group of PingFederate servers to appear as a single system to browsers and partner federation servers. In this configuration, all client traffic normally goes through a load balancer, which routes requests to the PingFederate servers in the cluster.

Server clustering can facilitate high availability of critical services and increase both performance and overall system throughput. However, availability and performance are often at opposite ends of the deployment spectrum, requiring you to balance them according to your deployment goals



#### Note:

PingFederate provides separate failover capabilities specifically for outbound provisioning, which by itself does not require either load balancing or state management. For more information, see [Deploying provisioning failover](#) on page 221.

#### Running multiple maintenance versions

You can run multiple maintenance versions of PingFederate in a cluster. For example, a cluster can contain servers running 10.0.0, 10.0.1, and 10.0.2. However, a cluster cannot contain servers running multiple major or minor versions, such as 10.0.0 and 10.1.0.

When running multiple versions in a cluster, the following message appears at the top of the console: `The cluster is running more than one version of PingFederate.` Visit the [Cluster Management](#) page to see the versions. The [Cluster management](#) on page 926 window displays the version of PingFederate running on each server node.



#### Note:

Running multiple versions of PingFederate in a cluster might cause inconsistencies in runtime behavior.

Clustering with multiple maintenance versions can reduce the upgrade burden by eliminating downtime. Running in mixed mode should be a temporary solution, letting you gradually update each node until all of them are running the same maintenance version.

**Important:**

When upgrading the servers in the cluster, upgrade the administrative console first. The maintenance release might contain UI changes that need to be replicated throughout the cluster.

## General cluster architecture

The cluster architecture has two layers:

### Cluster-protocol layer

The cluster-protocol layer allows the PingFederate servers to discover a cluster, communicate with each other, detect and relay connectivity failures, and maintain the cluster as individual servers join and leave.

### Runtime state-management services

The runtime state-management services communicate session-state information required to process SSO and SLO requests. PingFederate abstracts its runtime state-management services behind Java service interfaces, which enables PingFederate to use interface implementations without regard to underlying storage and sharing mechanisms. Abstracting also provides a well-defined point of extensibility in PingFederate. Depending on the chosen runtime state-management architecture, each service can share session-state information with a subset of nodes or all nodes.

## Runtime state-management architectures

PingFederate supports both adaptive clustering and directed clustering. Adaptive clustering offers the benefits of scaling PingFederate horizontally with little or no configuration requirement. Directed clustering allows administrators to specify which runtime state-management service uses which architecture model.

### Group-RPC oriented approach

The prepackaged state-management implementations use a remote-procedure-call (RPC) framework for reliable group communication in a variety of deployments, allowing PingFederate servers to share state information within a cluster.

### Load balancing

Clustered deployments of PingFederate for SSO and SLO transactions typically require the use of at least one load balancer, fronting multiple PingFederate servers.

When a client accesses the load balancer's virtual IP, the balancer distributes the request to one of the PingFederate servers in the cluster. Based on the configuration of the associated runtime-state management service, the processing server contacts other PingFederate servers through remote procedure calls as it processes SSO and SLO requests.

PingFederate does not automatically balance the traffic among the servers in the cluster. To avoid overloading individual servers in the cluster, you must manage SSO and SLO requests externally. Because each server can only handle a certain amount of traffic, see [PingFederate Performance Tuning Guide](#) on page 1079 to plan ahead.

How you configure the balancer to select the appropriate server can vary from simple to highly complex, depending on your deployment requirements. For specific balancing strategies, their strengths and weaknesses, as well as the impacts on PingFederate performance, see [Runtime state-management architectures](#) on page 192.

Load balancers can incorporate SSL/TLS accelerators or work closely with them. Because of the high computational overhead of the SSL handshake, you should terminate SSL/TLS on a dedicated server external to PingFederate for deployments in which performance is a concern. You can still use SSL between the proxy or balancer and PingFederate but as a separate connection.

### Server modes

In a cluster, you can configure each PingFederate instance, or node, as either an administrative console or a runtime engine. Runtime engines, also known as engine nodes, service federated-identity protocol requests, while the console server, also known as the console node, administers policy and configuration for the entire cluster through the administrative console. A cluster can contain one or more engine nodes but only one console node.

**Note:**

To successfully process SSO requests, you must set the administrative console node to run outside of the load-balanced group.

## Cluster protocol architecture

---

PingFederate's cluster-protocol services manage discovery, cluster messaging, connectivity failure detection, membership, and merging of split clusters.

**Important:**

Nodes in the cluster must be able to communicate with one another over both the cluster bind port and the cluster failure detection port. This communication requirement remains true regardless of the chosen cluster discovery method or runtime state-management architecture.

### Cluster discovery

PingFederate supports two cluster discovery methods.

#### Static discovery

Static discovery is suitable for a small cluster with about five to six engine nodes. Configuration requires no external component. You must configure each node with at least one expected node in a cluster. In practice, the initial discovery list should contain all nodes known in advance in the cluster, including itself, to increase the likelihood of new members finding and joining the cluster.

#### Dynamic discovery

Dynamic discovery is well-suited for environments where traffic volume may spike and require additional resources during peak hours. Instead of configuring a static list of known nodes ahead of time, configure new nodes to pull cluster membership information from a centralized repository. Because safe storage and ready accessibility of the information by all nodes is crucial, PingFederate supports IAM roles for Amazon Elastic Compute Cloud (Amazon EC2), Amazon Simple Storage Service (Amazon S3), and OpenStack Swift. The dynamic discovery method requires only a one-time setup. Once configured, maintaining a static discovery list requires no coordination effort.

Regardless of the discovery method, as individual nodes join and leave the cluster, the cluster-protocol service synchronizes the new membership information across all nodes.

## Failure detection

The failure detection mechanism detects network connectivity failures by establishing TCP connections with other nodes at their cluster failure detection ports and sending occasional network messages. When a node detects a failure, it propagates the condition to other nodes, sharing new membership information across the cluster.



### Important:

If you deploy any networking devices, such as a firewall, between nodes, you must configure them to allow inbound TCP connections to the cluster failure detection ports, and not to terminate these connections based on their potentially low volumes of network activities.

## Runtime state-management architectures

This section provides an overview of runtime state-management architecture options available for PingFederate.

Runtime state-management services distribute session-state information in the cluster, making it possible for multiple nodes to handle SSO and logout requests as a single system. In a cluster consisting of a large number of nodes, it might be desirable for performance reasons to share session-state information with only a subset of nodes. PingFederate supports two runtime state-management architectures: adaptive clustering and directed clustering.

### Adaptive clustering

Adaptive clustering automatically distributes session-state information to multiple nodes. Administrators do not have to modify individual configuration files to specify which nodes should participate in tracking user sessions.

In essence, each session receives an address from within an internally-defined range. For redundancy, multiple nodes store each session. These nodes form a replica set. Any node that receives a request and must look up or store session-state information can do so by calculating the address of the session and reaching out to the corresponding replica set.

As individual nodes join and leave the cluster, adaptive clustering redistributes session-state information to maintain the replica set throughout the cluster.

The default size of a replica set is three, which provides redundancy in case two nodes fail and ensures that a single node's slow response time doesn't delay requests. The **replication.factor** setting is in the `<pf_install>/pingfederate/server/default/conf/cluster-adaptive.conf` file.

Enable adaptive clustering by setting the **pf.cluster.adaptive** property in the `run.properties` file to `true`. This is the default state in new installations. For upgrades, if such property is not found or is set to `false`, the system disables adaptive clustering and enables directed clustering instead. To enable or disable adaptive clustering, set the **pf.cluster.adaptive** property to `true` or `false` on each node and then restart PingFederate. The `run.properties` file is in the `<pf_install>/pingfederate/bin` directory.



### Important:

After making changes to the `cluster-adaptive.conf` and the `run.properties` files, you must manually repeat the changes to all nodes in the cluster. The configuration replication process does not push these files across the cluster. When you are finished, restart PingFederate to apply the changes.



### Note:



Adaptive clustering does not support the SAML 2.0 single logout (SLO) profile using the SOAP binding. If you have configured one or more SAML 2.0 connections to support SLO using SOAP, you must either share all nodes or designate state servers deployment strategies in directed clustering. For more information, see [Directed clustering](#) on page 196.

#### Other advanced settings

Fine-tune each runtime state-management service implementation separately by modifying a configuration file located in the `<pf_install>/pingfederate/server/default/conf` directory. After making changes in these files, you must apply the changes to all nodes in the cluster manually.



#### Note:

The adaptive clustering concept is not applicable to the Artifact-Message Persistence and Retrieval Service, which always shares messages across all nodes to fulfill its objectives. As needed, you can modify other applicable properties, such as the `rpc.timeout` property. For more information, see [Artifact-Message Persistence and Retrieval Service](#) on page 205.



The following tables indicate the configuration file that applies to each implementation and the applicable properties. See the indicated sections for detailed information about each implementation.


#### Configuration file and service implementation

| Configuration file                                    | RPC-based service implementation   |
|---|--|
| <code>cluster-account-locking.conf</code>             | <a href="#">Account Locking Service</a> on page 207                            |
| <code>cluster-artifact.conf</code>                    | <a href="#">Artifact-Message Persistence and Retrieval Service</a> on page 205 |
| <code>cluster-assertion-replay-prevention.conf</code> | <a href="#">Assertion Replay Prevention Service</a> on page 204                |
| <code>cluster-idp-session-registry.conf</code>        | <a href="#">IdP Session Registry Service</a> on page 203                       |
| <code>cluster-inter-request-state.conf</code>         | <a href="#">Inter-Request State-Management (IRSM) Service</a> on page 202      |
| <code>cluster-session-revocation.conf</code>          | <a href="#">Back-Channel Session Revocation Service</a> on page 206            |
| <code>cluster-sp-session-registry.conf</code>         | <a href="#">SP Session Registry Service</a> on page 203                        |

#### Property description

| Property                 | Description  |
|--------------------------|--|
| <code>rpc.timeout</code> | How long, in milliseconds, this node waits before timing out unresponsive RPC invocations. The default value is 500, or half a second. |

| Property   | Description   |
|--|---|
| <code>synchronous.retrieval</code>   | Indicates how many responses to wait for when making synchronous remote procedure calls. When set to <code>true</code> , this node waits for the majority of the local replica set to respond. When set to <code>false</code> , it waits for all recipients to respond. <code>true</code> is the default value.   |
|  |  <b>Note:</b><br>This property is not applicable to the Account Locking Service and not found in the <code>cluster-account-locking.conf</code> file.   |
| <code>bulk.revoked.sris.time</code><br>(found only in the <code>cluster-session-revocation.conf</code> file) | <p>A node downloads a full revocation list from another node during startup or when it rejoins a cluster after being disconnected from it, for example due to a temporary network issue. This setting determines the amount of time in milliseconds PingFederate waits before aborting the download and reporting a timeout error.</p> <p>The default value is 10000, which is 10 seconds.</p>  |
| <code>read.local.only</code><br>(found only in the <code>cluster-session-revocation.conf</code> file)        | <p>Determines how PingFederate should process queries for revocation status.</p> <p>When set to <code>true</code>, PingFederate processes queries for revocation status locally. When set to <code>false</code>, the processing node pulls revocation status from other engine nodes in the cluster, subject to the <code>rpc.timeout</code> value. <code>true</code> is the default value.</p> |
|  |  <b>Note:</b><br>When adding a session to the revocation list, the processing node always propagates the information to all engine nodes in the cluster. For more information, see <a href="#">Back-Channel Session Revocation Service</a> on page 206.  |

 **Note:**

When you have enabled adaptive clustering, PingFederate ignores other properties found in these configuration files—namely `preferred.node.indices` and `preferred.node.group.id`. The latter is only in the `cluster-idp-session-registry.conf` file.

### Multi-region support

PingFederate supports multi-region server clusters in adaptive clustering architecture.

When a cluster spans multiple regions, administrators can specify region identifiers for different groups of nodes. When regions are defined, any node that receives a request and must store session-state information can do so by sending the information to replica sets in both the local and remote regions. Requests that require read-only access to session-state information are answered locally for optimal performance.

As individual nodes in different regions join and leave the cluster, adaptive clustering redistributes session-state information within the region where changes in the cluster membership occur. This approach strikes a balance between minimizing the volume of session-state network traffic and improving the accuracy of session-state information across regions.

Cross-region support is enabled by default when you configure region identifiers in adaptive clustering environments. PingFederate provides cross-region support for the following functions:

- User session-state information maintained by the [Inter-Request State-Management \(IRSM\) Service](#) on page 202, the [IdP Session Registry Service](#) on page 203, and the [SP Session Registry Service](#) on page 203
- [Assertion Replay Prevention Service](#) on page 204
- [Account Locking Service](#) on page 207
- Replication, validation, and revocation of access tokens using the reference token data model

When cross-region support is disabled in individual areas, engine nodes only communicate session-state information to and from the local replica set. To improve the accuracy of session-state information, you can deploy a network traffic management solution to persist, or stick, user sessions so that each subsequent request from the same user is directed to the same set of nodes.



#### Note:

To reduce cross-region network traffic, PingFederate does not normally replicate SSO transaction states to other regions. However, if DNS sends user requests to different regions during a single SSO transaction, the transaction will fail with the error `Unable to resume processing because saved state was not found for key`.

To let PingFederate asynchronously replicate SSO transaction states to other regions, open the `cluster-adaptive.conf` file and change the value of `inter.group.replicate.transaction.state` to `true`.

### OAuth access token management

PingFederate shares reference token information with a replica set when adaptive clustering is enabled. If region identifiers are defined, PingFederate shares reference token information among multiple replica sets across regions. Like other services, you can optionally override this default behavior by changing the `inter.group.replicate.reference.tokens` value in the `<pf_install>/pingfederate/server/default/conf/cluster-adaptive.conf` file.

When you disable cross-region support for access tokens using the reference token data model, PingFederate does not share reference token information across regions. As a result, PingFederate cannot de-reference, validate, or revoke a reference-style access tokens issued outside of its region. For this reason, we recommended switching to the self-contained token data model prior to disabling cross-region support for the reference token data model.

### Configuring multi-region support

Define region identifiers and configure cross-region settings for multi-region PingFederate server clusters.

#### Steps

1. To define a region identifier for a given node, update the `node.group.id` value in the `<pf_install>/pingfederate/server/default/conf/cluster-adaptive.conf` file, which is a per-server configuration.

Example: For example, if you have five engine nodes in the West Coast and six engine nodes in the East Coast, you can update the `node.group.id` value to `W` for each of the West Coast nodes and `E` for each of the six nodes in the East Coast.

- a. Restart PingFederate after making changes to the `cluster-adaptive.conf` file.

Result:

Once defined, the identifiers for all nodes are displayed on the **System # Server # Cluster Management** menu.

2. To configure cross-region support for individual areas, follow the inline instructions in the `cluster-adaptive.conf` file to update the relevant setting values.

## Directed clustering

This topic provides an overview of manual configuration of PingFederate sever nodes through directed clustering.

Directed clustering allows administrators to manually specify which PingFederate nodes should participate in tracking user sessions. Most group Remote Procedure Call (RPC)-based service implementations make use of a preferred-nodes concept, which assigns each node a list of other nodes, identified by index, with which it shares session-state information.

Each service implementation is controlled separately by a configuration file located in the `<pf_install>/pingfederate/server/default/conf` directory. You must replicate any changes manually for each cluster node.

The following tables indicate the configuration file that applies to each implementation and the applicable properties.




### Note:


The Artifact-Message Persistence and Retrieval Service uses only the `rpc.timeout` setting.

### Configuration file and service implementation

| Configuration file                                    | RPC-based service implementation   |
|---|--|
| <code>cluster-account-locking.conf</code>             | <a href="#">Account Locking Service</a> on page 207                            |
| <code>cluster-artifact.conf</code>                    | <a href="#">Artifact-Message Persistence and Retrieval Service</a> on page 205 |
| <code>cluster-assertion-replay-prevention.conf</code> | <a href="#">Assertion Replay Prevention Service</a> on page 204                |
| <code>cluster-idp-session-registry.conf</code>        | <a href="#">IdP Session Registry Service</a> on page 203                       |
| <code>cluster-inter-request-state.conf</code>         | <a href="#">Inter-Request State-Management (IRSM) Service</a> on page 202      |
| <code>cluster-session-revocation.conf</code>          | <a href="#">Back-Channel Session Revocation Service</a> on page 206            |
| <code>cluster-sp-session-registry.conf</code>         | <a href="#">SP Session Registry Service</a> on page 203                        |

## Property description

| Property  | Description  |
|---|--|
| <code>preferred.node.indices</code>   | <p>A comma-separated list of indices identifying the nodes with which this node shares session-state information for the associated service. If left blank, this node sends session-state information to all nodes in the cluster as it processes SSO and logout requests.</p> <p>The Artifact-Message Persistence and Retrieval Service and the Back-Channel Session Revocation Service do not support this parameter.</p> <p>Ignored when adaptive clustering is enabled.</p> <p>This property has no default value.</p>   |
| <code>preferred.node.group</code><br>(found only in the <code>cluster-idp-session-registry.conf</code> file)    | <p>An alphanumeric group ID for a subcluster. If specified, each subcluster must have a unique group ID. At startup, validates that the group ID is not already registered in the cluster by another list of preferred nodes. If the validation fails, aborts the startup process and exits.</p> <p>When the group ID is specified, the session identifier contains the information about the originating subcluster. This is helpful in deployments where has been configured to manage authentication sessions on the <b>Authentication # Policies # Sessions</b> window. When an engine node receives a request to query and extend a session, it can route the request to the corresponding subcluster based on the session identifier value.</p> <p>If subclusters are configured without specifying group IDs, a request to query and extend a session is processed on the subcluster that received the revocation status request, which may be different from the subcluster where the session is being tracked. As a result, the session could reach the idle timeout sooner than expected.</p> <p>Ignored when adaptive clustering is enabled.</p> <p>This property has no default value.</p> |
| <code>rpc.timeout</code>  | <p>How long, in milliseconds, this node waits before timing out unresponsive RPC invocations.</p> <p>The default value is 500, or half a second.</p>   |
| <code>synchronous.retrieve</code>   | <p>Indicates how many responses to wait for when making synchronous remote procedure calls. When set to <code>true</code>, this node waits for the majority of recipients to respond. When set to <code>false</code>, it waits for all recipients to respond.</p> <p>The default value is <code>true</code>.</p>   |
| <code>bulk.revoked.sris.timeout</code><br>(found only in the <code>cluster-session-revocation.conf</code> file) | <p>Determines the amount of time (in milliseconds) waits before aborting the download of revocation lists and reporting a timeout error. The default value is 10000, or 10 seconds.</p>  |
|   | <p> <b>Note:</b><br/>A node downloads a full revocation list from another node during startup or when it rejoins a cluster after being disconnected from it.</p>  |

| Property  | Description   |
|---|---|
| <b>read.local.only</b><br>(found only in the <code>cluster-session-revocation.conf</code> file) | Determines how processes queries for revocation status.<br><br>When set to <code>true</code> , queries for revocation status are processed locally. When <code>false</code> , the processing node pulls revocation status from other engine nodes in the cluster (subject to the <b>rpc.timeout</b> value).   |
|   | <div style="border: 1px solid #ccc; padding: 10px;"> <p> <b>Note:</b></p> <p>When adding a session to the revocation list, the processing node always propagates the information to all engine nodes in the cluster. See <a href="#">Back-Channel Session Revocation Service</a> on page 206 for more information.</p> </div> <p>The default value is <code>true</code>.</p> |

### Preferred node indices

Configuring the **preferred.node.indices** property can reduce the network communications and memory footprint. However, transaction volume and distribution can affect the resulting configuration. For more information on performance tuning, see [PingFederate Performance Tuning Guide](#) on page 1079.

Individual services within a single cluster deployment can use different preferred nodes, meaning you can set different values for the **preferred.node.indices** property for each service.

Using preferred nodes can translate into a variety of deployment configurations. The following sections discuss three primary strategies to consider for meeting your network requirements:

- [Sharing all nodes](#) on page 198
- [Designating state servers](#) on page 199
- [Defining subclusters](#) on page 200

### Note:


It is possible to configure overrides for authentication-adaptor processing based on the runtime node servicing a request. See [Configuring the Cluster Node Authentication Selector](#) on page 236 for more information.

### Sharing all nodes

The default directed clustering is the simplest deployment case, where all nodes are shared within a cluster.

Leaving the **preferred.node.indices** property blank in all cluster-configuration files results in a basic deployment case. An advantage of this approach is simplicity, including the option of using straightforward load-balancing strategies such as round robin. A disadvantage is that as additional nodes are added, the throughput improvement rate that clustering offers may decline as the state-replication overhead increases.

The following diagram illustrates this node-sharing approach. Requests in this deployment are directed to all nodes.



### Designating state servers

A state servers clustering deployment model improves scalability by reducing communication between nodes.

You can select a few engine nodes as state servers. This deployment approach scales better than the all-nodes approach because additional nodes do not require connections to every existing node, they only require a connection between each server and each state server.


Configure this deployment by setting the `preferred.node.indices` of other servers in a group to those of the state servers. Configure the load balancer to isolate the state-server nodes from end-user traffic.



#### Note:

The underlying cluster protocol still requires that all nodes are able to communicate with one another. The topology here is only an optimization for the runtime state-management services that support the concept of preferred nodes.

The following diagram illustrates the state-server approach.



In this example, the two state-server nodes have indices of 1 and 2. The **preferred.node.indices** property of the engine nodes handling requests would be `preferred.node.indices=1,2`.

Because the state servers are not processing transactions (based on the setup of the load balancer), the **preferred.node.indices** property for them is not used and can be left blank.



#### Note:

When acts as an OAuth authorization server (AS) and the access token management instance uses a reference token data model, the resource server (RS) must send a request to to de-reference the access token for the corresponding identity and security information. Because the OAuth clients and the RS send their requests separately, shares reference token information among all engine nodes despite any state server or subcluster setup.

### Defining subclusters

Subclustering improves efficient scaling by limiting session-state communication to other nodes within a subcluster.

Node indices can be configured to divide a cluster into subgroups, or subclusters, of a few nodes each. Using this configuration, each node in a subcluster shares session-state information only with other members of the subcluster. This approach requires a network traffic management solution to persist, or stick, user sessions so that each subsequent request from the same user is directed to the same set of nodes. The advantage of this approach is that cluster throughput scales more linearly, because the creation of an additional subcluster will not degrade the performance of any other group.



#### Note:


The underlying cluster protocol still requires that all nodes are able to communicate with one another. The topology here is only an optimization for the runtime state-management services that support the concept of preferred nodes.

Additionally, this architecture does not support the SAML 2.0 single logout (SLO) profile using the SOAP binding. If one or more SAML 2.0 connections are configured to support SLO via SOAP, you must choose between the sharing all nodes and designating state servers deployment strategies in directed clustering.



This architecture also does not support the capability to revoke sessions after password change or reset. If you are using this capability, you are limited to the sharing all nodes and designating state servers deployment strategies.

The following diagram illustrates the subcluster approach.



In this example, the `preferred.node.indices` property of each server in the cluster lists the indices of all nodes in its subgroup (including itself). Requests are directed to all nodes but the load balancer directs user sessions to the same subcluster.

#### Note:

When acts as an OAuth authorization server (AS) and the access token management instance uses a reference token data model, the resource server (RS) must send a request to to de-reference the access token for the corresponding identity and security information. Because the OAuth clients and the RS send their requests separately, shares reference token information among all engine nodes despite any state server or subcluster setup.

## Runtime state-management services

Runtime state-management services are a collection of interfaces defining the contract that PingFederate uses to manage session states for each service.

The `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file specifies the implementation of each service. You only need to modify this file if you want to customize the way services are handled in a cluster. You must manually replicate your changes in each cluster node.

By default, the interfaces listed in `hivemodule.xml` are proxies that select the best implementation for each service, based on the operational mode of the server. For example, an in-memory-only implementation applies if the server is in standalone mode, and a group RPC-based implementation applies to servers in clustered mode. These proxies are provided for convenience. You can specifically designate your desired implementation for each service, as described in the following sections.

- [Inter-Request State-Management \(IRSM\) Service](#) on page 202
- [IdP Session Registry Service](#) on page 203
- [SP Session Registry Service](#) on page 203
- [LRU memory management schemes](#) on page 204
- [Assertion Replay Prevention Service](#) on page 204
- [Artifact-Message Persistence and Retrieval Service](#) on page 205
- [Back-Channel Session Revocation Service](#) on page 206
- [Account Locking Service](#) on page 207
- [Other services](#) on page 207

Configuration files for the services are located in the `<pf_install>/pingfederate/server/default/conf` directory.

## Inter-Request State-Management (IRSM) Service

This topic is an overview of the two options for tracking session information between HTTP requests in PingFederate.

The PingFederate server tracks user-session state information between HTTP requests, such as when PingFederate, acting as an identity provider (IdP), redirects a user's browser to another system for authentication. When the user's browser returns to PingFederate after authentication, the server needs access to the state associated with that user from before the redirect. Generally, this state is short-lived.

The `InterRequestStateMgmtProxy` implementation chooses between two methods to track this state: group RPC-based (the clustering default) and local memory-based (the standalone default).

The configuration file is `<pf_install>/pingfederate/server/default/conf/cluster-inter-request-state.conf`.

### Group RPC-based session tracking

The group RPC-based implementation supports both adaptive clustering and directed clustering.

For adaptive clustering, PingFederate shares user session-state information with a replica set. If region identifiers are defined, PingFederate shares user session-state information among multiple replica sets across regions. You can override this default behavior in the `<pf_install>/pingfederate/server/default/conf/cluster-adaptive.conf` file.

For directed clustering, all preferred-node approaches are possible with this implementation.

The service-point `InterRequestStateMgmt` in the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file uses the proxy `InterRequestStateMgmtProxy` to assign this implementation as the clustering default. The specific class name is `org.sourceid.saml20.service.impl.grouprpc.InterRequestStateMgmtGroupRpcImpl`

### Local memory-based session tracking

The local memory-based session tracking implementation tracks users in the inter-request state in the local memory of the processing server. This is the standalone default.



#### Important:

Adaptive clustering does not support this implementation. Use the group RPC-based session tracking instead.

The service-point `InterRequestStateMgmt` in the `hivemodule.xml` file uses the proxy `InterRequestStateMgmtProxy` to assign this implementation as the clustering default. The specific class name is `org.sourceid.saml20.service.impl.localmemory.InterReqStateMgmtMapImpl`

## Local memory-based session tracking and clustering

Group RPC-based session tracking is the clustering default. To use local memory-based session tracking in a clustered environment, update the service-point `InterRequestStateMgmt` to use the local memory-based session tracking class, `org.sourceid.saml20.service.impl.localmemory.InterReqStateMgmtMapImpl`

### Note:

The load balancer must support sticky sessions to force all requests for the same user session to be routed to the same server.

## IdP Session Registry Service

PingFederate uses the IdP Session Registry Service to facilitate single logout (SLO) by tracking assertions issued to Service Provider (SP) partners.

PingFederate uses this service only when acting in an Identity Provider (IdP) role and supports SLO with one or more partner connections.

When PingFederate is in clustered mode, the service proxy uses a group RPC-based, preferred-nodes implementation. The configuration file is `<pf_install>/pingfederate/server/default/conf/cluster-idp-session-registry.conf`.

This service supports both adaptive clustering and directed clustering.

For adaptive clustering, PingFederate shares user session-state information with a replica set. If region identifiers are defined, PingFederate shares user session-state information among multiple replica sets across regions. You can optionally override this default behavior in the configuration file.

For directed clustering, all preferred-node approaches are possible with this implementation.

### Note:

Both adaptive clustering and the subcluster deployment strategies in directed clustering do not support the SAML 2.0 SLO profile using the SOAP binding. If one or more SAML 2.0 connections are configured to support SLO via SOAP, you must choose between the sharing all nodes and designating state servers deployment strategies in directed clustering (see [Directed clustering](#) on page 196).

The service proxy uses the class

```
org.sourceid.saml20.service.impl.grouprpc.IdpSessionRegistryGroupRpcImpl
```

### Note:

If the IdP session registry is configured with the Directed Clustering - Subclusters state management architecture, the capability to revoke sessions after password change or reset is not supported.

## SP Session Registry Service

PingFederate uses the SP Session Registry Service to facilitate SLO by tracking assertions issued from identity provider (IdP) partners. PingFederate uses this service only when the server is acting in a service provider (SP) role and supports SLO with one or more partner connections.

When PingFederate is in clustered mode, the service proxy uses a group RPC-based, preferred-nodes implementation. The configuration file is `<pf_install>/pingfederate/server/default/conf/cluster-sp-session-registry.conf`.

This service supports both adaptive clustering and directed clustering.

For adaptive clustering, PingFederate shares user session-state information with a replica set. If region identifiers are defined, PingFederate shares user session-state information among multiple replica sets across regions. You can override this default behavior in the configuration file.

For directed clustering, all preferred-node approaches are possible with this implementation.



#### Note:

Both adaptive clustering and the subcluster deployment strategies in directed clustering do not support the SAML 2.0 SLO profile using the SOAP binding. If one or more SAML 2.0 connections are configured to support SLO via SOAP, you must choose between the sharing all nodes and designating state servers deployment strategies in directed clustering (see [Directed clustering](#) on page 196).

The service proxy uses the class

```
org.sourceid.saml20.service.impl.grouprpc.SpSessionRegistryGroupRpcImpl.
```

## LRU memory management schemes

PingFederate uses an LRU memory manager to reduce memory usage by orphaned data.

During the normal course of transaction processing, the Inter-Request State-Management Service, the IdP Session Registry Service, and the SP Session Registry Service manage memory for PingFederate. End users abandoning web sessions results in orphaned data. To ensure that this orphaned data does not result in excessive memory usage, the data structures used by these services employ a least-recently-used (LRU) algorithm to purge old data. This algorithm automatically removes the oldest entries when a data structure reaches the maximum size.

Configure the maximum size of each data structure in the `<pf_install>/pingfederate/server/default/conf/size-limits.conf` file.

## Assertion Replay Prevention Service

The Assertion Replay Prevention Service tracks POST assertions to prevent replay.

SAML standards specify that when a service provider (SP) receives assertions from the POST binding, the SP should keep track of each assertion for the duration of its validity to ensure that it is not replayed (that is, intercepted by a third party and re-posted). For OAuth and OpenID Connect, PingFederate can mandate a unique signed JSON Web Token (JWT) from the client for each request when the client is configured to authenticate via the `private_key_jwt` client authentication method, to transmit request parameters using in signed request objects, or to do both. PingFederate delegates these responsibilities to the Assertion Replay Prevention Service.

When PingFederate is in clustered mode, the service proxy uses a group RPC-based, preferred-nodes implementation. The configuration file is `<pf_install>/pingfederate/server/default/conf/cluster-assertion-replay-prevention.conf`.

The Assertion Replay Prevention Service supports both adaptive clustering and directed clustering.

For adaptive clustering, PingFederate shares token (assertion or JWT) information with a replica set. If region identifiers are defined, PingFederate shares token information among multiple replica sets across regions. You can optionally override this default behavior in the configuration file for adaptive clustering.

For directed clustering, you must choose between the sharing all nodes and designating state servers deployment strategies in directed clustering for this service.

The service proxy uses the class

```
org.sourceid.saml20.service.impl.grouprpc.AssertionReplayPreventionServiceGroupRpcImpl.
```

Unlike other services, the Assertion Replay Prevention Service fulfills only a security condition, rather than supporting normal SSO functionality, because there might be situations where the priority placed on cluster performance outweighs the priority placed on this security check. If you are in this situation, you have the option to change the implementation for the service point `AssertionReplayPreventionService` in the

<pf\_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml file to one of these classes:

- `org.sourceid.saml20.service.impl.localmemory.AssertionReplayPreventionSvcInMemoryImpl`  
This is the implementation used in standalone mode. It performs all the appropriate replay checks but does not share any data with other nodes. A replay attempt routed to the same server node would fail, but other nodes would not have sufficient information to stop the transaction.
- `org.sourceid.saml20.service.impl.localmemory.AssertionReplayPreventionServiceNullImpl`  
This implementation disables assertion-replay prevention. Use with caution when performance is an absolute priority.

## Artifact-Message Persistence and Retrieval Service

PingFederate's Artifact-Message Persistence and Retrieval Service keeps track of one-time keys and associated data compliant with SAML and OAuth 2.0 standards.

The following standards require PingFederate to relay data to partners using a reference-style data transportation model and to guarantee that the reference keys are valid for one-time use only.

### SAML artifact binding

PingFederate sends an artifact to the partner when transmitting SAML-outbound messages using the artifact binding. Later, the partner returns to PingFederate to exchange the artifact for the actual message. If the request is valid, PingFederate delivers the message and invalidates the artifact.

### OAuth 2.0 authorization grant type

When processing an authorization request from an OAuth client that uses the authorization code grant type, PingFederate returns a code to the client based on specification. The client then includes that code in its token request to PingFederate to obtain an access token. If the request is valid, PingFederate delivers the access token and invalidates the code.

The Reference ID Adapter from the [Agentless Integration Kit](#) also applies the same data transportation model and one-time-use restriction in its drop-off and pick-up operations.

In a standard environment, the PingFederate server saves the data in memory, generates a key for the data, and sends the key to the partner. The Artifact-Message Persistence and Retrieval Service keeps track of the key and the associated data until the partner contacts the PingFederate server to exchange the key for the data.

### Group RPC-based retrieval

When multiple PingFederate servers are deployed to form a cluster, the keys and their data are saved in the server that creates them. Because they are not replicated to other PingFederate servers, it is possible for a key resolution request to arrive at a server that does not contain the requested data. To handle this scenario, the Artifact-Message Persistence and Retrieval Service uses a group Remote Procedure Call (RPC) retrieval approach, where the server handling the key resolution request determines the data-hosting server based on the key value and contacts the appropriate server to retrieve the requested data. This group RPC implementation is compatible with the SAML artifact binding, the OAuth 2.0 authorization code grant type, and the Reference ID Adapter.



#### Note:

The Artifact-Message Persistence and Retrieval Service also supports a local memory approach for SAML 2.0. This approach is only suitable in clustered environments where the OAuth 2.0 authorization code grant type and the Reference ID Adapter are not in use.

When PingFederate is in clustered mode, the service proxy selects a group RPC-based implementation, which takes advantage of node indexing but not the preferred-nodes concept. Sticky-session load-

balancing strategies are not effective when the key request and its subsequent key resolution request can come from different locations.

Although this implementation does not take advantage of adaptive clustering or the preferred-nodes concept, you can configure the RPC time-out in the `<pf_install>/pingfederate/server/default/conf/cluster-artifact.conf` file.

### SAML 2.0 indexing (local memory)

A SAML 2.0 federation entity can support multiple artifact resolution services, each identified by a unique index number. Artifacts include this index, and a federation partner must send the artifact resolution request to the appropriate endpoint for that index. This means that servers do not need to share information concerning the artifact.

With this approach, partners must know about each of your backend servers. Generally, this means providing partners with a list that includes multiple artifact-resolution service endpoints with the corresponding indices.



#### Note:

PingFederate does not automatically generate this information; an administrator must create it and send it to partners who are using the artifact binding.

For example, if you have four servers in a cluster, the list might look like this:

```
<ArtifactResolutionService Binding="..." Location="https://node1/idp/
ARS.ssaml2" index="1"/>
<ArtifactResolutionService Binding="..." Location="https://node2/idp/
ARS.ssaml2" index="2"/>
<ArtifactResolutionService Binding="..." Location="https://node3/idp/
ARS.ssaml2" index="3"/>
<ArtifactResolutionService Binding="..." Location="https://node4/idp/
ARS.ssaml2" index="4"/>
```

In this case, the index corresponds to the node index configured in the `run.properties` file on each individual server. This service encodes the node index in the artifact handle when running in a clustered mode (it will always use an index of 0 in standalone mode).

Partners also need direct access to each ARS endpoint, which can complicate your configuration of load balancers, proxies, and firewalls. This approach cannot be used for SAML 1.x, or with adapters that utilize PingFederate's artifact-data management.

To use this approach for SAML 2.0 federation deployments, edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file and change the implementation for the *ArtifactStore* service point to the class name `org.sourceid.saml20.service.impl.localmemory.ArtifactPersistenceServiceMapImpl`.

## Back-Channel Session Revocation Service

PingFederate uses the Back-Channel Session Revocation Service to provide OAuth clients the capabilities to add sessions to the revocation list and to query the revocation status.

When PingFederate is in clustered mode, the service proxy uses a group remote procedure call (RPC)-based implementation. When adding a session to its revocation list, the processing node always propagates the information to all engine nodes in the cluster. This allows you to choose whether queries are processed locally or after collecting information from other engine nodes.

Processing queries locally results in faster response times for engine nodes in well-connected networks. Requiring data from other engine nodes adds a layer of protection against inconsistency among engine nodes revocation lists due to network outages.

You can configure the RPC time-out and other settings in the `<pf_install>/pingfederate/server/default/conf/cluster-session-revocation.conf` file.

The service proxy uses the class

```
org.sourceid.saml20.service.impl.grouprpc.SessionRevocationServiceGroupRpcImpl.
```

FIFO memory management scheme

To ensure the revocation list does not result in excessive memory usage, the Back-Channel Session Revocation Service employs a first-in-first-out (FIFO) algorithm to purge old data. When the maximum size is reached, the oldest entries are automatically removed.

The maximum number of sessions is configurable by the

**SessionRevocationServiceMapImpl.max.revoked.sris** setting in the `<pf_install>/pingfederate/server/default/conf/size-limits.conf` file. The default value is 50000.

The FIFO memory manager operates in addition to the **Session Revocation Lifetime** setting, globally configured in the **System # OAuth Settings # Authorization Server Settings** menu.

## Account Locking Service

The PingFederate Account Locking Service includes account lockout prevention and password spraying prevention.

Account lockout protection prevents user accounts from locking at the underlying user repository based on too many failed authentication attempts. It also adds a layer of protection against brute force and dictionary attacks because the user is locked out for a time period when the number of failed attempts exceeds the threshold. This protection is enabled in many areas of , including the HTML Form Adapter, the Username Token Processor, the OAuth resource owner password credentials grant type, and the native authentication scheme for the administrative console and API.

Password spraying prevention adds a layer of defense against the attack pattern where bad actors try to gain access to protected resources by using the same password, typically weak or compromised, against multiple accounts from multiple locations. When enabled, tracks the number of failed login attempts per password. When the number of failures for a particular password reaches a threshold, that password is temporarily locked out. Password spraying prevention applies to the HTML Form Adapter, the Username Token Processor, and the OAuth 2.0 resource owner password credentials grant type.

When PingFederate is in clustered mode, the service proxy uses a group remote procedure call (RPC)-based implementation. The configuration file is `<pf_install>/pingfederate/server/default/conf/cluster-account-locking.conf`.

This service supports both the adaptive clustering and directed clustering.

For adaptive clustering, PingFederate shares state information with a replica set. If region identifiers are defined, PingFederate shares state information among multiple replica sets across regions. You can override this default behavior in the `<pf_install>/pingfederate/server/default/conf/cluster-adaptive.conf` file.

For directed clustering, PingFederate shares state information across all nodes, which helps in scenarios where PingFederate is deployed behind a load balancing infrastructure without sticky sessions.

## Other services

PingFederate offers an account linking service and a pseudonym service to support SAML 2.0 federation deployment needs.

Account linking service

The account linking service stores the association between the external and internal identifiers of an end user when your implementation uses account linking as a service provider (SP) identity-mapping strategy. The default, standalone implementation uses a Java Database Connectivity (JDBC) interface

to an embedded database within PingFederate. No information from the embedded database is shared across the cluster. When an identity provider (IdP) connection deployed in a cluster uses account linking, the default implementation will not work properly. In such cases, you must adjust the pointer for cluster use by pointing the service to an external database. For more information, see [Define an account-linking data store](#).

### Pseudonym service

The pseudonym service references the method needed by PingFederate to generate or look up a pseudonym for a user. PingFederate uses this service only if your site is acting in an IdP role and produces assertions containing pseudonyms as subject identifiers. The default implementation uses a message digest to produce the value so that no session-state synchronization is required. Developers who want to implement pseudonym handling differently can refer to the Javadoc reference describing `PseudonymService` interface for more information.

## Deploying cluster servers

---

A PingFederate cluster consists of multiple nodes, each of which are likely running on a dedicated host system.

### About this task

In a cluster, there are two types of nodes: engine nodes and an administrative console node. Engine nodes service end user traffic, and multiple nodes are recommended to ensure high availability for your deployment. Only one administrative console node can be running in a given cluster. This node hosts the user interface and APIs that you use to configure the cluster. Additionally, the administrative console node manages the following runtime functions:

- Performing periodic configuration archive backup
- Cleaning expired persistent authentication sessions
- Cleaning expired access grants
- Updating connections from metadata URLs, including PingOne SP connections if configured, and sends email notifications
- Performing automatic rotation of signing certificates if enabled



#### Note:

Additional steps are required to set up failover for provisioning. If you are grouping servers exclusively to provide for provisioning failover, skip these steps and see [Deploy provisioning failover](#).



These steps describe how to configure and deploy clustered PingFederate servers by editing each node in the `<pf_install>/pingfederate/bin/run.properties`.



### Steps



1. Install PingFederate on each node in a cluster.




2. Edit the clustering properties of each node in the `<pf_install>/pingfederate/bin/run.properties` file. See the following table for information about each property.

| Property                           | Description   |
|------------------------------------|---|
| <code>pf.operational.mode</code>   | <p>Controls the operational mode of the PingFederate server. PingFederate supports the following modes:</p> <p><code>STANDALONE</code> (default)</p> <p>This server is a standalone instance that runs both the administrative console and runtime engine.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Important:</b></p> <p>The value <code>STANDALONE</code> should only be used in a cluster where session-state management is not needed for any reason and configuration-archive deployment is used as the configuration synchronization method.</p> </div> <p><code>CLUSTERED_CONSOLE</code></p> <p>This server is part of a cluster and runs only the administration console.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Important:</b></p> <p>Only one node in a cluster can run the administrative console.</p> </div> <p><code>CLUSTERED_ENGINE</code></p> <p>This server is part of a cluster and runs only the runtime engine.</p> |
| <code>pf.cluster.node.index</code> | <p>Defines a unique index number for the server in a cluster. The index number is used to identify peers and optimize inter-node communication. The allowed range is 0 to 65535.</p> <p>If no value is set for the node index, the system assigns an auto-generated value in the range of 0 to 2147483647.</p> <p>This property has no default value. If you specify an index number, you can configure instances of the Cluster Node Authentication Selector and place them in authentication policies to customize authentication requirements based on the runtime node servicing a request.</p>   |

| Property                                   | Description  |
|--|--|
| <code>pf.cluster.auth.pwd</code>           | <p>Sets the password that each node in the cluster must use to authenticate when joining the cluster. This prevents unauthorized nodes from joining a cluster. The value can be any string, or blank.</p> <div data-bbox="565 342 1466 615" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>Consider using a randomly-generated password with 22 or more alphanumeric characters. A strong, obfuscated, Jgroups cluster password can be generated with the <code>clusterkey</code> utility (<code>clusterkey.bat</code> for Windows and <code>clusterkey.sh</code> for Linux), located in the <code>&lt;pf_install&gt;/pingfederate/bin</code> directory.</p> </div> <p>All nodes in a cluster must share the same value, blank or otherwise.</p>   |
| <code>pf.cluster.encrypt</code>            | <p>Indicates whether to encrypt network traffic sent between nodes in a cluster. The possible values are <code>true</code> or <code>false</code> (default).</p> <p>When set to <code>true</code>, communication within the cluster is encrypted with a symmetric key derived from the value of the <code>pf.cluster.auth.pwd</code> property.</p> <div data-bbox="565 884 1466 1087" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>When the <code>pf.cluster.encrypt</code> property is set to <code>true</code>, you must provide a value for the <code>pf.cluster.auth.pwd</code> property. Otherwise PingFederate aborts during its startup process.</p> </div> <p>All nodes in a cluster must have the same value for this property.</p> |
| <code>pf.cluster.encryption_keysize</code> | <p>The length of the key that PingFederate takes into consideration when deriving the symmetric key from the value of the <code>pf.cluster.auth.pwd</code> property for the purpose of encrypting network traffic sent between nodes in a cluster. Required only when the <code>pf.cluster.encrypt</code> is set to <code>true</code>.</p> <p>All nodes in a cluster must have the same value set for this property.</p> <p>The default value is 128.</p>  |

| Property  | Description   |
|---|---|
| <code>pf.cluster.bind.address</code>                | <p>Defaults to <code>NON_LOOPBACK</code>, which leaves the system to choose an available non-loopback IP address. Alternatively, enter an IP address of the network interface to which the cluster communication should bind. For machines with more than one network interface, provide a specific IP address.</p> <p>You can use this property to increase performance (particularly with UDP) and improve security by segmenting cluster-communication traffic onto a private network or VLAN.</p> <div data-bbox="565 520 1466 730" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>Besides <code>NON_LOOPBACK</code> or an IP address, you can also use other values supported by JGroups. For more information, see the <code>bind_addr</code> special values in <a href="#">JGroups documentation</a>.</p> </div> <div data-bbox="565 741 1466 919" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>This field does not support DNS name. Use the default value <code>NON_LOOPBACK</code> or replace it with an IP address.</p> </div> |
| <code>pf.cluster.bind.port</code>                   | <p>Specifies the port associated with the <code>pf.cluster.bind.address</code> property or with the default network interface used.</p> <p>This is the port used by other cluster members during their discovery process, usually via the <code>pf.cluster.tcp.discovery.initial.hosts</code> property.</p> <p>The default value is <code>7600</code>.</p>  |
| <code>pf.cluster.failure-detection.bind.port</code> | <p>Indicates the bind port of a server socket that is opened on the given node and used by other nodes as part of the cluster's failure-detection mechanisms. If set to <code>0</code> or unspecified, a random available port is used. The default value is <code>7700</code>.</p>   |

| Property                                    | Description   |
|---|---|
| <code>pf.cluster.transport.protocol</code>  | <p data-bbox="573 226 1461 321">Indicates the transport protocol used for cluster communication. Values are <code>udp</code> or <code>tcp</code>. The default value is <code>tcp</code>. All nodes in a cluster must have the same value set for this property.</p> <p data-bbox="573 342 1461 468">Use UDP when IP multicasting is enabled in the network environment and the majority of cluster traffic is point-to-full-group. You must also configure both the <code>pf.cluster.mcast.group.address</code> and <code>pf.cluster.mcast.group.port</code> properties.</p> <p data-bbox="573 489 1461 678">Use TCP for geographically dispersed servers or when multicast is not available or disabled for some other reason. For example, when using routers that do not support multicast messaging. TCP may also be appropriate if your cluster configuration employs more point-to-point or point-to-few messaging than point-to-group. You must also configure the <code>pf.cluster.tcp.discovery.inital.hosts</code> property.</p> <div data-bbox="573 699 1461 961" style="border: 1px solid black; padding: 5px;"> <p data-bbox="573 720 698 751"> <b>Note:</b></p> <p data-bbox="573 772 1461 930">This property is a reference to a protocol-stack XML configuration file located in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/</code> directory. Two stacks are provided: one for UDP multicast and one for TCP. You can customize either stack or add to it as needed by modifying the associated configuration file.</p> </div> |
| <code>pf.cluster.mcast.group.address</code> | <p data-bbox="573 993 1461 1150">Defines the IP address shared among nodes in the same cluster for UDP multicast communication; required when UDP is set as the transport protocol. The valid range is <code>224.0.0.0</code> to <code>239.255.255.255</code>. Some addresses in this range are reserved for other purposes. This property is not used for TCP.</p> <p data-bbox="573 1171 1461 1203">All nodes in a cluster must have the same value set for this property.</p> <p data-bbox="573 1224 1461 1255">The default value is <code>239.16.96.69</code>.</p>  |
| <code>pf.cluster.mcast.group.port</code>    | <p data-bbox="573 1276 1461 1371">Defines the port in conjunction with the <code>pf.cluster.mcast.group.address</code> property value. This property is not used for TCP configurations.</p> <p data-bbox="573 1392 1461 1423">All nodes in a cluster must have the same value set for this property.</p> <p data-bbox="573 1444 1461 1476">The default value is <code>7601</code>.</p>   |

| Property   | Description   |
|--|---|
| <code>pf.cluster.tcp.discovery.initial_hosts</code>  | <p>Designates a static list of PingFederate servers to be contacted for cluster membership information when discovering, joining, and rejoining the cluster. This value is required when TCP is set as the transport protocol. The value is a comma-separated list of host names (or IP addresses) and their cluster bind ports, for example, <code>host1[7600],10.0.1.4[7600],host7[1033],10.0.9.45[2231]</code>.</p> <p>When using static discovery, add at least one node for the cluster to know in advance. This property should contain all nodes in the cluster (including itself) to increase the likelihood of new members finding and joining the cluster.</p> <p>When using dynamic discovery, leave this property blank and enable dynamic discovery in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/tcp.xml</code> file. For more information, see <a href="#">Enabling dynamic discovery for clustering</a> on page 215.</p> |
| <code>pf.cluster.adaptive</code>   | <p>Indicates whether runtime state-management services should use the adaptive clustering architecture.</p> <p>The default value is <code>true</code> for new installations and <code>false</code> for upgrades.</p>  |
| <code>pf.cluster.diagnostics.enabled</code>  | <p>Indicates whether JGroups diagnostics are enabled. <code>true</code> turns it on.</p> <p>The default value is <code>false</code>.</p>  |
| <code>pf.cluster.diagnostics.multicast</code> and <code>pf.cluster.diagnostics.port</code> | <p>The multicast address and port this node listens on for diagnostic messages.</p> <p>The default values are <code>224.0.75.75</code> and <code>7500</code>, respectively. Do not change the default values.</p>   |
| <code>node.tags</code>   | <p>Defines the tags associated with this node.</p> <p>Configuration is optional. When configured, PingFederate considers this property when processing requests. For example, you can use tags to determine the datastore location that this PingFederate node communicates with. You can also use tags in conjunction with authentication selectors and policies to define authentication requirements.</p> <p>You can specify one tag.</p> <pre>node.tags=north</pre> <p>You can also specify a list of prioritized, space-separated tags.</p> <pre>node.tags=1 123 234</pre> <p>Tags cannot contain spaces.</p>  |

- Optional: Edit configuration files in each node that control the cluster protocol and runtime state-management service. For more information, see [Runtime state-management architectures](#) on page 192 and [Runtime state-management services](#) on page 201.
- Optional: If outbound provisioning is configured for your site and you want to provide failover capabilities, identify and configure the provisioning failover nodes. For more information, see [Deploy provisioning failover](#).
- Start or restart PingFederate on all nodes.

6. Sign on to the administrative console.
7. If you have not done so, import your PingFederate license. For more information, see [License management](#) on page 919.
8. On the **System # Server # Cluster Management** window, click **Replicate Configuration** to push the license information from the console node to all engine nodes.

## Result

After the clustered environment is set up, you can start configuring PingFederate through the administrative console. When PingFederate detects a change, it prompts you to replicate the configuration to all engine nodes.

## Dynamic cluster discovery

Instead of configuring a static list of known PingFederate nodes in advance, dynamic cluster discovery lets you configure new nodes to pull cluster membership information from a centralized repository.

Dynamic discovery is well-suited for environments where traffic volume could spike and require additional resources during peak hours. Because safe storage and ready accessibility of the information by all nodes is crucial, PingFederate supports identity and access management (IAM) roles for Amazon Elastic Compute Cloud (Amazon EC2), Amazon Simple Storage Service (Amazon S3), and OpenStack Swift. The dynamic discovery method requires only a one-time setup.

For information about configuring dynamic cluster discovery, see [Enabling dynamic discovery for clustering](#) on page 215.

### Dynamic cluster discovery protocols

In addition to the static cluster discovery protocol, `TCPPING`, PingFederate supports the following dynamic discovery protocols:

- `NATIVE_S3_PING`
- `DNS_PING`
- `AWS_PING`
- `SWIFT_PING`



#### Note:

The `S3_PING` discovery method has been deprecated because of the Amazon Web Services (AWS) deprecation of the SigV2 signing method. When deployed in AWS, the recommended discovery method is `NATIVE_S3_PING`. See the [JGroups documentation](#) for alternatives when deployed in other environments.

`NATIVE_S3_PING` and `SWIFT_PING` enable the flexibility to use both public and private cloud storage. PingFederate maintains cluster membership information in a centralized repository, a bucket in Amazon Simple Storage Service (Amazon S3) or a container in an OpenStack infrastructure.

PingFederate contacts the repository for a list of nodes. If PingFederate receives at least one node, a cluster exists, and it joins the cluster and updates the repository with its information, including its IP address. If PingFederate receives no node, it forms a new cluster and updates the repository with its information so that the next node can find the new cluster. When PingFederate shuts down, it removes itself from the list and pushes an update to the repository.

`NATIVE_S3_PING` uses the AWS SDK and provides a stable connection by using built-in security features, such as obtaining credentials through IAM server instance profiles. This protocol is the recommended dynamic discovery mechanism when you're running in AWS but aren't using Kubernetes.

`DNS_PING` uses `DNS A` or `SRV` records to perform discovery. This protocol is the recommended dynamic discovery mechanism when using Kubernetes. For more information, see the JGroups documentation about the [DNS\\_PING](#) protocol.

`AWS_PING` lets you scale your PingFederate infrastructure using Amazon EC2 instances in the AWS cloud, in one or multiple regions. PingFederate queries AWS for a list of eligible EC2 instances. If PingFederate receives at least one node, a cluster exists, and it joins that cluster. If PingFederate receives no node, it forms a new cluster.

You must enable permissions to `ec2:Describe*` actions in the AWS IAM role assigned to the EC2 instance or associate them with the `access_key` parameter that you provide as part of the dynamic discovery configuration. You can also use a combination of tags and filters, in which case only EC2 instances that satisfy both criteria are returned.

#### Discovery mechanisms versus runtime state-management architectures

Discovery mechanisms are separate from runtime state-management architectures. Discovery mechanisms determine how to find nodes to retrieve cluster information for the purpose of joining and rejoining a cluster. Runtime state-management architectures determine which nodes session-state information is shared to and fetched from.

PingFederate supports adaptive clustering and directed clustering runtime state-management architectures. When opting for dynamic discovery, consider enabling adaptive clustering whenever possible. If multiple regions are involved, configure multi-region support for adaptive clustering as well. For more information and configuration steps, see [Adaptive clustering](#) on page 192.

Regardless of the chosen runtime state-management architecture, all nodes must still be able to communicate with other nodes for clustering-protocol messages. For more information, see [Runtime state-management architectures](#) on page 192.

#### Enabling dynamic discovery for clustering

You can enable and configure dynamic discovery setup for clustered PingFederate deployments by editing the `run.properties` and `jgroups.properties` files.

#### Before you begin

If your PingFederate deployment has cluster discovery settings in the `tcp.xml` file, migrate those settings to the `jgroups.properties` file. For more information, see [Migrating cluster discovery settings](#) on page 219.

#### About this task



#### Important:

If you enable dynamic discovery, you must manually configure or synchronize the dynamic discovery properties in the `run.properties` file and `jgroups.properties` file on each node in the cluster. The files are not synchronized automatically across the nodes in a cluster, nor is it part of the replicate configuration process.

Whenever you add a node to the cluster, perform the following procedure on the new node.

To enable and configure dynamic discovery for clustering:

## Steps

1. Configure the cluster protocol properties in the `<pf_install>/pingfederate/bin/run.properties` file.

See the file's inline comments and the following table.

### Cluster protocol properties in `run.properties`

| Property   | Description   |
|--|---|
| <code>pf.operational.mode</code>                         | <p>Configure the operational mode of the PingFederate node. The value <code>CLUSTERED_CONSOLE</code> denotes an administrative console node. The value <code>CLUSTERED_ENGINE</code> denotes a runtime engine node.</p> <p>A PingFederate cluster has only one administrative console node. When you scale your PingFederate infrastructure, set the <code>pf.operational.mode</code> property value to <code>CLUSTERED_ENGINE</code> to deploy additional PingFederate runtime engine nodes.</p> |
| <code>pf.cluster.tcp.remove.any.configured.values</code> | Remove any configured values. No IP addresses are required here.  |
| <code>pf.cluster.transport.tcp</code>                    | Set the value to <code>tcp</code> .   |
| <code>pf.cluster.*</code>                                | See the inline comments to configure the rest of the <code>pf.cluster.*</code> property values.   |

2. Configure dynamic discovery properties in the `<pf_install>/pingfederate/bin/jgroups.properties` file.

See the file's inline comments and the following tables.

### NATIVE\_S3\_PING properties in `jgroups.properties`

| Property                                       | Description   |
|--|---|
| <code>pf.cluster.NATIVE_S3_PING.region</code>  | <p>The name of the region in which discovery should be attempted.</p> <p>If no region is specified, only nodes in the same region as this node can be discovered.</p>   |
| <code>pf.cluster.NATIVE_S3_PING.bucket</code>  | <p>The name of the bucket in your Amazon S3 environment.</p> <p>For information about buckets, see the <a href="#">Create a bucket documentation</a> from Amazon.</p>   |
| <code>pf.cluster.NATIVE_S3_PING.cleanup</code> | <p>When set to <code>true</code> (the default), JGroups cleans up data when it detects a view change.</p> <p>For more information, see <a href="http://www.jgroups.org/manual4/index.html#FILE_PING">http://www.jgroups.org/manual4/index.html#FILE_PING</a>.</p> |



| Property                                     | Description   |
|--|---|
| <code>pf.cluster.NATIVE_WRITE_TIMEOUT</code> | Default value of <code>write_timeout</code> property where subclusters could fail to merge after a network partition. |

### DNS\_PING properties in `jgroups.properties`

| Property                                     | Description  |
|--|--|
| <code>pf.cluster.DNS_ADDITIONAL_QUERY</code> | <p>A DNS query to the DNS Server that obtains information about the cluster members. For example, <code>jgroups-dns-ping.myproject.svc.cluster.local</code>.</p> <p>For more information, see <a href="http://www.jgroups.org/manual4/index.html#_dns_ping">http://www.jgroups.org/manual4/index.html#_dns_ping</a>.</p> |

### AWS\_PING properties in `jgroups.properties`

| Property   | Description  |
|--|--|
| <code>pf.cluster.AWS_PING_FEDERATE_PORT</code>       | <p>The port on which PingFederate listens for cluster communication.</p> <p>The default value is <code>\${pf.cluster.bind.port}</code>, which pulls the value defined by the <code>pf.cluster.bind.port</code> property in the <code>&lt;pf_install&gt;/pingfederate/bin/run.properties</code> file.</p>   |
| <code>pf.cluster.AWS_PING_FEDERATE_PORT_RANGE</code> | <p>The number of additional ports that PingFederate can probe when attempting to connect to other nodes in the event that it fails to connect to the port specified by the <code>port_number</code> property.</p> <p>For example if the <code>port_number</code> property is 7600, a <code>port_range</code> property value of 0 means PingFederate will only try to connect at port 7600. If the <code>port_range</code> property value is set to 2, PingFederate will make up to two additional attempts, with the port value increasing by one each time. For example, if PingFederate fails to connect at port 7600, it will try at port 7601. If it fails again, it will try at port 7602.</p> <p>The default value is 0.</p> |
| <code>pf.cluster.AWS_PING_FEDERATE_REGIONS</code>    | <p>A comma-separated list of EC2 regions in which PingFederate will attempt discovery.</p> <p>If no regions are specified, only nodes in the same region as this node can be discovered. List all regions where you have nodes running.</p> <p>For information about regions, see the AWS documentation on <a href="#">Regions, Availability Zones, and Local Zones</a>.</p>   |
| <code>pf.cluster.AWS_PING_FEDERATE_TAGS</code>       | <p>A comma-separated list of EC2 tag names.</p> <p>When specified, only EC2 instances that have been assigned with the specified tags can be discovered. If multiple tags are specified, only EC2 instances that have been assigned with all tags can be discovered.</p> <p>For information about tags, see the <a href="https://docs.aws.amazon.com/AWSEC2/latest/UserGuide/Using_Tags.html">documentation</a> from Amazon (docs.aws.amazon.com/AWSEC2/latest/UserGuide/Using_Tags.html).</p>   |

| Property   | Description   |
|--|---|
| <code>pf.cluster.AWS_filters</code>  | <p>A semicolon separated list of key value pairs of system metadata.</p> <p>When specified, only EC2 instances that match the specified filters can be discovered. If multiple filters are specified, only EC2 instances that match all filters can be discovered.</p> <p>Note that you can enter a comma separated list of values for each filter. In this case, a filter is considered a match if one of the values is satisfied. For example, if you enter: <code>filters="instance-type=t2.small,t2.medium;architecture=x86_64"</code>, then only EC2 instances that have an <code>instance-type</code> of either <code>t2.small</code> or <code>t2.medium</code> and also an <code>architecture</code> of <code>x86_64</code> can be discovered.</p> <p>For information about filters, see the <a href="#">describe-instances documentation</a> from Amazon.</p> |
| <code>pf.cluster.AWS_ACCESS_KEY_ID</code> and <code>pf.cluster.AWS_SECRET_KEY</code> | <p>The access key and its secret key for the purpose of querying AWS for EC2 instances.</p> <p>Applicable and required only if permissions to <code>ec2:Describe*</code> actions are associated with the access key.</p> <p>Keys can be encrypted using the <b>obfuscate</b> utility (<code>obfuscate.bat</code> for Windows or <code>obfuscate.sh</code> for Linux), located in the <code>&lt;pf_install&gt;/pingfederate/bin</code> directory.</p>  |
| <code>pf.cluster.AWS_LOG_MESSAGES</code>   | <p>When set to <code>aws</code> (the default), error messages received from AWS are logged to the server log.</p>   |

### SWIFT\_PING properties in `jgroups.properties`

| Property  | Description  |
|---|--|
| <code>pf.cluster.SWIFT_PING_auth_type</code>  | The authentication type.   |
| <code>pf.cluster.SWIFT_PING_auth_url</code>   | The authentication URL.  |
| <code>pf.cluster.SWIFT_PING_auth_username</code> and <code>pf.cluster.SWIFT_PING_auth_password</code> | <p>The security credentials.</p> <p>Password can be encrypted using the <b>obfuscate</b> utility (<code>obfuscate.bat</code> for Windows or <code>obfuscate.sh</code> for Linux), located in the <code>&lt;pf_install&gt;/pingfederate/bin</code> directory.</p> |
| <code>pf.cluster.SWIFT_PING_auth_tenant</code>  | The name of your OpenStack Keystone tenant.  |
| <code>pf.cluster.SWIFT_PING_auth_inet</code>  | The name of the inet container.  |
|   | <p>For more information about each of the <code>SWIFT_PING</code> properties, see <a href="http://jgroups.org/manual4/index.html#_swift_ping">jgroups.org/manual4/index.html#_swift_ping</a>.</p>  |

| Property   | Description  |
|--|--|
| <code>pf.cluster.SWIFT.remove_(the_default)_JGroups_cleanup</code> | When set to <code>true</code> (the default), JGroups cleans up data when it detects a view change.<br><br>For more information, see <a href="http://jgroups.org/manual4/index.html#FILE_PING">jgroups.org/manual4/index.html#FILE_PING</a> . |

 **Note:**

To use a discovery protocol that PingFederate does not officially support, set the discovery protocol and class in `jgroups.properties`:

```
pf.cluster.discovery.protocol={discovery protocol}
pf.cluster.discovery.class={fully qualified class name}
```

For example, to use a discovery protocol called CUSTOM, add the following lines:

```
pf.cluster.discovery.protocol=CUSTOM
pf.cluster.discovery.class=org.jgroups.custom.discovery
```

To add a custom attribute to a protocol, use the following syntax in `jgroups.properties`:

```
pf.cluster.{discovery protocol}.{attribute name}={attribute value}
```

For example, to add a custom attribute called `bucket_prefix` to the `NATIVE_S3_PING` protocol and assign it the value `jgroups`, add the following line:

```
pf.cluster.NATIVE_S3_PING.bucket_prefix=jgroups
```

3. Start or restart PingFederate.
4. Repeat these steps for each node in the cluster.

### Migrating cluster discovery settings

To simplify future upgrades, you should migrate the cluster discovery settings in the `tcp.xml` file to the `jgroups.properties` file.

#### About this task

When you upgrade, PingFederate can set the default configuration of any new features in the supported discovery protocols. Because of this, you should use the `<pf_install>/pingfederate/bin/jgroups.properties` file to enable and configure cluster discovery settings. For example, if `NATIVE_S3_PING` gets a new discovery protocol configuration, a PingFederate upgrade could automatically add the following line to `jgroups.properties` as a reasonable default, letting you take advantage of the new configuration:

```
pf.cluster.NATIVE_S3_PING.new_configuration=reasonable-default-configuration-value
```

For more information, see [Dynamic cluster discovery](#) on page 214.

 **Note:**

The `tcp.xml` file has a `${DISCOVERY_TAG}` that replaces all content related to cluster discovery protocol configuration. The `jgroups.properties` file is where the discovery protocol configuration exists and lets you do what you previously did in `tcp.xml`, such as:

- Add custom configuration to discovery protocols that PingFederate officially supports, using the following syntax:

```
pf.cluster.{discovery protocol}.{attribute name}={attribute value}
```

For example, the following line adds a custom attribute called `bucket_prefix` with the value `jgroups` to the `NATIVE_S3_PING` protocol configuration:

```
pf.cluster.NATIVE_S3_PING.bucket_prefix=jgroups
```

- Add and configure a discovery protocol that PingFederate does not officially support, using the following syntax:

```
pf.cluster.discovery.protocol={discovery protocol}
pf.cluster.discovery.class={fully qualified class name}
```

For example, the following lines add a discovery protocol called `CUSTOM` and then add an attribute called `attr1` with the value `value1` to it:

```
pf.cluster.discovery.protocol=CUSTOM
pf.cluster.discovery.class=org.jgroups.custom.discovery
pf.cluster.CUSTOM.attr1=value1
```

The examples in the following table compare the syntax of cluster discovery settings in the `tcp.xml` file and the `jgroups.properties` file.

| Examples in <code>tcp.xml</code>  | Examples in <code>jgroups.properties</code>  |
|---|--|
| <pre>&lt;TCPPING   initial_hosts="\${pf.cluster.tcp.discovery.initial_hosts}   return_entire_cache="true"   port_range="0"/&gt;</pre>   | <pre>pf.cluster.TCPPING.initial_hosts= \${pf.cluster.tcp.discovery.initial_hosts} pf.cluster.TCPPING.return_entire_cache=true pf.cluster.TCPPING.port_range=0</pre>  |
| <pre>&lt;org.jgroups.aws.s3.NATIVE_S3_PING   region_name="us-east-1"   bucket_name="["...]"   endpoint="["...]"    remove_all_data_on_view_change="true"   write_data_on_find="true"/&gt;</pre> | <pre>pf.cluster.NATIVE_S3_PING.region_name=us- east-1 pf.cluster.NATIVE_S3_PING.bucket_name= pf.cluster.NATIVE_S3_PING.endpoint= pf.cluster.NATIVE_S3_PING.remove_all_data_on_view_change= pf.cluster.NATIVE_S3_PING.write_data_on_find=true</pre> |
| <pre>&lt;dns.DNS_PING   dns_query="["service name"].default.svc.cluster.local" /&gt;</pre>  | <pre>pf.cluster.DNS_PING.dns_query=["service name"].default.svc.cluster.local</pre>  |

To migrate the cluster discovery settings from the `tcp.xml` file to the `jgroups.properties` file:

### Steps

1. Open the `<pf_install>/pingfederate/bin/jgroups.properties` file and the `<pf_install>/pingfederate/server/default/conf/tcp.xml` file in a text editor.

2. In the `jgroups.properties` file:
  - a. Specify the cluster discovery protocol.

Example:

For example:

```
pf.cluster.discovery.protocol=NATIVE_S3_PING
```

- b. Specify the values for the cluster discovery protocol parameters that correspond with the values in the `tcp.xml` file.

Example:

For example:

```
pf.cluster.NATIVE_S3_PING.region_name=us-east-1
pf.cluster.NATIVE_S3_PING.bucket_name=
pf.cluster.NATIVE_S3_PING.endpoint=
pf.cluster.NATIVE_S3_PING.remove_all_data_on_view_change=true
pf.cluster.NATIVE_S3_PING.write_data_on_find=true
```

3. In the `tcp.xml` file, insert the `${DISCOVERY_TAG}` and remove the cluster discovery protocol settings.



**Note:**

Do not remove other settings from the `tcp.xml` file.

4. Repeat these steps for the other PingFederate nodes in the cluster.

## Deploying provisioning failover

After configuring outbound provisioning, you can set up one or more PingFederate failover servers specifically for provisioning backup.

About this task

Provisioning runtime processing and failover is independent of single sign-on (SSO) or single logout (SLO) runtime processing and server clustering. However, if you are already deploying, or have deployed, a cluster for federation-protocol runtime processing, you can use a subset of those servers for provisioning failover. Alternatively, you can mix the configuration or set up provisioning-failover servers independently.



**Note:**

Each server in the failover network must be configured to use the same relational database.



**CAUTION:**



Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

Steps

1. Select two or more runtime instances of PingFederate to configure for provisioning failover.

- For each server instance, edit provisioning properties in the `<pf_install>/pingfederate/bin/run.properties` file as follows:

| Property                                       | Description   |
|--|---|
| <code>pf.provisioner.mode</code>               | <p>The status of outbound provisioning. Allowed values are:</p> <p>OFF (default)<br/>Outbound provisioning is disabled.</p> <p>STANDALONE<br/>Provisioning is enabled, without failover.</p> <p>FAILOVER<br/>Provisioning is enabled, with failover.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>The value <code>STANDALONE</code> cannot be used for failover configuration. This property must be set to <code>FAILOVER</code> on the primary and secondary servers.</p> </div>  |
| <code>provisioner.node.id</code>               | <p>The unique index number of the provisioning server.</p> <p>Each server must have a unique index number, which is used to prioritize which server is currently active and which is next in line in case of a failure. Values are any number.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>The primary active primary server should have an index number of 1. The lowest value in the environment becomes the primary.</p> <p>These node IDs are not required to start at 1, but it is recommended that they start at 1. The node IDs for each node must increase sequentially. The number must not exceed the maximum integer value supported by Java, which is 2147483647. Initial start-up performance degradation may result if the node ID does not start at 1.</p> </div> |
| <code>provisioner.failover.grace.period</code> | <p>The time interval (in seconds) between the first indication that a node is dead and failover to the next server in line. The time period should be greater than the <b>Synchronization Frequency</b> set in the <b>System # Server # Protocol Settings # Outbound Provisioning</b> tab on the administrative console.</p> <p>The default value is 600, which is 10 minutes.</p>  |

 **Important:**

You must separately configure the failover properties in the `run.properties` file on each provisioning server, because the `run.properties` file is not copied among the provisioning servers automatically or as part of the **Replicate Configuration** process.

- Start or restart all of the PingFederate servers.

4. If you have not already done so, set up an external database to facilitate provisioning and then update the **Provisioning Data Store** setting on the **System # Server # Protocol Settings # Outbound Provisioning** tab. See [Configuring outbound provisioning settings](#) on page 911 for more information.
5. After configuration, if the provisioning servers belong to the same PingFederate clustered environment, go to the **System # Server**. In the **Cluster Management** window, replicate the new **Provisioning Data Store** setting to all nodes. If the provisioning servers are individual PingFederate servers, for each provisioning server, create a datastore connection to the same external database and update the **Provisioning Data Store** setting manually.

## Configuration synchronization

All nodes in a PingFederate clustered environment must have the same configuration settings, as set through the administrative console. You can use any of the following methods to ensure that configuration data is synchronized on all cluster nodes.

- Push from the administrative console.
- Deploy configuration archive.
- Make a RESTful API call to the `/cluster` administrative API endpoint.
- Make a web service call to the `/pf-mgmt-ws/ws/ConfigReplication` Connection Management Service endpoint.



### Note:

Changes made directly to configuration files must be replicated manually across the cluster, as applicable. If the PingFederate servers are running, you must restart them after you replicate the changes.

## Console configuration push

When multiple PingFederate servers are set up to run as a cluster, the administrative console provides a **Cluster Management** window.

Whenever applicable changes are made through the administrative console, a message appears at top of the console as a reminder to go to the **Cluster Management** window and to replicate the current console configuration to all server nodes in the cluster.



### Note:

You must also use the **Replicate Configuration** window to initiate the transmission of the license file from the console node to all server nodes.

The **Cluster Management** window is also useful for verifying the current member servers of your PingFederate cluster.

## Configuration-archive deployment

Uploading configuration archives is an alternate method of copying configurations to clustered PingFederate servers.

After you configure or reconfigure the console, you can also update cluster nodes by downloading a configuration archive from the **System # Server # Configuration Archive** window and then deploying it either manually or using a scripted process to the `<pf_install>/pingfederate/server/default/data/drop-in-deployer` directory on each cluster node or provisioning-failover server.



### Attention:

If you use the drop-in deployment process:

- PingFederate will not let you import the configuration archive of an older or newer version, and to ensure successful importation of the configuration archive file with this process, you must rename the file `data.zip`.
- On startup, the heartbeat endpoint will not return 200 until the archive import completes. If you have configured a health check or probe that can trigger a restart of the server, crash loop behavior can result. Review the configuration of these checks to ensure time thresholds are set appropriately.

A configuration archive contains the same information sent during the configuration push from the administrative console described in [Console configuration push](#) on page 223. However, configuration-archive deployment also provides for scheduling and scripting cluster synchronization.

#### Runtime state-management services

If you have configured one of the following runtime state-management services on the engine nodes, you must manually migrate the configuration files to the engine nodes. The configuration files are located at `<pf_install>/pingfederate/server/default/conf`

#### Configuration file and service implementation

| Configuration file                                    | RPC-based service implementation   |
|---|--|
| <code>cluster-account-locking.conf</code>             | <a href="#">Account Locking Service</a> on page 207                            |
| <code>cluster-artifact.conf</code>                    | <a href="#">Artifact-Message Persistence and Retrieval Service</a> on page 205 |
| <code>cluster-assertion-replay-prevention.conf</code> | <a href="#">Assertion Replay Prevention Service</a> on page 204                |
| <code>cluster-idp-session-registry.conf</code>        | <a href="#">IdP Session Registry Service</a> on page 203                       |
| <code>cluster-inter-request-state.conf</code>         | <a href="#">Inter-Request State-Management (IRSM) Service</a> on page 202      |
| <code>cluster-session-revocation.conf</code>          | <a href="#">Back-Channel Session Revocation Service</a> on page 206            |
| <code>cluster-sp-session-registry.conf</code>         | <a href="#">SP Session Registry Service</a> on page 203                        |

## Administrator's Reference Guide

---

This guide provides information about using PingFederate to deploy a secure internet single sign-on (SSO) solution based on the latest security and e-business standards.

Use this guide to learn about the following:

- [Attribute mapping expressions](#) on page 225
- [Authentication policies](#) on page 231
- [Bundled adapters](#) on page 299
- [Customer IAM configuration](#) on page 357
- [Customizing assertions and authentication requests](#) on page 390



- [Fulfillment by datastore queries](#) on page 397
- [IdP-to-SP bridging](#) on page 408
- [Identity provider SSO configuration](#) on page 419
- [OAuth configuration](#) on page 518
- [Security management](#) on page 656
- [Self-service user account management](#) on page 703
- [Service provider SSO configuration](#) on page 712
- [System administration](#) on page 820
- [System settings](#) on page 909
- [Troubleshooting](#) on page 1024
- [WS-Trust STS configuration](#) on page 1041

## Attribute mapping expressions

---

As of PingFederate 10.1, the use of expressions is enabled by default. You can use the Expression Admin administrative role to map user attributes by using OGNL expressions.

If you upgraded to PingFederate 10.1 from a previous version, the use of expressions is still enabled or disabled based on the configuration in the earlier version. Also, when upgrading PingFederate to 10.1 or later, administrative users who were granted the Admin role in the earlier installation are granted the Expression Admin role automatically.

### Enabling and disabling expressions

As of PingFederate 10.1, the use of expressions is enabled by default. You can manually disable the use of expressions by editing a configuration file.

About this task

When upgrading PingFederate to 10.1 or later, administrative users who were granted the Admin role in the earlier installation are granted the Expression Admin role automatically.

You can disable the use of expressions by setting `evaluateExpressions` to false as described in the following procedure. Also, go to **System # Server # Administrative Accounts** and remove the **Expression Admin** role from all Admin users. Doing this will prevent Admin users from entering expressions into PingFederate if the `evaluateExpressions` element is set to true at a later time. For more information, see [Administrative accounts](#) on page 914.



#### Important:

If the current configuration contains expressions, disabling the feature causes errors during runtime processing.

#### Steps

1. Edit the `org.sourceid.common.ExpressionManager.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.



#### Note:

If you have a clustered PingFederate environment, edit the configuration file on the console node.

2. Change the value of the element named `evaluateExpressions` to either `true` or `false` and save the file.

```
<?xml version="1.0" encoding="UTF-8"?>
<config xmlns="http://www.sourceid.org/2004/05/config">
  <item name="evaluateExpressions">true</item>
</config>
```



**Note:**

The absence of an installed default value does not necessarily disable the use of expressions. You can successfully import configuration archives containing expressions to facilitate backward compatibility when no value is present, and further use of the feature is enabled. The term “silent” is used for this condition in the server log.

3. If you have a stand-alone PingFederate environment, start or restart PingFederate.



**Tip:**

If you are enabling expressions to use for mapping outbound provisioning attributes, you do not need to restart the PingFederate server.

4. If you have a clustered PingFederate environment:
  - a. Sign on to the PingFederate administrative console.
  - b. From **System # Server # Cluster Management**, click **Replicate Configuration**.

## Result

When you enable expressions, they are available for use in multiple locations:

- The **Source** list under each of the administrative-console contract fulfillment windows
- The **Show Advanced Criteria** section on the **Issuance Criteria** window following each of the administrative-console contract fulfillment windows
- The provisioning attribute-mapping window when the **Outbound Provisioning** protocol is enabled

## Construct OGNL expressions

Use OGNL expressions and syntax to evaluate and manipulate attribute values and return information based on the results.

OGNL is based on the Java programming language. You can transform a range of values into a text description or do the same for a sequence of ranges.

Use the # symbol to reference OGNL variables. For an identity provider (IdP), PingFederate provides predefined OGNL variables for IdP-adaptor attributes, any attributes retrieved from datastores, and attributes for token authorization. For a service provider (SP), variables are available for attributes received in an assertion, an attribute query, and attributes for token authorization. For example, you can retrieve the **SAML\_SUBJECT** value with `#SAML_SUBJECT`.



**Note:**

Use the following construction for any attributes from any source that contain special characters that cannot be parsed by OGNL: `#this.get("<attribute_name>")`.



**Note:**

Because OGNL uses the “at” symbol (@) to reference static Java methods, expressions containing the symbol must be enclosed in double quotes. Otherwise, expression parsing fails. For example, use `#SAML_SUBJECT="usr@msn.com"`, not `#SAML_SUBJECT=usr@msn.com`.

### Data store syntax

For datastore attributes with an attribute source ID, use the `#this.get("ds.attr-source-id.attribute_name")` syntax.

For datastore attributes without an attribute source ID, use the `#this.get("ds.attribute_name")` syntax.

### Other variable syntax

To access mapped attributes, use the `#this.get("mapped.attribute_name")` syntax.

To access most context attributes, use the `#this.get("context.attribute_name")` syntax.

To access the HTTP Request context attribute, use the `#this.get("context.HttpServletRequest").getObjectValue()` syntax.



#### Note:

The returned value is an instance of `javax.servlet.http.HttpServletRequest`. See <http://docs.oracle.com/javaee/7/api/javax/servlet/http/HttpServletRequest.html>.

### Sample OGNL expressions

OGNL expressions provide the flexibility to evaluate and manipulate values. These applications include using the following expressions to determine net worth, form a single sign-on (SSO) token, verify a user's group, retrieve a value from an HTTP request object, and check the authenticity of a client certificate..

#### General

In this sample expression, the value of the attribute “net-worth” is transformed first to eliminate any dollar signs or commas, then the result is evaluated to determine whether the user's net worth falls into a “bronze,” “silver,” or “gold” category.

```
#result=#this.get("net-worth").toString(),
#result=#result.replace("$", ""),
#result=#result.replace(",", ""),
#result < 500000 ? "bronze" :
#result < 1000000 ? "silver" : "gold"
```

#### Multivalued attribute

```
new org.sourceid.saml20.adapter.attribute.AttributeValue( {"Blue", "Gray",
"Pink"})
```

This expression formulates a multivalued attribute in an SSO token.

```
<saml:Attribute Name="clrs" ...>
  <saml:AttributeValue ...>Blue</saml:AttributeValue>
  <saml:AttributeValue ...>Gray</saml:AttributeValue>
  <saml:AttributeValue ...>Pink</saml:AttributeValue>
</saml:Attribute>
```

and

```
{
  ...,
  "clrs": [
    "Blue",
    "Gray",
    "Pink"
  ],
  ...
}
```

In these truncated samples, `clrs` is the multivalued attribute. The former is a SAML assertion through a SAML service provider (SP) connection. The latter is a JSON web token (JWT) through a WS-Federation SP connection using JWT as the token type.

### Token authorization

This expression verifies whether a user is a member of the “Engineering” or “Marketing” group.

```
#this.get("ds.memberOf") != null?
(
  (
    #this.get("ds.memberOf").hasValue("CN=Eng,OU=E,DC=contoso,DC=com")
    &&
    #this.get("context.VirtualServerId").toString().equals("Engineering")
  )
  ||
  (
    #this.get("ds.memberOf").hasValue("CN=Mkt,OU=M,DC=contoso,DC=com")
    &&
    #this.get("context.VirtualServerId").toString().equals("Marketing")
  )
):false
```

The following expression extracts the domain information out of an email address (`mail`) and returns true if it matches a specific domain.

```
#this.get("mail") != null?
(
  #email=#this.get("mail").toString(),
  #atSign="@",
  #at=#mail.indexOf(#atSign),
  #at > 0?
  (
    #domain=#mail.subject(#at+1),
    #domain.matches("(?i)example.com")
  ):false
):false
```



#### Note:

Line breaks are inserted to both samples for readability only. You must enter statements calling methods whose arguments are enclosed in quote on a single line.

This sample expression returns true when the IP address of the client is within the specified CIDR range of `fe80::74da:14b:76d1:eba3/128`.

```
#isWithinCidrRange =
  @com.pingidentity.sdk.CIDROperations@isInRange(#this.get("context.ClientIp"), "fe80::74
```

The `isInRange` method supports both IPv4 and IPv6 CIDR notations.

### HTTP request context

You can use the following example to retrieve a value from an HTTP request object. The expression retrieves the **User-Agent** HTTP header value and compares it against a value required for token authorization.

```
#this.get("context.HttpRequest").getObjectValue().getHeader("User-
Agent").equals("somevalue")
```

### STS client authentication context

This security token service (STS) SSL Client Certificate Chain example checks that the issuer of the client certificate matches the specified distinguished name (DN).

```
#this.get("context.StsSSLClientCertChain").getObjectValue()
[1].getSubjectX500Principal().equals(new
  javax.security.auth.x500.X500Principal("CN=Ping Identity
  Engineering,OU=Engineering,O=Ping Identity,L=Denver,ST=CO,C=USA"))
```



#### Note:

`#this.get("context.StsSSLClientCertChain").getObjectValue()` returns an array of `java.security.cert.X509Certificate` instances. This array starts with the client certificate itself.

For more information, see <https://docs.oracle.com/javase/8/docs/api/java/security/cert/X509Certificate.html>.

### Issuance criteria and multiple virtual server IDs

Virtual server IDs offer critical information and functionality in the context of connections.

When you use virtual server IDs to connect to multiple environments in one connection, verifying at runtime the virtual server ID in conjunction with other end-user attributes, such as group membership, protects against unauthorized access.

For instance, both the sales and the support departments of `contoso.com`, the identity provider (IdP), have their own departmental subdomains, `sales.contoso.com` and `support.contoso.com`. The service provider (SP) identifies both environments under the parent domain, `contoso.com`.

In this scenario, you can configure the PingFederate IdP server to include both `sales.contoso.com` and `support.contoso.com` as the virtual server IDs in the SP connection.

If you use one IdP adapter to authenticate end users from both departments, use an OGNL expression to cross-check the virtual server ID information in the request and the end user's group membership information.

```
#this.get("ds.memberOf") !=null?
(
  (
    #this.get("ds.memberOf").toString().matches("(?
i)CN=Eng,OU=E,DC=contoso,DC=com")
    &&
    #this.get("context.VirtualServerId").toString()=="Engineering"
```

```

) ||
(
  #this.get("ds.memberOf").toString().matches("(?
i) CN=Mkt, OU=M, DC=contoso, DC=com")
  &&
  #this.get("context.VirtualServerId").toString()=="Marketing"
)
):false

```



#### Note:

Line breaks are inserted for readability only. You must enter statements calling methods whose arguments are enclosed in quotes on a single line.

### Expressions for OAuth and OpenID Connect uses cases

You can use OGNL expressions to retrieve various request-attributes through the HTTP Request Java object.

#### Client authentication method

The following sample expression retrieves the authentication method that a client uses. This sample expression is applicable to all clients.

```
#this.get("context.HttpRequest").getObjectValue().getAttribute("com.pingidentity.oauth.o
```

#### Private key JSON web token (JWT)

In the following sample expressions, the former retrieves a claim value from the private key JWT with which a client authenticates and the latter retrieves the private key JWT itself. They are only applicable to clients using the `private_key_jwt` authentication method.

##### Retrieving the `aud` claim value

```

#claims =
  #this.get("context.HttpRequest").getObjectValue().getAttribute("com.pingidentity.o
#claims.get("aud")

```

##### Retrieving the entire private key JWT

```
#this.get("context.HttpRequest").getObjectValue().getParameter("client_assertion")
```

## Using the OGNL edit window

Access the in-line OGNL editor and test expressions.

#### About this task

An in-line editor is available for OGNL expressions. The editor validates the expression and allows an administrator to enter input values and test the resulting output.

## Steps

- To reach the OGNL editor, click **Edit** under **Actions** for an expression on any of the **Attribute Fulfillment** windows or click **Test** in the **Show Advanced Criteria** section on the **Issuance Criteria** window.



### Note:

The test function does not work for the `context.httpRequest` attribute because its value is an object rather than text.

- To test an expression:
  - a. Enter an input value in the **Value** text box associated with the attribute.
  - b. Click the **Test** link near the bottom-right of the window.

If the expression contains no errors, the result appears under **Test Results**.



### Important:

If you want to save changes to an expression, click **Update** under **Actions**. To discard changes, click the **Cancel** link under **Actions**. Click the **Cancel** button near the bottom of the window to discard all changes you made in the current task.


## Authentication policies

---

Authentication policies are an optional configuration in PingFederate and help administrators implement complex authentication requirements.

As needed, administrators can configure one or more authentication selector instances to evaluate conditions of the requests and define policies to route the request to a series of approved authentication sources or deny the request based on the results from the authentication selector instances, authentication sources, or both. Administrators can also reuse an authentication policy by ending it with an authentication policy contract or a local identity profile and then applying the authentication policy contract in multiple use cases.

## OAuth/OIDC and SAML browser authentication flows





## Processing steps

1. A client initiated authentication request is sent to PingFederate.
2. PingFederate evaluates the [authentication policy](#), which defines the decision to route a request through a series of approved authentication sources.
3. The [authentication policy](#) is mapped to the [policy contract](#).

The authentication policy determines how the user signs on and drives the authentication experience, such as form based authentication, Kerberos authentication, or MFA.

### **Note:**

PingFederate can enforce authentication policies based on the requesting OAuth client as well as only enforce policy rules for authentication policy contract branches that are mapped to an access token manager (ATM). For more information, see [Policies](#).

4. For an OIDC/OAuth flow, the policy contract checks the attribute contract connected to authentication sources or datastores, or for a SAML connection, the policy contract checks the SAML connection tied to the policy contract.

### **Important:**

For an OIDC authentication flow, you must set up an OIDC application in PingFederate. For more information, see [Setting up an OIDC application in PingFederate](#).

5. The authentication request either succeeds or fails based on the results of the policy evaluation and authentication requirements.

## Selectors

Authentication selectors provide a plugin capability for PingFederate to evaluate various conditions related to the requests. PingFederate comes bundled with a set of authentication selectors.

As an example, you can create an HTTP Header Authentication Selector to detect mobile browsers, a CIDR Authentication Selector to evaluate whether the users' IP addresses fall within your internal network ranges, or an HTTP Request Parameter Authentication Selector to identify identity provider (IdP) connections based on the `PartnerIdpId` parameter values provided in the service provider (SP)-initiated SSO requests.

Alternatively, you can create custom authentication selectors that suit your needs by using the PingFederate SDK.

### **Tip:**

The Javadoc for is located in the `<pf_install>/pingfederate/sdk/doc` directory.

## Managing authentication selector instances

You can manage authentication selectors on the **Selectors** window in the PingFederate administrative console.

### Steps

- Go to **Authentication # Policies # Selectors**.
- To configure a new instance, on the **Selectors** window, click **Create New Instance**.
- To modify an existing instance, select it by its name under **Instance Name**.

- To remove an existing instance or to cancel the removal request, click **Delete** or **Undelete**.

**Note:**

You can only remove a selector instance if it is not deployed in any authentication policy.

**Choosing a selector type**

Choose an authentication selector instance from the list of available selector types.

## Steps

1. Go to **Authentication # Policies # Selectors**.
2. Click **Create New Instance**.
3. In the **Instance Name** field, enter an instance name.
4. In the **Instance ID** field, enter an instance ID.
5. From the **Type** list, select the desired type of authentication selector.

**Configuring an authentication selector instance**

The configuration of an authentication selector instance varies depending on the authentication selectors deployed on your server.

## Steps

1. Refer to subsequent topics for configuration steps of each of the bundled authentication selectors.
2. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

*Configuring the CIDR Authentication Selector*

The CIDR Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on the IP address of an incoming single sign-on request.

## About this task

Use this selector in authentication policies to choose from authentication sources that share a similar level of assurance, such as among multiple HTML Form Adapter instances or between a Kerberos Adapter instance and an X.509 identity provider (IdP) Adapter instance. For example, use this selector in authentication policies to route internal requests to a Kerberos Adapter instance.

## Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.

4. On the **Authentication Selector** tab, click **Add a new row to 'Networks'** and enter a network range. Click **Update**.

**Note:**

To see the **Add a new row to 'Networks'** option, ensure you have set the **Authentication Selector Instance** type to **CIDR Authentication Selector** on the **Type** tab.

Example:

Sample IPv4 network range

Enter `192.168.101.0/24` to cover 256 IPv4 addresses, ranging from `192.168.101.0` through `192.168.101.255`.

Sample IPv6 network range

Enter `2001:db8::/123` to cover 32 IPv6 addresses, ranging from `2001:db8::` through `2001:db8::1f`.

5. Optional: Repeat the previous step to add more network ranges.

**Note:**

Display order does not matter.

**Tip:**

If you want to include all IPv4 addresses for testing, add two separate ranges: `0.0.0.0/1` and `128.0.0.0/1`. The CIDR Authentication Selector interprets a specification of `0.0.0.0/0` as an empty range rather than as a wildcard for all addresses.

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

6. Optional: Enter a **Result Attribute Name** value.

**Note:**

This field provides a means to indicate in the SAML assertion whether a network range was matched during processing; the value is either *Yes* or *No*. Any authentication sources configured as a result of this authentication selector must have their attribute contract extended with the value of the **Result Attribute Name** field to use its value to fulfill an attribute contract or for issuance criteria.

7. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

## Result

When you place this selector instance as a checkpoint in an authentication policy, it forms two policy paths: **Yes** and **No**. If the IP address of an incoming single sign-on (SSO) request matches one of the defined network ranges, the selector returns true. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **Yes**. If the IP address of an incoming SSO request matches none of the defined network ranges, the selector returns false. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **No**.

### Configuring the Cluster Node Authentication Selector

The Cluster Node Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on the PingFederate cluster node that is servicing the request in authentication policies.

#### About this task

For example, this selector allows you to choose whether Integrated Windows Authentication (IWA) is attempted based on the PingFederate cluster node with which a Key Distribution Center (KDC) is associated.

#### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. On the **Authentication Selector** window, select the **Field Value** on which to branch policy paths. The authentication selector provides a means of choosing authentication sources at runtime based on the cluster node on which it is executing.

#### Node Index

Select **Node Index** to use the `pf.cluster.node.index` value specified in `run.properties`.

#### Node Tag

Select **Node Tag** to use the `node.tags` values specified in `run.properties`.

5. On the **Selector Result Values** window, specify the relevant node index or node tag values.



#### Note:

Each selector result value forms a policy path when you place this selector instance as a checkpoint in an authentication policy.

- a. In the **Result Values** field, enter a node index or node tag value based on your cluster configuration and click **Add**. This value should correspond to a node index or node tag of one of the engine nodes in the cluster.
- b. Optional: Add more values to differentiate criteria for authentication selection.



#### Note:

Display order does not matter.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Click **Delete** to remove an entry.

6. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

### *Configuring the Connection Set Authentication Selector*

The Connection Set Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on a match found between the target service provider (SP) connection used in a single sign-on (SSO) request and SP connections configured within PingFederate.

#### About this task

This selector allows you to override connection authentication selection on an individual connection basis in one or more authentication policies.

#### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. From the **Type** list, make sure you select **Connection Set Authentication Selector**.
5. Click **Next**. In the **Authentication Selector** window, click **Add a new row to 'Connections'**.
6. From the **Connection** list, select an SP connection and click **Update**.
7. Optional: Repeat the previous step to add more connections. Display order does not matter.  
Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.
8. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

#### Result

When you place this selector instance as a checkpoint in an authentication policy, it forms two **Yes** and **No** policy paths. If the invoking SP connection matches one of the connections from the set, the selector returns true. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **Yes**. If the invoking SP connection matches none of the connections from the set, the selector returns false. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **No**.

### *Configuring the Extended Property Authentication Selector*

The Extended Property Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on a match found between a selector result value and an extended property value from the invoking browser-based SSO connections or OAuth client.

#### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. On the **Authentication Selector** tab, select a property from the **Extended Property** list.



#### **Note:**

The extended property is the property that this selector instance should look for from the invoking connection or client, and compare the populated property value, or values if it is a multivalued extended property, against the selector result values defined in this selector instance.

5. On the **Selector Result Values** tab, specify one or more expected result values.
  - a. Enter the exact, case-sensitive, value under **Result Values** and click **Add**.
  - b. Optional: Add more values to differentiate criteria for authentication selection.

Display order might matter.

Expected result values are always sorted alphabetically in ascending order here.

When you place this selector instance as a checkpoint in an authentication policy, each selector result value forms a policy path. The display order of the resulting policy paths matches the display order here, which may impact the policy outcome. When the policy engine reaches this selector instance, the selector starts from top to bottom. As soon as it finds a match, it exits and returns true. The matching mechanism varies, depending on the type of the extended property selected in step 4.

#### Matching mechanism for single-value extended properties

The selector compares the property value populated in the invoking connection or client against the configured selector result value. When multiple selector result values exist, the selector starts from the top. If the current selector result value is a case-sensitive exact match, it returns true and exits. Otherwise, it moves on to the next selector result value and tries again.

For example, assume this selector instance, named `ExtProps`, is configured with expected result values of `Alpha`, `Bravo`, and `Charlie`. The invoking connection is populated with an extended property value of `Bravo`, and this selector instance is placed as a checkpoint in an authentication policy as follows.

```
ExtProps
+--Alpha
| <policy path>
|
+--Bravo
| <policy path>
|
+--Charlie
  <policy path>
```

Given this setup, the selector returns true and exits when it reaches the second selector result value. The policy engine regains control of the request and proceeds with the policy path configured for the selector result value of `Bravo`.

#### Matching mechanism for multivalued extended properties

The selector compares the property values populated in the invoking connection or client against the configured selector result value. If any one of the property values from the invoking connection or client is a case-sensitive exact match, the selector returns true and exits. When multiple selector result values exist, the selector starts from the top. If the current selector result value is a case-sensitive exact match to any one of the property values from the invoking connection or client, it returns true and exits. Otherwise, it moves on to the next selector result value and tries again.

For example, assume the previous selector instance remains. The invoking connection is populated with extended property values of `Alpha` and `Charlie`, and this selector instance remains as a checkpoint in an authentication policy.

In this scenario, the selector returns true and exits when it reaches the first selector result value. The policy engine regains control of the request and proceeds with the policy path configured for the selector result value of `Alpha`. Even though `Charlie`, the expected selector result value, is also a case-sensitive exact match to `Charlie`, one of the property values from the invoking connection, because the selector has already exited and returned

control to the policy engine when it reaches `Alpha`, the policy engine will never execute the policy path configured for the selector result value of `Charlie`.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Click **Delete** to remove an entry.

6. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

#### Example

1. Go to **System # Server # Extended Properties**.
2. On the **Extended Properties** window, define a multivalued extended property, and name it `configStatus`.
3. Create an SP connection with the following characteristics:
  - On the **Extended Properties** window, add two values for the `configStatus` extended property: `DEV` and `TEST`.
  - On the **Attribute Source Mapping** window, map an authentication policy contract to the service provider (SP) connection. The policy contract name is `APC`.
4. Create an instance of the Extended Property Authentication Selector with the following characteristics:
  - On the **Type** tab, name the selector instance `ExProps`.
  - On the **Authentication Selector** tab, select `configStatus` from the list.
  - On the **Selector Result Values** tab, enter `DEV` and `TEST`.
5. Create and activate the following identity provider (IdP) authentication policy.

```
ExtProps
+--DEV
|   OpenToken
|   +--Fail: Done
|   +--Success: APC
|
+--TEST
   HTML
   +--Fail: Done
   +--Success: APC
```

Configure each `APC` to fulfill values obtained from its preceding adapter instance.

When processing SSO requests intended for this SP connection, because the policy engine is able to match one of the populated property values, `DEV`, from the SP connection to the first selector result value, also `DEV`, it will always invoke the `OpenToken` IdP Adapter instance based on the `DEV` policy path. The `TEST` policy path is never executed for this SP connection.

On the other hand, if you remove `DEV`, an extended property value, from the SP connection, the policy engine will route SSO requests intended for this SP connection to the `HTML Form` Adapter instance based on the `TEST` policy path. The `DEV` policy path is never executed for this SP connection.

#### *Configuring the HTTP Header Authentication Selector*

The HTTP Header Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on a match found in a specified HTTP header.

#### About this task

Use this selector in one or more authentication policies to choose from authentication sources that share a similar level of assurance, such as among multiple HTML Form Adapters or between a Kerberos Adapter

and an X.509 Adapter. For example, use this selector to choose an authentication source based on the user's browser identified by the **User-Agent** HTTP header.



**Important:**

Do not use this selector to determine whether an authentication source with a higher level of assurance should be bypassed because HTTP request headers could potentially be forged.

### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. On the **Authentication Selector** tab, click **Add a new row to 'Results'**.
5. Enter an expression for use when inspecting the HTTP header value of the target HTTP header under **Match Expression**, and click **Update**.



**Note:**

Wildcard entries are allowed, such as `*value*`.

6. Optional: Repeat the previous step to add more expressions. Display order does not matter.



**Note:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

7. In the **Header Name** field, enter the type of HTTP header you want the selector to inspect. This field is not case-sensitive.
8. Optional: To disable case-sensitive matching between the HTTP header values from the requests and the **Match Expression** values specified on this window, clear the **Case-Sensitive Matching** check box.  
  
The **Case-Sensitive Matching** check box is selected by default.
9. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

### Result

When you place this selector instance as a checkpoint in an authentication policy, it forms two policy paths: **Yes** and **No**. If the value of the specified HTTP header matches one of the configured values, the selector returns true. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **Yes**. If the value of the specified HTTP header matches none of the configured values, the selector returns false. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **No**.



Example

Example

To detect the most common browsers based on the **User-Agent** HTTP request header, configure an HTTP Header Authentication Selector instance as follows.

1. Enter these entries under **Match Expression**.

| Browser | Expression |
|---------|------------|
| Chrome  | *Chrome*   |
| Firefox | *Firefox*  |
| Safari  | *Safari*   |

2. In the **Header Name** field, enter `User-Agent`.

#### *Configuring the HTTP Request Parameter Authentication Selector*

The HTTP Request Parameter Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on query parameter values.

About this task

Use this selector in one or more authentication policies to choose from authentication sources that share a similar level of assurance, such as among multiple instances of the HTML Form Adapter or between a Kerberos Adapter instance and an X.509 Adapter instance. For example, use an instance of this selector to choose an authentication experience based on the reward program information indicated by a query parameter in the single sign-on (SSO) request.



#### **Important:**

Do not use this selector to determine whether an authentication source with a higher level of assurance should be bypassed because query parameters could potentially be forged.

Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. On the **Authentication Selector** tab, configure the applicable selector instance settings.
  - a. Enter the exact, case-sensitive name of the request parameter in the **HTTP Request Parameter Name** field.



#### **Important:**

The policy engine is capable of tracking HTTP request parameters that it receives from the initial request and making them available to selector instances throughout the policy. If you plan on using this selector instance as the second, or subsequent, checkpoint in at least one

authentication policy, add the **HTTP Request Parameter Name** value on the **Tracked HTTP Parameters** window. For more information, see [Defining authentication policies](#) on page 254.

- b. Optional: To disable case-sensitive matching between the HTTP request parameter values from the requests and the **Match Expression** values specified on the **Selector Result Values** window, clear the **Case-Sensitive Matching** check box.

 **Note:**

The **Case-Sensitive Matching** check box is selected by default.

- c. Optional: Enable policy paths to handle additional scenarios.  
For more information, see the following table.

| Field                                | Description   |
|--------------------------------------|---|
| Enable 'Any' Result Value            | <p>Each configured selector result value forms a separate authentication policy path.</p> <p>Select this check box if you want to enable a single policy path for the scenario where the HTTP request parameter value matches any one of the configured selector result values.</p> <p>This check box is not selected by default.</p>     |
| Enable 'No Match' Result Value       | <p>Selector evaluation fails and the next applicable authentication policy is executed when the HTTP request parameter value does not match any of the configured selector result values.</p> <p>Select this check box if you want to enable a policy path to handle this scenario.</p> <p>This check box is not selected by default.</p> |
| Enable 'Not in Request' Result Value | <p>Selector evaluation fails and the next applicable authentication policy is executed if the HTTP request parameter is not found.</p> <p>Select this check box if you want to enable a policy path to handle this scenario.</p> <p>This check box is not selected by default.</p>  |

5. On the **Selector Result Values** window, enter a request parameter value under **Result value**, and then click **Add**.

 **Note:**

Wildcard entries are allowed, such as `*value*`.

 **Important:**

A more specific match is a better match and an exact match is the best match.

6. Optional: Repeat the previous step to add more request parameter values. Display order does not matter.

**Note:**

If you have not enabled the **Any** policy path in [step 4c](#), each selector result value forms a policy path when you place this selector instance as a checkpoint in an authentication policy.

If you have enabled the **Any** policy path, only one policy path is formed.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Click **Delete** to remove an entry.

7. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

## Example

## Example

Suppose you enter three selector result values, *Central*, *Eastern*, and *Southern*, on the **Selector Result Values** window, as illustrated in the following screen capture.

If you have not enabled any additional policy paths in [step 4c](#), as you place this selector instance as a checkpoint in an authentication policy, three policy paths are extended from the selector instance, one for each of the configured selector result values.

*Configuring the OAuth Client Set Authentication Selector*

The OAuth Client Set Authentication Selector selector allows you to override client authentication select on an individual client basis in one or more authentication policies.

## About this task

The selector enables PingFederate to choose configured authentication sources or other selectors based on a match found between the client information in an OAuth request and the OAuth clients configured in the PingFederate OAuth authorization server (AS).

**Note:**

The OAuth Client Set Authentication Selector is only applicable to OAuth clients using the authorization code or implicit flow.

## Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.

4. On the **Authentication Selector** tab, click **Add a new row to 'Clients'**.

**Note:**

If you do not see **Add a new row to 'Clients'**, go back to the **Type** tab and ensure you have selected **OAuth Client Set Authentication Selector** from the **Type** list.

5. From the **Client ID** list, select an OAuth client and click **Update**.
6. Optional: Repeat the previous step to add more clients.

Display order does not matter.

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

7. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

### Result

When you place this selector instance as a checkpoint in an authentication policy, it forms two policy paths: **Yes** and **No**. If the invoking client matches one of the clients from the set, the selector returns true. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **Yes**. If the invoking client matches none of the clients from the set, the selector returns false. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **No**.

#### *Configuring the OAuth Scope Authentication Selector*

The OAuth Scope Authentication Selector enables PingFederate to choose configured authentication sources or other selectors based on a match found between the scopes of an OAuth authorization request and scopes configured in the PingFederate OAuth authorization server (AS).

### Before you begin

Go to **System # OAuth Settings # Authorization Server Settings** and configure one or more scopes.

### About this task

This selector allows you to control the strength of authentication based on client access requirements. For example, if a client requires write access to a resource, you can deploy an instance of the OAuth Scope Authentication Selector in one or more authentication policies to choose an adapter that offers a stronger form of authentication, such as the X.509 client certificate, instead of username and password.

### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.

4. On the **Authentication Selector** tab, select the required scopes, scope groups, or both.

**Note:**

Both common and exclusive scopes are available for selection.

**Important:**

This selector matches only scopes from OAuth authorization requests to the authorization endpoint, `/as/authorization.oauth2`. SAML single sign-on (SSO) requests do not match this authentication selector's criteria and result in a returned result value of `No`. If you are using this selector and selectors specific to SAML connections, list this selector first in the mapping list so that it takes precedence for OAuth without disrupting selector logic on SAML connections.

5. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

## Result

When you mark this selector instance as a checkpoint in an authentication policy, it forms two policy paths: **Yes** and **No**. If the requested scopes satisfy all the selected scopes, the selector returns true. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **Yes**. If the requested scopes do not satisfy all the selected scopes, the selector returns false. The policy engine regains control of the request and proceeds with the policy path configured for the result value of **No**.

*Configuring the Requested AuthN Context Authentication Selector*

The Requested AuthN Context Authentication Selector enables PingFederate to choose configured authentication sources or other selectors.

## About this task

This selector chooses authentication sources or selectors based on the authentication contexts requested by a service provider (SP) for browser single sign-on (SSO) requests, or a relying party (RP) for OAuth with OpenID Connect use cases in authentication policies.

For browser SSO, this authentication selector works in conjunction with SP connections with SAML 2.0 only, using the SP-initiated SSO profile. Other browser SSO protocols do not support authentication context. For OAuth, clients supporting the OpenID Connect protocol must include the optional `acr_values` parameter in their authorization requests to indicate their preferred authentication context, or contexts.

## Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.
2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.

4. On the **Authentication Selector** tab, configure the applicable selector instance settings.
  - a. Select the **Add or Update AuthN Context Attribute** check box if you want to update the authentication context attribute value with the value specified in the **Selector Result Values** tab.  
Result:

When selected, which is the default, the check box on this window provides a means to:

- Add the value of the authentication context determined by the selector into the SAML assertion.
  - When applicable, replace any value returned from the associated adapter instance with the selector-result value.
- b. Optional: Enable policy paths to handle additional scenarios.  
For more information, refer to the following table.

| Field                                | Description  |
|--------------------------------------|--|
| Enable 'No Match' Result Value       | <p>Selector evaluation fails and the next applicable authentication policy is executed if the requested authentication context does not match any of the configured selector result values.</p> <p>Select this check box if you want to enable a policy path to handle this scenario. This check box is not selected by default.</p> |
| Enable 'Not in Request' Result Value | <p>Selector evaluation fails and the next applicable authentication policy is executed if no requested authentication context is found.</p> <p>Select this check box if you want to enable a policy path to handle this scenario. This check box is not selected by default.</p>   |

5. On the **Selector Result Values** window, specify the authentication contexts to use as the criteria.
  - a. Enter the exact, case-sensitive parameter value under **Result Values**, and then click **Add**.

 **Note:**

The value can include URIs defined in [Authentication Context for the OASIS Security Assertion Markup Language \(SAML\) 2.0](#) or any other value agreed upon with the partner.

- b. Optional: Add more values to differentiate criteria for authentication selection.

Display order does not matter.

Each selector result value forms a policy path when you place this selector instance as a checkpoint in an authentication policy (regardless of whether you have enabled the **No Match** or **Not in Request** policy path in [step 4b](#)).

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Click **Delete** to remove an entry.

6. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

#### Configuring the Session Authentication Selector

The Session Authentication Selector enables PingFederate to choose a policy path at runtime based on whether the user already has a PingFederate authentication session for a particular source.

#### Steps

1. Go to **Authentication # Policies # Selectors** to open the **Selectors** window.

2. On the **Selectors** window, click **Create New Instance** to start the **Create Authentication Selector Instance** workflow.
3. On the **Type** tab, configure the basics of this authentication selector instance.
4. On the **Authentication Selector** window, click **Add a new row to 'Authentication Sources'**.
5. Select an IdP adapter instance or an IdP connection from the list, enter a value under **Result Value** for the selected authentication source, then click **Update**.

The **Result Value** field controls the label shown for the policy path created by the selected authentication source.



**Note:**

You must enable authentication sessions for the selected authentication source, or globally for all authentication sources, on the **Sessions** window. Click **Manage Sessions** to review and configure authentication sessions.

6. Optional: Repeat the previous step to add more authentication sources.

Display order might matter.

When you place this selector instance as a checkpoint in an authentication policy, each selector result value forms a policy path. The display order of the resulting policy paths matches the display order here, which may impact the policy outcome. When the policy engine reaches this selector instance, the selector starts from top to bottom. It exits and returns true as soon as it finds a match.

As needed, use the up and down arrows to re-arrange the display order here, which also re-prioritizes the resulting policy paths.

In addition, when no session exists for any of the defined sources, the result value for the first authentication source is returned unless the **Enable 'No Session' Result Value** check box is selected, in which case an additional policy path is added as the last path when this selector instance is placed as a checkpoint in an authentication policy.

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

7. Optional: Select the **Enable 'No Session' Result Value** check box to create a separate policy path for the scenario where no session exists for any of the defined sources.

This check box is not selected by default.

8. Complete the configuration.
  - a. On the **Summary** tab, click **Done**.
  - b. On the **Selectors** window, click **Save**.

## Result

When you place this selector instance as a checkpoint in an authentication policy, each selector result value forms a policy path that you can define the desired authentication experience and requirements.

## Example

### Example

The following screen capture illustrates a configuration where three authentication sources are defined and the **Enable 'No Session' Result Value** check box is selected.

When this selector instance (named Intranet sessions) is placed in a policy, four policy paths are formed.

## Configuring a sample use case

Use the following sample setup to configure one of the common use cases where you have two categories of service providers (SPs).

### Before you begin

For this sample use case, you must have the following components:

- An authentication policy contract
- Multiple SP connections. All connections use the same authentication policy contract as their sole authentication source
- Instances of the required adapters
- An instance of the Connection Set Authentication Selector to isolate high-value connections from the rest of the connections

### About this task

The Session Authentication Selector lets you choose a policy path at runtime based on whether the user already has an authentication session for a particular source.

You need to enforce authentication requirements on two categories of service provider connections:

- For high-value connections, users must authenticate using the X.509 Adapter followed by the PingID Adapter.
- For low-value connections, users can authenticate using the HTML Form Adapter or the X.509 Adapter followed by the PingID Adapter.

To fulfill this use case, follow these configuration steps.

### Steps

1. Go to **Authentication # Policies # Selectors**.
2. Create an instance of the Session Authentication Selector to account for authentication sessions acceptable for low-value connections.
  - a. Click **Create New Instance**.
  - b. On the **Type** tab, enter a name (for example, Sessions for low-value connections) and an ID. Then select **Session Authentication Selector** from the list.
  - c. On the **Authentication Selector** tab, leave the **Enable 'No Session' Result Value** check box clear; then configure the following authentication source-to-result value entries.

| Authentication source (adapter instance name) | Result value (policy path label) |
|---|----------------------------------|
| HTML  | SSO                              |



| Authentication source (adapter instance name) | Result value (policy path label) |
|---|----------------------------------|
| X.509   | Mutual TLS and MFA               |

Example:

The following screen capture illustrates the

## Manage Authentication Selector Instances | Create Authentication Selector Instance

| Type | Authentication Selector | Summary |
|------|-------------------------|---------|
|------|-------------------------|---------|

Complete the configuration needed for this Selector Instance.

This authentication selector chooses a policy tree branch at runtime based on whether the user already has a session for the selected authentication source.

### AUTHENTICATION SOURCES

(A table of authentication sources and result values)

#### AUTHENTICATION SOURCE

(Select from the available IdP adapters and connections)

#### RESULT VALUE

(The result value returned if a session exists for this source)

HTML - (Adapter)

SSO

X.509 - (Adapter)

Mutual TLS and MFA

[Add a new row to 'Authentication Sources'](#)

| Field Name                       | Field Value              | Description   |
|----------------------------------|--------------------------|---|
| ENABLE 'NO SESSION' RESULT VALUE | <input type="checkbox"/> | By default, if no session exists for any of the authentication sources listed above, the result value of the first authentication source is returned. Selecting this option will cause the selector to return a separate result value for each authentication source. |

setup.

- d. On the **Summary** tab, click **Done**.
  - e. On the **Manage Authentication Selector Instances** window, click **Save** to keep the newly configured authentication selector instance.
3. Go to **Authentication # Policies # Policies**.

4. On the **Policies** window, define an authentication policy for high-value connections.
  - a. Click **Add Policy**.
  - b. In the **Name** field, enter a name for the policy, such as `High-value connections`.
  - c. From the **Policy** list, select the instance of the Connect Set Authentication Selector that isolates high-value connections from the rest.
  - d. For the **No** policy path, select **Continue**.
  - e. For the **Yes** policy path, select the X.509 Adapter instance.
  - f. For the **X.509 Adapter instance # Fail** policy path, select **Done**.
  - g. For the **X.509 Adapter instance # Success** policy path, select the PingID Adapter instance.
  - h. Below the PingID Adapter instance, click **Options**.
  - i. On the **Incoming User ID** window, select the X.509 Adapter instance as the source and **username** as the attribute.

**Tip:**

This step applies only to adapters that support a user identifier to be passed in from an earlier authentication source. The PingID Adapter requires this user identifier. For more information, see [Specifying incoming user IDs](#) on page 258.

- j. For the **X.509 Adapter instance # Success # PingID Adapter instance # Fail** policy path, select **Done**.
- k. For the **X.509 Adapter instance # Success # PingID Adapter instance # Success** policy path, select the authentication policy contract.
- l. Complete the contract mapping for the authentication policy contract.  
Example:  
The following illustrates the policy created for high-value connections.
- m. Click **Done**.

5. Define an authentication policy for low-value connections.
  - a. Click **Add Policy**.
  - b. Enter a name for the policy, such as Low-value connections.
  - c. From the **Policy** list, select the instance of the Session Authentication Selector. For more information, see [step 2](#).
  - d. For the single sign-on (**SSO**) policy path, select the HTML Form Adapter instance.
  - e. For the **HTML Form Adapter instance # Fail** policy path, select **Done**.
  - f. For the **HTML Form Adapter instance # Success** policy path, select the authentication policy contract.
  - g. Complete the contract mapping for the authentication policy contract.
  - h. For the **Mutual TLS and MFA** policy path, select the X.509 Adapter instance.
  - i. For the **X.509 Adapter instance # Success** policy path, select the PingID Adapter instance.
  - j. Below the PingID Adapter instance, click **Options**. Select the X.509 Adapter instance as the source and `username` as the attribute on the **Incoming User ID** window.

**Tip:**

This step only applies to adapters that support a user identifier to be passed in from an earlier authentication source. The PingID Adapter requires this user identifier. For more information, see [Specifying incoming user IDs](#) on page 258.

- k. For the **X.509 Adapter instance # Success # PingID Adapter instance # Fail** policy path, select **Done**.
- l. For the **X.509 Adapter instance # Success # PingID Adapter instance # Success** policy path, select the authentication policy contract.
- m. Complete the contract mapping for the authentication policy contract.  
Example: The following illustrates the policy created for low-value connections.
- n. Click **Done**.
- o. To activate authentication policies for identity provider (IdP) browser SSO requests, adapter-to-adapter requests, and browser-based OAuth authorization code and implicit flows, select the **IdP Authentication Policies** check box.  
Example:  
The following screen capture illustrates the policies created this sample use case.

6. To keep the newly configured authentication policies, click **Save**.

## Policies

You can configure policies, fragments, selectors, policy contracts, and sessions under **Authentication # Policies**.

An authentication policy is a tree of authentication sources, selector instances, or a combination of them, that defines the decision to route a request through a series of approved authentication sources with an optional authentication policy contract or a local identity profile at the end or to deny the request.

Administrators can enable authentication policies on identity provider (IdP) browser single sign-on (SSO) requests, adapter-to-adapter requests, and browser-based OAuth authorization code and implicit flows. Administrators can also enable authentication policies on service provider (SP)-initiated Browser SSO requests received at the `/sp/startSSO.ping` endpoint. Individual policies can be disabled, as needed.

The order of authentication policies matters because the policy engine starts from the first policy and works its way down. At runtime, the policy engine derives an authentication tree from the applicable policies and either approves or denies a request.

## Policy paths, authentication policy contracts, and local identity profiles

### Policy paths

An authentication policy starts with either a selector instance or an authentication source. Authentication sources and most selectors have two results, **Success** or **Fail**, **Yes** or **No**. Each result forms a policy path.

A policy path is open-ended if it contains only one or more selector instances, without any authentication sources. In this scenario, the policy engine continues to the next applicable authentication policy, if any.

A policy path is closed-ended if it contains one or more authentication sources, with or without any selector instances. A closed-ended path can optionally end with an authentication policy contract or a local identity profile.

#### **Note:**

A policy path is also closed-ended if it ends with an instance of a custom authentication selector that returns an IdP adapter instance ID or the connection ID of an IdP connection. Because the custom selector returns an authentication source, such a closed-ended path cannot end with an authentication policy contract or a local identity profile. Instead, it must end with an action of **Done** or **Restart**.

### Authentication policy contracts and local identity profiles

An authentication policy contract can harness attribute values obtained from all authentication sources along the path leading up to it. Administrators can select the same authentication policy contract or local identity profile for different closed-ended paths, in one or more authentication policies, and fulfill them differently to suit the requirements. To enforce the same set of authentication policies in multiple use cases, map the authentication policy contract to the applicable Browser SSO connections and OAuth grant-mapping configuration.

A policy becomes more complex as the number of paths grows with the number of authentication sources and selector instances.

### Multiple policies and runtime behavior

A complex policy can cover a lot of ground. However, depending on the authentication requirements, administrators can also create multiple policies to suit their needs.

When a request arrives at PingFederate, the policy engine skips all disabled policies and any closed-ended paths that are inapplicable to the request. A closed-ended path is considered inapplicable to a request in any of the following conditions:

- The local identity profile at the end of a path is associated with an authentication policy contract that is not mapped to the invoking use case or is blocked by the virtual server ID included in the request.
- The authentication policy contract at the end of a path is not mapped to the invoking use case or is blocked by the virtual server ID included in the request.
- The last authentication source at the end of a path, that does not end with an authentication policy contract or a local identity profile, is not mapped to the invoking use case or is blocked by the virtual server ID included in the request.

#### **Note:**

Virtual server IDs are not applicable to adapter-to-adapter mappings or OAuth use cases.

After pruning inapplicable policies and paths, the policy engine starts evaluating the request against the first applicable policy. Generally speaking, the policy engine moves on to the next applicable policy when it hits the end of an open-ended path, as indicated by an action of **Continue**, and stops when it hits the end of a closed-ended path, as indicated by an authentication policy contract or an action of **Done** or **Restart**. Depending on the policies, the policy engine might find an authentication source, a series of authentication sources, or no authentication source at all.

#### Default authentication sources

In the event that a request has only passed through an open-ended path and the policy engine finds no authentication source after evaluating the request through all the applicable policies, it picks the first applicable default authentication source. A default authentication source is considered applicable if it is mapped to the use case of the request.

If the policy engine cannot find a default authentication source and the **Fail if policy engine finds no authentication source** check box is not selected, PingFederate chooses an authentication source based on the following prioritized preferences:

1. If the request comes with an **IdpAdapterId** query parameter or a **pfidpaid** cookie, and if the authentication source specified by the query parameter or the cookie is mapped to the corresponding use case, PingFederate uses the specified authentication source. If the authentication source is not mapped, PingFederate denies the request and returns an error message.



#### Note:

If the request presents both the **IdpAdapterId** query parameter and the **pfidpaid** cookie, the **IdpAdapterId** query parameter takes precedence.

2. If the request comes with neither an **IdpAdapterId** query parameter nor a **pfidpaid** cookie, and if there is only one authentication source mapping, PingFederate uses the mapped authentication source.



#### Note:

If there are multiple authentication-source mappings, PingFederate returns the available authentication sources and lets the user authenticate through one of them. If the user selected the **Remember selection** check box and successfully authenticated, PingFederate returns a **pfidpaid** persistent cookie, identifying the user's preference.

If the **Fail if policy engine finds no authentication source** check box is selected, PingFederate denies the request and returns an error message.



#### Note:

If a request has passed through a closed-ended path, the policy engine has already found at least one authentication source for the user; in this scenario the policy engine ignores all default authentication sources.

#### Tracked HTTP request parameters

The policy engine is capable of tracking HTTP request parameters that it receives from the initial request and making them available to authentication sources, selector instances, and contract mappings throughout the policy.

## Local identity profiles and authentication policy contracts

PingFederate empowers administrators to deliver a secure and easy-to-use customer authentication, registration, and profile management solution. A typical use case involves an HTML Form Adapter instance, a local identity profile, an authentication policy contract, and an IdP authentication policy. The HTML Form Adapter captures user attributes and maps them into an authentication policy contract through a local identity profile. In terms of configuration, the latter is accomplished by placing a local identity profile at the end of a policy path and completing the **Local Identity Mapping # Contract Fulfillment** configuration.

## Policy enforcement based on OAuth clients

PingFederate can enforce authentication policies based on the requesting OAuth client, among other factors. To do that, you can include an OAuth Client Set Authentication Selector or an Extended Property Authentication Selector in a policy. For more information, see [Configuring the OAuth Client Set Authentication Selector](#) on page 243 and [Configuring the Extended Property Authentication Selector](#) on page 237

Another option is to leverage the policy enforcement rule that PingFederate ignores authentication policy contract branches that are not mapped to an access token manager (ATM) that the requesting client can access. This rule also applies to policy branches that end on an authentication source. For more information, see [Managing access token mappings](#) on page 616.

Keep that policy enforcement rule in mind when you configure clients and ATMs. You can configure a client so that it can access only its default ATM. You can also configure an ATM so that only specific clients can access it. Those settings affect the authentication policy. For more information, see [Configuring OAuth clients](#) on page 566 and [Access token management](#) on page 603.

## Defining authentication policies

You can manage authentication policies and settings on the **Policies** window.

### Steps

1. Go to **Authentication # Policies # Policies**.
2. On the **Policies** tab, select the **IdP Authentication Policies** check box if you want to enable authentication policies for identity provider (IdP) browser single sign-on (SSO) requests, adapter-to-adapter requests, and browser-based OAuth authorization code and implicit flows.
3. Select the **SP Authentication Policies** check box if you want to enable authentication policies for service provider (SP)-initiated browser SSO requests received at the `/sp/startSSO.ping` endpoint.



#### Note:

Selecting the **SP Authentication Policies** check box does not enable authentication policies for IdP browser SSO requests, adapter-to-adapter requests, and browser-based OAuth authorization code and implicit flows.

4. Select the **Fail if policy engine finds no authentication source** check box if you want to deny the requests and to return an error message when the policy engine finds no authentication source or authentication policy contract from the applicable policies and none of the default authentication sources are applicable. This check box is not selected by default.

5. On the **Policies** window, click **Add Policy** to create an authentication policy.



**Tip:**

If you want to create a new policy based on an existing policy, then in the policy's **Select Action** menu, select **Copy**.

- a. In the **Policy** window, enter a name and, optionally, a description of the policy.
- b. Select the **Handle Failures Locally** check box if you want to keep users on the local IdP instead of returning them to the SP when an SP-initiated SSO request fails.

When selected, after an SSO failure, the IdP uses the error template to give users more useful contextual information about the error than the SP can provide. The default error template is `idp.sso.error.page.template.html`.

The check box is cleared by default.

- c. From the **Policy** list, choose an authentication source, an IdP adapter instance or an IdP connection, a selector instance, or a fragment.



**Note:**

If you started this new policy by copying an existing policy, your new policy is pre-populated. Modify the policy to suit your new use cases.



**Tip:**

When implementing your authentication requirements, think of authentication sources and selectors as checkpoints.

### Options

For the PingID Adapter, IdP adapters developed using the `IdpAuthenticationAdapterV2` interface from the PingFederate SDK, including the HTML Form Adapter, and SAML 2.0 IdP connections supporting the SP-initiated browser SSO profile, you can specify a user ID to be passed in from an earlier-factor adapter.

Click **Options** and follow the on-screen instructions to select the source and the attribute to be used as the incoming user ID.



**Note:**

The **User ID Authenticated** check box must be selected for users to register as a new PingID user. Otherwise, the adapter automatically fails.

### Rules

For any authentication source, you can optionally create one or more rules to define additional successful results. For example, if you want to deploy multi-factor authentication using the PingID Adapter in stages by groups, you can create a rule to check for group membership information and only apply the PingID authentication flow to users who are members of certain groups.

Click **Rules** and follow the on-screen instructions to manage your rules.

### Copy and Paste

The **Copy** and **Paste** feature lets you copy a policy path and paste it into another place in the same policy, another policy, or a policy fragment. After you copy and paste a path, follow the on-screen instructions to correct any errors.



**Tip:**

One benefit of this feature is that you can easily add a new step at the start or middle of an existing policy. To do that, copy and then remove the existing path below the point where you will define the new step. After you define the new step, paste the copied path back into the policy below the new step.

All results, including those based on rules, are displayed under the selected authentication source or selector instance. Each result forms a policy path.

- d. For each policy path, select a policy action from the list.



**Important:**

You can select **Fragments** as the policy action and then select a policy fragment that you have created. (See [Policy fragments](#) on page 285 for information about creating policy fragments.) When you select a fragment, click **Fragment Mapping** and use the in-product help links to access the topics that describe how to configure the mapping.

- If additional processing is required, repeat [step 4b](#).
- If the policy path is extended from an authentication source and it is the end of the path, select **Done** or **Restart**, which marks this policy path a closed-ended path.



**Tip:**

A policy path is closed-ended if it contains one or more authentication sources, with or without any selector instances. A closed-ended path can optionally end with an authentication policy contract or a local identity profile.

If you need to reuse an authentication policy in multiple use cases, select an authentication policy contract or a local identity profile as the last policy action of a path, configure its contract fulfillment, and map the authentication policy contract to the applicable Browser SSO connections or OAuth grant-mapping configuration. Click **... Mapping** underneath your selection and then follow the on-screen instructions to complete the contract fulfillment configuration.



**Note:**

A policy path is also closed-ended if it ends with an instance of a custom authentication selector that returns an IdP adapter instance ID or the connection ID of an IdP connection. Because the custom selector returns an authentication source, such a closed-ended path cannot end with an authentication policy contract or a local identity profile. Instead, it must end with an action of **Done** or **Restart**.

The **Restart** policy action provides users the opportunity to do over. When triggered, the policy engine routes the requests back to the first checkpoint of the invoked authentication policy. It makes most sense to use the **Restart** policy action for a **Fail** policy path if the policy engine can route the request differently based on user input prompted by an authentication



source. For a sample use case, see step 5 in [Enabling third-party identity providers](#) on page 376.

 **Note:**

Undesirable looping behaviors can occur if you select **Restart** for the **Fail** path at the root of an authentication policy tree. PingFederate mitigates this risk by automatically limiting the number of policy restarts per transaction.

- If the policy path is extended from a selector instance and it is the end of the path without any prior authentication source, select **Continue**, which leaves this path as an open-ended path.

 **Tip:**

A policy path is open-ended if it contains only selector instances without any authentication sources. In this scenario, the policy engine continues to the next applicable authentication policy, if any.

- e. Click **Done** to go back to the **Policies** window.

Result:

Your policy is enabled by default. As needed, toggle its status to disable the policy.

6. Optional: Repeat [step 4](#) to create additional authentication policies.

 **Important:**

The order of authentication policies matters because the policy engine starts from the first policy and works its way down. As needed, reorder your policies by using the up and down arrows.

7. If any individual policy is no longer required, select the **Delete** action or toggle its status to disable the policy.
8. Optional: On the **Policies # Default Authentication Sources** tab, select one or more default authentication sources from the list for the policy engine to fall back on when it finds no authentication source from the applicable policies.

 **Important:**

Order matters because the policy engine starts from the first default authentication source on the list and works its way down. As needed, reorder your authentication sources by using the up and down arrows. There is no default selection.

9. Optional: On the **Policies # Tracked HTTP Parameters** tab, add one or more HTTP request parameters to be tracked throughout a request.

 **Important:**

For each instance of the HTTP Request Parameter Authentication Selector that you place in a policy as the second, or subsequent, checkpoint, add its configured **HTTP Request Parameter Name** value here. By doing so, the policy engine preserves the parameter it receives from the initial request and makes it available to the selector instance throughout the policy. For more information, see [Configuring the HTTP Request Parameter Authentication Selector](#) on page 241.

10. Click **Save**.

## Specifying incoming user IDs

You can configure authentication policies to use incoming user identifiers at request time.

### About this task

Some authentication sources make use of a user identifier at request time. For example:

- The PingID Adapter requires a user ID to be passed in from an earlier-authentication step to perform multi-factor authentication.
- The HTML Form Adapter and custom IdP adapters developed using the `IdpAuthenticationAdapterV2` interface from the PingFederate SDK can pre-populate username information based on an incoming user ID.
- A SAML 2.0 identity provider (IdP) connection can use an incoming ID to specify the `subject` value in its authentication requests.
- An OpenID Connect IdP connection can leverage an incoming user ID to specify a `login_hint` parameter value in its OAuth authorization requests.

To address these use cases, specify the source and the attribute of the incoming user ID in an authentication policy.

You can select any IdP adapter instance or IdP connection that has been placed in the same policy path ahead of the current authentication source to be the source of the incoming user ID. After you select a source, choose an attribute from the selected IdP adapter contract or IdP connection. At runtime, the attribute value becomes the incoming user ID.

Alternatively, you can use the originating SAML 2.0, WS-Federation, or OpenID Connect authentication request as the source. In this scenario, the incoming user ID is derived from the `subject` element in a SAML 2.0 authentication request, the `username` parameter in a WS-Federation authentication request, or the `login_hint` parameter in an OpenID Connect authentication request.

### Steps

1. Go to **Authentication # Policies # Policies**. On the **Policies** window, select the applicable authentication policy.
2. On the **Policy** tab, locate the authentication source that you need to provide an incoming user ID and then click **Options** underneath it.
3. On the **Incoming User ID** dialog, select the source of the incoming user ID from the **Source** list.



#### Note:

If you want the policy engine to derive the incoming user ID from the originating SAML 2.0 or WS-Federation authentication request, select **Context**.

4. Select an attribute of the incoming user ID from the **Attribute** list.



#### Note:

If you have selected **Context** in the previous step, select **Requested User** to derive the incoming user ID from the `subject` element, the `username` parameter, or the `login_hint` parameter in the SAML 2.0, WS-Federation, or OpenID Connect authentication request, respectively.

### Result:

During runtime, if a request does not originate from a SAML 2.0, WS-Federation, or OpenID Connect authentication request, or if the SAML 2.0, WS-Federation, or OpenID Connect authentication request does not include the optional `subject` element, `username` parameter, or `login_hint` parameter, the policy engine advances without providing username information to the authentication source.

5. Select the **User ID Authenticated** check box to signal to the adapter that the value of the incoming user ID has been authenticated by a previous authentication source.  
Adapters can choose to enable certain functionality, such as registering new MFA devices, only when the user ID value has previously been authenticated.
6. On the **Incoming User ID** dialog, click **Done**.
7. On the **Policy** tab, continue with the rest of your policy configuration.

### Configuring rules in authentication policies

PingFederate supports more granular control through the use of rules in authentication policies.

#### About this task

An authentication source in an authentication policy has two results, Fail or Success, for which you can set one of the following actions:

- Append another authentication source for further processing.
- Append a selector for further processing.
- Select **Done** to terminate the authentication policy, making it a closed-ended path.
- Select an authentication policy contract or a local identity profile, also terminating the authentication policy, making it a closed-ended path.



#### Tip:

A policy path is closed-ended if it contains one or more authentication sources, with or without any selector instances. A closed-ended path can optionally end with an authentication policy contract or a local identity profile.



#### Note:

A policy path is also closed-ended if it ends with an instance of a custom authentication selector that returns an IdP adapter instance ID or the connection ID of an IdP connection. Because the custom selector returns an authentication source, such a closed-ended path cannot end with an authentication policy contract or a local identity profile. Instead, it must end with an action of **Done** or **Restart**.

By applying multiple rules to an authentication source, an administrator can define additional, successful, results based on attribute values from the authentication source and set different action for each result.

For example, your OpenToken IdP Adapter instance returns an attribute, **EmployeeType**, that identifies the employee profile; a value of `temp` indicates the user is a contractor. Your organization mandates that all contractors must authenticate successfully against the OpenToken identity provider (IdP) adapter, followed by another IdP adapter, such as an instance of the PingID Adapter for multifactor authentication. To fulfill this authentication requirement, you can define a successful result by adding a rule to evaluate the **EmployeeType** value, and then select the PingID Adapter instance as the action for this match.

When multiple rules exist for a given authentication source, the first match wins. If no rule returns a match, administrators have the option to treat the authentication as successful or failure.

#### Steps

1. Go to **Authentication # Policies # Policies**. On the **Policies** window, select the applicable authentication policy.
2. On the **Policy** tab, locate the authentication source that you want to define additional successful results for further processing, and then click **Rules** underneath it.
3. On the **Rules** window, select an attribute from the **Attribute Name** list.

- From the **Condition** list, select how PingFederate should compare the value that you are going to specify in the next step against the attribute value from the authentication source.

The choices are:

- equal to
- equal to (case insensitive)
- equal to DN
- not equal to
- not equal to (case insensitive)
- not equal to DN
- multi-value contains
- multi-value contains (case insensitive)
- multi-value contains DN
- multi-value does not contain
- multi-value does not contain (case insensitive)
- multi-value does not contain DN

Use one of the first six choices only for attributes consisting of a single value. Use the multi-value conditions when you want PingFederate to verify whether an attribute contains or does not contain the specified value in its attribute list.



**CAUTION:**

Using a single-value condition when an attribute has multiple values causes the condition to evaluate consistently to false.

- In the **Value** field, enter the desired value to be compared against the attribute value from the authentication source.
- In the **Result** field, enter a unique label.
- Optional: To add another rule, click **Add** and repeat steps 3 to 6.
- If any individual rule is no longer required, select the **Delete** action.
- Select the **Default to Success** check box if you want the policy engine to treat the authentication attempt as successful when no rules return a match.



**Note:**

The **Default to Success** check box is selected by default. When you clear this check box, the policy engine treats the attempt as a failure when no rules return a match.

- To close the **Rules** window, click **Done**.

Result:

Your policy is now updated with a new policy path, or paths if you have added multiple rules.

For instance, if you have added two rules with labels **Contractors**, the first rule, and **Senior executives**, the second rule, to an authentication source, you should see the following results in the policy:

- **Fail**
- **Contractors**, a new result based on the first rule
- **Senior executives**, a new result based on the second rule
- **Success**, available only when the **Default to Success** check box is selected

- On the **Policy** window, continue with the rest of your policy configuration.

## Defining authentication policies based on group membership information

PingFederate lets you configure authentication policies based on group membership information through the use of rules.

### About this task

Assume you have created the following authentication policy to enforce multifactor authentication using PingID after the users have successfully authenticated against an HTML Form Adapter instance.

While this policy satisfies the authentication requirements, you might prefer to roll out multi-factor authentication based on group membership over a period of time. To accomplish this policy deployment strategy, you can use rules to define the applicable groups and set different policy actions accordingly.

As an example, suppose you want to enforce PingID multi-factor authentication to two Active Directory (AD) groups:

- CN=helpdesk,OU=IT,DC=example,DC=com (IT helpdesk personnel)
- CN=leads,OU=IT,DC=example,DC=com (Leaders in the IT department)

### Steps

1. If you have not done so, create a new AD group, for example, CN=PingIDRequired,OU=IT,DC=example,DC=com, and place those two groups as members of the new group.


#### Tip:

Generally speaking, this step streamlines the process of deploying your authentication policies to additional groups of users later. In other words, when you are ready to roll out your authentication policies to more users, simply add the applicable groups as members of the new group. This way, you are not required to make any changes to the authentication policies, after they are configured.

2. If you have not done so, follow these steps to extend the HTML Form Adapter instance to return group membership information from your AD.
  - a. Extend the HTML Form Adapter instance with the `memberOf` attribute on the **Extended Contract** window.
  - b. Configure PingFederate to fulfill the `memberOf` attribute from your AD.

#### Note:

Because the actual groups are nested inside the new group created in [step 1](#), configure the IdP adapter contract to pull the `memberOf` attribute values with nested groups on the LDAP Directory Search window. For more information, see [Defining the IdP adapter contract](#) on page 424.



| Attribute Name | Attribute ID | Action |
|----------------|--------------|--------|
| memberOf       | memberOf     |        |

3. Go to **Authentication # Policies # Policies**. On the **Policies** window, select the applicable authentication policy.
4. On the **Policy** window, click **Rules** underneath the HTML Form Adapter instance.

5. In the **Rules** dialog, add a rule to check for membership information obtained from the HTML Form Adapter instance.
  - a. From the **Attribute Name** list, select `memberOf`.
  - b. Select how PingFederate should compare the value that you are going to specify in the next step against the attribute value from the HTML Form Adapter instance. For example, **multi-value contains DN** works well for the `memberOf` AD user attribute.
  - c. Enter the distinguished name (DN) of the new group created in [step 1](#) in the **Value** field, such as `CN=PingIDRequired,OU=IT,DC=example,DC=com`.
  - d. In the **Result** field, enter a label, for example, `PingID users`.
  - e. Leave the **Default to Success** check box as selected.

 **Note:**

When the **Default to Success** check box is selected, you can set the action for the scenario where none of the rules returns a match.

Example:

Your **Rules** dialog should be similar to the following sample.

6. To close the **Rules** window, click **Done**.
7. For the new **HTML Form # PingID users** policy path, select your PingID Adapter instance as the policy action from the list.

 **Note:**

To open the **Incoming User ID** dialog, click **Options**, underneath the PingID Adapter instance. Configure the source of the user ID required by the PingID Adapter, and then click **Done** to close the dialog. For more information, see [Specifying incoming user IDs](#) on page 258.

Result:

Your policy should be similar to the following sample.

There are four policy paths:

- **HTML Form # Fail**
- **HTML Form # PingID users # Fail**
- **HTML Form # PingID users # Success**
- **HTML Form # Success**

8. Update your policy as follows:

**HTML Form # Fail**

Leave **Done** as the policy action. At runtime, PingFederate terminates the request and returns an error message to the user.

**HTML Form # PingID users # Fail**

Select **Done** as the policy action. At runtime, PingFederate terminates the request and returns an error message to the user.

**HTML Form # PingID users # Success**

Select an authentication policy contract as the policy action. Click **Contract Mapping** to complete its fulfillment. At runtime, PingFederate fulfills the authentication policy contract and carries on with the request.

#### HTML Form # Success

Reconfigure the policy action for this policy path. Select an authentication policy contract as the policy action. Click **Contract Mapping** to complete its fulfillment. At runtime, PingFederate fulfills the authentication policy contract and carries on with the request.

Result:

Your policy should be similar to the following sample.

9. To close the **Policy** window, click **Done**.
10. On the **Policies** window, click **Save**.



#### Note:

Group membership is only one of the possible factors that you can use to define additional policy paths and their policy actions. In general, you can use any attributes available from the authentication source when configuring rules.

### Applying policy contracts or identity profiles to authentication policies

To apply an authentication policy contract to a policy, select an authentication policy contract or a local identity profile as the last action of one or more closed-ended paths and configure fulfillment for each contract.

About this task

An authentication policy contract can harness attribute values obtained from all authentication sources along the path leading up to it. Administrators can select the same authentication policy contract or local identity profile for different closed-ended paths, in one or more authentication policies, and fulfill them differently to suit the requirements. To enforce the same set of authentication policies in multiple use cases, map the authentication policy contract to the applicable Browser SSO connections and OAuth grant-mapping configuration.

Steps

1. Go to **Authentication # Policies # Policies**. On the **Policies** window, select the applicable authentication policy.
2. On the **Policy** window, locate all closed-ended paths in the policy.

A policy path is closed-ended if it contains one or more authentication sources, with or without any selector instances. A closed-ended path can optionally end with an authentication policy contract or a local identity profile.



#### Note:

A policy path is also closed-ended if it ends with an instance of a custom authentication selector that returns an IdP adapter instance ID or the connection ID of an IdP connection. Because the custom

selector returns an authentication source, such a closed-ended path cannot end with an authentication policy contract or a local identity profile. Instead, it must end with an action of **Done** or **Restart**.

Consider the following sample policy.

This policy has two selector instances, **Test** and **Retail**, two identity provider (IdP) adapter instances, and five policy paths:

- **Test # No # HTML Form # Fail**
- **Test # No # HTML Form # Success # Retail # No**
- **Test # No # HTML Form # Success # Retail # Yes # PingID # Fail**
- **Test # No # HTML Form # Success # Retail # Yes # PingID # Success**
- **Test # Yes**

The first four paths are closed-ended while the last path is open-ended.

3. Select **Done** as the policy action for the following paths:

- **Test # No # HTML Form # Fail**
- **Test # No # HTML Form # Success # Retail # Yes # PingID # Fail**

Result:

At runtime, PingFederate terminates the request and returns an error message to the user.

4. Select the applicable authentication policy contract or local identity profile as the policy action for the rest of the closed-ended paths:

- **Test # No # HTML Form # Success # Retail # No**
- **Test # No # HTML Form # Success # Retail # Yes # PingID # Success**

Suppose your use case does not involve consumer authentication, registration, and profile management. It makes sense to select an authentication policy contract for the **PingID # Success** result, because the users have successfully met all your authentication requirements.

At runtime, PingFederate fulfills the authentication policy contract and carries on with the request.

Depending on your use case, you might also select an authentication policy contract for the **PingID # Fail** result, possibly with an attribute indicating that the users have failed a certain part of your authentication requirements, and make other authorization decision using the Token Authorization framework in the applicable connections later.

5. For each selected authentication policy contract, if any, click **Contract Mapping** and then complete the **Manage Authentication Policies # Authentication Policy Contract Mapping** workflow to complete the configuration. For more information, see [Configuring contract mapping](#) on page 265 .
6. For each selected local identity profile, if any, click **Local Identity Mapping** and then complete the **Manage Authentication Policies # Inbound Mapping & Contract Fulfillment** workflow to complete the configuration. For more information, see [Configuring local identity mapping](#) on page 265.
7. Select **Continue** as the policy action for the open-ended path **Test # Yes**.

Result:

At runtime, PingFederate skips to the next policy. Your policy should be similar to the following sample.

8. To close the **Policy** window, click **Done**.
9. On the **Policies** window, click **Save**.



## Configuring contract mapping

Configure authentication policy contract grant mappings in the PingFederate administrative console.

### Steps

1. Optional: Go to **Authentication # OAuth # Authentication Policy Contract Mapping**.
2. Optional: From the **Authentication Policy Contract** list, click the desired mapping or select the desired mapping from the **Authentication Policy Contract** list.



#### Note:

If you do not have an authentication policy contract mapping already configured, go to **Authentication # Policies # Policy Contracts** and configure and save a new contract.

3. Optional: On the **Attribute Sources & User Lookup** window, click **Add Attribute Source** to configure datastore queries.
4. On the **Contract Fulfillment** tab, fulfill the selected contract.



#### Note:

If the selected closed-ended path contains more than one authentication source, you have access to attributes obtained successfully from the previous authentication sources along the same path.

For example, referring to the earlier policy in [Applying policy contracts or identity profiles to authentication policies](#) on page 263, if you select an authentication policy contract for the **PingID (Adapter) # Success** result, you can map attributes from the HTML Form Adapter and the PingID Adapter.

Besides the preceding identity provider (IdP) connection or IdP adapter instance, you can also use dynamic text, attribute mapping expression, if enabled, and tracked HTTP request parameter, if configured, as the source of fulfillment.

5. Optional: On the **Issuance Criteria** tab, configure conditions to be validated before issuing an authentication policy contract. For more information, see [Defining issuance criteria for contract or local identity mapping](#) on page 266.
6. On the **Summary** tab, review your configuration, modify as needed, and then click **Done**.
7. On the **Policy** window, continue with the rest of your policy configuration.

## Configuring local identity mapping

You can configure your local identity mapping in the PingFederate administrative console.

### Steps

1. On the **Inbound Mapping** tab, configure the attribute mappings for registration and profile management.



#### Note:

At runtime, PingFederate fulfills the value of the `pf.local.identity.unique.id` built-in local identity field based on this configuration and passes the value to PingDirectory. PingDirectory uses this value to determine whether such identity has already been created. The `pf.local.identity.unique.id` field value should therefore be mapped from the subject identifier of the preceding authentication source. You can also map other local identity fields so that

PingFederate can streamline the registration process by pre-populating values on the registration page.



**Note:**

This configuration overrides the default field values configured within the local identity profile. For more information, see [Configure a local identity field](#).

This tab does not apply and stays hidden if your use case does not involve registration and profile management. See [Enabling third-party identity providers without registration](#) on page 387.

2. Optional: On the **Attribute Sources & User Lookup** tab, click **Add Attribute Source** to configure datastore queries.
3. On the **Contract Fulfillment** tab, fulfill the authentication policy contract associated with the selected local identity profile.

If the selected closed-ended path contains more than one authentication source, you have access to attributes obtained successfully from the previous authentication sources along the same path.

For example, select your local identity profile under **Source** and the desired local identity field under **Value**.



**Note:**

If your use case does not involve registration or profile management, the source of fulfillment is limited to the preceding identity provider (IdP) connection or IdP adapter instance, dynamic text, attribute mapping expression, if enabled, and tracked HTTP request parameter, if configured.

4. Optional: On the **Issuance Criteria** tab, configure conditions to be validated before issuing an authentication policy contract. For more information, see [Defining issuance criteria for contract or local identity mapping](#) on page 266.
5. On the **Summary** tab, review your configuration, modify as needed, and then click **Done**.
6. On the **Policy** window, continue with the rest of your policy configuration.

### Defining issuance criteria for contract or local identity mapping

You must define certain criteria for contract or local identity mapping in PingFederate to process a request.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.

**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source  | Description   |
|---|---|
| Adapter   | Select to evaluate attributes from any preceding IdP adapter instance.  |
| IdP Connection  | Select to evaluate attributes from any preceding IdP connection.  |
| Local Identity  | Select to evaluate any local identity fields.<br>Not applicable for the <b>Contract Mapping</b> configuration.  |
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.   |
| Tracked HTTP Parameters   | Select to evaluate tracked request parameters.<br>Visible and applicable only if at least one HTTP request parameter has been configured on the <b>Tracked HTTP Parameters</b> tab of the <b>Policies</b> window. For more information, see . |

2. In the **Attribute Name** list, select the attribute to be evaluated.
3. In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**

**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

4. In the **Value** field, enter the comparison value.

**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

5. In the **Error Result** field, enter a custom error message.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

6. Click **Add**.
7. Optional: Repeat to add more criteria.
8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Mapping a policy contract to multiple use cases

The last step to reuse an authentication policy in multiple service provider (SP) connections is to map the authentication policy contract into the applicable SP connections.

#### About this task

In general, for identity provider (IdP) browser single sign-on (SSO) use cases, if you select authentication policy contracts in your authentication policies then you must map the authentication policy contracts to the applicable SP connections.

#### Steps

1. Go to **Applications # Integration # SP Connections**.
2. Select the applicable SP connection from the list of connections.
3. On the **Activation & Summary** tab, click **Authentication Source Mapping**.
4. Click **Map New Authentication Policy** and use the in-product help on each screen as needed to map the authentication policy contract into the SP connection.

## Result

Similarly, to reuse an authentication policy for browser-based OAuth authorization code and implicit flows, map the authentication policy contract to the applicable browser SSO connections and OAuth grant-mapping configuration. For more information, see [Managing authentication policy contract grant mapping](#) on page 593.

### SP authentication policies

Service provider (SP) authentication policies provide a means for you to impose authentication requirements on SP-initiated browser single sign-on (SSO) requests received at the `/sp/startSSO.ping` endpoint.

When you enable this optional feature, you create policies that the PingFederate SP server can use to find the applicable SP adapter instance to access target applications. For this reason, you must configure the target applications to provide the `SpSessionAuthnAdapterId` parameter or the `TargetResource` parameter, or both, in their SP-initiated SSO requests.

If you prefer to provide the `TargetResource` parameter without the `SpSessionAuthnAdapterId` parameter, you must go to **Applications # Integration # Target URL Mapping** and configure entries to map the `TargetResource` values to the applicable SP adapter instances.



#### Note:

SP authentication policies only apply to SP-initiated browser SSO requests received at the `/sp/startSSO.ping` on page 1256 SP application endpoint. They do not apply to unsolicited SSO requests received at the SP protocol endpoints.

In addition, enabling SP authentication policies does not enable authentication policies for identity provider (IdP) browser SSO requests, adapter-to-adapter requests, and browser-based OAuth authorization code and implicit flows.

For more information and configuration steps, see the subsequent sample use cases.

### Configuring an SP authentication policy for users from one IdP

You can configure a service provider (SP) authentication policy to enforce authentication requirements for an identity provider (IdP) connection.

#### Before you begin

This example requires the following components:

- An SP adapter instance deployed, configured, and integrated with the target application.
- An IdP connection to the partner. For more information, see [step 1](#).
- An IdP connection to the third-party IdP that facilitates the multifactor authentication process. For more information, see [step 2](#).
- An authentication policy contract to carry user attributes from the partner to the target application. For more information, see [step 3](#).
- An SP authentication policy. For more information, see [step 4](#) and [step 7](#).
- An adapter mapping between the authentication policy contract and the applicable SP adapter instance. For more information, see [step 5](#).
- An SP-initiated single sign-on (SSO) URL. For more information, see [step 6](#).

#### About this task

In this example, you want to create an IdP connection to Alpha, which passes two attributes in its assertions, `SAML_SUBJECT` and `samlEmail`, on your PingFederate SP server. You also want to enforce multi-factor authentication (MFA) for users from Alpha through Bravo, a third-party IdP that returns only the `SAML_SUBJECT` attribute and requires a user ID to be passed in from the original source. Both Alpha and Bravo support SAML 2.0 and only the SP-initiated single sign-on (SSO) profile.

Create an SP adapter instance using the **Applications # Integration # SP Adapters** configuration wizard and complete the last-mile integration with the target application. The SP adapter instance name and ID are **Sample** and `sample`, respectively. On **System # Server # Protocol Settings # Federation Info**, the base URL for your PingFederate SP server is `https://sso.xray.local:9031`. There are no other IdP connections besides those required to connect with Alpha and Bravo.

### Steps

1. Go to **Authentication # Integration # IdP Connections**. On the **IdP Connections** window, click **Create Connection**.
  - a. Follow the connection workflow to create a SAML 2.0 IdP connection to Alpha.  
In this example, Alpha's entity ID is `sso.alpha.local`.
  - b. On the **SAML Profiles** tab, make sure that the **SP-Initiated SSO** check box is selected.
  - c. On the **Identity Mapping** window, select **No Mapping**.



#### Tip:

If the partner and your organization agree to support account linking, select **Account Linking**. If the partner and your organization agree to support the IdP-initiated profile, select **Account Mapping** or **Account Linking**.

Both use cases require the applicable SP adapter instance (**Sample**) to be mapped into the connection. To get to the **Target Session Mapping** tab, go to **IdP Connection # Browser SSO # User-Session Creation**. The rest of the steps remain unchanged.

This sample configuration uses neither **Account Linking** or **Account Mapping**.

- d. Complete the rest of the connection configuration.
2. Repeat [step 1](#) to create a SAML 2.0 IdP connection to Bravo.  
In this example, Bravo's entity ID is `sso.bravo.local`.
3. Go to **Authentication # Policies # Policy Contracts**. On the **Policy Contracts** window, click **Create New Contract**.



#### Tip:

The purpose of an authentication policy contract is to harness user attributes obtained through one or more authentication sources as the request flows through the applicable authentication policy. It is the medium between the authentication policies and the target applications. In general:

- You map attributes to authentication policy contracts from authentication policies. For more information, see [step 4](#) in this example.
- You map attributes from authentication policy contracts to target applications through adapter mappings. For more information, see [step 5](#) in this example.

- a. On the **Contract Info** tab, enter a name for this authentication policy contract.  
In this example, the name of the policy contract is `Authenticated`.
- b. On the **Contract Attributes** tab, enter `mail` under **Extend the Contract** and click **Add**.
- c. Complete the rest of the connection configuration.

Result:

When finished, your policy contract has two attributes: `subject` and `mail`.

4. Go to **Authentication # Policies # Policies**. On the **Policies** window, click **Add Policy** to define a policy to enforce the third-party authentication requirement.
  - a. On the **Policy** window, enter a name and a description for this policy, and select **sso.alpha.local (IdP Connection)** as the first policy action from the list.

Result:

An IdP connection has two results, **Fail** and **Success**, as illustrated in the following screen capture.

Each result forms its own policy path that requires further configuration.

- b. For the **sso.alpha.local # Fail** path, click **Done** as the policy action.

Result:

At runtime, PingFederate terminates the request and returns an error message to the user.

- c. From the **sso.alpha.local # Success** list, select **sso.bravo.local** as the policy action.
- d. Below **sso.bravo.local**, click **Options** to relay the user ID (**SAML\_SUBJECT**) from **sso.alpha.local** to **sso.bravo.local**.
- e. On the **Incoming User ID** dialog window, select **IdP Connection (sso.alpha.local)** from the **Source** list and **SAML\_SUBJECT** from the **Attribute** list.

To close the **Incoming User ID** dialog window, click **Done**.

- f. For the **sso.bravo.local # Fail** path, select **Done** as the policy action.

Result:

At runtime, PingFederate terminates the request and returns an error message to the user.

- g. For the **sso.bravo.local # Success** path, select the authentication policy contract created in [step 3](#).

Result:

Your policy should be similar to the following sample.

- h. Below the authentication policy contract, click **Contract Mapping** and follow the **Manage Authentication Policies # Authentication Policy Contract Mapping** configuration workflow to configure the fulfillment of the authentication policy contract.
  - i. On the **Attribute Sources & User Lookup** tab, click **Add Attribute Source** to configure datastore queries.
  - j. On the **Contract Fulfillment** tab, from the **Source** list select **IdP Connection (sso.alpha.local)** and the appropriate attributes from the **Value** list to fulfill the authentication policy contract attributes.

Manage Authentication Policies | Authentication Policy Contract Mapping

Actions: **Attribute Sources & User Lookup** | **Contract Fulfillment** | Issuance Criteria | Summary

Configure your Authentication Policy Contract with values from the authentication sources or with dynamic test values.

| Contract Fulfillment | Source                           | Value        | Actions        |
|----------------------|----------------------------------|--------------|----------------|
| mail                 | IdP Connection (sso.alpha.local) | saml:mail    | None available |
| subject              | IdP Connection (sso.alpha.local) | SAML_SUBJECT | None available |



**Tip:**

In this configuration, you are mapping attributes to an authentication policy contract from the authentication policy.

**Optional:** On the **Issuance Criteria** tab, configure conditions to be validated before issuing an authentication policy contract.

On the **Summary** tab, click **Done**.

On the **Policy** window, click **Done**.

On the **Policies** window, click **Save**.

5. Go to **Applications # Integration # Policy Contract Adapter Mappings**. Map the authentication policy contract to the SP adapter instance that you have deployed, configured, and integrated with the target application.
  - a. From the **Source Instance** list, select the authentication policy contract, created in [step 3](#).
  - b. From the **Target Instance** list, select the applicable SP adapter instance (**Sample**).
  - c. Click **Add Mapping**.
  - d. Follow the **Mapping Configuration** workflow to create the mapping.
  - e. On the **Attribute Sources & User Lookup** tab, click **Add Attribute Source** to configure datastore queries.
  - f. On the **Adapter Contract Fulfillment** window, select **Authentication Policy Contract** from the **Source** list and the appropriate contract attributes from the **Value** list to fulfill the SP adapter contract.



**Tip:**

In this configuration, you are mapping attribute values from the authentication policy contract to the target application through the applicable SP adapter instance.

**Optional:** On the **Default Target URL** tab, specify a default target URL for this mapping configuration.

**Optional:** On the **Issuance Criteria** tab, configure conditions to be validated before issuing an SP adapter contract.

Click **Done**.

6. Configure an SP-initiated SSO URL in your target application by combining the base URL of your PingFederate SP server, `https://sso.xray.local:9031`, the PingFederate's application SSO endpoint, `/sp/startSSO.ping`, and the `SpSessionAuthnAdapterId` parameter with the adapter ID of the applicable SP adapter instance as the parameter value.

For example: `https://sso.xray.local:9031/sp/startSSO.ping?SpSessionAuthnAdapterId=sample`

If you have not defined a default URL for the adapter mapping, configured in [step 5](#), the IdP connection, or the PingFederate SP server, you must also configure your target application to include the `TargetResource` parameter in its SP-initiated SSO requests.



**Important:**

When using the parameters `TargetResource` or `TARGET` with their own query parameters included, the parameter value must be URL-encoded. Any other parameters that contain restricted characters, such as many SAML URNs, also must be URL-encoded. For information about URL encoding, see third party resources such as [HTML URL-encoding Reference](#). Parameters are case-sensitive.

7. When you are ready to test your new use case, go to **Authentication # Policies # Policies**. On the **Policies** window, select the **SP Authentication Policies** check box to enable policies for SP-initiated Browser SSO requests received by at the `/sp/startSSO.ping` endpoint, and click **Save**.



## Configuring SP authentication policies for users from multiple IdPs

You can configure service provider (SP) authentication policies to handle different authentication requirements for multiple identity provider (IdP) connections.

About this task

Assume you configure the following use cases in an earlier version of PingFederate:

- Two SP adapter instances on **Applications # Integration # SP Adapters**.

| Instance Name | Instance ID | Extended Contract |
|---------------|-------------|-------------------|
| Sample        | sample      | subject and email |
| Sample Delta  | sampleDelta | subject and email |

- Three entries on **Applications # Integration # Target URL Mapping**.

| URL   | Target Session |
|---|----------------|
| https://sso.xray.local:9031/SpSample/MainPage?app=Alpha&*   | Sample         |
| https://sso.xray.local:9031/SpSample/MainPage?app=Charlie&* | Sample         |
| https://sso.xray.local:9031/SpSample/MainPage?app=Delta&*   | Sample Delta   |

- Three IdP connections to your partners.

| Partner<br>(Federation ID)     | Identity Mapping | Attribute Contract            | Target Session Mapping<br>SP adapter instance name<br>(SP adapter instance ID) |
|--------------------------------|------------------|-------------------------------|--|
| Alpha<br>(sso.alpha.local)     | Account Mapping  | SAML_SUBJECT and<br>samLEmail | Sample<br>(sample)   |
| Charlie<br>(sso.charlie.local) | Account Mapping  | SAML_SUBJECT and<br>samLEmail | Sample<br>(sample)   |
| Delta<br>(sso.delta.local)     | Account Mapping  | SAML_SUBJECT and<br>samLEmail | Sample Delta<br>(sampleDelta)  |

In this example, all partners support SAML 2.0 and only the SP-initiated single sign-on (SSO) profile.

- SP-initiated SSO URLs for users from Alpha, Charlie, and Delta.

| Partner | SSO URL  |
|---------|--|
| Alpha   | https://sso.xray.local:9031/sp/startSSO.ping?<br>PartnerIdpId=sso.alpha.local&TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DAIph%26t%3Daa     |
| Charlie | https://sso.xray.local:9031/sp/startSSO.ping?<br>PartnerIdpId=sso.charlie.local&TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DCharlie%26t%3Dc |
| Delta   | https://sso.xray.local:9031/sp/startSSO.ping?<br>PartnerIdpId=sso.delta.local&TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DDelta%26t%3Dd     |

After upgrading to PingFederate 10.1, you have the following new requirements:

- Create new IdP connections to three new partners: Echo, Foxtrot and Golf.
  - Enforce multi-factor authentication (MFA) for users from Alpha, Charlie, Echo, and Golf through Bravo.
- Bravo requires a user ID to be passed in from the original source and returns only the user ID when the users fulfill the multi-factor authentication (MFA) requirement.

The new required components are:

- Two additional SP adapter instances. For more information, see [step 1](#):
  - **Sample Echo** to integrate with Echo's target application.
  - **Sample Golf** to integrate with Golf's target application.
- Four new IdP connections. For more information, see [step 2](#), [step 3](#), and [step 4](#):

| Partner<br>(Federation ID)     | Identity Mapping | Attribute Contract                          | Target Session Mapping<br>SP adapter instance name<br>(SP adapter instance ID) |
|--------------------------------|------------------|---|--|
| Bravo<br>(sso.bravo.local)     | No Mapping       | <b>SAML_SUBJECT</b> and no other attributes | N/A  |
| Echo<br>(sso.echo.local)       | No Mapping       | <b>SAML_SUBJECT</b> and <b>samlEmail</b>    | N/A  |
| Foxtrot<br>(sso.foxtrot.local) | Account Mapping  | <b>SAML_SUBJECT</b> and <b>samlEmail</b>    | Sample<br>(sample)   |
| Golf<br>(sso.golf.local)       | No Mapping       | <b>SAML_SUBJECT</b> and <b>samlEmail</b>    | N/A  |

In this example, all partners support SAML 2.0 and only the SP-initiated SSO profile.

- Three authentication policy contracts. For more information, see [step 5](#):
  - An authentication policy contract, **Authenticated**, to carry user attributes from Alpha and Charlie to their respective target applications.
  - Two other authentication policy contracts, **Echo authenticated** and **Golf authenticated**, to carry user attributes from Echo and Golf to their target applications.
- An instance of the HTTP Request Parameter Authentication Selector, **PartnerIdpId**, to determine if a request is meant for Alpha or Charlie, because Alpha's and Charlie's target applications share an SP adapter instance. For more information, see [step 6](#).
- Three SP authentication policies to enforce the multifactor authentication requirement. For more information, see [step 7](#), [step 8](#), and [step 12](#).
- Three adapter mappings between the authentication policy contracts and the applicable SP adapter instances. For more information, see [step 9](#):
  - Map from **Authenticated** to **Sample**.
  - Map from **Echo authenticated** to **Sample Echo**.
  - Map from **Golf authenticated** to **Sample Golf**
- Three additional target URL mappings between the applications requested by users from Echo, Foxtrot, and Golf to their respective SP adapter instances. For more information, see [step 10](#).
- SSO URLs for all partners. For more information, see [step 11](#).

Follow these steps to fulfill the new requirements:

### Steps

1. Go to **Applications # Integration # SP Adapters**. On the **SP Adapters** window, create two new SP adapter instances, as shown in the following table.

| Instance Name | Instance ID | Extended Contract |
|---------------|-------------|-------------------|
| Sample Echo   | sampleEcho  | subject and email |
| Sample Golf   | sampleGolf  | subject and email |

2. Create an IdP connection to Bravo.
  - a. On the **IdP Connections** window (**Authentication # Integration # IdP Connections**) create a SAML 2.0 IdP connection.
  - b. On **IdP Connection # Browser SSO # SAML Profiles**, select the **SP-Initiated SSO** check box.
  - c. On **IdP Connection # Browser SSO # User-Session Creation # Identity Mapping**, select **No Mapping**.
  - d. Complete the rest of the connection configuration.
3. Create IdP connections to Echo and Golf.
  - a. Go to **Authentication # Integration # IdP Connections**. On the **IdP Connections** window, create a SAML 2.0 IdP connection to Echo, and then to Golf.
  - b. On **IdP Connection # Browser SSO # SAML Profiles**, select the **SP-Initiated SSO** check box.
  - c. On **IdP Connection # Browser SSO # User-Session Creation # Identity Mapping**, select **No Mapping**.



#### Tip:

If the partner and your organization agree to support account linking, select **Account Linking**. When the **Account Linking** option is selected, you must map the applicable SP adapter instance, **Sample Echo** for Echo or **Sample Golf** for Golf, to the connection on **IdP Connection # Browser SSO # User-Session Creation # Target Session Mapping**. The rest of the steps remain unchanged.

This example does not use account linking.

- d. On **IdP Connection # Browser SSO # User-Session Creation # Attribute Contract**, enter `samlEmail` under **Extend the Contract**.
  - e. Complete the rest of the connection configuration.
  - f. Repeat these steps to create a SAML 2.0 IdP connection to Golf.
4. Create an IdP connection to Foxtrot.
    - a. On the **IdP Connections** window, create a SAML 2.0 IdP connection.
    - b. On **IdP Connection # Browser SSO # SAML Profiles**, select the **SP-Initiated SSO** check box.
    - c. On the **User-Session Creation** tab, click **Configure User-Session Creation**.
    - d. On the **Identity Mapping** tab, select **Account Mapping**.
    - e. On the **Attribute Contract** tab, enter `samlEmail` under **Extend the Contract**.
    - f. On the **Target Session Mapping** tab, click **Map New Adapter Instance** and follow the **Adapter Mapping & User Lookup** configuration workflow to map the attributes from the assertion to the SP adapter instance **Sample**.

Example:

| Adapter Contract | Source    | Value                  |
|------------------|-----------|------------------------|
| email            | Assertion | <code>samlEmail</code> |

| Adapter Contract | Source    | Value        |
|------------------|-----------|--------------|
| subject          | Assertion | SAML_SUBJECT |

- g. Complete the rest of the connection configuration.
5. Create three authentication policy contracts, one for Alpha and Charlie, one for Echo, and one for Golf.



**Note:**

The purpose of an authentication policy contract is to harness user attributes obtained through one or more authentication sources as the request flows through the applicable authentication policy. It is the medium between the authentication policies and the target applications. In general:

- You map attributes to authentication policy contracts from authentication policies. For more information, see [step 7](#) in this example.
- You map attributes from authentication policy contracts to target applications through adapter mappings. For more information, see [step 9](#) in this example.

- a. Go to **Authentication # Policies # Policy Contracts**. On the **Policy Contracts** window, click **Create New Contract** to create an authentication contract for users from Alpha and Charlie, for users from Echo, and then for users from Golf.
- b. On the **Contract Info** tab, enter a name for this authentication policy contract.  
In this example, the names are `Authenticated`, `Echo authenticated`, and `Golf authenticated`.
- c. On the **Contract Attributes** tab, extend the authentication policy contract with an attribute for user's email address, such as `mail`.
- d. Complete the rest of the connection configuration.
- e. Repeat these steps to create an authentication policy contract for users from Echo, and then for users from Golf.

Result:

Your policy contracts should be similar to the following samples.

| Contract Name      | Callback ID        | Adapter |
|--------------------|--------------------|---------|
| Authenticated      | 225C274E-0104      | OAuth   |
| Echo authenticated | 1928469D-0A34      | OAuth   |
| Golf authenticated | M564678B-0000-0104 | OAuth   |

6.



**Note:**

If multiple target applications share the same SP adapter instance, you must use a selector to evaluate the SP-initiated requests such that the policy engine can route the requests to the policy paths that are meant for the respective IdPs. This example uses an instance of the HTTP Request Parameter

Authentication Selector to categorize requests based on their respective `PartnerIdpId` query parameter values at runtime. The policy diverts accordingly based on the selector results.

Create an instance of the HTTP Request Parameter Authentication Selector.

- a. Go to **Authentication # Policies # Selectors**. On the **Selectors** window, click **Create New Instance**.
- b. On the **Type** tab, select **HTTP Request Parameter Authentication Selector** from the **Type** list and provide a name and ID for the selector instance.

In this example, the name and ID are both `PartnerIdpId`.

- c. On the **Authentication Selector** tab, enter `PartnerIdpId` in the **HTTP Request Parameter Name** field.
- d. On the **Selector Result Values** tab, enter `sso.alpha.local` and `sso.charlie.local` as the result values.


 **Note:**

In general, for the IdPs that you want to enforce additional authentication requirements through one or more SP authentication policies and whose target applications share an SP adapter instance, you must enter their federation IDs here.

- e. Complete the rest of the configuration.

Result:

Your selector instance should be similar to the following sample.



| Summary Information         |   |
|-----------------------------|---|
| Instance Name               | PartnerIdpId  |
| Instance ID                 | PartnerIdpId  |
| Type                        | HTTP Request Parameter Authentication Selector                      |
| Code Name                   | sso.alpha.local/sso.charlie.local/sso.charlie.local/sso.alpha.local |
| Parent Instance Name        | None  |
| Authentication Selector     |   |
| HTTP Request Parameter Name | PartnerIdpId  |
| Selector Result Values      |   |
| Result 1                    | sso.alpha.local   |
| Result 2                    | sso.charlie.local   |

7. Go to **Authentication # Policies # Policies**. On the **Policies** window, click **Add Policy** to define a policy to enforce the third-party authentication requirement for users from Echo, and then for users from Golf.

 **Tip:**

If you need more information about each sub step, see [step 4](#) in [Configuring an SP authentication policy for users from one IdP](#) on page 269.

- a. On the **Policy** window, enter a name and a description for this policy, and select **sso.echo.local (IdP Connection)** as the first policy action from the list.
- b. For the **sso.echo.local # Fail** path, select **Done** as the policy action.
- c. For the **sso.echo.local # Success** path, select **sso.bravo.local (IdP Connection)** as the policy action.
- d. Click **Options**, underneath **sso.bravo.local (IdP Connection)**, to relay the user ID (**SAML\_SUBJECT**) from `sso.echo.local` to `sso.bravo.local`.
- e. For the **sso.bravo.local # Fail** path, select **Done** as the policy action.
- f. For the **sso.bravo.local # Success** path, select the policy contract **Echo authenticated** as the policy action, and then click **Contract Mapping**, underneath the policy contract, to configure the fulfillment of the policy contract.

 **Tip:**

Essentially, you are mapping attributes to an authentication policy contract from the authentication policy.

- g. Repeat these steps to define a new authentication policy to enforce third-party authentication for users from Golf.

Result:

Your policies should be similar to the following samples.

8. On the **Policies** tab, click **Add Policy** to define a new authentication policy to enforce third-party authentication for users from Alpha and Charlie.

 **Note:**

If multiple target applications share the same SP adapter instance, you must use a selector to evaluate the SP-initiated Browser SSO requests, such that the policy engine can route the requests to the

policy paths that are meant for the respective IdPs. This example uses an instance of the HTTP Request Parameter Authentication Selector created in [step 6](#).

- a. On the **Policy** window, enter a name and a description for this policy, and select the instance of the HTTP Request Parameter Authentication Selector as the first policy action from the list.
- b. For the **sso.alpha.local** path, repeat [step 7](#) to configure the authentication requirement for the `sso.alpha.local` IdP connection.
- c. For the **sso.charlie.local** path, repeat [step 7](#) to configure the authentication requirement for the `sso.charlie.local` IdP connection.
- d. For the **sso.foxtrot.local** path, repeat [step 7](#) to configure the authentication requirement for the `sso.foxtrot.local` IdP connection.

**Result:**

Your policy should be similar to the following sample.



**Note:**

This window capture collapses the **sso.charlie.local** and **sso.foxtrot.local** policy paths for documentation presentation purposes.

When you go back to the **Policies** tab, your policies should be similar to the following samples.

- e. Click **Save**.

9. Create adapter mappings.

- a. Go to **Applications # Integration # Policy Contract Adapter Mappings**. On the **Policy Contracts** window, create three adapter mappings to map from the authentication policy contracts, created in [step 5](#), to the applicable SP adapter instances.
  - Map from **Authenticated** to **Sample**.
  - Map from **Echo authenticated** to **Sample Echo**.
  - Map from **Golf authenticated** to **Sample Golf**.



**Tip:**

If you need more information about each sub step, see [step 5](#) in [Configuring an SP authentication policy for users from one IdP](#) on page 269.

Your mappings should be similar to the following samples.

| Authentication Policy Adapter Mappings | Action |
|--|--------|
| Authenticated to Sample                | Delete |
| Echo authenticated to Sample Echo      | Delete |
| Golf authenticated to Sample Golf      | Delete |

Each adapter mapping should be similar to the following configuration.

| Attribute Sources & User Lookup            | Target App Info                          | Adapter Contract Fulfillment | Default Target URL | Resource Criteria | Summary |
|--|--|------------------------------|--------------------|-------------------|---------|
| <b>Mapping Configuration</b>               |  |                              |                    |                   |         |
| <b>Attribute Sources &amp; User Lookup</b> |  |                              |                    |                   |         |
| Data Sources                               | None                                     |                              |                    |                   |         |
| <b>Target App Info</b>                     |  |                              |                    |                   |         |
| <b>Adapter Contract Fulfillment</b>        |  |                              |                    |                   |         |
| subject                                    | subject (Authentication Policy Contract) |                              |                    |                   |         |
| what                                       | what (Authentication Policy Contract)    |                              |                    |                   |         |
| <b>Default Target URL</b>                  |  |                              |                    |                   |         |
| Resource Criteria                          | None                                     |                              |                    |                   |         |



**Tip:**

You are essentially mapping attribute values from the authentication policy contracts to target applications through the applicable SP adapter instances.

10. Create target URL mappings.

- a. Go to **Applications # Integration # Target URL Mapping**. On the **Target URL Mapping** window, add the following mappings.

| URL  | Target Session     |
|--|--------------------|
| https://sso.xray.local:9031/SpSample/MainPage/?app=Echo&*    | <b>Sample Echo</b> |
| https://sso.xray.local:9031/SpSample/MainPage/?app=Foxtrot&* | <b>Sample</b>      |
| https://sso.xray.local:9031/SpSample/MainPage/?app=Golf&*    | <b>Sample Golf</b> |

Result:

Your target URL mappings should be similar to the following samples.



## 11. Configure the following SSO URLs.

| Partner | SSO URL   |
|---------|---|
| Alpha   | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?PartnerIdpId=sso.alpha.local&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DAlpha%26t%3Da</code></p> <p>The SSO URL has not changed.</p> <p>Based on the current configuration, because the target applications for Alpha and Charlie share the same SP adapter instance, the <b>PartnerIdpId</b> query parameter is required for the configured policy to route the request to the corresponding IdP connection.</p>   |
| Charlie | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?PartnerIdpId=sso.charlie.local&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DCharlie%26t%3Dc</code></p> <p>The SSO URL has not changed.</p> <p>Based on the current configuration, because the target applications for Alpha and Charlie share the same SP adapter instance, the <b>PartnerIdpId</b> query parameter is required for the configured policy to route the request to the corresponding IdP connection.</p>   |
| Delta   | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?PartnerIdpId=sso.delta.local&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DDelta%26t%3Dd</code></p> <p>The SSO URL has not changed.</p> <p>Optionally, based on the current configuration, you can remove the <b>PartnerIdpId</b> query parameter because it is not required. You can also replace the <b>TargetResource</b> query parameter and its value with the <b>SpSessionAuthnAdapterId</b> query parameter and the applicable SP adapter instance ID, <code>SpSessionAuthnAdapterId=sampleDelta</code>, if you have configured a default target URL in the IdP connection to Delta, or a default SP SSO URL for all IdP connections.</p> |
| Echo    | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?SpSessionAuthnAdapterId=sampleEcho&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DEcho%26t%3De</code></p> <p>This is a new SSO URL.</p> <p>Optionally, based on the current configuration, you can remove the <b>TargetResource</b> query parameter and its value if you have configured a default target URL in the IdP connection to Echo, or a default SP SSO URL for all IdP connections.</p>   |

| Partner | SSO URL   |
|---------|---|
| Foxtrot | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?PartnerIdpId=sso.foxtrot.local&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DFoxtrot%26t%3Df</code></p> <p>This is a new SSO URL.</p> <p>Optionally, based on the current configuration, you can remove the <b>TargetResource</b> query parameter and its value if you have configured a default target URL in the IdP connection to Foxtrot, or a default SP SSO URL for all IdP connections.</p> |
| Golf    | <p><code>https://sso.xray.local:9031/sp/startSSO.ping?SpSessionAuthnAdapterId=sampleGolf&amp;TargetResource=https%3A%2F%2Fsso.xray.local%3A9031%2FSpSample%2FMainPage%3Fapp%3DGolf%26t%3Dg</code></p> <p>This is a new SSO URL.</p> <p>Optionally, based on the current configuration, you can remove the <b>TargetResource</b> query parameter and its value if you have configured a default target URL in the IdP connection to Golf, or a default SP SSO URL for all IdP connections.</p>   |



#### Important:

When using the parameters **TargetResource** or **TARGET** with their own query parameters included, the parameter value must be URL-encoded. Any other parameters that contain restricted characters, such as many SAML URNs, also must be URL-encoded. For information about URL encoding, see third party resources such as HTML URL-encoding Reference. Parameters are case-sensitive.

- To test your new use case, go to **Authentication # Policies # Policies**. On the **Policies** window, select the **SP Authentication Policies** check box to enable policies for SP-initiated Browser SSO requests received by at the `/sp/startSSO.ping` endpoint, and click **Save**.

#### Configuring SP authentication policies for internal users

The `/pf/adapter2adapter.ping` endpoint initiates direct IdP-to-SP adapter mapping, mostly intended for the internal users to access resources without maintaining a service provider (SP) and an identity provider (IdP) connection on the same server.

#### About this task

To prevent users from circumventing the SP authentication policies, this endpoint becomes inactive when SP authentication policies are enabled but IdP authentication policies are disabled. Administrators can configure SP authentication policies for the internal users to re-enable access to protected resources.

Suppose you have configured the following use cases in PingFederate 8.0.

For users from Hotel, an IdP:

- An SP adapter instance:
  - Name: Sample Hotel
  - ID: sampleHotel

- A SAML 2.0 IdP connection:
  - Partner: Hotel
  - Federation ID: sso.hotel.local
  - SAML Profile: SP-initiated single sign-on (SSO) only
  - Identity mapping method: Account mapping
  - Default target URL: <https://sso.xray.local:9031/SpSample/MainPage/?app=Hotel&t=h>
  - SSO URL: <https://sso.xray.local:9031/sp/startSSO.ping?PartnerIdpId=sso.hotel.local>

For internal users:

- An IdP HTML Form Adapter instance, HTML Form, validating credentials through a Password Credential Validator (PCV) instance against your user directory
- An adapter-to-adapter mapping:
  - Source: HTML Form
  - Target: Sample Hotel
  - Default target URL: <https://sso.xray.local:9031/SpSample/MainPage/?app=Internal&t=i>
  - SSO URL: <https://sso.xray.local:9031/pf/adapter2adapter.ping?SpSessionAuthnAdapterId=sampleHotel>

After upgrading to PingFederate 10.1, if you want to enforce multi-factor authentication for users from Hotel through Bravo, you can create an IdP connection to Bravo and the following authentication policy.

Because the authentication policy ends with a policy contract **Hotel authenticated**, you must create an adapter mapping, from the policy contract, to **Sample Hotel**, the SP adapter instance integrated with the target application. You also need to update the SSO URL for users from Hotel to <https://sso.xray.local:9031/sp/startSSO.ping?SpSessionAuthnAdapterId=sampleHotel>.

When you select the **SP Authentication Policies** check box without selecting the **IdP Authentication Policies** check box, the `/pf/adapter2adapter.ping` endpoint is disabled to prevent malicious Hotel's users, with specific knowledge of PingFederate endpoints, your PingFederate configuration, and functional credentials, from trying to access the target application through the SSO URL intended for your internal users. By doing so, you circumvent the SP authentication policy that is meant for them.

To re-enable access to the application for the internal users, you need the following new components:

- An additional SP adapter instance, **Sample Internal** to integrate with the target application. See [step 1](#).
- An authentication policy contract, **Internal authenticated**, to carry attributes from internal users to the target applications. See [step 2](#).
- An instance of the CIDR Authentication Selector to be deployed in the authentication policy to reject users from external networks to access protected resources using your HTML Form Adapter. Alternatively, deploy an instance of the PingID Adapter in the authentication policy to enforce multifactor authentication for users who authenticated successfully using the HTML Form Adapter. See [step 3](#).
- An authentication policy for the internal users. See [step 4](#).
- An adapter mapping to map from the authentication policy contracts **Internal authenticated** to the SP adapter instance **Sample Internal**. See [step 5](#).
- A new SSO URL for the internal users. See [step 6](#).

Follow these steps to fulfill the new requirements.

Steps

1. Go to **Applications # Integration # SP Adapters**.

2. Click **Create New Instance** to create a new SP adapter instance.

For each new instance, include the name, ID, and extended contract.

| Instance Name   | Instance ID    | Extended Contract |
|-----------------|----------------|-------------------|
| Sample Internal | sampleInternal | subject and email |

3. Go to **Authentication # Policies # Policy Contracts**.
4. Click **Create New Contract** to create an authentication policy contract.

 **Note:**

In this example, the name of the policy contract is `Internal authenticated`.

The purpose of an authentication policy contract is to harness user attributes obtained through one or more authentication sources as the request flows through the applicable authentication policy. It is the medium between the authentication policies and the target applications. Generally speaking:

- You map attributes to authentication policy contracts from authentication policies. [step 4](#) in this example.
- You map attributes from authentication policy contracts to target applications through adapter mappings, [step 5](#) in this example.

5. Go to **Authentication # Policies # Selectors**.
6. Click **Create New Instance** to create an instance of the CIDR Authentication Selector with one or more network ranges that correspond to your internal users.

 **Note:**

In this example, the name and ID are both `Internal users`.

The purpose of the CIDR Authentication Selector is for the policy engine to reject users from external networks to access protected resources using your HTML Form Adapter. You can also deploy the PingID Adapter to enforce multifactor authentication for users authenticated through the HTML Form Adapter. If users fail to fulfill the PingID multifactor authentication requirement, the policy engine rejects their requests, thus providing another layer of protection against unauthorized access from malicious users.

7. Go to **Authentication # Policies # Policies** to configure your policies as follows.

### With PingID Adapter

#### With CIDR Authentication Selector

8. Go to **Applications # Integration # Policy Contract Adapter Mappings**.
9. Click **Create New Instance** and create a mapping from the new authentication policy contract, `Internal authenticated.`, to the new SP adapter instance, `sampleInternal`.
10. On the **Default Target URL** window, enter `https://sso.xray.local:9031/SpSample/MainPage/?app=Internal&t=i`.
11. Update the SSO URL for your internal users to `https://sso.xray.local:9031/sp/startSSO.ping?SpSessionAuthnAdapterId=sampleInternal`.

## Policy fragments

You can manage policy fragments under **Authentication # Policies # Fragments**. You can create reusable policy fragments and apply them in multiple authentication policies.

Fragments make policies easier to administer, allowing you to extract common patterns that exist among different policies and to manage them in one place. For example, you can create a reusable policy fragment with policy components that you frequently use and apply that fragment in multiple policies. When the authentication requirements need adjustments, you can make those changes in the fragment without updating the policies that reference it.

Fragments can use other fragments; you can chain five or more fragments together. You can also use as many fragments as you want throughout a policy, provided that the way the policy is structured, there aren't over five fragments being processed at one time.

On the **Fragments** window:

- Click **Add Fragment** to define a policy fragment.
- Click the name of an existing fragment to edit its configuration.
- Click **Select Action** to copy or delete an existing fragment.

### Defining policy fragments

You define policy fragments in the **Fragment** window.

Before you begin

Make sure that you have configured at least two policy contracts to function as input and output contracts.

Steps

1. In the **Name** field, type a name for the policy fragment.
2. Optional: Change the identifier for the fragment. This ID will be used to reference input and output attributes in the advanced Expressions fulfillment option. It cannot be changed after the fragment has been created.
3. Optional: Type a description for the fragment.
4. From the **Inputs** list, select the input authentication policy contract that calling members will need to fulfill. The attributes contained in the contract will be available for use throughout the policy.
5. From the **Outputs** list, select the output authentication policy contract that this fragment will fulfill. Calling members will be able to use the values of the attributes contained in the output policy contract.

6. From the **Policy** list, select an IdP adapter, an IdP connection, a selector, or a fragment. (Detailed policy configuration instructions are provided in step 5 in [Defining authentication policies](#) on page 254.)



#### Important:

You can select **Fragments** as the policy action and then select a policy fragment that you have created. When you select a fragment, click **Fragment Mapping** and use the in-product help links to access the topics that describe how to configure the mapping.

- a. Click **Options**, and select the source and the attribute to be used as the incoming user ID.
- b. Click **Rules**, and define authentication policy rules using attributes from the previous authentication source.
- c. Configure **Fail** and **Success** paths. For a fragment to succeed, you must map it into a LIP or APC based on the output contract. You can also use a fragment in a calling policy and set both of the fragment's exit Fail/Success nodes to Done.



#### Note:

The **Copy** and **Paste** feature lets you copy a policy path and paste it into another place in the same policy, another policy, or a policy fragment. After you copy and paste a path, follow the on-screen instructions to correct any errors.

One benefit of this feature is that you can easily add a new step at the start or middle of an existing policy. To do that, copy and then remove the existing path below the point where you will define the new step. After you define the new step, paste the copied path back into the policy below the new step.

7. Click **Save**.

## Policy contracts

Authentication policy contracts, formerly known as connection mapping contracts, give PingFederate administrators a variety of capabilities.

Authentication policy contracts provide PingFederate administrators the following benefits:

- The capability to build an attribute contract with attribute values from multiple authentication sources or datastore queries through an authentication policy.
- The flexibility to map only the policy contract to a connection. Administrators do not have to map into the connection the authentication sources in the policy leading up to the contract. For example, administrators can experiment with various IdP adapter instances without the burden of adding and removing them to and from the connection.
- The potential to reuse authentication policies that use the same policy contract in multiple service provider (SP) connections, identity provider (IdP) connections, and OAuth use cases, using the OAuth Authorization Code or Implicit grant types.

Authentication policy contracts are also the media to carry user attributes from IdPs to SPs when PingFederate is deployed as a federation hub. For more information, see [Federation hub use cases](#) on page 108.

### Managing policy contracts

You can manage authentication policy contracts in the **Authentication # Policies # Policy Contracts** window.

#### Steps

1. Click **Create New Contract** to create a new authentication policy contract.

2. Edit an existing authentication policy contract by clicking its name.
3. Check the policy contract usage.
4. Optional: On the **Policy Contracts** window, click **Delete** to remove an authentication policy contract, if the authentication policy contract is not in use, or cancel the removal request.

### Editing contract information

You can create new policy contracts or edit existing ones from the **Policy Contracts** window.

#### Steps

1. Go to **Authentication # Policies # Policy Contracts**.
2. Click **Create New Contract** or select an existing contract.
3. On the **Contract Info** tab, enter or modify the contract name.
4. Click **Next**.

### Defining contract attributes

To manage the user attributes in the authentication policy contract, go to **Authentication # Policies # Policy Contracts**.

#### About this task

Every authentication policy contract comes with a `subject` attribute. You can extend the contract with additional attributes as needed.

#### Steps

- If needed, enter an attribute under **Extend the Contract**, and then click **Add**.



#### Note:

Attribute names are case-sensitive and must suit the needs of your partners. Repeat to add more attributes as needed.

- Click **Edit**, **Update**, or **Cancel** to modify an existing attribute or undo changes.
- Click **Delete** to remove an existing attribute.

### Reviewing the policy contract

On the **Summary** tab, you can review the policy contract.

#### Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

### Special attribute names in contracts

PingFederate handles the `SAML_AUTHN_CTX` and `SAML_AUTHN_INSTANT` attribute names in specific ways.

#### `SAML_AUTHN_CTX`

The `SAML_AUTHN_CTX` attribute is involved in determining the authentication context value for the flow, which is mapped into the `acr` claim in the OpenID Connect (OIDC) ID token or the `AuthnContextClassRef` in the SAML assertion. The authentication context value represents the quality or type of authentication that was performed and may be used by downstream applications to decide what

privileges to grant a user. The `AuthnContextClassRef` is required in SAML assertions and will be set to `urn:oasis:names:tc:SAML:1.0:am:unspecified` if a value can't be determined by the procedure below.

`PingFederate` determines the authentication context value by iterating over each authentication source that was invoked in the flow. Identity provider (IdP) adapters can return an authentication context value by including the `org.sourceid.saml20.adapter.idp.authn.authnCtx` attribute in the attribute map returned from `lookupAuthN()`.

For IdP connections, the authentication context value comes from the `acr` claim in the ID token or the `AuthnContextClassRef` value in the assertion. `PingFederate` also allows a mapping to be configured in the IdP connection between local and remote authentication context values under **Browser SSO # Protocol Settings # Overrides**.

`PingFederate` iterates over the authentication sources that were invoked, pulling an authentication context value from each one. The last authentication context value returned by an authentication source becomes the authentication context value for the overall flow.

Further control over the authentication context value for the flow is available by adding `SAML_AUTHN_CTX` to an authentication policy contract (APC). Any value mapped into this attribute overrides the authentication context value for the flow and will be passed to downstream applications through the ID token or assertion.

In some cases, you might want to populate the `SAML_AUTHN_CTX` in the APC with the value from a specific source. For SAML IdP connections, you can add `SAML_AUTHN_CTX` to the attribute contract. The corresponding attribute for OIDC IdP connections is `acr`. This will be automatically populated with the authentication context value coming from that IdP connection and you can then map from that attribute into `SAML_AUTHN_CTX` in the APC.

For IdP adapters that return an authentication context value, you can do the same thing by adding `org.sourceid.saml20.adapter.idp.authn.authnCtx` to the IdP adapter contract.



#### Note:

Mapping into the `org.sourceid.saml20.adapter.idp.authn.authnCtx` attribute in the adapter's internal **Adapter Contract Mapping** will not have any effect. The authentication context value for the adapter will still be the value returned from `lookupAuthN()`.

Another thing you might want to do is ensure that the authentication context value for the overall flow matches the value that was requested by the client or partner (through the `acr_values` request parameter, or the `RequestedAuthnContext` for SAML authentication requests). This can be done by adding a **Requested AuthN Context** selector to the authentication policy and configuring it to **Add or Update AuthN Context Attribute**. When you do this, the requested authentication context value is added to the attributes of the first authentication source encountered after the selector in the policy. The key for the added attribute is `SAML_AUTHN_CTX`. This attribute can then be added to the contract of that authentication source and mapped in the `SAML_AUTHN_CTX` of the APC to ensure that it becomes the authentication context value for the flow.

There's a last opportunity to override the authentication context value for a particular flow at the level of the service provider (SP) connection or the OIDC policy. For an SP connection, you can add `SAML_AUTHN_CTX` to the attribute contract and map the desired value into it. For an OIDC policy, you can add `acr` to the policy contract and map a value into it.

`SAML_AUTHN_INSTANT`

The `SAML_AUTHN_INSTANT` attribute is involved in determining the authentication instant value for the flow, which is mapped into the `auth_time` claim in the OIDC ID token or the `AuthnInstant` in the SAML assertion. This value is used by downstream applications to determine how recently the end user authenticated. Certain actions may be restricted if the authentication was not recent enough. The



`AuthnInstant` is required in SAML assertions and will be set to the current time if a value can't be determined by the procedure below.

`PingFederate` determines the authentication instant value by iterating over each authentication source that was invoked in the flow. IdP adapters can return an authentication instant value by including the `org.sourceid.saml20.adapter.idp.authn.authnInst` attribute in the attribute map returned from `lookupAuthN()`.

For IdP connections, the authentication instant value comes from the `auth_time` claim in the ID token or the `AuthnInstant` value in the assertion.

When an authentication session exists for an authentication source and is used in the flow, the authentication instant value originally obtained from the IdP adapter or connection is used. If the source didn't return an authentication instant, the creation time of the session is used instead.

`PingFederate` iterates over the authentication sources that were invoked, pulling an authentication instant value from each one. The most recent authentication instant value returned by an authentication source becomes the authentication instant value for the overall flow.

Further control over the authentication instant value for the flow is available by adding `SAML_AUTHN_INSTANT` to the APC. Any value mapped into this attribute overrides the authentication instant value for the flow and will be passed to downstream applications through the ID token or assertion.

In some cases, you might want to populate the `SAML_AUTHN_INSTANT` in the APC with the value from a specific source. For SAML IdP connections, you can add `SAML_AUTHN_INSTANT` to the attribute contract. The corresponding attribute for OIDC IdP connections is `auth_time`. This will be automatically populated with the authentication instant value coming from that IdP connection and you can then map from that attribute into `SAML_AUTHN_INSTANT` in the APC.

For IdP adapters that return an authentication instant value, you can do the same thing by adding `org.sourceid.saml20.adapter.idp.authn.authnInst` to the IdP adapter contract.



#### Note:

Mapping into the `org.sourceid.saml20.adapter.idp.authn.authnInst` attribute in the adapter's internal **Adapter Contract Mapping** will not have any effect. The authentication instant value for the adapter will still be the value returned from `lookupAuthN()`.

There's a last opportunity to override the authentication instant value for a particular flow at the level of the OIDC policy. You can add `auth_time` to the policy contract and map a value into it.

## Adapter Mappings

Configuring adapter mappings allows administrators to map attributes from an authentication policy contract directly to a service provider (SP) adapter instance.

This allows the administrators to chain multiple authentication sources in an SP authentication policy, to build an authentication policy contract using attributes from authentication sources in the policy path, and to apply the authentication policy contract to the target application.

### Configuring authentication policy adapter mappings

Authentication policy adapter mappings allow administrators to map attributes from an authentication policy contract directly to a service provider (SP) adapter instance.

#### Steps

1. Go to **Applications # Integration # Policy Contract Adapter Mappings**.
2. From the **Source Instance** list, select the applicable authentication policy contract from the .
3. From the **Target Instance** list, select the SP adapter instance integrated with your target application.
4. Click **Add Mapping**.

5. Follow the **Applications # Integration # Adapter-to-Adapter Mappings** wizard to create the mapping.
  - a. Optional: On the **Attribute Sources & User Lookup** tab, click **Add Attribute Source** to configure datastore queries to fulfill the SP adapter contract.

Queries are executed in the order they are displayed on the **Attribute Sources & User Lookup** tab. Use the up and down arrows as needed to adjust the order.

If a required attribute cannot be fulfilled, such as the user identifier of an adapter, the request fails. For more information, see [Fulfillment by datastore queries](#) on page 397.

- b. On the **Adapter Contract Fulfillment** tab, select a source and an attribute to fulfill the SP adapter contract.

 **Note:**

Select **Authentication Policy Contract** from the **Source** list to map directly from the policy contract to the SP adapter contract or another choice to fulfill the SP adapter contract through datastore queries, dynamic texts, or results from OGNL expression

- c. Optional: On the **Default Target URL** tab, specify a default target URL for this mapping configuration.
    - d. Optional: On the **Issuance Criteria** tab, configure conditions to be validated before issuing an SP adapter contract. For more information, see [Define issuance criteria for adapter mapping](#).
    - e. On the **Adapter-to-Adapter Mapping Summary** tab, review the configuration and modify as needed. When complete, click **Done**.
6. On the **Adapter-to-Adapter Mappings** window, click **Save**.

### Defining issuance criteria for adapter mapping

You can define issuance criteria for adapter mappings in PingFederate to conditionally approve or reject requests based on individual attributes. Satisfy criteria in order for PingFederate to move a request to the next phase.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.


 **Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description  |
|--|--|
| <b>Authentication Policy Contract</b>                          | Select to evaluate attributes from the authentication policy contract.   |
| Context  | Select to evaluate properties returned from the context of the transaction at runtime.   |
|  |  <b>Note:</b><br>The <b>HTTP Request</b> context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values. |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.   |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.  |

2. In the **Attribute Name** list, select the attribute to be evaluated.
3. In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**

 **Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.
- If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - For more information, see [Attribute mapping expressions](#) on page 225.
  - Click **Show Advanced Criteria**.
  - In the **Expression** field, enter the required expressions.
  - Optional: In the **Error Result** field, enter an error code or message.



**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- Click **Add**.
- Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- Optional: Repeat to add multiple criteria using attribute mapping expressions.

## Sessions

This topic describes the differences between application and authentication sessions.

### Application sessions

Application sessions apply to PingFederate applications hosted on its user-facing endpoints, such as the profile management page and the grant management endpoints. When the inactivity threshold or the maximum lifetime is reached, PingFederate redirects previously authenticated users back to the authentication sources, identity provider (IdP) adapter instances or IdP connections, subject to the configuration of authentication sessions.

### Authentication sessions

Authentication sessions control when PingFederate redirects previously authenticated users back to the authentication sources on subsequent requests for browser-based single sign-on (SSO) or PingFederate applications.

Authentication sessions typically wrap an adapter so that PingFederate creates the session when user authentication has succeeded. PingFederate invokes the adapter's authentication logic again only when the session reaches its limits. However, depending on the implementation, an adapter can be aware of an authentication session that wraps it and override this logic. In particular, PingFederate creates

authentication sessions configured for an Identifier First Adapter instance only when the complete single sign-on (SSO) transaction has succeeded. This lets the adapter prompt the user for a different user identifier when a chained adapter authentication fails because, for example, there's a typo in the user identifier.

### Session storage options

When authentication sessions are enabled, PingFederate maintains session data in memory.

PingFederate also supports maintaining session data both in memory and on an external storage. This optional capability allows administrators to support use cases where a longer session duration or a greater resilience against restarts of PingFederate and browsers is desired. The retrieval and update operations are optimized to provide a fast and seamless user experience. For instance, a retrieval from the external storage is only required when an authentication session is not found in memory.

#### **Note:**

Persistent authentication sessions require an external storage. For more information, see [Defining a datastore for persistent authentication sessions](#) on page 957.

### Inactivity (idle) timeout and maximum lifetime

When authentication sessions are enabled, an authenticated user is not sent back to the authentication system as long as the user makes another request within the idle timeout window, 60 minutes by default. If the user makes another request within the idle timeout window, the authentication session is extended by the idle timeout value, another 60 minutes by default. For externally stored authentication sessions, this operation is optimized to only send updates to the external storage when the remaining idle timeout window is less than 75%.

An authentication session can be repeatedly extended by multiple requests and remains valid until the maximum timeout value is reached, in which case the user will be redirected back to the authentication system.

#### **Tip:**

The authentication system might or might not challenge the user to complete an authentication process based on its own session management policy or processing logic.

### Configuration options

Administrators can enable authentication sessions for all authentication sources, with or without making the authentication sessions persistent, and with or without specifying overrides for selected authentication sources.

Alternatively, administrators can enable authentication sessions for a few selected authentication sources, optionally with their own sets of overrides. The override options include:

- Disable or enable authentication sessions
- Make authentication sessions persistent
- Override the idle timeout, the maximum timeout, or both, in minutes, hours, or days
- Enforce authentication requirement based on authentication context

Because sessions are tracked with their respective authentication context, administrators can optionally configure PingFederate to compare the requested authentication context found in the authentication request against the authentication context found in the session. If the values do not match, PingFederate redirects the user back to the authentication system.

## Tracking options for logout

Administrators can optionally configure additional tracking options for logout to control whether PingFederate should leverage the single logout (SLO) application endpoints to terminate adapter sessions, add sessions to the session revocation list as users sign out, or do both. Publish revoked sessions to provide a secure SLO experience with PingAccess deployments.

### Configuring tracking options for logout

You can configure PingFederate to track adapter sessions for logout.

#### About this task

An adapter session is a logout entry that, if tracked, ensures a logout request is sent to the adapter during single logout (SLO). Then the adapter can remove any session data that it is tracking for the user.

#### Steps

1. Go to **Authentication # Policies # Sessions**.
2. Optional: Enable SLO for all adapter instances on a per-user basis by selecting the **Track Adapter Sessions for Logout** check box.

When this check box is selected, an adapter session is tracked whenever an adapter is invoked during single sign-on (SSO). When this check box is not selected, the tracking of the adapter session depends on other factors, such as whether SLO is enabled on the partner connection involved in the SSO. This check box is not selected by default.

3. Optional: Add the associated sessions to the revocation list on logout by selecting the **Track Revoked Sessions on Logout** check box.

When selected, PingFederate always adds the associated sessions to the session revocation list as users sign off, even if an error occurs to the logout requests. This allows other systems, such as PingAccess, to query the validity of a given session at the Session Revocation API endpoint, `/pf-ws/rest/sessionMgmt/revokedSris`. This check box is selected by default for new installations.



#### Note:

If your use cases involve OAuth requests, consider enabling the **Check session revocation status** option in the applicable Access Token Management instances so that the token validation process takes into account whether a session has been added to the revocation list. For more information, see [Managing session validation settings](#) on page 612.

4. Optional: Change the number of minutes until the revoked sessions are removed from the revocation list for optimal performance by changing the value in the **Session Revocation Lifetime** field. You can enter an integer between 1 and 43200. The default value is 490 minutes.



#### Important:

The **Session Revocation Lifetime** value should match or exceed the idle timeout value, or the maximum session lifetime value, of the authentication sources and the relying parties. For example, the default value of 490 minutes exceeds the global **Max Timeout** value for authentication sessions by 10 minutes to allow for clock skew among servers.

5. Click **Save**.

### Configuring application sessions

You can configure and override the default timeout limits for application sessions in the PingFederate administrative console.

#### Steps

1. Go to **Authentication # Policies # Sessions**.
2. Optional: On the **Sessions** window, override the default timeout values under **Application Sessions**.

| Field                 | Description   |
|-----------------------|---|
| Idle Timeout (Minute) | <p>Modify the default inactivity timeout value in the <b>Idle Timeout (Minute)</b> field.</p> <p>You can enter an integer between 1 and 1576800, representing a range of one minute to 1,095 days. You can also empty the value to indicate that the inactivity timeout value should match the maximum lifetime.</p> <p>The default value is 60 minutes.</p>  |
| Max Timeout (Minutes) | <p>Modify the default maximum lifetime of an authentication session in the <b>Max Timeout (Minutes)</b> field.</p> <p>You can enter an integer between 1 and 1576800, representing a range of one minute to 1,095 days. You can also empty the value to indicate that the authentication sessions do not expire until they are removed from the system.</p> <p>The value of the <b>Max Timeout (Minutes)</b> field cannot be less than that of the <b>Idle Timeout (Minute)</b> field.</p> <p>The default value is 480 minutes, which is 8 hours.</p> |

3. To keep your configuration, click **Save**.

### Configuring authentication sessions

Use the **Sessions** window to configure and override the default timeout limits for authentication sessions.

#### Steps

1. Go to **Authentication # Policies # Sessions**.
2. Optional: In the **Sessions** window, configure the global policy and timeout settings under **Authentication Sessions**.

**AUTHENTICATION SESSIONS**

ENABLE AUTHENTICATION SESSIONS FOR ALL SOURCES

MAKE AUTHENTICATION SESSIONS PERSISTENT

HASH UNIQUE USER KEY VALUE

IDLE TIMEOUT   ▼

MAX TIMEOUT   ▼

- a. Select the **Enable Sessions for All Authentication Sources** check box if PingFederate should track authentication sessions for all authentication sources. Clear this check box if you prefer to

enable authentication sessions for only a few authentication sources or disable authentication sessions altogether. This check box is not selected by default.

 **Note:**

For any HTML Form Adapter instance that has been configured to allow users to indicate whether their device is shared or private, if a user signs on without selecting the **This is my device** check box on the login form, PingFederate removes authentication session information, if found, and does not store authentication sessions for the user.

- b. If your use cases require longer sessions or greater resilience against restarts of PingFederate and browsers, select the **Make Authentication Sessions Persistent** check box.

 **Note:**

Selecting the check box causes the PF.PERSISTENT cookie to be set in the user's browser. By default, this cookie persists across browser restarts. To allow for very long sessions, the expiration period for the cookie defaults to 94608000 seconds, or 3 years. You can change this period in the **cookie-max-age** setting in the file `persistent-session-cookie-config.xml`. If you prefer to have the PF.PERSISTENT cookie cleared on browser exit, set **cookie-max-age** to -1. Regardless of the cookie's expiration period, PingFederate always enforces the configured session timeouts. However a user might lose their session earlier if the PF.PERSISTENT cookie expires or is removed by the browser.

Persistent authentication sessions require an external storage.

 **Note:**

As of version 9.3, PingFederate alleviates DoS attacks by protecting the persistent session process. It does this by treating repeated persistent cookies that do not have a PF cookie as a replay if repeated in a specified time. This time is set to 300 seconds by default, and you can change it by modifying **EmptySessionReplayRetentionsSecs** in the `<pf-install>/server/default/data/config-store/org.sourceid.saml20.service.session.StoredSessionServiceImpl.xml` file.

For example:

- If a request arrives with a PF.PERSISTENT cookie and without a PF cookie, PingFederate starts counting the time set in **EmptySessionReplayRetentionsSecs**.
- If another request arrives with the same PF.PERSISTENT cookie and without a PF cookie within the time specified in the configuration file, PingFederate treats it as a replayed request and does not perform a database lookup.

You can disable this behavior by setting **EmptySessionReplayRetentionsSecs** to 0.

- c. Select the **Hash Unique User Key Value** check box if you want the unique user key to be hashed using SHA-256. When this option is enabled, PingFederate associates this hashed value with the particular user's authentication sessions.

The hashed value is used for features related to unique user keys; for example, the HTML Form Adapter's **Revoke Sessions After Password Change or Reset** option (for more information, see [Configuring an HTML Form Adapter instance](#) on page 306). The hashed value will be visible



in server and audit logs, and in session storage if **Make Authentication Sessions Persistent** is enabled.

- d. Optional: Override the default timeout values for all authentication sources.

| Field        | Description  |
|--------------|--|
| Idle Timeout | <p>Modify the default inactivity timeout value in the <b>Idle Timeout</b> field and select a unit of measurement from the list.</p> <p>You can enter an integer that represents a time period between 1 minute and 1,095 days. You can also empty the value to indicate that the inactivity timeout value should match the maximum lifetime.</p> <p>The default inactivity timeout value is 60 minutes.</p>  |
| Max Timeout  | <p>Modify the default maximum lifetime of an authentication session in the <b>Max Timeout</b> field and select a unit of measurement from the list.</p> <p>You can enter an integer that represents a time period between 1 minute and 1,095 days. You can also empty the value to indicate that the authentication sessions do not expire until they are removed from the system.</p> <p>The value of the <b>Max Timeout</b> field cannot be less than that of the <b>Idle Timeout</b> field.</p> <p>The default inactivity timeout value is 480 minutes, or eight hours.</p> |

- 3. Optional: Configure policy and settings for individual authentication sources under **Overrides**.


OVERRIDES

| Authentication Source | Enable Sessions          | Persistent               | Override Timeouts        | Idle Timeout | Max Timeout | Units   | Authentication Context Sensitive | Action |
|-----------------------|--------------------------|--------------------------|--------------------------|--------------|-------------|---------|----------------------------------|--------|
| Select                | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |              |             | Minutes | <input type="checkbox"/>         | Add    |

- a. From the **Authentication Source** list, select an identity provider (IdP) adapter instance or an IdP connection.
- b. Configure individual policy for the selected authentication source as follows.

| Global policy (under Authentication Sessions)   | Individual policy (under Overrides)  |
|---|--|
| <p>The <b>Enable Sessions for All Authentication Sources</b> check box is not selected.</p> <p>Authentication-session tracking is not enabled for all authentication sources.</p> | <p>Select the <b>Enable Sessions</b> check box to enable authentication-session tracking for the selected authentication source.</p> |

| Global policy (under Authentication Sessions)   | Individual policy (under Overrides)   |
|---|---|
| <p>The <b>Enable Sessions for All Authentication Sources</b> check box is selected.</p> <p>Authentication-session tracking is enabled for all authentication sources.</p> | <p>Clear the <b>Enable Sessions</b> check box to disable authentication-session tracking for the selected authentication source.</p> <p>Select the <b>Enable Sessions</b> check box for the purpose of overriding other authentication-session settings for the selected authentication source.</p> |


 **Note:**

The **Enable Sessions** check box is not selected by default.

For any HTML Form Adapter instance that has been configured to allow users to indicate whether their device is shared or private, if a user signs on without selecting the **This is my device** check box on the login form, PingFederate removes authentication session information, if found, and does not store authentication sessions for the user.

- c. Select the **Persistent** check box if your use cases require a longer session duration or a greater resilience against restarts of PingFederate and browsers.

Available and applicable only if the **Enable Sessions** check box is selected. The **Persistent** check box is not selected by default.

 **Note:**

Persistent authentication sessions require an external storage.

 **Note:**

Notes under step 2b apply here as well.

- d. If authentication-session tracking is enabled for the selected authentication source and if you want to configure specific timeout values, select the **Override Timeouts** check box and configure timeout settings.

| Field        | Description  |
|--------------|--|
| Idle Timeout | <p>You can enter an integer that represents a time period between 1 minute and 1,095 days. You can also empty the value to indicate that the inactivity timeout value should match the maximum lifetime.</p> <p>This field has no default value.</p>   |
| Max Timeout  | <p>You can enter an integer that represents a time period between 1 minute and 1,095 days. You can also empty the value to indicate that the authentication sessions do not expire until they are removed from the system.</p> <p>The value of the <b>Max Timeout</b> field cannot be less than that of the <b>Idle Timeout</b> field.</p> <p>This field has no default value.</p> |

| Field | Description   |
|-------|---|
| Unit  | Select from the list the unit of measurement for both the <b>Idle Timeout</b> and <b>Max Timeout</b> fields.<br><br>The default selection is <b>Minutes</b> . |

- e. If authentication-session tracking is enabled for the selected authentication source and if you want to enforce authentication requirement based on the authentication context for the selected authentication source, select the **Authentication Context Sensitive** check box. This check box is not selected by default.
- f. Click **Add**.
- g. Repeat these steps to configure individual policy and settings for additional authentication sources.

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

4. To save your configuration changes, click **Save**.

#### Result

When PingFederate authentication sessions are enabled, you can configure session-validation options for your OAuth use cases. These optional settings enable you to conjoin the validity of access tokens and the authentication sessions of the users. For more information, see [Managing session validation settings](#) on page 612.

## Bundled adapters

---

PingFederate comes bundled with a set of adapters for integration and customizable configuration, depending on your service needs.

PingFederate's bundled set of adapters:

- Composite Adapter
- HTML Form IdP Adapter
- HTTP Basic IdP Adapter
- Identifier First Adapter
- Kerberos Adapter
- OpenToken IdP Adapter
- OpenToken SP Adapter
- Passthrough IdP Adapter
- PingID Adapter
- PingOne Fraud Adapter
- PingOne MFA Adapter
- PingOne Protect Adapter
- PingOne Verify Adapter
- Reference ID IdP Adapter
- Reference ID SP Adapter
- X.509 Certificate IdP Adapter

## Composite Adapter

PingFederate's Composite Adapter allows adapter chaining for single sign-on (SSO) requests that best fit your user or organization's needs.

For an Identity Provider (IdP), PingFederate includes a Composite Adapter that allows an administrator to chain the selection of available adapter instances for a connection. At runtime, adapter chaining means that SSO requests are passed sequentially through each adapter instance specified until one or more authentication results are found for the user.

Adapter chaining can be used to choose an adapter instance based on the method by which a user authenticated, or to integrate an organization's multi-factor authentication requirement.



### Tip:

For complex authentication requirements, consider implementing authentication policies. Go to **Authentication # Policies**. From the **Policies** window, make changes on the **Policies** tab.

### Configuring a Composite Adapter instance

Configuring a Composite Adapter instance allows you to enable adapter chaining for a user authentication connection.

About this task

Configure an instance of a Composite Adapter in PingFederate using the administrative console.

Steps


1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. On the **IdP Adapter** tab, configure your Composite Adapter instance as follows:
  - a. Click **Add a new row to 'Adapters'**.
  - b. From the **Adapter Instance** list, select an IdP adapter instance. Click **Update**.

For more information, see the **Description** column in each configuration section and the following table.

#### PingFederate's column names and descriptions for creating an adapter instance

| Column                             | Description  |
|------------------------------------|--|
| Policy<br>(Required)               | <p><b>Required</b> (the default) indicates authentication through this adapter instance is needed to continue SSO processing and to invoke any remaining instances in the chain. If you are integrating multifactor authentication, use this policy for each instance. The Composite Adapter instance returns an error when the authenticate attempt against a required adapter instance fails.</p> <p><b>Sufficient</b> indicates that authentication through this adapter instance is enough to satisfy requirements, along with any required instances that have already been selected. Any subsequent configured instances in the chain are not invoked.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>For the sufficient policy to work correctly, the adapter must return control to PingFederate after any kind of a failure.</p> </div> |
| AuthN Context Weight<br>(Required) | <p>If more than one adapter instance in the chain is capable of returning an authentication context, this relative weight is used to determine which value is included in the assertion, unless the value is overridden under <b>AuthN Context Override</b>.</p> <p>If weights are the same for two or more contexts, the first one processed is included in the assertion.</p> <p>The default value is 3.</p>   |
| AuthN Context Override             | <p>If provided, this value overrides the authentication context value that might be returned from the adapter instance. The value in this field can be sent in the assertion if the associated adapter instance is invoked.</p> <p>If weights are the same for two or more contexts, the first one processed is included in the assertion.</p>   |

- c. Add at least one more adapter instance and configure its **Policy**, **AuthN Context Weight**, and **AuthN Context Override** settings.

Repeat this step to add more adapter instances as needed.

At runtime adapter chaining is sequential, starting at the top of the list.

#### **Important:**

You can configure several types of adapters -- for example, the IWA IdP Adapter -- to direct end users to an error page if authentication fails for any reason, which will halt further progress through

a composite-adapter chain. For such adapter instances, ensure the **Error URL** option is not used in the instance configuration when continuation through an adapter-chaining sequence is required.

- d. Optional: In the **Action** column, manage the selected adapter instances.
- e. Configure **Input User ID Mapping**.

If you have configured any IdP Adapter developed using the `IdpAuthenticationAdapterV2` interface from the PingFederate SDK, including the HTML Form Adapter, the **Input User ID Mapping** section appears. Additionally, some IdP adapters, such as the PingID Adapter and the separately available Symantec VIP Adapter, require a user ID to be passed in from an earlier-authentication step to perform multifactor authentication. If so, an administrator must specify the attribute containing the unique ID on this window. For example, to pre-populate the username

of an HTML Form Adapter instance with an attribute from an earlier authentication source in the previous steps:

1. Click **Add a new row to 'Input User ID Mapping'**.
2. From the **Target Adapter** list, select the HTML Form Adapter instance.
3. From the **User ID Selection** list, select a source attribute.
4. Click **Update**.

 **Note:**

For OAuth use cases, entries in the **Input User ID Mapping** section might override the `login_hint` parameter value provided by the OAuth clients when they submit their requests to the `/as/authorization.oauth2` authorization endpoint.

 **Tip:**

By default, the HTML Form Adapter does not allow the users to change the username if it is configured to be pre-populated with an attribute from another authentication source. You can override this restriction by enabling the **Allow Username Edit** option on a per-adapter instance.

f. Configure **Attribute Name Synonyms**.

If any attributes are logically equivalent across two adapter instances but have different names, click **Add a new row to 'Attribute Name Synonyms'**. Select attributes from the **Name** and **Synonym** lists to create a mapping between them.

The attribute name under **Synonym** and its value are used in the SAML assertion when the two values returned from each adapter are identical. If returned values are different, both values are sent for the synonym.

 **Note:**

Without this configuration to identify synonymous attribute names, both names and their values are sent in the SAML assertion.

g. Define the order in which different values are returned for the same attribute name.

For attributes of the same name configured in different adapter instances, you can change the order of returned values when the values are different. (Values are merged if they are the same.)

By default, the **Add to Back** value for an attribute name configured in the first instance is returned first and also listed first in the resulting SAML assertion. Then any different value from the same attribute name in a subsequently invoked instance is appended.

The order might not matter for many attributes, but in the case of the SAML-subject attribute, only the first value in the SAML assertion can be used for an SP connection partner under normal circumstances. Click **Add to Front** to reverse the default order, if needed.

5. On the **Extended Contract** tab, click **Add** to add attributes to be returned from each adapter instance configured on the previous window.

 **Note:**

Attributes must correspond exactly to any or all of the attribute names listed on the Adapter Attribute tab for each configured adapter instance.

6. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
9. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration. If you want to exit without saving the configuration, click **Cancel**.



## HTML Form Adapter

The HTML Form Adapter supports user authentication when it occurs outside of the PingFederate server through an application or the authentication module of an identity access management (IAM) system that leverages multiple user repositories and a password credential validator (PCV) instance.

Initial user authentication is normally handled outside of the PingFederate server using an application or an IAM system authentication module. Adapters or agents from PingFederate integration kits are typically used to integrate with these local authentication mechanisms.

PingFederate packages an HTML Form Adapter that delegates user authentication to a PCV, such as an LDAP Username PCV. The adapter validates credentials against a user repository through a PCV instance.

To validate against multiple user repositories, you can add multiple PCV instances to an instance of the HTML Form Adapter. In this case, if a PCV instance fails to validate the user credentials, PingFederate uses the next PCV instance.

When PingFederate receives an authentication request and the use case involves an HTML Form Adapter instance, PingFederate invokes the adapter if it does not find a valid authentication session. If the HTML Form Adapter does not find a valid adapter session, it displays a sign-on page and prompts the user for credentials.

If you configure and enable customer IAM, users can optionally register local accounts or sign on using third-party identity providers (IdPs). If a user chooses to sign on using local accounts, the credentials are validated using the designated PCV instance or instances. If validated, PingFederate generates the requested single sign-on (SSO) token or moves the request to the next checkpoint if authentication policies are involved.

In terms of the sign-on experience, the HTML Form Adapter lets you:

- Use different customizable and localizable template files.
- Define a logout path or a logout redirect page.
- Notify users with password expiry information.
- Let users change or reset their network passwords, or redirect users to a company-hosted password management system.
- Enable self-service password reset, account unlock, and username recovery.

You can configure all capabilities on a per-adapter instance basis.

PingFederate also tracks sign-on attempts per adapter instance, which adds a layer of protection against brute force and dictionary attacks. When the **Challenge Retries** threshold is reached, PingFederate locks out the user for a period of time. The default value for the **Challenge Retries** setting is 3. If a higher value is preferred, consider reviewing the account lockout policy of the user repository first. For example, if the account lockout threshold is set to 5 on the target directory server and the **Challenge Retries** setting is also set to 5 or higher, the fifth sign-on attempt could lock the user accounts on the directory server. The lockout period is controlled by the Account Locking Service.



### Note:

The HTML Form Adapter considers a password consisting only of spaces as empty and does not refer to the underlying LDAP for authentication. As a result, while passwords containing only spaces will trigger PingFederate's Account Locking Service, the service will not lock the account at the LDAP level even if the user exceeds the LDAP limit for sign-on attempts. If the LDAP service locks the account due to too many failed sign-on attempts with passwords that contain non-space characters, and a user attempts to log in using a password consisting only of spaces after the Account Locking Service's lockout period has ended, PingFederate will report the situation as an invalid password, rather than a locked account.

This adapter does not provide an authentication context. For SAML connections, sets the authentication context as follows:

- urn:oasis:names:tc:SAML:1.0:am:unspecified for SAML 1.x
- urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified for SAML 2.0

can override the authentication context with either an instance of the Requested AuthN Context Authentication Selector or the **SAML\_AUTHN\_CTX** attribute in the SAML attribute contract. The latter takes precedence.



#### Note:

The HTML Form Adapter is authentication API-capable. The authentication API is a JSON-based API that enables end-user interactions, such as credential prompts, to be handled by an external web application. This API does so by providing access to the current state of the flow as an end user steps through a authentication policy.

For more information, see [Authentication applications and the authentication API](#) on page 429.


### Configuring an HTML Form Adapter instance

In the **IdP Adapters** window, configure an HTML Form Adapter instance to validate a user authentication session with a *[[password credential validator (PCV)]]* when your initial authentication needs to integrate with an external application or an identity management system (IdM) authentication module.

#### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.
4. On the **IdP Adapter** tab, configure your HTML Form Adapter instance as follows:
  - a. If you have not yet defined the desired Password Credential Validator instance, click **Manage Password Credential Validators** to do so.



- b. Click **Add a new row to 'Credential Validators'** to select a credential-authentication mechanism instance for this adapter instance.
- c. From the **Password Credential Validator Instance** list, select a Password Credential Validator instance. Click **Update**.


Add as many validators as necessary. Use the up and down arrows to adjust the order in which you want PingFederate to attempt credential authentication. If the first mechanism fails to validate the credentials, PingFederate moves sequentially through the list until credential validation


succeeds. If none of the Password Credential Validator instances can authenticate the user's credentials, and the challenge retries maximum has been reached, the process fails.




 **Note:**




If usernames overlap across multiple Password Credential Validator instances, this failover setup could lock out those accounts in their source locations.



- d. Click **Add a new row to 'Credential Validators'** to select a credential-authentication mechanism instance for this adapter instance.
- e. Enter values for the adapter configuration, as described below.


| Field                           | Description   |
|---------------------------------|---|
| Challenge Retries<br>(Required) | <p>The account lockout threshold for this adapter instance. When the number of login failures reaches this threshold, the user is locked out for a period time.</p> <p>The default value is 3.</p>  |
| Session State                   | <p>Determines whether this HTML Form Adapter instance maintains adapter sessions and shares adapter sessions with other HTML Form Adapter instances.</p> <p><b>Globally</b></p> <p>Adapter sessions from this HTML Form Adapter instance are shared among other HTML Form Adapter instances that use the same <b>Session State</b> field value <b>Globally</b>.</p> <p><b>Per Adapter</b></p> <p>HTML Form Adapter maintains adapter sessions on a per-instance basis. Sessions from this HTML Form Adapter instance are not shared with other HTML Form Adapter instances.</p> <p><b>None</b></p> <p>This HTML Form Adapter does not maintain adapter sessions for this HTML Form Adapter instance.</p> <div data-bbox="609 1329 737 1373" data-label="Section-Header"> <p> <b>Note:</b></p> </div> <div data-bbox="609 1388 1459 1518" data-label="Text"> <p>To enable PingFederate authentication sessions globally or individually for this adapter instance, select <b>None</b>. For more information about PingFederate authentication sessions, see <a href="#">Sessions</a> on page 292 and <a href="#">Configuring authentication sessions</a> on page 295.</p> </div> <p>The default selection is <b>None</b>.</p> |

| Field           | Description   |
|-----------------|---|
| Session Timeout | <p>The number of idle minutes before an HTML Form Adapter session times out based on inactivity. If left blank, the lifetime falls back on the <b>Session Max Timeout</b> field value. Ignored if <b>None</b> is selected for the <b>Session State</b> field.</p> <p>Applicable only when the <b>Session State</b> field is set to <b>Globally</b> or <b>Per Adapter</b>.</p> <div data-bbox="605 432 1464 667" style="border: 1px solid black; padding: 5px;"><p> <b>Tip:</b></p><p>When you enable PingFederate authentication sessions globally or individually for this adapter instance, you can configure the <b>Idle Timeout</b> setting for the same purpose. For more information, see <a href="#">Configuring authentication sessions</a> on page 295.</p></div> <p>The default value is 60 minutes.</p> |


| Field               | Description   |
|---------------------|---|
| Session Max Timeout | <p>The maximum lifetime, in minutes, before an HTML Form Adapter session expires regardless of whether the <b>Session Timeout</b> field value has been reached. Ignored if <b>None</b> is selected for the <b>Session State</b> field.</p> <p>Applicable only when the <b>Session State</b> field is set to <b>Globally</b> or <b>Per Adapter</b>.</p> <div data-bbox="602 432 1474 669" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>When you enable PingFederate authentication sessions globally or individually for this adapter instance, you can configure the <b>Max Timeout</b> setting for the same purpose. For more information, see <a href="#">Configuring authentication sessions</a> on page 295.</p> </div> <p>The default value is 480 minutes, which translates to 8 hours.</p> <div data-bbox="602 732 1474 1478" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This setting sets a maximum lifetime, subject to inactivity timeout. Consider the following examples:</p> <ul style="list-style-type: none"> <li>▪ A user initiated a single sign-on (SSO) request at 9 a.m. and has not made another SSO request since then. At 10 a.m., the HTML Form Adapter session times out based on inactivity based on the default <b>Session Timeout</b> field value of 60 minutes.</li> <li>▪ Another user initiated an SSO request at 9 a.m. and has been making SSO requests every hour at least once. This HTML Form Adapter session does not time out because the user has been actively making SSO requests; however, the HTML Form Adapter session does expire at 5 p.m. based on the default <b>Session Max Timeout</b> default value of 8 hours.</li> <li>▪ If you leave both the <b>Session Max Timeout</b> and <b>Session Timeout</b> fields blank, HTML Form Adapter sessions do not expire until PingFederate restarts or the HTML Form Adapter sessions are cleaned up by another means.</li> <li>▪ If you leave the <b>Session Max Timeout</b> field blank but set a value for the <b>Session Timeout</b> field, HTML Form Adapter sessions do not expire until they time out based on inactivity.</li> </ul> </div> <div data-bbox="602 1493 1474 2024" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>Session information is stored in the PF cookie. By default, the PF cookie is a session cookie and is typically removed when the user closes the browser.</p> <p>You can optionally extend the lifetime of the PF cookie by editing the <code>session-cookie-config.xml</code> file, located in the <code>&lt;pf_install&gt;/pingfederate/server/default/data/config-store</code> directory. For more information, see <a href="#">Extending the lifetime of the PingFederate cookie</a> on page 904 .</p> <p>Alternatively, you can enable PingFederate authentication sessions, store the authentication sessions externally, and leverage them as users request protected resources after restarting their browsers. For more information, see <a href="#">Sessions</a> on page 292.</p> </div> |



| Field                         | Description  |
|-------------------------------|--|
| Allow Password Changes        | <p data-bbox="613 207 1455 300">Enables or disables the ability for users to change their network password using this adapter instance as they initiate SSO requests and are prompted to enter their username and password.</p> <p data-bbox="613 319 1455 474">As needed, you can also provide your users the Change Password endpoint shown on the <b>Summary</b> window. The Change Password endpoint allows users to change their password without submitting SSO requests. For more information, see the <code>/ext/pwdchange/Identify</code> section.</p> <div data-bbox="613 499 1474 705" style="border: 1px solid black; padding: 5px;"> <p data-bbox="613 516 735 554"> <b>Note:</b></p> <p data-bbox="613 575 1414 667">The LDAP Username PCV and the PingOne for Enterprise Directory PCV are currently the only PCVs bundled with PingFederate that support the change password feature.</p> </div> <div data-bbox="613 716 1474 926" style="border: 1px solid black; padding: 5px;"> <p data-bbox="613 737 797 779"> <b>Important:</b></p> <p data-bbox="613 800 1430 892">When connecting to an Active Directory (AD) server, you must secure the datastore connection using LDAPS. AD requires this level of security to allow password changes.</p> </div> <p data-bbox="613 940 1097 970">This check box is not selected by default.</p> |
| Password Management System    | <p data-bbox="613 999 1349 1058">The URL for redirecting users to a company-specific password management system to change their password.</p> <p data-bbox="613 1077 971 1106">This field has no default value.</p>  |
| Enable 'Remember My Username' | <p data-bbox="613 1136 1442 1257">Allows users to store their username as a cookie when authenticating with this adapter. Once stored, the username in the login form is pre-populated for subsequent transactions. Select the check box to enable the cookie functionality.</p> <div data-bbox="613 1272 1474 1509" style="border: 1px solid black; padding: 5px;"> <p data-bbox="613 1293 735 1331"> <b>Note:</b></p> <p data-bbox="613 1352 1455 1478">This option is hidden when users authenticate through a Composite Adapter instance that chains this adapter behind another authentication source with an <b>Input User ID Mapping</b> configuration and the <b>Allow Username Edits</b> check box is not selected.</p> </div> <p data-bbox="613 1524 1097 1554">This check box is not selected by default.</p>  |


| Field                           | Description   |
|---------------------------------|---|
| Enable 'This is My Device'      | <p>Allows users to indicate whether their device is shared or private by selecting the <b>This is my device</b> check box on the login form. In this mode, PingFederate authentication sessions, if enabled, are not stored unless the user indicates the device is private. For more information about PingFederate authentication session, see <a href="#">Sessions</a> on page 292.</p> <p>This check box is not selected by default.</p> <div data-bbox="602 464 1466 674" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>Adapter session tracking, if enabled by setting the <b>Session State</b> field to <b>Globally</b> or <b>Per Adapter</b>, is not affected by this configuration and the user's selection.</p> </div>                     |
| Change Password Policy Contract | <p>Select an authentication policy contract to enforce strong authentication requirements, such as multi-factor authentication through PingID, before letting their users change their passwords. This is similar to using a <b>Password Reset Policy Contract</b>.</p> <p>The field is empty by default.</p>   |
| Change Password Notification    | <p>When selected, a notification is generated for the user who has successfully changed the password through the HTML Form Adapter. The destination is the user's email address, specifically the mail attribute value returned by the LDAP Username PCV instance.</p> <div data-bbox="602 1031 1466 1346" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This option requires the selection of the <b>Allow Password Changes</b> check box and a notification publisher instance. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p> <p>In addition, the LDAP Username PCV is the only PCV bundled with PingFederate that supports this notification feature.</p> </div> |
|                                 | <p>This check box is not selected by default.</p>   |


| Field                          | Description   |
|--------------------------------|---|
| Show Password Expiring Warning | <p>When selected, the HTML Form Adapter displays a warning to an authenticated user if the password associated with the account is about to expire soon. The message provides the number of days until the expiry of the current password and the options to change the password immediately or to snooze the message. Both the threshold and the snooze interval are configurable in the <b>Advanced fields</b> section; the default values are 7 days and 24 hours, respectively.</p> <div data-bbox="602 445 1471 682" style="border: 1px solid black; padding: 5px;"><p> <b>Note:</b></p><p>This option requires the selection of the <b>Allow Password Changes</b> check box. (Both check boxes are not selected by default.) In addition, the LDAP Username PCV is currently the only PCV bundled with PingFederate that supports the password expiring warning feature.</p></div> |
|                                | <p>This check box is not selected by default.</p>   |



| Field               | Description  |
|---------------------|--|
| Password Reset Type | <p>Select one of the following methods for self-service password reset (SSPR).</p> <p><b>Authentication Policy</b></p> <p>Based on the policy contract selected from the <b>Password Reset Policy Contract</b> list, finds the applicable authentication policy to handle self-service password reset requests. If the users are able to fulfill the authentication requirements as specified by the policy, allows the users to reset their password.</p> <p><b>Email One-Time Link</b></p> <p>Users receive a notification with a URL to reset their password. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p> <p><b>Email One-Time Password</b></p> <p>Users receive a notification with a one-time password (OTP) to reset their password. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p> <p><b>PingID</b></p> <p>Users are prompted to follow the PingID authentication flow to reset their password. Ensure the <b>PingID Username Attribute</b> field in the selected LDAP Username PCV instance is configured; otherwise, users will not be able to reset their password. You must also download the settings file from the PingOne admin portal and upload the file to the <b>PingID Properties</b> advanced field.</p> <div data-bbox="651 1184 1468 1581" style="border: 1px solid black; padding: 10px;"> <p> <b>Important:</b></p> <p>Do not use a method that is already part of a multi-factor authentication policy that includes a password challenge, as that would indirectly reduce that authentication policy to a single factor. For example, if users normally authenticate with a password challenge and then PingID, the self-service password reset method should not be PingID. Instead, choose the <b>Authentication Policy</b> option, select a policy contract from the <b>Password Reset Policy Contract</b> list, and configure an authentication policy for self-service password reset.</p> </div> <p><b>Text Message</b></p> <p>Users receive a text message notification with an OTP to reset their password. Ensure the <b>SMS Attribute</b> field in the selected LDAP Username PCV instance is configured; otherwise, users will not receive text message notification for password reset. If you have not yet configured SMS provider settings in , click <b>Manage SMS Provider Settings</b>.</p> <p><b>None</b></p> <p>Users cannot reset password through this HTML Form Adapter instance.</p> <p>The default selection is <b>None</b>.</p> |

| Field  | Description  |
|--|--|
| Password Reset Policy Contract                 | <p>If you use an authentication policy to handle SSPR requests, you must select a policy contract here.</p> <p>This policy contract doesn't require any extended attributes because uses this policy only to find the applicable authentication policies for password resets.</p> <div data-bbox="602 401 1474 926" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>You must use a policy contract dedicated only to password reset. You can't use this policy contract for SSO anywhere else. To define a policy contract solely for password reset, click <b>Manage Policy Contracts</b>.</p> <p>An authentication policy that uses this contract allows users to reset their password. Ensure the policy uses strong authentication methods to securely identify the user who initiated the password reset operation. Map the <i>incoming user ID</i> for adapters in the policy to <b>Requested User</b> and confirm that adapters will only return success when this user is the one authenticating.</p> <p>For guidelines on designing adapters for use in password reset or password change authentication policies, see <a href="#">Developing IdP adapters</a> on page 1120.</p> </div> |
| Revoke sessions after password change or reset | <p>Revokes a user's authentication sessions in other browsers after a password change or reset is completed by this adapter. This option relies on selecting a unique user key attribute for this adapter (see <a href="#">Setting pseudonym and masking options</a> on page 423).</p> <p>To enable this option, you must also enable the <b>Allow Password Changes</b> option, or set the <b>Password Reset Type</b> option to something other than <b>None</b>.</p> <div data-bbox="602 1203 1474 1451" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This revocation capability is not supported if the IdP session registry is configured with the Directed Clustering - Subclusters state management architecture. For more information, see <a href="#">IdP Session Registry Service</a> on page 203 and <a href="#">Defining subclusters</a> on page 200.</p> </div>   |

| Field                  | Description  |
|------------------------|--|
| Account Unlock         | <p data-bbox="613 207 1455 300">Enables or disables the ability for users to unlock their account using this adapter instance as they initiate SSO requests and are prompted to enter their username and password.</p> <p data-bbox="613 321 1450 478">As needed, you can also provide your users the Account Recovery endpoint shown on the <b>Summary</b> tab. The Account Recovery endpoint allows users to unlock their account without submitting SSO requests. For more information, see the <a href="#">/ext/pwdreset/Identify</a> section in <a href="#">IdP endpoints</a> on page 1250.</p> <div data-bbox="613 499 1466 730" style="border: 1px solid black; padding: 5px;"> <p data-bbox="613 510 735 562"> <b>Note:</b></p> <p data-bbox="613 573 1433 699">You must also select a <b>Password Reset Type</b> value other than <b>None</b> and the <b>Allow Password Changes</b> check box as well because the initiating user must prove ownership of the account through the password reset flow.</p> </div> <p data-bbox="613 751 1466 1003">Unlike self-service password reset self-service password reset (SSPR), when users succeed in proving account ownership, they are allowed to retain their current password or to reset their password as needed. Furthermore, self-service account unlock is only compatible with PingDirectory and Microsoft AD. If the underlying datastore is connected to an Oracle Unified Directory or Oracle Directory Server, users can only unlock their account by changing their current password through the password reset flow.</p> <p data-bbox="613 1024 1401 1077">In addition, the LDAP Username PCV is the only PCV bundled with PingFederate that supports self-service account unlock.</p> <p data-bbox="613 1098 1101 1129">This check box is not selected by default.</p> |
| Local Identity Profile | <p data-bbox="613 1161 1450 1276">Select a local identity profile to offer users the options to authenticate through third-party identity providers, self-register as part of the sign-on experience, and manage their accounts through a self-service profile management page.</p> <p data-bbox="613 1297 954 1329">There is no default selection.</p>  |
| Notification Publisher | <p data-bbox="613 1350 1433 1444">If this adapter instance is configured with self-service account management capabilities, select a notification publisher instance from the list.</p> <p data-bbox="613 1465 1450 1591">Based on selected notification publisher instance configuration, PingFederate generates the required notification messages. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p>   |

| Field                    | Description   |
|--------------------------|---|
| Enable Username Recovery | <p>Enables or disables the ability for users to recover their username when using this adapter instance as they initiate SSO requests and are prompted to enter their username and password.</p> <p>As needed, you can also provide your users the Username Recovery endpoint shown on the <b>Summary</b> tab. The Username Recovery endpoint allows users to recover their username without submitting SSO requests. For more information, see the <code>/ext/idrecovery/Recover</code> section in <a href="#">IdP endpoints</a> on page 1250.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>This capability requires a notification publisher instance. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>. In addition, the LDAP Username PCV is the only PCV bundled with PingFederate that supports self-service username recovery.</p> </div> <p>For each username recovery request, if PingFederate can locate the user record using the email address provided by the user and other requirements are met, PingFederate generates a notification containing the recovered username. The destination is the email address provided by the user.</p> <p>This check box is not selected by default.</p> |

- f. Optional: Click **Show Advanced Fields** to review or modify default values.
  - g. If you have chosen **Text Message** as the password reset type, click **Manage SMS Provider Settings** at the bottom of the page to configure the SMS provider through which PingFederate can send text message notifications to the users.
5. On the **Extended Contract** tab, configure additional attributes for this adapter instance as needed. The HTML Form Adapter contract includes two core attributes: `username` and `policy.action`. At runtime, PingFederate fulfills the `policy.action` core attribute as described in the following table.

| Local identity profile | Runtime fulfillment   |
|------------------------|---|
| A selection is made.   | <p>If the local identity profile is configured with one or more authentication sources, and if the user chooses to register or authenticate with one of them, PingFederate sets the value to that authentication source. This design allows you to create rules in your authentication policies and form different policy paths for each authentication source. For more information, see <a href="#">Enabling third-party identity providers</a> on page 376.</p> <p>Whether or not the local identity profile is configured with any authentication sources, if the user chooses to register directly by clicking on the <b>Register now</b> link, sets the value to <code>identity.registration</code>. This fulfillment allows you to create rules to differentiate authentication requirements from the registration flow. For more information, see <a href="#">Creating advanced registration mapping</a> on page 384.</p> |
| No selection is made.  | The <code>policy.action</code> attribute is not fulfilled.  |

6. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**


Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.


- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
9. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration. If you want to exit without saving the configuration, click **Cancel**.



## HTML Form Adapter advanced fields

When configuring an HTML Form Adapter, you can use the advanced fields at the bottom of the **IdP Adapter** tab in the **Create Adapter Instance** window.

Advanced fields for setting password credentials and changes

| Property                                | Description   |
|---|---|
| <b>Login Template</b><br>(Required)     | <p>The HTML core template to prompt the users for their credentials. PingFederate allows each configured adapter instance to use a different login page template.</p> <p>The default template file is <code>html.form.login.template.html</code>.</p> <p>Unless otherwise stated, all template files are located in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/template</code> directory.</p>  |
| <b>Logout Path</b>                      | <p>Any path in the format indicated. Setting a path invokes adapter logout functionality that is normally invoked during SAML 2.0 single-logout (SLO) processing. The resulting logout path is <code>/ext/&lt;Logout Path&gt;</code>. The logout path extends from the base URL. If virtual host names are configured, the logout path is accessible at those locations as well.</p> <p>Available primarily for use cases where the partner software as a service (SaaS) providers who do not support SAML SLO but want the users' identity provider (IdP) single sign-on (SSO) sessions to end after logging out of the SaaS services. For these use cases, the SaaS providers could redirect the users to the logout URL after the users sign out of their platforms.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If specified, the path must be unique across all HTML Form Adapter instances, including child instances.</p> </div> <p>This field has no default value.</p> |
| <b>Logout Redirect</b>                  | <p>The landing page at the service provider (SP) after successful identity provider (IdP) logout, applicable only when the <b>Logout Path</b> field is configured.</p> <p>This field has no default value.</p>  |
| <b>Logout Template</b>                  | <p>The HTML template displayed when a user has successfully logged out in a configuration where the <b>Logout Path</b> field is configured, but the <b>Logout Redirect</b> field is not.</p> <p>The default template file is <code>idp.logout.success.page.template.html</code>.</p>  |
| <b>Change Password Template</b>         | <p>The HTML core template to prompt the users to change their password. PingFederate allows each configured adapter instance to use a different change password template.</p> <p>The default template file is <code>html.form.change.password.template.html</code>.</p>   |
| <b>Change Password Message Template</b> | <p>The HTML template to be displayed when a user has successfully changed the password through the HTML Form Adapter.</p> <p>The default template file is <code>html.form.message.template.html</code>.</p>   |

| Property  | Description  |
|---|--|
| <b>Password Management System Message Template</b>          | <p>The HTML template notifies the users that they are being redirected to a password management system to change their password.</p> <p>The default template file is <code>html.form.message.template.html</code>.</p>   |
| <b>Password Timeout Update</b>                              | <p>The time, in minutes, a user has for a password change session on the <b>Change Password</b> and <b>Reset your password</b> pages.</p> <p>By default, the value is 30 minutes and this feature is enabled. If the field is left blank, this feature is disabled.</p> <div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <ul style="list-style-type: none"> <li>▪ To use this feature for the self-service password reset (SSPR) flow, you must select a <b>Password Reset Type</b> other than <b>None</b>.</li> <li>▪ To use this feature for the change password with an authentication policy flow, you must select a policy contract for the <b>Change Password Policy Contract</b> and enable <b>Allow Password Changes</b>.</li> </ul> </div> |
| <b>Change Password Email Template</b>                       | <p>The HTML email template PingFederate uses to generate the email message to notify the user that the password has been changed or reset successfully through the HTML Form Adapter.</p> <p>The default template file is <code>message-template-end-user-password-change.html</code>, located in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/template/mail-notifications</code> directory.</p> <p>Applicable only if an instance of the SMTP Notification Publisher is selected in the <b>Notification Publisher</b> list.</p>  |
| <b>Expiring Password Warning Template</b>                   | <p>The HTML core template to warn the users about approaching the password expiry day.</p> <p>The default template file is <code>html.form.password.expiring.notification.template.html</code>.</p>  |
| <b>Threshold for Expiring Password Warning</b>              | <p>The threshold, in days, to start warning the user about approaching the password expiry day.</p> <p>The default value is 7 days.</p>  |
| <b>Snooze Interval for Expiring Password Warning</b>        | <p>The amount of time, in hours, to delay the next warning after the user has chosen to change the password later.</p> <p>The default value is 24 hours.</p>   |
| <b>Require Re-authentication for Expiring Password Flow</b> | <p>Requires a user to sign on again after changing their password if they initiated the change on the password expiring warning.</p> <p>By default, this feature is disabled.</p> <p>Applicable only when the <b>Show Password Expiry Warning</b> is enabled.</p>  |
| <b>Require Re-authentication for Change Password Flow</b>   | <p>Requires a user to sign on again with their new password after completing a successful change password flow.</p> <p>By default, this feature is enabled.</p>  |


| Property   | Description  |
|--|--|
| <b>Require Re-authentication for Password Reset Flow</b> | <p>Requires a user to sign on again with their new password after completing a successful password reset or account unlock flow.</p> <p>By default, this feature is enabled.</p>   |
| <b>Login Challenge Template</b>                          | <p>The HTML core template to be displayed as the second step during a strong authentication. It is used to prompt the user to answer a challenge question after the first-factor login. The RADIUS Username Password Credential Validator (PCV) is an example of where it could be used.</p> <p>The default template file is<br/><code>html.form.login.challenge.template.html</code>.</p>   |
| <b>'Remember My Username' Lifetime</b>                   | <p>The number of days the cookie remains valid. Enter the number of days you want the username remembered in a cookie.</p> <p>The cookie lifetime is reset upon each successful login in which the <b>Remember my username</b> check box on the login form is selected.</p> <div data-bbox="521 758 1466 995" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>The value is ignored when users authenticate through a Composite Adapter instance that chains this adapter behind another authentication source with an <b>Input User ID Mapping</b> configuration, and the <b>Allow Username Edits</b> check box is not selected.</p> </div> <p>You can enter an integer between 1 and 3650.</p> <p>The default value is 30 days.</p>  |
| <b>'This is My Device' Lifetime</b>                      | <p>The number of days that a user's selection of the <b>This is my device</b> check box on the login form is retained.</p> <p>The lifetime is reset upon each successful login in which the <b>This is my device</b> check box on the login form is selected.</p> <p>You can enter an integer between 1 and 3650.</p> <p>The default value is 30 days.</p>   |
| <b>Allow Username Edits During Chaining</b>              | <p>When users authenticate through a Composite Adapter instance that chains this adapter behind another authentication source with an <b>Input User ID Mapping</b> configuration or initiate an OAuth authorization request with a <code>login_hint</code> parameter, the username in the login form is pre-populated. Users are not allowed to edit their usernames.</p> <p>Select this check box if you want to allow users to edit the pre-populated username in the login form.</p> <div data-bbox="521 1650 1466 1854" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>Users who authenticate through a Composite Adapter instance without an <b>Input User ID Mapping</b> configuration or this adapter directly always need to enter their usernames.</p> </div> <p>This check box is not selected by default.</p> |



| Property  | Description   |
|---|---|
| <b>Track Authentication Time</b>                    | <p>When selected, the time of authentication for each user is tracked and can be utilized by applicable use cases. For example, if an OAuth client sends an authorization request with a <b>max_age</b> parameter, such request prompts the user to reauthenticate when the elapsed time between the current time and the time of the previous authentication is greater than the <b>max_age</b> value.</p> <p>This check box is selected by default.</p> |
| <b>Post-Password Change Re-Authentication Delay</b> | <p>The HTML Form Adapter reauthenticates the user using the new password immediately after a successful password change request. As needed, enter the amount of time, in milliseconds, that the adapter can wait prior to the reauthentication attempt.</p> <p>The default value is 0, which is the minimum value. The maximum value is 60000, or 1 minute.</p>   |

Advanced fields for self-service password reset and account unlock

| Property   | Description  |
|--|--|
| <b>Password Reset One-Time Link Email Template</b>     | <p>The HTML template to send the user an email with a password reset link when <b>Password Reset Type</b> is <b>Email One-Time Link</b>.</p>   |
| <b>Password Reset One-Time Password Email Template</b> | <p>The HTML template to send the user an email with a one-time password reset code when <b>Password Reset Type</b> is <b>Email One-Time Password</b>.</p> <p>The default template file is <code>message-template-forgot-password-code.html</code>.</p>   |
| <b>Password Reset Complete Email Template</b>          | <p>The HTML template to send the user an email that the password reset is complete.</p> <p>The default template file is <code>message-template-forgot-password-complete.html</code>.</p>   |
| <b>Password Reset Failed Email Template</b>            | <p>The HTML template to send the user an email that the password reset attempt failed.</p> <p>The default template file is <code>message-template-forgot-password-failed.html</code>.</p>  |
| <b>Password Reset Code Template</b>                    | <p>The HTML template to prompt the user to enter the one-time passcode (OTP) for password reset.</p> <p>This template applies when the password reset type is <b>Email One-Time Password</b> or <b>Text Message</b>.</p> <p>The default template file is <code>forgot-password-resume.html</code>.</p> |
| <b>Password Reset Template</b>                         | <p>The HTML template to prompt the user to define a new password.</p> <p>This template applies for all password reset types other than <b>None</b>.</p> <p>The default template file is <code>forgot-password-change.html</code>.</p>  |

| Property                                  | Description  |
|---|--|
| <b>Password Reset Error Template</b>      | <p>The HTML template to notify the user that the password reset attempt has failed.</p> <p>This template applies for all password reset types other than <b>None</b>.</p> <p>The default template file is <code>forgot-password-error.html</code>.</p>   |
| <b>Password Reset Success Template</b>    | <p>The HTML template to notify the user that the password reset attempt has succeeded.</p> <p>This template applies for all password reset types other than <b>None</b>.</p> <p>The default template file is <code>forgot-password-success.html</code>.</p>  |
| <b>Account Unlock Template</b>            | <p>The HTML template to notify the user that the account unlock attempt has succeeded and to prompt the user to retain the current password or reset it.</p> <p>The default template file is <code>account-unlock.html</code>.</p>   |
| <b>Account Unlock Email Template</b>      | <p>The HTML template to send the user an email that the account unlock attempt has succeeded.</p> <p>The default template file is <code>message-template-account-unlock-complete.html</code>.</p>  |
| <b>OTP Length</b>                         | <p>The number of characters in the one-time password for password reset.</p> <p>The default value is 8.</p>  |
| <b>Allowed OTP Character Set</b>          | <p>The alphanumeric characters that PingFederate can include in an OTP.</p> <p>The default value is<br/>23456789BCDFGHJKLMNPQRSTUVWXYZbcdfghjkmnpqrstvwxyz.</p> <div data-bbox="522 1157 1472 1346" style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You must enter a minimum of 10 characters.</p> <p>Provide unique characters to ensure a secure OTP.</p> </div>  |
| <b>Password Reset Token Validity Time</b> | <p>The validity in minutes for the OTP or the one-time link.</p> <p>The default value is 10 minutes.</p>   |
| <b>PingID Properties</b>                  | <p>To configure self-service password reset using , you must obtain the <code>pingid.properties</code> file and upload it to the HTML Form Adapter instance.</p> <ol style="list-style-type: none"> <li>1. Sign on to the admin portal.</li> <li>2. Go to <b>Setup # PingID # Client Integration</b>.</li> <li>3. Download the settings file <code>pingid.properties</code>.</li> <li>4. Close the admin portal.</li> <li>5. On the <b>Manage IdP Adapters</b> tab in the administrative console, click <b>Choose File</b>.</li> <li>6. Select the <code>pingid.properties</code> file and click <b>Open</b>.</li> </ol> |

 **Note:**

When configuring an adapter to use a custom template name, make sure the `pingfederate/server/default/conf/language-packs/pingfederate-email-messages.properties` file and any language specific version, such as `pingfederate-email-messages_fr.properties`, includes that name so that the email subject found in the properties file is used.

For example, to customize an adapter to use a new password reset complete email template using `my-template-forgot-password-complete.html`, add the new property with the email's subject text. The new entry should be `my-template-forgot-password-complete.html=Password Reset`.

Find the configurable text that applies to a specific template in the `pingfederate-email-messages.properties` file, and make sure the same key-value pairs are specified for their new template name.

#### Advanced fields for self-service username recovery

| Property                                | Description   |
|---|---|
| <b>Require Verified Email</b>           | <p>When selected, PingFederate requires that the user's email address is verified before sending a password reset, account unlock, or username recovery email.</p> <p>If users are permitted to manage their accounts, they will be blocked from accessing any connected application until they have verified their email.</p> <p>For more information about enabling user account management, see <a href="#">Configuring local identity profiles</a> on page 359.</p> <p>By default, the check box is not selected.</p> |
| <b>Username Recovery Template</b>       | <p>The HTML template to prompt the user to enter an email address to recover the username associated with the account.</p> <p>This template applies when username recovery is enabled.</p> <p>The default template file is <code>username.recovery.template.html</code>.</p>  |
| <b>Username Recovery Info Template</b>  | <p>The HTML template to notify the user to retrieve the email message with the recovered username.</p> <p>This template applies when username recovery is enabled.</p> <p>The default template file is <code>username.recovery.info.template.html</code>.</p>   |
| <b>Username Recovery Email Template</b> | <p>The HTML email template PingFederate uses to generate the email message containing the recovered username.</p> <p>The default template file is <code>message-template-username-recovery.html</code>, located in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/template/mail-notifications</code> directory.</p> <p>Applicable only if an instance of the SMTP Notification Publisher is selected in the <b>Notification Publisher</b> list.</p>  |

#### CAPTCHA options

| Property                          | Description  |
|-----------------------------------|--|
| <b>CAPTCHA for Authentication</b> | Enable CAPTCHA to protect the authentication process from automated attacks. |

| Property                             | Description  |
|--------------------------------------|--|
| <b>CAPTCHA for Password Change</b>   | Enable CAPTCHA to protect the password change process from automated attacks.  |
| <b>CAPTCHA for Password Reset</b>    | Enable CAPTCHA to protect the account recovery process for password reset and account unlock from automated attacks. |
| <b>CAPTCHA for Username Recovery</b> | Enable CAPTCHA to protect the username recovery process from automated attacks.                                      |

By default, CAPTCHA check boxes are cleared.

Other settings

| Property                                      | Description   |
|---|---|
| <b>Fail Authentication on Account Lockout</b> | <p>This setting determines the adapter's behavior when PingFederate locks a user's account due to too many failed login attempts.</p> <ul style="list-style-type: none"> <li>When selected, the adapter returns an error and policy processing continues on the FAIL branch.</li> <li>When cleared, the adapter displays the login page with an error message stating the account is locked.</li> </ul> <p>The check box is cleared by default.</p> |

Variables available to HTML Form Adapter templates

The following variables are available to the HTML Form Adapter templates for core templates as well as password reset, change password, and username recovery use cases:

- `$adapterId` - The IdP adapter ID used in this transaction
- `$baseUrl` - The base URL of the PingFederate instance
- `$client_id` - The ID of the OAuth client used in this transaction
- `$connectionName` - The name of the SP connection used in this SSO transaction
- `$entityId` - The entity ID (connection ID) of the SP connection used in this SSO transaction
- `$spAdapterId` - The SP adapter ID used in this transaction



**Note:**

Variables are populated when applicable.

The core templates are:

- `html.form.login.template.html`
- `html.form.message.template.html`
- `html.form.password.expiring.notification.template.html`
- `html.form.login.challenge.template.html`

## HTTP Basic Adapter

The HTTP Basic adapter provides user authentication through a password credential validator (PCV) to integrate PingFederate with local authentication mechanisms.

Initial user authentication is normally handled outside of the PingFederate server using an application or an Identity Management system authentication module. Adapters or agents from PingFederate integration kits are typically used to integrate with these local authentication mechanisms.

PingFederate packages an HTTP Basic Adapter that delegates user authentication to a Password Credential Validator, such as an LDAP Username PCV (see [Password Credential Validators](#) on page 980). This authentication mechanism validates credentials against a user repository through an instance of a PCV. You can add multiple PCV instances to an instance of the HTTP Basic Adapter to validate against multiple user repositories, in which case PingFederate falls to the subsequent PCV instance if the previous PCV instance fails to validate the user credentials.

When PingFederate receives an authentication request and the use case is associated with an HTTP Basic Adapter instance, PingFederate invokes the adapter if it does not find a valid authentication session (see [Sessions](#) on page 292). If the HTTP Basic Adapter does not find a valid adapter session, it prompts the user for credentials.

This adapter does not provide an authentication context. For SAML connections, sets the authentication context as follows:

- `urn:oasis:names:tc:SAML:1.0:am:unspecified` for SAML 1.x
- `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified` for SAML 2.0

can override the authentication context with either an instance of the Requested AuthN Context Authentication Selector or the `SAML_AUTHN_CTX` attribute in the SAML attribute contract. The latter takes precedence.

### Configuring an HTTP Basic Adapter instance

Configure an HTTP Basic Adapter instance to use credentials against a user repository through an instance of a password credential validator (PCV) to support user authentication when it occurs outside of the PingFederate server.

About this task

Using the administrative console, configure an HTTP Basic Adapter instance.

Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. On the **IdP Adapter** tab, configure your HTTP Basic Adapter instance as follows:
  - a. If you have not yet defined the desired Password Credential Validator instance, click **Manage Password Credential Validators** to do so.
  - b. Click **Add a new row to 'Credential Validators'** to select a credential-authentication mechanism instance for this adapter instance.
  - c. From the **Password Credential Validator Instance** list, select a Password Credential Validator instance. Click **Update**.

Add as many validators as necessary. Use the up and down arrows to adjust the order in which you want to attempt credential authentication. If the first mechanism fails to validate the credentials, moves sequentially through the list until credential validation succeeds. If none of the Password Credential Validator instances can authenticate the user's credentials, and the challenge retries maximum has been reached, the process fails.


 **Note:**

If usernames overlap across multiple Password Credential Validator instances, this failover setup could lock out those accounts in their source locations.

- d. Enter values for the adapter configuration.

See the on-window field descriptions and the following table for more information.

**PingFederate's fields and descriptions for creating an HTTP Basic Adapter instance**

| Property                        | Description  |
|---------------------------------|--|
| Realm<br>(Required)             | The name of a protected area. The value of this field is sent as a part of the HTTP Basic authentication request. It appears in a dialog box that prompts the user for a username and password.  |
|                                 | <p> <b>Note:</b></p> <p>After a user authenticates against a realm, if additional HTTP Basic Adapter instances share the same realm, the user is not prompted to re-authenticate.</p> |
| Challenge Retries<br>(Required) | The number of attempts allowed for password authentication. The default value is 3.  |

5. On the **Extended Contract** window, configure additional attributes for this adapter instance as needed.

The HTTP Basic Adapter contract includes one core attribute: **username**.

6. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
9. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration. If you want to exit without saving the configuration, click **Cancel**.

## Identifier First Adapter

The Identifier First Adapter works best for use cases when a variety of user types are authenticating with PingFederate. The adapter analyzes the type of user and the credentials with which they have enrolled before, including datastore queries and user attributes, to provide support for user authentication.

When PingFederate receives an authentication request and the use case is associated with an Identifier First Adapter instance, PingFederate invokes the adapter if it does not find a valid [authentication session](#). The adapter prompts the user to enter their identifier and captures the identifier in the `subject` attribute.



### Note:

`subject` is one of the two core attributes in the adapter contract. `domain` is the other one.

If the identifier is an email address, the adapter extracts the email address suffix and exposes it downstream through the `domain` attribute. Additionally, the adapter can leverage datastore queries to fulfill the `domain` attribute, or other extended attributes, to support identifiers of other kinds.

Based on the identification result and the configured authentication policies, PingFederate routes the user to the desired policy path. As the user fulfills the authentication requirements, the adapter preserves the identifier on the client side in a persistent cookie.

When the user signs off and makes a subsequent sign-on request from the same browser, the adapter offers the user to either select the previously authenticated identifier found in the cookie or to enter a new one. If the user opts to enter a new identifier, the adapter adds that identifier to the cookie after the user completes the authentication requirements.

The adapter keeps adding the most-recently-authenticated identifier until the number of identifier reaches a configurable limit. When the threshold is reached, the adapter removes the least-recently-used identifier from the cookie.

Lastly, the Identifier First Adapter also allow users to continue without entering or selecting an identifier, in which case it treats the authentication attempt as a failure and returns control to PingFederate. PingFederate can then route the request based on the configured policy path.



### Tip:

PingFederate creates authentication sessions configured for an Identifier First Adapter instance only when the complete single sign-on (SSO) transaction has succeeded. This lets the adapter prompt the user for a different user identifier when a chained adapter authentication fails because, for example, there's a typo in the user identifier.



### Note:

The Identifier First Adapter is authentication API-capable. For more information, see [Authentication applications and the authentication API](#) on page 429.

## Configuring an Identifier First Adapter instance

Configure an instance of the Identifier First Adapter in PingFederate following these instructions and for additional configuration information on fieldnames, descriptions, and optimal settings depending on your use case.

About this task

Using the PingFederate administrative console, configure an Identifier First Adapter instance.



## Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. On the **IdP Adapter** tab, configure your Identifier First Adapter instance.

For more information about each field, see the following table.

#### PingFederate's fields and descriptions for creating an Identifier First Adapter instance

| Field  | Description   |
|--|---|
| Identifier Cookie Lifetime   | <p>Determines the number of days that previously authenticated identifiers are preserved as a cookie on the client side. This value can range from 0 through 3650.</p> <p>Set to 0 to disable the storage of any previously authenticated identifiers.</p> <p>The default value is 30.</p>  |
| Allow Cancelling Identifier Selection  | <p>Determines whether a user is allowed to continue without entering or selecting an identifier.</p> <p>If allowed, when a user decides to continue without providing an identifier, the Identifier First Adapter treats the authentication attempt as a failure and returns control to PingFederate.</p> <p>This check box is not selected by default.</p>   |
| <p>Click <b>Show Advanced Fields</b> to review the following settings. Modify as needed.</p> |   |
| Maximum Identifiers Count  | <p>Determines the maximum number of previously authenticated identifiers can be preserved in the identifier cookie. This value can range from 0 through 10.</p> <p>Set to 0 to disable the storage of any previously authenticated identifiers.</p> <p>The default value is 5.</p>  |
| Identifier Selection Template  | <p>The HTML template to prompt the user to enter or select an identifier. PingFederate allows each configured adapter instance to use a different template as needed.</p> <p>The default template file is <code>identifier.first.template.html</code>.</p> <p>Like other Velocity template files, it is located in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/template</code> directory.</p> |

5. On the **Extended Contract** tab, configure additional attributes for this adapter instance as needed. The Identifier First Adapter contract includes two core attributes: **subject** and **domain**.

If the identifier is an email address, the adapter extracts the email address suffix and exposes it downstream through the **domain** attribute. As needed, the adapter can leverage datastore queries to fulfill the **domain** attribute. For more information, see [step 7](#).

6. On the **Adapter Attributes** tab, do the following:
- Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.

7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
9. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration.
 

If you want to exit without saving the configuration, click **Cancel**.

### Identifier First Adapter and authentication policies

The Identifier First Adapter works best in conjunction with authentication policies and setting expected attribute values to enforce authentication requirements.

The Identifier First Adapter is designed to identify user populations. It supports email addresses natively: it extracts the email address suffix and exposes it downstream through the `domain` attribute. Additionally, the adapter can leverage datastore queries to fulfill the `domain` attribute or other extended attributes to support identifiers of other kinds.

The Identifier First Adapter is most effective when used in conjunction with authentication policies. The policy paths are created by having rules matching expected values of the `domain` attribute or other extended attribute. Each expected value forms its own policy path, to which a series of authentication sources can be appended to enforce the desired authentication requirements.

For more information and configuration steps, see the subsequent sample use case.

### Configuring a policy for multiple user populations

Configure an Identifier First Adapter instance to determine user populations based on user identifiers usernames and an authentication policy to route sign-on requests to authentication sources tailored for their respective user populations.

#### About this task

Using the administrative console, follow the instructions below for configuring an Identifier First Adapter instance, creating an authentication policy to prompt the user for their identifier first, determining their user population, and routing the request to the desired authentication recommendations. Consider the sample use case here.

You need to enforce different sets of authentication requirements for two sets of users, employees, and external consultants.

Employees are given `username@example.com` email addresses, such as `asmith@example.com`. User records are stored in a local directory server. Employees sign on through an HTML Form Adapter instance.

Consultants have either `username@example.org` or `username@example.info` email addresses. User records are stored in a local database. Consultants can sign on using their username or email address and password through a local web portal. This web portal is integrated with PingFederate using the OpenToken framework.

Your organization owns another local database that keeps track of username, domain information, and email address for both employees and consultants. The column names are `dsUId`, `dsDomain`, and `dsMail`, respectively. For simplicity, no users share the same `dsUId` value.

In this sample use case, you must make sure that the Identifier First Adapter instance can handle the scenario where users might enter their email address or just their username when setting up the Identifier First Adapter instance. Additionally, when accessing protected resources, your organization has agreed to send the user's email address in the security token.

You have already created the following components:

- An LDAP datastore connecting to the local directory server. The attribute name of the user identifier is `uid`.
- An instance of the LDAP Username Password Credential Validator (PCV) validating credentials against the local directory server with the LDAP datastore. The LDAP Username PCV instance is extended with an additional attribute `mail`. The search filter is configured to handle identifiers in the format of an email address or a username. See the following code example.

```
(|(uid=${username})(mail=${username}))
```

- An HTML Form Adapter instance delegating credential-validation to the LDAP Username PCV instance. The HTML Form Adapter instance is also extended with an additional attribute `mail`, which takes the `mail` attribute value from the LDAP Username PCV instance. The ID of this HTML Form Adapter instance is `htmlForm`.
- An OpenToken IdP Adapter instance digesting tokens from the web portal as the source of user attributes. The adapter contract is extended with an additional attribute `mail`. The web portal is designed to always include the user's email address in the token through the `mail` attribute. The ID of this OpenToken IdP Adapter instance is `opentokenIdp`.

This sample use case requires the following additional components:

- An expression-enabled PingFederate environment. See [step 1](#).
- An authentication policy contract to carry the email address from your organization to your partners. See [step 2](#).
- A Java Database Connectivity (JDBC) datastore connecting to the database that hosts username, email, and domain information. See [step 3](#).
- An Identifier First Adapter instance with an attribute source lookup configuration and a contract fulfillment via expressions for the `domain` adapter attribute. See [step 4](#).
- An authentication policy to route user requests to different authentication sources based on user populations. See [step 5](#).

To fulfill the requirements:

### Steps


1. Enable expressions in PingFederate.  
For configuration steps, see [Enabling and disabling expressions](#) on page 225.
2. Go to **Authentication # Policies # Policy Contracts**.
3. On the **Policy Contracts** window, click **Create New Contract** and create an authentication policy contract without any additional attributes.
4. Go to **System # Data & Credential Stores # Data Stores**.
5. From the **Data Stores** window, click **Add New Data Store**.
  - a. On the **Data Store Type** tab, enter **Name**.
  - b. From the **Type** list, select **Database (JDBC)** to create a JDBC datastore connection to the database that hosts username and domain information.

6. Create an instance of the Identifier First Adapter instance.
  - a. Follow steps 1 through 6 in [Configuring an Identifier First Adapter instance](#) on page 328.  
For the sample use case, suppose you name the adapter instance ID 1st.
  - b. Go to **Applications # Integration # Adapter-to-Adapter Mappings**.
  - c. On the **Adapter-to-Mappings** window, select a source instance and a target instance, and click **Add Mapping**.
  - d. On the **Attribute Sources & User Lookup** tab, click **Add Attribute Source**.

 **Note:**

For more information about configuring the following steps, see [Datastore query configuration](#) on page 398.

1. On the **Data Store** tab, enter an ID in **Attribute Source ID** and a name in **Attribute Source Description**, such as `domainInfo` and `Domain Info`, respectively. In the **Active Data Storelist**, select the JDBC datastore created previously. Click **Next**.
  2. On the **Database Table and Columns** tab, select the applicable options from the **Schema** and **Table** lists.
  3. Under **Columns to return from SELECT**, select the `dsDomain` column and click **Add Attribute**. Click **Next**.
  4. On the **Database Filter** tab, in the **Where** field, specify a filter to search by identifier that can handle identifiers in the format of an email address or a username.  
  
See the following example of a filter entry.  
  
`dsUId='${subject}' OR dsMail='${subject}'.`
  5. Click **Next**.
  6. On the **Summary** tab, click **Done**.
- e. On the **Adapter Contract Fulfillment** tab, configure as follows.

| Contract | Source     | Value   |
|----------|------------|---|
| domain   | Expression | <pre>#this.get("domain").toString().matches("(?i).+") ? #this.get("domain") : #this.get("ds.domainInfo.dsDomain")</pre> <div data-bbox="784 1386 1474 1528" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b><br/>Line breaks are inserted for readability only.</p> </div> |
| subject  | Adapter    | Not applicable. No selection is required.   |

The expression checks the `domain` attribute value returned by the Identifier First Adapter. If the value contains one or more character, PingFederate uses that as the value for the `domain`

attribute. Otherwise, it uses the `dsDomain` column value returned from the JDBC datastore. In other words, this expression handles identifiers in the format of an email address or a username.

This sample expression is intended to demonstrate the capability of the Identifier First Adapter. Depending on the actual use cases, expressions may vary. For more information about expressions, see [Construct OGNL expressions](#) on page 226.

- f. On the **Issuance Criteria** tab, click **Next**.

 **Note:**

Depending on the actual use cases, you can add issuance criteria.

- g. On the **Adapter-to-Adapter Summary** tab, review your configuration instance. Click **Done** to save your adapter instance configuration.
7. Create an authentication policy with rules to form policy paths based on results from `domain` attribute values returned by the Identifier First Adapter.
    - a. Go to **Authentication # Policies # Policies**.
    - b. From the **Policies** tab, click **Add Policy**.
    - c. On the **Policy** window, enter a **Name**, and optionally a **Description**, for the policy.
    - d. From the **Policy** list, select the Identifier First Adapter instance created in [step 5](#).
    - e. Click **Rules** to open the **Rules** dialog.
    - f. Add three rules as follows.

#### Defining Authentication Policy Rules dialog fields and entries

| Attribute Name | Condition | Value        | Result       |
|----------------|-----------|--------------|--------------|
| domain         | equal to  | example.com  | Example COM  |
| domain         | equal to  | example.org  | Example ORG  |
| domain         | equal to  | example.info | Example INFO |

 **Note:**

Add one rule for each expected `domain` attribute value.

- g. Clear the **Default to Success** check box to disable the option to specify a policy path for the scenario where the `domain` attribute value from the Identifier First Adapter instance does not match any configured value on the **Rules** dialog.

If you want to enable an authentication policy path for unexpected `domain` attribute values, leave the **Default to Success** check box as selected.

For more information about rules, see [Configuring rules in authentication policies](#) on page 259.

- h. Click **Done** to close the **Rules** dialog.

Result:

By adding three rules and disabling the default to success option, the Identifier First Adapter instance now contains four policy paths: Fail, Example COM, Example ORG, and Example INFO.

- i. Configure each policy path.

Fail

Select **Done**, which terminates the request in an error condition.

Example COM

Select the HTML Form Adapter instance, which contains two paths: Fail and Success.

Configure each policy path.

Fail

Select **Done**, which terminates the request in an error condition.

Success

Select the policy contract created in [step 2](#).

Click **Options** to open the **Incoming User ID** dialog.

1. From the **Sourcelist**, select **Adapter (ID 1st)**.
2. From the **Attribute** list, select **subject**.
3. Click **Done** to close the **Incoming User ID** dialog.

For more information, see [Specifying incoming user IDs](#) on page 258.

Example ORG (and then Example INFO)

Select the OpenToken IdP Adapter instance, which contains two paths: Fail and Success.

Configure each policy path by using the same steps documented for the **Example COM** policy path

- j. Configure contract fulfillment for each authentication policy contract as follows.

#### Contract Fulfillment fieldnames and entries

| Result from rules | Contract Attribute | Source                    | Value |
|-------------------|--------------------|---------------------------|-------|
| Example COM       | subject            | Adapter (htmlForm)        | mail  |
| Example ORG       | subject            | Adapter<br>(openTokenIdp) | mail  |
| Example INFO      | subject            | Adapter<br>(openTokenIdp) | mail  |

For more information, see [Configuring contract mapping](#) on page 265.

- k. Click **Done**. Click **Save**.

Result

You have now successfully configured an Identifier First Adapter instance and an authentication policy to prompt the user for their identifier first, determine their user population, and route the request to the desired authentication policy path.

## Kerberos Adapter

The integrated Kerberos Adapter provides a seamless single sign-on (SSO) experience for Windows clients by authenticating SSO requests using the Kerberos v5 protocol against Active Directory (AD) domains.

When the PingFederate Identity Provider (IdP) server receives an authentication request for Service Provider-initiated SSO or a user clicks a hyperlink for IdP-initiated SSO, PingFederate invokes the Kerberos Adapter and returns to the browser an HTTP 401 Unauthorized response. When PingFederate receives a Kerberos ticket from the browser, it validates the ticket against the domain defined in the Kerberos Adapter configuration. If validation succeeds, PingFederate retrieves the username, the domain, and the security identifiers (ObjectSID and SIDs) from the ticket; generates a SAML assertion with the username and optionally the associated domain, security identifiers, or both; and passes it to the SP.



**Note:**

The Kerberos Adapter supports authentications by Kerberos only.

### Authentication mechanism assurance

The integrated Kerberos Adapter supports authentication mechanism assurance from Active Directory domain service.

With an Identity Provider (IdP), you can use the Token Authorization framework to verify the `ObjectSID` and `SIDs` values before issuing a token. Alternatively, you can map the `SIDs` value to an attribute in the contract and let the Service Provider (SP) determine if the user meets the requirements to access the protected resource. For the purpose of protecting resources based on sign-on method, authentication mechanism assurance from Active Directory (AD) domain service adds an additional group membership to the user's security identifiers attribute `SIDs` when a user signs on using a certificate-based sign-on method, such as a smart-card sign-on. For example, you can restrict access to sensitive resources to users who sign on by using their smart cards, which requires a physical reader that you place in a physically secured location.

The integrated Kerberos Adapter supports authentication mechanism assurance by including the `ObjectSID` and `SIDs` attributes of the authenticated user in the adapter contract.

If your use case requires authentication mechanism assurance, you can add a criterion in the Token Authorization framework to verify that the `SIDs` attribute contains the security identifier (SID) value associated with the required login method. If the `SIDs` attribute does not contain the specified SID value, the request is denied.



#### Note:

The `SIDs` attribute contains multiple values. Use the **multi-value contains** condition or the **multi-value contains (case insensitive)** condition to verify whether the `SIDs` attribute contains a specific value. You can also configure more complex evaluations using OGNL expressions.

Alternatively, you can map the `ObjectSID` and `SIDs` attributes into the contract and let the SP determine if the user meets the requirements to access the protected resource.

For more information about authentication mechanism assurance, see the [Authentication Mechanism Assurance for AD DS in Windows Server 2008 R2 Step-by-Step Guide](#) from Microsoft's documentation.

### Configuring a Kerberos Adapter instance for SSO authentication

When integrating PingFederate with Windows client applications so that they can use single sign-on to authenticate, create and configure an instance of the Kerberos Adapter.


#### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.



4. On the **IdP Adapter** window, configure your Kerberos Adapter instance.  
See the on-window field descriptions and the following table for more information.

| Field   | Description  |
|---|--|
| <b>Domain/Realm Name</b><br>(Required)  | Select your Windows domain.<br><br>If the domain or realm you want does not appear, click <b>Manage Active Directory Domains/Kerberos Realms</b> to add it. For more information, see <a href="#">Active Directory and Kerberos</a> on page 992.   |
| <b>Error URL Redirect</b>   | Enter a URL for redirecting the user if there are errors. This URL has an <b>errorMessage</b> query parameter appended to it, which contains a brief description of the error that occurred. The error page can optionally display this message on the window to provide guidance on remedying the problem.<br><br><div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>In the case of an error, if you define an <b>Error URL Redirect</b> and the adapter instance is included in an instance of the Composite Adapter, the user is redirected to the configured error URL rather than continuing on to the next adapter in the chain. Leave this field blank to have the adapter continue on to the next adapter.</p> <p>When employing the <b>errorMessage</b> query parameter in a custom error page, adhere to Web-application security best practices to guard against common content injection vulnerabilities. If no URL is specified, the appropriate default error landing page appears.</p> </div> |
| Click <b>Show Advanced Fields</b> to review the following settings. Modify as needed. |  |
| <b>Error Template</b>   | When selected, displays a template to provide standardized information to the end user when authentication fails. The <b>Error URL Redirect</b> value is ignored.<br><br>The template <code>kerberos.error.template.html</code> in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/template</code> directory uses the Velocity template engine and can be modified in a text editor to suit your particular branding and informational needs. For example, you can give the user the option to try again if authentication fails. For more information on Velocity templates, see <a href="#">Customizable user-facing pages</a> on page 869 .   |
| <b>Fail when Re-authentication is Requested</b>                                       | When the check box is selected, if PingFederate receives an authentication request containing a re-authentication parameter, the adapter will respond with a failure status so that the policy's failure branch is followed.<br><br>For OAuth 2.0, the re-authentication parameter is <code>ForceAuthn=true</code> . For OpenID Connect, the re-authentication parameter is <code>prompt=login</code> .<br><br>By default, the check box is cleared.   |

| Field                               | Description   |
|-------------------------------------|---|
| <b>Authentication Context Value</b> | <p>This can be any value agreed to with your SP partner to indicate the type of credentials used to authenticate. Standard URIs are defined in the SAML specifications. For more information on SAML specifications, see the OASIS documents <a href="#">oasis-sstc-saml-core-1.1.pdf</a> and <a href="#">saml-authn-context-2.0-os.pdf</a>.</p> <p>If left blank, PingFederate sets the authentication context as follows:</p> <ul style="list-style-type: none"> <li>▪ <code>urn:oasis:names:tc:SAML:1.0:am:unspecified</code> for SAML 1.x</li> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified</code> for SAML 2.0</li> </ul> <p>Either an instance of the Requested AuthN Context Authentication Selector or the <b>SAML_AUTHN_CTX</b> attribute can override the authentication context in the SAML attribute contract. The latter takes precedence.</p> |

5. On the **Extended Contract** tab, configure additional attributes for this adapter instance as needed. The Kerberos Adapter contract includes four core attributes: **Domain/Realm Name**, **ObjectSID**, **SIDs**, and **Username**.
6. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that

you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
    - Configure one or more data sources for datastore queries.
    - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
    - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
  8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
  9. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration.
 

If you want to exit without saving the configuration, click **Cancel**.

### Configuring browsers for Kerberos authentication

You can configure browsers at your site to use the Kerberos Adapter to authenticate users.

The client-side configuration requires the base URL or an applicable virtual host name of your PingFederate environment. The base URL is defined on the **System # Server # Protocol Settings # Federation Info** tab. To see a list of defined virtual host names, if configured, go to **System # Server # Virtual Host Names**.

The following information explains how to configure the Microsoft Edge, Mozilla Firefox, and Google Chrome browsers.

 **Important:**

If the browser is not properly configured, the user might be prompted to authenticate manually with their network credentials. Otherwise, authentication fails the single sign-on (SSO) to the service providers.

### Configuring Microsoft Edge for Kerberos authentication


You can configure Microsoft Edge browsers for Kerberos authentication.

#### About this task

Because Edge doesn't honor intranet sites, the PingFederate Kerberos Adapter isn't allowed by default to request the Kerberos ticket for a user. To resolve this issue, there's a group policy object (GPO) that can send intranet site requests to Internet Explorer 11 instead of Edge. It lets you put PingFederate in the Intranet Sites Zone (not the Trusted Sites Zone) in Internet Explorer and enable Kerberos.


Steps

1. In the Group Policy Management editor, go to **User Configuration # Administrative Templates # Windows Components # Microsoft Edge** and enable the **Send All intranet sites to IE11** setting.




2. Go to **Administrative Templates # Windows Components # Internet Explorer # Internet Control Panel # Security Page # Site to Zone Assignment List**.
3. In the **Show Contents** dialog box's **Value Name** column enter the `<PingFederate URL>`.

4. In the **Value** column enter 1.



5. Go to **User Configuration # Administrative Templates # Windows Components # Internet Explorer # Internet Control Panel # SecurityPage # Intranet Zone**.

- In the **Logon Option** dialog box's **Logon options** list, select **Automatic logon with current username and password**.



### Configuring Mozilla Firefox for Kerberos authentication

You can configure Microsoft Firefox browsers for Kerberos authentication.

#### Steps

- Start Firefox.
- Open a new tab and enter `about:config` in the address bar.
- Double-click the `network.negotiate-auth.trusted-uris` preference name to modify its value to include the base URL of your PingFederate environment. For example, `www.example.com`.
- Click **OK** and close the `about:config` tab.

### Configuring Google Chrome for Kerberos authentication

Google Chrome browsers support Kerberos authentication.

#### About this task

If you configure Microsoft Edge for Kerberos authentication, then you don't need to configure Google Chrome because Chrome uses the settings in Edge. For more information, see the Microsoft Edge tab on this topic.

## OpenToken Adapter

To transfer identity and other user information between the PingFederate server and an end application, the PingFederate architecture allows for custom adapters to be deployed with the server.

PingFederate ships with a deployed OpenToken Adapter, which uses a secure token format `OpenToken` to transfer user attributes between an application and the PingFederate server.

On the identity provider (IdP) side, the OpenToken Adapter allows the PingFederate server to receive a user's identity from the IdP application.

For SAML connections, the IdP application can provide an authentication context to the service provider (SP) by including the `authnContext` attribute with the desired value in the secure token. Standard URIs are defined in the SAML specifications. For more information on assertions and protocol for SAML, see [oasis-sstc-saml-core-1.1.pdf](#) and [saml-authn-context-2.0-os.pdf](#) in the OASIS documentation.

If the secure token does not contain the `authnContext` attribute, PingFederate sets the authentication context as follows:

- `urn:oasis:names:tc:SAML:1.0:am:unspecified` for SAML 1.x
- `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified` for SAML 2.0

As needed, the authentication context can be overridden by either an instance of the Requested AuthN Context Authentication Selector or the `SAML_AUTHN_CTX` attribute in the SAML attribute contract. The latter takes precedence.


On the SP side, the OpenToken Adapter can be used to transfer user-identity information to the target SP application.

Specialized application integration kits are available from the Ping Identity Downloads website. Many kits leverage the OpenToken Adapter to integrate applications with the PingFederate server. The agent portions of the integration kits reside with the application and use the OpenToken to communicate with the OpenToken Adapter.

#### Note:

To integrate applications for use with the OpenToken Adapter, download an integration kit for PingFederate from the Ping Identity Downloads website and follow instructions for installing and using Agent Toolkits in the accompanying documentation. Follow the configuration instructions in [Configuring an OpenToken IdP Adapter instance](#) to setup and to use with your applications.

The following figure shows a basic IdP-initiated single sign-on (SSO) scenario using PingFederate with the Java Integration Kit on both sides of an identity federation.



### IdP-Initiated SSO: POST/POST

Processing steps

1. A user initiates an SSO transaction.

2. The IdP application inserts attributes into the Agent Toolkit for Java, which encrypts the data internally and generates an `OpenToken`.
3. A request containing the `OpenToken` is redirected to the PingFederate IdP server.
4. The server invokes the OpenToken IdP Adapter, which retrieves the `OpenToken`, decrypts, parses, and passes it to the PingFederate IdP server. The PingFederate IdP server then generates a SAML assertion.
5. The SAML assertion is sent to the SP site.
6. The PingFederate SP server parses the SAML assertion and passes the user attributes to the OpenToken SP Adapter. The Adapter encrypts the data internally and generates an `OpenToken`.
7. A request containing the `OpenToken` is redirected to the SP application.
8. The Agent Toolkit for Java decrypts and parses the `OpenToken` and makes the attributes available to the SP Application.

### Configuring an OpenToken IdP Adapter instance

Configure an instance of the OpenToken IdP Adapter in PingFederate.

#### About this task

Configure an OpenToken Identity Provider (IdP) Adapter instance using the administrative console to enable a secure authentication plugin for your custom application.

#### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.
 

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.
4. On the **IdP Adapter** tab, configure your OpenToken IdP Adapter instance.



#### Note:

These values depend on your developer's implementation.


For more information, see the **Description** field provided on-window and in the following table.

#### PingFederate's field names and descriptions for creating an OpenToken IdP Adapter instance

| Field                                | Description  |
|--------------------------------------|--|
| Password                             | The password to use for generating the encryption key. It is also known as the shared secret.  |
| Confirm Password<br>(Required)       |  |
| Authentication Service<br>(Required) | The URL to which the user is redirected for a single sign-on (SSO) event. This URL is part of an external application, which performs user authentication. |



| Field  | Description  |
|--|--|
| Click <b>Show Advanced Fields</b> in the <b>Instance Configuration</b> tab to review the following settings. Modify as needed. |  |
| Transport Mode   | How the token is transported to and from the application, either through a query parameter, a cookie (default), or as a form POST.   |
| Token Name<br>(Required)   | The name of the cookie or query parameter that contains the token. This name must be unique for each adapter instance. Override the default value <code>opentoken</code> as needed.                              |
| Cipher Suite   | The algorithm, cipher mode, and key size that should be used for encrypting the token. The default selected value is <b>AES-128/CBC</b> .  |
| Logout Service   | The URL to which the user is redirected for a single-logout event. This URL is part of an external application, which terminates the user session.   |
| Cookie Domain  | The server domain; for example, <code>example.com</code> . If no domain is specified, the value is obtained from the request.  |
| Cookie Path  | The path for the cookie that contains the token.   |
| Token Lifetime<br>(Required)   | The duration in seconds for which the token is valid. Valid range is 1 to 28800. The default value is 300 (5 minutes).   |
| Session Lifetime<br>(Required)   | The duration in seconds for which the token may be re-issued without authentication. Valid range is 1 to 259200. The default value is 43200 (12 hours).  |
| Not Before Tolerance<br>(Required)   | The amount of time in seconds to allow for clock skew between servers. Valid range is 0 to 3600. The default value is 0.   |
| Force SunJCE Provider  | If selected, the SunJCE provider is forced for encryption and decryption.  |
| Use Verbose Error Messages   | If selected, use verbose TokenException messages.  |
| Obfuscate Password   | If selected, the default, the password is obfuscated and password-strength validation is applied. Clearing the check box allows backward compatibility with previous OpenToken agents.                           |
| Session Cookie   | If selected, OpenToken is set as a session cookie, rather than a persistent cookie. Applies only if the <b>Transport Mode</b> field is set as <b>Cookie</b> . The check box is not selected by default.          |
| Secure Cookie  | If selected, the OpenToken cookie is set only if the request is on a secure channel (https). Applies only if the <b>Transport Mode</b> field is set to <b>Cookie</b> . The check box is not selected by default. |
| Delete Cookie  | If selected, the token cookie is deleted immediately after consumption. Applies only if the <b>Transport Mode</b> field is set to <b>Cookie</b> . The check box is not selected by default.                      |

| Field                              | Description   |
|------------------------------------|---|
| Replay Prevention                  | <p>Selecting this option is recommended only if <b>Query Parameter</b> is the chosen token transport mode and form POST is used by an associated connection to send the SAML assertion. If selected, PingFederate ensures that the token can be used only once. By default, the check box is not selected.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b><br/>Selecting this option might affect resource utilization and performance.</p> </div> |
| Skip Malformed Attribute Detection | <p>If not selected, the default, it prevents insecure content from affecting the security of your application and the agent. Update your applications with the latest version of the agent. We recommend not to change the value of this flag.</p>  |

- On the **Actions** tab, click **Download** under **Action Invocation Link**, and then click **Export** to save the properties file.

The values in the resulting file, `agent-config.txt`, represent the console configuration and are used by the Identity Provider (IdP) application. See the documentation of your respective integration kit for more information.

- On the **Extended Contract** tab, configure additional attributes for this adapter instance as needed.

The OpenToken IdP Adapter contract includes one core attribute: **subject**.

The OpenToken IdP Adapter always extends the core contract with an attribute `userId` as well and fulfills it with the value of **subject** for backward compatibility reason.

7. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
8. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
9. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.
10. When finished in the **IdP Adapters** window, click **Save** to confirm the adapter instance configuration. If you want to exit without saving the configuration, click **Cancel**.

## Configuring an OpenToken SP Adapter instance

Configure an instance of the deployed OpenToken Adapter, which uses a secure token format to transfer user attributes between an application and the PingFederate server.

### About this task

Configure an OpenToken Service Provider (SP) Adapter instance to enable a secure transfer of the user-identity information to the target SP application.

### Steps

1. Go to **Applications # Integration # SP Adapters** to access the **Manage SP Adapters Instances** window.
2. Click **Create New Instance** to start the **Create Adapter Instance** configuration wizard.
3. On the **Type** tab, configure the basics of this adapter instance.
  - a. Enter the **Instance Name**, **Instance ID**, and **Parent Instance** information and select the adapter type from the **Type** list.
  - b. Optional: Select a **Parent Instance** from the list.
 

This is useful when you are creating an instance that is similar to an existing instance. The child instance inherits the configuration of its parent. In addition, you have the option to override one or more settings during the rest of the setup. Select the **Override ...** check box and make the adjustments as needed in one or more subsequent windows.
4. On the **Instance Configuration** tab, configure your OpenToken SP Adapter instance security context.



#### Note:

These values are dependent on your developer's implementation.

For more information, see the **Description** field provided in-window and in the following table.

### PingFederate's field names and descriptions for creating an adapter instance

| Field  | Description   |
|--|---|
| Password   | The password to use for generating the encryption key. It is also known as the shared secret.   |
| Confirm Password<br>(Required)   |   |
| Click <b>Show Advanced Fields</b> in the <b>Instance Configuration</b> tab to review the following settings. Modify as needed. |   |
| Transport Mode   | How the token is transported to and from the application, either through a query parameter, a cookie, or as a form POST (default).  |
| Token Name   | The name of the cookie or query parameter that contains the token. This name must be unique for each adapter instance. Override the default value <code>opentoken</code> as needed. |
| Cipher Suite   | The algorithm, cipher mode, and key size that should be used for encrypting the token. The default selected value is <b>AES-128/CBC</b> .   |
| Authentication Service   | The URL to which the user is redirected for a single sign-on (SSO) event. This URL overrides the Target Resource, which is sent as a parameter to the Authentication Service.       |

| Field                                 | Description   |
|---------------------------------------|---|
| Account Link Service                  | The URL to which the user is redirected for account linking. This URL is part of an external SP application. This external application performs user authentication and returns the local user ID inside the token.   |
| Logout Service                        | The URL to which the user is redirected for a single-logout event. This URL is part of an external application, which terminates the user session.  |
| Cookie Domain                         | The server domain; for example, <code>example.com</code> . If no domain is specified, the value is obtained from the request.   |
| Cookie Path                           | The path for the cookie that contains the token.  |
| Token Lifetime<br>(Required)          | The duration in seconds for which the token is valid. Valid range is 1 to 28800. The default value is 300 (5 minutes).  |
| Session Lifetime<br>(Required)        | The duration in seconds for which the token may be re-issued without authentication. Valid range is 1 to 259200. The default value is 43200, 12 hours.  |
| Not Before Tolerance<br>(Required)    | The amount of time in seconds to allow for clock skew between servers. Valid range is 0 to 3600. The default value is 0.  |
| Force SunJCE Provider                 | If selected, the SunJCE provider is forced for encryption/decryption.   |
| Use Verbose Error Messages            | If selected, use verbose TokenException messages.   |
| Obfuscate Password                    | If selected, the default, the password is obfuscated and password-strength validation is applied. Clearing the check box allows backward compatibility with previous OpenToken agents.  |
| Session Cookie                        | If selected, OpenToken is set as a session cookie rather than a persistent cookie. Applies only if the <b>Transport Mode</b> field is set to <b>Cookie</b> . The check box is not selected by default.  |
| Secure Cookie                         | If selected, the OpenToken cookie is set only if the request is on a secure channel (https). Applies only if the <b>Transport Mode</b> field is set to <b>Cookie</b> . The check box is not selected by default.  |
| Send Subject as Query Parameter       | Selecting this check box sends the user identifier <code>subject</code> as a clear-text query parameter, if the <b>Transport Mode</b> field is set to <b>Query Parameter</b> . If <b>Form POST</b> is the chosen token transport mode, the user identifier is sent as POST data.  |
| Subject Query Parameter               | The parameter name used for the user identifier when the <b>Send Subject ID as Query Parameter</b> check box is selected.   |
| Send Extended Attributes              | Extended Attributes are typically sent only within the token, but this option overrides the normal behavior and allows the attributes to be included in browser cookies or query parameters.  |
| Skip Trimming of Trailing Backslashes | If not selected, the default, it prevents insecure content from affecting the security of your application and the agent. Update your applications with the latest version of the agent. We recommend not to change the value of this flag to avoid a negative security impact, such as someone maliciously adding slashes to exploit the system. |
| URL Encode Cookie Values              | If checked, the extended attribute cookie value will be URL encoded.  |

5. In the **Actions** tab, click **Download** under **Action** section. Click **Export** to save the properties file.

The values in the resulting file, `agent-config.txt`, represent the console configuration and are used by the SP application. See the documentation of your respective integration kit for more information.

6. Optional: In the **Extended Contract** tab, configure additional attributes for this adapter instance.
7. In the **Summary** tab, review your configuration, modify as needed. Click **Done**.
8. On the **SP Adapters** window, click **Save** to confirm the adapter instance configuration.

If you want to exit without saving the configuration, click **Cancel**.

## Configuring a Passthrough IdP Adapter

The Passthrough IdP Adapter allows a user key to be associated with a user's authentication sessions.

### About this task

By placing the Passthrough IdP Adapter downstream from an IdP connection in a policy tree, you can take advantage of additional capabilities associated with defining a user key. For example, you can use the user key to [query or revoke a user's authentication sessions](#). The adapter automatically sets the `username` attribute in its core contract to match the configured *incoming user ID*. With an upstream IdP connection, the incoming user ID can be mapped to the connection's `SAML_SUBJECT` attribute.

### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select **Passthrough IdP Adapter**.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.
4. On the **IdP Adapter** tab, there are no configurable fields, so skip to the **Extended Contract** tab.
5. On the **Extended Contract** tab, you can extend the contract by entering the name of the desired attribute and clicking **Add**. You can add multiple attributes.
6. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

#### **Note:**

If you choose a custom user key attribute, PingFederate uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute

that is based on the username, configure the adapter's password credential validators to trim spaces.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want PingFederate to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
7. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
    - Configure one or more data sources for datastore queries.
    - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
    - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
  8. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.

## Configuring a Reference ID Adapter



The Reference ID Adapter allows user attributes to be passed in and out of the PingFederate server through direct HTTP(S) calls. Attributes are retrieved using a Reference ID.

### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. On the **IdP Adapter** tab, configure the Reference ID Adapter instance as follows:
  - a. Enter values for the adapter configuration, as described in the following table.

| Field                   | Description   |
|-------------------------|---|
| Authentication Endpoint | The application endpoint URL where the end user is redirected for authentication.   |
| User Name               | The ID that the application uses to authenticate to the PingFederate server.  |
| Pass Phrase             | The pass phrase that the application uses to authenticate to the PingFederate server.   |
| Allowed Subject DN      | The subject DN from the client certificate. If entered, PingFederate restricts client-certificate authentication (when enabled) by matching against this DN.  |
|                         |  <b>Note:</b><br>This field supports the asterisk (*) wildcard character and multiple DNs, separated by the pipe ' '.  |
| Allowed Issuer DN       | The issuer DN from the client certificate. If entered, PingFederate restricts client-certificate authentication (when enabled) by matching against this DN.   |
|                         |  <b>Note:</b><br>Supports the asterisk (*) wildcard character and multiple DNs, separated by the pipe ' '.  |
| Logout Service Endpoint | The application endpoint URL used for single logout. The <b>Logout Service Endpoint</b> works in conjunction with <b>Logout Mode</b> .  |
| Logout Mode             | Select the option that determines how the application logout is handled.<br><br><b>Front Channel</b> - Redirects the user to the application endpoint and expects the application to redirect back to the provided PingFederate resume path.<br><br><b>Back Channel</b> - Sends a direct HTTP request from the server to the application.<br><br>The default setting is <b>None</b> . |

- b. Optional: Click **Show Advanced Fields** to review or modify default values.
5. On the **Actions** tab, you can optionally click **Show Pass Phrase** to display the pass phrase for the adapter.
6. On the **Extended Contract** tab, extend the contract as needed by entering the name of the desired attribute and clicking **Add**. You can add as many attributes as needed.



7. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

 **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

 **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

 **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

 **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.
8. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
9. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.

## Configuring an X.509 Certificate IdP Adapter

The X.509 Certificate IdP Adapter allows a PingFederate identity provider (IdP) server to perform client X.509 certificate authentication for single sign-on (SSO) to service provider (SP) applications.

### About this task

When PingFederate is acting as an IdP, this adapter validates X.509 certificates against the certificate authorities (CA) in the PingFederate certificate store. Use the **IdP Adapter** window to configure the X.509 Certificate IdP Adapter.

### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. On the **IdP Adapters** window, click **Create New Instance** to start the **Create Adapter Instance** configuration.
3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. Optional: On the **IdP Adapter** tab, in the **Constrain Acceptable Root Issuers** section, specify the certificate authorities (CA) that you want to use to validate end-user X.509 certificates.



#### Note:

Client certificates are always validated against all trusted CAs in PingFederate and the Java Virtual Machine. This section only restricts which issuers are used to validate end-user certificates.

- a. Click **Add a new row to 'Constrain Acceptable Root Issuers'**.
  - b. In the **Issuer DN** field, enter the subject distinguished name (DN) of an issuer listed on the **Trusted CAs** window. For more information, see [Manage trusted certificate authorities](#) on page 657.
  - c. In the **Action** column, click **Update**.
  - d. To add more acceptable issuers, repeat steps a-c.
5. Enter values for the adapter configuration, as described in the following table.

| Field                | Description  |
|----------------------|--|
| Client Auth Port     | The port that PingFederate uses to validate client certificates.                       |
| Client Auth Hostname | The PingFederate hostname that is configured to use client-certificate authentication. |

| Field                                       | Description  |
|---|--|
| Parse Client Cert Subject and Issuer DNs    | <p>When enabled, the subject and issuer distinguished names (DN) in the client certificate are treated as separate attributes. This allows you to do the following:</p> <ul style="list-style-type: none"> <li>▪ Add subject or issuer DN attributes, such as CN or UID, to the adapter's extended contract.</li> <li>▪ Use the subject DN <code>email</code> attribute in the adapter's core contract.</li> <li>▪ Use Object-Graph Navigation Language (OGNL) expressions to extract other information from the X.509 certificate.</li> </ul> <p>This option is enabled by default.</p> |
| Match Issuer DN in Client X.509 Certificate | <p>Determines how PingFederate validates the issuer distinguished name (DN) for the client certificate.</p> <p>When selected, the issuer DN is matched against the entries that are defined in the <b>Constrain Acceptable Root Issuers</b> section.</p> <p>When cleared, the issuer DN is matched against the default top level certificate in the chain that is presented by the client.</p>   |
| <b>Advanced Fields</b>                      |  |
| Return Success on SLO                       | <p>When enabled, a "success" message is sent in response when the adapter receives a single logout (SLO) request.</p> <p>SLO is not supported by this adapter and the user session is not terminated. This feature only prevents other sites from experiencing an SLO failure.</p> <p>This option is enabled by default.</p>   |
| Authentication Context                      | <p>The value used to populate the "Authentication Context" field in the SAML token that PingFederate sends after validating the X.509 certificate.</p> <p><b>Default</b> - Sets the value to "TLSClient".</p> <p><b>Policy OID</b> - Sets the value to the identifier for the policy.</p> <p><b>Custom</b> - Sets based on the value you enter in the <b>Custom Authentication Context</b> field.</p>  |
| Custom Authentication Context               | <p>The value used to populate the "Authentication Context" field in the SAML token. Applies when <b>Authentication Context</b> is set to <b>Custom</b>.</p>  |
| Include Subject Alternative Name (SAN)      | <p>When enabled, the adapter includes the following decoded SAN attributes from the X.509 certificate and makes them available in the attribute contract:</p> <ul style="list-style-type: none"> <li>▪ userPrincipalName</li> <li>▪ RFC822Name</li> <li>▪ fascn_sen</li> <li>▪ fascn_wo_sen</li> <li>▪ fascn_hex</li> <li>▪ deviceId</li> </ul>  |

6. On the **Extended Contract** tab, add any attributes, that you want to include in the extended contract. Enter attributes in uppercase. Only attributes specified in [RFC 2253](#) are allowed: CN, L, ST, O, OU, C, STREET, DC, and UID.

**Note:**

You can include subject DN components in this list.

If you selected **Parse Client Cert Subject and Issuer DNs** on the **IdP Adapter** tab, you can also include the subject DN `email` component, as well as issuer DN components.

For issuer DN components, prefix the attribute with `issuer_`, such as `issuer_CN`.

7. On the **Adapter Attributes** tab, do the following:
- Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

**Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

**Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

**Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

**Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.

8. Optional: On the **Adapter Contract Mapping** tab, configure the adapter contract for this instance with the following optional workflows:
  - Configure one or more data sources for datastore queries.
  - Fulfill adapter contract with values from the adapter, the default, datastore queries, if configured, context of the request, text, or expressions, if enabled.
  - Set up the Token Authorization framework to validate one or more criteria prior to the issuance of the adapter contract.
9. On the **Summary** tab, review your configuration and modify as needed. Click **Save**.

## Customer IAM configuration

---

PingFederate empowers administrators to deliver a secure and easy-to-use customer authentication, registration, and profile management solution. This solution leverages the HTML Form Adapter to offer users the options to authenticate through third-party identity providers (IdPs), self-register as part of the sign-on experience, and manage their accounts through a self-service profile management page.

Like other user-facing windows, administrators can customize and localize both the registration and profile management pages to present a consistent branding experience based on the needs of the users and the organizations.

Furthermore, administrators can allow users to leverage their existing identities from third-party identity providers. Any IdP connection or IdP adapter, such as the LinkedIn Cloud Identity Connector, can be used as an authentication source to a third-party identity provider. This optional capability enables a mapping configuration between the attributes returned by the identity provider and the fields within the registration page, streamlining the registration process.

Depending on the requirements and configuration of existing components, the configuration process might involve changes to these configuration components: authentication policy contracts, local identity profiles, HTML Form Adapter instances, and IdP authentication policies.



### Note:

The HTML Form Adapter is authentication API-capable. The authentication API is a JSON-based API that enables end-user interactions, such as credential prompts, to be handled by an external web application. This API does so by providing access to the current state of the flow as an end user steps through a authentication policy. For more information, see [Authentication applications and the authentication API](#) on page 429.

## Setting up PingDirectory for customer identities

PingFederate can optionally store customer identities in PingDirectory. After you have installed PingDirectory, update the LDAP schema with a new object class and a couple attributes to store customer identities and their connections.

About this task

Update the LDAP schema with a new object class and a couple attributes using an LDIF file provided. To optimize performance, apply updates in indexes to the directory as well. In addition, you must configure in PingFederate an LDAP datastore connection to your PingDirectory and an LDAP Username Password Credential Validator instance for the HTML Form Adapter to validate user credentials. If you have previously created these components, you can reuse them.



### Note:

Skip this configuration if your use case does not involve registration or profile management. For more information, see [Enabling third-party identity providers without registration](#) on page 387.

## Steps

1. Update the LDAP schema.
  - a. Sign on to the PingDirectory administrative console.
  - b. Go to the **LDAP Schema # Schema Utilities** screen.
  - c. Click **Import Schema Element**.
  - d. Copy the schema changes from the `<pf_install>/pingfederate/server/default/conf/local-identity/ldif-scripts/local-identity-pingdirectory.ldif` file and paste them into the text area.
 

If you are creating a new organizational unit as part of the LDIF import, edit the DN information.
  - e. Click **Import**.
2. Create an equality index for the `pf-connected-identity` attribute.

Use PingDirectory's `dsconfig` utility to create this index. The `dsconfig` utility is interactive. You can also provide inputs as command arguments. For example, the following samples create the `pf-connected-identity` index.

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name pf-connected-identity \
  --set index-type:equality
```

After adding the index, use the `rebuild-index` utility to build the indexes. For instance, the following sample builds the required index.

```
$ bin/rebuild-index \
  --baseDN "dc=example,dc=com" \
  --index pf-connected-identity
```

3. Create an LDAP datastore connection to your PingDirectory on **System # Data Stores**.
 

If you have already created an LDAP datastore connection to your PingDirectory, you can reuse it.
4. Create an instance of the LDAP Username Password Credential Validator on **System # Password Credential Validators** to validate user credentials stored in PingDirectory.
 

If you have already created an LDAP Username Password Credential Validator instance, you can reuse it.



### Note:

Later you will create a local identity profile as part of the customer IAM configuration. The **Search Base** value here should match the **Base DN** value defined in the local identity profile. For more information, see [Configuring LDAP base DN and attributes](#) on page 368.

## Managing local identity profiles

A local identity profile (LIP) is a stored user identity (PingDirectory) created and maintained by PingFederate. It provides the capability for user creation and administration, and centralizes those policies with the authentication and authorization policies already within PingFederate.

### About this task

Users can enter their information during registration using a link on the HTML Login page or after successful authentication from a third-party IdP. You can configure LIPs for user registration, third-party federation (provisioned through SAML), and user profile management.

A typical customer identity and access management (CIAM) use case only requires one LIP. As needed, you can create multiple profiles to suit the needs of your organization. Using the administrative console, LIPs are defined in the **Identity Policies** section.



### Note:

As of PingFederate 10.1, an authentication session is automatically created for a user after registration, preventing the user from having to log in again during the next single sign-on (SSO) transaction. This feature is enabled by default for all new and existing local identity profiles. However, if needed, you can disable it through the `/localIdentity/identityProfiles` administrative API endpoint by setting the `createAuthnSessionAfterRegistration` attribute to `false`.

When associated with an HTML Form Adapter instance, a local identity profile provides users the option to authenticate through third-party identity providers, self-register as part of the sign-on experience, and manage their accounts through a self-service profile management page.

### Steps

- To configure a new profile, go to **Authentication # Policies # Local Identity Profiles**. Click **Create New Profile**.
- To modify an existing profile, select it by its name under **Local Identity Profile Name**.
- To review the usage of an existing profile, click **Check Usage** under **Action**.
- To remove an existing instance or to cancel the removal request, click **Delete** or **Undelete** under **Action**.

### Next steps

See the following topics for detailed instructions that enable you to complete these configurations:

- [Setting up self-service registration](#) on page 371
- [Enabling third-party identity providers](#) on page 376
- [Enabling profile management](#) on page 383
- [Creating advanced registration mapping](#) on page 384
- [Enabling third-party identity providers without registration](#) on page 387

## Configuring local identity profiles

In the **Local Identity Profiles** window, configure a new local identity profile and provide profile information on the **Profile Info** tab.

### About this task

This section only provides instructions for configuring the fields in the Local Identity Profile (LIP) configuration tabs. For instructions on using the LIP configuration as part of a greater customer identity access management solution, see the following topics:

- [Setting up self-service registration](#) on page 371

- [Enabling third-party identity providers](#) on page 376
- [Enabling profile management](#) on page 383
- [Creating advanced registration mapping](#) on page 384
- [Enabling third-party identity providers without registration](#) on page 387

### Steps

1. To configure a new profile, go to **Authentication # Policies # Local Identity Profiles**. Click **Create New Profile**.
2. On the **Profile Info** tab, in the **Local Identity Profile Name** field, enter a name.
3. From the **Authentication Policy Contract** list, select a contract.  
If you have not yet defined the desired contract, click **Manage Policy Contracts**.
4. Select the **Enable Registration** check box if you want to enable users to complete a self-service registration as part of the sign-on experience through an instance of the HTML Form Adapter.
5. Select the **Enable Profile Management** check box if you want to allow users to manage their accounts.
6. When finished, click **Next**.

### Defining authentication sources

Authentication sources are identifiers for third-party identity providers, such as social providers used to display these providers on the HTML form adapter user interface as alternate authentication and registration options. They are also used in authentication policies to configure branches to identity provider (IdP) adapters and connections.

### About this task

Authentication sources are optional. They are the identifiers for third-party identity providers, such as social network providers. When defined, the associated HTML Form Adapter instance displays them on the sign-on page as alternative options for authentication and registration, if enabled. If profile management is enabled, users can connect or disconnect third-party identity providers to and from their accounts.

You can store attributes received from third-party identity providers as part of the user records. If required, attributes can be updated as users authenticate. By default, attributes are removed from user records as users disconnect third-party identity providers from their accounts. It is worth noting that storing attributes received from third-party identity providers is optional and configurable on a per-local identity profile basis. Additionally, this option is only applicable when a local identity profile is configured with registration, profile management, or both.

### Steps

1. On the **Authentication Sources** tab, type a source in the **Authentication Source** field, and click **Add**.



#### Tip:

If you use the authentication source names Facebook, Google, LinkedIn, Twitter, FIDO, the HTML Form Adapter default templates render the associated icons on the registration and profile management pages.



#### Note:

As of PingFederate 10.2, you can use `Security Key` as an authentication source. The Security Key authentication source automatically adds a Security Key button to the HTML Form Adapter and Local Identity Profile management and registration pages. It allows users to authenticate with a hardware



security key such as YubiKey. The button displays only if the user's device or browser supports the Web Authentication (WebAuthn) protocol.

You can also use the Security Key authentication source with the PingID adapter by configuring a policy tree with a rule that includes a `policy.action` attribute equal to a **Value** and **Result** of `Security Key`. Then select the PingID Adapter under **Security Key** in the policy and configure it as needed. For information about configuring authentication policies and rules, see [Defining authentication policies](#) on page 254 and [Configuring rules in authentication policies](#) on page 259.

Result:

Make a note of the values defined here. In a later step, you will create a rule for each authentication source in an identity provider (IdP) authentication policy. Each rule forms a policy path that initiates the authentication process.

2. If needed, modify or remove existing authentication sources.



**CAUTION:**

When removing an authentication source, keep in mind that accounts that were created using the associated third-party identity provider will no longer be usable after the removal. To minimize the risk of accidental removals, the administrative console prompts to confirm each removal request.

3. Configure storage settings for attributes received from third-party IdP.



**Note:**

The attribute storage settings are inapplicable and not shown if neither **Enable Registration** nor **Enable Profile Management** check box not selected on the **Profile Info** tab.

Choose from:

- If storing attributes, select the **Store Attributes** check box.
- If you want attributes retained after users disconnect third-party IdP from their accounts, select the **Keep Attributes After Users Disconnect** check box.
- If you want attributes updated as users authenticate, select the **Update Attributes When Users Authenticate** check box and enter a value in the **Minimum Number of Days Between Updates** field.

4. When finished, click **Next**.

### Configuring local identity fields

Configuring local identity fields determines which fields will be displayed as input controls on the user registration and profile management pages.

About this task

When registration is enabled for a local identity profile, select a local identity field to be the unique identifier for the purpose of identifying the users. To enable email ownership verification, add a field to store the email address and another field to store the verification status. While the former can be any field that uses the **Email** or **Text** input control, the latter must use the **Hidden** input control.

Steps

1. On the **Fields** tab, click **Create New Field**.
2. In the **ID** field, enter a unique identifier. The ID references the field throughout the user interface and is the field name in the HTML template.

3. In the **Label** field, type the field name that users see on the user registration and profile management pages.
4. From the **Type** list, select the type of input control for the field being configured.
5. Under **Applies To**, select one or both options to configure this field to appear on the user registration page, the profile management page, or both. Both options are selected by default.  
This step is applicable only if both **Enable Registration** and **Enable Profile Management** are enabled on the **Profile Info** tab.
6. Optional: Select the relevant parameters under **Parameters**.  
You can make a non-hidden field required or read-only. You can also configure PingFederate not to record values from this field in logs.
7. Optional: Enter a value under **Default Value**.  
Specifying a default value can streamline the registration process. This is the default value of the field unless another value is specified in the authentication policy. For more information, see [Configuring local identity mapping](#) on page 265.  
**Default Value** is not shown if you have chosen an input control of **Checkbox group**, **Email**, **Phone**, or **Hidden**, or the **Read-Only** parameter.
8. Add the applicable predefined values under **Options**.  
This step is applicable and required only if you have chosen **Checkbox Group** or **Dropdown** as the input control.
9. Click **Done**.  
Result:  
The administrative console returns to the **Fields** tab.
10. Select the **Unique ID** option for the applicable field. This is applicable and required only if registration is enabled on the **Profile Info** tab.

**Note:**

You cannot choose any field that uses the **Checkbox**, **Checkbox Group**, **Date**, or **Dropdown** input control as a unique identifier, because values from these fields will likely collide as the population of users grows.

11. Clear the check box beside **Strip Leading/Trailing Spaces From the Value of the Unique ID Field** only if you do not want to check for leading and trailing spaces in the unique ID field.
12. Select **Mask All OGNL-Expression Generated Log Values** if you want to mask local identity field values in logs when OGNL expressions might be used to map derived values into outbound single sign-on (SSO) tokens in authentication policies.
13. Click **Next**.

**Configuring email ownership verification options**

Based on your customer IAM use cases, you can optionally offer users the opportunity to confirm the ownership of the email address associated with their accounts. This configuration can be configured on a per-local identity profile basis.

## About this task

Using the administrative console, configure the email ownership verifications settings for a local identity profile.

If you enable email ownership verification, when a user submits a registration request, PingFederate sends an email ownership verification message to the email address. The message is valid for a configurable period. If the user cannot find the message, they can request another one by accessing the email ownership verification endpoint. Moreover, if you enable profile management, the profile management

page displays a reminder until the user verifies the email address. Like other local identity fields, the email verification status is stored in the directory and can be relayed to the applicable target applications through identity provider (IdP) authentication policies.

#### Steps

1. Go to **Authentication # Policies # Local Identity Profiles**.
2. On the **Email Verification** tab, select the **Enable Email Ownership Verification** check box to offer users the opportunity to verify the email address associated with their accounts.

The **Email Verification** tab appears only when you select the **Enable Registration** check box or the **Enable Profile Management** check box on the **Profile Info** tab.

The **Enable Email Ownership Verification** check box is not selected by default.



#### Note:

The rest of the steps apply only if you select to enable email ownership verification.

3. In the **Email Address Field** list, select a field.  
The field value represents the recipient of the verification message.  
Only fields that use the **Email** or **Text** input control are eligible and shown.
4. In the **Ownership Status Field** list, select a field.  
The field value represents the email ownership verification status. PingFederate sets the value to `false` in the directory when it receives a new or an updated email address from the user. After the user verifies the email ownership, PingFederate sets the value to `true`.  
Only fields that use the **Hidden** input control are eligible and shown.

5. To verify emails with one-time passcodes, which is the default option:
  - a. Set the **Email Verification Type** to **One-Time Passcode**.
  - b. Optional: Change any of the values in the following fields:
    - **One-Time Passcode Length**
    - **One-Time Passcode Retry Attempts**
    - **Allowed One-Time Passcode Character Set**
    - **One-Time Passcode Lifetime**

EMAIL VERIFICATION TYPE  One-Time Passcode  One-Time Link

|   |   |
|---|---|
| ONE-TIME PASSCODE LENGTH                | <input type="text" value="8"/>                            |
| ONE-TIME PASSCODE RETRY ATTEMPTS        | <input type="text" value="3"/>                            |
| ALLOWED ONE-TIME PASSCODE CHARACTER SET | <input type="text" value="23456789BCDFGHJKM"/>            |
| ONE-TIME PASSCODE LIFETIME              | <input type="text" value="15"/>                           |
| ONE-TIME PASSCODE TEMPLATE              | <input type="text" value="local.identity.email.verific"/> |
| EMAIL TEMPLATE                          | <input type="text" value="message-template-ema"/>         |
| SUCCESS TEMPLATE                        | <input type="text" value="local.identity.email.verific"/> |
| ERROR TEMPLATE                          | <input type="text" value="local.identity.email.verific"/> |
| NOTIFICATION PUBLISHER                  | <input type="text" value="Notification Publisher 1"/> ▾   |
| REQUIRE VERIFIED EMAIL                  | <input checked="" type="checkbox"/>                       |

6. To verify emails with one-time links:
  - a. Set the **Email Verification Type** to **One-Time Link**.
  - b. Optional: Change the length of the **One-Time Link Lifetime**.

|                                 |  |
|---------------------------------|--|
| EMAIL VERIFICATION TYPE         | <input type="radio"/> One-Time Passcode<br><input checked="" type="radio"/> One-Time Link  |
| ONE-TIME LINK LIFETIME          | <input type="text" value="1440"/>  |
| EMAIL TEMPLATE                  | <input type="text" value="message-template-ema"/>  |
| SENT TEMPLATE                   | <input type="text" value="local.identity.email.verific"/>  |
| SUCCESS TEMPLATE                | <input type="text" value="local.identity.email.verific"/>  |
| ERROR TEMPLATE                  | <input type="text" value="local.identity.email.verific"/>  |
| NOTIFICATION PUBLISHER          | <input style="border: none; background-color: #f0f0f0; padding: 2px 5px; display: inline-block; width: 100%;" type="text" value="Notification Publisher 1"/> |
| REQUIRE VERIFIED EMAIL          | <input checked="" type="checkbox"/>  |
| REQUIRE VERIFIED EMAIL TEMPLATE | <input type="text" value="local.identity.email.verific"/>  |

7. Optional: To use different template files, update the template fields.

The template files are in the `<pf_install>/pingfederate/server/default/conf/template` directory and the `<pf_install>/pingfederate/server/default/conf/template/mail-notifications` directory.



**Note:**

The email templates are only applicable when using an SMTP notification publisher to deliver email-verification messages.

8. Select a **Notification Publisher** instance.

If you haven't yet [configured the desired notification publisher instance](#), click **Manage Notification Publishers**, configure the instance, and then select it.

9. Optional: To require users to verify their email address ownership before they can access any connected applications:
  - a. Select the **Require Verified Email** check box.
  - b. Optional: If the **Email Verification Type** is set to **One-Time Link**, you can specify a different template in the **Require Verified Email Template** field.

The default template gives users options to **Resend** the verification email, **Continue**, or **Cancel**.

The **Require Verified Email Template** field appears only after you select the **Require Verified Email** check box.



**Note:**

If you select the **Require Verified Email** check box, users can sign on to their local identity profile and manage their account but PingFederate blocks them from accessing any connected applications until they have successfully verified their email address.

To let users manage their accounts, select the **Enable Profile Management** check box on the **Profile Info** tab, as described in [Configuring local identity profiles](#) on page 359.

10. Click **Next**.

### Configuring registration options

On the **Registration** tab, you can configure the user registration experience and specify the template file for the registration page.

#### Steps

1. Go to **Authentication # Policies # Local Identity Profiles # Registration**.
2. If you want to enable invisible reCAPTCHA from Google to prevent automated registration attempts, select the **CAPTCHA** check box, and then click **Manage CAPTCHA Settings**.
3. If you want to use a different template file, update the **Registration Template** field. The default value is `local.identity.registration.html`.
4. If you want to allow users to indicate whether their device is shared or private, select the **Enable 'This is my device'** check box.
5. If you want PingFederate to create an authentication session after a local account is registered, leave the **Create Session After Registration** check box selected. It is selected by default.
6. If you want to override the value in the **Unique ID** field as the username that is sent to adapters in the policy, select a username in the **Username Field** list.
7. If you have a policy fragment that needs to be executed as part of the workflow, select the fragment in the **Registration Workflow** list. Click **Add Policy Fragments**, if needed, to create one or more fragments.

When you select a fragment, you can then choose whether PingFederate should execute the registration workflow before or after account creation. **After Account Creation** is selected by default.



**Note:**

The registration fragment always executes after the user has entered their information in the registration form. There's an implicit mapping between fields in the local identity profile (LIP), which may have been populated in the registration form, and attributes in the registration fragment input

authentication policy contract (APC). Implicit mapping is a mapping that executes automatically if the name of a field in the LIP matches the name of an attribute in the APC.

There's also an implicit mapping between attributes in the registration fragment output APC and fields in the LIP. So, you can use the fragment to populate or overwrite the LIP fields. This works whether you configure the fragment to execute before or after account creation.

8. Click **Next**.

### Configuring profile management options

Configure the profile management experience and specify the template file for the profile management page.

About this task

Using the administrative console, configure the user registration in the local identity profiles section.

Steps

Go to **Authentication # Policies # Local Identity Profiles**. In the **Local Identity Profile** window, using the tabs, configure the user registration page settings.

Choose from:

- If you want to give users the option to delete their local accounts without administrator assistance, select the **Enable Profile Deletion** check box.

This check box is not selected by default.

If enabled, when users choose to delete their accounts, their user records are removed from your directory.

- If you want to use a different template file, update the **Registration Template** field.

The default value is `local.identity.profile.html`.

### Managing datastore configuration

PingFederate requires datastore configuration because it stores customer identities in PingDirectory.

Configure the datastore where local identities are stored.

- To begin, click **Configure Data Store**.

### Selecting a datastore for customer identities

PingFederate stores customer identities in PingDirectory, improving the flexibility, scale, and security of your user data. Follow these steps to connect PingFederate to a directory to store identity and profile data and expose the data to all applications and channels through LDAPv3.

About this task

Using the **Data Store Configuration** tab, connect your LDAP datastore to PingFederate.

Steps

1. Go to **Authentication # Policies # Local Identity Profiles**.
2. On the **Data Store Configuration** tab, click **Configure Data Store**.  
Result: This will open a **Data Store** window.
3. On the **Data Store Type** tab, enter a name in the **Name** field, and from the **Type** list, select **Directory (LDAP)**.
4. Click **Next**.

If you have not yet created an LDAP datastore to connect PingFederate to your PingDirectory or if you want to review your LDAP datastore settings, click **Manage Data Store**.

## Configuring LDAP base DN and attributes

Configure the datastore to search for a user's authentication starting with the base distinguished name (DN) and attributes within the LDAP directory.

About this task

On the **LDAP Configuration** tab, specify the branch of your directory hierarchy where you want PingFederate to store customer identities. Then, select the object class and the attributes to be associated with local identity fields.



### Note:

Later you will associate the local identity profile with an HTML Form Adapter instance and apply the profile in an identity provider (IdP) authentication policy as part of the customer IAM configuration. If your use case requires registration or profile management, the policy engine must look up the users as they access the registration page or the profile management page. The scope of this search begins at the base DN defined here.

For this reason, the base DN here should match the value of the **Search Base** field defined in the LDAP Username Password Credential Validator instance used by the associated HTML Form Adapter instance.

For more information about each field, refer to the following table.

| Field             | Description  |
|-------------------|--|
| Base DN           | The base distinguished name of the tree structure where PingFederate stores customer identities. |
| Root Object Class | The object class containing the desired attributes.  |
| Attributes        | A list of attributes based on the selected <b>Root Object Class</b> value.                       |

Steps

1. Go to **Authentication # Policies # Local Identity Profiles**.
2. On the **Data Store Configuration** tab, click **Configure Data Store**.  
Result: This will open a **Data Store** window.
3. On the **LDAP Configuration** tab, enter the applicable fields.
4. In the **User DN** field, specify a base DN.



### Tip:

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

5. Optional: Click **View Local Identity Fields** to determine which attributes from the directory server should be added to the local identity profile.
6. From the **LDAP Configuration** tab, click **Advanced**.  
Result: This will open the **LDAP Binary Attributes** tab.
7. On the **LDAP Binary Attributes** tab, add attributes.
  - a. Enter a name in the **Binary Attribute Name**.
  - b. Click **Add**.
  - c. Select a root object class, select an applicable attribute, and then click **Add Attribute**.

Repeat this step to add more attributes as needed.



8. Click **Done**. Click **Save**.

### Configuring LDAP relative DN and object class

When a user submits a registration request, PingFederate formulates the distinguished name (DN) of the user by prefixing the relative distinguished name (RDN) to the base DN defined in the LDAP configuration and then asks PingDirectory to create a new account based on the selected object class.

#### Steps

1. Optional: Click **View List of Available LDAP Attributes** to determine which LDAP attributes can be used to construct the RDN pattern.
2. In the **Relative DN Pattern** field, enter a valid pattern.

The pattern is as follows.

```
attribute1=value1[, ..., attributeN=valueN]
```

If you want to use the `${entryUUID}` variable to guarantee the uniqueness of the relative DNs for all users, you must use it with the `entryUUID` LDAP attribute, such as in the following example.

```
entryUUID=${entryUUID}
```

3. From the **Object Class** list, select the primary objectClass value used when creating a new local identity profile; for example, `inetOrgPerson`.
4. Optional: From the **Auxiliary Object Class Name** list, select an objectClass that contains additional required attributes that are not available in the primary objectClass, and click **Add**. You can add multiple object classes as needed.

For example, if you require the `placeOfBirth` attribute for a user's profile, you can add the `naturalPerson` root object class to the **Auxiliary Object Class Name** list. Doing this requires that you have done the following:

- a. Added `placeOfBirth` as a field on the **Fields** tab when configuring the local identity profile.
- b. Added the `naturalPerson` root object class and `placeOfBirth` attribute on the **LDAP Configuration** tab when configuring the datastore.

5. Click **Next**.

### Defining datastore mapping configuration

Configure the mapping between the local identity profile fields and the datastore attributes.

#### About this task

#### Steps

In the **Data Store Configuration**, on the **Data Store Mapping** tab, select an LDAP attribute under **Data Store Attribute** for each local identity field.

## Reviewing datastore configuration

On the **Summary** tab, you can review your data store configuration settings and then save them.

### Steps

1. In the **Data Store Configuration** window, on the **Summary** tab, review your changes. Choose from:
  - To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
  - To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.
2. Click **Done**.

## Reviewing a local identity profile

Review or make changes to your local identity profile configuration.

### About this task

Using the administrative console, on the **Summary** tab, amend, save, or discard your local identity profile changes.

### Steps

1. In the **Data Store Configuration** window, on the **Summary** tab, review your changes.
  - a. To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
  - b. To keep your changes, click **Done** and continue with the rest of the configuration.
  - c. To discard your changes, click **Cancel**.
2. When finished, click **Done**.

## Configuring the HTML Form Adapter for customer identities

After defining a local identity profile, associate it with an instance of the HTML Form Adapter for PingFederate to leverage the HTML Form Adapter to present users the options to authenticate through third-party identity providers, self-register as part of the sign-on experience, and manage their accounts through a self-service profile management page.

### About this task

Using the administrative console, on the **IdP Adapter** tab, create or add an HTML Form Adapter instance.



#### Note:

For registration and profile management, ensure the HTML Form Adapter instance is configured to validate credentials stored in PingDirectory. This validation configuration is not required if your use case does not involve registration or profile management. For more information, see [Enabling third-party identity providers without registration](#) on page 387.

## Steps

1. Go to the **Authentication # Integration # IdP Adapters**.
2. To create a new HTML Form Adapter instance, click **Create New Instance** or to reuse an existing instance, click on its name.
3. On the **IdP Adapter** tab, from the **Password Credential Validator Instance** list, select the LDAP Username Password Credential Validator instance that has been set up to validate credentials stored on your PingDirectory.



### Note:

Skip this step if your use case does not involve registration or profile management.

4. On the **IdP Adapter** tab, from the **Local Identity Profile** list, select a local identity profile.
5. Click **Next** and complete the rest of the configuration tabs.
6. On the **Summary** tab, click **Done**. This will open the **Manager IdP Adapter Instances** window.
7. In the **Manager IdP Adapter Instances** window, click **Save** to save all changes.

## Setting up self-service registration

PingFederate leverages the HTML Form Adapter to deliver a secure and easy-to-use customer authentication, registration, and profile management solution.

### About this task

A typical self-service registration setup involves five components:

- A PingDirectory installation ([step 1](#))
- An authentication policy contract ([step 2](#))
- A local identity profile ([step 3](#))
- An HTML Form Adapter instance ([step 4](#))
- An IdP authentication policy ([step 5](#))

To illustrate the configuration steps, consider the following example.

You need to support a consumer registration use case, where users complete a self-service registration process to create their accounts and then access resources protected by multiple service providers. For a registration to complete successfully, a user must provide an email address, a first name, a last name, an optional mobile phone number, and a password. The email address is the user identifier. All attributes are sent to the service providers as per the partner agreements. You have already created a specific object class in the directory to store the user information. The object class name is **aPerson**, and the LDAP attributes are **mail**, **givenName**, **sn**, and **mobile**.

## Steps

1. Install PingDirectory.
2. Create an authentication policy contract.
  - a. Go to **Authentication # Policies # Policy Contracts**.
  - b. In the **Policy Contracts** window, click **Create New Contract**.
  - c. On the **Contract Attributes** tab, in the **Extend the Contract** field, extend the authentication policy contract with three additional attributes, such as, **firstName**, **lastName**, and **mobileNumber**.
  - d. After each entry add, click **Add**. Click **Next**.
  - e. On the **Summary** tab, review your changes. Click **Save**.


For more information, see [Managing policy contracts](#) on page 286.

3. Create a local identity profile using the **Authentication # Policies # Local Identity Profiles** configuration wizard.
  - a. In the **Local Identity Profiles** window, click **Create New Profile**.
  - b. On the **Profile Info** tab, enter a name in the **Local Identity Profile Name** field.
  - c. From the **Authentication Policy Contract** list, select the authentication policy (from [step 2](#)), and select the **Enable Registration** check box. Click **Next**.
  - d. On the **Authentication Sources** tab, click **Next**.
  - e. On the **Fields** tab, click **Create New Field**.
  - f. In the **Field Configuration** window, on the **Field Configuration** tab, define four local identity fields. Enter the information described in the following table.

#### Local Identity Profile fields and entries

| Type  | ID           | Label         | Parameters                            |
|-------|--------------|---------------|---------------------------------------|
| Email | lipEmail     | Email address | Select the <b>Required</b> check box. |
| Text  | lipFirstName | First name    | Select the <b>Required</b> check box. |
| Text  | lipLastName  | Last name     | Select the <b>Required</b> check box. |

| Type  | ID        | Label         | Parameters                  |
|-------|-----------|---------------|-----------------------------|
| Phone | lipMobile | Mobile number | No parameters are required. |



- g. After each field entry, click **Next**. On the **Summary** tab, review your changes. Click **Done**.
- h. Repeat steps e through g until the fields are entered.

As needed, select the **Mask Log Values** check box for any of the four local identity fields and the **Mask all OGNL-expression generated log values** check box. The latter applies to all local identity fields.

- i. In the **Local Identity Profile** window, on the **Fields** tab, identify an ID field to be the unique ID for your configuration, and click the corresponding **Unique ID**. Click **Next**.
- j. On the **Email Verification** tab, click **Next**.
- k. On the **Registration** tab, click **Next**.
- l. On the **Data Store Configuration** tab, click **Configure Data Store**.
- m. In the **Data Store Configuration** window, on the **Data Store** tab, from the **Data Store** list, select the LDAP datastore that has been set up to connect to your PingDirectory. Click **Next**.
- n. In the **Data Store Configuration** window, on the **LDAP Configuration** tab, specify the branch of your directory hierarchy where you want to store customer identities in the **Base DN** field and the LDAP attributes to be associated with fields defined in this local identity profile under **Attribute**.
- o. In the **Data Store Configuration** window, on the **Identity Creation** tab, define the RDN pattern in the **Relative DN Pattern** field, and select your object, such as class **aPerson** for this sample use case, from the **Object Class** list.

The pattern is as follows.

```
attribute1=value1[, ..., attributeN=valueN]
```

If you want to use the `${entryUUID}` variable to guarantee the uniqueness of the relative DN's for all users, you must use it with the `entryUUID` LDAP attribute.

```
entryUUID=${entryUUID}
```

- p. In the **Data Store Configuration** window, on the **Data Store Mapping** tab, configure the mapping between the local identity profile fields and the datastore attributes. See the following table.

**Mapping entries for local identity profile fields and datastore attributes**

| Field    | Data Store Attribute |
|----------|----------------------|
| lipEmail | mail                 |

| Field        | Data Store Attribute |
|--------------|----------------------|
| lipFirstName | givenName            |
| lipLastName  | sn                   |
| lipMobile    | mobile               |

- q. In the **Data Store Configuration** window, on the **Summary** tab, click **Done**.
- r. On the **Summary** tab of the local identity profile, click **Save**.

For more information, see [Configuring local identity profiles](#) on page 359.

4. Configure an HTML Form Adapter instance for customer identities.
  - a. Go to the **Authentication # Integration # IdP Adapters**.
  - b. Create a new HTML Form Adapter instance or reuse an existing one by clicking its name.
  - c. On the **IdP Adapter** tab, in the **Password Credential Validator Instance** section add the LDAP Username Password Credential Validator instance that has been set up to validate credentials stored on your PingDirectory.
  - d. On the **IdP Adapter** tab, select the newly created local identity profile in the **Local Identity Profile** list.
  - e. Complete the rest of the configuration and save all changes.

(For more information, see .)
5. Create an IdP authentication policy.
  - a. Go to **Authentication # Policies # Policies**.
  - b. Click **Add Policy**.
  - c. In the **Policy** window, in the **Name** field, enter a name.
  - d. Select the HTML Form Adapter instance (configured in [step 4](#)) under **Policy**.
    1. For its **Fail** path, select **Done**.
    2. For its **Success** path, select the local identity profile (created in [step 3](#)).
  - e. Click **Local Identity Mapping** underneath the selected local identity profile, which opens the **Inbound Mapping & Contract Fulfillment** configuration wizard.
  - f. On the **Inbound Mapping & Contract Fulfillment Inbound Mapping** window, configure the `pf.local.identity.unique.id` built-in local identity field for the registration process.
 

At runtime, fulfills the value of the `pf.local.identity.unique.id` built-in local identity field based on this configuration and passes the value to PingDirectory. PingDirectory uses this value to determine whether such identity has already been created. The `pf.local.identity.unique.id` field value should therefore be mapped from the subject

identifier of the preceding authentication source, namely the **username** attribute from the HTML Form Adapter.


For this sample use case, configure the **Inbound Mapping** window as shown in the following table.

| Inbound Mapping Fulfillment | Source  | Value    |
|-----------------------------|---------|----------|
| pf.local.identity.unique.id | Adapter | username |

- g. On the **Attribute Sources & User Lookup** tab, click **Next**.
- h. On the **Contract Fulfillment** tab, fulfill the authentication policy contract with values from this local identity profile as follows:

| Outbound Contract Fulfillment | Source         | Value        |
|-------------------------------|----------------|--------------|
| subject                       | Local Identity | lipEmail     |
| firstName                     | Local Identity | lipFirstName |
| lastName                      | Local Identity | lipLastName  |
| mobileNumber                  | Local Identity | lipMobile    |

- i. On the **Issuance Criteria** tab, click **Next**.
- j. On the **Summary** tab, click **Done**.
- k. On the **Policy** window, click **Done**.
- l. On the **Policies** window, select the **IdP Authentication Policies** check box.

 **Note:**

Other IdP authentication policies, if any, are enabled as well.


- m. Click **Save** to keep your changes.

For more information, see [Applying policy contracts or identity profiles to authentication policies](#) on page 263.

6. Map the authentication policy contract to the applicable Browser SSO connections, OAuth grant-mapping configuration, or both. See [Managing authentication source mappings](#) on page 459 and [Managing authentication policy contract grant mapping](#) on page 593.

## Result

You have now successfully set up self-service registration. When users sign on through this HTML Form Adapter instance, they have the option to complete a self-service registration process to create their accounts using the **Register now** link, as illustrated in the following screen capture.



If a user chooses to register, the HTML Form Adapter redirects the user to the registration page. Based on the configuration of this sample use case, as illustrated in the following registration screen capture.

### Enabling third-party identity providers

For registration, you can optionally allow users to leverage their existing identities from third-party identity providers. Any identity provider (IdP) connection or IdP adapter, such as the LinkedIn IdP Adapter in the LinkedIn Login Integration Kit, can be used as an authentication source to a third-party identity provider.

#### About this task

Using the Administrative console, enable third-party IdP. This configuration involves the same five components to set up registration, plus the IdP connections or IdP adapter instances to connect with the third-party identity providers. This capability enables a mapping configuration between the attributes returned by the identity provider and the fields within the registration page, streamlining the registration process. See the following configuration steps.

- IdP connections or IdP adapter instances
- A PingDirectory installation ([step 1](#))
- An authentication policy contract ([step 2](#))
- A local identity profile ([step 3](#))
- An HTML Form Adapter instance ([step 4](#))
- An IdP authentication policy ([step 5](#))

To illustrate the configuration steps, consider the following example.

You need to support a consumer registration use case, where users complete a self-service registration process to create their accounts and then access resources protected by multiple service providers. For a registration to complete successfully, a user must provide an email address, a first name, a last name, an optional mobile phone number, and a password. The email address is the user identifier. All attributes are sent to the service providers as per the partner agreements. You have already created a specific object class in the directory to store the user information. The object class name is `aPerson`, and the LDAP attributes are `mail`, `givenName`, `sn`, and `mobile`.

Additionally, this use case must also allow users to take advantage of their existing accounts at ACME, a major social network, for registration and authentication. It happens that you have already established an IdP connection to this social network, from which you received the same set of attributes: `SAML_SUBJECT` for the user's email address, `ssoFirstName`, `ssoLastName`, and `ssoMobile`.

Configure a third-party identifier.



#### Tip:

If you know how to set up PingDirectory to connect with PingFederate and an authentication policy contract shown in [Setting up self-service registration](#) on page 371, you can skip to [step 3](#) to create a local identity profile.



## Steps

1. Install PingDirectory.
2. Create an authentication policy contract.
  - a. Go to **Authentication # Policies # Policy Contracts**.
  - b. In the **Policy Contracts** window, click **Create New Contract**.
  - c. On the **Contract Attributes** tab, in the **Extend the Contract** field, extend the authentication policy contract with three additional attributes, such as, **firstName**, **lastName**, and **mobileNumber**.
  - d. After each entry add, click **Add**. Click **Next**.
  - e. On the **Summary** tab, review your changes. Click **Done**.
  - f. In the **Policy Contracts** window, click **Save**.

For more information, see .

3. Create a local identity profile using the **Authentication # Policies # Local Identity Profiles**. Click **Create New Profile** to access the **Local Identity Profile** window and configuration wizard.
  - a. On the **Profile Info** tab, enter a name in the **Local Identity Profile Name** field, select the authentication policy from [step 2](#), and select the **Enable Registration** check box. Click **Next**.
  - b. On the **Authentication Sources** tab, enter `ACME` in the **Authentication Source** field. Click **Add**.


 **Note:**

To support additional third-party identity providers, enter a value for each. At runtime, the sign-on page displays them in the order defined on this window.

 **Tip:**

If you know how to set up a local identity profile and an HTML Form Adapter instance for customer identities shown in [Setting up self-service registration](#) on page 371), you can skip to [step 5](#) to create an IdP authentication policy.

- c. On the **Fields** tab, define four local identity fields as shown in the following table.

| Type  | ID           | Label         | Parameters   |
|-------|--------------|---------------|--|
| Email | lipEmail     | Email address | Select the <b>Required</b> and <b>Unique ID</b> check boxes.   |
|       |              |               |  <b>Note:</b><br>The <b>Unique ID</b> check boxes are on the <b>Fields</b> tab. |
| Text  | lipFirstName | First name    | Select the <b>Required</b> check box.  |
| Text  | lipLastName  | Last name     | Select the <b>Required</b> check box.  |

| Type  | ID        | Label         | Parameters     |
|-------|-----------|---------------|----------------|
| Phone | lipMobile | Mobile number | None required. |

As needed, select the **Mask Log Values** check box for any of the four local identity fields, and select the **Mask all OGNL-expression generated log values** check box for all fields.

- d. On the **Email Verification** tab, click **Next**.
- e. On the **Registration** tab, click **Next**.
- f. On the **Data Store Configuration** tab, click **Configure Data Store**.
- g. In the **Data Store Configuration** window, on the **Data Store** tab, from the **Data Store** list, select the LDAP datastore that has been set up to connect to your PingDirectory. Click **Next**.
- h. In the **Data Store Configuration** window, on the **LDAP Configuration** tab, specify the branch of your directory hierarchy where you want to store customer identities in the **Base DN** field and the LDAP attributes to be associated with fields defined in this local identity profile under **Attribute**.
- i. In the **Data Store Configuration** window, on the **Identity Creation** tab, define the RDN pattern in the **Relative DN Pattern** field, and select your object, such as class **aPerson** for this sample use case, from the **Object Class** list.

The pattern is as follows.

```
attribute1=value1[, ..., attributeN=valueN]
```

If you want to use the `${entryUUID}` variable to guarantee the uniqueness of the relative DN's for all users, you must use it with the **entryUUID** LDAP attribute.

```
entryUUID=${entryUUID}
```

- j. In the **Data Store Configuration** window, on the **Data Store Mapping** tab, configure the mapping between the local identity profile fields and the datastore attributes. See the following table.

#### Mapping entries for local identity profile fields and datastore attributes

| Field        | Data Store Attribute |
|--------------|----------------------|
| lipEmail     | mail                 |
| lipFirstName | givenName            |
| lipLastName  | sn                   |
| lipMobile    | mobile               |

- k. In the **Data Store Configuration** window, on the **Summary** tab, click **Done**.
- l. On the **Summary** tab of the local identity profile, click **Save**.

For more information, see [Configuring local identity profiles](#) on page 359.

4. Configure an HTML Form Adapter instance for customer identities.
  - a. Go to the **Authentication # Integration # IdP Adapters**.
  - b. Create a new HTML Form Adapter instance or reuse an existing one by clicking its name.
  - c. On the **IdP Adapter** tab, in the **Password Credential Validator Instance** section add the LDAP Username Password Credential Validator instance that has been set up to validate credentials stored on your PingDirectory.
  - d. On the **IdP Adapter** tab, select the newly created local identity profile in the **Local Identity Profile** list.
  - e. Complete the rest of the configuration and save all changes.

(For more information, see .)

5. Create an IdP authentication policy.
  - a. Go to the **Authentication # Policies # Policies**.
  - b. Under **Policy**, select the HTML Form Adapter instance configured in [step 4](#).
  - c. In the **Policy** window, under the **Value** section, select the drop-down arrow to show the **Fail** and **Success** fields.
    1. For the **Fail** path, select **Done**.
    2. For the **Success** path, select the local identity profile created in [step 3](#). Click **Done**.
  - d. Click **Local Identity Mapping** underneath the selected local identity profile, which opens the **Inbound Mapping & Contract Fulfillment** configuration wizard.

**Note:**

The next few steps configure the fulfillment of the authentication policy contract for the scenario where users choose to register directly without going through ACME.

**Tip:**

If you know how to setup the inbound mapping and contract fulfillment of an authentication policy contract through a local identity profile shown in [Setting up self-service registration](#) on page 371, you can skip to [step i](#) to create a rule for the scenario where users choose to register and subsequently authenticate via ACME.

- e. On the **Inbound Mapping & Contract Fulfillment Inbound Mapping** window, configure the `pf.local.identity.unique.id` built-in local identity field for the registration process.  
At runtime, fulfills the value of the `pf.local.identity.unique.id` built-in local identity field based on this configuration and passes the value to PingDirectory. PingDirectory uses this value to determine whether such identity has already been created. The `pf.local.identity.unique.id` field value should therefore be mapped from the subject

identifier of the preceding authentication source, namely the **username** attribute from the HTML Form Adapter.

For this sample use case, configure the **Inbound Mapping** window as shown in the following table.

| Inbound Mapping Fulfillment | Source  | Value    |
|-----------------------------|---------|----------|
| pf.local.identity.unique.id | Adapter | username |

- f. On the **Attribute Sources & User Lookup** tab, click **Next**.
- g. On the **Attribute Sources & User Lookup** tab, click **Next**.
- h. On the **Issuance Criteria** tab, click **Next**.
- i. On the **Inbound Mapping & Contract Fulfillment # Summary** window, click **Done**.

The **Inbound Mapping & Contract Fulfillment** configuration wizard brings back the **Manage Authentication Policies** window.


 **Note:**

The remaining steps configure the fulfillment of the authentication policy contract for the scenario where users choose to register and subsequently authenticate through ACME.

- j. Click **Rules** underneath the **Success** path of the HTML Form Adapter instance.
- k. On the **Rules** dialog, create a policy path for users who choose to register and authenticate via ACME. For this sample use case, configure as in the following table.

**Authentication policy rules fields and entries**

| Attribute Name | Condition | Value | Result     |
|----------------|-----------|-------|------------|
| policy.action  | equal to  | ACME  | ACME users |

 **Important:**

The value here must match the value defined on the **Authentication Sources** window. See [step 3b](#).

The **Result** field controls the label shown for the policy path of this rule. The value does not need to match the value defined on the **Authentication Sources** window.

 **Important:**

If you have defined multiple third-party identity providers on the **Authentication Sources** window, you must repeat these steps to add a **policy.action** rule to create a policy path for each.

In addition, select the **Default to Success** check box, the default behavior. When selected, the **Success** path remains, which is important for this sample use case where users are free to choose whether to register and subsequently authenticate via ACME.

When finished, click **Done**, which brings you back to the **Authentication Policies** window.

- l. For the **ACME users** path, select the IdP connection to ACME under **Action**.

 **Tip:**

Generally speaking, any IdP adapter instance or IdP connection that connects to the third-party identity provider can be used here.

1. For its **Fail** path, select **Done**.



**Note:**

If you have defined multiple third-party identity providers and added rules to create a policy path for each, you may select **Restart**. The **Restart** policy action provides users the opportunity to do over. When triggered, the policy engine routes the requests back to the first checkpoint of the invoked authentication policy.

By selecting **Restart** for the **Fail** path, you give users the opportunity to choose another third-party identity provider when they fail to authenticate through ACME.

Undesirable looping behaviors can occur if you select **Restart** for the **Fail** path at the root of an authentication policy tree. PingFederate mitigates this risk by automatically limiting the number of policy restarts per transaction.

2. For its **Success** path, select the local identity profile created in [step 3](#).
- m. Click **Local Identity Mapping** underneath the selected IdP connection, which opens the **Inbound Mapping & Contract Fulfillment** configuration wizard.
  - n. On the **Inbound Mapping & Contract FulfillmentInbound Mapping** window, configure the `pf.local.identity.unique.id` built-in local identity field for the registration process and optionally other fields so that PingFederate can pre-populate values for these fields on the registration page.

At runtime, fulfills the value of the `pf.local.identity.unique.id` built-in local identity field based on this configuration and passes the value to PingDirectory. PingDirectory uses this value to determine whether such identity has already been created. The `pf.local.identity.unique.id` field value should therefore be mapped from the subject identifier of the preceding authentication source, namely the subject identifier from the IdP connection.

For this sample use case, the **Inbound Mapping** window is configured as in the following table.

**Inbound Mapping fields and entries**

| Inbound Mapping Fulfillment              | Source         | Value        |
|--|----------------|--------------|
| <code>pf.local.identity.unique.id</code> | IdP Connection | SAML_SUBJECT |
| <code>lipEmail</code>                    | IdP Connection | SAML_SUBJECT |
| <code>lipFirstName</code>                | IdP Connection | ssoFirstName |
| <code>lipLastName</code>                 | IdP Connection | ssoLastName  |

| Inbound Mapping Fulfillment Source | Value          |
|------------------------------------|----------------|
| lipMobile                          | IdP Connection |
|                                    | ssoMobile      |

- o. On the **Attribute Sources & User Lookup** tab, click **Next**.
- p. On the **Attribute Sources & User Lookup** tab, click **Next**.
- q. On the **Issuance Criteria** tab, click **Next**.
- r. On the **Inbound Mapping & Contract Fulfillment Summary** tab, click **Done**.

The **Inbound Mapping & Contract Fulfillment** configuration wizard brings back the **Manage Authentication Policies** window.

 **Important:**

If you have defined multiple rules, each forming a policy path for a third-party identity provider, ensure you complete the **Inbound Mapping & Contract Fulfillment** configuration for each of them.

- s. In the **Policies** window, on the **Policies** tab, select the **IdP Authentication Policies** check box.

 **Note:**

Other IdP authentication policies, if any, are enabled as well.

- t. Click **Save** to keep your changes.


For more information, see [Applying policy contracts or identity profiles to authentication policies](#) on page 263.

## Result

You have now successfully set up self-service registration with an option for users to register and subsequently authenticate via ACME. When users sign on through this HTML Form Adapter instance, they have two registration options:

- Click the **Register now** link, fill in the registration page, and register.
- Click the social sign-on link, authenticate via ACME, review the registration page, and register.

Based on the configuration of this sample use case, the following screen capture of a sign-on page is presented.



If you have added Facebook, Google, LinkedIn, and Twitter as the authentication sources, the following sign-on page is presented.

Suppose a user chooses to register through ACME. Once authenticated and redirected back to PingFederate, PingFederate pre-populates the registration page with values it receives from ACME, as illustrated in this screen capture.

This registration option streamlines the self-service registration process.

### Enabling profile management

In addition to registration, you can enable self-service profile management and specify which local identity fields users can update on the profile management page.

#### About this task

Use the administrative console to enable profile management.

To illustrate the configuration steps, consider the sample use case in [Setting up self-service registration](#) on page 371 or [Enabling third-party identity providers](#) on page 376 with the added requirement of allowing users to modify their mobile number and to remove their local accounts.

Configuration steps:



#### Tip:

As the required components remain the same, the step sequence matches those in [Setting up self-service registration](#) on page 371 and [Enabling third-party identity providers](#) on page 376 as well. If you require more information for a given step, see the same step in one of the aforementioned pages.

#### Steps

1. Set up PingDirectory to connect with PingFederate.
2. Create an authentication policy contract. For more information on how to create an authentication policy contract, see [Managing policy contracts](#).

3. Configure profile management when creating a new or reconfiguring an existing local identity profile.
  - a. Go to **Authentication # Policies # Local Identity Profiles** configuration wizard.
  - b. On the **Profile Info** tab, select the **Enable Profile Management** check box. Click **Next**.
  - c. Optional: On the **Authentication Sources** tab, define authentication sources. For more information, see [Defining authentication sources](#).
  - d. On the **Fields** tab, select the **Profile Management** check box under **Applies To** for the applicable fields as you define local identity fields.
 

These selected local identity fields will be shown to authenticated users on the profile management page.

For this sample use case, select the **Profile Management** check box for the `lipMobile` local identity field.
  - e. On the **Email Verification** tab, click **Next**.
  - f. On the **Registration** tab, click **Next**.
  - g. On the **Profile Management** tab, select the **Enable Profile Deletion** check box.
 

In general, this is an optional feature. It is selected here because it is one of the requirements of this sample use case.
  - h. Continue from step 3f as documented in [Setting up self-service registration](#) on page 371 or [Enabling third-party identity providers](#) on page 376.
4. Configure an HTML Form Adapter instance for customer identities. For more information, see [Configuring the HTML Form Adapter for customer identities](#).
5. Create an IdP authentication policy. For more information, see [Defining authentication policies](#).
6. Provide the profile management URL to users.
  - a. Go to **Authentication # Policies # Local Identity Profiles**.
  - b. Select the local identity profile that you have configured profile management in [step 3](#).
  - c. Copy the profile management URL as shown on the **Summary** tab and pass it to the users.

## Result

You have now successfully enabled profile management. Authenticated users can review and modify the local identity fields that have been configured to show on the profile management page and delete their local accounts if the option has been enabled.

The following screen capture provides a sample of the profile management page based on the sample use case.

If you add Facebook, Google, LinkedIn, and Twitter to the local identity profile, when a user accesses the profile management page, the user will see a page similar to the following screen capture.

If you have only one authentication source, the profile management page reminds the users that they must set a password for their local accounts before disconnecting the third-party identity provider.

## Creating advanced registration mapping

PingFederate leverages the HTML Form Adapter to deliver a secure and easy-to-use customer authentication, registration, and profile management solution. The HTML Form Adapter contract includes two core attributes.

### About this task

Using the administrative console, create advanced registration mapping by defining authentication policies in your adapter instances.



To illustrate the configuration steps, consider the following setup that you have already made with the parameters `username` and `policy.action`. Whether or not the local identity profile is configured with any authentication sources, if the user chooses to register directly by clicking on the **Register now** link, sets the value to `identity.registration`. This fulfillment allows you to create rules to differentiate authentication requirements from the registration flow.

- A PingDirectory installation with a set of users.
- An LDAP datastore, an LDAP Username Password Credential Validator instance, and an HTML Form Adapter instance on PingFederate to validate credentials stored in PingDirectory.
- An IdP authentication policy that chains the HTML Form Adapter instance, an PingID Adapter instance, and an authentication policy contract for the purpose of enforcing PingID multi-factor authentication in multiple browser-based single sign-on (SSO) use cases through service provider (SP) connections, OAuth authorization code flow, and OAuth implicit flow. The following window capture illustrates your existing policy.

To illustrate the configuration steps, consider the following setup that you have. You need to add support for a consumer registration use case similar to the one in [Setting up self-service registration](#) on page 371, and, at the same time, keep the policy that enforces the multi-factor authentication requirement.

Configuration steps.

### Steps

1. Set up PingDirectory for customer identities.
2. Make a note of which authentication policy contract is currently being used in your policy.
3. Create a local identity profile.
  - a. Go to **Authentication # Policies # Local Identity Profiles** configuration wizard.
  - b. On the **Profile Info** tab, in the **Local Identity Profile Name** field, enter a name of the local identity profile, and from the **Authentication Policy Contract** list, select the authentication policy from [step 2](#). Select the **Enable Registration** check box.
 

If you want to enable profile management as well, select the relevant check box.
4. Configure the HTML Form Adapter instance for customer identities.
  - a. Go to **Authentication # Integration # IdP Adapters**.
  - b. From the **Instance Name** section, select the **HTMLFormAdapter**.
  - c. On the **IdP Adapter** tab, from the **Local Identity Profile** list, select a local identity profile.
  - d. Complete the rest of the configuration and save all changes.

5. Modify your existing IdP authentication policy.
  - a. Go to **Authentication # Policies # Policies**.
  - b. On the **Policies** tab, under the **Policy** section, click the relevant policy to open the **Policy** window.
  - c. Under the **Success** path of the HTML Form Adapter instance, click **Rules**.
  - d. In the **Rules** dialog, create a policy path for users who choose to register. For this sample use case, configure as follows.

#### Defining authentication policy rules attributes field and values

| Attribute Name | Condition | Value                 | Result  |
|----------------|-----------|-----------------------|---|
| policy.action  | equal to  | identity.registration | Registration<br><br>Complete the rest of the configuration to create the local identity. The <b>Result</b> field controls the label shown for the policy path of this rule. |

In addition, ensure the **Default to Success** check box is selected. When selected, the **Success** path remains, which is important for this sample use case where users are redirected to the

PingID Adapter instance to fulfill the multi-factor authentication requirement after authenticating successfully against the HTML Form Adapter.

When finished, click **Done**, which brings you back to the **Manage Authentication Policies** window.

- e. For the **Registration** path, select the local identity profile from [step 3](#) under **Action** and then complete its **Local Identity Mapping** configuration.

The following screen capture illustrates your new policy.

The screenshot shows the 'Manage Authentication Policies' interface. At the top, there are checkboxes for 'ENABLE IDP AUTHENTICATION POLICIES' (checked), 'ENABLE SP AUTHENTICATION POLICIES' (unchecked), and 'FAIL IF POLICY ENGINE FINDS NO AUTHENTICATION SOURCE' (unchecked). Below this is a table with columns 'Action', 'Result', and 'Action'. The first row shows 'HTML Form - (Adapter)' as the Action, 'Fail' as the Result, and 'Done' as the Action. The second row shows 'Registration - (Local Identity Profile)' as the Action, 'Local Identity Mapping' as the Result, and 'Done' as the Action. The third row shows 'PingID - (Adapter)' as the Action, 'Fail' as the Result, and 'Done' as the Action. The fourth row shows 'Primary contract - (Policy Contract)' as the Action, 'Fail' as the Result, and 'Contract Mapping' as the Action.

- f. If you have enabled profile management in [step 3](#), you must also replace the policy contract with the local identity profile and then complete its **Local Identity Mapping** configuration.

This step is required so that PingFederate can route users through the **HTML Form # PingID** policy path when they try to access the profile management page.

The following screen capture illustrates this change.

The screenshot shows the 'Manage Authentication Policies' interface. At the top, there are checkboxes for 'ENABLE IDP AUTHENTICATION POLICIES' (checked), 'ENABLE SP AUTHENTICATION POLICIES' (unchecked), and 'FAIL IF POLICY ENGINE FINDS NO AUTHENTICATION SOURCE' (unchecked). Below this is a table with columns 'Action', 'Result', and 'Action'. The first row shows 'HTML Form - (Adapter)' as the Action, 'Fail' as the Result, and 'Done' as the Action. The second row shows 'Reg and PM - (Local Identity Profile)' as the Action, 'Local Identity Mapping' as the Result, and 'Done' as the Action. The third row shows 'PingID - (Adapter)' as the Action, 'Fail' as the Result, and 'Done' as the Action. The fourth row shows 'Reg and PM - (Local Identity Profile)' as the Action, 'Local Identity Mapping' as the Result, and 'Done' as the Action.

#### **Note:**

No reconfiguration is required in your Browser SSO connections and OAuth grant-mapping configuration for your new policy to take effect.

- g. Click **Save** to keep your changes.

#### Result

You have now successfully added the requested consumer registration and profile management use case to your current policy.

## Enabling third-party identity providers without registration

If you have already configured identity provider (IdP) connections or IdP adapters to connect with third-party identity providers, you can enhance the HTML Form Adapter sign-on page with the option to authenticate with these providers.

#### About this task

You configure an IdP authentication policy to chain the HTML Form Adapter instance and an authentication policy contract. Then the policy contract can harness attribute values returned by the HTML Form Adapter

instance for multiple browser-based single sign-on (SSO) use cases through service provider (SP) connections, OAuth authorization code flow, and OAuth implicit flow.

The following procedure offers an example of how you could enhance the sign-on experience by giving users the option to authenticate with their local accounts or their existing accounts on a major social network to which you have already established an IdP connection. In this example, the social network is named "ACME".

**Tip:**

You can also deploy and configure Cloud Identity Connectors to support identities from Facebook, Google, LinkedIn, or Twitter.

**Steps**



1. Verify that the IdP connection to ACME returns the attributes required to complete the browser-based SSO use cases.
2. Note which authentication policy contract your policy uses.
3. Create a local identity profile:
  - a. Go to **Authentication # Policies # Local Identity Profiles**. Click **Create New Profile**.
  - b. On the **Profile Info** tab, in the **Local Identity Profile Name** field, enter a name.
  - c. From the **Authentication Policy Contract**, select the authentication policy contract from [step 2](#). Click **Next**.
  - d. On the **Authentication Sources** tab, under **Authentication Source**, enter `ACME`, and then click **Add**. Click **Done**.

**Note:**

To support additional third-party identity providers, enter a value for each. At runtime, the sign-on page displays them in the order defined on this window.

4. Configure the HTML Form Adapter instance for customer identities:
  - a. Go to **Integration # IdP Adapters**.
  - b. On the **IdP Adapters** window, from the **Instance Name** list, click the **HTMLFormAdapter** instance.
  - c. On the **IdP Adapter** tab, from the **Local Identity Profile** list, select a local identity profile.
  - d. Complete the rest of the configuration and save all changes.

5. Modify your existing IdP authentication policy:
  - a. Go to **Authentication # Policies # Policies**.
  - b. On the **Policies** tab, in the **Policy** section, click the existing IdP policy.
  - c. In the **Success** path of the HTML Form Adapter instance, click **Rules**.
  - d. In the **Rules** dialog, create a policy path for users who choose to authenticate with ACME. For this example, configure the fields as shown in the following table.

| Attribute Name | Condition | Value  | Result   |
|----------------|-----------|--|--|
| policy.action  | equal to  | ACME   | ACME users   |
|                |           |  <b>Important:</b><br>The value here must match the value defined on the <b>Authentication Sources</b> tab. See <a href="#">step 3d</a> . |  <b>Note:</b><br>The <b>Result</b> field controls the label shown for the policy path of this rule. The value does not need to match the value defined on the <b>Authentication Sources</b> window. |

 **Important:**

If you have defined multiple third-party identity providers on the **Authentication Sources** tab, you must repeat these steps to add a `policy.action` rule to create a policy path for each.

In addition, ensure the **Default to Success** check box is selected. When selected, the **Success** path remains, which is important when users can also authenticate using their local accounts, like in this example.

- e. Click **Done**.  
Result: This returns you to the **Authentication Policies** window.
- f. For the **ACME users** path, under **Action**, select the IdP connection to ACME.

 **Tip:**

Generally, any IdP adapter instance or IdP connection that connects to the third-party identity provider can be used here.

- g. For the ACME **Fail** path, select **Done**.

 **Note:**

If you have defined multiple third-party identity providers and added rules to create a policy path for each, you can select **Restart**. The **Restart** policy action provides users the opportunity to do over. When triggered, the policy engine routes the requests back to the first checkpoint of the invoked authentication policy. By selecting **Restart** for the **Fail** path, you give users the

opportunity to choose another third-party identity provider if they fail to authenticate through ACME.

- h. For the ACME **Success** path, select the local identity profile created in [step 3](#), and then complete the **Local Identity Mapping** configuration.


 **Note:**

Because this use case does not involve registration, the source of fulfillment is limited to the preceding IdP connection or IdP adapter instance, dynamic text, and attribute mapping expression, if enabled.


- i. Click **Save**.

## Result

After you give users the option to authenticate with ACME without enabling registration, when users sign on through this HTML Form Adapter instance, the following sign-on page is presented.



If you also added Facebook, Google, LinkedIn, and Twitter as authentication sources, the following sign-on page is presented.



## Customizing assertions and authentication requests

Customize applicable messages by enabling OGNL expression and going to the **URL** window to access the **Show Advanced Customizations** option.

### About this task

Some browser single sign-on (SSO) use cases might require additional customizations in the assertions sent from the PingFederate identity provider (IdP) server to the service provider (SP), or in the authentication requests sent from the PingFederate SP server to the IdP. PingFederate can fulfill these use cases on a per-connection basis using OGNL expressions.

### Steps

1. Enable OGNL expression by editing the `org.sourceid.common.ExpressionManager.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
2. Select the applicable SP or IdP connection.

3. On the **Activation & Summary** window, scroll to the Protocol Settings section, and click **Assertion Consumer Service URL** for an SP connection, or click **SSO Service URLs** for an IdP connection.
4. Click **Show Advanced Customizations** to customize the applicable message.

The available customizable **Message Types** vary depending on your federation role (IdP or SP) as well as the protocol of the connection (SAML 1.x, SAML 2.0, and WS-Federation). After you select a message type, you have access to its list of **Available Variables**. You can customize the assertions or the authentication requests as needed.

## Message types and available variables

Advanced customizations depend on available message types and available variables for both service provider (SP) connections and identity provider (IdP) connections.

The following tables describe the relationship between message type and available variable, as well as the corresponding class or interface information in Javadoc.



### Tip:

The Javadoc for is located in the `<pf_install>/pingfederate/sdk/doc` directory.

### SP connections (SAML 2.0)

| Message Types    | Available Variables<br>Classes/Interfaces in Javadoc  |
|------------------|---|
| AssertionType    | #AssertionType<br>org.sourceid.saml20.xmlbinding.assertion.AssertionType<br>#AssertionTypes<br>org.sourceid.saml20.xmlbinding.assertion.AssertionType []<br>#Attributes<br>org.sourceid.util.log.AttributeMap |
| ResponseDocument | #ResponseDocument<br>org.sourceid.saml20.xmlbinding.protocol.ResponseDocument<br>#Attributes<br>org.sourceid.util.log.AttributeMap  |

### SP connections (SAML 1.x)

| <b>Message Types</b> | <b>Available Variables</b><br><b>Classes/Interfaces in Javadoc</b>   |
|----------------------|--|
| AssertionType        | #AssertionType<br>org.sourceid.protocol.saml11.xml.AssertionType<br>#AssertionTypes<br>org.sourceid.protocol.saml11.xml.AssertionType[]<br>#Attributes<br>org.sourceid.util.log.AttributeMap |
| ResponseDocument     | #ResponseDocument<br>org.sourceid.protocol.samlp11.xml.ResponseDocument<br>#Attributes<br>org.sourceid.util.log.AttributeMap   |

## SP connections (WS-Federation)

| <b>Message Types</b>                 | <b>Available Variables</b><br><b>Classes/Interfaces in Javadoc</b>  |
|--------------------------------------|---|
| AssertionType                        | #AssertionType<br>org.sourceid.protocol.saml11.xml.AssertionType<br>#Attributes<br>org.sourceid.util.log.AttributeMap   |
| RequestSecurityTokenResponseDocument | #RequestSecurityTokenResponseDocument<br>org.xmlsoap.schemas.ws.x2005.x02.trust.RequestSecurityTokenResponseDocument<br>#Attributes<br>org.sourceid.util.log.AttributeMap |

## IdP connections (SAML 2.0)

| <b>Message Type</b>  | <b>Available Variables</b><br><b>Classes/Interfaces in Javadoc</b>                    |
|----------------------|---|
| AuthnRequestDocument | #AuthnRequestDocument<br>org.sourceid.saml20.xmlbinding.protocol.AuthnRequestDocument |

## Other available variables (regardless of roles and protocols)

| <b>Available Variables</b> | <b>Classes/Interfaces in Javadoc</b> |
|----------------------------|--------------------------------------|
| #XmlHelper                 | com.pingidentity.sdk.xml.XmlHelper   |



| Available Variables  | Classes/Interfaces in Javadoc          |
|----------------------|--|
| #HttpServletRequest  | javax.servlet.http.HttpServletRequest  |
| #HttpServletResponse | javax.servlet.http.HttpServletResponse |

Variables related to Federation Hub (regardless of message type)

| Connections            | Protocol      | Available Variables<br>Classes/Interfaces in Javadoc   |
|------------------------|---------------|--|
| SP and IdP connections | SAML 2.0      | #FedHubIncomingAuthnRequest<br>org.sourceid.saml20.xmlbinding.protocol.AuthnRequestDocument  |
| SP connection          | SAML 2.0      | #FedHubOutgoingAuthnRequest<br>org.sourceid.saml20.xmlbinding.protocol.AuthnRequestDocument  |
| SP connection          | SAML 2.0      | #FedHubIncomingAuthnResponse   |
|                        | SAML 1.x      | org.sourceid.saml20.xmlbinding.protocol.ResponseDocument (SAML 20)   |
|                        | WS-Federation | org.sourceid.protocol.samlp11.xml.ResponseDocument (SAML 1.x)<br>org.xmlsoap.schemas.ws.x2005.x02.trust.RequestSecurityToken (WS-Federation) |
| SP connection          | SAML 2.0      | #FedHubIdpConnPartnerId  |
|                        | SAML 1.x      | java.lang.String   |
|                        | WS-Federation | The <b>Partner's Entity ID</b> in the IdP connection that bridges the identity provider.   |
| SP connection          | SAML 2.0      | #FedHubIdpConnProtocol   |
|                        | SAML 1.x      | java.lang.String   |
|                        | WS-Federation | The protocol of the SP connection. The returned values are SAML20, SAML11, SAML10, or WSFED.   |
| IdP connection         | SAML 2.0      | #FedHubSpConnApplicationName   |
|                        | SAML 1.x      | java.lang.String   |
|                        | WS-Federation | The application name in the SP connection that bridges the service provider.   |
| IdP connection         | SAML 2.0      | #FedHubSpConnName  |
|                        | SAML 1.x      | java.lang.String   |
|                        | WS-Federation | The connection name in the SP connection that bridges the service provider.  |

| Connections    | Protocol      | Available Variables<br>Classes/Interfaces in Javadoc   |
|----------------|---------------|--|
| IdP connection | SAML 2.0      | #FedHubSpConnPartnerId   |
|                | SAML 1.x      | java.lang.String   |
|                | WS-Federation | The <b>Partner's Entity ID</b> in the SP connection that bridges the service provider.                                       |
| IdP connection | SAML 2.0      | #FedHubSpConnProtocol  |
|                | SAML 1.x      | java.lang.String   |
|                | WS-Federation | The protocol of the IdP connection. The returned values are SAML20, SAML11, SAML10, or WSFED.                                |
| Not applicable | OAuth         | #FedHubOAuthClientId<br>java.lang.String<br>The client ID in the authorization server that bridges the service provider.     |
| Not applicable | OAuth         | #FedHubOAuthClientName<br>java.lang.String<br>The client name in the authorization server that bridges the service provider. |

## Sample customizations

Use OGNL expressions to customize assertions and authentication requests in different ways.

Add `SessionNotOnOrAfter` to assertions

This expression adds the optional `SessionNotOnOrAfter` attribute to the `<AuthnStatement>` element and sets the value to 60 minutes.

Message Type

AssertionType

Expression

```
#cal = new org.apache.xmlbeans.XmlCalendar(new java.util.Date()),
#cal.setTimeZone(@java.util.TimeZone@getTimeZone("UTC")),
#cal.add(@java.util.Calendar@MINUTE, 60),
#AssertionType.getAuthnStatementArray(0).setSessionNotOnOrAfter(cal)
```

Expected assertions

```
...
<saml:AuthnStatement ... AuthnInstant="2015-03-20T16:27:37.344Z"
  SessionNotOnOrAfter="2015-03-20T17:27:37.398Z">
  <saml:AuthnContext>
    <saml:AuthnContextClassRef>...</saml:AuthnContextClassRef>
  </saml:AuthnContext>
</saml:AuthnStatement>
```

...

### Use well-formed XML as attribute value

The following expression inserts well-formed XML in the `<AttributeValue>` element if the **Attribute Name Format** is `urn:pingidentity.com:SAML:attrname-format:xml:complex`.

#### Message Type

AssertionType

#### Expression

```
#i = 0,
#AssertionType.getAttributeStatementArray(0).getAttributeArray().{
  #this.getNameFormat().equals('urn:pingidentity.com:SAML:attrname-
format:xml:complex')}?{
  #xml = #this.getAttributeValueArray(0).getStringValue(),
  #ast =
  @org.sourceid.saml20.xmlbinding.assertion.AttributeStatementType
  $Factory@parse(#xml),
  #AssertionType.getAttributeStatementArray(0).setAttributeArray(#i,
  ast.getAttributeArray(0))
}:null,
#i = #i+1
}
```

#### Note:

Line breaks are inserted for readability only. Statements calling methods whose arguments are enclosed in quotes must be entered on a single line.

This example uses well-formed XML as the attribute value for attributes that are configured as `urn:pingidentity.com:SAML:attrname-format:xml:complex` (a custom attribute name format added to `<pf_install>/pingfederate/server/default/data/config-store/custom-name-formats.xml`) in the **Attribute Contract** window. You can use other application logic here.

#### Sample inputs (attributes and their values)

|                       |   |
|-----------------------|---|
| Attribute Name        | ExtAttr1  |
| Attribute Name Format | urn:oasis:names:tc:SAML:2.0:attrname-format:unspecified |
| Attribute Value       | 123   |

|                |          |
|----------------|----------|
| Attribute Name | ExtAttr2 |
|----------------|----------|

Attribute Name Format urn:pingidentity.com:SAML:attrname-format:xml:complex

Attribute Value

```
<saml:Attribute
  xmlns:saml="urn:oasis:names:tc:SAML:2.0:assertion"
  Name="ExtAttr2"
  NameFormat="urn:oasis:names:tc:SAML:2.0:attrname-
format:unspecified">
  <saml:AttributeValue
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance"
    xmlns:customNs="http://www.sample.tld/
customnamespace">
    <customNs:Line>Documentation</customNs:Line>
    <customNs:Line>Ping Identity</customNs:Line>
  </saml:AttributeValue>
</saml:Attribute>
```



**Note:**

This is a well-formed XML document in one line.

### Expected results

```
...
<saml:Attribute Name="ExtAttr1"
  NameFormat="urn:oasis:names:tc:SAML:2.0:attrname-format:unspecified">
  <saml:AttributeValue xsi:type="xs:string"
    xmlns:xs="http://www.w3.org/2001/XMLSchema"
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
    123
  </saml:AttributeValue>
</saml:Attribute>
<saml:Attribute Name="ExtAttr2"
  NameFormat="urn:oasis:names:tc:SAML:2.0:attrname-format:unspecified">
  <saml:AttributeValue
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
    xmlns:customNs="http://www.sample.tld/customnamespace">
    <customNs:Line>Documentation</customNs:Line>
    <customNs:Line>Ping Identity</customNs:Line>
  </saml:AttributeValue>
</saml:Attribute>
...
```

### Include extensions in authentication requests

This expression includes the optional **Extensions** element in the authentication requests if a certain query parameter (`oid` in this example) is sent to the `/sp/startSSO.ping` endpoint to start an SP-initiated SSO request.

### Message Type

AuthnRequestDocument

### Expression

```
#element = #XmlHelper.addToSaml2Extensions(#AuthnRequestDocument,
  '<saml:orgId name="orgId" xmlns:saml="urn:org.sample.wms"/>'),
```

```
#value = #HttpServletRequest.getParameter('oid') == null ?
'someDefaultValue' : #HttpServletRequest.getParameter('oid') ,
#XmlHelper.setAttribute(#element, 'value', #value)
```

### Expected AuthnRequest

A GET request to `https://<pf_host>:<pf.https.port>/sp/startSSO.ping?PartnerIdId=<entityID>&oid=123` would trigger the following Extensions block.

```
<samlp:AuthnRequest ...>
  <saml:Issuer ...>...</saml:Issuer>
  <samlp:Extensions>
    <samlplens:orgId name="orgId" value="123"
  xmlns:samlplens="urn:org.sample.wms"/>
  </samlp:Extensions>
  ...
</samlp:AuthnRequest>
```

## Fulfillment by datastore queries

You can configure PingFederate to use local datastores to fulfill various contracts or conditions to verify in the token authorization process.

Datastores represent external systems where user attributes and other data are stored. Once defined, you can configure to retrieve user attributes from datastores for contract fulfillment and token authorization in various use cases.

supports a wide variety of database servers and directory servers. As needed, the SDK supports the creation of custom drivers for connecting to other types of data repositories, such as flat files or SOAP-connected databases. For more information, see the Javadoc for the `CustomDataSourceDriver` interface, the `SamplePropertiesDataStore.java` file for a sample implementation, and the [SDK Developer's Guide](#) on page 1115 for build and deployment information.



### Tip:


The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

## Attribute mapping with multiple data sources

PingFederate can query multiple datastores for additional attributes in most configurations.

### Multiple datastores in one mapping

The IdP server supports separate datastores to look up attributes for a single mapping. For example, you can query multiple datastores for values and map those values in one mapping, or query a datastore for a value and use that value as input for subsequent queries of other datastores.



If a datastore uses results from previous queries as input, and if the previous queries return no result, continues the process by moving on to the next datastore in the setup. If you prefer to abort and fail the requests, see [Configuring the behavior of searching multiple datastores with one mapping](#) on page 908.


If a required attribute, such as `SAML_SUBJECT` in a SAML contact or `subject` in an authentication policy contract, is not fulfilled, the request fails.

Multiple datastores in one mapping are available for browser single sign-on (SSO) and WS-Trust security token service (STS) on the identity provider (IdP) side, authentication policy contract to service provider (SP) adapter mappings, and the following OAuth workflows:

- Identity provider (IdP) adapter grant mappings
- Resource owner credential grant mappings
- Access token mappings
- OpenID Connect policies (the user-attributes mapping process)

### Multiple mappings and failsafe mapping

For browser SSO and WS-Trust STS on the IdP side, PingFederate also supports separate search parameters for each datastore and for "fall-through" searches. For example, you can add the same datastore more than once, using different search queries for each instance, or you can search different datastores successively. If any search fails to find a user in the specified attribute source, the next search is executed until a match is found. You can also configure a failsafe attribute source, providing a default set of attributes from the IdP adapter and using text values.



## Datastore query configuration

You can query attributes from a datastore by choosing a datastore instance, specifying the search location and the desired attributes, and entering the search term.

After the configuration is complete, you can fulfill a contract or verify a condition in the Token Authorization framework using the results from the datastore queries.

### Choosing a datastore

This topic describes how to select a datastore for PingFederate to use for looking up attributes.

#### About this task

On the **Data Store** window, choose a datastore for to look up attributes.

#### Steps

1. Enter a description and ID, if prompted, for the datastore.
2. Select a datastore instance from the **Active Data Store** list.



**Tip:**

If the datastore you want is not shown in the **Active Data Store** list, click **Manage Data Stores** to review or add a datastore instance.

- Depending on the datastore type, the rest of the setup varies as follows.

| Data store type | Required tasks   |
|-----------------|--|
| JDBC            | <ul style="list-style-type: none"> <li><a href="#">Specifying database tables and columns</a> on page 399</li> <li><a href="#">Entering a database search filter</a> on page 400</li> </ul>  |
| LDAP            | <ul style="list-style-type: none"> <li><a href="#">Specifying directory properties and attributes</a> on page 401</li> <li><a href="#">Defining encoding for binary attributes</a> on page 403 (optional)</li> <li><a href="#">Entering a directory search filter</a> on page 404</li> </ul> |
| Other           | <ul style="list-style-type: none"> <li><a href="#">Specifying data source filters and fields</a> on page 405</li> </ul>  |

### Specifying database tables and columns

In the **Database Table and Columns** window, you can specify exactly where additional data can be found to fulfill your use case. You can only use one table as a source of data for a database query.

About this task

For more information about each field, see the following table.

| Field                         | Description  |
|-------------------------------|--|
| Schema                        | Lists the table structure that stores information within a database. Some databases require selection of a specific schema for database queries. Other databases do not require selection of a schema. |
| Table                         | Displays the tables contained in the database. Select the table to retrieve data from the datastore.   |
| Columns to return from SELECT | Displays selected columns from the selected tables. Select the columns that are associated with the desired attributes you want to return from the database queries.                                   |



#### Important:

For MySQL users — To allow for table and column names that might contain spaces, PingFederate inserts double quotes around the names at runtime. To avoid SQL syntax errors resulting from the quotes, add the session variable `sql_mode=ANSI_QUOTES` to the Java Database Connectivity (JDBC) connection string of your datastore instance, as in the following example.

```
jdbc:mysql://myhost.mydomain.com:3306/pf?sessionVariables=sql_mode=ANSI_QUOTES
```

Alternatively, you can configure the system variable `sql_mode` with the `ANSI_QUOTES` option. For more information, see <https://dev.mysql.com/doc/refman/5.7/en/server-system-variables.html>.

### Steps

- From the **Schema** list, choose a schema when applicable.
- From the **Table** list, select a table.
- Optional: To determine what attributes to examine, click **View Attribute Contract**.
- Optional: To update an existing configuration where changes to the database might have occurred, click **Refresh**.

- Under **Columns to return from SELECT**, choose a column name and click **Add Attribute**.

**Note:**

You do not have to add a column here to use it as part of a search filter. Add only the column that is required by subsequent sibling configuration items, such as contract fulfillment or token authorization. Any added columns left unused are removed when the configuration is saved.

Repeat this step to add more columns as needed.

Example

Example

Suppose you, the identity provider (IdP), have a data table named **ACCESSTABLE** with three columns: **userid**, **department**, and **accesslevel**. Your use case requires you to map **accesslevel** into a SAML contract to an SP.

On the **Database Table and Columns** window, select the **ACCESSTABLE** table and add the **accesslevel** column.

**Entering a database search filter**

Use a **WHERE** clause on the **Database Filter** window to set up a database search filter in PingFederate.

About this task

On the **Database Filter** window, enter a **WHERE** clause for PingFederate to query the database table you selected to retrieve a record associated with particular values. The clause is in the form:

```
[WHERE] column1=value1
```

The left side (*column1*) is a column from the database table that you selected on the **Database Table and Columns** window.

**Tip:**

To get a list of columns, click the **View List of Columns from ...** link.

The right side (*value1*) is the match-against value, generally a variable passed in from either an authentication source for an identity provider (IdP) or an assertion for a service provider (SP). The variables are shown underneath the **Where** text field. If you are retrieving attributes from multiple data stores using one mapping, attributes available from other sources, if previously configured, are listed near the bottom of the window.

You can also apply additional search criteria by using other columns from the targeted table.

Steps

- Enter a **WHERE** clause in the text field.

**Note:**

The initial **WHERE** is optional.



2. Ensure the syntax and variable names are correct. For more information about *WHERE* clauses, consult your database management system (DBMS) documentation.

**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `${ and }` in the default value.

3. Click **Next** to complete the configuration to query attributes from the database server.

Later in the workflow, you can use the attribute values returned from the database in the applicable contract fulfillment window, the issuance criteria window, or both, to fulfill your use case.

**Example****Example**

Suppose you have selected a data table named **ACCESSTABLE** on the **Database Table and Columns** window. You, the IdP, want to locate user records by matching `userid` column against the username from an HTML Form Adapter. As a passed-in variable from the HTML Form Adapter, `${username}` is shown underneath the **Where** text field.

On the **Database Filter** window, enter the following filter in the **Where** text field:

```
userid='${username}'
```

```
userid
```

The column in the table containing the username information in this example.

```
'${username}'
```

The value of the username variable (`username`) from an HTML Form Adapter

**Important:**

You must use the `${}` syntax to retrieve the value of the enclosed variable and insert single quotation marks around the `${}` characters.

**Specifying directory properties and attributes**

Use these instructions to initiate ways to specify methods for PingFederate to search for particular user data.

**About this task**

On the **LDAP Directory Search** window, specify the branch of your directory hierarchy where you want PingFederate to look up user data. For more information about each field, refer to the following table.

| Field                    | Description  |
|--------------------------|--|
| <b>Base DN</b>           | The base distinguished name (DN) of the tree structure in which the search begins. This field is optional if records are located at the root of the directory. |
| <b>Search Scope</b>      | The node depth of the query. Select <b>Subtree</b> (the default value), <b>One level</b> or <b>Object</b> .  |
| <b>Root Object Class</b> | The object class containing the desired attributes.  |

| Field                       | Description  |
|-----------------------------|--|
| <b>Attributes</b>           | A list of attributes based on the selected <b>Root Object Class</b> value. |
| <b>Option</b><br>(optional) | The attribute option for the selected attribute.                           |

### Steps

1. Optional: Specify a base DN.



#### Tip:

Choose a base DN that is as specific as possible for your search. A broad base DN can result in longer search times and increased network traffic, while a narrow base DN can help ensure that your search is accurate and efficient.

2. Select a search scope.
3. Optional: Click **View Attribute Contract** to determine what attributes to look up.
4. Select a root object class, an attribute, and, optionally, enter an **Option**. Click **Add Attribute**.



#### Note:

You do not have to add an attribute here to use it as part of a search filter. Add only the attributes that are required by subsequent sibling configuration items, such as contract fulfillment or token authorization. Any added attributes that are left unused are removed when the configuration is saved.

Choose from:

- Microsoft Active Directory

If you choose the **memberOf** attribute, an optional check box, **Nested Groups**, appears on the right. Select this check box if you want PingFederate to query for groups the end users belong to directly and indirectly through nested group membership (if any) under the base DN.

For example, if you have three groups under a base DN: Canada, Washington and Seattle. Seattle is a member of Washington. Ana Smith is an end user and a member of Seattle. If the **Nested Groups** check box is selected, when PingFederate queries for Ana's **memberOf** attribute values, the expected results are Seattle and Washington. When the **Nested Groups** check box is not selected (the default), the expected result is Seattle.



#### Important:

Do not enter any value for the **Option** field. Only the attributes that are defined in the directory server schema can be returned.

- Oracle Directory Server or Oracle Unified Directory

Choose **isMemberOf** under **Attribute** for nested group membership. For information related to Oracle Directory Server, go to [docs.oracle.com/cd/E29127\\_01/doc.111170/e28967/ismemberof-5dsat.htm](https://docs.oracle.com/cd/E29127_01/doc.111170/e28967/ismemberof-5dsat.htm). For information related to Oracle Unified Directory, go to [Fusion Middleware Administering Oracle Unified Directory](#) and search for *memberof user attributes*.



#### Tip:

If you need to include **tokenGroups** as one of the attributes, select **Object** as the search scope and enter a base DN matching the subject DN of the authenticated user—you can use variables from the

authentication source (an adapter or an authentication policy contract) or results from the previous lookup in the base DN to fulfill this requirement.

5. Repeat step 4 to add more attributes as needed.

### Example

#### Example

Suppose you want to map the `sn` Active Directory (AD) user attribute into an OpenID Connect policy. The users for this use case reside under a specific container on your directory server, `OU=West, DC=example, DC=com`.

On the **LDAP Directory Search** window, enter `OU=West, DC=example, DC=com` as the base DN, keep the default **Search Scope** value (**Subtree**), select **<Show All Attributes>** from the **Root Object Class** list, select the `sn` AD user attribute, and click **Add Attribute**.

#### Defining encoding for binary attributes

Use the **LDAP Binary Attribute Encoding Types** window to specify an encoding type to apply during fulfillment.

#### About this task

The **LDAP Binary Attribute Encoding Types** window appears when at least one attribute is configured as such in the datastore. Because you cannot use binary attribute data in an assertion to the service provider (SP), you must specify the encoding type that you want to apply during fulfillment. The available choices are **Base64**, **Hex**, and **SID**.



#### Note:

Defining encoding for binary attributes is only applicable to identity provider (IdP) and IdP-to-SP bridging use cases.

### Steps

To set an encoding type, select a value from the **Attribute Encoding Type** list.

Repeat this step for each binary attribute.

### Example

#### Examples

Microsoft Office 365 relies on an immutable Active Directory binary attribute associated with user accounts (`objectGUID`), and requires this binary data to be Base64-encoded to correlate provisioned federated user data to Active Directory accounts. Select **Base64** from the **Attribute Encoding Type** list.

Claims-based authentication with Microsoft Outlook Web App and Exchange admin center (EAC) requires `tokenGroups` (another binary attribute in Active Directory) to be SID-encoded. Select **SID** from the **Attribute Encoding Type** list.

## Entering a directory search filter

You can use a filter in PingFederate to query your selected data and retrieve a record associated with it.

About this task

On the **LDAP Filter** window, enter a filter for PingFederate to query the data you selected. The filter is in the form:

```
attribute1=value1
```

The left side (*attribute1*) is an attribute from your directory.



### Tip:

To see a list of attributes, click the **View List of Available LDAP Attributes** link.

The right side (*value1*) is the match-against value, generally a variable passed in from either an authentication source for an identity provider (IdP) or an assertion for a service provider (SP). The variables are shown underneath the **Filter** text field. If you are retrieving attributes from multiple data stores using one mapping, attributes available from other sources, if previously configured, are listed near the bottom of the window.

You can also apply additional search criteria by using other attributes from the target object class.

A filter narrows a search to locate requested data by either including or excluding specific records. A filter includes the attributes in the search and the value or range of values that the search is attempting to match. Searches are conducted by using three components: at least one attribute (attribute data type) on which to search, a search filter operator that will determine what to match, and the value of the attribute being sought.

## Steps

1. On the **LDAP Filter** window, enter a search filter in the text field.



### Tip:

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `${ and }` in the default value.

2. Ensure the syntax and variable names are correct. For general information about search filters, consult your directory documentation.
3. Click **Next** to complete the configuration to query attributes from the directory server.

Later in the workflow, you can use the attribute values returned from your directory server in the applicable contract fulfillment window, the issuance criteria window, or both, to fulfill your use case.

## Example

### Example

Suppose you want to locate user records by matching the **mail** Active Directory (AD) user attribute against an extended attribute, **em1**, in your access token contract for the purpose of mapping attributes to an OpenID Connect policy. As a passed-in variable from the access token, `${em1}` is shown underneath the **Filter** text field.

On the **LDAP Filter** window, enter the following filter in the **Filter** text field.

```
mail=${em1}
```

mail

An AD user attribute containing the email address of the user

`${em1}`

The value of the extended attribute (**em1**) in the access token contract



### Important:

You must use the `${}` syntax to retrieve the value of the enclosed variable.

## Specifying data source filters and fields

PingFederate lets you configure data source filters, fields, and other settings for your data store.

When configuring how PingFederate will retrieve attribute values from data stores, the procedures depend on the type of data store.

- [Specifying data source filters for REST API data stores](#) on page 405
- [Specifying a dynamic authorization header for a REST API data store](#) on page 406
- [Specifying filters and fields for a custom data store](#) on page 407

## Specifying data source filters for REST API data stores

On the **Configure Data Source Filters** window, you can specify a resource path for a REST API data store.

### Steps

1. On the **Attribute Sources & User Lookup** window, go to the **Configure Data Source Filters** tab.

IdP Adapters | Create Adapter Instance | Adapter Contract Mapping | Attribute Sources & User Lookup



Perform any filter configuration for the data source.

Populate filtering configuration

| Field Name           | Field Value  | Description  |
|----------------------|--|--|
| RESOURCE PATH        | <input type="text" value="/users?uid=\${username}"/>   | Optionally define the resource path appended to the base URL of the REST API data store. Relative URL paths, query strings and references to attributes in context of the transaction can be used to query for specific resources. For example, <code>/users?uid=\${username}</code> could be used to request a user object by username. |
| AUTHORIZATION HEADER | <input type="text"/>   | Optionally specify the bearer token to be used in an Authorization header that was received from earlier in the authentication flow (like in an OIDC IdP connection). For example, to use the access token from a Google OIDC IdP Connection specify "Bearer <code>\${idp.https://accounts.google.com.access_token}</code> "             |
| BODY                 | <input style="font-family: monospace;" type="text" value='{"login": "\${username}", "department": "\${departmentNumber}"}'/> | Optionally define the body sent on a GET or POST request to the REST API data store. The body should match the Content-Type header specified in the data store. For example, <code>{"login": "\${username}", "department": "\${departmentNumber}"}</code> could be used for a GET or POST JSON request.                                  |

- Optional: Enter a relative path, additional query parameters, or both in the **Resource Path** field.

**Tip:**

You can specify a default attribute value in the form of `${attributeName:-defaultValue}` to use at runtime when the attribute value is not available. Do not use `#{` and `}` in the default value.

- Optional: To use a previously-received bearer token in an authorization header, specify the bearer token in the **Authorization Header** field.
- Optional: Define the **Body** sent with a GET or POST request to the REST API datastore.

## Example

## Example

You have use cases that can leverage user attributes obtained through REST APIs. The data source returns user records in JSON. It also provides the following paths to access its data based on user populations:

- https://rest.example.com/development/users
- https://rest.example.com/staging/users

To retrieve the record of a particular user, the request must include the `uid` query parameter with the identifier of the user.

Your use cases focus on users under the `/staging/users` path. Your authentication policy uses the HTML Form Adapter, which captures user identifiers using the `username` attribute.

To address this sample use case:

- Create a REST API datastore with a base URL of `https://rest.example.com`.
- Add the REST API datastore as an attribute source in the applicable use cases, such as a service provider (SP) connection that uses an HTML Form Adapter instance or an OAuth identity provider (IdP) Adapter Mapping configuration that maps from an HTML Form Adapter instance into the persistent grants.
- When prompted to configure the filtering option on the **Configure Data Source Filters** window, enter `/staging/users?uid=${username}` in the **Resource Path** field.

**Specifying a dynamic authorization header for a REST API datastore**

When you configure an Open ID Connect identity provider (IdP) connection with an application, you can use the access token from the connection as a bearer token in an authorization header to receive additional information as needed.

## Before you begin

- Create a Service Provider Open ID Connect IdP connection.
- Configure an Identity Provider authentication policy for the connection.

## Steps

- Make the Open ID Connect call to the application to obtain the access token that you plan to use as a bearer token.

After you've made the connection, you can find the access token attribute name in `<pf_install>/pingfederate/log/server.log` in debug mode.

2. On the **Configure Data Source Filters** window, enter the access token attribute name in the **Authorization Header** field.

**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `${` and `}` in the default value.

## Example

## Authorization Headers

**Authorization Header** entries are shown here for Yahoo and Google Open ID Connect IdP connections:

- For Yahoo: `Bearer $(idp.https://api.login.yahoo.com.access_token)`
- For Google: `Bearer $(idp.https://accounts.google.com.access_token)`

**Specifying filters and fields for a custom datastore**

PingFederate enables you to specify a filter/search query for your data source, then configure fields for your use case.

## About this task

Follow this path to set up attribute queries from a custom datastore.

## Steps

1. On the **Configure Data Source Filters** window, specify a filter, or search query, for your data source.  
This window display and the syntax of the filter depend on your developer's implementation of the PingFederate SDK.
2. On the **Configure Data Source Fields** window, select the fields applicable to your use case.  
These choices are supplied by the driver implementation. Select only those needed to fulfill your use case.

## Result

You can use the values returned from your data source in the applicable contract fulfillment window, the issuance criteria window, or both.

**Configuring failsafe options**

From the **Failsafe Attribute Source** window, you can enable the failsafe mapping or stop the single sign-on (SSO) transaction when all attribute sources fail to return values for any reason.

## About this task

When a datastore is configured and the attribute mappings under **Attribute Sources & User Lookup** fail to complete the attribute contract in a service provider (SP) connection, you can choose to configure a set of failsafe **Attribute Contract Fulfillment** mappings. For example, you might configure a set of attributes to identify the SSO subject as a guest user at the SP.

**Note:**

The **Failsafe Attribute Source** window does not appear if you have selected the **Retrieve additional attributes from multiple data stores using one mapping** option on the **Mapping Method** window.

**Important:**

The attribute contract is fulfilled using either the mapping configured under **Attribute Sources & User Lookup** or the failsafe mapping, not both. In other words, you cannot use the failsafe mapping to fill in missing attributes when some are found with the datastore mapping setup but others are not.

The failsafe mapping is used only when all of the mappings configured in the datastore setup fail to return values for any reason. If any mapping succeeds (an attribute mapped to text, for example), failover does not occur.

Alternatively, you can have PingFederate stop the SSO transaction. This choice depends on your agreement with the SP.

**Steps**

- To enable the failsafe mapping, select **Send user to SP using default list of attributes**, and then map or enter the desired values on the **Attribute Contract Fulfillment** window.
- To stop the SSO transaction, select **Abort the SSO transaction**.

**Reviewing datastore query configurations**

You can review the configuration on the **Summary** window to determine whether to change your configuration, save those changes, or discard them.

**Steps**

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## IdP-to-SP bridging

---

The IdP-to-SP bridging links on the Server Configuration menu provide access to advanced federation settings.

### Adapter-to-adapter mappings

PingFederate can act as both identity provider (IdP) and service provider (SP) running on the same server with this configuration.

This configuration is provided for special use cases in which PingFederate is acting as both an IdP and an SP, and user attributes from an IdP adapter are used to create an authenticated session with an SP adapter on the same PingFederate server. Generally, these cases involve software-as-a-service (SaaS) providers who might not support standards-based single sign-on (SSO) but do provide proprietary SSO with “delegated authentication”, such as Salesforce and Workday.

In effect, this configuration provides an alternative to setting up complete connections to send SAML assertions and other messages back and forth between an IdP and an SP running on the same PingFederate server in a loop-back configuration to enable nonstandard use cases. Instead, attributes that would normally be sent in an assertion are mapped directly from the IdP authentication adapter to an SP adapter, resulting in a secure SP user session.



To use this configuration, ensure that you have already configured the required IdP and SP adapter instances. You can reuse instances that are also in use for connection configurations.

### Managing mappings

Manage adapter-to-adapter mappings using the **Adapter-to-Adapter Mappings** window to control how many you use in PingFederate.

About this task

On the **Adapter-to-Adapter Mappings** window you can add, modify, or delete adapter-to-adapter mappings. The **Adapter-to-Adapter Mappings** window is located at **Applications # Integration # Adapter-to-Adapter Mappings**.

Steps

- To add a mapping, select an identity provider (IdP) adapter instance from the **Source Instance** list, a service provider (SP) adapter instance from the **Target Instance** list, and then click **Add Mapping**.



#### Note:

You can create only one mapping of a source to the same target. However, you can map different sources to the same target, and the reverse.

- To edit a mapping, select the mapping and then follow the configuration wizard to complete the task.
- To remove a mapping, select **Delete** under **Action** for the mapping.

### Assigning a license group

Select a license group if your PingFederate license manages connections by groups.

About this task

Adapter-to-adapter mapping is considered a connection for licensing purposes.



#### Note:

This window is not displayed for unrestricted or other types of licenses.

Steps

- Select the license group from the list.

### Identifying the target application

On the **Target App Info** tab, you can enter the name of the target application and the URL of the application icon.

About this task

The URL is accessible through the IdP Adapter interface, `IdpAuthenticationAdapterV2`, in the PingFederate Java SDK. For more information about the SDK, see [SDK Developer's Guide](#) on page 1115. Both fields are optional.



#### Note:

If this is a child instance, select the **Override** check box to modify the configuration.

## Steps

1. Optional: Enter the application name in the **Application Name** field.
2. Optional: Enter the URL to the application icon in the **Application Icon URL** field.
3. Click **Next**.

### Configuring attribute sources and user lookup for adapter-to-adapter mappings

To look up attributes and to set up search parameters, configure or modify attribute sources to configure one or more datastores.

#### About this task

Attribute sources are specific datastore or directory locations containing information possibly required to fulfill the service provider (SP) adapter contract.

## Steps

- To configure an attribute source, click **Add Attribute Source** and complete the setup steps (see [Choosing a datastore](#) on page 398).
- To modify an attribute source configuration, select the attribute source and follow the configuration wizard to complete the task.



#### Note:

Depending on what you change, you might need to modify dependent data in subsequent steps, as indicated.

### Configuring target application information

Optionally, you can specify the name and the icon URL of the target application in the **Target App Info** tab.

## Steps

1. Enter the target application's name and icon URL.
2. Click **Next**.

### Configuring contract fulfillment for adapter-to-adapter mappings

Use one of the listed sources to map each attribute to fulfill the adapter contract.

#### About this task

The next step in this configuration is to map values from the identity provider (IdP) adapter into the attributes required by the service provider (SP) adapter (the adapter contract).

On the **Adapter Contract Fulfillment** tab, map each attribute to fulfill the adapter contract from one of these sources:

#### Adapter

When you make this selection, the associated **Value** drop-down list is populated by the IdP adapter.

#### Context

Values are returned from the context of the transaction at runtime.



#### Note:

The HTTP Request selection is retrieved as a Java object rather than text. For this reason, OGNL expressions are more appropriate to evaluate and return values.

Choose **Expression** and then click **Edit** to enter an expression (see [Using the OGNL edit window](#) on page 230). If the **Expression** selection is not listed, then the feature is not enabled (see [Enabling and disabling expressions](#) on page 225). For syntax and examples, see sections under [Construct OGNL expressions](#) on page 226.

LDAP/JDBC/Other (when a datastore is used)

Values are returned from your datastore, if used. When you make this selection, the **Value** list is populated by the attributes from the datastore.

Expression (when enabled)

This option provides more complex mapping capabilities—for example, transforming incoming values into different formats (see [Attribute mapping expressions](#) on page 225). All of the variables available below for text entries are also available for expressions.

No mapping

Select this option to ignore the **Value** field, making the value selection unnecessary.

Text

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the IdP adapter, using the `${attribute}` syntax.

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the IdP adapter, using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using the following syntax.

```
${ds.attr-source-id.attribute}
```

where `attr-source-id` is the **Attribute Source ID** value (see [Choosing a datastore](#) on page 398) and `attribute` is any of the datastore attributes you select.

Steps

1. Select a source of the attribute under **Source** for each SP adapter contract attribute.
2. Specify an attribute under **Value** for each attribute.

### Configuring a default target URL (optional)

You can enter a URL in the **Default Target URL** field to override any **SP Default URL SSO** setting.

About this task

For more information, see [Configuring default URLs](#) on page 719.



#### Note:

If specified, the adapter-to-adapter endpoint parameter tab, enter your default URL into the the **TargetResource** overrides any default target URL for an adapter-to-adapter mapping. See If specified, the adapter-to-adapter endpoint parameter [System-services endpoints](#) on page 1269.

## Steps

1. On the **Default Target URL** tab, if specified, the adapter-to-adapter endpoint parameter tab, enter your default URL into the **Default Target URL** tab.



### Note:

This URL overrides any setting within the **SP Default URL SSO** field.

2. Click **Next**.

## Defining issuance criteria for adapter-to-adapter mappings

You can define the criteria that must be satisfied for PingFederate to further process a request.

### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. On the **Issuance Criteria** tab, from the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source         | Description  |
|----------------|--|
| <b>Adapter</b> | Select to evaluate attributes from the IdP adapter instance.                           |
| <b>Context</b> | Select to evaluate properties returned from the context of the transaction at runtime. |

### Note:

The **HTTP Request** context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values.

| Source  | Description  |
|---|--|
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source. |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.                  |

- From the Attribute Name list, select the attribute to be evaluated.
- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

Error results are handled in one of the two ways.

Redirect

When an **InErrorResource** URL is provided, the value of the **Error Result** field is used by the query parameter **ErrorDetail** in the redirect URL.

Template

When an **InErrorResource** URL is not provided, the value of the **Error Result** field is used by the variable `$errorDetail` in the `idp.sso.error.page.template.html` template file.

Using an error code in the **Error Result** field allows the error template or an application to process the code in a variety of ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

6. Click **Add**.
7. Optional: Repeat to add more criteria.
8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing the adapter-to-adapter mapping

Use the **Summary** tab to edit, save, and discard changes to your configuration of an adapter-to-adapter mapping.

About this task

When you have finished configuring an adapter-to-adapter mapping, you can review the configuration on the **Summary** tab.

Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

### Token translator mappings

Use the token translator configuration to map incoming user attributes from an identity provider (IdP) token processor directly to a service provider (SP) token generator.

This configuration is provided for use cases in which the PingFederate WS-Trust STS exchanges one type of security token for another without needing to generate a SAML token in between. See [WS-Trust STS](#) on page 80. Use this configuration, for example, to convert a user's Kerberos token to a third-party proprietary web access management (WAM) session token.

In effect, this configuration provides an alternative to setting up complete STS connections to make such an exchange using the same instance of PingFederate. Instead, incoming user attributes from an IdP token processor are mapped directly to an SP token generator.

To use this configuration, ensure that you have enabled both the IdP and SP roles for PingFederate, including the WS-Trust protocol. See [Enabling the WS-Trust protocol](#) on page 1041. Make sure to configure the required token-translator instances. You might reuse instances that are also in use for STS connection configurations.

### Managing token mappings

Use the **Token Generator Mappings** window to manage your token-to-token mappings.

About this task

On the **Applications # Token Exchange # Token Translator Mappings** window you can add, modify, or delete token-to-token mappings.

Steps

- To add a mapping, select a token processor instance from the **Source Instance** list and a token generator instance from the **Target Instance** list, and then click **Add Mapping**.



#### Note:

You can create only one mapping of a source to the same target. However, you can map different sources to the same target, and vice versa. When you configure multiple identity provider (IdP) token processors, service provider (SP) token generators, or both, you must provide the **TokenProcessorId**, the **TokenGeneratorId** query parameters, or both, in the request (see [System-services endpoints](#) on page 1269).

- To edit a mapping, select the mapping and then follow the configuration wizard to complete the task.
- To remove a mapping, select **Delete** under **Action** for the mapping.

### Configuring attribute sources and user lookup for token mapping

Configure one or more datastores using this optional adapter-to-adapter configuration to look up attributes and to set up search parameters to find information needed to fulfill contracts.

About this task

Attribute sources are specific datastore or directory locations containing information that you might require to fulfill the contract of the token generator.

Steps

- To configure an attribute source, click **Add Attribute Source** and complete the setup steps. For more information, see [Choosing a datastore](#) on page 398.
- To modify an attribute source configuration, select the attribute source and follow the configuration wizard to complete the task.



#### Note:

Depending on what you change, you might need to modify dependent data in subsequent steps, as indicated.

## Configuring contract fulfillment for token exchange mapping

Use the listed sources to map values from the token processor into the attributes required by the token generator, the Token Generator Contract.

### About this task

Map each attribute to fulfill the Token Generator Contract from one of these sources:

#### Token

When you make this selection, the associated **Value** drop-down list is populated by the token processor.

#### LDAP/JDBC/Other (when a datastore is used)

Values are returned from your datastore, if used. When you make this selection, the **Value** list is populated by the attributes from the datastore.

#### Expression (when enabled)

This option provides more complex mapping capabilities—for example, transforming incoming values into different formats (see [Attribute mapping expressions](#) on page 225). All of the following variables available for text entries are also available for expressions.

#### No Mapping

Select this option to ignore the **Value** field, making it necessary to have no value selection.

#### Text

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the token processor, using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using the following syntax.

```
${ds.attr-source-id.attribute}
```

where `attr-source-id` is the **Attribute Source ID** value (see [Fulfillment by datastore queries](#) on page 397) and `attribute` is any of the datastore attributes you select.

### Steps

1. Under **Source**, select a source of the attribute for each attribute in the contract of the token generator.
2. Under **Value**, specify an attribute for each attribute.

## Defining issuance criteria for token translator mapping

Use the PingFederate issuance criteria features to process requests based on individual attributes.

### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-**



**value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

### Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source  | Description   |
|---|---|
| Context   | Select to evaluate properties returned from the context of the transaction at runtime. <div data-bbox="574 821 1472 1024" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The <b>HTTP Request</b> and <b>STS SSL Client Certificate Chain</b> context values are retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.   |
| Token   | Select to evaluate attributes from the token processor instance.  |

2. Select the attribute to evaluate under **Attribute Name**.



**Note:**

To evaluate the **STS Basic Authentication Username**, **STS SSL Client Certificate Chain**, or **STS SSL Client Certificate's Subject DN** context value, ensure that the associated authentication is enabled and configured on **System # Server # Protocol Settings** to open the **WS-Trust STS Settings** window.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.



**Note:**

To evaluate the **STS SSL Client Certificate's Subject DN** context value, you must select one of the ... **DN** conditions. These methods normalize the DN before comparison to accommodate for different string representations that are still considered equivalent, such as case sensitivity or white space.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The **Error Result** field is used by the `faultstring` element for SOAP 1.1 and the **Reason/Text** element for SOAP 1.2. For more information on SOAP, see the World Wide Web Consortium's [http://www.w3.org/TR/2000/NOTE-SOAP-20000508/#\\_Toc478383507](http://www.w3.org/TR/2000/NOTE-SOAP-20000508/#_Toc478383507).

Using an error code in the **Error Result** field allows an application to process the code in a variety of ways, such as display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

**Reviewing the token exchange mapping**

Use the **Summary** tab to modify a configuration and then either save, edit, or discard the changes.

## About this task

When you finish configuring a token exchange mapping, you can review the configuration on the **Summary** tab.

## Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

## Identity provider SSO configuration

---

Identity providers (IdP) can use the PingFederate administrative console to configure local application-integration information and to manage connections to service provider (SP)-partner sites.

You only need one connection per partner, even if you are targeting more than one web application at the destination SP site.

While your entity ID is defined on the **Federation Info** tab of the **Protocol Settings** window, you can identify your organization differently using virtual server IDs on a per-connection basis. For more information, see [Multiple virtual server IDs](#) on page 115.

You can deploy an SP connection to bridge a service provider to one or more identity providers through authentication policy contracts. For more information, see [Federation hub use cases](#) on page 108.

**Note:**

This topic applies to configuration settings needed for browser-based single sign-on (SSO). If you are using PingFederate exclusively as a security token service (STS), start with [WS-Trust STS configuration](#) on page 1041.

## IdP application integration settings

PingFederate uses identity provider (IdP) adapters to look up session information and authenticate users in integrated applications.

The integration of local applications with PingFederate is the essential "first-mile" configuration that allows end-users to access protected resources across domains. This process is facilitated through the use of application-integration kits and a robust SDK (see [Bundled adapters and authenticators](#) on page 65).

PingFederate uses IdP adapters such as the **HTML Form Adapter** to authenticate users at your site through applications or access-management systems. Go to **Authentication # Integration # IdP Adapters** to configure instances of IdP adapters.

For authentication sources and selectors that are capable of delegating end-user interactions to external web applications, you can create authentication applications to represent them.

You can also set a default URL to which users can be directed during single logout (SLO), and you can look up system endpoints that application developers at your site need to access PingFederate's single sign-on (SSO) and SLO services.



### Note:

If your PingFederate configuration enables the WS-Trust security token service (STS), the selections under **Integration** also include menu items for configuring plugin **Token Processors** and optionally **STS Request Parameters**, see [IdP configuration for STS](#).

## Managing IdP adapters

You must configure at least one instance of an identity provider (IdP) adapter to set up connections to service provider (SP) partners to manage and view your IdP adapter in the **IdP Adapters** window.

### About this task

An IdP adapter looks up session information and provides user identification to PingFederate. PingFederate comes bundled with the PingID integration kit and the following adapters:

- Composite Adapter
- HTML Form IdP Adapter
- HTTP Basic IdP Adapter
- Identifier First Adapter
- Kerberos Adapter
- OpenToken IdP Adapter
- Passthrough IdP Adapter
- PingID Adapter
- PingOne Fraud Adapter
- PingOne MFA Adapter
- PingOne Protect Adapter
- PingOne Verify Adapter
- Reference ID IdP Adapter
- X.509 Certificate IdP Adapter

Additional integration kits are available on the PingFederate [download page](#) on the **Add-ons** tab.

### Steps

1. Go to **Authentication # Integration # IdP Adapters**.

2. In the **IdP Adapters** window, choose from the following options.

| Option  | Description  |
|---|--|
| <b>Configure a new instance</b>               | Click <b>Create New Instance</b>   |
| <b>Modify an existing instance</b>            | Click the name of instance in the <b>Instance Name</b> column              |
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |



**Note:**

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

### Creating an IdP adapter instance

To create an adapter instance, you must choose an adapter type.

#### Steps

- On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

### Configuring an IdP adapter instance

You can configure existing instances of identity provider (IdP) adapters.

#### About this task

Depending on the selected adapter, the **IdP Adapters** window presents different configuration parameters.

#### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. Click the IdP adapter instance you want to configure.

3. Follow the in-product instructions to configure the adapter instance.

**Note:**

If this is a child instance, select the **Override** check box to modify the configuration.

If you are configuring one of the bundled adapters, see [Bundled adapters](#) on page 299 or [Integrate with PingID for PingFederate SSO](#) for configuration information.

If you are configuring an adapter from an integration kit, including any software as a service (SaaS) connector, go to [Integration overview](#) on page 65, locate the adapter's documentation, and configure the adapter instance accordingly.

**Invoking IdP adapter actions**

You can write identity provider (IdP) adapters to fulfill a variety of functions.

About this task

You can write adapters to:

- Provide configuration assistance
- Perform validation actions
- Generate parameters that might need to be set manually in a configuration file

Steps

- Follow the on-screen instructions to complete the actions required.

**Extending an IdP adapter contract**

You can use the **Extended Contract** tab to extend the contract of existing identity provider (IdP) adapters, especially those using the Composite Adapter.

About this task

If you are using the Composite Adapter, you must add attributes from the IdP adapter instances that comprise the composite configuration in this tab. For more information, see [Composite Adapter](#) on page 300.

If the adapter doesn't return values for the extended attributes, or if you prefer to fulfill them differently using datastore queries, dynamic text values, or results from OGNL expressions, you can define their fulfillment on the **Adapter Contract Mapping** tab. For more information, see [Defining the IdP adapter contract](#) on page 424.

**Note:**

If this is a child instance, select the **Override** check box to modify the configuration.

Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. Click the name of the IdP adapter instance you want to modify.
3. On the **Create Adapter Instance** window, select the **Extended Contract** tab.
4. For each attribute that you want to add, enter the name of the attribute under **Extend the Contract** and click **Add**.
5. Click **Save**.

## Setting pseudonym and masking options

You can set pseudonym and masking options to uniquely identify a user to your PingFederate SP partners.

### Steps

1. Go to **Authentication # Integration # IdP Adapters** and click the identity provider (IdP) adapter instance that you want to change.
2. On the **Adapter Attributes** tab, do the following:
  - a. Optional: From the **Unique User Key Attribute** list, select an attribute to uniquely identify users signing on with this adapter.

The attribute's value is used to identify user sessions across all adapters. **None** is selected by default.

#### **Note:**

If you choose a custom user key attribute, uses the value of the attribute after the Adapter Contract Mapping (if any) has been evaluated. If you choose a custom user key attribute that is based on the username, configure the adapter's password credential validators to trim spaces.

#### **Important:**

For the HTML Form Adapter, If you enabled the **Revoke Sessions after Password Change or Reset** option on the **IdP Adapter** tab, you cannot select **None** as the unique user key attribute. Doing so results in an error message.

- b. Select the check box under **Pseudonym** for the user identifier of the adapter and optionally for the other attributes, if available.

This selection is used if any of your service provider (SP) partners use pseudonyms for account linking.

#### **Note:**

A selection is required whether or not you use pseudonyms for account linking. This allows account linking to be used later without having to delete and reconfigure the adapter. Ensure that you choose at least one attribute that is unique for each user, such as a user's email, to prevent assigning the same pseudonym to multiple users.

- c. Select the check box under **Mask Log Values** for any attributes whose values you want to mask in its logs at runtime.

#### **Note:**

Masking is not applied to the unique user key attribute in the logs even though the attribute used for the key is marked as **Mask Log Values**.

- d. Select the **Mask all OGNL-expression generated log values** check box if OGNL expressions might be used to map derived values into outgoing assertions and you want those values masked.

## Defining the IdP adapter contract

You can modify the default identity provider (IdP) adapter contract settings using the **Adapter Contract Mapping** tab.

About this task

An IdP adapter contract is a contract that can be used to fulfill the attribute contract passed to your service provider (SP) partners. By default, PingFederate fulfills the IdP adapter contract with attribute values from the adapter.

You can optionally configure PingFederate to fulfill the IdP adapter contract with:

- Attribute values from local datastores
- Dynamic text values
- Results from OGNL expressions
- A combination of any of these

In addition, you can verify requests using the token authorization framework.

Steps

1. Go to **Authentication # Integration # IdP Adapters**
2. Click the **Instance Name** of the existing IdP adapter instance you want to configure.
3. Go to the **Adapter Contract Mapping** tab.



### Note:

If this is a child instance, select the **Override Adapter Contract** check box to modify the configuration unless you have already selected the override option on the **Extended Contract** tab, in which case the **Override Adapter Contract** check box is automatically selected for you.

4. Click **Configure Adapter Contract**.
  - For information on **Attribute Sources & User Lookup**, see [Defining attribute sources and user lookup](#) on page 424.
  - For information on **Adapter Contract Fulfillment**, see [Configuring IdP adapter contract fulfillment](#) on page 425.
  - For information on **Issuance Criteria**, see [Defining issuance criteria for IdP adapter contract](#) on page 427.
5. On the **Summary** tab, click **Done** to save your adapter contract configurations, or click **Cancel** to discard them.

### *Defining attribute sources and user lookup*

In the **Attribute Sources & User Lookup** window, you can add new attribute sources or manage existing attribute sources to supply attributes for the identity provider (IdP) adapter contract or the token authorization framework.

About this task

Attribute sources are specific datastore or directory locations containing information that might be needed for the IdP adapter contract or the token authorization framework. You can use more than one attribute source when mapping values to the IdP adapter contract.

For more information about token authorization, see [Token authorization](#) on page 105.

The IdP server supports separate datastores to look up attributes for a single mapping. For example, you can query multiple datastores for values and map those values in one mapping, or query a datastore for a value and use that value as input for subsequent queries of other datastores.



Queries are executed in the order they are displayed on the **Attribute Sources & User Lookup** tab. Use the up and down arrows as needed to adjust the order.



**Note:**

If a required attribute, such as the user identifier `username` for the HTML Form Adapter or `subject` for the OpenToken IdP Adapter, cannot be fulfilled, the request fails.

Steps

1. Go to **Authentication # Integration # IdP Adapters**
2. Click the name of the existing IdP adapter instance you want to configure in the **Instance Name** list.
3. Click the **Adapter Contract Mapping** tab.



**Note:**

If this is a child instance, select the **Override Adapter Contract** check box to modify the configuration unless you have already selected the override option in the **Extended Contract** tab, in which case the **Override Adapter Contract** check box is automatically selected for you.

4. Click **Configure Adapter Contract**.  
Choose from:
  - If your use case requires only dynamic texts or results from OGNL expressions without any attributes from local datastores, skip to [Configuring IdP adapter contract fulfillment](#) on page 425.
  - To add an attribute source, click **Add Attribute Source**.
  - To modify an existing instance, select it by name under **Description**.
  - To remove an existing instance or to cancel the removal request, click **Delete** or **Undelete** under **Action**.

*Configuring IdP adapter contract fulfillment*

You can map values into the identity provider (IdP) adapter contract using the **Adapter Contract Fulfillment** tab.

Steps

1. Go to **Authentication # Integration # IdP Adapters**
2. Click the **Instance Name** of the existing IdP adapter instance you want to configure.
3. Go to the **Adapter Contract Mapping** tab.




**Note:**

If this is a child instance, select the **Override Adapter Contract** check box to modify the configuration unless you have already selected the override option in the **Extended Contract** tab, in which case the **Override Adapter Contract** check box is automatically selected for you.

4. Click **Configure Adapter Contract**.
5. Select a source in the **Source** list and specify a **Value** to associate with it.

For more information about the **Source** list and the possible **Values**, see the following table.

| Source  | Description   |
|---------|---|
| Adapter | Select <b>Adapter</b> to use the attribute value returned by the IdP adapter without customization. |

| Source   | Description  |
|--|--|
| <b>Context</b>   | Select <b>Context</b> to return specific information from the request.   |
| JDBC, LDAP, or other types of datastores (if configured) | <p>Select an attribute source when PingFederate should retrieve attribute value from a datastore.</p> <p>When you make this selection, the <b>Value</b> list is populated with attributes from your database, directory, or other datastore.</p> <p>Applicable only if you have added at least one attribute source on the <b>Attribute Sources &amp; User Lookup</b> tab. For more information, see <a href="#">Defining attribute sources and user lookup</a> on page 424.</p>   |
| <b>Expression</b> (if enabled)                           | <p>Select <b>Expression</b> to support complex mapping requirements; for example, transforming incoming values into different formats. Additionally, the HTTP request is retrieved as a Java object instead of text. For this reason, select <b>Expression</b> as the source and use OGNL expressions to evaluate and return specific information from the HTTP request.</p> <p>Applicable only if you have enabled the use of expressions in PingFederate. For more information, see <a href="#">Attribute mapping expressions</a> on page 225.</p>   |
| <b>No Mapping</b>  | Select <b>No Mapping</b> to ignore the <b>Value</b> field.   |
| <b>Text</b>  | <p>Select <b>Text</b> to return the value you enter under <b>Value</b>.</p> <p>There are a variety of reasons to use a static text value. For example, if the target web application provides a service based on the name of your organization, you can provide the attribute value as a constant.</p> <p>You can mix text with references to attributes from the IdP adapter contract by using the <code>\${attribute}</code> syntax.</p> <p>You can also enter references to attributes from configured attribute sources by using the <code>\${ds.attr-source-id.attribute}</code> syntax, where <code>attr-source-id</code> is the <b>Attribute Source ID</b> value you entered on <b>Attribute Sources &amp; User Lookup # Data Store</b> and <code>attribute</code> is an attribute from the datastore. For more information, see <a href="#">Defining attribute sources and user lookup</a> on page 424.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>You can reference attribute values in the form of <code>\${attributeName:-defaultValue}</code>. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use <code>{</code> and <code>}</code> in the default value.</p> </div> |

6. Repeat these steps until all attributes are configured.
7. Click **Done**.

### Defining issuance criteria for IdP adapter contract

You can manage criteria that PingFederate evaluates to determine whether to issue an identity provider (IdP) adapter contract token for a user.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



#### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

#### Steps

1. Go to **Authentication # Integration # IdP Adapters**.
2. Click the name of the existing instance you want to change in the **Instance Name** list.
3. Click **Adapter Contract Mapping # Configure Adapter Contract # Issuance Criteria**.
4. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>Adapter</b>   | Select to evaluate attributes from the IdP adapter instance.  |
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.  |
|  | <div data-bbox="574 1562 620 1604" data-label="Image"> </div> <div data-bbox="623 1575 698 1604" data-label="Section-Header"> <h4>Note:</h4> </div> <div data-bbox="568 1621 1417 1715" data-label="Text"> <p>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |

| Source                   | Description                               |
|--------------------------|---|
| <b>Mapped Attributes</b> | Select to evaluate the mapped attributes. |

5. In the **Attribute Name** list, select the attribute to be evaluated.
6. In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

7. In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

8. In the **Error Result** field, enter a custom error message.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

9. Click **Add**.
10. Optional: Repeat to add more criteria.

11. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

#### Reviewing an IdP adapter contract

On the **Create Adapter Instance** window's **Summary** tab, review the adapter contract.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### Reviewing and saving an IdP adapter configuration

Review your identity provider (IdP) configuration and save your changes on the **Summary** tab.

#### Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

#### Authentication applications and the authentication API

The PingFederate authentication API is a JSON-based API that enables end-user interactions, such as credential prompts, to be handled by an external web application. This API does so by providing access to the current state of the flow as an end user steps through a PingFederate authentication policy.

Authentication flows are initiated through browser-based single sign-on (SSO) application endpoints, such as `/idp/startSSO.ping`, or a protocol request, such as an OpenID Connect authentication request received at the authorization endpoint: `/as/authorization.oauth2`. As PingFederate runs the configured authentication policy, if it encounters an API-capable adapter or selector, and an authentication application is configured for the policy, PingFederate redirects to the authentication application's URL, passing the ID of the flow in the `flowId` query parameter.

The authentication application can then retrieve the current state of the flow by issuing a **GET** request to the `/pf-ws/authn/flows/{flowId}` endpoint. The `_links` field in the response lists the available

authentication actions that can be performed from the current state. To invoke an action, the authentication application sends a **POST** request to the `/pf-ws/authn/flows/{flowId}` endpoint.

The API client can choose authentication actions using either an **action** query parameter or a custom content type. The **action** query parameter should be used when your networks block custom content types, and is specified using the following format:

```
/pf-ws/authn/flows/<flowId>?action=<actionID>
```

For example, to check username and password, pass the `checkUsernamePassword` action ID through the query parameter as follows:

```
/pf-ws/authn/flows/<flowId>?action=checkUsernamePassword
```

For the custom content type, the action ID is specified using the Content-Type HTTP request header in the following format:

```
application/vnd.pingidentity.<actionId>+json
```

For example, to indicate a username and password check from the HTML Form Adapter, specify the following:

```
application/vnd.pingidentity.checkUsernamePassword+json
```

When the application invokes an action, PingFederate responds either with the next state for the flow or an error.

When the user completes the authentication policy steps successfully, the authentication API returns a **RESUME** status to the authentication application. This status indicates that the API client should redirect the user's browser to the `resumeUrl` specified in the response. PingFederate will then be responsible for the final step in the flow, such as passing a SAML assertion to a partner. A **RESUME** status will also be sent if PingFederate encounters an identity provider (IdP) connection in the policy tree, or an IdP adapter or selector that is not API-capable. When the API client redirects the user, PingFederate will take the steps needed to invoke the authentication source.

If the user has interacted with an authentication application and the flow terminates with an error, the API client will receive a **FAILED** status from the API.

Authentication applications must be highly trusted.



**Note:**

To avoid issues with third-party cookies in some browsers, give the authentication application the same parent domain as the PingFederate base URL.

## Key concepts

### Flow

The SSO transaction invoking the authentication API.

### States

The available states (if any) for a given API-enabled adapter or selector.

### Current state

Indicates what the adapter or selector is ready to do next.

### Actions

The available actions (if any) for a given state.

### Default authentication application

In addition to specifying an authentication application for each policy, you can also configure a default application. PingFederate uses the default application if it encounters an API-capable adapter outside of a policy tree. For example, the default application activates if the user navigates to the Change Password endpoint, `/ext/pwdchange/Identify`, or the Account Recovery endpoint, `/ext/pwdreset/Identify`. PingFederate also uses the default application if authentication policies are disabled, or if the flow falls through to a default authentication source.

### Managing authentication applications

You can create and manage authentication applications that use the authentication API.

#### About this task

Authentication applications display user interfaces to collect credentials when authentication is completed through the PingFederate authentication API. The default authentication application is used for authentication sources that support the authentication API functionality and are invoked directly, rather than as part of an authentication policy.

#### Steps

1. To manage authentication applications, go to **Authentication # Integration # Authentication API Applications**.

### Authentication API Applications

Authentication Applications present user interfaces to collect credentials when authentication is completed via the Authentication API. The Default Authentication Application is used for Authentication Sources that are invoked directly (not as part of Authentication Policy) and that support the Authentication API.

- ENABLE AUTHENTICATION API
- ENABLE API EXPLORER
- RESTRICT ACCESS TO REDIRECTLESS MODE
- INCLUDE REQUEST CONTEXT IN API RESPONSES

DEFAULT AUTHENTICATION APPLICATION

Authentication API Explorer ▾

| Application Name ^          | Application ID            | Action                               |
|-----------------------------|---------------------------|--------------------------------------|
| Authentication API Explorer | QDa7gyNft8nsaBROGNnrT2Ye3 | Delete   <a href="#">Check Usage</a> |

Add Authentication Application

Cancel

Save

2. To toggle the availability of authentication API support, select or clear the **Enable Authentication API** check box.




**Note:**

The **Enable API Explorer**, **Restrict Access to Redirectless Mode**, and **Include Request Context in API Responses** check boxes are applicable and shown if the **Enable Authentication API** check box is selected.


| Option   | Description   |
|--|---|
| <p><b>Enable API Explorer</b></p>                      | <p>PingFederate includes an API Explorer that allows you to view the states, actions, and models available for the various API-capable adapters and selectors included in your PingFederate environment.</p> <p>The endpoint for the Authentication API Explorer is <code>/pf-ws/authn/explorer</code>. For more information, see <a href="#">Exploring the authentication API</a>.</p> <p>This check box is enabled by default.</p>  |
| <p><b>Restrict Access to Redirectless Mode</b></p>     | <p>It is strongly recommended to enable the <b>Restrict Access to Redirectless Mode</b> setting. If it is not enabled, authentication applications can use a user's existing session to obtain tokens for any public client defined in the deployment, that is any client with no authentication method defined.</p> <p>Enabling <b>Restrict Access to Redirectless Mode</b> ensures that authentication applications can only obtain tokens for the client specified in the application's settings. When you enable this setting, make sure to update authentication applications that use redirectless mode and specify the client that they are allowed to use.</p> <p>For more information on how to allow highly-trusted authentication applications to employ the PingFederate Authentication API, see <a href="#">Configuring authentication applications</a>.</p> <p><b>Restrict Access to Redirectless Mode</b> is enabled by default.</p> |
| <p><b>Include Request Context in API Responses</b></p> | <p>To pass single sign-on (SSO) request context parameters and tracked parameters to authentication applications, select the <b>Include Request Context in API Responses</b> check box.</p> <p>Enabling this feature allows authentication API clients to use the context of SSO requests to make decisions and change branding. When enabled, the authentication API response includes the <code>requestContext</code> parameter of</p>  |



| Option | Description   |
|--------|---|
|        | <p>type Map. The following parameters are included when they are relevant to the SSO transaction:</p> <p><b>pluginId</b><br/>The ID of the identity provider (IdP) adapter or the authentication selector</p> <p><b>entityId</b><br/>The ID of the service provider (SP) connection used in the SSO transaction</p> <p><b>applicationName</b><br/>The name of the SP connection or OAuth client used in the SSO transaction</p> <p><b>client_id</b><br/>The ID of the OAuth client used in the SSO transaction</p> <p><b>spAdapterId</b><br/>The ID of the SP adapter used in the SSO transaction</p> <p><b>oidcUiLocales</b><br/>The OIDC <code>ui_locales</code></p> <p><b>trackedHttpParams</b><br/>An array of the tracked HTTP parameters passed when processing authentication policies</p> <p><b>extendedProperties</b><br/>Passes defined extended properties to all applicable velocity templates and as a request context parameter in the authentication API</p> <div data-bbox="867 1377 1466 1745" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>Except for tracked HTTP parameters, these parameters do not include sensitive information. Whether tracked HTTP parameters include sensitive information depends on which parameters you choose to track in policies. For information about configuring tracked HTTP parameters, see <a href="#">Defining authentication policies</a> on page 254.</p> </div> |

3. In the **Default Authentication Application** section, perform any of the following actions.

| Option                                    | Action  |
|---|---|
| <b>Default Authentication Application</b> | Select an application from the list to designate as the default authentication application. |

| Option                                | Action   |
|---------------------------------------|--|
| <b>Check Usage</b>                    | Click to open a pop-up window listing the configurations in which the authentication is used.  |
|                                       |  <b>Note:</b><br>This is only available for the default authentication application. |
| <b>Add Authentication Application</b> | Click to add a new authentication application. See <a href="#">Configuring authentication applications</a> on page 434   |
| <b>Delete</b>                         | Click to remove an authentication application.   |

4. Click **Save**.

### Configuring authentication applications

You can let highly-trusted authentication applications employ the PingFederate Authentication API.

About this task

The following procedure describes how to use the **Authentication Application** window to integrate an authentication application with PingFederate.

The screenshot displays the PingFederate Administration Console interface. The top navigation bar includes the PingFederate logo and tabs for AUTHENTICATION, APPLICATIONS, SECURITY, and SYSTEM. The left sidebar shows a navigation menu with options: Integration, IdP Connections, IdP Adapters, Authentication API Applications (selected), and IdP Default URL. The main content area is titled 'Authentication API Applications | Authentication A' and contains the following configuration fields:

- NAME:** AuthnApp1
- DESCRIPTION:** Authentication API app
- URL:** https://localhost:9031/pf-ws/a
- ADDITIONAL ALLOWED ORIGINS:** (Empty field)
- ALLOW REDIRECTLESS MODE:**  Allow
- CLIENT FOR REDIRECTLESS MODE:** Client Credentials (JWT)



A 'Manage Clients' button is located at the bottom of the configuration area.

### Steps

1. Go to **Authentication # Integration # Authentication API Applications**.  
Choose from:
  - To integrate a new application, click **Add Authentication Application**.
  - To modify an existing application's settings, click the **Application Name**.

2. Provide information for each field.

For more information, see the following table.

| Field                               | Description   |              |                   |                             |   |                                  |  |                             |  |
|-------------------------------------|---|--------------|-------------------|-----------------------------|---|----------------------------------|--|-----------------------------|--|
| <b>Name</b>                         | The name of the authentication application.   |              |                   |                             |   |                                  |  |                             |  |
| <b>Description</b>                  | An optional description of the authentication application.  |              |                   |                             |   |                                  |  |                             |  |
| <b>URL</b>                          | The URL of the authentication application.  |              |                   |                             |   |                                  |  |                             |  |
| <b>Additional Allowed Origins</b>   | <p>Enter any number of trusted origins to enable cross-origin resource sharing (CORS) support for the authentication API endpoint.</p> <p>Once configured, client-side web applications from the trusted origins are allowed to make requests to the PingFederate authentication API endpoint. For more information about CORS, see <a href="#">W3C's recommendation on Cross-Origin Resource Sharing</a>.</p> <table border="1"> <thead> <tr> <th>Sample entry</th> <th>Expected behavior</th> </tr> </thead> <tbody> <tr> <td>https://<br/>www.example.com</td> <td>CORS requests originating from https://<br/>www.example.com are allowed.</td> </tr> <tr> <td>https://<br/>www.example.com:8080</td> <td>CORS requests originating from https://<br/>www.example.com:8080 are allowed.</td> </tr> <tr> <td>https://<br/>www.example.com</td> <td>CORS requests originating from https://<br/>www.example.com:&lt;any port&gt; are allowed.</td> </tr> </tbody> </table> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Given this sample entry, a port number is required in the <b>Origin</b> request header.</p> </div> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>Although using the wildcard character provides the convenience of allowing multiple origins with one entry, consider adding individual origins to limit CORS requests to a list of trusted hosts.</p> </div> <p>Click <b>Add</b> to save an entered origin. Repeat to add multiple origins.</p> | Sample entry | Expected behavior | https://<br>www.example.com | CORS requests originating from https://<br>www.example.com are allowed. | https://<br>www.example.com:8080 | CORS requests originating from https://<br>www.example.com:8080 are allowed. | https://<br>www.example.com | CORS requests originating from https://<br>www.example.com:<any port> are allowed. |
| Sample entry                        | Expected behavior   |              |                   |                             |   |                                  |  |                             |  |
| https://<br>www.example.com         | CORS requests originating from https://<br>www.example.com are allowed.   |              |                   |                             |   |                                  |  |                             |  |
| https://<br>www.example.com:8080    | CORS requests originating from https://<br>www.example.com:8080 are allowed.  |              |                   |                             |   |                                  |  |                             |  |
| https://<br>www.example.com         | CORS requests originating from https://<br>www.example.com:<any port> are allowed.  |              |                   |                             |   |                                  |  |                             |  |
| <b>Allow Redirectless Mode</b>      | <p>To allow the authentication application to use redirectless mode with a specified OAuth client, select this check box. Then select a <b>Client for Redirectless Mode</b>.</p> <p>This check box is not selected by default. It is visible only if the <b>Restrict Access to Redirectless Mode</b> check box on the <b>Authentication API Applications</b> window is selected. For more information, see <a href="#">Managing authentication applications</a> on page 431.</p>  |              |                   |                             |   |                                  |  |                             |  |
| <b>Client for Redirectless Mode</b> | <p>Select the OAuth client that will use this authentication application in redirectless mode. The client must allow authentication API redirectless mode. For more information, see <a href="#">Configuring OAuth clients</a> on page 566.</p> <p>This field is visible only if the <b>Allow Redirectless Mode</b> check box is selected.</p>  |              |                   |                             |   |                                  |  |                             |  |

3. To keep your configuration, click **Save** to or click **Cancel** to discard any changes made.

## Configuring a default URL and error message

As an identity provider (IdP), you can optionally prompt end users to confirm their single logout (SLO) requests and provide a default URL indicating a successful SLO to the end-user, if no other page is designated.

About this task

You can also customize an error message to be displayed as part of the error page rendered in the end-user's browser if an error occurs during IdP-initiated single sign-on (SSO). For example, you might consider modifying the default text to include useful information regarding whom the user should contact or what their next step should be.

Your application or your partner's application can supply the SLO URL at runtime. However, if none is provided, PingFederate will use the default value you enter on this window. For more information, see [IdP endpoints](#) on page 1250.

If you leave the default URL blank, PingFederate provides a built-in landing page for the user. This web page is among the templates you can modify with your own branding or other information. For more information, see [Customizable user-facing pages](#) on page 869).

Steps

1. Go to **Authentication # Integration # IdP Default URL**.
2. Select the check box to prompt the user to confirm SLO.
3. Enter a default URL to send the user to on successful SLO.
4. Enter a custom error message to display on unsuccessful SLO.



### Note:

The error message is displayed only when the application calling the start-SSO endpoint does not explicitly provide its own error page URL. The default entry in this field is used to localize the message. For information about how to use the PingFederate localization feature, see [Localizing messages for end users](#) on page 889. If localization is not needed, you can also specify a default message in this field.

5. Click **Save** to save your changes.

## Viewing IdP application endpoints

Web-application developers at your site need to know the application endpoints to initiate transactions through PingFederate.

Steps

- Go to **System # Endpoints # IdP Application Endpoints** to see a list of endpoints and descriptions applicable to your federation role.

These endpoints are built into PingFederate and cannot be changed.

For specific parameters required or allowed for these endpoints, see [IdP endpoints](#) on page 1250 and [System-services endpoints](#) on page 1269.

## IdP protocol endpoints

PingFederate provides a list of identity provider (IdP) protocol endpoints and exportable metadata for your configuration.

You can find a list of applicable SAML, WS-Federation, and WS-Trust STS endpoints in **System # Endpoints # IdP Endpoints**. The pop-up window displays only those endpoints related to the federation



protocols enabled on **System # Server # Protocol Settings # Federation Info**. These endpoints are built into PingFederate and cannot be changed.

Your federation partners or security token service (STS) clients need to know the applicable IdP services endpoints to communicate with your PingFederate server. Configured service endpoints for SAML connections are included in metadata export files.

PingFederate provides a favicon for all protocol endpoints. For more information, see [Customizing the favicon for application and protocol endpoints](#) on page 908.

The following table describes each endpoint.

| Service                                       | URL and Description   |
|---|---|
| <b>Single Logout Service (SAML 2.0)</b>       | <code>/idp/SLO.saml2</code><br>The URL that receives and processes logout requests and responses.   |
| <b>Single Sign-on Service (SAML 2.0)</b>      | <code>/idp/SSO.saml2</code><br>The SAML 2.0 implementation URL that receives authentication requests for processing.  |
| <b>Artifact Resolution Service (SAML 2.0)</b> | <code>/idp/ARS.ssaml2</code><br>The SOAP endpoint that processes artifacts returned from a federation partner to retrieve the referenced XML message on the back channel. See the note at the end of this table.  |
| <b>Attribute Query Service (SAML 2.0)</b>     | <code>/idp/attrsvc.ssaml2</code><br>The SAML implementation that receives and processes attribute requests. See the note at the end of this table.  |
| <b>Single Sign-on Service (SAML 1.x)</b>      | <code>/idp/isx.saml1</code><br>The SAML 1.x implementation of IdP intersite transfer service (ISX) to which clients are redirected for single sign-on (SSO) requests.   |
| <b>Artifact Resolution Service (SAML 1.x)</b> | <code>/idp/soap.ssaml1</code><br>The SOAP endpoint that processes artifacts returned from a federation partner to retrieve the referenced XML message on the back channel. See the note at the end of this table. |
| <b>Single Sign-on Service (WS-Federation)</b> | <code>/idp/prp.wsf</code><br>The WS-Federation implementation URL that receives and processes security-token requests and single log-out (SLO) messages.  |

| Service                             | URL and Description   |
|-------------------------------------|---|
| <b>WS-Trust STS (two endpoints)</b> | <p><code>/idp/sts.wst</code></p> <p>The SOAP endpoint that receives and processes security-token requests from STS clients (web service clients at the IdP site) to be exchanged for a SAML token based on the configured service provider (SP) connection.</p>   |
|                                     | <p><code>/pf/sts.wst</code></p> <p>Initiates direct STS token-to-token exchange and token validation from an IdP token processor to an SP token generator, when that feature is configured. For more information, see <a href="#">Token translator mappings</a> on page 414.</p>  |
|                                     | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If multiple token-processor instances of the same type are configured for the same connection or token-to-token mapping, a query parameter, <b>TokenProcessorId</b>, must be added to either of these endpoints. For more information, see <a href="#">Managing token processors</a> on page 1043.</p> </div> <p>See the note at the end of this table.</p> |
|                                     | <p> <b>Important:</b></p> <p>If mutual SSL/TLS is used for authentication, a secondary PingFederate listening port must be configured and used by partners or STS clients for the relevant endpoints—<code>*.ssaml*</code> and <code>*.wst</code>. For more information, see <a href="#">Configuring PingFederate properties</a> on page 820.</p>  |

Virtual server ID support

For SAML connections using multiple virtual server IDs, each virtual server ID has its own set of protocol endpoints. For more information, see [Multiple virtual server IDs](#) on page 115. You can export connection metadata for your partner from **System # Protocol Metadata # Metadata Export**. For more information, see [Exporting connection-specific SAML metadata](#) on page 932.

For WS-Federation (and SAML) connections using multiple virtual server IDs, you can provide your partner the federation metadata endpoint, `/pf/federation_metadata.ping`, with the **PartnerSpId** and **vsid** parameters, as in the following example.

| Partner's entity ID | Your virtual server ID | Federation metadata URL  |
|---------------------|------------------------|--|
| SP                  | idev1                  | <code>https://www.example.com/pf/federation_metadata.ping?PartnerSpId=SP&amp;vsid=idev1</code> |
|                     | idev2                  | <code>https://www.example.com/pf/federation_metadata.ping?PartnerSpId=SP&amp;vsid=idev2</code> |

In this example, the base URL and the runtime port of your PingFederate server are `www.example.com` and `443`, respectively.

When the request includes the **vsid** parameter, the federation metadata endpoint returns information that is specific for a given virtual server ID.

For WS-Trust STS, you can provide your partner the STS metadata endpoint `/pf/sts_mex.ping` with the **PartnerSpId** and **vsid** parameters. When the STS metadata request includes the **vsid** parameter, the STS metadata endpoint returns information that is specific for a given virtual server ID.

For more information about these metadata endpoints, see [System-services endpoints](#) on page 1269.



**Note:**

The virtual server ID concept does not apply to the `/pf/sts.wst` endpoint because token-to-token exchange does not involve any connections. As needed, you can pass the token-to-token endpoint to your partners as-is.

## SP connection management

As an identity provider (IdP), you manage connection settings to support the exchange of federation-protocol messages such as SAML, WS-Federation, or WS-Trust with a service provider (SP) or security token service (STS) client application at your site.

The settings your IdP manages include:

- User attributes that you expect to send in a single sign-on (SSO) token, including SAML assertions, WS-Trust STS SAML tokens, or WS-Federation JSON Web Tokens (JWT).
- User attributes that are sent using the SAML Attribute Query profile, if that profile is used. For more information, see [Configuring the Attribute Query profile in an SP connection](#) on page 480.
- The protocol, profiles, and bindings of the connection, including detailed security specifications such as the use of back-channel authentication, digital signatures, signature verification, and XML encryption

To establish a connection, you and your partner must decide this information in advance. For more information, see [Federation planning checklist](#) on page 113.

If your agreement includes sending assertions containing attribute values from local datastores, you must define the required datastores. For more information, see [Datastores](#) on page 936.

### Administrative interface

Manage connection settings using the **SP Affiliations** window, accessed from **System # Protocol Metadata**, which organizes the settings into a series of primary tasks.

Some primary tasks have one or more levels of sub task. Each primary or sub task has its own tab for managing one or more settings. You can move to a sibling task using the **Next** or **Previous** button. If you are on a sub task, you can also move to its parent task using the **Done** button.

When creating a new connection, you can save your progress using the **Save Draft** button. Not all windows offer this option. When you reach the **Activation & Summary** tab, you must click **Save** to complete the new connection.

When editing an existing connection, make changes and then click **Save** to commit your changes. You are not required to step through all window to reach the **Activation & Summary** window before you can save your changes.



**Note:**

The **Save** button is available on most tabs. If a window does not show a **Save** button, click **Next** or **Done** until you reach a window where you can use its **Save** button to commit your changes.



## Accessing SP connections

The **SP Connections** window lists all service provider connections and displays up to 20 connections at a time. As needed, you can use the pagination controls to navigate through your connections, narrow connections by protocol type or status, or search for connection by name or ID.

### About this task

A connection is included in the search results so long as its name or ID is a partial, case-insensitive match to a search term.

### Steps

- Go to **Applications # Integration # SP Connections**.
- To edit a connection, select the connection by its name. For the setting you want to make a change, select the corresponding window title and then follow the configuration wizard to complete the task.
- To create a connection, click **Create Connection** and follow the on-screen steps.
- To copy a connection, click **Select Action # Copy** and then follow the on-screen steps.

This is most useful if the new connection and the source connection share many common setting values.



#### Note:

PingFederate doesn't include outbound provisioning configurations in connection copies. For more information, see [Configuring outbound provisioning](#) on page 496.

- To export a connection, click **Select Action # Export Connection** and then save the XML file as prompted.

This is useful in situations where you want to make a backup of a connection prior to changing it.

- To import a connection, click **Import Connection**. For more information, see [Importing a connection](#) on page 442.

If the connection already exists, you have the option to overwrite the existing connection.



#### Note:

Prior to the import, you can modify the XML file to suit your needs. The XML file can also be imported to another PingFederate environment acting in the same federation role (IdP) at your site. The source and the target must run the same version of PingFederate.

- To export metadata for any SAML Browser SSO connection, click **Select Action # Export Metadata** and then follow the on-screen instructions.
- To update a SAML Browser SSO connection, click **Select Action # Update with Metadata**, then follow the on-screen instructions. For more information, see [Importing SP metadata](#) on page 447.

You can update a connection via a metadata XML file or a metadata URL.



#### Important:

The update operation might require additional configuration. Review the connection after the update operation.

- Click the toggle to enable or disable a connection.
- To remove a connection, click **Select Action # Delete**.

- To override the verbosity of runtime transaction logging for all SP connections, click **Show Advanced Fields** and select the desired override option.

| Override option | Description   |
|-----------------|---|
| <b>Off</b>      | Select this option and let the per-connection <b>Logging Mode</b> configuration determine the amount of information PingFederate records in the runtime transaction log.<br><br>This is the default selection.                  |
| <b>On</b>       | Select this option, followed by one of the four logging modes, to set the verbosity of runtime transaction logging for all SP connections. This is most useful when troubleshooting an issue that affects multiple connections. |

- To turn off automatic multi-connection error checking, click **Show Advanced Fields # Disable Automatic Connection Validation** check box.

This check box is not selected by default.

Once selected or cleared, the state of this setting is also reflected on the **Authentication # Integration # IdP Connections** window.

For more information about this advanced setting and its impact, see [Configuring automatic connection validation](#) on page 860.

- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

### Resolving SP connection errors

You can diagnose and resolve service provider (SP) connection errors from the **SP Connections** menu.

About this task

PingFederate automatically validates configured connections before displaying them on the **SP Connections** window. This validation ensures these connections have not been adversely affected by any subsequent changes in the supporting components, such as an adapter instance or an authentication policy contract.

If errors are found, the administrative console displays a visual cue next to the applicable connections.

Steps

1. Go to **Applications # Integration # SP Connections**.
2. To resolve the error, select the connection and follow the on-screen instructions to modify the configuration, one connection at a time.

### Importing a connection

You can import a connection in the **Import Connection** window.

About this task



#### Note:

Prior to the import, you can modify the XML file to suit your needs. The XML file can also be imported to another PingFederate environment acting in the same federation role. The source and the target must run the same version of PingFederate.

## Steps

1. Go to **Applications # Integration # SP Connections**.
2. Click **Import Connection**.
3. Click **Choose File** and browse to a connection XML file.
4. Select the **Allow Update** check box to overwrite an existing connection with the imported file.
5. Click **Import** and **Done**.

**Updating a SAML connection using metadata**



You can update an existing SAML connection using a metadata file or a metadata URL from your partner.


## About this task

This manual update is independent from the optional and per-connection automatic update feature.

## Steps

1. Go to **Applications # Integration # SP Connections**.
2. For the SAML connection that you want to update, click **Select Action # Update with Metadata**.
3. See the following steps to import or update metadata. Instructions vary depending on the medium of the metadata.

| Metadata medium          | Steps   |
|--------------------------|---|
| <b>Metadata XML File</b> | <ol style="list-style-type: none"> <li>a. On the <b>Import Metadata</b> window, select the <b>File</b> option.</li> <li>b. Choose the metadata file, and then click <b>Next</b>.</li> </ol> <div data-bbox="919 1041 1472 1310" style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>If the metadata file is digitally signed but the verification certificate is provided outside of the metadata, import the metadata verification certificate on the <b>Import Certificate</b> tab, and then click <b>Next</b>.</p> </div> <ol style="list-style-type: none"> <li>c. On the <b>Metadata Summary</b> window, review the signature information to evaluate the authenticity of the metadata.</li> <li>d. Click <b>Save</b>.</li> </ol> |
| <b>A metadata URL</b>    | <ol style="list-style-type: none"> <li>a. On the <b>Import Metadata</b> window, select the <b>URL</b> option.</li> <li>b. Select the metadata from the <b>Metadata URL</b> list.</li> </ol> <div data-bbox="919 1629 1472 1827" style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Tip:</b></p> <p>If the metadata you want is not shown in the list, click <b>Manage Partner Metadata URLs</b> and enter the URL in the text box.</p> </div>  |

| Metadata medium | Steps   |
|-----------------|---|
|                 | <p>c. Click <b>Load Metadata</b>.</p> <div data-bbox="917 247 1466 457" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If there is a digital signature error, click <b>Manage Partner Metadata URLs</b> to resolve the issue.</p> </div> <p>d. Click <b>Save</b>.</p> |

4. On the **Connections** window, click **Save**.

#### Result

 **Note:**

If the endpoints in the metadata share the same base URL (protocol, hostname, and port), PingFederate uses this information to populate the Base URL field. Consequently, individual endpoints on other windows do not include this information. Only relative paths are shown.

#### Example

#### Example

A service provider (SP) has just changed its signing certificate and published a new metadata with the new certificate. To minimize the impacts to your users, you as the identity provider (IdP) can update the SP connection using the metadata immediately.

1. Access the **SP Connections** window from **Applications # Integration # SP Connections**.
2. For the applicable SAML connection, click **Select Action # Update with Metadata**.
3. Follow the workflow to complete the task.

#### Choosing an SP connection template

The **Connection Template** tab allows you to choose a quick-connection template for new connection if your installation includes an optional PingFederate SaaS Connector.

#### About this task

 **Tip:**

When you select a connection template, many connection settings are configured for you automatically.

#### Steps

1. Go to **Applications # Integration # SP Connections**.
2. Click **Create Connection**.

3. To use a template, select **Use a template for this connection**, then choose the template and enter additional information as required.

**Important:**

After you click **Next**, you cannot return to this window and make a different selection. If you intended to use a different template or no template, you must create a new connection.

**Choosing an SP connection type**

You can manually create service provider (SP) connections in PingFederate using browser single sign-on (SSO), WS-Trust security token service (STS), outbound provisioning, or any combination thereof.

## About this task

If you are not using a connection template, which pre-configures browser-based SSO, indicate on the **Connection Type** tab whether the connection to this partner is for Browser SSO, WS-Trust STS, outbound provisioning, or any combination of them.

**Tip:**

You can add STS, OAuth, and outbound provisioning support to any existing SSO connection, or vice versa, at any time.

**Note:**

If your partner's deployment supports multiple protocols and you intend to communicate using more than one, you must set up a separate connection for each protocol. Each connection must use a unique (partner) connection ID.

## Steps

1. Go to **Applications # Integration # SP Connections**.
2. Click **Create Connection**.
3. Select **Do not use a template for this connection**.

- To configure a connection for secure browser-based SSO, select the **Browser SSO Profiles** check box.

If you are not using a connection template, you must select the applicable protocol from the list when establishing a new connection.

For a WS-Federation connection, select the desired token type, either **SAML 1.1**, **SAML 2.0**, or **JWT** (JSON Web Token).



**Note:**

For information about creating a SAML application, see [Configuring a SAML application in PingFederate](#).



**Tip:**

If you are creating a WS-Federation connection to Microsoft Windows Azure Pack, select JWT as the token type.



**Tip:**

PingFederate can encrypt the subject and attributes of SAML 2.0 assertions.

For information about configuring encryption policies on a PingFederate identity provider (IdP), see [Configuring XML encryption policy \(SAML 2.0\)](#).

For information about configuring encryption policies on a PingFederate SP, see [Specifying XML encryption policy \(for SAML 2.0\)](#).

- Optional: Choose one or both of the following depending on your configuration needs.

| Connection Template          | Step   |
|------------------------------|--|
| <b>WS-TRUST STS</b>          | Select the <b>WS-Trust STS</b> check box.  |
| <b>Outbound Provisioning</b> | Select <b>Outbound Provisioning</b> and then select the provisioning type from the list. |

- If your PingFederate license manages connections by groups, select a license group for this connection.

This option is not shown for unrestricted or other types of licenses.

- To save your settings, click **Next**.

### Choosing SP connection options

On the **Connection Options** tab, you can enable browser-based single sign-on (SSO), Attribute Query, or both for the current connection.

Before you begin

For initial steps in creating a service provider (SP) connection, see [Choosing an SP connection type](#) on page 445.

## Steps

1. Choose one or more of the following options.

| Connection option      | Description   |
|------------------------|---|
| <b>Browser SSO</b>     | Select to create a connection for browser-based SSO.  |
| <b>IdP Discovery</b>   | Select to enable identity provider (IdP) discovery. This option is only available if you have configured IdP discovery. For more information, see <a href="#">Configuring standard IdP Discovery</a> on page 912. |
| <b>Attribute Query</b> | Select to create a connection that facilitates the SAML 2.0 Attribute Query profile. For more information, see <a href="#">Attribute Query and XASP</a> on page 49.   |

2. To save your changes, click **Next**.

### Importing SP metadata

When creating or modifying service provider (SP) connections, PingFederate allows you to import metadata from an XML file or a metadata URL.

#### About this task

If you are using one of the SAML protocols without a connection template, you can expedite the setup by one of the following actions:

- Import a metadata file
- Select a metadata URL

When you select a metadata URL, also enables the automatic update option and checks the metadata periodically. If detects changes in the partner's signing certificates for digital signature verification, encryption key, or contact information, it updates the connection automatically. For better housekeeping, the update process removes verification certificates from the connection when the partner no longer maintains them in its metadata. In a clustered environment, automatically replicates verification certificates and encryption key changes to all engine nodes. Offline engine nodes will also consume these changes as they restart and rejoin the cluster. If you prefer to update the connection manually, you can clear the **Enable Automatic Reloading** check box.

You can configure reload frequency at **System # Protocol Metadata # Metadata Settings # Metadata Lifetime** tab. The default reload frequency is daily.

We recommend you turn on notifications for SAML metadata update events at **System # Monitoring & Notifications # Runtime Notifications**.



#### Note:

The notification message provides a list of the applicable items if the metadata contains changes that require additional configuration.

After creating the connection, you can add, remove, or change the metadata URL associated with the connection in the **Metadata URL** tab. In addition, you can toggle the **Enable Automatic Reloading** check box for the connection.







#### Tip:



Using a metadata URL with automatic reloading streamlines the configuration process. For example, you can quickly establish a browser SSO connection to an InCommon-participating partner. For more information, see [www.incommon.org/participants](http://www.incommon.org/participants).

## Steps

1. Select from one of the following steps to import or update metadata.

| Metadata medium             | Steps  |
|-----------------------------|--|
| <p><b>Metadata file</b></p> | <ol style="list-style-type: none"> <li>a. On the <b>Import Metadata</b> tab, select the <b>File</b> option.</li> <li>b. Choose the metadata file, and then click <b>Next</b>.</li> </ol> <div data-bbox="917 611 1472 814" style="border: 1px solid black; padding: 5px; margin-bottom: 5px;"> <p> <b>Note:</b></p> <p>If the metadata contains multiple entries, select the desired partner from the <b>Select Entity ID</b> list and click <b>Next</b>.</p> </div> <div data-bbox="917 831 1472 1100" style="border: 1px solid black; padding: 5px; margin-bottom: 5px;"> <p> <b>Note:</b></p> <p>If the metadata file is digitally signed but the verification certificate is provided outside of the metadata, import the metadata verification certificate on the <b>Import Certificate</b> tab, and then click <b>Next</b>.</p> </div> <ol style="list-style-type: none"> <li>c. On the <b>Metadata Summary</b> tab, review the signature information to evaluate the authenticity of the metadata.</li> </ol> |
| <p><b>Metadata URL</b></p>  | <ol style="list-style-type: none"> <li>a. On the <b>Import Metadata</b> tab, select the <b>URL</b> option.</li> <li>b. Select the metadata from the <b>Metadata URL</b> list.</li> </ol> <div data-bbox="917 1381 1472 1619" style="border: 1px solid black; padding: 5px; margin-bottom: 5px;"> <p> <b>Tip:</b></p> <p>If the metadata you want is not shown in the list, click <b>Manage Partner Metadata URLs</b>. For more information, see <a href="#">Manage Partner metadata URLs</a> on page 688.</p> </div> <ol style="list-style-type: none"> <li>c. Optionally, clear the <b>Enable Automatic Reloading</b> check box to disable automatic update.</li> </ol> <div data-bbox="917 1734 1472 1934" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>A warning will display if you do not have runtime notifications enabled. To enable these notifications, go to <b>System # Monitoring &amp; Notifications # Runtime</b></p> </div>   |



| Metadata medium | Steps   |
|-----------------|---|
|                 | <p data-bbox="917 199 1466 283"><b>Notifications</b> and select the <b>Notification for SAML Metadata Update Events</b> box.</p> <p data-bbox="885 294 1185 325">d. Click <b>Load Metadata</b>.</p> <div data-bbox="917 346 1466 556" style="border: 1px solid #ccc; padding: 5px;"> <p data-bbox="925 367 1047 409"> <b>Note:</b></p> <p data-bbox="925 420 1421 514">If the metadata contains multiple entries, select the desired partner from the <b>Select Entity ID</b> list and click <b>Next</b>.</p> </div> <div data-bbox="917 567 1466 766" style="border: 1px solid #ccc; padding: 5px;"> <p data-bbox="925 588 1047 630"> <b>Note:</b></p> <p data-bbox="925 640 1453 735">If there is a digital signature error, click <b>Manage Partner Metadata URLs</b> to resolve the issue.</p> </div> |

2. Click **Next**.

### Identifying the SP

On the **General Info** tab, you provide your partner's unique federation identifier, the display name of the connection, and some other optional information, such as virtual server IDs, contact information, and logging mode for runtime transaction logging.

#### Steps

1. For information on initial steps for managing SP connections, see [Choosing an SP connection type](#) on page 445.
2. Provide the basic information to identify your partner.

See the following table for more information.

| Field  | Description  |
|--|--|
| <p data-bbox="267 1297 552 1417"><b>Partner's Entity ID, Issuer, Partner's Realm, or Connection ID</b></p> <p data-bbox="267 1438 397 1470">(Required)</p> | <p data-bbox="576 1297 1372 1329">The published, protocol-dependent, unique identifier of your partner.</p> <p data-bbox="576 1344 1339 1375">For a SAML 2.0 connection, this is your partner's SAML Entity ID.</p> <p data-bbox="576 1390 1445 1484">For a SAML 1.x connection, this is the <i>Audience</i> your partner advertises. This ID may have been obtained out-of-band or using a SAML metadata file.</p> <p data-bbox="576 1501 1299 1533">For a WS-Federation connection, this is your partner's Realm.</p> <p data-bbox="576 1549 1453 1612">For a security token service (STS)-only connection, you can designate any unique identifier.</p> |
| <p data-bbox="267 1638 503 1669"><b>Connection Name</b></p> <p data-bbox="267 1684 397 1715">(Required)</p>  | <p data-bbox="576 1638 1429 1732">A plain-language identifier for the connection. For example, a company or department name. This name is displayed in the connection list on the administrative console.</p>  |
| <p data-bbox="267 1753 495 1785"><b>Virtual Server IDs</b></p>   | <p data-bbox="576 1753 1445 1843">If you want to identify your server to this connection partner using an ID other than the one you specified at <b>System # Server # Protocol Settings # Federation Info</b>, enter a virtual server ID in this field and click <b>Add</b>.</p> <p data-bbox="576 1858 1104 1890">Enter additional virtual server IDs as needed.</p>  |

| Field                       | Description  |
|-----------------------------|--|
| <b>Base URL</b>             | The fully qualified host name and port on which your partner's federation deployment runs. For example, <i>https://www.example.com:9031</i> . This entry is an optional convenience, allowing you to enter relative paths to specific endpoints, instead of full URLs, during the configuration process. |
| <b>Company</b>              | The name of the partner company to which you are connecting.   |
| <b>Contact Name</b>         | The contact person at the partner company.   |
| <b>Contact Number</b>       | The phone number of the contact person at the partner company.   |
| <b>Contact Email</b>        | The email address for the contact person at the partner company.   |
| <b>Application Name</b>     | The name of the application, accessible through the IdP Adapter interface <code>IdpAuthenticationAdapterV2</code> in the PingFederate Java SDK.<br><br>This field is not applicable to an STS-only connection.   |
| <b>Application Icon URL</b> | The URL of the application icon, accessible through the IdP Adapter interface <code>IdpAuthenticationAdapterV2</code> in the PingFederate Java SDK.<br><br>Note that this field is not applicable to an STS-only connection.   |
| <b>Logging Mode</b>         | The level of transaction logging applicable for this connection.   |

3. After entering the relevant identification information, click **Next**.

### Populating extended property values for SP connections

Add, modify, or delete extended properties for service provider (SP) connections on the **Extended Properties** page.

About this task

Extended property values can serve as metadata. They can also help drive authentication requirements. For more information, see [Extended properties](#) on page 929.

Steps

1. Go to **System # Server # Extended Properties**.
2. Enter the **Name** and **Description** for the property you want to add.

Any extended properties that are defined will be passed to all applicable velocity templates and as a request context parameter in the authentication API.

3. Optional: Select the **Multivalued** check box to indicate that the property permits multiple values.
4. Click **Add**.

### Configure IdP Browser SSO

Browser-based single sign-on (SSO), also known as Browser SSO, relies on a user's web browser and HTTP requests to broker identity-federation messaging in XML or JSON web token (JWT) between an identity provider (IdP) and a service provider (SP).

Go to **Applications # Integration # SP Connections** to access an existing or create a new SP connection. For more information, see [Accessing SP connections](#) on page 441.

From the **Browser SSO** tab inside your SP connection instance, click **Configure Browser SSO** and follow the steps below based on your federation protocol.



**Tip:**

Many steps involved in setting up a federation connection are protocol-independent. They are required steps for all connections, regardless of the associated standards. For more information, see [Federation roles](#) on page 35.

Some steps are required under the applicable protocol, while others are optional. Still others are required only based on certain selections. The administrative console determines the required and optional steps based on the protocol and dynamically presents additional requirements or options based on selections.

The following sections provide sequential information about every step you might encounter while configuring browser-based SSO, depending on the protocol you are using for a particular connection.

#### SAML 2.0 configuration steps

- [Choosing SAML 2.0 profiles](#) on page 452
- [Setting an SSO token lifetime](#) on page 453
- [Configuring SSO token creation](#) on page 453
  - [Choosing an identity mapping method for IdP SSO](#) on page 454
  - [Setting up an attribute contract](#) on page 456
  - [Managing authentication source mappings](#) on page 459
- [Configuring protocol settings](#) on page 471
  - [Setting Assertion Consumer Service URLs \(SAML\)](#) on page 472
  - [Specifying SLO service URLs \(SAML 2.0\)](#) on page 476
  - [Choosing allowable SAML bindings \(SAML 2.0\)](#) on page 477
  - [Setting an artifact lifetime \(SAML\)](#) on page 477
  - [Specifying artifact resolver locations \(SAML 2.0\)](#) on page 478
  - [Defining signature policy \(SAML\)](#) on page 478
  - [Configuring XML encryption policy \(SAML 2.0\)](#) on page 479

#### SAML 1.x configuration steps

- [Setting an SSO token lifetime](#) on page 453
- [Configuring SSO token creation](#) on page 453
  - [Choosing an identity mapping method for IdP SSO](#) on page 454
  - [Setting up an attribute contract](#) on page 456
  - [Managing authentication source mappings](#) on page 459
- [Configuring protocol settings](#) on page 471
  - [Setting Assertion Consumer Service URLs \(SAML\)](#) on page 472
  - [Setting a default target URL \(SAML 1.x\)](#) on page 473
  - [Setting an artifact lifetime \(SAML\)](#) on page 477
  - [Defining signature policy \(SAML\)](#) on page 478

#### WS-Federation configuration steps

- [Setting an SSO token lifetime](#) on page 453
- [Configuring SSO token creation](#) on page 453
  - [Choosing an identity mapping method for IdP SSO](#) on page 454
  - [Setting up an attribute contract](#) on page 456
  - [Managing authentication source mappings](#) on page 459
- [Configuring protocol settings](#) on page 471
  - [Defining a service URL \(WS-Federation\)](#) on page 474

After configuring SSO settings, you will normally need to configure authentication credentials, the range of which depends on your SSO selection. For more information, see [Configuring credentials](#) on page 487. You might need to complete further configuration tasks for new or modified connections, depending on the selected options on the **Connection Options** tab.

### Choosing SAML 2.0 profiles

A SAML profile is the message-interchange scenario that you and your federation partner have agreed to use. SAML binding, by contrast, is the transport protocol of SAML messages.

About this task

On the **SAML Profiles** tab, select one or more SAML 2.0 profiles for your IdP Browser SSO configuration.



#### Note:

The **SAML Profiles** tab is not shown for SAML 1.x connections because identity provider (IdP) single sign-on (SSO) is assumed, single logout (SLO) profiles are not supported, and the server supports the "destination-first" (SP-initiated) profile SSO automatically. This window is also not presented for WS-Federation connections because profile selection is not required.



#### Note:

When configuring a local loopback connection, in which one PingFederate instance is both the identity provider and the service provider, disable the IdP-Initiated SLO and SP-Initiated SLO options on the Browser SSO window's SAML Profiles tab. These options determine whether SAML logout requests should be sent to the partner during the SLO flow. Those requests aren't necessary and can cause unexpected behavior when the partner connection exists locally. All local sessions for loopback connections are terminated during the SLO flow without the need to send SAML requests.

For SAML 2.0, PingFederate supports all IdP- and SP-initiated SSO and SLO profiles. For more information on typical SSO and SLO profile configurations, including illustrations, see [SAML 2.0 profiles](#) on page 40.

Steps

1. Go to **Applications # Integration # SP connections**.
2. Click on the SP connection you want to configure. For more information, see [Accessing SP connections](#) on page 441.
3. On the **Browser SSO** tab, click **Configure Browser SSO**.
4. Select either **IdP-Initiated SSO** or **SP-Initiated SSO** or both, depending on your partner agreement.  
You must select at least one SSO profile.

- Select either **IdP-Initiated SLO** or **SP-Initiated SLO** or both, depending on your partner agreement. SLO profile options are only enabled after you choose an SSO profile.

## IdP Connections | IdP Connection | Browser SSO

|               |                       |                   |         |
|---------------|-----------------------|-------------------|---------|
| SAML Profiles | User-Session Creation | Protocol Settings | Summary |
|---------------|-----------------------|-------------------|---------|

A SAML Profile defines what kind of messages may be exchanged between an Identity Provider (IdP) and a Service Provider (SP), and how the messages are transported (bindings). As an SP, you configure this information for your IdP connection.

| Single Sign-On (SSO) Profiles                         | Single Logout (SLO) Profiles                          |
|---|---|
| <input checked="" type="checkbox"/> IDP-INITIATED SSO | <input checked="" type="checkbox"/> IDP-INITIATED SLO |
| <input type="checkbox"/> SP-INITIATED SSO             | <input type="checkbox"/> SP-INITIATED SLO             |

- Click **Next** to save your changes.

### Setting an SSO token lifetime

Identity-federation standards require a window of time during which a SSO token is considered valid. Each SSO token has an issuance time-stamp element and elements indicating the allowable lifetime of the SSO token before and after the issuance time stamp.

Before you begin

For previous steps in configuring Browser SSO, see [Choosing SAML 2.0 profiles](#) on page 452. For more information about managing service provider (SP) connections, see [Accessing SP connections](#) on page 441.

About this task

PingFederate gives you the option to change the valid lifetime of the single sign-on (SSO) token.

Steps

- Optional: Override the default values for the following fields.

| Field                 | Description   |
|-----------------------|---|
| <b>Minutes Before</b> | The amount of time before the SSO token was issued during which it is to be considered valid. |
| <b>Minutes After</b>  | The amount of time after the SSO token was issued during which it is to be considered valid.  |

The default value is 5 minutes for both fields.

- Click **Next** to save your changes.

### Configuring SSO token creation

As an identity provider (IdP), you must specify how PingFederate obtains user-authentication information and use it to create single sign-on (SSO) tokens appropriate for your service provider (SP) partner, including additional user attributes as needed.

About this task

If you are a federation hub bridging a service provider to one or more identity providers, you can associate one or more authentication policy contracts to the SP connection. For more information, see [Federation hub use cases](#) on page 108.

The configuration involves choosing an identity-mapping method, if applicable; establishing an attribute contract, as needed; and mapping one or more IdP adapter instances, authentication policy contracts, or both.

#### Steps

1. Go to **Applications # Integration # SP Connections**.
2. Click on the SP connection that you want to configure.
3. Follow the steps to reach the **Browser SSO** tab for your connection. For more information, see [Configure IdP Browser SSO](#) on page 450.
4. On the **Assertion Creation** tab, click **Configure Assertion Creation**.

#### *Choosing an identity mapping method for IdP SSO*

In the **Identity Mapping** window, you choose the type of name identifier your partner requires. Your selection might affect the way that the service provider (SP) looks up and associates your users at the SP site. You and the SP should decide in advance which option to use.

The choices of name-identifier types depend on whether you use the SAML or WS-Federation protocol. For more information, see one of the following.

- [Selecting a SAML Name ID type](#) on page 454
- [Selecting a WS-Federation Name ID type](#) on page 455



#### **Note:**

The **Identity Mapping** window does not apply for connections using the WS-Federation protocol in conjunction with JSON web token (JWT)-based single sign-on (SSO) tokens. Instead, work with the SP to define an attribute contract that it can use to map users to accounts at the SP site.

#### Selecting a SAML Name ID type

You can choose a name identifier for your SAML Browser single sign-on (SSO) configuration on the **identity Mapping** tab. The type of name identifier you select affects how your service provider (SP) partner makes use of account mapping or account linking.

#### Before you begin

For previous steps in configuring Browser SSO, see [Configure IdP Browser SSO](#) on page 450. For more information about managing service provider (SP) connections, see [Accessing SP connections](#) on page 441.

#### About this task

If your SP uses account linking, establishing an attribute contract is not required. However, depending on your agreement, you can choose to supplement the account link with an attribute contract. In this configuration, the account link is used to determine the user's identity, while the additional attributes might be used for authorization decisions, customized web pages, and so on, at the SP site. For more information, see [User attributes](#) on page 101.



#### **Important:**

If you change your configuration to use account linking without additional attributes, any existing attribute contract will be discarded in favor of the new configuration.

## Steps

1. Select the type of name identifier that you and your SP have agreed to use.

| Option           | Description  |
|------------------|--|
| <b>Standard</b>  | <p>Select if you want to send a known attribute to identify a user, for example, a username or an email address.</p> <p>In this scenario, the SP often uses account mapping to identify the user locally.</p>  |
| <b>Pseudonym</b> | <p>Select if you and the SP have agreed to use a unique, opaque persistent name identifier, which cannot be traced back to the user's identity at the IdP.</p> <p>The SP might also use the identifier for account linking to make a persistent association between the user and a specific local account.</p> <p>Select the <b>Include attributes in addition to the pseudonym</b> box if you want to set up an attribute contract to use in conjunction with an opaque identifier. For more information, see <a href="#">Setting up an attribute contract</a> on page 456.</p>                                   |
| <b>Transient</b> | <p>Select <b>Transient</b> to enhance the privacy of a user's identity. Unlike a pseudonym, a transient identifier is different each time a user initiates SSO.</p> <p>An example application for this selection might be when an SP provides generalized group accounts based on organizational rather than individual identity.</p> <p>Select the <b>Include attributes in addition to the transient identifier</b> box if you want to set up an attribute contract to use in conjunction with an opaque identifier. For more information, see <a href="#">Setting up an attribute contract</a> on page 456.</p> |

2. Click **Next** to save your changes.

## Next steps

If you opted to include attributes in your name identifier, your next step will be to define the attributes. For more information, see [Setting up an attribute contract](#) on page 456. Otherwise proceed to [Managing authentication source mappings](#) on page 459.

## Selecting a WS-Federation Name ID type

You can choose a name identifier for your WS-Federation Browser single sign-on (SSO) configuration on the **Identity Mapping** tab. Your selection might affect the way the service provider (SP) looks up and associates your users to their local accounts.

## Before you begin

For previous steps in configuring Browser SSO, see [Configure IdP Browser SSO](#) on page 450. For more information about managing service provider (SP) connections, see [Accessing SP connections](#) on page 441.

## About this task

The **Identity Mapping** window is not applicable to connections using the WS-Federation protocol in conjunction with JSON web token (JWT)-based SSO tokens. Instead, work with the SP to define an attribute contract that it can use to map users to accounts at the SP site.

## Steps

1. Select the type of name identifier that you and your SP have agreed to use.

| Option                     | Description   |
|----------------------------|---|
| <b>Email Address</b>       | This attribute is commonly used as a unique identifier for SSO and single logout (SLO). Make this selection, for example, if a user logs in using an email address or if the information is available for lookup in a local datastore.                                    |
| <b>User Principal Name</b> | The username or other unique ID of the subject initiating the transaction. Make this selection, for example, if a username will be available from the current user session as part of a cookie or can be derived from a local datastore.                                  |
| <b>Common Name</b>         | This selection provides for anonymous SSO to your SP, generally using a hard-coded generalized sign on. Make this selection if your partner agreement involves a many-to-one use case, such as if the SP has a group account set up for all users in a particular domain. |

2. Click **Next** to save your changes.

*Setting up an attribute contract*

An attribute contract is the set of user attributes that you and your partner have agreed will be sent in the single sign-on (SSO) tokens for this connection.

## About this task

You specify the attributes for the name identifier on your WS-Federation or, optionally, for your SAML configuration on the **Attribute Contract** tab. For more information, see [Attribute contracts](#) on page 101.

WS-Federation connections require you to define attribute contracts. For SAML connections, attribute contracts are optional if you are sending either pseudonym or transient identifiers to the partners. For more information, see [Selecting a SAML Name ID type](#) on page 454.

When establishing an attribute contract, you can change the name format when certain conditions are met. The following table summarizes the conditions and the possible actions that you can perform on the **Attribute Contract** tab.

| Protocol             | Identity mapping       | Attribute contract   | SAML_SUBJECT  | Additional attributes   |
|----------------------|------------------------|--|---|---|
| SAML 2.0 or SAML 1.1 | Standard               | Required   | Built-in.<br>Subject name format can be changed by selecting a value from a list. | Optional.<br>Attribute name format can be changed by selecting a value from a list.                 |
| SAML 2.0 or SAML 1.1 | Pseudonym or Transient | Required only if the <b>Include attributes ...</b> check box is selected on the <b>Identity Mapping</b> window. Otherwise the <b>Attribute Contract</b> window is not shown. | Assumed and cannot be added as an additional attribute.                           | At least one is required.<br>Attribute name format can be changed by selecting a value from a list. |



| Protocol   | Identity mapping                                   | Attribute contract   | SAML_SUBJECT  | Additional attributes   |
|--|--|--|---|---|
| SAML 1.0   | Standard   | Required   | Built-in.<br>Subject name format can be changed by selecting a value from a list. | Optional.<br>There is no attribute name format.                                       |
| SAML 1.0   | Pseudonym or Transient                             | Required only if the <b>Include attributes ...</b> check box is selected on the <b>Identity Mapping</b> window. Otherwise the <b>Attribute Contract</b> window is not shown. | Assumed and cannot be added as an additional attribute.                           | At least one is required.<br>There is no attribute name format.                       |
| WS-Federation in conjunction with SAML 1.1 as the token type | Email address, user principal name, or common name | Required   | Built-in.<br>There is no subject name format.                                     | Optional.<br>Attribute name format can be changed by selecting a value from a list.   |
| WS-Federation in conjunction with SAML 2.0 as the token type | Email address, user principal name, or common name | Required   | Built-in.<br>There is no subject name format.                                     | Optional.<br>Attribute name format can be changed by selecting a value from the list. |
| WS-Federation in conjunction with JWT as the token type      | Not applicable                                     | Required   | Not applicable  | At least one is required.<br>There is no attribute name format.                       |



#### Tip:

If you are creating or updating a SAML service provider (SP) connection, consider using the partner's metadata to do so. If the metadata contains the required information, PingFederate automatically populates the attribute contract for you. For more information, see [Importing SP metadata](#) on page 447.

#### Steps

1. Follow the required steps to create an SSO token depending on your federation protocol. For more information, see [Configure IdP Browser SSO](#) on page 450.
2. If you are using a SAML protocol, on the **Identity Mapping** tab you must select either **Pseudonym** or **Transient**, and also select the **Include Attributes** box to access the **Attribute Contract** tab. For more information, see [Selecting a SAML Name ID type](#) on page 454.

3. Optional: Click the **Attribute Name Format** drop-down to select a different format for the built-in subject identifier, **SAML\_SUBJECT**.

Applicable if you and the SP have agreed to a specific format. For more information, see [Attribute contracts](#) on page 101.



**Note:**

As needed, you can customize name-format alternatives in the `<pf_install>/pingfederate/server/default/data/config-store/custom-name-formats.xml` configuration file. Restart PingFederate to activate any changes made to this file.

4. Extend the contract with additional attributes.
  - a. Enter the name of an additional attribute in the text field under **Extend the Contract**.

Attribute names are case-sensitive and must correspond to the attribute names expected by your partner.



**Tip:**

You can add a special attribute, **SAML\_AUTHN\_CTX**, to indicate to the SP, if required, the type of credentials used to authenticate to the identity provider (IdP) application.

The value of this attribute can then be mapped later on the **Attribute Contract Fulfillment** window. For more information, see [Configuring contract fulfillment for IdP Browser SSO](#) on page 469. The mapped value overrides the authentication context provided by the IdP adapter instance or the Requested AuthN Context Authentication Selector instance, through an authentication policy. If no authentication context is provided by the **SAML\_AUTHN\_CTX** attribute, the IdP adapter instance, or the Requested AuthN Context Authentication Selector instance, PingFederate sets the authentication context as follows:

- For SAML 1.x `urn:oasis:names:tc:SAML:1.0:am:unspecified`
- For SAML 2.0 `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified`



**Tip:**

If you are configuring a WS-Federation connection to Microsoft Windows Azure Pack, add `upn` to the JWT's attribute contract.



**Tip:**

If you are configuring a SAML connection to an InCommon participant (see [Incommon federation participants](#)), the attribute contract might contain or require attributes such as `urn:oid:0.9.2342.19200300.100.1.3` and `urn:oid:2.5.4.42`, which are standard names under various specifications, such as [RFC4524](#) and [RFC4519](#). The following table describes a subset of the object IDs referenced by the most common attributes used by InCommon participants.

| Object ID value           | Description                |
|---------------------------|----------------------------|
| 0.9.2342.19200300.100.1.3 | mail                       |
| 1.3.6.1.4.1.5923.1.1.1.6  | eduPersonPrincipalName     |
| 1.3.6.1.4.1.5923.1.1.1.7  | eduPersonEntitlement       |
| 1.3.6.1.4.1.5923.1.1.1.9  | eduPersonScopedAffiliation |

| Object ID value           | Description         |
|---------------------------|---------------------|
| 1.3.6.1.4.1.5923.1.1.1.10 | eduPersonTargetedID |
| 2.5.4.3                   | cn                  |
| 2.5.4.4                   | sn                  |
| 2.5.4.10                  | o                   |
| 2.5.4.42                  | givenName           |
| 2.16.840.1.113730.3.1.241 | displayName         |

For other attributes, see the metadata from your partner. The **FriendlyName** values, if available, should provide additional information about the attributes. Alternatively, third-party resources, such as <https://www.ldap.com/ldap-oid-reference> and <http://www.oid-info.com/>, might help as well.

- b. Select an attribute name format from the list.

Applicable if you and the SP have agreed to a specific format. For more information, see [Attribute contracts](#) on page 101.



**Note:**

As needed, you can customize name-format alternatives in the `<pf_install>/pingfederate/server/default/data/config-store/custom-name-formats.xml` configuration file. Restart PingFederate to activate any changes made to this file.

- c. Click **Add**.
- d. Repeat until all desired attributes are defined.
5. Optional: Click **Edit** to change the configuration of an existing attribute.
6. Optional: Click **Delete** to remove an existing attribute.
7. Click **Next** to save changes.

#### *Managing authentication source mappings*

On the **Authentication Source Mapping** tab, you can map identity provider (IdP) adapters and authentication policies to authenticate users to your service provider (SP).

#### About this task

IdP adapters are responsible for handling user authentication as part of a single sign-on (SSO) operation. A configured adapter in PingFederate is known as an adapter instance.

In a basic scenario, you map an IdP adapter instance to a SP connection on the **Authentication Source Mapping** tab and complete its mapping configuration through a series of sub tasks. When a user starts an SSO request, the corresponding IdP adapter is triggered to authenticate the user. Upon successful authentication, PingFederate creates and sends an SSO token to the SP based on the connection settings. As needed, you can map multiple IdP adapter instances to an SP connection, the same IdP adapter instance to multiple SP connections, or a combination of them.

If you use authentication policies to route users through a series of authentication sources and end each successful policy path with an authentication policy contract (APC), you can map the APC to your connection. Like IdP adapter instances, you can map multiple APCs to an SP connection, the same APC to multiple SP connections, or a combination of them.



**Tip:**

For more information about authentication policies and contracts, see [Authentication policies](#) on page 231.

You can also map one or more APCs to an SP connection to bridge a service provider to one or more identity providers. In this scenario, PingFederate is a federation hub for both sides. PingFederate uses APCs to associate this SP connection with the applicable IdP connections to the identity providers. Each APC has its own set of attributes which you map values to the SSO tokens.



**Tip:**

For more information about the federation hub, see [Federation hub use cases](#) on page 108.

Regardless of how many IdP adapter instances and APCs are mapped to an SP connection, PingFederate uses only one adapter instance or policy path to authenticate a user. You can leave the decision to the users or create authentication policies to mandate authentication requirements. Because each adapter instance or APC could return different user attributes, each mapping must define how the attribute contract is fulfilled in its mapping configuration.

### Steps

1. For initial steps to configure SP connections, see [Accessing SP connections](#) on page 441.
2. For initial steps to configure Browser SSO, see [Configure IdP Browser SSO](#) on page 450.
3. For initial steps to configure assertion creation. see [Configuring SSO token creation](#) on page 453.
4. On the **Authentication Source Mapping** tab, select one of the following.  
Choose from:
  - Click **Map New Adapter Instance** to map a new IdP Adapter instance. For more information, see [Mapping an adapter instance](#) on page 460.
  - Click **Map New Authentication Policy** to map a new APC. For more information, see [Mapping an authentication policy](#) on page 461
  - Click on an existing instance to edit its configuration.
  - Click **Delete** to remove an existing adapter instance or APC. Click **undelete** to cancel the removal request

When authentication sources, such as IdP adapter instances or connection mapping contracts, are restricted to certain virtual server IDs, the allowed IDs are displayed under **Virtual Server IDs**.

5. When your authentication sources have been mapped, click **Next** save your changes.

### Mapping an adapter instance

After extending your attribute contract, you can map adapter instances on the **Authentication Source Mapping** tab.

### Steps

1. For initial steps, see [Managing authentication source mappings](#) on page 459.
2. On the **Authentication Source Mapping** tab, click **Map New Adapter Instance**.
3. On the **Adapter Instance** tab, select an adapter instance from the **Adapter Instance** drop-down list.

- Optional: If you want to customize one or more adapter settings for this connection alone, select the **Override Instance Settings** check box.

**Note:**

If you are editing a currently mapped adapter instance, you can toggle **Override Instance Settings**. Clearing it removes all previously overridden settings for this connection. Selecting it provides you the opportunity to customize adapter settings specifically for this connection.

**Tip:**

Alternatively, you can create child adapter instances of a base adapter instance (with overrides) so that customized settings can be applied to several connections. For more information, see [Hierarchical plugin configurations](#) on page 99.

Result: Selecting the **Override instance settings** box will add the **Override Instance** tab to the navigation bar. For more information, see [Overriding an IdP adapter instance](#) on page 461

- Click **Next**, and refer to the following topics to complete the configuration.

## Mapping an authentication policy

After extending your attribute contract, the **Authentication Source Mapping** tab gives you the option to map an authentication policy.

## Steps

- Click **Map New Authentication Policy**.
- On the **Authentication Policy Contract** tab, select a contract from the **Authentication policy contract** list.

If you need to create a new contract or manage an existing contract, click **Manage Policy Contracts**.

- Click **Next**, and refer to the following topics to complete the configuration.

## Overriding an IdP adapter instance

On the **Override Instance** window, you can start a series of sub tasks to override adapter settings specifically for this connection.

## About this task

**Note:**

Any changes to the base adapter instance are propagated to a connection as long as you don't override those changes.

## Steps

- For initial steps to configure authentication source mapping, see [Managing authentication source mappings](#) on page 459.
- On the **Adapter Instance** tab, click **Override Instance Settings**.

3. On each of the settings tabs, select the **Override** check box, make your changes, and then click **Next**.

**Note:**

If you are editing a currently mapped adapter instance, click **Override Instance Settings** to reconfigure any overridden settings for this connection. You can also remove all overridden settings on a per-window basis by clearing the **Override** check box near the top of the window.

The override setting windows are functionally identical to those used for creating a new adapter instance. For more information, see [Managing IdP adapters](#) on page 420.

4. When you are finished, click **Done** to proceed to [Selecting an attribute mapping method](#) on page 462.

## Restricting an authentication source to certain virtual server IDs

On the **Virtual Server IDs** tab, when you multiplex one connection for multiple environments, you can enforce authentication requirements by restricting an authentication source to certain virtual server IDs.

## About this task

Authentication sources are unrestricted by default. For more information, see [Multiple virtual server IDs](#) on page 115

## Steps

1. Select the **Restrict Virtual Server IDs** check box.
2. Select one or more virtual server IDs that you want to allow for this authentication source.

## Result

If you are editing a currently mapped adapter instance or authentication policy contract (APC), you can toggle the **Restrict Virtual Server IDs** setting. You can also change the allowed virtual server IDs.

## Selecting an attribute mapping method

On the **Mapping Method** tab, you can select if and how PingFederate should query local datastores to help fulfill the attribute contract in conjunction with attribute values from the authentication source.

## About this task

To determine whether you need to look up additional values, compare the attribute contract against the adapter contract or the authentication policy contract. If the attribute contract requires more information, you must determine whether local datastores can supply it.

**Tip:**


Alternatively, you can configure datastore queries as part of the fulfillment configuration for the applicable identity provider (IdP) adapter contract or authentication policy contract. If so, you do not need to set up datastore query on the connection level.

For more information, see [Defining the IdP adapter contract](#) on page 424 or [Applying policy contracts or identity profiles to authentication policies](#) on page 263.

## Steps

1. For initial steps to configure IdP adapter instances, see [Mapping an adapter instance](#) on page 460.

2. On the **Mapping Method** tab, select one of the following options.

| Mapping method  | Description   |
|---|---|
| <b>Retrieve additional attributes from multiple data stores using one mapping</b> | Select to configure one or more datastores to look up attributes for a single mapping.  |
| <b>Retrieve additional attributes from a data store</b>                           | Select to define alternate datastores to look up attributes and a failsafe mapping configuration.   |
|   |  <b>Note:</b><br>When this option is selected, the token authorization framework, through issuance criteria, does not apply. For more information, see <a href="#">Token authorization</a> on page 105 and <a href="#">Selecting an attribute mapping method</a> . |
| <b>Use only the adapter contract values in the SAML assertion</b>                 | Select if you do not require connection-level datastore query.  |

3. Click **Next** to save changes and proceed to the next tab.

If you opted to require datastore queries, see [Configuring attribute sources and user lookup](#) on page 468. If not, see [Configuring contract fulfillment for IdP Browser SSO](#) on page 469.

#### Configuring default contract fulfillment for IdP Browser SSO

On the **Attribute Contract Fulfillment** tab, you can define the default attributes PingFederate will send to the service provider (SP) in case of failure to complete the attribute contract.

Before you begin

For initial steps to configure identity provider (IdP) adapter instances or authentication policy contracts (APC), see [Managing authentication source mappings](#) on page 459.

If you have selected the failsafe option on the **Mapping Method** tab and the **Send user to SP using default list of attributes** option on the **Failsafe Attribute Source** tab, define the default values that should be sent in the single sign-on (SSO) tokens to the SP.

About this task

On the **Attribute Contract Fulfillment** tab, you must complete the following steps for each adapter instance or APC.

Steps

1. Select a source from the **Source** drop-down list.

2. Select a source from the **Source** list and then choose or enter a value. You must map all attributes. See the following table for more information.

- **Adapter or Authentication Policy Contract** (the authentication source)

When selected, the **Value** list is populated with attributes from the authentication source. Select the desired attribute from the list. At runtime, the attribute value from the authentication source is mapped to the value of the attribute in the SSO token.

For example, to map the value of the HTML Form Adapter's **username** attribute as the value of the **SAML\_SUBJECT** attribute on the contract, select **Adapter** from the **Source** list and **username** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the SSO token.



**Important:**

If you are configuring an SP connection to bridge one or more identity providers to a service provider, consider mapping the original issuer of the assertions into an attribute by selecting **Context** as the source and **Authenticating Authority** as the value. This is important when bridging multiple identity providers to one service provider, where the service provider should take the information about the original issuer into consideration before granting access to protected resources.

For more information, see [Bridging multiple IdPs to an SP](#) on page 110.



**Note:**

Because the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values (see **Expression**).

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under



**Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field, causing no value selection to be necessary.

- **Text**

When selected, the text you enter is mapped to the value of the attribute in the single sign-on tokens at runtime. You can mix text with references to any of the values from the authentication source using the `${attribute}` syntax.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.



**Tip:**

Two other text variables are also available: `${SAML_SUBJECT}` and `${TargetResource}`. **SAML\_SUBJECT** is the initiating user (or other entity). **TargetResource** is a reference to the protected application or other resource for which the user requested SSO access; the `${TargetResource}` text variable is available only if specified as a query parameter for the relevant endpoint (either as **TargetResource** for SAML 2.0 or **TARGET** for SAML 1.x).

3. After all attributes have been mapped, click **Next** to save changes.

### Defining issuance criteria for IdP Browser SSO

Configure the criteria that PingFederate uses to determine user authorization to access service provider (SP) resources.

#### About this task

On the **Issuance Criteria** tab, define the criteria that must be satisfied in order for to process a request further. This token authorization feature provides the capability to conditionally approve or reject requests based on individual attributes.



**Note:**

The **Issuance Criteria** tab does not appear if you have chosen the failsafe option on the **Mapping Method** tab. For more information, see [Selecting an attribute mapping method](#) on page 462.

Begin this optional configuration by adding a criterion. Choose the source that contains the attribute to be verified. Some sources, such as **Mapped Attributes**, are common to almost all use cases. Other sources, such as **JDBC**, depend on the type of configuration. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to be verified. Depending on the selected source, the available attributes or properties vary. Finally, specify the comparison method and the desired, compared-to, value.

If you define multiple criteria, all criteria must be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value depending on the chosen comparison method. The multi-value contains and multi-value does not contain comparison methods are intended for attributes that might contain multiple values. Such criterion is considered satisfied if one of the multiple values matches or does not match the specified value.

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



### Important:

When you multiplex one connection for multiple environments, consider using attribute mapping expressions to verify the virtual server ID in conjunction with other conditions, such as group membership information, to protect against unauthorized access. For more information, see [Multiple virtual server IDs](#) on page 115 and [Issuance criteria and multiple virtual server IDs](#) on page 229.



### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. In the **Source** list, select the attribute's source.

| Source   | Description  |
|--|--|
| <b>Adapter or Authentication Policy Contract</b>               | Select to evaluate attributes from an identity provider (IdP) adapter instance or an authentication policy contract.   |
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.   |
|  | <b>Note:</b><br>The <b>HTTP Request</b> context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values. |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.   |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.  |

2. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

Error results are handled differently for IdP-initiated single sign-on (SSO) and SP-initiated SSO requests.

IdP-initiated SSO

Redirect

When an **InErrorResource** URL is provided, the value of the **Error Result** field is used by an **ErrorDetail** query parameter in the redirect URL.

Template

When an **InErrorResource** URL is not provided, the value of the **Error Result** field is used by the variable `$errorDetail` in the `idp.sso.error.page.template.html` template file.

SP-Initiated SSO

SAML

The **Error Result** field value is used by the **StatusMessage** element in the response to the SP.

WS-Federation (Template)

The **Error Result** field value is used by the `$errorDetail` variable in the `<pf_install>/pingfederate/server/default/conf/template/sourceid-wsfed-idp-exception-template.html` template file.

Using an error code in the **Error Result** field allows the error template or an application to process the code in a variety of ways. For example, the template or application can display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

6. Click **Add**.
7. Optional: Repeat to add more criteria.
8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Configuring attribute sources and user lookup

Attribute sources are specific datastore or directory locations containing information that might be needed for the attribute contract. You can use more than one attribute source when mapping values to the attribute contract.

#### About this task

The order in which attribute sources are listed affects the queries differently based on the selection made on the **Mapping Method** tab. For more information, see [Selecting an attribute mapping method](#) on page 462.

#### Retrieve additional attributes from multiple data stores using one mapping

If you plan on using the result of a query as an input to a subsequent query, stack your attribute sources accordingly.

#### Retrieve additional attributes from a data store

As soon as a query succeeds, PingFederate moves on to the next task, contract fulfillment. Therefore you should prioritize the attribute sources.

#### Steps

1. Click **Add Attribute Source** and then follow a series of sub tasks to complete the configuration.
2. See [Choosing a datastore](#) on page 398 for instructions on configuring and adding attribute sources.

3. Repeat as necessary to add additional sources.

## Result

If you are editing a currently mapped adapter instance or authentication policy contract, you can add, remove, or reorder attribute sources, which might require additional configuration changes in subsequent tasks.

## Configuring contract fulfillment for IdP Browser SSO

On the **Attribute Contract Fulfillment** tab, you can map values to the attributes defined for the contract. These are the values that will be included in the single sign-on (SSO) tokens sent to the service provider (SP).

### Before you begin

For initial steps to configure identity provider (IdP) adapter instances or authentication policy contracts (APC), see [Managing authentication source mappings](#) on page 459.

### About this task

If you are bridging one or more identity providers to a service provider, map values to an authentication policy contract. For more information, see [Federation hub use cases](#) on page 108.

At runtime, an SSO operation fails if PingFederate cannot fulfill the required attribute.

On the **Attribute Contract Fulfillment** tab, you must complete the following steps for each attribute contract.

### Steps

1. Select a **Source** from the drop-down.
2. Select a **Value** from the drop-down or enter a **Value** in the text field. See the following for more information.

- **Adapter or Authentication Policy Contract** (the authentication source)

When selected, the **Value** list is populated with attributes from the authentication source. Select the desired attribute from the list. At runtime, the attribute value from the authentication source is mapped to the value of the attribute in the SSO token.

For example, to map the value of the HTML Form Adapter's **username** attribute as the value of the **SAML\_SUBJECT** attribute on the contract, select **Adapter** from the **Source** list and **username** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the SSO token.

### Important:

If you are configuring an SP connection to bridge one or more identity providers to a service provider, consider mapping the original issuer of the assertions into an attribute by selecting **Context** as the source and **Authenticating Authority** as the value. This is important when bridging multiple identity providers to one service provider, where the service provider should take

the information about the original issuer into consideration before granting access to protected resources.

For more information, see [Bridging multiple IdPs to an SP](#) on page 110.

 **Note:**

Because the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values (see **Expression**).

- **LDAP, JDBC, or Other**

When selected, the **Value** list populates with attributes that you have selected in the attribute source configuration. Select the desired attribute from the list. At runtime, the attribute value from the attribute source is mapped to the value of the attribute in the SSO token.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under **Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

When selected, the text you enter is mapped to the value of the attribute in the single sign-on tokens at runtime. You can mix text with references to any of the values from the authentication source using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using this syntax:

```
${ds.attr-source-id.attribute}
```

where `attr-source-id` is the attribute source ID value and `attribute` is one of the selected attributes in the attribute source configuration.

Note that when using alternate data stores with a failsafe mapping, the attribute source ID value is not applicable. Use the following syntax instead:

```
${ds.attribute}
```

 **Tip:**

Two other text variables are also available: `${SAML_SUBJECT}` and `${TargetResource}`. **SAML\_SUBJECT** is the initiating user (or other entity). **TargetResource** is a reference to the protected application or other resource for which the user requested SSO access; the `${TargetResource}` text variable is available only if specified as a query parameter for the relevant endpoint (either as **TargetResource** for SAML 2.0 or **TARGET** for SAML 1.x).

There are also a variety of reasons why you might hard code a text value. For example, if the SP web application provides a service based on the name of your organization, you might provide that attribute value as a constant.

3. After all attributes have been mapped, click **Next** to save changes.

**Note:**

If you are editing a currently mapped adapter instance or APC, you can update the mapping configuration, which might require additional configuration changes in subsequent tasks.

### Reviewing the authentication source mapping

You can review and save your authentication source mapping in the **Summary** tab.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Reviewing the SSO token creation summary

Review and save your single sign-on (SSO) token creation configuration in the **Summary** tab.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Configuring protocol settings

The **Protocol Settings** tab provides the launching point for configuring partner endpoints, message customizations, and other protocol-specific settings for browser-based single sign-on (SSO) connections.

#### Before you begin

For initial steps to configure a service provider (SP) connection, see [Accessing SP connections](#) on page 441.

For initial steps to configure Browser SSO, see [Configure IdP Browser SSO](#) on page 450.

#### About this task

##### SAML 2.0

- Outbound SSO bindings (POST, artifact) and the corresponding assertion consumer service (ACS) URLs
- Outbound SLO bindings (POST, redirect, artifact, SOAP) and the corresponding protocol endpoints

- Inbound bindings (POST, redirect, artifact, SOAP)
- Artifact lifetime
- Signature policy
- Encryption policy

#### SAML 1.x

- Outbound SSO bindings (POST, artifact) and the corresponding assertion consumer service (ACS) URLs
- Default target URL
- Artifact lifetime
- Signature policy

#### WS-Federation

- Protocol endpoint
- Default target URL

#### Steps

1. Before configuring Browser SSO protocol settings, you must first configure assertion configuration. For more information, see [Configuring SSO token creation](#) on page 453
2. In the **Protocol Settings** tab, click **Configure Protocol Settings** to begin.

#### Setting Assertion Consumer Service URLs (SAML)

If your PingFederate configuration uses any version of SAML, you can configure assertion indexes, bindings, and endpoint URLs on the **Assertion Consumer Service URL** tab.

#### Before you begin

For prerequisites and initial steps to configure Browser SSO protocol settings, see [Configuring protocol settings](#) on page 471.

#### About this task

The assertion consumer service (ACS) endpoint is a location to which the single sign-on (SSO) tokens are sent, according to partner requirements. ACS is applicable to all SAML versions and both the identity provider (IdP)- and service provider (SP)-initiated SSO profiles.



#### Note:

The SP might request that the SAML assertion be sent to one of several URLs, using different bindings. PingFederate uses the defined URL entries on this page to validate the authentication request. However, per SAML specifications, if the request is signed, PingFederate can verify the signature instead. The ACS URL does not necessarily need to be listed here. This is useful for scenarios where an ACS URL might be dynamically generated.

Some federation use cases might require additional customizations in the assertions sent from the PingFederate IdP server to the SP, such as placing well-formed XML in the `<AttributeValue>` element or including the optional `sessionNotOnOrAfter` attribute in the `<AuthnStatement>` element. You can use OGNL expressions to fulfill these use cases.



## Steps

1. In the **Assertion Consumer Service URL** tab, configure one or more SAML ACS endpoints.
  - a. Select a SAML binding from the **Binding** drop-down list.
  - b. Enter the ACS endpoint URL to the **Endpoint URL** field.

You can enter a relative path (begin with a forward slash) if you have provided a base URL on the **General Info** window.

- c. Optional: Select the **Default** box if you want this entry to be the default ACS endpoint.

The administrative console always sets the first entry as the default ACS endpoint. You can reset the default endpoint when you add ACS endpoint.

- d. Optional: Enter an integer to the **Index** field for this ACS endpoint.

The administrative console automatically assigns an index value for each ACS endpoint, starting from 0. If you want to define your own index values, you must make sure the index values are unique.

- e. Click **Add**.
  - f. Optional: Repeat to add additional ACS endpoints.

2. Optional: Customize messages using OGNL expressions.



### Note:

OGNL expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- a. Click **Show Advanced Customizations**.
  - b. Select a message type from the list.
  - c. Enter an OGNL expression to fulfill your use case.



### Note:

For more information about **Message Type**, available variables, and sample OGNL expressions, see [Customizing assertions and authentication requests](#) on page 390.

- d. Click **Add**.
  - e. Optional: Repeat to add another message customization.

3. Click **Next** to proceed to the next tab. For SAML 1.x configurations, see [Setting a default target URL \(SAML 1.x\)](#) on page 473. For SAML 2.0, see [Specifying SLO service URLs \(SAML 2.0\)](#) on page 476.

## Result

If you are editing an existing connection, you can reconfigure any items, which could require additional configuration changes in subsequent tasks. You must always configure at least one ACS endpoint.

### Setting a default target URL (SAML 1.x)

SAML 1.x service provider (SP) connections require that a default target URL be specified for a scenario where the identity provider (IdP) application does not include one in its single sign-on (SSO) request. This default URL represents the destination on the SP where the user will be directed.

### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

## Steps

1. Enter default destination in the **Default Target URL** field.
2. Click **Next** to save your setting.

## Result

If you are editing an existing connection, you update the target destination. You must always define a default destination when configuring a SAML 1.x SP connection.

### *Specifying the WS-Trust version*

You can specify whether to use WS-Trust version 1.2 or 1.3 for tokens. The default version is 1.2.

### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

## Steps

1. From the **WS-Trust Version** drop-down list, select version **1.2** or **1.3**.



### Note:

For version 1.3, the response is always a `RequestSecurityTokenResponseCollection` object, as in the following example.

```
<wst:RequestSecurityTokenResonseCollection xmlns:wst="http://docs.oasis-open.org/ws-sx/ws-trust/200512/">
```

For more information about WS-Trust version 1.3, see [OASIS WS-Trust 1.3 Standards](#).

2. Click **Next** to save your changes.

### *Defining a service URL (WS-Federation)*

On the **Service URL** tab, you can enter the WS-Federation protocol endpoint of your service provider (SP) partner where PingFederate will send single sign-on (SSO) tokens and single logout (SLO) cleanup messages.

### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

### About this task

The SSO tokens are transmitted within a Request for Security Token Response (RSTR) message in response to a request for authentication from the SP. SLO cleanup messages are sent to your partner when PingFederate, as the identity provider (IdP), receives a user's SLO request. These cleanup messages indicate that the user's local session has been terminated.

To protect against session token hijacking, you can specify additional allowed domains and paths on this window. If the option to validate **wreply** for SLO is enabled, these additional domains and paths will also be taken into consideration as well. For more information, see [Managing partner redirect validation](#) on page 696.

Some federation use cases might require additional customizations in the RSTR message sent from the PingFederate IdP server to the SP. You can use OGNL expressions to fulfill these use cases.

## Steps

1. On the **Service URL** tab, enter the WS-Federation protocol endpoint at the SP site in the **Endpoint URL** field.

You can enter a relative path (begin with a forward slash) if you have provided a base URL on the **General Info** tab. For more information, see *Identifying the SP* on page 449.

2. Optional: Specify additional allowed domains and paths.
  - a. Indicate whether to mandate secure connections when this resource is requested under **Require HTTPS**.

 **Important:**

This selection is recommended to ensure that the validation will always prevent message interception for this type of potential attack, under all conceivable permutations.

This check box is selected by default.

- b. Enter the expected domain name or IP address of this resource under **Valid Domain Name**.

Enter a value without the protocol, such as `example.com` or `10.10.10.10`.

Prefix a domain name with a wildcard followed by a period to include subdomains using one entry. For instance, `*.example.com` covers `hr.example.com` or `email.example.com` but not `example.com`, the parent domain.

 **Important:**

While using an initial wildcard provides the convenience of allowing multiple subdomains using one entry, consider adding individual subdomains to limit the redirection to a list of known hosts.

- c. Optional: Enter the exact path of this resource under **Valid Path**.

Start with a forward slash, without any wildcard characters in the path. If left blank, any path under the specified domain or IP address is allowed. This value is case-sensitive. For instance, `/inbound/Consumer.jsp` allows `/inbound/Consumer.jsp` but rejects `/inbound/consumer.jsp`.

You can allow specific query parameters with or without a fragment by appending them to the path. For instance, `/inbound/Consumer.jsp?area=West&team=IT#ref1001` matches `/inbound/Consumer.jsp?area=West&team=IT#ref1001` but not `/inbound/Consumer.jsp?area=East&team=IT#ref1001`.

- d. Optional: Select the check box under **Allow Any Query/Fragment** to allow any query parameters or fragment for this resource.

Selecting this check box also means that no query parameter and fragment are allowed in the path defined under **Valid Path**.

This check box is not selected by default.

- e. Click **Add**.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Use the **Delete** and **Undelete** workflow to remove an existing entry or cancel the removal request.

- f. Repeat these steps to define multiple expected resources.

 **Note:**

The display order does not matter. A more specific match is considered a better match and an exact match is considered the best match.

3. Optional: Customize messages using OGNL expressions.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- a. Click **Show Advanced Customizations**.
- b. Select a message type from the list.
- c. Enter an OGNL expression to fulfill your use case.



**Note:**

For more information about **Message Type**, available variables, and sample OGNL expressions, see [Customizing assertions and authentication requests](#) on page 390.

- d. Click **Add**.
  - e. Optional: Repeat to add another message customization.
4. Click **Next** to save your changes.

## Result

If you are editing an existing connection, you can reconfigure any items, which might require additional configuration changes in subsequent tasks.

### *Specifying SLO service URLs (SAML 2.0)*

On the **SLO Service URLs** tab, you associate bindings to the endpoints where your service provider (SP) receives logout requests when single logout (SLO) is initiated at your site and where PingFederate sends SLO responses when it receives SLO requests from the SP.

### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

### About this task

This step applies only to SAML 2.0 connections when either SLO profile is selected on the **SAML Profiles** tab. For more information, see [Choosing SAML 2.0 profiles](#) on page 452.

## Steps

1. Select a SAML binding from the list.
2. Enter the SLO endpoint URL to the **Endpoint URL** field.

You can enter a relative path (begin with a forward slash) if you have provided a base URL on the **General Info** tab. For more information, see [Identifying the SP](#) on page 449.

3. Optional: Enter a URL in the **Response URL** field.

When specified, this URL is the location to which SLO logout response messages are sent based on your partner agreement. When omitted, PingFederate sends logout responses to the SLO endpoint URL.

You can enter a relative path (begin with a forward slash) if you have provided a base URL on the **General Info** window. For more information, see [Identifying the SP](#) on page 449.

4. Click **Add**.
5. Optional: Repeat to add additional SLO endpoints.
6. Click **Next** to save your settings.

## Result

If you are editing an existing connection, you can reconfigure the SLO endpoints, which might require additional configuration changes in subsequent tasks.

### *Choosing allowable SAML bindings (SAML 2.0)*

On the **Allowable SAML Bindings** tab, you select the one or more bindings that your service provider (SP) partner can use to send SAML authentication requests or single logout (SLO) messages.

## Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

## About this task

This step applies only to SAML 2.0 connections when the SP-initiated SSO profile or either SLO profile is selected on the **SAML Profiles** tab.

## Steps

1. On the **Allowable SAML Bindings** tab, select the applicable SAML bindings based on your partner agreement.



### **Note:**

If you have specified an Assertion Consumer Service (ACS) or SLO endpoint using the artifact (outbound) binding, you must include SOAP as one of the allowable (inbound) bindings.

2. Click **Next** to save changes and proceed to **Artifact Resolver Locations**. For more information, see [Specifying artifact resolver locations \(SAML 2.0\)](#) on page 478.

## Result

If you are editing an existing connection, you can reconfigure the allowable bindings, which might require additional configuration changes in subsequent tasks.

### *Setting an artifact lifetime (SAML)*

When PingFederate sends an artifact to your service provider (SP)'s SAML ACS endpoint or SAML 2.0 SLO endpoint, an element in the message indicates how long it should be considered valid. On the **Artifact Lifetime** tab, you can specify the expiry information in seconds.

## Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

## About this task

You can change the default value to meet your requirements. You should also consider synchronizing your server clock with your partner's SAML gateway server. If clocks are not synchronized, you might need to set the artifact lifetime to a higher value to prevent latency issues.

## Steps

1. Optional: On the **Artifact Lifetime** tab, override the default value of the **Artifact Lifetime** field. The default value is 60 (seconds).
2. Click **Next** to save your changes.

### *Specifying artifact resolver locations (SAML 2.0)*

When the artifact binding is enabled as one of the allowable bindings on the **Allowable SAML Bindings** tab, you must provide at least one artifact resolution service (ARS) endpoint on the **Artifact Resolver Locations** tab.

#### About this task

The ARD endpoint is where PingFederate sends back-channel requests to resolve artifacts received from the service provider (SP).

#### Steps

1. On the **Artifact Resolver Locations** tab, enter the ARS endpoint URL in the **URL** field.  
You can enter a relative path (begin with a forward slash) if you have provided a base URL on the **General Info** tab. For more information, see [Identifying the SP](#) on page 449.
2. Optional: Enter an integer to the **Index** field for this ACS endpoint.  
The administrative console automatically assigns an index value for each ARS endpoint, beginning with 0. If you want to define your own index values, you must make sure the index values are unique.
3. Click **Add**.
4. Optional: Repeat to add additional ARS endpoints.

**Note:**

When specifying multiple ARS endpoints, each endpoint must share the same transport protocol. That is, if one endpoint uses HTTPS, then all must use HTTPS.

5. After you have entered all of your ARS endpoints, click **Next** to save changes.

#### Result

If you are editing an existing connection, you can reconfigure any ARS endpoints.

### *Defining signature policy (SAML)*

On the **Signature Policy** tab, you can control how digital signatures are used for SAML messages.

#### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

#### About this task

The choices made in this tab depend on your partner agreement and your federation protocol. For more information, see [Digital signing policy coordination](#) on page 97.

#### SAML 2.0

Digital signing is required for SAML response messages sent from the identity provider (IdP) with the POST or redirect binding. Based on the SAML specifications, PingFederate provides three options:

- Select **Always Sign Assertion** to always sign the assertion portion inside the SAML response message.
- Select **Sign Response As Required** to sign the SAML response message per the SAML specifications. This is the default selection.
- Select both to always sign the assertion portion inside the SAML response message for all bindings and to sign the SAML response message per the SAML specifications.

Authentication request messages from the service provider (SP) may also be signed to enforce security. This scenario applies only when the SP-initiated single sign-on (SSO) profile is enabled on the **SAML Profiles** tab. Select **Require Authn Requests to be Signed** to enforce this digital signature requirement. For more information, see [Choosing SAML 2.0 profiles](#) on page 452.

#### SAML 1.x

For SAML 1.0 and SAML 1.1, the assertion portion inside the SAML response message can be digitally signed.

- Select **Always Sign Assertion** to always sign the assertion portion inside the SAML response message.

#### Steps

1. On the **Signature Policy** tab, select the options based on your partner agreement and federation protocol.
2. Click **Next** to save changes.

#### Result

If you are editing an existing connection, you can reconfigure the digital signature policy, which might require additional configuration changes in subsequent tasks.

#### *Configuring XML encryption policy (SAML 2.0)*

For SAML 2.0 configurations, in addition to using signed assertions to ensure authenticity, you and your partner can also agree to encrypt all or part of an assertion to improve privacy. If so, you can configure these settings on the **Encryption Policy** tab.

#### Before you begin

For prerequisites and initial steps for configuring Browser SSO protocols, see [Configuring protocol settings](#) on page 471.

#### About this task



#### Note:

For WS-Fed connections with SAML 2.0 assertions, you cannot encrypt the entire assertion.

| Option                 | Name identifier (SAML_SUBJECT) | Other attributes        | Encrypt the SAML_SUBJECT in SLO messages to the SP                                       | Allow encryption in SLO messages from the SP   |
|------------------------|--------------------------------|-------------------------|--|--|
| None                   | No encryption.                 | No encryption.          | No encryption.   | No encryption.   |
| The entire assertion   | Encrypted.                     | Encrypted.              | Available as an option.  | Available as an option.  |
| One or more attributes | Available as an option.        | Available as an option. | Available as an option only if you select to encrypt the name identifier (SAML_SUBJECT). | Available as an option only if you select to encrypt the name identifier (SAML_SUBJECT). |

#### Steps

1. Select the options based on your partner agreement.

2. Click **Next** to save changes.

## Result

If you are editing an existing connection, you can reconfigure the XML encryption policy, which might require additional configuration changes in subsequent tasks.

### *Reviewing protocol settings*

On the **Summary** tab, you can review and save your protocol settings.

## Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## **Reviewing browser-based SSO settings**

On the **Summary** tab, you can review and save your browser-based single sign-on (SSO) settings.

## Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## **Configuring the Attribute Query profile in an SP connection**

At the Attribute Query step, you configure your connection to respond to requests for user attributes from your partner service provider (SP), if you have chosen this option.

### Before you begin

For prerequisites and previous steps to configure identity provider (IdP) Browser single sign-on (SSO), see [Configure IdP Browser SSO](#) on page 450.

### About this task

For more information about the Attribute Query profile, see [Choosing SP connection options](#) on page 446.

Attribute queries do not depend on SSO, but can be used independently or in conjunction with Browser SSO or provisioning to provide flexibility in how a user authenticates with SP applications. For more information, see [Attribute Query and XASP](#) on page 49.



## Steps

On the **Attribute Query** tab, click **Configure Attribute Query Profile**. See [Defining retrievable attributes](#) on page 481 for next steps.

### Defining retrievable attributes

On the **Retrievable Attributes** window, you specify the user attributes you and your partner have agreed to allow in an attribute query transaction.

### Before you begin

For prerequisites and previous steps to configure the Attribute Query profile, see [Configuring the Attribute Query profile in an SP connection](#) on page 480.

### About this task



#### Note:

The service provider (SP) might not necessarily request all of these attributes in each attribute-query request. Instead, the list simply limits the request to a subset of these attributes.

## Steps

1. On the **Retrievable Attributes** tab, follow these steps to configure your Attribute Query attributes. To add an attribute, enter the attribute name in the text box and then click **Add**.



#### Note:

Attribute names are case-sensitive and must correspond to the attribute names expected by your partner.

2. To modify an attribute name:

| Action                              | Steps  |
|-------------------------------------|--|
| <b>Add an attribute</b>             | Enter the attribute name in the text box. Click <b>Add</b> .                         |
| <b>Modify an existing attribute</b> | Click <b>Edit</b> . Modify the attribute name in the text box. Click <b>Update</b> . |
| <b>Delete an existing attribute</b> | Click <b>Delete</b> .  |

3. Click **Next** to save your changes.

### Configuring attribute lookup

The optional attribute lookup configuration allows you to configure one or more datastores to look up attributes and to set up search parameters.

### Before you begin

For prerequisites and previous steps to configure the Attribute Query profile, see [Configuring the Attribute Query profile in an SP connection](#) on page 480.

### About this task

Attribute sources are specific datastore or directory locations containing information that is returned to the service provider (SP) in response to an attribute request.

## Steps

1. On the **Attribute Sources & User Lookup** tab, you can do the following  
Choose from:
  - To configure an attribute source, click **Add Attribute Source** and complete the setup steps. For more information, see [Choosing a datastore for Attribute Query](#) on page 482.
  - To modify an attribute source configuration, select the attribute source and complete the setup steps.

### **Note:**

Depending on what you change, you might need to modify dependent data in subsequent steps, as indicated.

2. When your attribute sources are configured, click **Next** to save your changes.

## Choosing a datastore for Attribute Query

On the **Data Store** tab, choose a datastore instance for PingFederate to look up attributes.

### Before you begin

For prerequisites and previous steps to configure the Attribute Query profile, see [Configuring the Attribute Query profile in an SP connection](#) on page 480.

### About this task

The process of configuring PingFederate to look up attributes in a datastore for attribute-query responses is similar to that used for single sign-on (SSO) Attribute Sources and User Lookup.

## Steps

1. Enter a **Description** for the datastore in the text box.
  - a. If prompted, enter an **ID** in the text box.
2. Select a datastore instance from the **Active Data Store** list.

### **Tip:**

If the datastore you want is not shown in the **Active Data Store** list, click **Manage Data Stores** to review or add a datastore instance. For more information, see [Datastores](#) on page 936.

3. Depending on the datastore type, the rest of the setup varies as follows.

| Data store type | Required tasks   |
|-----------------|--|
| JDBC            | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying database tables and columns</a> on page 399</li> <li>▪ <a href="#">Entering a database search filter</a> on page 400</li> </ul>  |
| LDAP            | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying directory properties and attributes</a> on page 401</li> <li>▪ <a href="#">Defining encoding for binary attributes</a> on page 403 (optional)</li> <li>▪ <a href="#">Entering a directory search filter</a> on page 404</li> </ul> |

| Data store type | Required tasks  |
|-----------------|---|
| Other           | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying data source filters and fields</a> on page 405</li> </ul> |

 **Important:**

When attribute queries are sent using X.509 Attribute Sharing Profile (XASP), use the variable `${SubjectDN}`—rather than `${SAML_SUBJECT}`—to retrieve the subject identifier.

You can also use any of these distinguished name (DN)-parsing variables:

- `${CN}`
- `${OU}`
- `${O}`
- `${L}`
- `${S}`
- `${C}`
- `${DC}`

If more than one value exists for any of the parsing variables, then they are enumerated. For example, if the Subject DN is `cn=John Smith,ou=service,ou=employee`, then you could use any of these elements in your filter qualifier:

- `${SubjectDN}=cn=John Smith,ou=service,ou=employee`
- `${ou}=service`
- `${ou1}=employee`

For more information about XASP, see [Attribute Query and XASP](#).

4. When you have finished configuring your datastore, click **Next** to save changes.

### Configuring mapping fulfillment for Attribute Query

The last step in configuring an attribute source is to map values into the assertion to be sent in response to an attribute query on the **Attribute Mapping Fulfillment** tab.

Before you begin

For prerequisites and previous steps to configure the Attribute Query profile, see [Configuring the Attribute Query profile in an SP connection](#) on page 480.

Steps

1. For each attribute, select a source from the **Source** list and then choose or enter a value.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the SSO token.

 **Important:**

If you are configuring an SP connection to bridge one or more identity providers to a service provider, consider mapping the original issuer of the assertions into an attribute by selecting **Context** as the source and **Authenticating Authority** as the value. This is important when bridging multiple identity providers to one service provider, where the service provider should take

the information about the original issuer into consideration before granting access to protected resources.

For more information, see [Bridging multiple IdPs to an SP](#) on page 110.

 **Note:**

Because the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values (see **Expression**).

- LDAP/JDBC/Other (when a datastore is used)

Values are returned from your datastore (if used). When you make this selection, the Value list is populated by the attributes from the datastore.

- Expression (when enabled)

This option provides more complex mapping capabilities—for example, transforming incoming values into different formats (see [Attribute mapping expressions](#) on page 225). All of the variables available for text entries (see below) are also available for expressions.

- No Mapping

Select this option to ignore the **Value** field, causing no value selection to be necessary.

- Text

This can be text only, or you can mix text with references to any of the values from your user-datastore using this syntax:

```
${ds.attr-source-id.attribute}
```

where `attr-source-id` is the **Attribute Source ID** value (see [Choosing a datastore for Attribute Query](#) on page 482) and `attribute` is any of the datastore attributes you have selected.

There are a variety of reasons why you might hard code a text value. For example, if your SP's web application provides a service based on your company's name, you might provide that attribute value as a constant.

 **Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use ``${` and `}`` in the default value.

2. Click **Next** to save changes.

### Defining issuance criteria for Attribute Query

Use the **Issuance Criteria** tab to define issuance criteria for the service provider (SP) Attribute Query profile.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.




**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

### Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description  |
|--|--|
| <b>Context</b>                                 | Select to evaluate properties returned from the context of the transaction at runtime.<br><br> <b>Note:</b><br>As the <b>HTTP Request</b> context value is retrieved as a Java object rather than text, attribute mapping expressions are more appropriate to evaluate and return values. |
| <b>JDBC, LDAP, or other types of datastore</b> | Select to evaluate attributes returned from a datastore, if configured.  |
| <b>Mapped Attributes</b>                       | Select to evaluate the mapped attributes.  |

2. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The **Error Result** field is used by the **StatusMessage** element in the SAML response to the SP.

Using an error code in the **Error Result** field allows an application to process the code in a variety of ways; for example, display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions

. For more information, see [Attribute mapping expressions](#) on page 225.

- a. Click **Show Advanced Criteria**.
- b. In the **Expression** field, enter the required expressions.
- c. Optional: In the **Error Result** field, enter an error code or message.



**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Specifying security policy

The **Specify Security Policy** tab allows you to specify the digital signing and encryption policy to which you and your partner have agreed.

About this task



**Note:**

The selections you make on this tab will trigger requirements for setting up Credentials. For more information, see [Configuring credentials](#) on page 487.

Steps

1. Select or clear the check boxes.
2. Click **Next** or **Done**.

### Reviewing the Attribute Query configuration

Review and save your Attribute Query configuration changes on the **Summary** tab.

Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Configuring credentials

The **Credentials** tab provides the launching point for configuring security requirements you might need, depending on the federation protocol you are using and the choices you make.

Steps

- To continue, click **Configure Credentials**.  
See subsequent topics for configuration steps.

## Configuring back-channel authentication (SAML)

Depending on your browser single sign-on (SSO) use cases, the administrative console prompts you to configure authentication requirements for inbound messages, outbound messages, or both.

About this task

See the following table for more information about the back-channel configuration (SAML) authentication requirements.

| Use case  | Back-channel authentication requirements | Back-channel messages                         |
|---|--|---|
| A connection is configured with a SAML ACS endpoint that uses the artifact binding on <b>Protocol Settings # Assertion Consumer Service URL</b> . | Inbound                                  | Artifact resolution requests                  |
| A connection is configured with a SAML 2.0 SLO endpoint that uses the artifact binding on <b>Protocol Settings # SLO Service URLs</b> .           | Inbound                                  | Artifact resolution requests<br>SOAP messages |
| A connection is configured with a SAML 2.0 SLO endpoint that uses the SOAP binding on <b>Protocol Settings # SLO Service URLs</b> .               | Outbound                                 | SOAP SLO messages                             |
| The SAML 2.0 Artifact binding is enabled on <b>Protocol Settings # Allowable SAML Bindings</b> .  | Outbound                                 | Outbound artifact resolution requests         |
| The SOAP binding is enabled on <b>Protocol Settings # Allowable SAML Bindings</b> .   | Inbound                                  | Inbound SOAP messages                         |
| The SAML 2.0 Attribute Query profile is enabled on the <b>Connection Options</b> tab.   | Inbound                                  | Inbound Attribute Query requests              |

Steps

- See subsequent topics for configuration steps.

### *Configuring authentication requirements for outbound messages*

You can configure the authentication requirements used to validate outbound messages in PingFederate.

Steps

1. On the **Back-Channel Authentication** tab, in the **Send to your partner** section, click **Configure**.
2. On the **Outbound SOAP Authentication Type** tab, choose one or more authentication methods.

#### HTTP Basic

When selected, the administrative console prompts you to enter the credentials on the **Basic SOAP Authentication (Outbound)** tab.

You must obtain these credentials from your partner.

#### SSL Client Certificate

Applicable only if you specify an endpoint that uses HTTPS.

When selected, the administrative console prompts you to specify your client certificate on the **SSL Authentication Certificate** tab. If you have not yet created or imported the client certificate, click **Manage Certificates** to do so. For more information, see .



**Important:**



When exporting this client certificate for your partner, choose the **Certificate Only** option.

#### Digital Signature (Browser SSO profile only)

You select a signing certificate on the **Digital Signature Settings** tab.

This option leverages on the digital signature of the message.

#### Perform validation on partner's SSL server certificate when SSL used

By default, validates your partner's HTTPS server certificate, verifying that the certificate chain is rooted by a trusted certificate authority (CA) and that the hostname matches the certificate's common name (CN).

Clear the associated check box if you do not want this validation to occur.

These options can be used in any combination or independently.

3. On the **Summary** tab, review your configuration and perform one of the following tasks.

#### Amend your configuration

Click the corresponding tab title and then follow the configuration wizard to complete the task.

#### Keep your changes

Click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

#### Discard your changes

Click **Cancel**.

#### *Configuring authentication requirements for inbound messages*

You can configure the authentication requirements used to validate inbound messages in PingFederate.

#### Steps

1. On the **Back-Channel Authentication** tab, in the **Received from your partner** section, click **Configure**.
2. On the **Inbound Authentication Type** tab, choose one or more authentication methods.

#### HTTP Basic

When selected, the administrative console prompts you to enter the credentials on the **Basic SOAP Authentication (Inbound)** tab.



#### Important:

If you are configuring more than one connection that uses the artifact or HTTP profile, you must ensure that the username is unique for each connection. You must communicate these credentials to your partner out-of-band.

#### SSL Client Certificate

When selected, the administrative console prompts you to specify the trust model and the related certificate settings on subsequent windows. See the next step.

### Digital Signature (Browser SSO profile only)

You select a signing certificate on the **Signature Verification Settings** tab.

This option leverages on the digital signature of the message.

### Require SSL

When selected, incoming HTTP transmissions must use a secure channel. This option is selected by default.

You can clear the check box if you do not require a secure channel and client certificate authentication.

For SAML 2.0, use these options in any combination or independently. For SAML 1.x, you must enable HTTP Basic authentication, client certificate authentication, or both. You can also add digital signing to ensure message integrity.

3. If you chose **SSL Client Certificate** in the previous step, select a trust model on the **Certificate Verification Method** tab.

#### Anchored

The partner certificate must be signed by a trusted certificate authority (CA). Optionally, you can also restrict the issuer to a specific Trusted CA to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections. The CA's certificate must be imported into the Trusted CA store on the **Trusted CAs** window..

#### Unanchored

The partner certificate is self-signed or you want to trust a specified certificate.



#### Note:

When anchored certificates are used between partners, certificates can be changed without sending the update to your partner. If the certificate is unanchored, any changes must be promulgated.

For more information, see .

| Trust model | Subsequent steps   |
|-------------|--|
| Anchored    | <p>On the <b>Subject DN</b> tab:</p> <ol style="list-style-type: none"> <li>Enter the <b>subject DN</b> of the certificate.</li> <li>Optionally, select the <b>Restrict Issuer</b> check box and enter the <b>Issuer DN</b> of the certificate.</li> </ol> <div data-bbox="625 1455 669 1499" data-label="Image"> </div> <p><b>Important:</b></p> <p>Consider enabling this option to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections.</p> |
| Unanchored  | <p>On the <b>SSL Verification Certificate</b> tab, select the client certification from your partner.</p> <p>If you have not yet imported the client certificate from your partner, click <b>Manage Certificates</b> to do so. For more information, see .</p>   |

4. On the **Summary** tab, review your configuration and perform one of the following tasks.

Amend your configuration

Click the corresponding tab title and then follow the configuration wizard to complete the task.

Keep your changes

Click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

Discard your changes

Click **Cancel**.

### Configuring digital signatures for service provider connections

Digital signing is required for browser-based single sign-on (SSO) tokens and single logout (SLO) messages sent through POST or redirect bindings.

About this task

Digital signing is also required for WS-Trust STS service provider (SP) connections, for signing the outbound SAML security tokens.

 **Remember:**

Configuring digital signatures for SP connections is just one step in configuring an SP connection. For more information, see [SP connection management](#) on page 440.

For browser-based SSO, digital signing is not always required for profiles using the artifact or SOAP bindings unless you chose to sign the SAML assertion on **Protocol Settings # Signature Policy**, or the artifact resolution messages on **Back-Channel Authentication # Outbound SOAP Authentication Type**.

If digital signing is not required, PingFederate does not show the **Digital Signature Settings** tab.

Steps

1. On the **Digital Signature Settings** tab, select the certificate that you will use to sign the SSO tokens and SLO messages for the SP.
2. Select a signing certificate from the **Signing Certificate** list.

If you have not yet created or imported your certificate into PingFederate, click **Manage Certificates**. For more information, see [Manage digital signing certificates and decryption keys](#) on page 667.

 **Note:**

For WS-Federation connections using JSON Web Tokens (JWTs), only EC and RSA certificates are supported. RSA certificates must have a minimum key size of 2,048 bits. The **Signing Certificate** list automatically filters out certificates that do not meet these requirements.

- Optional: Select a **Secondary Signing Certificate** for inclusion in the connection metadata.

**Note:**

You can't add a secondary certificate if the primary certificate has certificate rotation enabled. Also, you can't use a certificate that has rotation enabled as the secondary signing certificate.

**Tip:**

To deselect an existing secondary signing certificate, select **-SELECT-** in the **Secondary Signing Certificate** list. You can then delete the certificate by clicking **Manage Certificates** and selecting **Delete** from the **Actions** list.

- Optional: Select the **Include the certificate in the signature <KeyInfo> element** check box if you have agreed to send your public key with the message.

**Note:**

For WS-Trust STS, the <KeyInfo> element in the SAML token includes a reference to the certificate rather than the full certificate by default unless this check box is checked.

**Note:**

This step is not applicable to WS-Federation connections using JWTs.

Select the **Include the raw key in the signature <KeyValue> element** check box if your partner agreement requires it.

- Optional: Select the signing algorithm from the list.

The default selection is **RSA SHA256** or **ECDSA SHA256**, depending on the **Key Algorithm** value of the selected digital signing certificate. Make a different selection if you and your partner have agreed to use a stronger algorithm.

### Configuring signature verification settings (SAML 2.0)

You can configure the signature verification settings for the certificates in the PingFederate administrative console.

#### About this task

Depending on your partner agreement, digital signature processing might be required.

If you choose to require digital signatures on SAML 2.0 authentication requests on **Protocol Settings # Signature Policy** or inbound messages on **Back-Channel Authentication # Inbound Authentication Type**, you must configure the required certificate information that PingFederate can use to verify the signed messages.

The **Signature Verification Settings** tab is the launching point for this task. If digital signature verification is not required, the **Signature Verification Settings** tab is not shown.

#### Steps

- On the **Signature Verification Settings** tab, click **Manage Signature Verification Settings**.
- On the **Trust Model** window, select a trust model on the **Certificate Verification Method** tab.

Anchored

The partner certificate must be signed by a trusted certificate authority (CA). Optionally, you can also restrict the issuer to a specific Trusted CA to mitigate potential man-in-the-middle attacks and provide a means to isolate certificates used by different connections. The CA's certificate must be imported into the PingFederate Trusted CA store on **Security # Certificate & Key Management # Trusted CAs**.



**Important:**

If you are using the redirect binding for single logout (SLO), you cannot use anchored certificates because SAML 2.0 does not permit certificates to be included using this transport method.

### Unanchored

The partner certificate is self-signed or you want to trust a specified certificate.





**Note:**

When anchored certificates are used between partners, certificates can be changed without sending the update to your partner. If the certificate is unanchored, any changes must be promulgated.

For more information, see [Digital signing policy coordination](#) on page 97.

| Trust model | Subsequent steps   |
|-------------|--|
| Anchored    | <p>On the <b>Subject DN</b> tab:</p> <ol style="list-style-type: none"> <li>a. Enter the <b>subject DN</b> of the certificate or extract it from your service provider (SP) partner's certificate if the certificate is stored on an accessible file system.</li> <li>b. Optionally, select the <b>Restrict Issuer</b> check box and enter the <b>Issuer DN</b> of the certificate. Alternatively, extract it from your partner's certificate.</li> </ol> <div data-bbox="630 1251 672 1297" data-label="Image"> </div> <p><b>Important:</b></p> <p>You can enable this option to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections.</p> |

| Trust model | Subsequent steps  |
|-------------|---|
| Unanchored  | <p>On the <b>Signature Verification Certificate</b> tab:</p> <ol style="list-style-type: none"> <li>Select a certificate from the list.</li> </ol> <p>If you have not yet imported the certificate from your partner, click <b>Manage Certificates</b> to do so. For more information, see <a href="#">Managing certificates from partners</a> on page 681.</p> <ol style="list-style-type: none"> <li>Optionally, select additional certificates.</li> </ol> <div data-bbox="613 451 1466 655" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When configured, PingFederate considers a digital signature valid so long as it can verify the signature using one of the certificates from this list.</p> </div> <div data-bbox="613 676 1466 1056" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>This is useful in situations where your partner has sent you a certificate to replace the current certificate. Adding this second certificate allows PingFederate to continue validating digital signatures as the partner switches to the new signing certificate.</p> <p>It also adds support for scenarios where your partner uses a pool for certificates to sign its messages. Adding these certificates ensures digital signatures can be validated as the partner rotates its signing certificates.</p> </div> |

- On the **Summary** tab, review your configuration and perform one of the following tasks.

#### Amend your configuration

Click the corresponding tab title and then follow the configuration wizard to complete the task.

#### Keep your changes

Click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

#### Discard your changes

Click **Cancel**.

### Selecting an encryption certificate

For browser-based single sign-on (SSO), if you choose to encrypt all or part of an SSO assertion on **Protocol Settings # Encryption Policy**, you must identify the certificate that PingFederate can use to do so.

#### About this task

You must also select a certificate if your requirements include encrypting an assertion in response to an attribute query on **Attribute Query # Security Policy**.

For WS-Trust security token service (STS), this configuration is also required if you enabled the **Generate Key for SAML Holder of Key Subject Confirmation Method** or **Encrypt SAML 2.0 Assertion** option, or both, on **WS-Trust # Protocol Settings**.

If encryption is not required, the **Select XML Encryption Certificate** tab is not shown.

#### Steps

1. Optional: Select an option under **Block Encryption Algorithm**.

#### **Important:**

Because of the import restrictions of some countries, Oracle Server Java SE Runtime Environment (JRE) 8 has built-in restrictions on available cryptographic strength (key size). To use larger key sizes, enable the Java Cryptography Extension (JCE) unlimited strength jurisdiction policy. For more information, see the Java 8 release notes in Oracle's documentation.

For Oracle Java SE Development Kit 11, the JCE jurisdiction policy defaults to unlimited strength. For more information, see the Oracle JDK Migration Guide in Oracle's documentation.

The default selection is **AES-128**.

For more information about XML block encryption and key transport algorithms, see XML Encryption Syntax and Processing from W3C.

2. Select an option under **Key Transport Algorithm**.

#### **Note:**

Due to security risks associated with the RSA-v1.5 algorithm used for key transport, it is no longer available for new connections. Existing connections in which this algorithm is configured continue to support it. However, you should upgrade such connections to use the newer algorithm **RSA-OAEP**.

The default selection is **RSA-OAEP**.

3. Select a partner certificate from the list.

If you have not imported the certificate from your partner, click **Manage Certificates** to do so. For more information see [Managing certificates from partners](#) on page 681.

#### **Selecting a decryption key (SAML 2.0)**

To enable inbound encryption in PingFederate, you must select a certificate on the decryption key.

#### About this task

When you choose to encrypt the name identifier (**SAML\_SUBJECT**) on **Protocol Settings # Encryption Policy**, you can also allow the service provider (SP) to encrypt the name identifier in its single logout (SLO) requests, if the SP-initiated single sign-on (SSO) profile is enabled for the connection. To enable this inbound encryption, you must specify at least one certificate on the **Select Decryption Keys** tab.

If decryption is not required, the **Select Decryption Keys** window is not shown.

#### Steps

1. Select the primary XML decryption key from the list.

If you have not created or imported your certificate into , click **Manage Certificates**. For more information, see .

2. Optional: Select the secondary XML decryption key from the list.

## Reviewing SP credential settings

You can review, modify, save, and discard changes to your service provider (SP) credential settings.

### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Configuring outbound provisioning

PingFederate's outbound provisioning allows an [MISSING glossAcronymn or glossSurfaceform for gIDP] to create and maintain user accounts at standards-based partner sites using [MISSING glossAcronymn or glossSurfaceform for gSCIM] as well as select-proprietary provisioning partner sites that are protocol-enabled.

### About this task

In the **SP Connections** window, configure outbound provisioning. For more information, see [Outbound provisioning for IdPs](#) on page 106.




#### Note:

This configuration task is presented in the administrative console only when you enable the **Outbound Provisioning** protocol. For more information, see [Choosing an SP connection type](#) on page 445.

### Steps

- **Go to Applications # Integration # SP Connection.** To continue, click **Configure Provisioning**.





## Defining a provisioning target

You can define a provisioning target, including the provider's web-service endpoint for provisioning users and, if required, credentials that PingFederate uses for authentication to the provisioning API for the service provider (SP).

### About this task



#### Note:

The target configuration settings vary among System for Cross-domain Identity Management (SCIM) outbound provisioning and various software as a service (SaaS) provisioning.

For SCIM provisioning to PingOne for Enterprise, sign on to the [PingOne admin portal](#) and review the target information on the **Setup # Identity Repository** tab.

For any SaaS Connector target, see documentation in the add-on distribution package.

The following steps describe the fields required for the bundled PingFederate provisioning plugin for SCIM partners.

### Steps


1. Enter the endpoint for managing users in the **Users Resource URL** field, such as, `https://example.com/v1/Users`.

This field is always required for SCIM outbound provisioning.

2. Go to **Applications # Integration # SP Connections # SP Connection # Configure Channels**.
3. On the **Custom SCIM Attributes** tab, configure the rest of the outbound provisioning settings.

See the following table for detailed information about each field.

| Field               | Description  |
|---------------------|--|
| Groups Resource URL | The partner's group management endpoint. For example, <code>https://example.com/v1/Groups</code> .<br><br>Required if the partner supports this notion and groups should be provisioned. |

| Field  | Description   |
|--|---|
| Authentication Method                            | <p>The authentication scheme that the partner's endpoints support.</p> <p>Available options:</p> <ul style="list-style-type: none"> <li>▪ <b>None</b></li> <li>▪ <b>Basic Authentication</b> (Default)</li> <li>▪ <b>OAuth 2.0 Bearer Token</b> - Uses the resource owner grant type by submitting the client ID, client secret, username, and password to the configured token endpoint URL in exchange for an access token that will be sent in each SCIM request.</li> </ul>   |
| User, and Password                               | <p>Valid credentials to access the partner's endpoint.</p> <p>Required if <b>Basic Authentication</b> is the selected authentication method.</p>  |
| Client ID, Client Secret, and Token Endpoint URL | <p>Valid OAuth client credentials and token endpoint to access the partner's endpoint.</p> <p>Required if <b>OAuth 2.0 Bearer Token</b> is the selected authentication method.</p>  |
| SCIM SP Supports Patch Updates                   | <p>Clear this check box if the partner does not support PATCH updates.</p> <p>For information about PATCH, see the <a href="http://www.simplecloud.info/specs/draft-scim-api-01.html#edit-resource-with-patch">SCIM specification</a> (www.simplecloud.info/specs/draft-scim-api-01.html#edit-resource-with-patch).</p> <p>This check box is selected by default.</p>   |
| Provision Groups with Distinguished Name         | <p>Select this check box to provision groups by supplying complete LDAP distinguished names (DNs), rather than only common names (CNs), to identify groups.</p> <p>Some SCIM partners, including PingOne for Enterprise, allow administrators to parse full DN's when necessary, such as in the case of duplicate CNs, to determine group access mapping to specific applications based on other DN elements. Consult the partner for its requirement.</p> <p>This check box is selected by default.</p>  |
| Deprovision Method                               | <p>Deprovisioning is triggered when previously provisioned users no longer meet the condition set in <b>Manage Channels # Channel # Source Location</b>.</p> <p>Available options:</p> <ul style="list-style-type: none"> <li>▪ <b>Disable User</b> (Default)<br/>This option deactivates the user accounts.</li> <li>▪ <b>Delete User</b><br/>This option removes the user accounts.</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>For SaaS provisioning, the provisioner does not necessarily remove deprovisioned users from target data stores in accordance with common practice. Rather their status is changed to indicate that the accounts are no longer active.</p> </div> |

| Field                 | Description  |
|-----------------------|--|
| Rate Limit Error Code | The expected error code returned by the partner based on its rate-limiting threshold.<br><br>The default value is 429. |

4. Click **Next**.



**Note:**

For some provisioning plugins, including the built-in SCIM outbound provisioner, when you enter or change credentials and click **Next**, PingFederate immediately tests connectivity to the target.

### Specifying custom SCIM attributes

You can configure simple, multivalued, and complex custom System for Cross-domain Identity Management (SCIM) attributes in PingFederate.

About this task

supports SCIM attributes in the core schema and custom attributes through a schema extension.



**Note:**

Custom attributes are optional. If your use case does not require any additional attributes, click **Next** on the **Custom SCIM Attributes** tab.

To support custom attributes, you must specify the schema extension and the custom attributes in the connection. There are four attribute types:

- Simple attributes
- Simple multivalued attributes
- Complex attributes
- Complex multivalued attributes

The following fragment illustrates a SCIM message supporting schema extension

`urn:scim:schemas:extension:custom:1.0` with four attributes, one of each attribute type. The table afterward describes the details of each attribute.


```
{
  "userName": "CBrown",
  "active": true,
  "schemas": [
    "urn:scim:schemas:core:1.0",
    "urn:scim:schemas:extension:custom:1.0"
  ],
  ...
  "urn:scim:schemas:extension:custom:1.0": {
    "supervisor": "JSmith",
    "territories": [
      "Montana",
      "Idaho",
      "Wyoming"
    ],
    "options": {
      "quantity": "10000",
      "strike": "5.25",
      "first": "2017-12-01",
      "last": "2025-03-31"
    }
  }
}
```

```

    },
    "tablets": [
      {
        "model" : "8086",
        "serial" : "5500-2020-965",
        "type" : "office"
      },
      {
        "model" : "8088",
        "serial" : "5500-2040-151",
        "type" : "remote"
      }
    ]
  }
}

```

| Attribute Name     | Attribute Type      | Sub-Attributes (Complex)   |
|--------------------|---------------------|--|
| <b>supervisor</b>  | Simple              | Not applicable   |
| <b>territories</b> | Simple multivalued  | Not applicable   |
| <b>options</b>     | Complex             | <b>quantity</b> , <b>strike</b> , <b>first</b> , and <b>last</b> |
| <b>tablets</b>     | Complex multivalued | <b>model</b> , <b>serial</b> , and <b>type</b> .                 |

 **Note:**

**type** is a reserved sub-attribute for a complex multivalued attribute.

**Tip:**

For more information about SCIM and attribute types, see the website [www.simplecloud.info](http://www.simplecloud.info).


## Steps

1. Go to **Applications # Integration # SP Connection # Configure Channels**. Specify the URI of the schema extension in the **Extension Namespace** field.





**Tip:**




The default value is `urn:scim:schemas:extension:custom:1.0`. You can keep this value if your partner identifies custom attributes by this URI in its SCIM messages.

2. Enter an attribute name and click **Add** to add a custom attribute.  
Repeat this step to add more custom attributes as needed.

 **Tip:**  
Use the **Delete** and **Undelete** workflow to remove or cancel the removal request of existing custom attributes.

3. Click **Edit** next to the custom attribute to perform one of the following tasks.

|   |  |
|---|--|
| <p><b>Change the attribute name</b></p>   | <p>a. Replace the current value in the Name field.<br/>b. Click <b>Done</b>.</p>    |
| <p><b>Set the attribute as a simple multivalued attribute</b></p>                         | <p>a. Select the <b>Is Multivalued</b> check box.<br/>b. Click <b>Done</b>.</p>    |
| <p><b>Add sub-attributes to make the attribute a complex attribute</b></p>                | <p>a. Enter a sub-attribute and click <b>Add</b>. Repeat this step to add more sub-attributes as needed.<br/>b. Use the <b>Edit</b>, <b>Update</b>, and <b>Cancel</b> workflow to make or undo a change to the name of a sub-attribute. Use the <b>Delete</b> and <b>Undelete</b> workflow to remove a sub-attribute or cancel the removal request.<br/>c. Click <b>Done</b>.</p>   |
| <p><b>Add sub-attributes and set the attribute as a complex multivalued attribute</b></p> | <p>a. Enter a sub-attribute and click <b>Add</b>. Repeat this step to add more sub-attributes as needed.</p> <div data-bbox="581 1606 1469 1806" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b><br/>Use the <b>Edit</b>, <b>Update</b>, and <b>Cancel</b> workflow to make or undo a change to the name of a sub-attribute. Use the <b>Delete</b> and <b>Undelete</b> workflow to remove a sub-attribute or cancel the removal request.</p> </div> <p>b. Select the <b>Is Multivalued</b> check box.</p> |

|   |  |
|---|--|
| <p><b>Change the attribute name</b></p> | <p><b>a. Replace the current value in the Name field.</b><br/> <b>b. Click Done.</b></p>    |
|   | <p><b>c. Specify at least one value under the <b>Types</b> column for <b>type</b>, a reserved sub-attribute for a complex multivalued attribute.</b></p> <div data-bbox="586 512 1464 716" style="border: 1px solid black; padding: 10px;"> <p> <b>Tip:</b></p> <p>Use the <b>Edit</b>, <b>Update</b>, and <b>Cancel</b> workflow to make or undo a change to the <b>type</b> value. Use the <b>Delete</b> and <b>Undelete</b> workflow to remove a <b>type</b> value or cancel the removal request.</p> </div> <p><b>d. Click Done.</b></p>  |

## Managing channels

You can use the PingFederate administrative console to add, modify, and delete provisioning channels.

### About this task


A provisioning channel is a mapping configuration between user attributes contained in a source user store and attributes supported or required by the targeted software-service application. You can have multiple channels to the same target as needed, such as if your organization has separate LDAP stores, or different nodes in the same store, for various user groups needing single sign-on (SSO) access and provisioning to the same domain.

### **Important:**

If two different channels have the same group name, the provisioning channel will overwrite the group members in the other channel. For example, channel1 reads from AD1 where user1 is in a group named "Admins," and channel2 reads from AD2 where user2 is in a group also named "Admins." When group membership is provisioned to the same target, channel2 will overwrite the data provisioned by channel1 for the "Admins" group so that user2 will now be in "Admins" in the target.

### **Tip:**

There can be only one provisioning target per connection. If your organization subscribes to multiple provisioning targets for which you need provisioning support, you need a separate service provider (SP) connection for each provisioning target.



Go to **Applications # Integration # SP Connection # Configure Channels**. On the **Manage Channels** tab, you can perform the following tasks:

### Steps

- To add a new channel, click **Create**.

Alternatively, you can create a new channel by copying an existing channel and making other required changes.

- To modify existing channel settings, select an existing channel.
- To remove or cancel the removal request of the existing channel, use the **Delete** and **Undelete** workflow.

### Specifying channel information


When configuring channels in PingFederate, you can specify channel information such as the channel name, max threads, and timeout.

### About this task

On the **Channel Info** tab, specify a unique identifier for the channel and adjust the values for the **Max Threads** and **Timeout** fields as needed to optimize data-transfer performance, particularly if large numbers of records need to be provisioned at the target site. The **Max Threads** and **Timeout** settings apply to the phase of provisioning when PingFederate is pushing updates to the provisioning target.

The **Max Threads** setting determines how many threads PingFederate can use to send updates to the target. Using multiple threads should let PingFederate finish this provisioning phase faster. There is no particular order in which PingFederate processes updates. Each thread pulls the user and group update operations from a queue. As soon as a thread finishes one operation, it pulls another operation from the queue. Eventually there will be no more operations in the queue, so all threads will finish at close to the same time, but not exactly.

The **Timeout** setting determines how long PingFederate has to update a record. If PingFederate takes too long to update a record, it moves to the next record. During the next provisioning cycle, PingFederate will try again to update the skipped record.



### Steps

- Go to **Applications # Integration # SP Connection # Configure Channels # Channel**. In the **Channel Name** field, enter a channel name.

If you are copying a channel, you must enter a new value in this field.

- Optional: Update the values for the **Max Threads** and **Timeout** fields.

The **Timeout** value applies only when the **Max Threads** value allows multiple threads.

- Click **Next**.


## Identifying the source datastore

You can identify the source datastore for the service provider (SP) channel configuration in the PingFederate administrative console.

### About this task

PingFederate supports PingDirectory, Microsoft Active Directory, Oracle Unified Directory, and Oracle Directory Server as source user repositories for outbound provisioning. However, you can use other types of LDAP servers, either identifying them as **Generic** or registering them with PingFederate. For more information, see the `sample.template.txt` in the `<pf_install>/pingfederate/server/default/conf/template/ldap-templates` directory.

Information from your user-datastore is used to supply mapped values for each user attribute required by the service provider (SP).



### Steps

1. Go to **Applications # Integration # SP Connections # SP Connection # Configure Channels # Channel**.
2. On the **Source** tab, choose the LDAP store to use for this channel.  
If the datastore you want is not shown in the list, PingFederate is not configured to access the store. To create a connection to the datastore, click **Manage Data Stores**.
3. Click **Next**.

## Modifying source settings

You can modify the source settings for the datastore configuration in the PingFederate administrative console. You can add, change, and remove user information.

### About this task

The **Source Settings** tab shows the default configuration of the datastore selected on the **Source** tab, including settings used by the PingFederate provisioner to determine when user information is added, changed, or removed.



SP Connection | Configure Channels | Channel

Channel Info | Source | **Source Settings** | Source Location | Attribute Mapping | Activation & Summary

Enter or modify LDAP settings that apply to the source user data store, as needed. Note that these fields are preconfigured with default settings based on the LDAP Type, when specified (see documentation). For most LDAP Directory installations, the default settings can be used.

**Data Source**

DATA SOURCE: ldaps2.pt.ping-eng.com

DATA SOURCE DESCRIPTION: Active Directory

LDAP TYPE: ActiveDirectory

**Identity**

ENTRY GUID ATTRIBUTE: objectGUID

GUID TYPE: Binary

**Group Membership Detection**

MEMBER OF GROUP ATTRIBUTE: memberof

GROUP MEMBER ATTRIBUTE: member

**Change Detection**

USER OBJECT CLASS: user

GROUP OBJECT CLASS: group

CHANGED USERS/GROUPS ALGORITHM: Active Directory USN

USN ATTRIBUTE: usnChanged

TIMESTAMP ATTRIBUTE: modifyTimestamp

**Account Management**

ACCOUNT STATUS ATTRIBUTE: userAccountControl

ACCOUNT STATUS ALGORITHM: Active Directory Bitmap


DEFAULT STATUS: true

FLAG COMPARISON VALUE:

FLAG COMPARISON STATUS: false

See the following table for more information about each field.

| Field                     | Description   |
|---------------------------|---|
| Entry GUID Attribute      | The name of the attribute in the datastore representing the user's GUID.  |
| GUID Type                 | Indicates whether the GUID is stored in binary or text format. Microsoft Active Directory is always binary. Other LDAP stores most often use text.<br><br>If binary is selected, ensure that the entered Entry GUID Attribute is set as a binary attribute in the source LDAP datastore. For more information, see <a href="#">Setting advanced LDAP options</a> on page 945.   |
| Member of Group Attribute | A multivalued user attribute containing the distinguished names (DNs) of the groups to which an entry belongs. This attribute only applies to some LDAP servers, such as Microsoft Active Directory. When this attribute doesn't apply, the Group Member Attribute is used instead. Microsoft Active Directory use both values to provide a two-way mapping between user and group objects.                                   |
| Group Member Attribute    | The name of a multivalued group attribute used to track membership in the group using either DN or GUID values.   |
| User objectClass          | The LDAP object class to which user entries belong, used to restrict search results to user entries only. The default value is: <ul style="list-style-type: none"> <li>▪ inetOrgPerson if the <b>Data Source</b> is PingDirectory</li> <li>▪ person if the <b>Data Source</b> is Oracle Directory Server or Oracle Unifier Directory</li> <li>▪ objectGUID if the <b>Data Source</b> is Microsoft Active Directory</li> </ul> |

| Field                          | Description   |
|--------------------------------|---|
| Group objectClass              | The LDAP object class to which group entries belong, used to restrict search results to group entries only.   |
| Changed Users/Groups Algorithm | <p>The method by which PingFederate determines if user records have been updated or new records added, thus requiring provisioning updates at the target site. The three choices are:</p> <ul style="list-style-type: none"> <li>▪ <b>Active Directory USN</b> – For Microsoft Active Directory only, this algorithm queries for update sequence numbers on user records that are larger than the last time records were checked.</li> <li>▪ <b>Timestamp</b> – Queries for timestamps on user records that are not older than the last time records were checked. This check is more efficient from the perspective of the PingFederate provisioner but can be more time consuming on the LDAP side, particularly with Oracle Unified Directory and Oracle Directory Server.</li> <li>▪ <b>Timestamp No Negation</b> – Queries for timestamps on user records that are newer than the last time records were checked. This algorithm is recommended for Oracle Unified Directory and Oracle Directory Server.</li> </ul> |
| USN Attribute                  | The name of the attribute used to store the update sequence number. Applicable when the Microsoft Active Directory algorithm is chosen in the row above.  |
| Timestamp Attribute            | The name of the attribute used to store the timestamp on user records.  |
|                                | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This attribute name is case-sensitive. Ensure the attribute name matches the name your directory uses. For example, in PingDirectory and Oracle, the attribute is <code>modifyTimestamp</code>, but in Microsoft Active Directory, the attribute is <code>modifyTimeStamP</code>. They have different capitalization.</p> </div>  |
| Account Status Attribute       | The name of the attribute in which the user's account status, active or inactive, is stored. For example, Microsoft Active Directory = <code>userAccountControl</code> and Oracle Directory Server = <code>nsaccountlock</code> .   |
| Account Status Algorithm       | <p>The method by which PingFederate determines a user's account status. The values are:</p> <ul style="list-style-type: none"> <li>▪ <b>Active Directory Bitmap</b> for Microsoft Active Directory, which uses a bitmap for each user entry. For more information about <code>userAccountControl</code> flags, see Microsoft's <a href="#">knowledge base</a>.</li> <li>▪ <b>Flag</b>– For Oracle Unified Directory, Oracle Directory Server, and other LDAP directories that use a separate attribute to store the user's status. When this option is selected, the Flag Comparison Value and Flag Comparison Status fields below are also used.</li> </ul>  |
| Default Status                 | Indicates the user's status if the attribute is missing.  |
| Flag Comparison Value          | <p>Indicates the value for the attribute, such as <code>nsaccountlock</code>, that PingFederate expects to be returned. The value is case-sensitive.</p> <p>Used when the Account Status Algorithm is set to <b>Flag</b>.</p>   |

| Field                  | Description   |
|------------------------|---|
| Flag Comparison Status | <p>Indicates whether the user is enabled or disabled when the flag has the value specified in the Flag Comparison Value field. Setting the value to <code>true</code> equals enabled, while setting the value to <code>false</code> equals disabled.</p> <p>For example, if the Account Status Attribute is set to <code>nsaccountlock</code>, and the Flag Comparison Value is set to <code>true</code>, and the Flag Comparison Status is set to <code>false</code>, then any users with <code>nsaccountlock=true</code> are disabled.</p> <p>Used when the Account Status Algorithm is set to <b>Flag</b>.</p> |

If you are using PingDirectory, Microsoft Active Directory, Oracle Unified Directory, or Oracle Directory Server, in most cases no changes are needed on this tab unless your datastore uses a customized schema.

If you are using a different LDAP directory, you must supply the required information on this tab unless you have defined a template for the datastore. For more information, see the `sample.template.txt` in the `<pf_install>/pingfederate/server/default/conf/template/ldap-templates` directory.

### Steps

1. Modify the settings, as needed.
2. Click **Next**.

### Specifying a source location

You can indicate on the **Source Location** tab where PingFederate should look for user records in the datastore.

### About this task

The same location can be used to retrieve user-group distinguished names (DNs) for maintaining corresponding groups at the service provider (SP).

After specifying the required base DN, you can provision users, and groups when applicable, based on group membership information or LDAP search results.



### Note:



Groups provisioning is supported for System for Cross-domain Identity Management (SCIM) and the Google Apps Connector (version 2.0 and higher) but might not be supported for other software as a service (SaaS) Connectors. If not, the associated fields under **Groups** on the **Source Location** tab are inactive. Support for the feature might become available in future SaaS Connector releases. See the documentation in your add-on distribution package.



## Steps

1. Go to **Applications # Integration # SP Connections # Configure Channels # Channel**. In the **Base DN** field, enter the base DN where user records are stored.

PingFederate looks only at this node level, or below it, for user accounts and groups (when applicable) that need to be provisioned based on the conditions set in the next step.

2. Specify group membership information or an LDAP filter to search for users, and groups when applicable, to be provisioned. For more information, see the following table.

| Object | Field description  |
|--------|--|
| Users  | <p data-bbox="576 499 706 531"><b>Group DN</b></p> <p data-bbox="576 548 1388 611">The distinguished name (DN) of a group in the user repository whose member groups should be provisioned.</p> <p data-bbox="576 627 1437 785">Optionally, select the <b>Nested Search</b> check box to include users that are members of the specified group through nested group membership. Nested group membership is preserved for SCIM provisioning, and SaaS provisioning if the vendor and the SaaS Connectors support hierarchical structure in groups.</p> <div data-bbox="576 802 1469 1041" style="border: 1px solid #ccc; padding: 5px;"> <p data-bbox="576 821 698 863"> <b>Note:</b></p> <p data-bbox="576 884 1437 1010">The <b>Nested Search</b> feature is available when Microsoft Active Directory, Oracle Unified Directory, or Oracle Directory Server is selected as the source user repository. For more information, see <a href="#">Identifying the source datastore</a> on page 504.</p> </div> <p data-bbox="576 1056 641 1087"><b>Filter</b></p> <p data-bbox="576 1104 1453 1167">An LDAP search filter that returns user objects representing the users that should be provisioned.</p> <p data-bbox="576 1184 1421 1247">For information about LDAP filters, see your LDAP documentation. You might need to escape any special characters.</p> <div data-bbox="576 1264 1469 1404" style="border: 1px solid #ccc; padding: 5px;"> <p data-bbox="576 1283 763 1325"> <b>Important:</b></p> <p data-bbox="576 1346 1388 1377">The <b>Group DN</b> field is ignored when a <b>Filter</b> field value is configured.</p> </div> <p data-bbox="576 1423 1258 1486">If you are using Active Directory, the filter must include <code>objectClass=user</code> for the provisioner to retrieve users.</p> |

| Object                          | Field description   |
|---------------------------------|---|
| <b>Groups</b> (when applicable) | <p data-bbox="573 226 1472 489"> <b>Group DN</b><br/>           The DN of the group in the user repository that should be provisioned.<br/><br/>           Optionally, select the <b>Nested Search</b> check box to include groups that are members of the specified group through nested group membership. Nested group membership is preserved for SCIM provisioning, and SaaS provisioning if the vendor and the SaaS Connectors support hierarchical structure in groups.         </p> <div data-bbox="573 499 1472 730" style="border: 1px solid black; padding: 5px;"> <p data-bbox="581 510 1464 720">  <b>Note:</b><br/>           The <b>Nested Search</b> feature is available when Microsoft Active Directory, Oracle Unified Directory, or Oracle Directory Server is selected as the source user repository. For more information, see <a href="#">Identifying the source datastore</a> on page 504.         </p> </div> <p data-bbox="573 741 1472 951"> <b>Filter</b><br/>           An LDAP search filter that returns group objects representing the groups that should be provisioned.<br/><br/>           For information about LDAP filters, refer to your LDAP documentation. You might need to escape any special characters.         </p> <div data-bbox="573 961 1472 1171" style="border: 1px solid black; padding: 5px;"> <p data-bbox="581 972 1464 1161">  <b>Important:</b><br/>           The <b>Group DN</b> field is ignored when a <b>Filter</b> field value is configured.<br/><br/>           If both the <b>Group DN</b> field and the <b>Filter</b> field are blank, no groups will be provisioned.         </p> </div> |


3. Click **Next**.

### Mapping attributes

Mapping attributes determines how attributes from your user store are mapped to the System for Cross-domain Identity Management (SCIM) attributes in the core schema and custom attributes through a schema extension or to the provisioning fields supported for your organization's software as a service (SaaS) customer account.

#### About this task

Edit the mapping of attributes from the local datastore into fields specified by the service provider (SP).



| Field Name      | Attribute(s)    | Expression | Default | Action |
|-----------------|-----------------|------------|---------|--------|
| Username*       | -sAMAccountName |            |         | edit   |
| Expiration Date |                 |            |         | edit   |
| Entry Name      | -sAMAccountName |            |         | edit   |
| Given Name      | -givenName      |            |         | edit   |

### Important:

If you are provisioning for SCIM, your SP can make one or more optional core attributes mandatory. For more information, see the SCIM documentation from the SP or the SCIM Resource Schema representation.

**Tip:**

For non-SCIM SaaS connectors, PingFederate automatically retrieves from the vendor the **Field Names** shown on this tab, but only on the first pass through the configuration flow. If you are using this configuration to modify an existing mapping configuration, click **Refresh Fields** to synchronize the list with the target if needed.

For each field, the **Attribute Mapping** option provides a means of adding or modifying the mapping details.

**Note:**

All required attributes listed in the **Field Name** column, indicated with asterisks, must be mapped. Click **View Partner Field Specifications** for a summary of requirements for all fields specified for the target partner.

For some fields, PingFederate preselects LDAP attributes commonly used to store the required values.

## Steps

1. Go to **Applications # Integration # SP Connections** to open the **SP Connections** configuration window.
2. To edit an existing SP connection, open an SP connection by clicking on its name in the **Connection Name** column.
3. On the **Outbound Provisioning** tab, click **Configure Provisioning** to open the **Configure Channels** configuration window.

**Note:**

The **Outbound Provisioning** tab is only visible after you go to the **Connection Type** tab, select the **Outbound Provisioning** check box and in the **Type** list, select the type.

4. Go to the **Manage Channels** tab.
5. Select a channel.
6. Go to the **Attribute Mapping** tab.
7. To edit a field, click **Edit** in the **Action** column.

**Tip:**

If you have specified any custom attributes, they are listed at the end of the **Attribute Mapping** configuration.

8. On the **Attribute Mapping** tab, provide mapping details.

**Note:**

To prevent unexpected errors when reading or encoding binary attributes from Microsoft Active Directory (AD), add any AD binary attributes mapped during provisioning to the **LDAP Binary Attributes** list in the Data Store **Advanced LDAP Options**. For more information, see [Setting advanced LDAP options](#) on page 945.

- Repeat steps for each attribute shown in the **Field Name** column as needed.

**Tip:**

For most fields, if you map more than one attribute from your datastore into a single field at the target location, then you must use an OGNL expression to indicate how to combine the attribute values.

The only exception is the **LDAP Attributes Map** field, which is provided primarily to support SCIM attributes specific to PingOne for Enterprise. This field can contain multiple attributes without using OGNL.

- Click **Next**.

*Specifying mapping details*

Define specific mapping information for each field, required or optional, for provisioning as needed.

**CAUTION:**

If end-users at your site are permitted to edit some of their own attributes directly in the LDAP store, ensure that the attributes are restricted and do not include any needed by the service provider to grant permissions.

## Defining mapping information for a standard attribute

## Before you begin

- Go to **Applications # Integration # SP Connections** to open the **SP Connections** configuration window.
- To edit an existing SP Connection, open an SP Connection by clicking on its name in the **Connection Name** column.
- On the **Outbound Provisioning** tab, click **Configure Provisioning** to open the **Configure Channels** configuration window.

**Note:**

The **Outbound Provisioning** tab, is only visible after you select the **OutBound Provisioning** check box and the type in the **Type** list, on the **Connection Type** tab.

- Go to the **Manage Channels** tab.
- Click the name of the channel to edit it.

**Tip:**

If you have specified any custom attributes, they are listed at the end of the **Attribute Mapping** configuration.

## Steps

- On the **Attribute Mapping** tab, click **Edit** in the **Action** column for the **Field Name** whose attributes you want to map.

2. Select the class containing a user-store attribute in the **Root Object Class** column that you want to map to the provisioning attribute shown in the **Field Name** column.

 **Note:**

For some fields, you might not need to map specific user attributes. If so, supply a value in the **Default Value** field, skip this step, and go to step 5. For certain attributes, you can specify LDAP attributes and a default value, as needed.

3. Select the source attribute from the class in the **Attribute** column. Click **Add Attribute**.

 **Note:**

If the selected source attribute is binary, ensure that the selected attribute is set as a binary attribute in the source LDAP datastore. For more information, see [Setting advanced LDAP options](#) on page 945.

4. Repeat the previous steps to add additional applicable attributes to use in a mapping expression.

 **Note:**

You must add an attribute for it to be used in an expression.

5. Optional: If one or more attributes are specified: go to the **Value Definition** section, and in the **Default Value** field, enter or select a default value.


If you have specified any custom attributes, they are listed at the end of the **Attribute Mapping** configuration.

A list appears for this field if the vendor requires a choice among specified values. When an expression is also supplied, the default value is sent during provisioning if an error occurs when evaluating the expression.

6. If more than one attribute is used for mapping fields other than **LDAP Attributes Map**, in the **Value Definition** section, enter an expression.

- a. To create and validate the expression for the **Expression** field, click **Edit**.

7. Select one or more processing options.

| Processing option      | Description  |
|------------------------|--|
| <b>Create Only</b>     | <p>The field is provisioned only once and not subsequently updated.</p> <p> <b>Note:</b></p> <p>For SCIM, the <code>Password</code> attribute should be passed only when creating a user or updating the password. Select <b>Create Only</b> to limit when the <code>Password</code> attribute is passed.</p> |
| <b>Trim</b>            | Removes any white space from the attribute values.   |
| <b>Mask Log Values</b> | Determines whether sensitive information, such as the <code>Password</code> attribute, will be masked in PingFederate log files.   |



| Processing option                               | Description  |
|---|--|
| <b>Upper Case, Lower Case, or None</b>          | Transforms the attribute values to the case indicated unless the default, <b>None</b> option, is selected.                                   |
| <b>Parsing &gt; Extract CN from DN</b>          | For attributes in the form of a distinguished name (DN), such as Group DNs in Active Directory, maps only the common name portion of the DN. |
| <b>Parsing &gt; Extract Username from Email</b> | For attributes containing an email address, maps only the username.  |

8. Click **Done**.

#### Defining mapping information for a custom attribute

##### Steps

1. Select a sub-attribute in the **Attribute** column and list.



**Note:**

Applicable only to complex attributes or complex multivalued attributes, see [Specifying custom SCIM attributes](#) on page 499.

2. Select the class containing a user-store attribute in the **Root Object Class** column that you want to map to the provisioning attribute shown in the **Field Name** column.



**Note:**

For some fields, you might not need to map specific user attributes. If so, supply a value in the **Default Value** field, skip this step, and go to step 5. For certain attributes, you can specify both LDAP attributes and a default value, as needed.

3. Select the source attribute from the class in the **LDAP Attribute** column. Click **Add Attribute**.



**Note:**

If the selected source attribute is binary, ensure that the selected attribute is set as a binary attribute in the source LDAP datastore. For more information, see [Setting advanced LDAP options](#) on page 945.

4. In the **Options** section, select one or more processing options.

| Processing option  | Description  |
|--------------------|--|
| <b>Create Only</b> | <p>The field is provisioned only once and not subsequently updated.</p> <div data-bbox="873 1627 917 1671" data-label="Image"> </div> <p><b>Note:</b></p> <p>For System for Cross-domain identity Management (SCIM), the <code>Password</code> attribute should be passed only when creating a user or updating the password. Select <b>Create Only</b> to limit when the <code>Password</code> attribute is passed.</p> |

| Processing option                               | Description  |
|---|--|
| <b>Trim</b>                                     | Removes any white space from the attribute values.   |
| <b>Mask Log Values</b>                          | Determines whether sensitive information, such as the <code>Password</code> attribute, will be masked in PingFederate log files.             |
| <b>Upper Case, Lower Case, or None</b>          | Transforms the attribute values to the case indicated unless the <b>None</b> option is selected, the default.                                |
| <b>Parsing &gt; Extract CN from DN</b>          | For attributes in the form of a distinguished name (DN), such as Group DNs in Active Directory, maps only the common name portion of the DN. |
| <b>Parsing &gt; Extract Username from Email</b> | For attributes containing an email address, maps only the username.  |

- In the **Default Value** field, enter a default value.
- Click **Add Mapping**.

 **Note:**

For complex attributes or complex multivalued attributes, repeat these steps to map additional sub-attributes as needed.

- Click **Done**.

### Reviewing channel settings

When you finish setting up a channel, you can choose to activate it immediately or activate the channel as needed.

About this task

On the **Activation & Summary** tab, review, activate, deactivate, or save your channel settings.

 **Note:**

A service provider connection must be active for any provisioning channels to be enabled. You can deactivate a channel at any time. When a channel is inactive, provisioning is suspended but single sign-on (SSO) and single logout (SLO) transactions can still occur if an associated connection is active.

### Steps

- Go to **Applications # Integration # SP Connections # SP Connection # Configure Channels # Channel**.
- On the **Activation & Summary** tab, select **Active** or **Inactive** to toggle the status. Click **Save**.

 **CAUTION:**

When a channel is activated, initial provisioning occurs as soon as the synchronization-frequency time period expires. See [Configuring outbound provisioning settings](#) on page 911. The default is 60 seconds. Because initial provisioning can consume considerable processing time, depending on the amount of data that needs to be transmitted, administrators should plan accordingly.

- To modify channel settings, click the associated heading in the **Summary** column.

**Important:**

Click **Save** to save the channel configuration.

**Reviewing SP connection settings**

When you finish creating or modifying a service provider (SP) connection, you can review the connection settings and toggle the connection status.

About this task

On the **Activation & Summary** tab, you can review, amend, discard, or save your changes.

Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

Result

**Important:**

When creating a new connection, the default connection status is **Enabled** when you reach the **Activation & Summary** tab.

Whether you choose to disable a new connection now or later, you must click **Save** on the **Activation & Summary** tab if you want to keep the new connection.

The **SSO Application Endpoint** provides a sample URL at the `/idp/startSSO.ping` application endpoint that webmasters or web application developers at your site can use to invoke single sign-on for the connection. For a list of supported parameters, see [Viewing IdP application endpoints](#) on page 437.

**SP affiliations**

A service provider (SP) affiliation is a SAML 2.0 specification that permits a group of service providers to make use of the same persistent name identifier for account linking.

SP affiliations are useful when multiple SPs share a business relationship in which users need services from each affiliated provider. By agreement among the affiliation members, the same pseudonym can be used to populate the `SAML_SUBJECT` of assertions sent to all of the SP partners contained in this affiliation.

**Note:**

Each connection in the affiliation must be configured to use the same identity provider adapter instance for generating account links. For more information, see [Managing authentication source mappings](#) on page 459.

## Managing SP affiliations

Use service provider (SP) affiliations when multiple SP's share a business relationship in which users need services from each affiliated provider. To support these needs, edit and delete your SP affiliations in PingFederate as needed.

About this task

In **SP Affiliations** window, create, edit, or delete an SP affiliation.

Steps

- To create a new SP affiliation, go to **System # Protocol Metadata # SP Affiliations** to open the **SP Affiliations** window. Click **Create Affiliation**.

Result: This will open the **Create an Affiliation** window configuration.

- To edit or delete an SP affiliation, choose from the following options.

Choose from:

- To edit an SP affiliation, on the **SP Affiliations** window, select the affiliation by its ID and follow the configuration wizard to complete the task.
- To delete an SP affiliation, in the **SP Affiliations** window, click **Delete** under **Action** for the SP affiliation.

## Importing affiliation metadata

You can import a metadata file for an identity provider (IdP) to send containing information that automatically specifies members of a service provider (SP) affiliation, describing this affiliation, to provide authentication for account linking.

About this task

On the **Import Metadata** tab, import a metadata file, or click **Next** if you do not want to import a file.

Steps

- Go to **System # Protocol Metadata # SP Affiliations** to open the **SP Affiliations** window. Click **Create Affiliation**.

Result: This will open the **Create an Affiliation** window configuration.

- To import a metadata file or not and move onto the next step, choose from the following options.

Choose from:

- To import a metadata file, on the **Import Metadata** tab, click **Choose File** to upload it. Click **Next**.
- If you do not have a metadata file, on the **Import Metadata** tab, click **Next**.

## Entering affiliation information

If you did not import a metadata file to describe a new service provider (SP) affiliation, enter the information manually to identify your SP affiliation to support authentication for account linking.

About this task

On the **Affiliation General Info** tab, enter the affiliation ID information, as described in the following table.

Steps

- To create a new SP affiliation, go to **System # Protocol Metadata # SP Affiliations** to open the **SP Affiliations** window. Click **Create Affiliation**.

Result: This will open the **Create an Affiliation** window configuration.

- On the **Affiliation General Info** tab, enter the following information.

#### Affiliation ID fields and descriptions

| Field             | Description  |
|-------------------|--|
| Affiliation ID    | A unique identifier for this affiliation. This value serves as the Name ID qualifier for SAML assertions sent to affiliated SP partners. |
| Affiliation Owner | Any SAML 2.0 SP connection can serve as the Owner.   |

If you imported a metadata file, this information is already supplied. However, you can change the Affiliation ID or select a different Affiliation Owner, if required.

When finished, click **Next**.

#### Managing affiliation membership

Manage the list of service provider (SP) connections that are part of this affiliation. Configure each of the SP connections in an affiliation to generate opaque pseudonyms using the same adapter attributes.

About this task

On the **Affiliation Membership** tab, create and manage a list of SP connections to be included in the affiliation.

If you imported a metadata file, this information is already supplied. However, you can add or remove connections from the affiliation.

Steps

- Go to **System # Protocol Metadata # SP Affiliations** to open the **SP Affiliations** window. Click **Create Affiliation**.  
Result: This will open a new **Create an Affiliation** configuration window.
- Click on the **Affiliation Membership** tab.
- To add an SP partner connection to the affiliation, from the **SP Connection Name** list, select the connection. Click **Add**.

#### Important:

Each connection in the affiliation must be configured to use the same identity provider (IdP) adapter instance for generating account links. For more information, see [Managing authentication source mappings](#) on page 459.

- To remove a member of the affiliation, click **Delete** under **Action** for the connection.

#### Note:

If you delete an affiliation member supplied by an imported metadata file and then save the affiliation, that connection will not appear in the drop-down list for re-adding in the future.

- When finished, click **Next**.

#### Reviewing an SP affiliation

Review the summary information for a service provider (SP) affiliation and make changes or save as needed.

About this task

On the **Activation & Summary**, review, amend, discard, or save your changes.

### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## OAuth configuration

---

OAuth is an open standard for authorization. To use PingFederate as an OAuth authorization server (AS), configure the OAuth AS settings as described in this section.



### Tip:

Service providers can also add OAuth capabilities to the Browser SSO configuration for identity provider (IdP) connection partners, see [Configure OAuth attribute mapping](#).

## Configuring OAuth use cases

Administrators can configure PingFederate to support the OAuth grant types that applications require.

### Steps

1. To configure the authorization server settings, go to **System # OAuth Settings # Authorization Server Settings**. For more information, see [Configuring authorization server settings](#).
2. Define any number of optional common scopes and exclusive scopes, create scope groups from optional scopes as needed, and enter an optional description for the default scope in the **System # OAuth Settings # Scope Management** window.
3. Create one or more access token management instances in the **Applications # OAuth # Access Token Management** window.



### Note:

You can also define the access token attribute contract for an access token management instance in this window.

4. Configure one or more entries to map attributes from authentication sources to the persistent grants.

#### Authorization Code or Implicit

- Map attributes from an identity provider (IdP) adapter instance to the persistent grants in **Authentication # OAuth # IdP Adapter Grant Mapping**.
- Map attributes from an IdP connection to the persistent grants in **IdP Connection # Browser SSO # OAuth Attribute Mapping**.
- Create an authentication policy contract (APC) using the **Policy Contracts** window, define an authentication policy to map attributes from the authentication sources (IdP adapter instances, IdP connections, or both) to the APC, and map attributes from the APC to the persistent grants using the **Authentication Policy Contract Grant Mapping** window.



### Tip:

If you are using a combination of authentication policies, APCs, and APC mappings, you can skip the **IdP Adapter Grant Mapping** and **OAuth Attribute Mapping** configurations.

## Resource Owner Password Credentials

- Map attributes from a password credential validator instance to the persistent grants using the **Authentication # OAuth # Resource Owner Credentials Grant Mapping** configuration wizard.



### Note:

This is the first stage of the two-stage access token mapping process through the persistent grants.

- Configure one or more entries to map attributes from the persistent grants (or the authentication sources directly) to the attribute contract of your access token management instances in the **Applications # OAuth # Access Token Mapping** window. Additionally, you can configure a mapping for clients using the client credential grant type.



### Note:

This is the second stage of the two-stage access token mapping process through the persistent grants. For more information about the access token mapping process, see [Mapping OAuth attributes](#) on page 90.

- For the client-initiated backchannel authentication (CIBA) flow, configure one or more CIBA authenticator instances and then one or more CIBA request policies.
- For the JSON web token (JWT) Bearer or SAML 2.0 Bear assertion grants flow, configure a mapping in **IdP Connection # OAuth Assertion Grant Attribute Mapping**.



### Note:

This use case exchanges a JWT or a SAML assertion for an OAuth access token.

- Define one or more OpenID Connect policies using the **Applications # OAuth # OpenID Connect Policy Management** window if you support OpenID Connect use cases.
- Go to **Applications # OAuth # Clients** and create one or more OAuth clients in the **Client** window.
- Optional: Configure client settings and registration policies for dynamic client registration.
- Optional: Configure client session management settings.

## Configuring authorization server settings


The **Authorization Server Settings** window provides controls over the usage and behavior of PingFederate as an OAuth authorization server (AS), including the policies and settings for various grant types, refresh-tokens, persistent grants, and ID tokens.

### Steps



- Go to **System # OAuth Settings # Authorization Server Settings**.
- Configure the AS to suit your use cases.



The following table describes each field.

| Field                                       | Description  |
|---|--|
| <b>Authorization Code Timeout (Seconds)</b> | The amount of time in seconds that an authorization code is considered valid. The default value is 60. |


| Field  | Description   |
|--|---|
| <b>Authorization Code Entropy (Bytes)</b>                          | The length in bytes of the authorization code returned to clients. The default value is 30.   |
| <b>Disallow the Plain PKCE Code Challenge Method</b><br>(optional) | <p>When selected, PingFederate, acting as the authorization server, rejects an authorization request that uses the PKCE <code>plain code_challenge_method</code>.</p> <p>By default this check box is cleared.</p> <p>For more information, see <a href="#">Proof Key for Code Exchange by OAuth Public Clients</a>.</p>  |
| <b>Include Issuer in Authorization Response</b>                    | When selected, PingFederate's issuer identifier <code>iss</code> parameter is returned in the authorization response. By default this check box is cleared.   |
| <b>Track User Sessions for Logout</b>                              | <p>When selected, PingFederate links the sessions for identity provider (IdP) adapters that are used by clients to the PingFederate authentication session of the resource owner. When a user initiates logout, PingFederate sends logout requests to close the adapter sessions through the browser.</p> <p>Selecting this check box also allows per-client logout endpoints to be defined, which will be invoked during logout.</p> <p>By default, this check box is cleared.</p>   |
| <b>Client Secret Retention Period</b>                              | <p>The amount of time in minutes that the previous client secret is retained after changing the secret.</p> <p>If value is 0, client secrets will not be retained. Maximum value is one month or 43800 minutes.</p>   |
|  | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>Global configuration can be overridden on a per client basis.</p> </div>   |
| <b>Pushed Authorization Request (PAR) Settings</b>                 |   |
| <b>PAR Status</b>  | <p>This field determines whether clients can or must use the PAR endpoint <code>/as/par.oauth2</code> on the AS to initiate authorization flows. The default setting is <b>Enabled</b>.</p> <p>This setting works in conjunction with each client's <b>Require Pushed Authorization Requests</b> check box on the <b>Client</b> window.</p> <p>For example:</p> <ul style="list-style-type: none"> <li>▪ If PAR is <b>Enabled</b> on the AS and required on the client, then the client must use PAR</li> <li>▪ If PAR is <b>Enabled</b> on the AS but not required on the client, then the client can use PAR</li> <li>▪ If PAR is <b>Required</b> on the AS but not required on the client, then the client must use PAR</li> <li>▪ If PAR is <b>Disabled</b> on the AS and required on the client, then the client cannot access the AS</li> </ul> <p>For more information about PAR, see <a href="#">Pushed authorization requests endpoint</a> on page 1191 and <a href="#">Configuring OAuth clients</a> on page 566.</p> |




| Field  | Description   |
|--|---|
| <b>PAR Reference Timeout (Seconds)</b>             | Specifies the lifetime of the request URI that the PAR endpoint returns to the client. The default is 60 seconds. The allowable values are 1 to 1800.   |
| <b>PAR Reference Entropy (Bytes)</b>               | Specifies the length of the request URI. Longer request URIs are more secure. The default is 24 bytes. The allowable values are 20 to 256.  |
| <b>Refresh Token and Persistent Grant Settings</b> |   |
| <b>Persistent Grant Max Lifetime</b>               | <p>This field determines whether persistent grants should expire, and if so, the default maximum lifetime for persistent grants.</p> <ul style="list-style-type: none"> <li>▪ Select <b>Grants Do Not Expire</b> to let persistent grants remain valid until they are revoked or removed.</li> <li>▪ Select the time value option to set a maximum lifetime for persistent grants. Enter an integer between 1 and 999 in the field and select <code>Days</code>, <code>Hours</code>, or <code>Minutes</code> from the list.</li> </ul> <p>The default selection is <b>Grants Do Not Expire</b>.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can override the expiration in individual client records or grant-mapping configurations. Grant-mapping configurations take precedence and require an extended persistent grant attribute, <code>PERSISTENT_GRANT_LIFETIME</code>.</p> </div>   |
| <b>Persistent Grant Idle Timeout</b>               | <p>This field determines whether persistent grants should expire due to inactivity, regardless of whether the maximum lifetime has been reached, and the default idle timeout period.</p> <ul style="list-style-type: none"> <li>▪ Select <b>Grants Do Not Timeout Due To Inactivity</b> and let persistent grants remain valid until they expire or are removed.</li> <li>▪ Select the time value option to set the default idle timeout window. Enter an integer between 1 and 999 in the field and select a unit of measurement from the list.</li> </ul> <p>If you configure an idle timeout value, the idle timeout window slides when a persistent grant updates. When you have an idle timeout value configured without a maximum lifetime, persistent grants remain valid until they expire due to inactivity or until the grant storage revokes or removes them. When you have an idle timeout value configured with a maximum lifetime, persistent grants remain valid until they expire due to inactivity or lifetime expiration or until the grant storage removes them. For more information, see <a href="#">Transient grants and persistent grants</a> on page 88.</p> <p>For new installations, the default inactivity allowance is 30 days. For upgrades, <b>Grants Do Not Timeout Due To Inactivity</b> is the default selection unless a specific value was set previously.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can override the expiration in individual client records.</p> </div> |


| Field  | Description   |
|--|---|
| <b>Refresh Token Length (Characters)</b>               | <p>The length of the refresh tokens in numerical characters.</p> <p>The default value is 42.</p>  |
| <b>Roll Refresh Token Values (Default Policy)</b>      | <p>When selected, PingFederate generates a new refresh token when a new access token is issued. Otherwise, each refresh token is used until it becomes invalid, either by manual revocation or another security setting that renders the token invalid.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>New refresh tokens are not issued during the interval defined by the <b>Minimum Interval to Roll Refresh Tokens</b> field.</p> </div> <p>This check box is cleared by default.</p>  |
| <b>Minimum Interval to Roll Refresh Tokens (Hours)</b> | <p>The minimum number of hours that must pass before a new refresh token can be issued. This setting provides a way to allow for rolling refresh tokens without having to send a new refresh token on every request.</p> <p>The default value is 0.</p>   |
| <b>Refresh Token Rolling Grace Period (seconds)</b>    | <p>The amount of time in seconds that a rolled refresh token is still valid in the event that the client failed to receive an updated one during a roll.</p> <p>The maximum value is 86400. For security reasons, we recommend setting the custom value as low as possible.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If specified:</p> <ul style="list-style-type: none"> <li>▪ the currently issued refresh tokens must be refreshed once and converted to the new format.</li> <li>▪ the global settings applies to all clients.</li> </ul> </div> |



| Field  | Description  |
|--|--|
| <b>Reuse Existing Persistent Access Grants for Grant Types</b>                       | <p>If a client makes multiple requests for the same user and the same or lesser scope, select the grant types that you want PingFederate to reuse the existing grant for, rather than creating a new grant for each request.</p> <p>Reusing an existing persistent grant imposes a limit of one grant per client, per user. In the context of refresh tokens, only the most recently issued is valid, and the previously issued refresh token is invalidated. If the same client are installed on multiple devices and used regularly by the same user, the grant type used by this client should be cleared.</p> <p>The applicable grant types are:</p> <ul style="list-style-type: none"> <li>▪ <b>Implicit</b> (default)</li> <li>▪ <b>Authorization Code</b></li> <li>▪ <b>Resource Owner Password Credentials</b></li> </ul> <p>When the <b>Implicit</b> check box is selected, PingFederate requests consent from the user only once. The user is not asked for authorization on subsequent requests until the access grant is revoked.</p> <p>When the <b>Authorization Code</b> check box is selected, the same is true if the <b>Bypass Authorization for Previously Approved Persistent Grants</b> check box is also selected.</p> |
| <b>Allow Unidentified Clients to Make Resource Owner Password Credentials Grants</b> | <p>When selected, PingFederate allows resource owners to obtain access tokens without client ID or client authentication.</p> <p>The check box is cleared by default.</p>  |
| <b>Allow Unidentified Clients to Request Extension Grants</b>                        | <p>When selected, PingFederate allows user-initiated or client-initiated events, such as a mobile application or a scheduled task, to obtain access tokens without the client presenting a <code>client_id</code> or <code>client_secret</code> for the extension grant types, namely:</p> <ul style="list-style-type: none"> <li>▪ JWT Bearer Token grant type <ul style="list-style-type: none"> <li><code>urn:ietf:params:oauth:grant-type:jwt-bearer</code></li> </ul> </li> <li>▪ SAML 2.0 Bearer Assertion grant type <ul style="list-style-type: none"> <li><code>urn:ietf:params:oauth:grant-type:saml2-bearer</code></li> </ul> </li> <li>▪ Validation grant type <ul style="list-style-type: none"> <li><code>urn:pingidentity.com:oauth2:grant_type:validate_bearer</code></li> </ul> </li> </ul> <p>The check box is cleared by default.</p>   |
| <b>Token Endpoint Base URL</b>   | <p>When clients authenticate with the <code>private_key_jwt</code> authentication method, PingFederate validates the <code>aud</code> parameter value found inside the signed JWT against its base URL or any configured virtual host names. If the values do not match, the authentication fails.</p> <p>Enter a separate base URL that PingFederate can take into consideration as well when validating the <code>aud</code> parameter.</p> <p>If configured, the OpenID Provider configuration endpoint <code>/.well-known/openid-configuration</code> uses the <b>Token Endpoint Base URL</b> field value as the base for the token endpoint.</p> <p>This field has no default value.</p>  |

| Field   | Description  |
|---|--|
| <b>Persistent Grant Extended Attributes</b>                           |  |
| <b>Attributes</b>   | <p>Extend persistent grants to include additional attributes from your authentication systems.</p> <p>Lifetime of persistent grants</p> <p>Add the attribute <code>PERSISTENT_GRANT_LIFETIME</code> to enable the option to set the lifetime of persistent grants based on the outcome of attribute mapping expressions in individual grant-mapping configurations. For grant-mapping configurations that do not require this fine-grain control, you can configure them to use the default value. This capability applies to the following grant-mapping configurations:</p> <ul style="list-style-type: none"> <li>▪ <b>IdP Adapter Grant Mapping</b></li> <li>▪ <b>OAuth Attribute Mapping</b></li> <li>▪ <b>Authentication Policy Contract Mapping</b></li> <li>▪ <b>Resource Owner Credentials Grant Mapping</b></li> </ul> <p>This field has no default entry. PingFederate allows multiple entries.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If you have already created grant mapping configurations and then add one or more attributes in this section, the newly added attributes are configured as <b>No Mapping</b> in all existing grant mapping configurations. You can configure fulfillment for the newly added attributes in individual grant mapping configurations when your use cases require those attributes.</p> </div> |
| <b>Authorization Consent</b>  |  |
| <b>Bypass Authorization for Previously Approved Persistent Grants</b> | <p>When selected, PingFederate requests consent from the user only once. The user is not asked for authorization on subsequent requests until the access grant is revoked. This applies only when using the authorization code grant type and when the <b>Reuse Existing Persistent Access Grants for Grant Types</b> check box is selected.</p> <p>The check box is cleared by default.</p>   |




| Field                         | Description  |
|-------------------------------|--|
| <b>Consent User Interface</b> | <p>Specifies whether PingFederate or a trusted web application should handle consent approval.</p> <p><b>Default</b></p> <p>Select <b>Default</b> and let PingFederate handle consent approval by presenting the <b>Request for Approval</b> page to the resource owner.</p> <p><b>External</b></p> <p>Select <b>External</b> to delegate the responsibilities of consent approval to a trusted web application.</p> <p>For example, if you have created an instance of the Reference ID Adapter version (version 1.5 or later), you can select it from the list. The expectation is that the trusted web application is integrated with PingFederate through this Reference ID Adapter instance.</p> <p>When selected, you must also configure two additional fields: <b>External Consent IdP Adapter</b> and <b>External Consent Scopes Attribute</b>.</p> <p><b>External Consent IdP Adapter</b></p> <p>The <b>External Consent IdP Adapter</b> field displays a list of IdP adapter instances that are capable of facilitating the consent approval process.</p> <p>For example, if you have created an instance of the Reference ID Adapter version (version 1.5 or later), you can select it from the list. The expectation is that the trusted web application is integrated with PingFederate through this Reference ID Adapter instance.</p> <p>Your development team can also create a custom adapter using the PingFederate SDK. For more information, see the <a href="#">Javadoc for the <code>IdpAuthenticationAdapterV2</code> interface</a>, the <code>ExternalConsentPageAdapter.java</code> file for a sample implementation, and the <a href="#">SDK Developer's Guide</a> on page 1115 for build and deployment information.</p> <div data-bbox="665 1360 1461 1535" style="border: 1px solid #ccc; padding: 10px; margin: 10px 0;"> <p> <b>Tip:</b></p> <p>The Javadoc for <code>ExternalConsentPageAdapter</code> and the sample implementation are in the <code>&lt;pf_install&gt;/pingfederate/sdk</code> directory.</p> </div> <p>After you've deployed, you can create an instance of the selected adapter instance.</p> <p><b>External Consent Scopes Attribute</b></p> <p>The <b>External Consent Scopes Attribute</b> field displays a list of attributes defined in the IdP adapter contract of the selected adapter instance. Select the attribute whose value contains the approved scopes returned by the trusted web application.</p> <p>For example, if you have added an attribute called <b>approvedScopes</b> to the adapter instance with the expectation that <b>approvedScopes</b> is the attribute that the trusted web application passes approved scopes to PingFederate, select <b>approvedScopes</b> from the list.</p> |



| Field   | Description   |
|---|---|
| <b>OAuth Administrative Web Services Settings</b>   |   |
| <b>Password Credential Validator</b>  | <p>Selects a Password Credential Validator (PCV) instance to manage clients using the OAuth Client Management Service or to manage persistent grants using the OAuth Access Grant Management Service.</p> <p>This setting has no default selection. When no PCV is selected, neither service can be used.</p> |
| <b>Persistent Grant Management API</b>  |   |
| <p>The Persistent Grant Management API allows clients to assume the responsibility of grant management if the users authorize the clients to do so. In this scenario, a client prompts the user to approve a specific scope for managing persistent grants on the user's behalf. If the user approves, the client requests an access token with such scope from PingFederate. As long as the access token remains valid, the client can retrieve and revoke persistent grants and their associated extended attribute names and values for that user. For more information, see <a href="#">OAuth Persistent Grant Management API</a> on page 1230.</p> |   |
| <b>Access Token Manager</b>   | <p>Selects an Access Token Management instance under which one or more clients can use the access tokens issued to manage persistent grants on their users.</p> <p>Such clients must also be configured to use this Access Token Management instance in their client configurations.</p>                      |
| <b>Required Scope</b>   | <p>Selects the scope that PingFederate looks for in access tokens prior to granting clients the permission to manage persistent grants for their users.</p> <p>Clients must obtain access tokens with this scope and include them in their grant-management requests.</p>                                     |
| <b>Cross-Origin Resource Sharing Settings</b>   |   |

| Field                                      | Description  |
|--|--|
| <b>Allowed Origin</b>                      | <p>Enter any number of trusted origins to enable cross-origin resource sharing (CORS) support for the following OAuth endpoints:</p> <ul style="list-style-type: none"> <li>▪ /as/token.oauth2</li> <li>▪ /as/revoke_token.oauth2</li> <li>▪ /idp/userinfo.openid</li> <li>▪ /pf-ws/rest/oauth/grants/</li> <li>▪ /pf/JWKS</li> <li>▪ /.well-known/openid-configuration</li> <li>▪ /as/bc-auth.ciba</li> </ul> <p>Once configured, client-side web applications from the trusted origins are allowed to make requests to the authorization server for the purpose of accessing protected resources, such as obtaining or renewing access tokens with refresh tokens, presenting access tokens for revocation, querying additional claims (user attributes), and retrieving OpenID Provider configuration information and JSON Web Key Sets. For more information about CORS, see <a href="#">W3C's recommendation on Cross-Origin Resource Sharing</a>.</p> <p>Here are some example entries and their behaviors:</p> <ul style="list-style-type: none"> <li>▪ https://www.example.com<br/>CORS requests originating from https://www.example.com are allowed.</li> <li>▪ https://www.example.com:8080<br/>CORS requests originating from https://www.example.com:8080 are allowed.</li> <li>▪ https://www.example.com:*<br/>CORS requests originating from https://www.example.com:&lt;any port&gt; are allowed. However, a port number is required in the <b>Origin</b> request header.</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>Although using the wildcard character provides the convenience of allowing multiple origins with one entry, consider adding individual origins to limit CORS requests to a list of trusted hosts.</p> </div> <p>This field has no default entry. PingFederate allows multiple entries.</p> |
| <b>Device Authorization Grant Settings</b> | <p>The <a href="#">OAuth 2.0 Device Authorization Grant</a> specification defines the process of a user granting authorization to a device using a browser on a second device, such as a smartphone or a computer. For more information, see <a href="#">Device authorization grant</a> on page 57.</p>  |

| Field                                       | Description  |
|---|--|
| <b>User Authorization URL</b><br>(Optional) | <p>This field determines whether PingFederate should use a different URL, possibly for ease of use or branding purposes, when formulating the verification URLs to be included in its device authorization responses. For more information, see <a href="#">Device authorization endpoint</a> on page 1182.</p> <p>For example, if this field is configured with a value of <code>https://www.example.org/welcome</code>, PingFederate returns <code>https://www.example.org/welcome</code> and <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> as the verification URIs.</p> <p>After processing the device authorization response, which includes the verification URIs, the device presents one of them to the user. The user is expected to browse to the presented verification URI on a second device.</p> <div data-bbox="565 615 1472 852" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>The target web server must redirect the browser to PingFederate at its user authorization endpoint. For more information, see <a href="#">User authorization endpoint</a> on page 1185. The target web server must also preserve the <code>user_code</code> parameter value, if provided.</p> </div> <p>For instance, if the base URL of your PingFederate server is <code>https://www.example.com</code> and this field is configured with a value of <code>https://www.example.org/welcome</code>, the target web server must redirect as follows:</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.org/welcome</code> to <code>https://www.example.com/as/user_authz.oauth2</code></li> <li>▪ <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> to <code>https://www.example.com/as/user_authz.oauth2?user_code=&lt;activationcode&gt;</code></li> </ul> <p>This field has no default value.</p> <div data-bbox="565 1241 1472 1381" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>You can override this setting in individual client records.</p> </div> |



| Field  | Description  |
|--|--|
| <p><b>Registered Authorization Path</b><br/>(Optional)</p> | <p>This field controls whether PingFederate should replace the user authorization endpoint with a different path, perhaps for ease of use or branding purposes, when formulating the verification URLs to be included in its device authorization responses. For more information, see <a href="#">Device authorization endpoint</a> on page 1182. The domain portion remains to be the base URL of PingFederate. For example, if the base URL is <code>https://www.example.com</code> and this field is configured with a value of <code>/go</code>, PingFederate returns <code>https://www.example.com/go</code> and <code>https://www.example.com/go?user_code=&lt;activationcode&gt;</code> as the user authorization URLs.</p> <p>If PingFederate receives a device authorization request at one of the configured virtual host names, PingFederate preserves the virtual host name in its device authorization responses.</p> <div data-bbox="565 661 1472 871" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>The registered authorization path behaves the same way as the user authorization endpoint does. For more information, see <a href="#">User authorization endpoint</a> on page 1185.</p> </div> <p>This field is ignored when the <b>User Authorization URL</b> field is configured here or in the individual client records.</p> <p>The configured value must begin with a forward slash.</p> <p>This field has no default value.</p> |
| <p><b>Pending Authorization Timeout (seconds)</b></p>      | <p>The lifetime of an activation code, the <code>user_code</code> parameter value, in seconds.</p> <p>The default value is 600.</p> <div data-bbox="565 1207 1472 1344" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>You can override this setting in individual client records.</p> </div>  |
| <p><b>Device Polling Interval (seconds)</b></p>            | <p>The amount of time in seconds that the device waits between polling requests to the PingFederate token endpoint.</p> <p>The default value is 5.</p> <div data-bbox="565 1501 1472 1648" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>You can override this setting in individual client records.</p> </div>   |

| Field   | Description   |
|---|---|
| <b>Check Activation Code</b>                          | <p>This setting determines whether the activation code verification step should happen before or after the user is authenticated. One advantage of checking before authentication is that it allows PingFederate to determine up front the client ID and scopes for the flow. As a result, selectors such as the <a href="#">OAuth Client Set Authentication Selector</a>, the <a href="#">Extended Property Authentication Selector</a>, and the <a href="#">OAuth Scope Authentication Selector</a> will work as expected in deciding the authentication policy for the user.</p> <p>The default setting is <b>After Authentication</b>.</p> <div data-bbox="565 506 1472 835" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>Checking the activation code before authentication means that the key PingFederate uses for rate limiting is based only on the user's IP address. This means that the rate limit must be higher, because the key will be shared across all users who have the same IP address. See the file <code>&lt;pf_install&gt;/pingfederate/server/default/data/config-store/oauth-device-flow.xml</code> for more information and to tune the rate limit appropriately for your deployment.</p> </div> |
| <b>Bypass Activation Code Confirmation</b>            | <p>When PingFederate receives a verification request that includes an activation code, the <code>user_code</code> parameter value, it prompts the user to confirm the activation code. This field determines whether PingFederate skips this confirmation step.</p> <p>Select the <b>Bypass Activation Code Confirmation</b> check box for PingFederate to skip the confirmation step.</p> <p>This check box is cleared by default.</p> <div data-bbox="565 1140 1472 1283" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>You can override this setting in individual client records.</p> </div>   |
| <b>JWT Secured Authorization Response Mode (JARM)</b> | <p>JARM is a mechanism to enhance the security of the standard authorization response. It adds support for signing and encryption, sender authentication, and audience restriction. It also offers protection from replay, credential leakage, and mix-up attacks. JARM can be combined with any response type. For more information, see the <a href="#">JARM specification</a>.</p>   |
| <b>JWT Lifetime (Seconds)</b>                         | <p>The lifetime of the authorization response token that PingFederate returns.</p> <p>The default value is 600 seconds.</p>   |

### External consent user interface

As use cases evolve and give users more control over their data, it is important to provide detailed information about the requests. In addition to scope descriptions, PingFederate supports the use of an external web application to prompt for authorization consent.

An external web application provides the opportunity to retrieve additional information specific to the users. For example, if a client requests the **read\_bank\_account** scope, the web application can retrieve the user's customer information file and give the user the ability to choose which accounts to be made available to the client.

To use an external web application for consent approval, configure the **Consent User Interface** setting in **System # OAuth Settings # Authorization Server Settings**. Select the **External** option and then configure the **External Consent IDP Adapter** and **External Consent Scopes Attribute** settings accordingly.

#### Responsibilities of the external web application

Delegating consent approval to an external web application implies that PingFederate can trust the web application. PingFederate expects this trusted web application to fulfill the following responsibilities:

- Retrieve from PingFederate the list of requested scopes in a secure manner.  
For example, when integrating the web application with PingFederate through an instance of the Reference ID Adapter, such communications occur through a direct connection between the web application and PingFederate. This back-channel connection is protected by authentication and encryption (HTTPS).
- Provide to the resource owner the information associated with the list of requested scopes and the user interface elements to approve or deny the requested scopes.
- Validate that the approved scopes found in the response from the resource owner do not exceed the requested scopes.



#### **Important:**

This validation guards against unauthorized access in the event that the response is tampered and the original approved scopes are compromised.

- As needed, modify the approved scopes before returning them to PingFederate.  
This allows the web application to override authorization decisions.
- Return the list of approved scopes to PingFederate in a secure manner.

#### Handling of approved scopes

By default, PingFederate handles consent approval by presenting the **Request for Approval** page to the resource owner. Upon receipt of the response from the resource owner, PingFederate validates that the approved scopes do not exceed the requested scopes. If the validation passes, PingFederate adds the approved scopes to the access token. Otherwise, PingFederate returns the `invalid_scope` error to the client.

When an external consent user interface is enabled, PingFederate delegates consent approval to an external web application. As PingFederate trusts this web application, it always adds the scopes returned by the trusted web application to the access token, regardless of whether the returned scopes have already been defined in the system. The issuance of the access token is still subject to the criteria defined in the grant mapping configuration, the token mapping configuration, or both. For more information, see [Grant contract mapping](#) on page 582 and [Token mapping](#) on page 603.

## Scopes and scope management

OAuth allows you to constrain the privileges associated with an access token, and scopes allow you to define the privileges requested and granted.

#### Static scopes versus dynamic scopes

As an authorization server, supports the concepts of static scopes and dynamic scopes. To define a static scope, use a text value such as `read_bank_account`. To define a dynamic scope, use a text value with a variable component represented by a wildcard, such as `read_bank_account_txn:*`. As illustrated, dynamic scopes allow clients to request authorization using scope values with a variable component from one request to another. For example, when a requested scope of `read_bank_account_txn:1234`, PingFederate can match the requested scope to the dynamic scope

pattern of `read_bank_account_txn:*` and can issue an access token with the requested scope of `read_bank_account_txn:1234`.

### Scope groups

For ease of management and subsequent client interactions, PingFederate has the capability to create multiple groups of static scopes. A client can reference a scope group in applicable OAuth 2.0 protocol interactions. When authorized, clients can subsequently request access tokens with fewer permissions by presenting to the token endpoint a refresh token and the desired subset of scopes.

A scope group must contain at least one static scope, and multiple sub scopes are allowed. Multiple scope groups can share the same set of sub scopes. However, no scope group can contain another scope group or the default scope.

### Scope group expansion

An authorization request can include one or more scope values. If the request is authorized, PingFederate issues an access token to the client. When the client brings the access token to a resource server to access protected resources, the resource server may contact PingFederate to validate the access tokens. Scope groups are not expanded in JSON web token (JWT)-based access tokens or token introspection responses by default. You can optionally enable scope group expansion per access token management instance.



#### Note:

Regardless of whether you choose to expand scope groups, the **Request for Approval** window always presents the description of the requested scope groups, if any.

### Common scopes and exclusive scopes

PingFederate has the flexibility to manage common and exclusive scopes and scope groups.

#### Common scopes and scope groups

Common scopes and scope groups are optional. If defined, they are available to all clients by default. As needed, you can restrict individual clients to a subset of common scopes or scope groups in their configurations.

Clients created via the Dynamic Client Registration protocol can also be restricted to a subset of common scopes or scope groups based on the configuration on the **Scope Constraints** tab in **System # OAuth Settings # Client Settings**. The **Scope Constraints** configuration is shared across all clients registered through dynamic client registration. If a certain client requires a different set of common scopes or scope groups, modify the client configuration by using the administrative console, the administrative API, or the OAuth Client Management Service after the client has been created.

#### Exclusive scopes and scope groups

Exclusive scopes and scope groups are optional. If defined, they are restricted from all clients by default. As needed, you can configure individual clients to allow a subset of exclusive scopes or scope groups in their configurations.

Clients created with the Dynamic Client Registration protocol can also be configured to allow a subset of exclusive scopes or scope groups based on the **Scope Constraints** tab on the **System # OAuth Settings # Client Settings** window. The **Scope Constraints** configuration is shared across all clients registered via dynamic client registration. If a certain client requires a different set of exclusive scopes or scope groups, modify the client configuration by using the administrative console, the administrative API, or the OAuth Client Management Service after the client has been created.

**Note:**

A scope or scope group is either a common scope or group, or an exclusive scope or group. Duplicate scopes and scope groups are not allowed. Scope and scope group values are case-sensitive.

**Tip:**

Create scopes that are intended for the majority of clients as common scopes. Create scopes that should be limited to the minority of clients as exclusive scopes.

## OpenID Connect

If one or more clients support the OpenID Connect standard, add the following scopes for the purpose of requesting specific sets of claims from the OpenID Provider:

- `openid`
- `address`
- `email`
- `phone`
- `profile`

**Tip:**

If most clients are allowed to use these scopes, create them as common scopes.

## Per-client scope management

You can manage scope access on a client-to-client basis. The client settings are **Restrict Common Scopes** and **Exclusive Scopes**.

### Restrict Common Scopes

This setting determines whether all common scopes and scope groups should be made available to the client, or only a select few.

When selected, the administrative console displays a list of existing common scopes and scope groups. Choose the common scopes and scope groups that are intended for the client. The rest, as well as any future common scopes and scope groups, become invalid for the client. If the client tries to use such scope or scope group, it will receive an `invalid_scope` error message from PingFederate.

When cleared, all existing and future common scopes and scope groups are available to the client. This is the default behavior.

### Exclusive Scopes

This setting determines whether any exclusive scopes and exclusive scope groups should be made available to the client.

When selected, the administrative console displays a list of existing exclusive scopes and scope groups. Choose the exclusive scopes and scope groups that are intended for the client. The rest, as well as any future exclusive scopes and scope groups, become invalid for the client. If the client tries to use such scope or scope group, it will receive an `invalid_scope` error message from PingFederate.

When cleared, no exclusive scopes and scope groups are available to the client. This is the default behavior.

**Note:**

Both settings impact dynamic scope evaluation. For more information, see [Dynamic scope evaluation and per-client scope management](#).

### Dynamic scopes

A dynamic scope is defined by using a text value with a variable component represented by an asterisk (\*). PingFederate supports three dynamic scope patterns:

- A prefix followed by a wildcard, for example: `prefixTextValue*`
- A wildcard followed by a suffix, for example: `*suffixTextValue`
- A wildcard placed between a prefix and a suffix, for example:  
`prefixTextValue*suffixTextValue`

PingFederate only allows one variable component. Backslashes (\) and double quotation marks (") are not allowed in the prefix or the suffix. Multiple dynamic scopes are supported in conjunction with any number of static scopes and scope groups.

### Dynamic scope evaluation

When a client sends an authorization or token request with a list of desired scopes, PingFederate validates the requested scopes against its configurations.

If PingFederate finds no match for the requested scopes, it returns an `invalid_scope` error message to the client.

If PingFederate matches the requested scope to an existing static scope or scope group, it checks the client configuration to determine whether such static scope or scope group is valid for the client. If it is, PingFederate proceeds further. For example, if PingFederate is configured to handle consent approval, it presents to the user the **Request for Approval** window with the description associated with the matched static scope or scope group. If PingFederate should issue an access token, the token is issued with the requested scope. If such static scope or scope group is not valid for the client, PingFederate returns an `invalid_scope` error message to the client.

If PingFederate finds no exact match but finds a partial match to one or more dynamic scopes, the partial match with the highest number of matched characters in the prefix, suffix, or both is the matched dynamic scope. In the event that two partial matches tie, the partial match with the highest number of characters matched in the prefix is the matched dynamic scope. PingFederate then checks the client configuration to determine whether such dynamic scope is valid for the client. If it is, PingFederate proceeds further. Otherwise, PingFederate returns an `invalid_scope` error message to the client. If PingFederate should issue an access token, the token is issued with the requested scope, not the matched dynamic scope pattern.

### Example

For example, you add the following dynamic scopes:

| Common Scopes | Exclusive Scopes    |
|---------------|---------------------|
| *123          | zSomeExclusiveScope |
| *12345        |                     |
| a*c#123       |                     |
| ab*#123       |                     |
| xy*123        |                     |

| Common Scopes | Exclusive Scopes |
|---------------|------------------|
| xy*           |                  |

You also add a client without any common scope restrictions. This client can access all common scopes.

The following table illustrates the expected results when the client sends an authorization request with these scopes:

- xy#1
- xy#12
- xy#123
- xy#1234
- xy#12345
- xy#123456
- xyz
- z123
- z12345
- abc#123

| Requested scope | Matched dynamic scope | Variable component from the requested scope |
|-----------------|-----------------------|---|
| xy#1            | xy*                   | #1  |
| xy#12           | xy*                   | #12   |
| xy#123          | xy*123                | #   |
| xy#1234         | xy*                   | #1234                                       |
| xy#12345        | *12345                | xy#   |
| xy#123456       | xy*                   | #123456                                     |
| xyz             | xy*                   | z   |
| z123            | *123                  | z   |
| z12345          | *12345                | z   |
| abc#123         | ab*#123               | b   |

The minimum length of the variable component is one character. If the variable component contains two or more characters, it may also contain the asterisk character as well. Given the same common dynamic scopes and the same client configuration, requested scopes of xyQ123, xy\*Q123, xyQ\*123, xy\*\*Q\*123 will be matched as in the following table.

| Requested scope | Matched dynamic scope | Variable component from the requested scope |
|-----------------|-----------------------|---|
| xyQ123          | xy*123                | Q   |
| xy*Q123         | xy*123                | *Q  |
| xyQ*123         | xy*123                | Q*  |
| xy**Q*123       | xy*123                | **Q*  |

If the client sends an authorization request with a requested scope of xy\*123, it will receive an `invalid_scope` error from PingFederate.

## Dynamic scope evaluation and per-client scope management

Depending on the configured dynamic scope patterns and if they are defined as common or exclusive dynamic scopes, per-client scope management settings can impact the results of scope evaluation.

The **Restrict Common Scopes** setting determines whether all common scopes and scope groups are available to the client, or only a select few. Use this setting to restrict certain common dynamic scopes.

The **Exclusive Scopes** setting determines whether any exclusive scopes and scope groups are available to the client. When this check box is not selected, PingFederate does not consider any exclusive dynamic scopes or any exclusive static scopes and scope groups when trying to match a requested scope against a list of configured scopes and scope groups. When the check box is selected, all exclusive scopes and scope groups are considered. If PingFederate matches a requested scope to an exclusive dynamic scope and such scope is not available to the client, PingFederate returns an `invalid_scope` error message to the client. This remains true for a lesser partial match to an available common dynamic scope.

### Example

For example, you update your previous sample scope configuration as in the following table.

| Common Scopes | Exclusive Scopes    |
|---------------|---------------------|
| *123          | xy*123              |
| *12345        | zSomeExclusiveScope |
| a*c#123       |                     |
| ab*#123       |                     |
| xy*           |                     |

The following table describes the results when the client sends an authorization request with a requested scope of `xy#123`.

| Per-client scope management settings  | Result  | Variable component from the requested scope |
|---|---|---|
| <b>Restrict Common Scopes</b> <ul style="list-style-type: none"> <li>Not selected.</li> </ul> | PingFederate matches the requested scope of <code>xy#123</code> to the common dynamic scope of <code>*123</code> .  | <code>xy#</code>                            |
| <b>Exclusive Scopes</b> <ul style="list-style-type: none"> <li>Not selected.</li> </ul>       | The exclusive dynamic scope of <code>xy*123</code> is not taken into consideration because the <b>Exclusive Scopes</b> check box is not selected. PingFederate does not consider any exclusive scopes and scope groups as eligible candidates in this scenario. |   |



| Per-client scope management settings  | Result   | Variable component from the requested scope |
|---|--|---|
| <p><b>Restrict Common Scopes</b></p> <ul style="list-style-type: none"> <li>Not selected.</li> </ul> <p><b>Exclusive Scopes</b></p> <ul style="list-style-type: none"> <li>Selected. <ul style="list-style-type: none"> <li>zSomeExclusiveScope is selected.</li> </ul> </li> </ul> <p>No other exclusive scope is selected.</p>  | <p>PingFederate returns an <code>invalid_scope</code> error message, because the exclusive dynamic scope of <code>xy*123</code> is not allowed based on the <b>Exclusive Scopes</b> configuration.</p>   | <p>Not applicable.</p>                      |
| <p><b>Restrict Common Scopes</b></p> <ul style="list-style-type: none"> <li>Not selected.</li> </ul> <p><b>Exclusive Scopes</b></p> <ul style="list-style-type: none"> <li>Selected. <ul style="list-style-type: none"> <li><code>xy*123</code> is selected.</li> </ul> </li> </ul> <p>It does not matter if any other exclusive scope is selected.</p>   | <p>PingFederate matches the requested scope of <code>xy#123</code> to the exclusive dynamic scope of <code>xy*123</code>.</p>  | <p>#</p>                                    |
| <p><b>Restrict Common Scopes</b></p> <ul style="list-style-type: none"> <li>Selected. <ul style="list-style-type: none"> <li><code>xy*</code> is selected</li> </ul> </li> </ul> <p>No other common scope is selected.</p> <p><b>Exclusive Scopes</b></p> <ul style="list-style-type: none"> <li>Not selected.</li> </ul>   | <p>PingFederate returns an <code>invalid_scope</code> error message, because the common dynamic scope of <code>*123</code> is not allowed based on the <b>Restrict Common Scopes</b> configuration.</p> <p>The exclusive dynamic scope of <code>xy*123</code> is not taken into consideration because the <b>Exclusive Scopes</b> check box is not selected. PingFederate does not consider any exclusive scopes and scope groups as eligible candidates in this scenario.</p> | <p>Not applicable.</p>                      |
| <p><b>Restrict Common Scopes</b></p> <ul style="list-style-type: none"> <li>Selected. <ul style="list-style-type: none"> <li><code>*123</code> is selected</li> </ul> </li> </ul> <p>It does not matter if any other common scope is selected.</p> <p><b>Exclusive Scopes</b></p> <ul style="list-style-type: none"> <li>Selected. <ul style="list-style-type: none"> <li><code>xy*123</code> is selected.</li> </ul> </li> </ul> <p>It does not matter if any other exclusive scope is selected.</p> | <p>PingFederate matches the requested scope of <code>xy#123</code> to the exclusive dynamic scope of <code>xy*123</code>, because <code>xy*123</code> is a better partial match than <code>*123</code>.</p>  | <p>#</p>                                    |

## Description for scopes and scope groups

When defining a scope or a scope group, enter a value and a description for the scope or the scope group. This description helps you identify the purpose of the scope or scope group at a later time. If PingFederate is configured to handle consent approval, the **Scope Description**, **Scope Group Description**, and **Default Scope Description** fields determines the text that appears on the **Request for Approval** window.

### Default scope

The default scope is the implied permissions when no scope and scope group values are indicated, or in addition to any scope or scope group values.

If your organization requires a localized description, enter a unique alias in the **Default Scope Description** field, such as `oauth.approval.page.template.defaultScope`. Insert the same alias with the desired localized text in the applicable language resource files, located in `<pf_install>/pingfederate/server/default/conf/language-packs`.

### Static scopes and scope groups

You can enter simple descriptions or localize the descriptions by using the PingFederate localization framework.

### Dynamic scopes

You can enter simple descriptions. You can also use a mix of text and scope-description variables. `${scope}` represents the requested scope, and `${scope-var}` represents the variable component found in the requested scope.

Suppose you added a dynamic scope with a pattern of `dynaGet67*10` and a scope description of `${scope} contains ${scope-var}`. If a client requests a scope value of `dynaGet67eight910`, the resulting scope description is `dynaGet67eight910 contains eight9`. (`eight9` is the variable component found in the requested scope.)

If your organization requires a localized description, enter a unique alias in the **Scope Description** field (for example, `oauth.approval.page.template.someDynamicScope`). Then insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory. You may also use scope-description variables as part of the localized text.



#### Note:

Both scope-description variables are intended for dynamic scopes only. When they are used as description for static scopes or a scope groups, PingFederate shows them on the **Request for Approval** window.

## Dynamic scopes and consent user interface

The default consent approval process and user interface in PingFederate are capable of handling dynamic scopes and their scope descriptions. While the scope description and the optional scope-description variables provide the basic controls to describe a given scope, PingFederate also supports the use of an external web application to prompt for authorization consent. This allows you to retrieve additional information specific to the users and apply application-specific scope-processing logic.

## Coordinating with developers

Regardless of whether a static scope, a scope group, or a dynamic scope is created as common or exclusive, a scope or a scope group represents access to a resource or API on the RS. Applicable scope or scope group values require coordination with developers that are familiar with the details of the RS OAuth implementation. For clients supporting the OpenID Connect protocol, you can direct the developers to your PingFederate OpenID Provider configuration endpoint to retrieve a list of common scopes and common scope groups.

**Note:**

The OpenID Provider configuration endpoint does not return exclusive static scopes, exclusive scope groups, common dynamic scopes, and exclusive dynamic scopes by default. You can optionally customize the response to include such scopes and scope groups as needed.

**Defining scopes**

PingFederate manages scopes and scope groups in common and exclusive buckets.

## About this task

Common scopes and scope groups are optional. They are available to all clients by default. You can restrict individual clients to a subset of common scopes or scope groups on a client-by-client basis in their client configurations.

Exclusive scopes and scope groups are also optional. They are restricted from all clients by default. However, you can grant individual clients access to one or more exclusive scopes or scope groups in their client configurations.

You can also create static scopes, static scope groups, and dynamic scopes. Scope groups allow clients to request a "super scope" and optionally downgrade to a subset of it later. Dynamic scopes address the business requirement where clients want to request authorization by using scope values with a variable component from one request to another. For detailed information about scopes, see [Scopes and scope management](#) on page 531.

You can manage scopes, scope groups, and the default scope description from **System # OAuth Settings** on the **Scope Management** window. Configuration steps for common and exclusive scopes and scope groups are identical.

**Note:**

A scope or scope group is either a common scope or group, or an exclusive scope or group. Duplicate scopes and scope groups are not allowed.

**Tip:**

Create scopes that are for the majority of clients as common scopes. Create scopes that are for a minority of clients as exclusive scopes. You can organize common or exclusive static scopes into common or exclusive scope groups.

## Steps

1. Go to **System # OAuth Settings # Scope Management**.

2. On the **Common Scopes** or **Exclusive Scopes** tab, configure any number of common or exclusive static scopes.
  - a. Enter a static scope value and a description in the **Scope Value** and **Scope Description** fields.  
Scope values are case-sensitive. A requested scope value of `email` does not match a configured static scope value of `Email`. Do not use backslashes (\) or double quotation marks (") in the **Scope Value** field.

 **Note:**

If PingFederate is configured to handle consent approval and your organization requires a localized description, enter a unique alias in the **Scope Description** field. For more information, see [Description for scopes and scope groups](#).

- b. Click **Add**.
  - c. Repeat to configure additional static scopes. Display order does not matter.
3. On the **Common Scopes** or **Exclusive Scopes** tab, configure any number of common or exclusive dynamic scopes.
  - a. Enter a dynamic scope pattern and a description in the **Scope Value** and **Scope Description** fields.  
You must use a case-sensitive text value with the asterisk character (\*). For supported dynamic scope patterns, see [Dynamic Scopes](#).  
You can enter a simple description, or you can use a mix of text and scope-description variables. For more information, see [Description for scopes and scope groups](#).

 **Note:**

If your organization requires additional information specific to the users or application-specific scope-processing logic, you can configure PingFederate to use an external web application to handle consent approval.

- b. Select the check box under **Dynamic**.
  - c. Click **Add**.
  - d. Repeat to define additional dynamic scopes. Display order does not matter.
4. On the **Common Scopes** or **Exclusive Scopes** tab, configure any number of common or exclusive scope groups.
  - a. Enter a scope group value and its description under **Scope Group Value** and **Scope Group Description**.  
If PingFederate is configured to handle consent approval and your organization requires a localized description, enter a unique alias in the **Scope Group Description** field. For more information, see [Description for scopes and scope groups](#).

 **Note:**

All scope groups are defined as static scope groups. The partial-matching concept is intended for dynamic scopes only and does not apply to scope groups. Like static scope values, scope group

values are case-sensitive. Do not use backslashes (\) or double quotation marks (") in the **Scope Group Value** field.

- b. Select at least one static scope under **Sub Scopes**.

 **Note:**

The administrative console filters out dynamic scopes because the scope-grouping capability is reserved for static scopes only.

- c. Click **Add**.
  - d. Repeat to define additional scope groups. Display order does not matter.
5. Optional: On the **Common Scopes** or **Exclusive Scopes** tab, use the **Edit**, **Update**, and **Cancel** buttons to make or undo a change to an existing entry. Use the **Delete** and **Undelete** buttons to remove an existing entry or cancel the removal request.

 **CAUTION:**

Updating or removing a scope or scope group value in production can cause runtime errors when a client request specifies the scope or scope group using the previously defined value. Errors can also occur when the requesting client is restricted to a scope or scope group that no longer exists unless the affected client configuration is also updated.

6. On the **Default Scope** tab, enter a description for the default scope.

If PingFederate is configured to handle consent approval and your organization requires a localized description, enter a unique alias in the **Default Scope Description** field. For more information, see [Description for scopes and scope groups](#).

 **Note:**

The default scope is the implied permissions when no scope and scope group values are indicated, or in addition to any scope or scope group values.

7. Click **Save**.

## Result

Scopes and scope groups represent access to resources or APIs on the resource server . For clients supporting the OpenID Connect protocol, you can direct the developers to your PingFederate OpenID Provider configuration endpoint to retrieve a list of common scopes and common scope groups.

 **Note:**

By default, the OpenID Provider configuration endpoint does not return exclusive static scopes, exclusive scope groups, common dynamic scopes, and exclusive dynamic scopes. You can customize the response to include such individual scopes and scope groups.

## Adding virtual issuers for OpenID Connect

You can define one or more virtual issuers for OpenID Connect, with or without a relative path. When minting an ID token, PingFederate populates the issuer claim according to the virtual issuer setting and the authorization request.

About this task

To add a virtual issuer to PingFederate, perform the following procedure. If you have multiple virtual issuers, ensure the combination of host and path values are unique.



### Note:

After you define virtual issuers, you can map them to sets of ID token signing keys. For more information, see [Mapping ID token signing keys to virtual issuers](#) on page 681.

Steps

1. Go to **System # OAuth Settings # Virtual Issuers**.
2. Click **Add Virtual Issuer**.
3. Enter a unique issuer **Name**.
4. Enter the **Host**.
5. Optional: Enter the relative **Path**, which must start with the value of the `pf.runtime.context.path` property in the `run.properties` file.
6. Click **Save**.

## Configuring client settings

Use the **Client Settings** window to configure dynamic client registration settings.

Steps

1. On the **Dynamic Client Registration** tab, modify settings as needed.
2. Click **Next** to advance to the next tab.
3. Click **Save** to retain your changes.

### Configuring dynamic client registration settings

Dynamic client registration allows developers to register OAuth clients through an API based on open standards.

About this task

PingFederate supports various client metadata as described in [Supported client metadata](#) on page 544. If specific use cases require additional metadata, add them as extended properties in **System # Server # Extended Properties**.



### Important:

As dynamic client registration can expose your server to unwanted client registrations, we recommend protecting by requiring an initial access token, configuring one or more client registration policies, and protecting access to the dynamic client registration endpoint.



### Note:



Dynamic client registration requires OAuth client storage in an external datastore, such as a database or LDAP directory. If you have not yet switched from the default on-disk client storage to an external

datastore, see [OAuth client datastores](#) on page 971. You can continue with the rest of the configuration; however, dynamic client registration remains inactive until an external client storage is defined.

### Steps

1. Go to **System # OAuth Settings # Client Settings** and click **Dynamic Client Registration**.
2. Select the check boxes for the options that you want to use.

The following table describes each option.

| Option                             | Description  |
|------------------------------------|--|
| Enable Dynamic Client Registration | Select this option to enable dynamic client registration. This option is disabled by default.  |
| Require Initial Access Token       | Select this option to require an initial access token. If selected, you must also select the required scope or scope group from the list.  |
|                                    |  <b>Important:</b><br>Although optional, selecting this option can prevent unwanted client registrations.   |
|                                    |  <b>Note:</b><br>Developers must be set up to obtain access tokens with the required scope or scope group from your PingFederate authorization server. For example, you can create a new OAuth client for a group of developers, assign this client a specific scope for the purpose of creating other clients using the OAuth 2.0 Dynamic Client Registration protocol, and let the developers obtain their access tokens directly by completing one of the supported OAuth flows. You can also write a custom web application that uses the OAuth flow to obtain access tokens on behalf of the developers as they make their requests. |
|                                    | This option is enabled by default.   |

| Option  | Description  |
|---|--|
| Enable Dynamic Client Registration Management | <p>Select this option to enable dynamic client registration management, and to make the following three client management/maintenance options visible.</p> <ul style="list-style-type: none"> <li>▪ <b>Rotate Client Secret</b> - Select this option to rotate the client secret when a client updates or retrieves its configuration. This option is enabled by default.</li> <li>▪ <b>Rotate Registration Access Token</b> - Select this option to rotate the registration access token when a client updates or retrieves its configuration. This option is enabled by default.</li> <li>▪ <b>Allow Client Delete</b> - Select this option to allow clients to deprovision themselves on the authorizations server. This option is enabled by default.</li> <li>▪ <b>Retain Client Secret</b> - Select this option to allow the client secret to be temporarily retained after a change. This option is not enabled by default.</li> </ul> <p>When enabled, <b>Client Secret Retention period</b> can be configured on the <b>Client Configuration Defaults</b> page.</p> <p>Dynamic client registration management allows a client to retrieve its configuration through <code>GET</code> requests, to update its configuration through <code>PUT</code> requests to the provided registration client URI, and to deprovision itself through a <code>DELETE</code>.</p> <p>For more information, see the <a href="#">OAuth 2.0 Dynamic Client Registration Management Protocol</a>.</p> <p>This option is disabled by default.</p> |

## Result

When dynamic client registration is active, developers can send client registrations to the `/as/clients.oauth2` endpoint to create OAuth clients dynamically.


Other maintenance calls can be made to the `registration_client_uri` returned in the original registration response. This endpoint has the format `/as/clients.oauth2/<clientId>`.


## Supported client metadata

PingFederate supports various client metadata, as described in the following table.

| Metadata field             | Metadata description  |
|----------------------------|---|
| client_name                | A descriptive name for the client instance. This name appears when the user is prompted for authorization.  |
| token_endpoint_auth_method | <p>The client authentication method.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ none</li> <li>▪ client_secret_basic</li> <li>▪ client_secret_post</li> <li>▪ tls_client_auth</li> </ul> <p>For more information, see <a href="#">Mutual TLS Profiles for OAuth clients</a>.</p> <ul style="list-style-type: none"> <li>▪ private_key_jwt</li> </ul> <p>For more information, see <a href="#">Client Authentication</a>.</p> |





| Metadata field                               | Metadata description  |
|--|---|
| <code>tls_client_auth_subject_dn</code>      | <p>The subject DN of the client certificate.</p> <p>This field is required if <code>tls_client_auth</code> is the value of the <code>token_endpoint_auth_method</code> parameter.</p>   |
| <code>token_endpoint_auth_signing_alg</code> | <p>The signing algorithm that the client must use to sign the JSON web tokens (JWT) for client authentication.</p> <p>This field applies only when the <code>token_endpoint_auth_method</code> parameter is provided with a value of <code>private_key_jwt</code>.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>If this parameter is not provided, the client can use any of the supported signing algorithms.</p> |


| Metadata field             | Metadata description  |
|----------------------------|---|
| request_object_signing_alg | <p>The signing algorithm that the client must use to sign its request objects for transmission of request parameters.</p> <p>Applicable only when the client might send its authorization requests using request objects.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>When this parameter is not provided, the client can use any of the supported signing algorithms.</p> <p>For more information about request objects, see <a href="#">JWT Secured Authorization Request (JAR) draft specification</a>.</p> |


| Metadata field        | Metadata description   |
|-----------------------|--|
| jwks_uri, and<br>jwks | <p>The URL of the JSON Web Key Set (JWKS) or the actual JWKS from the client.</p> <p>If the client is configured to use the <code>private_key_jwt</code> client authentication method, to transmit request parameters in signed request objects, or to transmit CIBA request parameters in signed request objects, only one of the previous values is required for to verify the authenticity of the JWTs.</p> <p>Either value can be defined even if the client is not configured to use JWTs for authentication or transmission of request parameters. This flexibility allows the client to transmit request parameters in signed request objects for some requests and without the use of signed request objects for some other transactions. For information on runtime processing, see .</p> <p>If the client signs its JWTs using an RSASSA-PSS signing algorithm, must be deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> <p>If the client is configured to encrypt ID tokens using an asymmetric encryption algorithm, either the JWKS URL or the actual JWKS must be provided. See the <b>ID Token Key Management Encryption Algorithm</b> setting.</p> |
| redirect_uris         | An array of one or more redirection URIs where the OAuth AS may redirect the resource owner's user agent after authorization is obtained. The authorization code and implicit grant types require at least one redirection URI.  |
| logo_uri              | The location of the logo used on user-facing OAuth grant authorization and revocation pages. For best results with the installed HTML templates, the recommended size is 72 x 72 pixels.   |
| scope                 | A space-separated list of one or more scopes, which a client can request.  |
| grant_types           | <p>An array of one or more grant types, which a client can request.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ <code>authorization_code</code></li> <li>▪ <code>implicit</code></li> <li>▪ <code>refresh_token</code></li> <li>▪ <code>client_credentials</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:device_code</code></li> <li>▪ <code>urn:openid:params:grant-type:ciba</code></li> <li>▪ <code>password</code></li> <li>▪ <code>extension</code> (JWT Bearer Token or SAML 2.0 Bearer Assertion)</li> </ul> <p>For more information about each grant type, see <a href="#">Grant types</a>.</p>   |

| Metadata field      | Metadata description  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
|---------------------|---|---------------|-------------|------|--------------------|---------------|---------------------------------|---------------------|---------------------------------|------------|---------------------------------|----------|----------|----------------|----------|-------|----------|
| response_types      | <p>An array of one or more response types, which a client can request.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ code</li> <li>▪ code id_token</li> <li>▪ code id_token token</li> <li>▪ code token</li> <li>▪ id_token</li> <li>▪ id_token token</li> <li>▪ token</li> </ul> <p>For more information about these response types, see <a href="#">Definitions of Multiple-Valued Response Type Combinations</a>.</p> <p>If one or more response types are specified, the resulting client is only allowed to send one of the specified response types at runtime. Requests from this client with other response types will be rejected.</p> <p>Response type and grant type parameters must be provided in tandem because certain response types require one or more grant types, and vice versa. The following table provides a summary of their relationship.</p> <table border="1" data-bbox="537 867 1453 1350"> <thead> <tr> <th data-bbox="537 867 997 919">response type</th> <th data-bbox="997 867 1453 919">grant types</th> </tr> </thead> <tbody> <tr> <td data-bbox="537 919 997 968">code</td> <td data-bbox="997 919 1453 968">authorization_code</td> </tr> <tr> <td data-bbox="537 968 997 1045">code id_token</td> <td data-bbox="997 968 1453 1045">authorization_code and implicit</td> </tr> <tr> <td data-bbox="537 1045 997 1123">code id_token token</td> <td data-bbox="997 1045 1453 1123">authorization_code and implicit</td> </tr> <tr> <td data-bbox="537 1123 997 1201">code token</td> <td data-bbox="997 1123 1453 1201">authorization_code and implicit</td> </tr> <tr> <td data-bbox="537 1201 997 1249">id_token</td> <td data-bbox="997 1201 1453 1249">implicit</td> </tr> <tr> <td data-bbox="537 1249 997 1297">id_token token</td> <td data-bbox="997 1249 1453 1297">implicit</td> </tr> <tr> <td data-bbox="537 1297 997 1350">token</td> <td data-bbox="997 1297 1453 1350">implicit</td> </tr> </tbody> </table> | response type | grant types | code | authorization_code | code id_token | authorization_code and implicit | code id_token token | authorization_code and implicit | code token | authorization_code and implicit | id_token | implicit | id_token token | implicit | token | implicit |
| response type       | grant types   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code                | authorization_code  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code id_token       | authorization_code and implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code id_token token | authorization_code and implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code token          | authorization_code and implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| id_token            | implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| id_token token      | implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| token               | implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |



| Metadata field               | Metadata description   |
|------------------------------|--|
| id_token_signed_response_alg | <p>The JSON Web Signature (JWS) algorithm required for the OpenID Connect ID tokens.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ none - No signing algorithm</li> <li>▪ HS256 - HMAC using SHA-256</li> <li>▪ HS384 - HMAC using SHA-384</li> <li>▪ HS512 - HMAC using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div data-bbox="574 810 1464 1115" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <div data-bbox="521 1129 1464 1335" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>If static keys for OAuth and OpenID Connect are enabled, use either an RSA algorithm or an EC algorithm that has been configured with an active static key.</p> </div> |

| Metadata field                  | Metadata description   |
|---------------------------------|--|
| id_token_encrypted_response_alg | <p>The algorithm used to encrypt or otherwise determine the value of the content encryption key.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ dir - Direct Encryption with symmetric key</li> <li>▪ A128KW - AES-128 Key Wrap</li> <li>▪ A192KW - AES-192 Key Wrap</li> <li>▪ A256KW - AES-256 Key Wrap</li> <li>▪ A128GCMKW - AES-GCM-128 key encryption</li> <li>▪ A192GCMKW - AES-GCM-192 key encryption</li> <li>▪ A256GCMKW - AES-GCM-256 key encryption</li> <li>▪ ECDH-ES - ECDH-ES</li> <li>▪ ECDH-ES+A128KW - ECDH-ES with AES-128 Key Wrap</li> <li>▪ ECDH-ES+A192KW - ECDH-ES with AES-192 Key Wrap</li> <li>▪ ECDH-ES+A256KW - ECDH-ES with AES-256 Key Wrap</li> <li>▪ RSA-OAEP - RSAES-OAEP</li> <li>▪ RSA-OAEP-256 - RSAES OAEP using SHA-256 and MGF1 with SHA-256</li> </ul> |
| id_token_encrypted_response_enc | <p>The content encryption algorithm used to perform authenticated encryption on the plain text payload of the token.</p> <p>Required if an algorithm is provided through the <b>id_token_encrypted_response_alg</b> parameter.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ A128CBC-HS256 - Composite AES-CBC-128 HMAC-SHA-256</li> <li>▪ A192CBC-HS384 - Composite AES-CBC-192 HMAC-SHA-384</li> <li>▪ A256CBC-HS512 - Composite AES-CBC-256 HMAC-SHA-512</li> <li>▪ AES-GCM-128 - A128GCM</li> <li>▪ AES-GCM-192 - A192GCM</li> <li>▪ AES-GCM-256 - A256GCM</li> </ul>  |

| Metadata field                                 | Metadata description  |
|--|---|
| introspection_signing_alg_values (optional)    | <p>The JSON Web Signature (JWS) algorithm used to sign the token introspection response.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ HS256 - HMAC using SHA-256</li> <li>▪ HS384 - HMAC using SHA-384</li> <li>▪ HS512 - HMAC using SHA-512</li> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>The default value is RS256.</p> <p><b>None</b> is not an allowed value.</p> |
| introspection_encryption_alg_values (optional) | <p>The JSON Web Encryption (JWE) algorithm used to encrypt the content-encryption key of the token introspection response.</p> <p>Allowed Values:</p> <ul style="list-style-type: none"> <li>▪ DIR - Direct Encryption with symmetric key</li> <li>▪ A128KW - ES-128 Key Wrap</li> <li>▪ A192KW - AES-192 Key Wrap</li> <li>▪ A256KW - AES-256 Key Wrap</li> <li>▪ A128GCMKW - AES-GCM-128 key encryption</li> <li>▪ A192GCMKW - AES-GCM-192 key encryption</li> <li>▪ A256GCMKW - AES-GCM-256 key encryption</li> <li>▪ ECDH_ES - ECDH-ES</li> <li>▪ ECDH_ES_A128KW - ECDH-ES with AES-128 Key Wrap</li> <li>▪ ECDH_ES_A192KW - ECDH-ES with AES-192 Key Wrap</li> <li>▪ ECDH_ES_A256KW - ECDH-ES with AES-256 Key Wrap</li> <li>▪ RSA_OAEP - RSAES-OAEP</li> <li>▪ RSA_OAEP_256 - RSAES-OAEP using SHA-256</li> </ul> <p>If asymmetric type, a JWKS or JWKS URL is required and must be valid.</p> <p>If symmetric type, the reversible secret is required.</p>   |

| Metadata field                           | Metadata description  |
|--|---|
| introspection_encryption_enc_values      | <p>The JSON Web Encryption (JWE) content-encryption algorithm for the token introspection response.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ AES_128_CBC_HMAC_SHA_256 - Composite AES-CBC-128 HMAC-SHA-256</li> <li>▪ AES_192_CBC_HMAC_SHA_384 - Composite AES-CBC-192 HMAC-SHA-384</li> <li>▪ AES_256_CBC_HMAC_SHA_512 - Composite AES-CBC-256 HMAC-SHA-512</li> <li>▪ AES_128_GCM - Composite A128GCM</li> <li>▪ AES_192_GCM - Composite A192GCM</li> <li>▪ AES_256_GCM - Composite A256GCM</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is required if <code>introspection_signing_alg_values_supported</code> is specified.</p> <p>This field must be empty if <code>introspection_signing_alg_values_supported</code> is not specified.</p> </div> |
| backchannel_token_delivery_method        | <p>The token delivery method that the client supports. supports poll and ping.</p> <p>Set to <code>poll</code> if the client can check for the authorization results periodically at the token endpoint.</p> <p>Set to <code>ping</code> if the client prefers to wait for a ping callback message from as a signal that the authorization result is ready for pickup.</p> <p>If this parameter is not provided and the CIBA grant type is enabled, the poll method is assumed.</p>   |
| backchannel_client_notification_endpoint | <p>The client notification endpoint, to which sends its ping call back messages.</p> <p>Required only if <code>ping</code> is the configured token delivery method.</p>   |



| Metadata field                               | Metadata description   |
|--|--|
| backchannel_authentication_signing_algorithm | <p>The signing algorithm that the client must use to sign its request objects for transmission of request parameters.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>If this parameter is not provided and the CIBA grant type is enabled, the client can use any of the allowed signing algorithms.</p> |
| backchannel_user_code_parameter              | <p>Indicates whether the client supports user code.</p> <p>The purpose of this code is to authorize the transmission of an authentication request to the user's authentication device.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided and the CIBA grant type is enabled, user code support is not enabled.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When user code support is enabled, the associated CIBA request policy must also be user code enabled.</p> </div>   |
| sector_identifier_uri                        | <p>A URL using the HTTPS scheme that references a JSON file containing an array of <code>redirect_uri</code> values. For more information, see <a href="https://openid.net/specs/openid-connect-registration-1_0.html#SectorIdentifierValidation">https://openid.net/specs/openid-connect-registration-1_0.html#SectorIdentifierValidation</a>.</p>  |
| subject_type                                 | <p>The type of subject used by the sector identifier, such as <code>public</code> or <code>pairwise</code>.</p>  |

## Configuring scope constraints

On the **Scope Constraints** tab, you can configure which scopes or scope groups that developers can request when registering clients using dynamic client registration.

### About this task

All clients created through dynamic client registration share this configuration. If a certain client requires a different set of common scopes, exclusive scopes, or both, modify the client configuration using the administrative console, the administrative API, or the OAuth Client Management Service after the client has been created. Scopes can also be overridden by client registration policies enforced during dynamic client registration.

### Steps

1. Go to **System # OAuth Settings # Client Settings** and click **Scope Constraints**.
2. To restrict clients created with the Dynamic Client Registration protocol to a subset of common scopes, select the **Restrict Common Scopes** check box and one or more applicable common scopes.

Result:

Your selections impact the developers in several ways:

- If you do not select the **Restrict Common Scopes** check box, developers can send client registrations without including the desired scopes. If the requests are valid, the clients are configured with all the common scopes and scope groups.
  - If you select the **Restrict Common Scopes** check box without selecting at least one common scope or scope group, clients resulting from valid client registrations are configured without any common scopes or scope groups.
  - If you select the **Restrict Common Scopes** check box with one or more applicable common scopes or scope groups, developers must send client registrations with the desired common scopes and scope groups. Otherwise, clients resulting from otherwise valid requests are also configured without any common scopes or scope groups.
3. To allow clients created with the Dynamic Client Registration protocol to request for a subset of exclusive scopes, select one or more applicable exclusive scopes in the **Allowed Exclusive Scopes** field.

Result:

Your selections impact the developers in several ways:

- If you do not select any exclusive scope, clients resulting from valid client registrations are configured without any exclusive scopes or scope groups.
- If you select one or more applicable exclusive scopes or scope groups, developers must send client registrations with the desired exclusive scopes and scope groups. If they fail to do so, clients resulting from otherwise valid requests are also configured without any exclusive scopes or scope groups.

### Result

Restricting common scopes and allowing exclusive scopes are not mutually exclusive. You can configure both options based on your use cases.

If you configure both options, developers must send client registrations with the desired common and exclusive scopes.

Depending on the configured dynamic scope patterns and whether they are defined as common or exclusive dynamic scopes, this configuration can impact the results of scope evaluation. The default scope is always available to all clients. For more information, see the **Dynamic scope evaluation and per-client scope management** section in [Scopes and scope management](#) on page 531.

## Managing client configuration defaults

On the **Client Configuration Defaults** tab, specify the default settings that are proprietary to PingFederate for clients created with the OAuth 2.0 Dynamic Client Registration protocol.


### About this task


Although these settings are shared among all clients created through dynamic client registration, they can be overridden by client registration policies enforced during dynamic client registration. You can also modify the client configuration using the administrative console, the administrative API, or the OAuth Client Management Service after the client has been created.

### Steps


1. Go to **System # OAuth Settings # Client Settings** and click **Client Configuration Defaults**.
2. Optional: Modify the default values as needed.



The following table describes each field.


| Field                                      | Description   |
|--|---|
| <b>Private Key JWT - Replay Prevention</b> | <p>This field determines whether mandates a unique signed JWT from the client for each request when the client is configured to authenticate via the <code>private_key_jwt</code> client authentication method, to transmit request parameters using in signed request objects, or to do both.</p> <p>This check box is not selected by default.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The underlying Assertion Replay Prevention Service is cluster-aware. For more information, see <a href="#">Assertion Replay Prevention Service</a> on page 204.</p> </div> |
| <b>Require Signed Requests</b>             | <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <code>request</code>. The value of the <code>request</code> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>This check box is not selected by default.</p>  |

| Field   | Description   |
|---|---|
| <b>Require JWT Secured Authorization Response Mode (JARM)</b> | <p>When selected, the client must use JARM. The client's authorization requests must include one of the following authorization response mode values:</p> <ul style="list-style-type: none"> <li>▪ <code>jwt</code>: <ul style="list-style-type: none"> <li>▪ query JWT response in the case of the authorization code grant</li> <li>▪ fragment JWT response in the case of the implicit grant</li> </ul> </li> <li>▪ <code>query.jwt</code>: <ul style="list-style-type: none"> <li>▪ JWT response in the case of the authorization code grant</li> <li>▪ Failure in the case of the implicit grant unless the response is an encrypted JWT based on the client settings</li> </ul> </li> <li>▪ <code>fragment.jwt</code>: fragment JWT response</li> <li>▪ <code>form_post.jwt</code>: auto form-post JWT response</li> </ul> <p>JARM is a mechanism to enhance the security of the standard authorization response. It adds support for signing and encryption, sender authentication, and audience restriction. It also offers protection from replay, credential leakage, and mix-up attacks. JARM can be combined with any response type. For more information, see the <a href="#">JARM specification</a>.</p> <p>This setting works in conjunction with the other <b>JWT Secured Authorization Response Mode</b> settings on this window.</p> <p>This check box is cleared by default.</p> |
| <b>Default Access Token Manager</b>                           | <p>Determines the default Access Token Management (ATM) instance for this client.</p>   |
| <b>Restrict to Default Access Token Manager</b>               | <p>If selected, the client can use only the <b>Default Access Token Manager</b>, even if other ATMs include the client in their access control lists.</p> <p>This check box is not selected by default.</p>   |
| <b>Persistent Grants Max Lifetime</b>                         | <p>Overrides the <b>Persistent Grant Max Lifetime</b> value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Grants Do Not Expire</b></li> <li>▪ A custom value in days, hours, or minutes.</li> </ul> <div data-bbox="573 1461 1463 1856" style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This setting can be overridden per grant-mapping configuration through the use of an extended persistent grant attribute <code>PERSISTENT_GRANT_LIFETIME</code>. The <code>PERSISTENT_GRANT_LIFETIME</code> attribute is defined in <b>System # OAuth Settings # Authorization Server Settings</b>. When this attribute is active, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions in individual grant-mapping configurations. For grant-mapping configurations that do not require this fine-grain control, you can configure them to use the default value.</p> </div>   |

| Field  | Description  |
|--|--|
| <b>Persistent Grants Idle Timeout</b>              | <p>Overrides the <b>Persistent Grant Idle Timeout</b> field value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Grants Do Not Timeout Due To Inactivity</b></li> <li>▪ A custom value in days, hours, or minutes.</li> </ul> <p>If you configure an idle timeout value, the idle timeout window slides when a persistent grant updates. When you have an idle timeout value configured without a maximum lifetime, persistent grants remain valid until they expire due to inactivity or until the grant storage revokes or removes them. When you have an idle timeout value configured with a maximum lifetime, persistent grants remain valid until they expire due to inactivity or lifetime expiration or until the grant storage removes them. For more information, see <a href="#">Transient grants and persistent grants</a> on page 88.</p> |
| <b>Client Authentication Certificate Issuer DN</b> | <p>Select a trusted CA from the list. You can review CA certificates imported into PingFederate them in <b>Security # Certificate &amp; Key Management # Trusted CAs</b>. You can select <b>Trust Any</b> to trust all the issuers found in the list.</p> <p>The default selection is <b>None (Client TLS Certificate Authentication Disabled)</b>, which does not allow developers to submit client registrations with a <code>token_endpoint_auth_method</code> parameter value of <code>tls_client_auth</code>.</p>   |
| <b>Refresh Token Rolling Policy</b>                | <p>Overrides the <b>Roll Refresh Token Values</b> setting configured globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Roll</b></li> </ul> <p>This value does not override the <b>Minimum Interval to Roll Refresh Tokens</b> value set in the <b>Authorization Server Settings</b> window.</p> <ul style="list-style-type: none"> <li>▪ <b>Don't Roll</b></li> </ul>   |
| <b>Refresh Token Rolling Interval</b>              | <p>Overrides the <b>Minimum Interval to Roll Refresh Tokens</b> value set in the <b>Authorization Server Settings</b> window.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ A custom value in hours. The maximum is 8760 hours (365 days).</li> </ul>  |


| Field   | Description  |
|---|--|
| <b>Refresh Token Rolling Grace Period (seconds)</b> | <p>The amount of time in seconds that a rolled refresh token is still valid in the event that the client failed to receive an updated one during a roll.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"><li>▪ <b>Use Global Setting</b> (default)</li><li>▪ A custom value in seconds. The maximum is 86400.</li></ul> <p>For security reasons, we recommend setting the custom value as low as possible.</p> <div data-bbox="565 506 1464 766"><p> <b>Note:</b></p><p>If specified:</p><ul style="list-style-type: none"><li>▪ the currently issued refresh tokens must be refreshed once and converted to the new format.</li><li>▪ this overrides the <b>Authorization Server Settings</b> default setting.</li></ul></div> |

| Field          | Description  |
|----------------|--|
| OpenID Connect | <p data-bbox="581 218 909 249">ID Token Signing Algorithm</p> <p data-bbox="626 275 1451 338">Select the signing algorithm for the ID tokens from the list. The default algorithm is <b>RSA using SHA-256</b>.</p> <p data-bbox="626 357 1451 575">If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div data-bbox="626 596 1451 911" style="border: 1px solid black; padding: 5px;"> <p data-bbox="626 617 748 653"> <b>Note:</b></p> <p data-bbox="626 678 1406 768">If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p data-bbox="626 789 1425 879">Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <div data-bbox="626 932 1451 1373" style="border: 1px solid black; padding: 5px;"> <p data-bbox="626 953 748 989"> <b>Note:</b></p> <p data-bbox="626 1014 1406 1199">While all settings on this window can be overridden by client registration policies enforced during the registration, <b>ID Token Signing Algorithm</b> is the only default setting that can also be overridden by including a different <code>id_token_signed_response_alg</code> client metadata value in the client registration.</p> <p data-bbox="626 1220 1451 1341">For a list of supported signing algorithm, see the <code>id_token_signing_alg_values_supported</code> parameter values returned by the PingFederate OpenID Provider configuration endpoint at <code>/.well-known/openid-configuration</code>.</p> </div> <p data-bbox="581 1398 656 1430">Policy</p> <p data-bbox="626 1455 1252 1486">Select a specific OpenID Connect policy from the list.</p> |

| Field                       | Description  |
|-----------------------------|--|
| <b>Device Authorization</b> | <p>Determines whether to use global device authorization grant settings defined in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>The default selection is <b>Use Global Settings</b>.</p> <p>You can select <b>Override</b> and configure any of the following settings.</p> <p><b>User Authorization URL</b></p> <p>This field determines whether should use a different URL when formulating the verification URLs to be included in its device authorization responses. For more information, see <a href="#">Device authorization endpoint</a> on page 1182.</p> <p>For example, if this field is configured with a value of <code>https://www.example.org/welcome</code>, returns <code>https://www.example.org/welcome</code> and <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> as the verification URIs.</p> <p>After processing the device authorization response, which includes the verification URIs, the device presents one of them to the user. The user is expected to browse to the presented verification URI on a second device.</p> <div data-bbox="617 850 1468 1087" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>The target web server must redirect the browser to at its user authorization endpoint. For more information, see <a href="#">User authorization endpoint</a> on page 1185. It must also preserve the <code>user_code</code> parameter value, if provided.</p> </div> <p>For example, if your server's base URL is <code>https://www.example.com</code> and the <b>User Authorization URL</b> value is <code>https://www.example.org/welcome</code>, the target web server must redirect as follows:</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.org/welcome</code> to <code>https://www.example.com/as/user_authz.oauth2</code></li> <li>▪ <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> to <code>https://www.example.com/as/user_authz.oauth2?user_code=&lt;activationcode&gt;</code></li> </ul> <p>This field has no default value.</p> <p><b>Pending Authorization Timeout (seconds)</b></p> <p>The lifetime of an activation code (the <code>user_code</code> parameter value) in seconds.</p> <p>This field has no default value.</p> <p><b>Device Polling Interval (seconds)</b></p> <p>The amount of time in seconds that the device waits between polling requests to the token endpoint.</p> <p>This field has no default value.</p> <p><b>Bypass Activation Code Confirmation</b></p> <p>When receives a verification request that includes an activation code (the <code>user_code</code> parameter value), it prompts the user to confirm the activation code.</p> <p>For to skip this confirmation step, select this check box.</p> <p>This check box is not selected by default.</p> |



| Field   | Description  |
|---|--|
| <b>Require Proof Key for Code Exchange (PKCE)</b> | <p>This field is only applicable when the client is configured to support the authorization code grant type.</p> <p>Determines whether the client must provide certain parameters to reduce the risk of authorization code interception attack. For more information, see the Proof Key for Code Exchange (PKCE) by OAuth Public Clients specification.</p> <p>When enabled, this client must include a one-time string value through the use of the <code>code_challenge</code> parameter in its authorization request. For more information, see <a href="#">Authorization endpoint</a> on page 1147. It must also submit the corresponding code verifier through the <code>code_verifier</code> parameter in its token request when exchanging an authorization code for an access token. For more information, see <a href="#">OAuth grant type parameters</a> on page 1164.</p> <p>This check box is not selected by default.</p> |
| <b>Polling Interval (seconds)</b>                 | <p>Specifies the number of seconds that the client must wait between its attempts to check for the authorization results at the token endpoint. When receives a token request within this time interval, it returns a <code>slow_down</code> error message to the client.</p> <p>A valid value ranges from 1 to 3600.</p> <p>The default value is 3.</p>   |
| <b>Policy</b>                                     | <p>Specifies the CIBA request policy associated with the client.</p> <p>uses CIBA request policies to determine various aspects of CIBA authentication request, such as the maximum lifetime of authentication requests, the validity of unsigned login hint tokens, and the mapping configuration of identity hints.</p> <p>Select an existing CIBA policy. You may also leave the selection of <b>Default</b> to indicate that should use the CIBA request policy that has been designated as the default CIBA request policy in <b>Applications # OAuth # CIBA Request Policies</b>.</p>  |
| <b>Require CIBA Signed Requests</b>               | <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <code>request</code>. The value of the <code>request</code> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>This check box is not selected by default.</p> <p>Note that if client-initiated back channel authentication (CIBA) signed requests are required, the dynamic client registration must include either the JWKS URL or the actual JWKS.</p>  |
| <b>Token Exchange</b>                             | <p>This field determines which token exchange processor policy PingFederate uses when the OAuth server receives an OAuth token exchange request from the client. If you select <b>Default</b>, PingFederate uses the token exchange processor policy that was set as the default on the <b>Token Exchange Processor Policy Management</b> tab, under <b>Applications # Token Exchange # Processor Policies</b>.</p> <p>For more information, see <a href="#">OAuth token exchange</a>.</p>   |

| Field                                 | Description   |
|---------------------------------------|---|
| <b>Client Secret Retention Period</b> | <p>Set the number of minutes that PingFederate retains a client secret after it is replaced. The retention period lets application teams update the client secret in their apps without disruption.</p> <p>If the value is 0, PingFederate won't retain replaced secrets. The maximum value is 43800, which is one month.</p> <p>Use one of these options:</p> <ul style="list-style-type: none"> <li>▪ Select <b>Use Global Setting</b>, which is configured on the <b>Authorization Server Settings</b> window</li> <li>▪ Override the global setting by entering a number in the field</li> </ul> <p>The default is to use the global setting. For information about configuring the global setting, see "Client Secret Retention Period" in <a href="#">Configuring authorization server settings</a> on page 519.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You must select the <b>Retain Client Secret</b> check box on the <b>Dynamic Client Registration</b> page for this option to appear.</p> </div> |

### Selecting client registration policies

Client registration policies can provide additional control over which registrations and configurations are accepted and stored for each client created with the OAuth 2.0 Dynamic Client Registration protocol.

#### About this task

If multiple policies are configured, PingFederate executes all of them based on the display order. If PingFederate completes the current policy, it moves on to the next policy. Otherwise, PingFederate returns an error message to the developers.

#### **Note:**

PingFederate must complete all policies successfully before a client can be created with the OAuth 2.0 Dynamic Client Registration protocol.

#### Steps

1. Go to **System # OAuth Settings # Client Registration Policies**.
2. Optional: Select a Client Registration Policy instance from the **Available Policies** list and click **Add**.

#### **Important:**

Select this option to add a layer of protection against unwanted client registrations.

If you have not yet defined the desired Client Registration Policy instance, click **Manage Client Registration Policies**.

3. Optional: Repeat the previous step to add other Client Registration Policy instances.

Add as many Client Registration Policy instances as necessary. Click the up and down arrows to adjust the execution order. Use the **Delete** and **Undelete** buttons to remove an existing instance or cancel the removal request.

## Reviewing client settings

On the **Summary** tab, review your client settings.

### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## Managing Client Registration Policy instances

The Client Registration Policy plugin allows you to write custom processing rules to provide additional control over which registrations and configurations are accepted and stored for each client created with the OAuth 2.0 Dynamic Client Registration protocol.

### About this task

Depending on the technical requirements of your use cases, you can create Client Registration Policy plugins using the PingFederate SDK. After deploying your plugins, you can create and configure instances of them. Configuration requirements vary based on your custom solutions. When you are ready to configure dynamic client registration, add your policies to its configuration.

### Steps

1. Implement the `DynamicClientRegistrationPlugin` interface.

For more information, refer to the [Javadoc for the `DynamicClientRegistrationPlugin` interface](#), the `SoftwareStatementValidatorPlugin.java` file for a sample implementation, and the SDK developer's guide for build and deployment information.

#### Tip:

The Javadoc for [and the sample implementation](#) are in the `<pf_install>/pingfederate/sdk` directory.

2. Create, modify, or remove one or more instances.  
Choose from:

- To configure a new instance, click **Create New Instance**.
- To modify an existing instance, select it under **Instance Name**.
- To remove an existing instance or to cancel the removal request, click **Delete** or **Undelete** under **Action**.

#### Note:

You can remove a Client Registration Policy instance only if it is not currently in-use by dynamic client registration.

- To save the plugin configuration, click **Save**.

### Result

#### Important:

A Client Registration Policy instance is not enforced, or executed as part of the dynamic client registration process, until it is selected on the **Client Registration Policies** window.

### Configuring a Client Registration Policy instance

For additional control over clients created with the OAuth 2.0 Dynamic Client Registration protocol, use the **Client Registration Policies** window to create or modify a Client Registration Policy instance.

#### Steps

1. Go to **System # OAuth Settings # Client Registration Policies**.  
Choose from:
  - To configure a new instance, click **Create New Instance**.
  - To modify an existing instance, select it under **Instance Name**.
2. On the **Type** tab, enter a name and an ID for a new instance, and then select a plugin from the list.

When modifying an existing policy plugin instance, you can only change the **Instance Name** field.

If the **Type** list does not contain the desired Client Registration Policy plugin, create one using the PingFederate SDK. For more information, refer to the Javadoc for the `DynamicClientRegistrationPlugin` interface, the `SoftwareStatementValidatorPlugin.java` file for a sample implementation, and the SDK developer's guide for build and deployment information.



#### Tip:

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

3. In the **Instance Configuration** tab, follow the on-screen instructions to configure the Client Registration Policy instance.



#### Note:

This window varies depending on the selected Client Registration Policy plugin.

4. On the **Summary** tab, review the plugin configuration. Click **Done**.
5. In the **Client Registration Policies** window, click **Save**.

#### Result



#### Important:

A Client Registration Policy instance is not enforced, or executed as part of the dynamic client registration process, until it is selected on the **Client Registration Policies** window.

### Configuring a Response Type Constraints instance

The Response Type Constraints policy plugin allows administrators to control which flows are allowed for clients created through the OAuth 2.0 Dynamic Client Registration protocol.

#### About this task

Configure an instance of the Response Type Constraints policy to limit which of the following `response_types` parameter values are allowed:

- **code**

- **code id\_token**
- **code id\_token token**
- **code token**
- **id\_token**
- **id\_token token**
- **token**

For more information about flows and response types, see the [OpenID Connect specification](#).

#### Steps

1. Go to **System # OAuth Settings # Client Registration Policies**.  
Choose from:
  - To configure a new instance, click **Create New Instance**.
  - To modify an existing instance, select it under **Instance Name**.
2. On the **Type** tab, enter a name and an ID for a new instance, and then select **Response Type Constraints** from the **Type** list.  
  
When modifying an existing policy plugin instance, you can only change the **Instance Name** field.
3. On the **Instance Configuration** tab, clear the applicable check boxes to remove the unwanted response types.



#### Note:

All response types are allowed by default.

4. On the **Summary** tab, review the plugin configuration. Click **Done**.
5. In the **Client Registration Policy Instances** window, click **Save**.

#### Result



#### Important:

Like other Client Registration Policy plugins, an instance of the Response Type Constraints policy plugin is not enforced, or executed as part of the dynamic client registration process, until it is selected in **System # OAuth Settings # Client Registration Policies**. If it is selected in the **Client Registration Policies** window, PingFederate discards all restricted response types when processing client registrations. If no response type is allowed, PingFederate rejects the registration and returns an error message to the originator.

## Managing OAuth clients

An OAuth client application interacts with an OAuth authorization server to obtain the required access tokens to call OAuth-protected services at the resource server.

#### About this task

The **Clients** window displays 20 clients at a time. You can sort the display order by name or ID. You can use the pagination controls to navigate through the rest of the clients or search clients by name or ID. A client is included in the search results if its name or ID is a partial, case-insensitive match to the search term.

#### Steps

To manage OAuth clients, go to **Applications # OAuth # Clients**.

| Action   | Steps  |
|--|--|
| To add a client                                  | Click <b>Add Client</b> and complete the configuration in the <b>Client</b> window.                      |
| To edit a recently modified client               | Select the client and update the configuration in the <b>Client</b> window.                              |
| To enable or disable one or more clients         | Click their toggle switches and then click <b>Save</b> .   |
| To remove a client or cancel the removal request | Use the <b>Delete</b> and <b>Undelete</b> buttons for the applicable client and then click <b>Save</b> . |

### Result

stores client records in XML files by default. On-disk storage allows you to manage clients using the administrative console and the administrative API. Client records are part of the configuration archive.

Alternatively, you can configure PingFederate to store client records externally, which allows you to manage client records through the OAuth Client Management Service or enable dynamic client registration for your partner-developers. In this case, client records are not part of the configuration archive. Instead, PingFederate stores them on a database server, a directory server, or another storage medium through the use of the PingFederate SDK. For more information, see [OAuth client datastores](#) on page 971.



### Configuring OAuth clients


The **Client** window provides controls over the usage and behavior of the applications requesting access to protected resources through the PingFederate OAuth authorization server (AS).

### Steps

1. Go to **Applications # OAuth # Clients**.
2. Configure a new or existing OAuth client to suit your use cases.



The following table describes each field on the **Client** window.


| Field                          | Description   |
|--------------------------------|---|
| <b>Client ID</b><br>(Required) | A unique identifier the client provides to the resource server (RS) to identify itself. This identifier is included with every request the client makes.  |
| <b>Name</b><br>(Required)      | A descriptive name for the client instance. This name appears when the user is prompted for authorization.<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Tip:</b><br/>If you want to localize the displayed name, you can enter a unique alias here, then use the same alias in language resource files. </div>                      |
| <b>Description</b>             | A description of what the client application does. This description appears when the user is prompted for authorization.<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Tip:</b><br/>If you want to localize the displayed description, you can enter a unique alias here, then use the same alias in language resource files. </div> |


| Field                        | Description   |
|------------------------------|---|
| <b>Client Authentication</b> | <p>The authentication method that the client uses.</p> <p><b>None</b></p> <p>Select this option if your use case does not require client authentication. This is the default selection.</p> <div data-bbox="613 396 1468 856" style="border: 1px solid black; padding: 10px;"> <p> <b>Note:</b></p> <p>A selection other than <b>None</b> is required for any of the following use cases:</p> <ul style="list-style-type: none"> <li>▪ This client uses the <b>Client Credentials</b> grant type. See the <b>Allowed Grant Types</b> check boxes.</li> <li>▪ This client signs its ID tokens using an HMAC signing algorithm. See the <b>ID Token Signing Algorithm</b> field.</li> <li>▪ This client is allowed to access the Session Revocation API. See the <b>Allow Access to Session Revocation API</b> check box.</li> <li>▪ This client is allowed to access the Session Management API. See the <b>Allow Access to Session Management API</b> check box.</li> </ul> </div> |
|                              | <p><b>Client Secret</b></p> <p>Select this option for HTTP Basic authentication.</p> <ul style="list-style-type: none"> <li>▪ To create a strong, random alphanumeric string or to manually enter a secret, click <b>Generate Secret</b>.</li> <li>▪ To modify an existing secret, select the <b>Change Secret</b> check box. Then, click <b>Generate Secret</b> to create a strong random alphanumeric string or manually enter a secret.</li> </ul>   |
|                              | <p><b>Client Secret Retention Period</b></p> <p>Set the number of minutes that PingFederate retains a client secret after it is replaced. The retention period lets application teams update the client secret in their app without disruption.</p> <p>If the value is 0, PingFederate won't retain replaced secrets. The maximum value is 43800, which is one month.</p> <p>Use one of these options:</p> <ul style="list-style-type: none"> <li>▪ Select <b>Use Global Setting</b>, which is configured on the <b>Authorization Server Settings</b> window</li> <li>▪ Override the global setting by entering a number in the field</li> </ul> <p>The default is to use the global setting. For information about configuring the global setting, see "Client Secret Retention Period" in <a href="#">Configuring authorization server settings</a> on page 519.</p>  |
|                              | <p><b>Client TLS Certificate</b></p> <p>Select this option for mutual TLS certificate-based authentication; recommended for client applications where security policies prohibit storing passwords.</p> <ul style="list-style-type: none"> <li>▪ Select a trusted CA from the <b>Issuer</b> list.</li> </ul> <p>These are CA certificates imported into PingFederate. You can review them on the <b>Security # Certificate &amp; Key Management # Trusted CAs</b> window. Alternatively, you can select <b>Trust Any</b> to trust all the issuers found in the list. <li>▪ Enter the client-certificate subject DN in the <b>Subject DN</b> or extract the subject DN from the certificate if the certificate is stored on an</li> </p>   |


| Field  | Description   |
|--|---|
| <b>Require Pushed Authorization Requests</b>           | <p>When selected, the client must use the PAR endpoint <code>/as/par.oauth2</code> on the AS to initiate authorization flows. When not selected, the client can use the PAR endpoint. This check box is not selected by default.</p> <p>This setting works in conjunction with the <b>PAR Status</b> setting on the AS. For example:</p> <ul style="list-style-type: none"> <li>▪ If PAR is <b>Enabled</b> on the AS and required on the client, then the client must use PAR</li> <li>▪ If PAR is <b>Enabled</b> on the AS but not required on the client, then the client can use PAR</li> <li>▪ If PAR is <b>Required</b> on the AS but not required on the client, then the client must use PAR</li> <li>▪ If PAR is <b>Disabled</b> on the AS and required on the client, then the client cannot access the AS</li> </ul> <p>Do not select this check box if PAR is disabled on the AS.</p> <p>For more information about PAR, see <a href="#">Pushed authorization requests endpoint</a> on page 1191 and <a href="#">Configuring authorization server settings</a> on page 519.</p>  |
| <b>Require JWT Secured Authorization Response Mode</b> | <p>When selected, the client must use JWT secured authorization response mode (JARM). The client's authorization requests must include one of the following authorization response mode values:</p> <ul style="list-style-type: none"> <li>▪ <code>jwt</code>: <ul style="list-style-type: none"> <li>▪ query JWT response in the case of the authorization code grant</li> <li>▪ fragment JWT response in the case of the implicit grant</li> </ul> </li> <li>▪ <code>query.jwt</code>: <ul style="list-style-type: none"> <li>▪ JWT response in the case of the authorization code grant</li> <li>▪ Failure in the case of the implicit grant unless the response is an encrypted JWT based on the client settings</li> </ul> </li> <li>▪ <code>fragment.jwt</code>: fragment JWT response</li> <li>▪ <code>form_post.jwt</code>: auto form-post JWT response</li> </ul> <p>JARM is a mechanism to enhance the security of the standard authorization response. It adds support for signing and encryption, sender authentication, and audience restriction. It also offers protection from replay, credential leakage, and mix-up attacks. JARM can be combined with any response type. For more information, see the <a href="#">JARM specification</a>.</p> <p>This setting works in conjunction with the other <b>JWT Secured Authorization Response Mode</b> settings on this window.</p> <p>This check box is cleared by default.</p> |




| Field                                   | Description   |
|---|---|
| <b>Require Signed Requests</b>          | <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <code>request</code>. The value of the <code>request</code> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <div data-bbox="565 394 1466 825" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If a client includes in an authorization request a request parameter other than <code>client_id</code>, as a parameter outside of the signed request object and a claim inside of the signed request object, always uses the claim value found inside the signed request object to process the request further.</p> <p>For the <code>client_id</code> request parameter, the values outside of the signed request object must match the claim values inside of the signed request object. If the values do not match, returns an error message to the client.</p> <p>If a request parameter is found only outside of the signed request object, ignores the request parameter and returns no error message.</p> </div> <div data-bbox="565 835 1466 1045" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>Per OAuth and OpenID Connect specifications, a client must always include in an authorization request the <code>client_id</code> parameter outside of the signed request object.</p> </div> <p>For more information about request objects, see <a href="#">JWT Secured Authorization Request (JAR) draft specification</a>.</p> |
| <b>Request Object Signing Algorithm</b> | <p>The signing algorithm that the client must use to sign its request objects for transmission of request parameters.</p> <p>Applicable only when the client may send its authorization requests using request objects.</p> <p>If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <p>The default selection is <b>Allow Any</b>, which allows the client to use any of the signing algorithms from the list.</p>  |

| Field                    | Description  |
|--------------------------|--|
| <b>JWKS URL and JWKS</b> | <p>The URL of the JSON Web Key Set (JWKS) or the actual JWKS from the client.</p> <p>If the client is configured to use the <code>private_key_jwt</code> client authentication method, to transmit request parameters in signed request objects, or to transmit CIBA request parameters in signed request objects, only one of the previous values is required for to verify the authenticity of the JWTs.</p> <p>Either value can be defined even if the client is not configured to use JWTs for authentication or transmission of request parameters. This flexibility allows the client to transmit request parameters in signed request objects for some requests and without the use of signed request objects for some other transactions. For information on runtime processing, see .</p> <p>If the client signs its JWTs using an RSASSA-PSS signing algorithm, must be deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> <p>If the client is configured to encrypt ID tokens using an asymmetric encryption algorithm, either the JWKS URL or the actual JWKS must be provided. See the <b>ID Token Key Management Encryption Algorithm</b> setting.</p> |
| <b>Redirection URIs</b>  | <p>URIs where the OAuth AS may redirect the resource owner's user agent after authorization is obtained. The authorization code and implicit grant types require at least one redirection URI.</p> <p>Enter a fully qualified URL and click <b>Add</b> for each entry required. Wildcards are allowed. However, for security reasons, make the URL as restrictive as possible, for example, <code>https://www.example.com/OAuthClientApp/callback.jsp</code>.</p> <div data-bbox="565 1268 1464 1535" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>If more than one URI is added or if a single URI uses wildcards, then the authorization code grant and the token requests must contain a specific matching <code>redirect_uri</code> parameter when contacting the authorization endpoint (<code>/as/authorization.oauth2</code>) and token endpoint (<code>/as/token.oauth2</code>).</p> </div>   |
| <b>Logo URL</b>          | <p>The location of the logo used on user-facing OAuth grant authorization and revocation pages. For best results with the installed HTML templates, the recommended size is 72 x 72 pixels.</p>  |


| Field   | Description  |
|---|--|
| <b>Allow Authentication API Redirectless Mode</b> | <p>When selected, the client can initiate an authentication API OAuth flow through the authorization endpoint without needing to handle HTTP redirections.</p> <p>When enabling this feature, consider the following:</p> <ul style="list-style-type: none"> <li>▪ Redirection URLs are optional, but without a redirection URL, browser-based OAuth flows will not work.</li> <li>▪ This flow does not support the user-facing scope consent page, Request for Approval. So, enabling this feature automatically enables the <b>Bypass Authorization Approval</b> feature and <b>Restrict Common Scopes</b> feature.</li> <li>▪ The client must manage the PF cookie and, if persistent authentication sessions are configured, the PF.PERSISTENT cookie.</li> </ul> <p>For more information, see <a href="#">Mobile application authentication through REST APIs</a> on page 1277.</p> |
| <b>Bypass Authorization Approval</b>              | <p>When selected, resource-owner approval for client access is assumed and PingFederate no longer presents to the user an authorization consent page or redirects to a trusted web application that is responsible to prompt the user for authorization for this client.</p> <p>For instance, use this setting when you want to deploy a trusted application and authenticate end users with an [MISSING glossAcronymn or glossSurfaceform for gIDP]adapter or IdP connection.</p>   |
| <b>Restrict Common Scopes</b>                     | <p>Controls whether all existing and future common scopes and scope groups should be made available to the client, or only the select few.</p> <p>When selected, the administrative console displays a list of existing common scopes and scope groups. Choose the common scope and scope groups that are intended for the client. The rest and any common scopes and scope groups created in the future become invalid for the client. In other words, if the client tries to use such scope or scope group, it will receive an <code>invalid_scope</code> error message from PingFederate.</p> <p>When cleared, all existing common scopes and scope groups and those created in the future are available to the client. This is the default behavior.</p>   |
|   | <div style="border: 1px solid #ccc; padding: 10px;"> <p> <b>Note:</b></p> <p>Depending on the configured dynamic scope patterns and whether they are defined as common or exclusive dynamic scopes, this setting can impact the results of scope evaluation. The default scope, however, is always allowed for and available to all clients. For detailed information, see the Dynamic scope evaluation and per-client scope management section in <a href="#">Scopes and scope management</a> on page 531.</p> </div>  |

| Field                      | Description   |
|----------------------------|---|
| <b>Exclusive Scopes</b>    | <p>Controls whether any exclusive scopes and scope groups should be made available to the client.</p> <p>When selected, the administrative console displays a list of existing exclusive scopes and scope groups. Choose the exclusive scopes and scope groups that are intended for the client. The rest and any exclusive scopes and scope groups created in the future become invalid for the client. In other words, if the client tries to use such scope or scope group, it will receive an <code>invalid_scope</code> error message from PingFederate.</p> <p>When cleared, no exclusive scopes and scope groups are available to the client. This is the default behavior.</p> <div data-bbox="565 583 1472 898" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>Depending on the configured dynamic scope patterns and whether they are defined as common or exclusive dynamic scopes, this setting can impact the results of scope evaluation. The default scope, however, is always allowed for and available to all clients. For detailed information, see the Dynamic scope evaluation and per-client scope management section in <a href="#">Scopes and scope management</a> on page 531.</p> </div> |
| <b>Allowed Grant Types</b> | <p>The grant types that this client can use.</p> <p>Select at least one of the following:</p> <ul style="list-style-type: none"> <li>▪ <b>Authorization Code</b></li> <li>▪ <b>Implicit</b></li> <li>▪ <b>Refresh Token</b></li> <li>▪ <b>Client Credentials</b></li> <li>▪ <b>Device Authorization Grant</b></li> <li>▪ <b>CIBA</b></li> <li>▪ <b>Token Exchange</b></li> <li>▪ <b>Resource Owner Password Credentials</b></li> <li>▪ <b>Assertion Grants</b></li> <li>▪ <b>Access Token Validation (Client is a Resource Server)</b></li> </ul> <p>There is no default selection.</p> <p>For more information about each grant type, see <a href="#">Grant types</a> on page 85.</p>  |




| Field   | Description   |
|---|---|
| <b>Restrict Response Types</b>                  | <p>Select this check box to limit the <code>response_type</code> parameter values that this client can use.</p> <p>Available response types are:</p> <ul style="list-style-type: none"> <li>▪ <b>code</b></li> <li>▪ <b>code id_token</b></li> <li>▪ <b>code id_token token</b></li> <li>▪ <b>code token</b></li> <li>▪ <b>id_token</b></li> <li>▪ <b>id_token token</b></li> <li>▪ <b>token</b></li> </ul> <p>For more information about these response types, see Definitions of Multiple-Valued Response Type Combinations.</p> <p>The <b>Restrict Response Type</b> check box is not selected by default. If selected, you must select at least one allowable <code>response_type</code> parameter value.</p> <p>Additionally, the <b>Restricted Response Types</b> and <b>Allowed Grant Types</b> settings must be configured in tandem because certain response types require one or more grant types, and vice versa.</p> <p>Authorization code grant types are compatible with the following response types:</p> <ul style="list-style-type: none"> <li>▪ code</li> <li>▪ code id_token</li> <li>▪ code id_token token</li> <li>▪ code token</li> </ul> <p>Implicit grant types are compatible with the following response types:</p> <ul style="list-style-type: none"> <li>▪ code id_token</li> <li>▪ code id_token token</li> <li>▪ code token</li> <li>▪ id_token</li> <li>▪ id_token token</li> <li>▪ token</li> </ul> |
| <b>Default Access Token Manager</b>             | <p>Determines the default Access Token Management (ATM) instance for this client.</p>   |
| <b>Restrict to Default Access Token Manager</b> | <p>If selected, this client can use only the <b>Default Access Token Manager</b>, even if other ATMs include this client in their access control lists. When this check box is selected, the <b>Validate Against All Eligible Access Token Managers</b> check box is hidden.</p> <p>This check box is not selected by default.</p>  |


| Field  | Description   |
|--|---|
| <b>Validate Against All Eligible Access Token Managers</b> | <p>Applicable only to resource server clients.</p> <p>If selected, this resource server client is not required to specify the additional <code>access_token_manager_id</code> or <code>aud</code> parameters to disambiguate the ATM instance in its token validation requests. When the resource server client does not specify the desired ATM instance, validates the access tokens against all eligible ATM instances. This simplifies interactions with PingAccess by avoiding the need to align resource URIs between PingAccess and .</p> <p>This check box is not selected by default.</p>  |
| <b>Require Proof Key for Code Exchange (PKCE)</b>          | <p>Displayed only when the client is configured to support the authorization code grant type.</p> <p>Determines whether the client must provide certain parameters to reduce the risk of authorization code interception attack. For more information, see the Proof Key for Code Exchange (PKCE) by OAuth Public Clients specification.</p> <p>When enabled, this client must include a one-time string value through the use of the <code>code_challenge</code> parameter in its authorization request. For more information, see <a href="#">Authorization endpoint</a> on page 1147. It must also submit the corresponding code verifier through the <code>code_verifier</code> parameter in its token request when exchanging an authorization code for an access token. For more information, see <a href="#">OAuth grant type parameters</a> on page 1164.</p> <p>This check box is not selected by default.</p> |
| <b>Persistent Grants Max Lifetime</b>                      | <p>Overrides the <b>Persistent Grant Max Lifetime</b> value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Grants Do Not Expire</b></li> <li>▪ A custom value in days, hours, or minutes.</li> </ul>  |
|  | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This setting can be overridden per grant-mapping configuration through the use of an extended persistent grant attribute <code>PERSISTENT_GRANT_LIFETIME</code>. The <code>PERSISTENT_GRANT_LIFETIME</code> attribute is defined in <b>System # OAuth Settings # Authorization Server Settings</b>. When this attribute is active, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions in individual grant-mapping configurations. For grant-mapping configurations that do not require this fine-grain control, you can configure them to use the default value.</p> </div>  |


| Field   | Description  |
|---|--|
| <b>Persistent Grants Idle Timeout</b>                   | <p>Overrides the <b>Persistent Grant Idle Timeout</b> field value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Grants Do Not Timeout Due To Inactivity</b></li> <li>▪ A custom value in days, hours, or minutes.</li> </ul> <p>If you configure an idle timeout value, the idle timeout window slides when a persistent grant updates. When you have an idle timeout value configured without a maximum lifetime, persistent grants remain valid until they expire due to inactivity or until the grant storage revokes or removes them. When you have an idle timeout value configured with a maximum lifetime, persistent grants remain valid until they expire due to inactivity or lifetime expiration or until the grant storage removes them. For more information, see <a href="#">Transient grants and persistent grants</a> on page 88.</p>   |
| <b>Reuse Existing Persistent Access for Grant Types</b> | <p>Overrides the <b>Reuse Existing Persistent Access Grants for Grant Types</b> setting configured globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Override Global Setting</b> (The admin selects or clears individual grant types as needed.) <ul style="list-style-type: none"> <li>▪ <b>Implicit</b></li> <li>▪ <b>Authorization Code</b></li> <li>▪ <b>Resource Owner Password Credentials</b></li> </ul> </li> </ul> <p>If the <b>Bypass Authorization Approval</b> client setting isn't enabled (the default), when the <b>Implicit</b> check box is selected, PingFederate requests consent from the user only one time. The user isn't asked for authorization on subsequent requests until the access grant is revoked.</p> <p>When the <b>Authorization Code</b> check box is selected, the same is true if the <b>Bypass Authorization for Previously Approved Persistent Grants</b> authorization setting is enabled and the <b>Bypass Authorization Approval</b> client setting is disabled. If the <b>Bypass Authorization Approval</b> client setting is enabled, resource-owner approval for client access is always assumed.</p> |
| <b>Refresh Token Rolling Policy</b>                     | <p>Overrides the <b>Roll Refresh Token Values</b> setting configured globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ <b>Roll</b></li> </ul> <p>This value does not override the <b>Minimum Interval to Roll Refresh Tokens</b> value set in the <b>Authorization Server Settings</b> window.</p> <ul style="list-style-type: none"> <li>▪ <b>Don't Roll</b></li> </ul>   |

| Field  | Description  |
|--|--|
| <p><b>Refresh Token Rolling Interval</b></p>               | <p>Overrides the <b>Minimum Interval to Roll Refresh Tokens</b> value set in the <b>Authorization Server Settings</b> window.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ A custom value in hours. The maximum is 8760 hours (365 days).</li> </ul>  |
| <p><b>Refresh Token Rolling Grace Period (seconds)</b></p> | <p>The amount of time in seconds that a rolled refresh token is still valid in the event that the client failed to receive an updated one during a roll.</p> <p>Select one of the following options:</p> <ul style="list-style-type: none"> <li>▪ <b>Use Global Setting</b> (default)</li> <li>▪ A custom value in seconds. The maximum is 86400.</li> </ul> <p>For security reasons, we recommend setting the custom value as low as possible.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If specified:</p> <ul style="list-style-type: none"> <li>▪ the currently issued refresh tokens must be refreshed once and converted to the new format.</li> <li>▪ this overrides the <b>Authorization Server Settings</b> default setting.</li> </ul> </div> |



| Field          | Description   |
|----------------|---|
| OpenID Connect | <p data-bbox="581 218 909 247">ID Token Signing Algorithm</p> <p data-bbox="626 275 1451 336">Select the signing algorithm for the ID tokens from the list. The default algorithm is <b>RSA using SHA-256</b>.</p> <p data-bbox="626 354 1451 573">If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div data-bbox="626 600 1451 911" style="border: 1px solid black; padding: 5px;"> <p data-bbox="626 615 748 653"> <b>Note:</b></p> <p data-bbox="626 676 1406 768">If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p data-bbox="626 787 1425 879">Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <p data-bbox="581 936 1159 966">ID Token Key Management Encryption Algorithm</p> <p data-bbox="626 984 1446 1045">The algorithm used to encrypt or otherwise determine the value of the content encryption key.</p> <p data-bbox="626 1056 1446 1178">PingFederate supports symmetric algorithms, such as <b>Direct Encryption with symmetric key, AES ... Key Wrap</b>, and <b>AES-GCM ... key encryption</b>, and asymmetric algorithms, such as <b>ECDH-ES, ECDH-ES ... Key Wrap</b>, and <b>RSAES OAEP</b>.</p> <div data-bbox="626 1205 1451 1482" style="border: 1px solid black; padding: 5px;"> <p data-bbox="626 1220 732 1257"> <b>Tip:</b></p> <p data-bbox="626 1276 1409 1369">If you select a symmetric algorithm, you should provide a <b>Client Secret</b>. The client secret will be used as the symmetric key even if your client doesn't use the client secret for authentication.</p> <p data-bbox="626 1388 1443 1449">If you select an asymmetric algorithm, you should provide a <b>JWKS</b> or <b>JWKS URL</b> so PingFederate can find the right client key.</p> </div> <p data-bbox="581 1507 1045 1537">ID Token Content Encryption Algorithm</p> <p data-bbox="626 1556 1377 1617">The content encryption algorithm used to perform authenticated encryption on the plain text payload of the token.</p> <p data-bbox="626 1627 1325 1688">Required if an algorithm is selected from the <b>ID Token Key Management Encryption Algorithm</b> list.</p> <p data-bbox="581 1707 656 1736">Policy</p> <p data-bbox="626 1759 1252 1789">Select a specific OpenID Connect policy from the list.</p> <div data-bbox="581 1822 1451 2028" style="border: 1px solid black; padding: 5px;"> <p data-bbox="581 1837 699 1875"> <b>Note:</b></p> <p data-bbox="581 1898 1425 1997">If the <b>Track User Sessions for Logout</b> check box is selected in the <b>Authorization Server Settings</b> window, PingFederate also displays the <b>PingAccess Logout Capable</b> and <b>Logout URIs</b> fields.</p> </div> <p data-bbox="581 2053 919 2083">PingAccess Logout Capable</p> |

| Field                        | Description   |
|------------------------------|---|
| <b>Session API Endpoints</b> | <p data-bbox="581 218 1101 249"><b>Allow Access to Session Revocation API</b></p> <p data-bbox="626 268 1422 426">Select this check box to allow this client application to add sessions to or query the revocation status via the Back-Channel Session Revocation API endpoint at <code>/pf-ws/rest/sessionMgmt/revokedSris</code>. Authentication is required. This check box is not selected by default.</p> <div data-bbox="626 443 1471 743" style="border: 1px solid black; padding: 10px;"><p data-bbox="626 464 748 501"> <b>Note:</b></p><p data-bbox="626 525 1455 711">If clients are allowed to add sessions to the revocation list, you can enable the <b>Check session revocation status</b> option in the applicable Access Token Management instances for the token validation process to consider whether a session has been added to the revocation list. For more information, see <a href="#">Managing session validation settings</a> on page 612.</p></div> <p data-bbox="581 766 1117 798"><b>Allow Access to Session Management API</b></p> <p data-bbox="626 816 1451 940">The session management API lets client applications get information about user sessions, extend sessions, and revoke sessions. For more information, see <a href="#">Session Management API by session identifiers</a> on page 1233.</p> |

| Field                             | Description  |
|-----------------------------------|--|
| <b>Device Authorization Grant</b> | <p>Determines whether to use global device authorization grant settings defined in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Displayed only if the <b>Device Authorization Grant</b> grant type is enabled for the client.</p> <p>The default selection is <b>Use Global Settings</b>.</p> <p>You can select <b>Override</b> and configure any of the following settings.</p> <p><b>User Authorization URL</b></p> <p>This field determines whether should use a different URL when formulating the verification URLs to be included in its device authorization responses. For more information, see <a href="#">Device authorization endpoint</a> on page 1182.</p> <p>For example, if this field is configured with a value of <code>https://www.example.org/welcome</code>, returns <code>https://www.example.org/welcome</code> and <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> as the verification URIs.</p> <p>After processing the device authorization response, which includes the verification URIs, the device presents one of them to the user. The user is expected to browse to the presented verification URI on a second device.</p> <div data-bbox="617 940 1461 1176" style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Important:</b></p> <p>The target web server must redirect the browser to at its user authorization endpoint. For more information, see <a href="#">User authorization endpoint</a> on page 1185. It must also preserve the <code>user_code</code> parameter value, if provided.</p> </div> <p>For example, if your server's base URL is <code>https://www.example.com</code> and the <b>User Authorization URL</b> value is <code>https://www.example.org/welcome</code>, the target web server must redirect as follows:</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.org/welcome</code> to <code>https://www.example.com/as/user_authz.oauth2</code></li> <li>▪ <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> to <code>https://www.example.com/as/user_authz.oauth2?user_code=&lt;activationcode&gt;</code></li> </ul> <p>This field has no default value.</p> <p><b>Pending Authorization Timeout (seconds)</b></p> <p>The lifetime of an activation code (the <code>user_code</code> parameter value) in seconds.</p> <p>This field has no default value.</p> <p><b>Device Polling Interval (seconds)</b></p> <p>The amount of time in seconds that the device waits between polling requests to the token endpoint.</p> <p>This field has no default value.</p> <p><b>Bypass Activation Code Confirmation</b></p> <p>When receives a verification request that includes an activation code (the <code>user_code</code> parameter value), it prompts the user to confirm the activation code.</p> <p>For to skip this confirmation step, select this check box.</p> <p>This check box is not selected by default.</p> |

| Field       | Description  |
|-------------|--|
| <b>CIBA</b> | <p>Displayed only if the <b>CIBA</b> grant type is enabled for the client.</p> <p><b>Token Delivery Method</b></p> <p>The token delivery method that the client supports. supports poll and ping.</p> <p>Select <b>Poll</b> if the client can check for the authorization results at the token endpoint periodically. Select <b>Ping</b> if the client prefers to wait for a ping callback message from PingFederate as a signal that the authorization result is ready for pickup.</p> <p>The default selection is <b>Poll</b>.</p> <p><b>Notification Endpoint</b></p> <p>The client's notification endpoint, to which sends its ping call back messages.</p> <p>Required and displayed only if ping is the configured token delivery method.</p> <p><b>Polling Interval (seconds)</b></p> <p>Specifies the number of seconds that the client must wait between its attempts to check for the authorization results at the token endpoint. When receives a token request within this time interval, it returns a <code>slow_down</code> error message to the client.</p> <p>A valid value ranges from 1 to 3600.</p> <p>The default value is 3.</p> <p><b>Policy</b></p> <p>Specifies the CIBA request policy associated with the client. uses CIBA request policies to determine various aspects of CIBA authentication request, such as the maximum lifetime of authentication requests, the validity of unsigned login hint tokens, and the mapping configuration of identity hints.</p> <p>Select an existing CIBA policy. You may also leave the selection of <b>Default</b> to indicate that should use the CIBA request policy that has been designated as the default CIBA request policy in <b>Applications # OAuth # CIBA Request Policies</b>.</p> <p><b>User Code Support</b></p> <p>Indicates whether the client supports user code.</p> <p>The purpose of this code is to authorize the transmission of an authentication request to the user's authentication device.</p> <p>This check box is not selected by default.</p> <p>When user code support is enabled, the associated CIBA request policy must also be user code enabled.</p> <p><b>Require CIBA Signed Requests</b></p> <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <code>request</code>. The value of the <code>request</code> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>This check box is not selected by default.</p> <p>If CIBA signed requests are required, the client must also be configured with either the JWKS URL or the actual JWKS from the</p> |

| Field   | Description   |
|---|---|
| <b>Token Exchange</b>                                 | <p>Displayed only if the <b>Token Exchange</b> grant type is enabled.</p> <p>Select the token exchange processor policy that PingFederate uses when the AS receives an OAuth token exchange request from the client. If you select <b>Default</b>, PingFederate uses the default token exchange processor policy.</p> <p>For more information, see <a href="#">OAuth token exchange</a>.</p>  |
| <b>Token Introspection</b>                            | <p>The algorithms that allow for token introspection signing and encryption.</p> <p>Displayed only when the <b>Access Token Validation (Client is a Resource Server)</b> grant type is enabled.</p> <p><b>Token Introspection Signing Algorithm</b></p> <p>The JSON Web Signature (JWS) algorithm used to sign the token introspection response. The default value is RS256.</p> <p><b>Token Introspection Key Management Encryption Algorithm</b></p> <p>The optional JSON Web Encryption (JWE) encryption algorithm used to encrypt the content-encryption key of the token introspection response.</p> <p><b>Token Introspection Content Encryption Algorithm</b></p> <p>The JWE content-encryption algorithm for the token introspection response. It's displayed only if a <b>Token Introspection Key Management Encryption Algorithm</b> is selected.</p> |
| <b>JWT Secured Authorization Response Mode (JARM)</b> | <p>The algorithms that allow for JARM signing and encryption.</p> <p>Displayed only when the <b>Access Code</b> or <b>Implicit</b> grant type is enabled.</p> <p><b>JARM Signing Algorithm</b></p> <p>The JWS algorithm used to sign the authorization response. The default value is RS256.</p> <p><b>JARM Key Management Encryption Algorithm</b></p> <p>The optional JWE algorithm used to encrypt the content-encryption key of the authorization response.</p> <p><b>JARM Content Encryption Algorithm</b></p> <p>The JWE content-encryption algorithm for the authorization response. It's displayed only if a <b>JARM Key Management Encryption Algorithm</b> is selected.</p>   |

- To enable or disable the client, click the toggle switch.

- Optional: On the **System** tab, add, remove, or update one or more values for any extended properties defined in **System # Server # Extended Properties**.

**Note:**

Any values defined for these extended properties will be passed to all applicable velocity templates and as a request context parameter in the authentication API.

Extended property values can serve as metadata. They can also help drive authentication requirements. For more information, see [Extended properties](#) on page 929.

- Click **Save**.

## Grant contract mapping

In the first stage of the OAuth attribute mapping process, PingFederate maps attributes to persistent grant contracts.

You configure PingFederate to use attributes from the following sources:

- authentication policy contracts
- authentication sources, such as IdP adapter instances and IdP connections
- password credential validator instances for resource owner credentials

Depending on the attribute source, use one of the following PingFederate windows to configure the grant contract mapping:

- Authentication # OAuth # Policy Contract Grant Mapping**
- Authentication # OAuth # IdP Adapter Grant Mapping**
- Authentication # OAuth # Resource Owner Credentials Grant Mapping**

These windows also let you configure issuance criteria to control whether PingFederate fulfills the contract.

Persistent grants, and any associated attributes and their values, remain valid until the grants expire or until PingFederate explicitly revokes them or cleans them up.

For more information about the OAuth attribute mapping process, see [Mapping OAuth attributes](#) on page 90

### Managing IdP adapter grant mapping

Use the **IdP Adapter Grant Mapping** to map authentication source values into persistent grants.

Persistent grants and any associated attributes and their values remain valid until the grants expire or until PingFederate explicitly revokes or cleans them up.


About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute. You can optionally set up datastore queries to supplement values returned from the source. This mapping configuration is suitable for the Authorization Code and Implicit grant types.

Steps

Go to **Authentication # OAuth # IdP Adapter Grant Mapping** and perform one of the following actions.

| Action                            | Steps  |
|-----------------------------------|--|
| <b>Create a mapping</b>           | Select the source of the attributes from the list and click <b>Add Mapping</b> . |
| <b>Modify an existing mapping</b> | Select your mapping under <b>Mappings</b> .                                      |

| Action   | Steps  |
|--|--|
| Remove an existing mapping or cancel the removal request | <p>Click <b>Delete</b> or <b>Undelete</b> under <b>Action</b>.</p> <p> <b>Note:</b></p> <p>Before removing a mapping from your configuration, ensure that it is not used by your OAuth use cases. Any corresponding entries defined in <b>Applications # OAuth # Access Token Mapping</b> will also be removed.</p> |

### Configuring IdP adapter attribute sources and user lookup

You can optionally set up datastore queries to supplement values returned from the identity provider (IdP) adapter attribute source. After the configuration is complete, you can fulfill a contract or verify a condition in the Token Authorization framework using the results from the queries.

#### Steps

- To set up datastore queries, click **Add Attribute Source**.

Follow the **Attribute Sources & User Lookup** window to complete the setup. For configuration steps, see [Datastore query configuration](#) on page 398.

- To skip this option, click **Next**.

### Fulfilling IdP adapter grant mapping

On the **Contract Fulfillment** tab, map authentication source values into persistent grants. Persistent grants and any associated attributes and their values remain valid until the grants expire or until PingFederate explicitly revokes or cleans them up.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute.

#### **Important:**

The **USER\_KEY** attribute values must be unique across all end users, because the **USER\_KEY** attribute is the user identifier to store and to retrieve persistent grants. For example, the **sAMAccountName** attribute value of an end user in one domain might match that of another end user in another domain. In this case, you can map the **Subject DN** attribute to the **USER\_KEY** attribute.

#### Steps

- Go to **Authentication # OAuth # IdP Adapter Grant Mapping** and select your mapping, or click **Add Mapping**.

2. On the **Contract Fulfillment** tab, select a source from the **Source** list and then select or enter a value for each attribute in the contract.

You can map each attribute from one of the following sources:

- **Adapter**

When selected, the associated **Value** drop-down list contains attributes configured in the IdP adapter instance.

- **Context**

Values are returned from the context of the transaction at runtime.

 **Note:**

If `PERSISTENT_GRANT_LIFETIME` is an extended attribute in **System # OAuth Settings # Authorization Server Settings**, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions, or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

As the **HTTP Request** context value is retrieved as a Java object rather than text, OGNL expressions are ideal to evaluate and return values.

- **Extended Client Metadata**

Values are returned from the client record.

- **LDAP/JDBC/Other**

Values are returned from your datastore, if used.

- **Expression**

If enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are available for expressions.

- **No Mapping**

This option ignores the **Value** field.

- **Text**

You can enter text only, or mix text with references to the attributes returned from the adapter instance, using the `${attribute}` syntax.

You can also enter values from your datastore using the `${ds.attribute}` syntax, where `attribute` is any of the datastore attributes you have selected.



3. Click **Next**.

### Defining issuance criteria for OAuth IdP adapter mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



#### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

#### Steps

1. Go to **Authentication # OAuth # IdP Adapter Grant Mapping**. Select an adapter instance, and then click **Issuance Criteria**.
2. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source                          | Description   |
|---------------------------------|---|
| <b>Adapter</b>                  | Select to evaluate attributes from the IdP adapter instance.  |
| <b>Context</b>                  | Select to evaluate properties returned from the context of the transaction at runtime.  |
|                                 | <div data-bbox="574 1562 620 1604" data-label="Image"> </div> <div data-bbox="625 1575 699 1604" data-label="Section-Header"> <h4>Note:</h4> </div> <div data-bbox="568 1621 1424 1715" data-label="Text"> <p>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>Extended Client Metadata</b> | Select to evaluate OAuth client metadata.   |

| Source  | Description  |
|---|--|
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source. |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.                  |

- In the **Attribute Name** list, select the attribute to be evaluated.
- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

This value is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in several ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing the IdP adapter mapping

On the **Summary** tab, review your identity provider (IdP) adapter mapping.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

### Configuring IdP connection grant mapping

Use this configuration to map values obtained from the single sign-on (SSO) tokens into the persistent grants. Persistent grants remain valid until the grant expires or is explicitly revoked.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute. You can optionally set up datastore queries to supplement values returned from the source. This mapping configuration is suitable for the Authorization Code and Implicit grant types.

#### Steps

1. Go to **Authentication # Integration # IdP Connections** and select an existing identity provider (IdP) connection or click **Create Connection**.
2. On the **Connection Type** tab, select the **Browser SSO Profiles** check box and the applicable protocol.
3. On the **Connection Options** window, select the **Browser SSO** check box and then select the **OAuth Attribute Mapping** check box.

 **Tip:**

You can also select other options on the **Connection Type** and **Connection Options** tabs. If you do, you will be prompted to complete the required configuration. For simplicity, this topic only focuses on the **OAuth Attribute Mapping** configuration.

4. On the **General Info** tab, enter the required information.

5. On the **Browser SSO** tab, click **Configure Browser SSO** and follow the steps to complete the **User-Session Creation** tab.
6. On the **OAuth Attribute Mapping** tab, select the **Map directly into Persistent Grant** option, and then click **Configure OAuth Attribute Mapping** to continue.

Alternatively, if you have mapped an authentication policy contract (APC) in **User-Session Creation # Target Session Mapping**, you can select the **Map to OAuth via Authentication Policy Contract** option, and then select the applicable APC from the list.

### Choosing an OAuth datastore

You can optionally set up OAuth datastore queries to supplement values returned from the source.

#### Steps

On the **Data Store** tab, perform one of the following actions.

Choose from:

- To set up datastore queries, select a datastore from the **Active Data Store** list and then click **Next**. For configuration steps, see [Datastore query configuration](#) on page 398.
- To skip this optional configuration, select **No Data Store**, and then click **Next**.

### Fulfilling OAuth attribute mapping

On the **Contract Fulfillment** tab, map authentication source values into persistent grants.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute.



#### Important:

The **USER\_KEY** attribute values must be unique across all end users because the **USER\_KEY** attribute is the user identifier to store and to retrieve persistent grants. For example, if you are configuring an **OAuth Attribute Mapping** configuration on a SAML 2.0 IdP connection and the **SAML\_SUBJECT** attribute uniquely identifies all end users, you can map the **SAML\_SUBJECT** attribute to the **USER\_KEY** attribute.

#### Steps

1. For each attribute, select a source from the list and then choose or enter a value.
  - **AccountLink**

When selected, the **Value** list is populated with **Local User ID**. You can map **Local User ID** to an attribute that represents the user identifier, such as the **USER\_KEY** attribute. This source appears

only if you have elected to use account linking for a target session on the **Identity Mapping** window.

- **Assertion or Provider Claims**

When selected, the **Value** list is populated with attributes from the SSO token. Select the desired attribute from the list.

For example, to map the value of **SAML\_SUBJECT** from a SAML assertion as the value of the **USER\_KEY** user identifier on the contract, select **Assertion** from the **Source** list and **SAML\_SUBJECT** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.

 **Note:**

As the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.

 **Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added **PERSISTENT\_GRANT\_LIFETIME** as an extended attribute in the **Authorization Server Settings** window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **Extended Client Metadata**

Values are returned from the client record.

- **LDAP, JDBC, or Other**

When selected, the **Value** list is populated with attributes selected from the datastore. Select the desired attribute from the list.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under

**Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

When selected, no value selection is necessary.

- **Text**

When selected, the text you enter is used at runtime. You can mix text with references to any of the values from the SSO token, using the `${attribute}` syntax.

When applicable, you can also enter values from your datastore using the `${ds.attribute}` syntax, where `attribute` is any attribute that you have selected from the datastore.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

2. Click **Next**.

### Defining issuance criteria for OAuth attribute mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Note:**


All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

Steps

1. Go to **Authentication # OAuth # IdP Adapter Grant Mapping** and select your mapping. Click the **Issuance Criteria** tab.

- In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>AccountLink</b>   | Select to evaluate the <b>Local User ID</b> value of the user.<br><br>Displayed only if <b>Account Linking</b> is the selected identity mapping method. For more information, see <a href="#">Choosing an identity mapping method for SP SSO</a> on page 736.   |
| <b>Assertion</b>   | Select to evaluate attributes from the IdP connection.  |
| <b>Assertion or Provider Claims</b>                            | Select to evaluate attributes from the IdP connection.  |
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.<br><br><div data-bbox="565 758 1474 968" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>Extended Client Metadata</b>                                | Select to evaluate OAuth client metadata.   |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.   |

- In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code several ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.



9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

**Reviewing the OAuth attribute mapping summary**

On the **Summary** tab, review your configuration.

**Steps**

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

**Managing authentication policy contract grant mapping**


Use the **Authentication Policy Contract Grant Mapping** window to map values obtained from the authentication policy contract into the persistent grants. Persistent grants and any associated attributes and their values remain valid until the grants expire or until PingFederate explicitly revokes or cleans them up.

**About this task**

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute. You can optionally set up datastore queries to supplement values returned from the source. This mapping configuration is suitable for the Authorization Code and Implicit grant types.

**Steps**

Go to **Authentication # OAuth # Authentication Policy Contract Grant Mapping** and perform one of the following actions.

| Action  | Steps  |
|---|--|
| <b>Create a mapping</b>   | Select the source of the attributes from the list and click <b>Add Mapping</b> .   |
| <b>Modify an existing mapping</b>                               | Select your mapping under <b>Mappings</b> .  |
| <b>Remove an existing mapping or cancel the removal request</b> | Click <b>Delete</b> or <b>Undelete</b> under <b>Action</b> . <div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Note:</b><br/>           Before removing a mapping from your configuration, ensure that it is not used by your         </div> |

| Action | Steps  |
|--------|--|
|        | OAuth use cases. Any corresponding entries defined in <b>Applications # OAuth # Access Token Mapping</b> will also be removed. |

### Configuring policy contract attribute sources and user lookup

You can optionally set up datastore queries to supplement values returned from the policy contract attribute source.

#### Steps

1. Go to **Authentication # OAuth # Authentication Policy Grant Mapping** and select your mapping, or click **Add Mapping**.
2. On the **Attribute Sources & User Lookup** tab, perform one of the following actions. Choose from:
  - To set up datastore queries, click **Add Attribute Source** and follow the steps to complete the setup. For configuration steps, see [Datastore query configuration](#) on page 398.
  - To skip this configuration, click **Next**.

### Fulfilling policy contract grant mapping

On the **Contract Fulfillment** tab, map authentication source values into persistent grants.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. The **USER\_NAME** attribute presents the name shown to the resource owner on OAuth user-facing pages. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute.



#### Important:

The **USER\_KEY** attribute values must be unique across all end users, because the **USER\_KEY** attribute is the user identifier to store and to retrieve persistent grants. For example, if you are configuring an OAuth attribute mapping on a SAML 2.0 identity provider (IdP) connection and the **SAML\_SUBJECT** attribute uniquely identifies all end users, you can map the **SAML\_SUBJECT** attribute to the **USER\_KEY** attribute.

#### Steps

1. On the **Contract Fulfillment** tab, select a source from the **Source** list, and then select or enter a value for each attribute in the contract.

Map each attribute from one of the following sources:

- **Authentication Policy Contract**  
Populates the associated **Value** list with attributes associated with the APC.
- **Context**

Values are returned from the context of the transaction at runtime.



#### Note:

If **PERSISTENT\_GRANT\_LIFETIME** is an extended attribute in **System # OAuth Settings # Authorization Server Settings**, you can set the lifetime of persistent grants based on the

outcome of attribute mapping expressions, or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

As the **HTTP Request** context value is retrieved as a Java object rather than text, OGNL expressions are ideal to evaluate and return values.

- Extended Client Metadata

Values are returned from the client record.

- LDAP/JDBC/Other (when a datastore is used)

Values are returned from your datastore. When you make this selection, the **Value** list populates with attributes from the datastore.

- Expression (when enabled)

Provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.

- No Mapping

Ignores the **Value** field.

- Text

You can enter a text value only, or you can mix text with references to the unique user ID returned from the credentials validator, using the `${attribute}` syntax. You can also enter values from your datastore, when applicable, using the `${ds.attribute}` syntax, where `attribute` is any of the datastore attributes you have selected.

## 2. Click **Next**.

### Defining issuance criteria for policy contract mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.

**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>Authentication Policy Contract</b>                          | Select to evaluate attributes from the authentication policy contract.  |
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.  |
|  | <div data-bbox="574 1041 613 1083" data-label="Image"> </div> <div data-bbox="623 1052 698 1081" data-label="Section-Header"><b>Note:</b></div> <div data-bbox="568 1098 1422 1192" data-label="Text"> <p>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>Extended Client Metadata</b>                                | Select to evaluate OAuth client metadata.   |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.   |

2. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in several ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing authentication policy contract mapping

On the **Summary** tab, review your configuration.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

### Managing resource owner credentials grant mapping


Use the **Resource Owner Credentials Grant Mapping** to map values obtained from the password credential validator instance into the persistent grants. Persistent grants and any associated attributes and their values remain valid until the grants expire or until PingFederate explicitly revokes or cleans them up.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute. You can optionally set up datastore queries to supplement values returned from the source. This mapping is intended for the Resource Owner Password Credential grant type.

#### Steps

Go to **Authentication # OAuth # Resource Owner Credentials Grant Mapping** and perform one of the following actions.

| Action  | Steps   |
|---|---|
| <b>Create a mapping</b>   | Select the source of the attributes from the list and click <b>Add Mapping</b> .  |
| <b>Modify an existing mapping</b>                               | Select your mapping under <b>Mappings</b> .   |
| <b>Remove an existing mapping or cancel the removal request</b> | Click <b>Delete</b> or <b>Undelete</b> under <b>Action</b> . <p> <b>Note:</b></p> Before removing a mapping from your configuration, ensure that it is not used by your OAuth use cases. Any corresponding entries |

| Action | Steps   |
|--------|---|
|        | defined in <b>Applications # OAuth # Access Token Mapping</b> will also be removed. |

### Configuring resource owner attribute sources and user lookup

You can optionally set up datastore queries to supplement values returned from the resource owner attribute source.

#### Steps

Go to **Authentication # OAuth # Resource Owner Credentials Grant Mapping** and select your mapping, or click **Add Mapping**.

Choose from:

- To set up datastore queries, click **Add Attribute Source** on the **Attribute Sources and User Lookup** tab. For configuration steps, see [Datastore query configuration](#) on page 398.
- To skip this optional configuration, click **Next**.

### Fulfilling resource owner credentials grant mapping

On the **Contract Fulfillment** tab, map authentication source values into persistent grants.

#### About this task

The **USER\_KEY** attribute is the identifier of the persistent grants. If extended attributes are defined in **System # OAuth Settings # Authorization Server Settings**, configure a mapping for each attribute.

#### Important:

The **USER\_KEY** attribute values must be unique across all end users, because the **USER\_KEY** attribute is the user identifier to store and to retrieve persistent grants. For example, the **sAMAccountName** attribute value of an end user in one domain might match that of another end user in another domain. In this case, you can map the **Subject DN** attribute to the **USER\_KEY** attribute.

#### Steps

1. On the **Contract Fulfillment** tab, select a source from the **Source** list, and then select or enter a value for each attribute in the contract.

Map each attribute from one of the following sources:

- Password Credential Validator

When selected, the associated **Value** list populates with attributes associated with the credential-validation instance.

- Context

Values are returned from the context of the transaction at runtime.

#### Note:

If **PERSISTENT\_GRANT\_LIFETIME** is an extended attribute in **System # OAuth Settings # Authorization Server Settings**, you can set the lifetime of persistent grants based on the

outcome of attribute mapping expressions, or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

As the **HTTP Request** context value is retrieved as a Java object rather than text, OGNL expressions are ideal to evaluate and return values.

- `Extended Client Metadata`

Values are returned from the client record.

- `LDAP/JDBC/Other (when a datastore is used)`

Values are returned from your datastore. When selected, the **Value** list is populated with attributes from the datastore.

- `Expression (when enabled)`

Provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.

- `No Mapping`

Ignores the **Value** field.

- **Text**

You can enter a text value only, or you can mix text with references to the unique user ID returned from the credentials validator, using the `${attribute}` syntax. You can also enter values from your datastore, when applicable, using the `${ds.attribute}` syntax, where `attribute` is any of the datastore attributes you have selected.

## 2. Click **Next**.

### Defining issuance criteria for resource-owner credentials mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.



You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

Steps

1. Go to **Authentication # OAuth # Resource Owner Credentials Grant Mapping** and select your mapping, or click **Add Mapping**.
2. On the **Issuance Criteria** tab, select the attribute's source from the **Source** list.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.  |
|  | <div data-bbox="574 1016 615 1058" data-label="Image"> </div> <p><b>Note:</b></p> <p>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> |
| <b>Extended Client Metadata</b>                                | Select to evaluate OAuth client metadata.   |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.   |
| Password Credential Validator                                  | Select to evaluate attributes from the Password Credential Validator instance.  |

3. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in several ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing the resource owner credentials mapping

On the **Summary** tab, review your configuration.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## Token mapping

You can configure how PingFederate maps attributes to OAuth access tokens and OpenID Connect ID tokens.

To configure how PingFederate maps attributes to OAuth access tokens, go to **Applications # OAuth # Access Token Mappings**. You can map attributes to access tokens from various context sources, depending on how users or clients authenticate. This is the second stage of mapping OAuth attributes to access tokens. The first stage is mapping OAuth attributes to persistent grant contracts. For more information, see [Mapping OAuth attributes](#) on page 90 and [Managing access token mappings](#) on page 616.

OpenID Connect policies include a map of attributes to ID tokens. To configure an OpenID Connect policy, go to **Applications # OAuth # OpenID Connect Policy Management**. For more information, see [Configuring OpenID Connect policies](#).

### Access token management

PingFederate supports multiple access token management (ATM) instances. You can configure different access token policies and attribute contracts for different OAuth clients. You can also control validation of access tokens to one or more resource servers.

When defining an ATM instance, you can customize various settings, including token format, lifetime, session validation settings, and attribute contract for this instance. You can also limit the ATM instance to a list of resource URIs, a set of clients in an access control list (ACL), or both.

For example, you can use the ACL to limit which clients can obtain access tokens from a particular ATM instance. You can also add a resource server client to the ACL of multiple ATMs instances, so that only the resource server client can submit token validation requests for access tokens issued by those ATM instances.

When there are multiple ATM instances, OAuth clients can specify the desired ATM instance by providing the `access_token_manager_id` ATM ID or an `aud` resource URI in their requests to the

PingFederate OAuth authorization server at the `/as/authorization.oauth2` authorization endpoint, the `/as/token.oauth2` token endpoint, and the `/as/introspect.oauth2` introspection endpoint. For resource server clients, you can configure on a per-client basis whether a resource server client must specify the desired ATM instance in its token validation requests at runtime. For more information, see [Configuring OAuth clients](#) on page 566.

At runtime, the OAuth authorization server uses the following rules to determine which ATM instances to use:

1. limits the eligible ATM instances to those that are available in the context of the request. For most requests, these are instances that have an attribute mapping defined in the **Access Token Mapping** window. For OAuth Assertion Grant requests, it is the set of instances for which a mapping is defined in the IdP connection. If configured, the ACL can also limit which ATM instances are eligible.
2. If the request comes with an `access_token_manager_id` or `aud` parameter, uses the information to determine the applicable ATM instance.
3. If the request does not come with either parameter, for OAuth clients supporting the OpenID Connect protocol by including the `openid` scope value, uses the ATM instance specified by the OpenID Connect policy associated with the client. For resource server clients, you can optionally configure to use any eligible ATM instances for the purpose of token validation.
4. If the request comes with neither of the two parameters nor the `openid` scope, uses the default ATM instance of the client if configured, or the default ATM instance defined for the installation if eligible. For token validation requests, if resource server clients do not provide either the `access_token_manager_id` or `aud` parameter in their requests and the resource server clients have not been configured to validate against any eligible ATM instances, the same logic applies.

If no match can be found in the eligible list of ATMs, PingFederate aborts the request.

### Managing access token management instances

Use the **Access Token Management** window to specify how the PingFederate OAuth AS manages access tokens.

#### Steps

1. Go to **Applications # OAuth # Access Token Management**.
2. In the **Access Token Management** window, choose from the following options.

| Option  | Description  |
|---|--|
| <b>Configure a new instance</b>               | Click <b>Create New Instance</b>   |
| <b>Modify an existing instance</b>            | Click the name of instance in the <b>Instance Name</b> column              |
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |

### Defining an access token management instance

Define your access token management instance in the **Type** tab. This capability allows you to configure different access token policies and attribute contracts for different OAuth clients. It also provides a means to control validation of access tokens to one or more resource servers.

#### Steps

1. Go to **Applications # OAuth # Access Token Management** and click **Create New Instance**.
2. On the **Type** tab, enter a name in the **Instance Name** field and an ID in the **Instance ID** field.

- From the **Type** list, select the plugin type of the access token management instance.

The **Type** list varies depending on the plugins deployed on your server. For information about adding a customized plugin, contact the [Ping Identity Support Center](#).

- Optional: Select a **Parent Instance** from the list.

Use this option when creating an instance that is similar to an existing one. The child instance inherits the configuration of its parent. You can also override one or more settings during the setup. Select the **Override ...** check box and make the adjustments as needed in one or more subsequent windows.

### Configuring an access token management instance

This configuration varies depending on the type of the access token manager.

#### Steps

- See subsequent topics for configuration steps.

#### *Configuring reference token management*

Access tokens that use the reference token data model provide a reference to a set of attributes.

The resource server must de-reference the access tokens for the corresponding identity and security information at the OAuth authorization server that issued them. PingFederate is the authorization server.

#### About this task

The reference token data model supports both adaptive clustering and directed clustering. For adaptive clustering, PingFederate shares token information across a replica set. If region identifiers are defined, PingFederate shares token information across replica sets in multiple regions. You can optionally override this default behavior in the configuration file for adaptive clustering. For directed clustering, PingFederate shares token information among all engine nodes, despite any state server or subcluster setup.

#### Steps

- Go to **Applications # OAuth # Access Token Management** and click **Create New Instance**.
- On the **Instance Configuration** window, modify the default values as needed.

The following table describes each field.

| Field                               | Description  |
|-------------------------------------|--|
| <b>Token Length</b><br>(Required)   | The number of characters that PingFederate uses to define the token reference. Increasing the length enhances token security.<br><br>The default value is 28 characters. The minimum and maximum values are 22 and 256, respectively.  |
| <b>Token Lifetime</b><br>(Required) | The amount of time in minutes that an access token is considered valid.<br><br>The default value is 120 minutes.   |
| <b>Lifetime Extension Policy</b>    | Indicates whether PingFederate should reset the lifetime of an access token each time the token is validated, subject to the values defined in the <b>Maximum Token Lifetime</b> and <b>Lifetime Extension Threshold Percentage</b> fields.<br><br>The options are: <ul style="list-style-type: none"> <li><b>No Extension</b></li> <li><b>Tokens Not Backed by Persistent Access Grants (Transient Grants)</b></li> <li><b>All Tokens</b></li> </ul> The default selection is <b>No Extension</b> . |

| Field  | Description   |
|--|---|
| <b>Maximum Token Lifetime</b>                                | <p>Defines an absolute maximum token lifetime for use with the <b>Lifetime Extension Policy</b> setting, in minutes. When configured, the lifetime of access tokens can be extended but not beyond the configured value. Any value, if specified, must be greater than or equal to the value specified in the <b>Token Lifetime</b> field.</p> <p>This optional field has no default value.</p>   |
| <b>Lifetime Extension Threshold Percentage</b><br>(Required) | <p>When PingFederate is deployed in a cluster and token-lifetime extension is enabled, there must be a cluster-group remote procedure call (RPC) to extend the life of a token.</p> <p>To limit RPC overhead, this setting suspends the calls until the remaining time is less than the chosen value, as a percentage of token lifetime. For example, if the token lifetime is 60 minutes and the <b>Lifetime Extension Threshold Percentage</b> value is 30 percent, the lifetime will not be extended until the remaining time is less than 18 minutes. This option can drastically reduce RPC traffic between nodes, while still supporting a lifetime extension policy.</p> <p>The default value is 30 percent.</p> |
| <b>Advanced Fields</b>                                       |   |
| <b>Mode for Synchronous RPC</b>                              | <p>Synchronous RPC calls occur when a node receives a verification request for a token it does not recognize, and for token issuance.</p> <p>When <b>Majority of Nodes</b> is selected, the server waits for the majority of recipients to respond. It also eliminates the need for a complete state synchronization at startup.</p> <p>When <b>All Nodes</b> is selected, the server waits for all recipients to respond.</p> <p>The default selection is <b>Majority of Nodes</b>.</p>  |
| <b>RPC Timeout</b><br>(Required)                             | <p>The timeout value between cluster nodes during synchronous communication, in milliseconds. The recommended value ranges from 100 milliseconds to 1000, or 1 second.</p> <p>The default value is 500 milliseconds.</p>  |
| <b>Expand Scope Groups</b>                                   | <p>Determines whether to expand scope groups into their corresponding scopes in the access token contents and introspection response.</p> <p>This check box is not selected by default.</p>   |

#### *Configuring JSON token management*

JSON web token (JWT) bearer access tokens are secure and self-contained tokens. This allows the target resource server to validate the access tokens locally or to send the access tokens to PingFederate for validation.

#### About this task

In the **Access Token Management** window, configure an access token management instance. This configuration uses either symmetric keys or asymmetric signing-certificate keys for token security. To facilitate rollover of keys when they expire, multiple entries are allowed for either signing mechanism. This token data model is suitable for both standalone and clustered environments.

## Steps

1. Go to **Applications # OAuth # Access Token Management** and click **Create New Instance**.
2. On the **Instance Configuration** tab, add one or more symmetric keys, signing certificates, or both.
  - a. Click **Add a new row to...**, or click **Update** to modify an existing entry.

**Important:**

The **Key ID** field values must be unique across all JSON token management instances, including child instances.

Access Token Management | Create Access Token Management Instance

Type Instance Configuration Session Validation Access Token Attribute Contract Resource URIs Access Control Summary

Complete the configuration necessary to issue and validate access tokens. This configuration was designed into, and is specific to, the selected Access Token Management plugin.

A JSON Web Token (JWT) Bearer Access Token Management Plug-in that enables PingFederate to issue (and optionally validate) cryptographically secure self-contained OAuth access tokens.

Symmetric Keys ⓘ

| Key ID ⓘ                          | Key ⓘ | Encoding ⓘ | Action |
|-----------------------------------|-------|------------|--------|
| Add a new row to 'Symmetric Keys' |       |            |        |

Certificates ⓘ

| Key ID ⓘ                        | Certificate ⓘ | Action |
|---------------------------------|---------------|--------|
| Add a new row to 'Certificates' |               |        |

- b. If you have not yet created or imported your certificate into PingFederate, click **Manage Signing Certificates** and complete the task.

**Note:**

To use an RSA-based algorithm for JSON web signature (JWS), the key size of the signing certificate must be at least 2,048 bits. For an EC-based JWS algorithm, the key size depends on the chosen algorithm.

Result: You are directed back to the **Instance Configuration** tab.




- c. Change or select the remaining field entries as needed.


For more information about JSON web algorithms (JWAs), see the [JSON Web Algorithms](#) specification.


| Field                               | Description   |
|-------------------------------------|---|
| <b>Token Lifetime</b><br>(Required) | <p>The amount of time that an access token is considered valid, in minutes.</p> <p>The default value is 120 minutes.</p> <p>Additionally, you can extend the contract of the access tokens with an attribute named <b>exp</b> on the <b>Access Token Attribute Contract</b> tab. When mapping attribute values from authentication sources to the access tokens issued by this Access Token Management instance, the value you specify on the <b>Contract Fulfillment</b> tab sets the expiry as this many minutes from the current time. PingFederate internally calculates the actual epoch time for the JWT "exp" claim value.</p> |

| Field  | Description  |
|--|--|
| <b>Use Centralized Signing Key</b>             | <p>Select this option to use a centralized key when signing JWTs using an RSA-based or EC-based algorithm.</p> <p>When this option is selected and static keys are not enabled, PingFederate manages and rotates a set of keys, and uses the current key corresponding to the selected signing algorithm to sign the JWT.</p> <p>When this option is selected and static keys are enabled, PingFederate uses the current key corresponding to the selected signing algorithm to sign the JWT.</p> <p>When this option is selected, an OAuth client that has been configured to use JWT access tokens through this ATM instance can retrieve the key it needs to validate the digital signature by contacting PingFederate at the <code>/pf/JWKS</code> endpoint.</p> |
| <b>JSON Web Signature (JWS) configuration</b>  |  |
| <b>JWS Algorithm</b>                           | <p>The hash-based message authentication code (HMAC) or the signing algorithm (EC or RSA) used to protect the integrity of the token. If PingFederate is deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM), additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration, see <a href="#">Supported hardware security modules</a> on page 177.</p> <p>Required if an asymmetric algorithm is selected in the <b>JWE Algorithm</b> list.</p>  |
| <b>Active Symmetric Key ID</b>                 | <p>The ID of the symmetric key to use when producing JWTs using an HMAC-based algorithm.</p> <p>Required if an HMAC-based JWS algorithm is selected in the <b>JWS Algorithm</b> list.</p>  |
| <b>Active Signing Certificate Key ID</b>       | <p>The ID of the key pair and certificate to use when producing JWTs using an EC-based or RSA-based algorithm.</p> <p>Required if an EC-based or RSA-based JWS algorithm is selected in the <b>JWS Algorithm</b> list.</p>   |
| <b>JSON Web Encryption (JWE) configuration</b> |  |
| <b>JWE Algorithm</b>                           | <p>The algorithm used to encrypt or otherwise determine the value of the content encryption key.</p> <p>PingFederate supports symmetric algorithms, such as <b>Direct Encryption with symmetric key, AES ... Key Wrap</b>, and <b>AES-GCM ... key encryption</b>, and asymmetric algorithms, such as <b>ECDH-ES, ECDH-ES ... Key Wrap</b>, and <b>RSAES OAEP</b>.</p>  |
| <b>JWE Content Encryption Algorithm</b>        | <p>The content encryption algorithm used to perform authenticated encryption on the plain text payload of the token.</p> <p>Required if an algorithm is selected in the <b>JWE Algorithm</b> list.</p>   |



| Field                                     | Description  |
|---|--|
| <b>Active Symmetric Encryption Key ID</b> | The ID of the key to use when using a symmetric encryption algorithm.<br>Required if a symmetric algorithm is selected in the <b>JWE Algorithm</b> list.   |
| <b>Asymmetric Encryption Key</b>          | An asymmetric encryption public key from your partner, which can be in either JSON web key (JWK) format or a certificate.<br><br>Applicable only if an asymmetric algorithm is selected from the <b>JWE Algorithm</b> list.<br><br><div data-bbox="600 504 1474 709" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>You can only specify an asymmetric encryption key here or the partner's JSON web key set (JWKS) endpoint in the <b>Asymmetric Encryption JWKS URL</b> field.</p> </div>   |
| <b>Asymmetric Encryption JWKS URL</b>     | The HTTPS URL of a JWKS endpoint that provides a list of one or more public keys for encryption.<br><br>Applicable only if an asymmetric algorithm is selected from the <b>JWE Algorithm</b> list.<br><br><div data-bbox="600 898 1474 1104" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>You can only specify an asymmetric encryption JWK URL here or the asymmetric encryption public key from your partner in the <b>Asymmetric Encryption Key</b> field.</p> </div>  |
| <b>Enable Token Revocation</b>            | When selected, PingFederate will directly revoke a JWT access token if the client that was issued the token requests its revocation. This provides a secure way to invalidate access tokens without needing to revoke the underlying refresh tokens or persistent grants. The client can request token revocation by sending a POST request with the token to the revocation endpoint at <code>/as/revoke_token.oauth2</code> .<br><br>When this check box is selected, the JWTs require a <b>Client ID Claim Name</b> and a minimum <b>JWT ID Claim Length</b> of 22 alphanumeric characters.<br><br>This check box is cleared by default.<br><br><div data-bbox="600 1503 1474 1709" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>When this feature is enabled, validation of access tokens may take longer, depending on the configuration of the session revocation service.</p> </div> |
| <b>Advanced fields</b>                    |  |
| <b>Include Key ID Header Parameter</b>    | When selected, the key ID is used in the <code>kid</code> header parameter for the token.<br><br>This check box is selected by default.  |

| Field  | Description  |
|--|--|
| <b>Include X.509 Thumbprint Header Parameter</b>     | <p>When selected, the X.509 certificate thumbprint is used in the <code>x5t</code> header parameter for the token.</p> <p>This check box is not selected by default.</p>   |
| <b>Default JWKS URL Cache Duration</b>               | <p>When an asymmetric encryption JWKS URL is specified, if the remote server does not contain any cache directives in its response, PingFederate only caches the content for 720 minutes (12 hours).</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When this threshold is reached or if the cache directives indicate that the content has expired at runtime, PingFederate contacts the remote server to refresh the list of encryption keys from the partner.</p> </div> |
| <b>Include JWE Key ID header parameter</b>           | <p>When selected, indicates whether the key ID (<code>kid</code>) header parameter will be included in the encryption header of the token, which can help identify the appropriate key during decryption.</p> <p>This check box is selected by default.</p>  |
| <b>Include JWE X.509 Thumbprint Header Parameter</b> | <p>When selected, the X.509 certificate thumbprint is used as the <code>x5t</code> header parameter value in the encryption header of the token. This can help identify the appropriate key during decryption.</p> <p>This check box is not selected by default.</p>   |
| <b>Client ID Claim Name</b>                          | <p>The name of a JWT claim used to represent the OAuth client ID.</p> <p>The default value is <code>client_id</code>.</p> <p>If the field value is empty, will not include the client ID of the requesting client in the self-contained tokens. If clients may use the UserInfo endpoint to retrieve additional claims about the users, see <a href="#">UserInfo endpoint</a> on page 1190 for more information.</p>   |
| <b>Scope Claim Name</b>                              | <p>The name of a JWT claim used to represent the scope of the grant.</p> <p>The default value is <code>scope</code>.</p> <p>If the field value is empty, PingFederate will not include any scope information in the self-contained token. If clients may use the UserInfo endpoint to retrieve additional claims about the users, see <a href="#">UserInfo endpoint</a> on page 1190 for more information.</p>   |
| <b>Space Delimit Scope Values</b>                    | <p>When selected, indicates scope strings will be delimited by spaces rather than represented as a JSON array.</p> <p>This check box is not selected by default.</p>   |

| Field                               | Description  |
|-------------------------------------|--|
| <b>Issuer Claim Value</b>           | <p>The value of the Issuer claim (<code>iss</code>) in the JWT. If left blank, this field is omitted.</p> <p>Additionally, you may extend the contract of the access tokens with an attribute named <code>iss</code> on the <b>Access Token Attribute Contract</b> tab. When mapping attribute values from authentication sources to the access tokens issued by this ATM instance, the value you specify on the <b>Contract Fulfillment</b> tab overrides the value here.</p>   |
| <b>Audience Claim Value</b>         | <p>The value of the Audience claim (<code>aud</code>) in the JWT. If left blank, this field is omitted.</p> <p>When no value is specified, PingFederate does not validate the <code>aud</code> value, if any is included in the access token.</p> <p>You can also extend the contract of the access tokens with an attribute named <code>aud</code> in the <b>Access Token Attribute Contract</b> tab. When mapping attribute values from authentication sources to the access tokens issued by this ATM instance, the value specified in the <b>Contract Fulfillment</b> window overrides this value.</p> |
| <b>JWT ID Claim Length</b>          | <p>Indicates the number of characters of the JWT ID (<code>jti</code>) claim in the JWT.</p> <p>The default value is 0, meaning no claim is included.</p>  |
| <b>Access Grant GUID Claim Name</b> | <p>The name of the JWT claim used to carry the persistent access grant GUID. If left blank, this field is omitted.</p> <p>If the claim is present during validation, PingFederate checks the grant database to ensure the grant is still valid.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This use case requires that the RS must send the JWT bearer access tokens to PingFederate for validation.</p> </div>   |
| <b>JWKS Endpoint Path</b>           | <p>The path on the PingFederate server to publish a JWKS with the keys and certificates that the partners can use for signature verification. Optional when an algorithm is selected in the <b>JWS Algorithm</b> list. If specified, the path must begin with a forward slash, such as <code>/oauth/jwks</code>.</p> <p>The resulting URL is <code>https://&lt;pf_host&gt;:&lt;pf.https.port&gt;/ext/&lt;JWKS Endpoint Path&gt;</code>.</p> <p>The path must be unique across all plugin instances, including any child instances.</p>   |
| <b>JWKS Endpoint Cache Duration</b> | <p>Informs the clients of the duration that they could cache the content from the JWKS endpoint path. Applicable only if the <b>JWKS Endpoint Path</b> field is configured.</p> <p>The default is 720 minutes, or 12 hours.</p>  |

| Field                               | Description  |
|-------------------------------------|--|
| <b>Publish Key ID X.509 URL</b>     | Indicates whether certificates will be made accessible by the key ID at <code>https://&lt;pf_host&gt;:&lt;pf.https.port&gt;/ext/oauth/x509/kid?v=&lt;id&gt;</code> .<br><br>This check box is not selected by default.                                 |
| <b>Publish Thumbprint X.509 URL</b> | Indicates whether certificates will be made accessible by thumbprint at <code>https://&lt;pf_host&gt;:&lt;pf.https.port&gt;/ext/oauth/x509/x5t?v=&lt;base64url encoded SHA-1 thumbprint&gt;</code> .<br><br>This check box is not selected by default. |
| <b>Expand Scope Groups</b>          | Determines whether to expand scope groups into their corresponding scopes in the access token contents and introspection response.<br><br>This check box is not selected by default.   |
| <b>Type Header Value</b>            | Indicates the value of the Type ( <code>typ</code> ) header in the JWT. If you do not specify a header, it is omitted.   |

### Managing session validation settings

When an OAuth client presents an access token for validation, PingFederate acts as an OAuth authorization server and checks the expiration and the other aspects of the access token. If the validation fails, PingFederate returns an `invalid_grant` error to the client.

Before you begin

The session validation features require authentication sessions. You must enable authentication sessions for either all authentication sources or the authentication source associated with the OAuth use cases.

About this task

Edit the session validation settings on the **Session Validation** tab.

When PingFederate authentication sessions are enabled, you can optionally configure the access token validation process to evaluate the authentication sessions of the users, or resource owners, before returning the validation results to the clients. Depending on the features selected on the **Session Validation** tab, PingFederate might return an `invalid_grant` error if the associated authentication session has timed out, expired, is not found, or has been revoked.

. You can also configure PingFederate to extend the authentication sessions upon successful validations.

When any session validation features are enabled, the associated session identifier (`pi.sri`) becomes available through the access tokens. For reference-style access tokens, PingFederate returns the associated session identifier in the response if the access token is valid. For JSON web token (JWT)-based access tokens, the session identifier is part of the access token. Through the session identifier, an OAuth client can contact the Session Management API and Session Revocation API endpoints to query the status of an authentication session, or to extend or revoke an authentication session.

The session validation features let you combine the status of access tokens and user authentication sessions. Because you can independently enable each feature per access token management (ATM) instance, you can customize unique API and web single sign-on (SSO) behaviors for your OAuth clients and users.


Steps

1. Go to **Applications # OAuth # Access Token Management**.

2. Select the applicable ATM instance or click **Create New Instance**.


If you are creating a new ATM instance, complete the required fields in the **Type** and **Instance Configuration** tabs.

3. On the **Session Validation** tab, select the check box for each relevant feature.

 **Important:**


If authentication sessions are not enabled, you can still select features on this tab, but access token validation might fail.

If this is a child ATM instance, select the **Override Session Validation Settings** check box and edit as needed.



Each feature is independent of each other. The following table describes each feature.

| Feature                                    | Description   |
|--|---|
| Include session identifier in access token | <p>When selected, the ATM instance includes the value of the pi.sri session identifier in the access tokens it issues.</p> <p>When processing a refresh-grant token request through an ATM instance where this feature is enabled, PingFederate includes the same session identifier if the original access token includes one.</p> <p>An OAuth client that is allowed to access the session management API can get information about sessions associated with the session identifier. The client can also request PingFederate to extend or revoke the sessions. For more information, see <a href="#">Session Management API by session identifiers</a> on page 1233.</p> |

| Feature                                | Description  |
|--|--|
| Check for valid authentication session | <p>When selected, an access token is considered invalid unless the user has a valid authentication session. If the user does not have a valid session, PingFederate returns an <code>invalid_grant</code> error.</p> <p>An authentication session is invalid when one of the following conditions applies:</p> <ul style="list-style-type: none"> <li>▪ The authentication session has timed out based on the <b>Idle Timeout</b> field value in <b>Authentication # Policies # Sessions</b>.</li> <li>▪ The authentication session has expired based on the <b>Max Timeout</b> field value in <b>Authentication # Policies # Sessions</b>.</li> <li>▪ The authentication session is not found, such as if the user has logged out.</li> </ul> <p>You can also optimize the access token lifetime.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If this ATM instance issues internally managed reference tokens, match the <b>Token Lifetime</b> value in the <b>Instance Configuration</b> tab to the <b>Idle Timeout</b> value. If you specify a <b>Maximum Token Lifetime</b> value on the <b>Instance Configuration</b> tab, ensure that the value matches that of the <b>Max Timeout</b> field.</p> <p>If this ATM instance issues JWT-based access tokens, match value of the <b>Token Lifetime</b> field to that of the <b>Max Timeout</b> field.</p> </div> |
| Check session revocation status        | <p>When selected, PingFederate verifies whether the session identifier has been added to the revocation list. If the session has been revoked, PingFederate returns an <code>invalid_grant</code> error.</p> <p>An authentication session can be revoked through the front-channel or the back-channel.</p>  |
| Update authentication session activity | <p>When selected, if the access token is valid, PingFederate also extends the lifetime of the authentication session by the <b>Idle Timeout</b> field value in <b>Authentication # Policies # Sessions</b>.</p> <p>For externally stored authentication sessions, this operation only sends updates to the external storage when the remaining idle timeout window is less than 75%.</p>   |

### Defining the access token attribute contract

On the **Access Token Attribute Contract** tab, define the attribute contract for the access tokens issued by this access token management (ATM) instance.

About this task


You must enter at least one attribute. For auditing purposes, an attribute can be chosen as the subject.

Steps

1. Go to **Applications # OAuth # Access Token Management** and select your instance, or click **Create New Instance**.

2. On the **Access Token Attribute Contract** tab use the **Extend the Contract** field and the **Add** button to add one or more attributes.
  - To always return this array in a token response, select the **Multi-Valued** check box.

For JSON web token (JWT) bearer access tokens, you can extend the attribute contract with the following attributes.

| Attribute  | Description  |
|--|--|
| <b>iss</b>   | <p>Adds the Issuer claim (<b>iss</b>) to the access token.</p> <p>When mapping attribute values from authentication sources to the access tokens issued by this ATM instance, the value specified on the <b>Access Token Attribute Contract</b> tab overrides any <b>Issuer Claim Value</b> defined on the <b>Instance Configuration</b> tab.</p>  |
| <b>aud</b>   | <p>Adds the Audience claim (<b>aud</b>) to the access token.</p> <p>When mapping attribute values from authentication sources to the access tokens issued by this ATM instance, the value you specify on the <b>Access Token Attribute Contract</b> tab overrides any <b>Audience Claim Value</b> defined on the <b>Instance Configuration</b> tab.</p>  |
| <b>exp</b>   | <p>Extends the value of the Expire claim (<b>exp</b>) by the specified value in seconds.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Define the Expire claim with the <b>Token Lifetime</b> setting in the <b>Instance Configuration</b> tab.</p> </div> |
| <p>The <b>Client ID Claim Name</b> field value, the <b>Scope Claim Name</b> field value, or the <b>Access Grant GUID Claim Name</b> field value defined on the <b>Instance Configuration</b> tab of this ATM instance.</p> | <p>When mapping attribute values from authentication sources to the access tokens issued by this ATM instance, the values defined in the <b>Access Token Attribute Contract</b> tab override the value of the client ID, the scope, or the persistent access grant GUID.</p>   |

3. Select an attribute from the **Subject Attribute Name** list.

Result:

When recording OAuth transactions in the audit log, PingFederate populates the subject field with values from this attribute specifically for token introspection and token validation using the `validate_bearer` grant type.

### Managing resource URIs

When sending its request to the authorization endpoint on the PingFederate OAuth authorization server, an OAuth client can optionally include the requested resource in the **aud** query parameter.

About this task

If the client is sending a token exchange request, it can specify an access token manager in the **resource** query parameter.

You can specify a list of resource URIs that PingFederate OAuth authorization server can use to select this access token management instance when the **aud** or **resource** query parameter is provided.

**Important:**

The resource URIs must correspond to the resource that the resource server expects.

## Steps

1. Go to **Applications # OAuth # Access Token Management** and select your instance, or click **Create New Instance**.
2. On the **Resource URI** tab, perform one of the following actions.

| Action                   | Steps  |
|--------------------------|--|
| Add a new entry          | Enter the desired value in the <b>Resource URIs</b> field, and then click <b>Add</b> . |
| Modify an existing entry | Use the <b>Edit</b> , <b>Update</b> , and <b>Cancel</b> buttons.                       |
| Remove an existing entry | Use the <b>Delete</b> and <b>Undelete</b> buttons.                                     |

**Defining access control**

On the **Access Control** tab, you can restrict which OAuth clients are allowed to use this access token management instance.

## Steps

1. Go to **Applications # OAuth # Access Token Management** and select your ATM instance or click **Create New Instance**.
2. On the **Access Control** tab, select the **Restrict Allowed Clients** check box.
3. Select a client from the **Allowed Clients** list, and then click **Add**.

Repeat this step to select additional clients as needed.

## Result

To remove a client from the **Allowed Clients** list or to cancel the removal request, click **Delete** or **Undelete** under **Action**.

To disable access control by clients altogether, clear the **Restrict Allowed Clients** check box.

**Reviewing the access token management configuration**

On the **Summary** tab, review your access token management configuration.

## Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

**Managing access token mappings**

In this required configuration, map attributes to be requested from the OAuth resource server into the access token and the token attribute contract.

## About this task

When mapping a default context, define how PingFederate maps values into the attributes based on the persistent-grant **USER\_KEY**, and any extended attributes defined in **System # OAuth Settings # Authorization Server Settings**. PingFederate acts as an OAuth authorization server.



When a specific context is selected, you can map attributes from the selected context, specifically the chosen IdP adapter instance, Password Credential Validator instance, or authentication policy contract, into the access tokens. You can also map attributes from an IdP connection with an OAuth attribute mapping configuration or an authentication policy contract mapping configuration. You can configure a mapping for clients using the client credential grant type.

The mapping used at runtime depends on the authentication context of the original grant. If the authentication context results in a match, PingFederate uses that specific mapping. Otherwise, it uses the default mapping for the applicable access token manager instance.



**Note:**

The **Access Token Mapping** window becomes available after at least one access token manager (ATM) instance has been configured in **Applications # OAuth # Access Token Management**.

Steps

Go to **Applications # OAuth # Access Token Management**.

| Action   | Steps   |
|--|---|
| <b>Create a mapping</b>  | Select the source of the attributes from the <b>Context</b> list and the target ATM instance from the <b>Access Token Manager</b> list, and then click <b>Add Mapping</b> . |
| <b>Modify an existing mapping</b>                                  | Select it by its name under <b>Mappings</b> .   |
| <b>Remove an existing mapping or to cancel the removal request</b> | Click <b>Delete</b> or <b>Undelete</b> under <b>Action</b> .  |
|  | <b>Note:</b><br>Before removing an existing mapping from your configuration, ensure that it is not used by your OAuth use cases.  |

**Configuring access token attribute sources and user lookup**

You can optionally set up datastore queries to supplement values returned from the access token attribute source.

Steps

Go to **Applications # OAuth # Access Token Mapping** and select your mapping, or click **Add Mapping**. Choose from:

- To set up datastore queries, click **Add Attribute Source** and complete the task in the **Attribute Sources & User Lookup** tab. For configuration steps, see [Datastore query configuration](#) on page 398.
- To skip this optional configuration, click **Next**.

### Configuring access token fulfillment

On the **Contract Fulfillment** tab, map values into the token attribute contract to be included or referenced in the access token.

#### Steps

1. Choose a source from the **Source** list, and then select a value from the **Value** list for each attribute in the contract, or enter your own.

Map each attribute from one of the following sources:

- **Client Credentials, IdP Adapter, IdP Connection, Password Credential Validator, or Token Exchange Processor Policy**

Depending on the selections under **Context** in the **Access Token Attribute Mapping** tab, you can map attributes from that specific authentication system. Select the corresponding context under **Source** and the desired attribute under **Value**.

- **Persistent Grant**

When selected, the associated **Value** list is populated with the `USER_KEY` and extended attributes from the persistent access-token grant.

- **Context**

Values are returned from the context of the transaction at runtime.



#### Note:

The **HTTP Request** context value is retrieved as a Java object rather than text. For this reason, OGNL expressions are preferred to evaluate and return values.

Select **Expression** under **Source**, and then click **Edit** to enter an expression.

The **HTTP Request**.Java object retrieves the authentication method that a client uses, or the private key JWT for client authentication if the client uses the `private_key_jwt` authentication

method.. For sample expressions, see [Expressions for OAuth and OpenID Connect uses cases](#) on page 230.

If the **Expression** selection is not available, you can enable it by editing the `org.sourceid.common.ExpressionManager.xml` file in the `<pf_install>/pingfederate/server/default/data/config-store` directory.

- **Extended Client Metadata**

Values are returned from the client record.

- **LDAP/JDBC/Other**

Values are returned from your datastore, if used. When you make this selection, the Value list populates with attributes from the datastore.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.

- **No Mapping**

This option ignores the **Value** field, causing no value selection to be necessary.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to the **USER\_KEY** using the `${USER_KEY}` syntax.

When applicable, you can also enter values from your datastore using the `${ds.attribute}` syntax, where `attribute` is any of the datastore attributes you have selected.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

2. Click **Next**.

### Defining issuance criteria for access token mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.

**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. Go to **Applications # OAuth # Access Token Mapping** and select your mapping, or click **Add Mapping**.
2. On the **Issuance Criteria** tab, select the attribute's source from the **Source** list.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.<br><br><div data-bbox="576 766 620 812" data-label="Image"></div> <b>Note:</b><br>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values. |
| <b>Extended Client Metadata</b>  | Select to evaluate OAuth client metadata.   |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b>   | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>   | Select to evaluate the mapped attributes.   |
| <i>Mapped from Context (Adapter, Authentication Policy Contract, IdP Connection, Password Credential Validator, token exchange Processor Policy)</i> | Select to evaluate attributes from the authentication source.<br><br>Visible and applicable only when configuring an access token mapping where the source of the attribute is something other than <b>Client Credentials</b> and <b>Default</b> . See .  |
| Persistent Grant   | Select to evaluate the default attribute <b>USER_KEY</b> and other extended attributes (if defined) from the persistent grant.<br><br>Visible and applicable only when configuring an access token mapping where the source of the attribute is not <b>Client Credentials</b> .   |

3. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in a variety of ways; for example, display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions

. For more information, see [Attribute mapping expressions](#) on page 225.

- a. Click **Show Advanced Criteria**.
- b. In the **Expression** field, enter the required expressions.
- c. Optional: In the **Error Result** field, enter an error code or message.



**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing the access token mapping

On the **Summary** tab, review your access token mapping configuration.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

### Configuring an OAuth assertion grant IdP connection

An OAuth assertion grant connection exchanges a SAML assertion or a JSON web token (JWT) for an OAuth access token with the PingFederate OAuth authorization server.

#### About this task

You can configure an OAuth assertion grant connection with an identity provider (IdP) partner either in conjunction with browser-based single sign-on (SSO), WS-Trust, or independently.

For more information, see [Security Assertion Markup Language \(SAML\) 2.0 Profile for OAuth 2.0 Client Authentication and Authorization Grants](#) and [JSON Web Token \(JWT\) Profile for OAuth 2.0 Client Authentication and Authorization Grants](#).

#### Steps

1. Go to **Authentication # Integration # IdP Connections** and then click **Create Connection**.
2. On the **Connection Type** tab, select the **OAuth Assertion Grant** check box.



**Tip:**

You can also select other options, such as the **Browser SSO Profiles** check box. If you do, you will be prompted to complete the required configuration. This topic only focuses on the **OAuth Assertion Grant** configuration.

3. On the **General Info** tab, enter the required information.
4. On the **OAuth Assertion Grant Attribute Mapping** tab, click **Configure OAuth Assertion Grant Attribute Mapping**.

## Defining an attribute contract for the OAuth assertion grant

### About this task

An attribute contract is a set of user attributes the IdP sends in the SAML assertions or JWTs for this connection. You identify these attributes on the **OAuth Assertion Grant Attribute Mapping # Attribute Contract** window.

**TOKEN\_SUBJECT** represents the name identifier of the user for whom the access token is being requested, the **SAML\_SUBJECT** attribute in SAML assertions and the **sub** claim in JWTs.

Optionally, you can mask the values of attributes (other than **TOKEN\_SUBJECT**) in the log files that PingFederate writes when it receives security tokens.

### Steps

- To add an attribute, follow these steps:
  - a. Enter the attribute name in the text box.  
Attribute names are case-sensitive and must correspond to the attribute names expected by your partner.
  - b. Select the check box under **Mask Values in Log**.
  - c. Click **Add**.
- To modify an attribute name or masking selection, follow these steps:
  - a. Click **Edit** under **Action** for the attribute.
  - b. Make the change and click **Update**.



#### Note:

If you change your mind, ensure that you click **Cancel** under **Action**.

- To delete an attribute, click **Delete** under **Action** for the attribute.

## Configuring access token manager mappings

To define how access tokens are created, use the **Access Token Manager Mapping** tab to associate one or more access token manager instances with this connection .

### Steps

1. Within your IdP connection configuration, go to the **Access Token Manager Mapping** tab within the **OAuth Assertion Grant Attribute Mapping** tab.
2. Perform one of the following actions.

| Action   | Steps   |
|--|---|
| <b>Create a new Access Token Manager mapping configuration</b>     | Click <b>Create New Access Token Manager Mapping</b> .                            |
| <b>Edit an existing Access Token Manager mapping configuration</b> | Click the mapping configuration's name.   |
| <b>Delete an Access Token Manager mapping</b>                      | Click <b>Delete</b> under <b>Action</b> for the applicable mapping configuration. |

*Selecting an access token manager instance*

This configuration maps attribute values from the (identity provider) IdP connection into the access token to define the resulting content of the access token.

## Steps

1. Within your IdP connection configuration, go to the **Access Token Manager** tab.
  - a. Click the **OAuth Assertion Grant Attribute Mapping** tab, and then click **Configure OAuth Assertion Grant Attribute Mapping**.
  - b. Click the **Access Token Manager Mapping** tab, and then click **Create New Access Token Manager Mapping**.
2. From the **Access Token Manager** list, select an access token manager instance.

**Tip:**

If the access token manager instance you need is not available, click **Manage Access Token Management Instances** to define one or more instances for this connection.

*Configuring a datastore for OAuth assertion grant attribute mapping*

You can optionally set up datastore queries to supplement values returned from the OAuth assertion grant attribute mapping source.

## Steps

1. Within your identity provider (IdP) connection configuration, go to the **Data Store** tab.
  - a. Click the **OAuth Assertion Grant Attribute Mapping** tab, and then click **Configure OAuth Assertion Grant Attribute Mapping**.
  - b. Click the **Access Token Manager Mapping** tab, and then click **Create New Access Token Manager Mapping**.
  - c. Click the **Data Store** tab.
2. Perform one of the following actions.
 

Choose from:

  - To set up datastore queries, select a datastore from the **Active Data Store** list, and then click **Next**. Follow the wizard to complete the setup. For configuration steps, see [Datastore query configuration](#) on page 398.
  - To skip this optional configuration, select **No Data Store** and then click **Next**.

*Configuring OAuth assertion grant contract fulfillment*

Map values from the SAML assertions or JSON web tokens (JWTs) to the attributes defined for the attribute contract. The access token manager instance requires these values to create an OAuth access token.

## About this task

At runtime, a single sign-on (SSO) operation fails if PingFederate cannot fulfill the required attribute.



## Steps

1. On **OAuth Assertion Grant Attribute Mapping # OAuth Assertion Grant Attribute Mapping Configuration # Contract Fulfillment**, select a source from the **Source** list and then choose or enter a value for each attribute.

- **Assertion**

When selected, the **Value** list populates with attributes from the SAML assertion or the JWT.

For example, to map the value of **SAML\_SUBJECT** from a SAML assertion, or **sub** from a JWT, as the value of an attribute on the access-token contract, select **Assertion** from the **Source** list and **TOKEN\_SUBJECT** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction.

**Note:**

Because the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values. For more information, see **Expression**.

- **Extended Client Metadata**

Values are returned from the client record.

- **LDAP, JDBC, or Other**

When selected, the **Value** list is populated with attributes that you have selected from the datastore. Select the desired attribute from the list.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under **Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

When selected, the text you enter is used at runtime. You can mix text with references to any of the values from the SSO token, using the `${attribute}` syntax.

When applicable, you can enter values from your datastore using the `${ds.<attribute>}` syntax, where `<attribute>` is any attribute that you have selected from the datastore.

**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

2. Click **Next**.

### Defining issuance criteria for OAuth assertion grants

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



#### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

#### Steps

1. Within your identity provider (IdP) connection configuration, go to **OAuth Assertion Grant Attribute Mapping # OAuth Assertion Grant Attribute Mapping Configuration # Issuance Criteria**.
2. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>Assertion</b>   | Select to evaluate attributes from the IdP connection.  |
| <b>Context</b>   | Select to evaluate properties returned from the context of the transaction at runtime.  |
|  | <div data-bbox="574 1514 613 1558" data-label="Image"> </div> <div data-bbox="621 1528 698 1558" data-label="Section-Header"> <h4>Note:</h4> </div> <div data-bbox="570 1575 1417 1669" data-label="Text"> <p>Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>Extended Client Metadata</b>                                | Select to evaluate OAuth client metadata.   |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |

| Source                   | Description                               |
|--------------------------|---|
| <b>Mapped Attributes</b> | Select to evaluate the mapped attributes. |

- In the **Attribute Name** list, select the attribute to be evaluated.
- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in a variety of ways, such as displaying an error message or emailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

#### *Reviewing OAuth assertion grant attribute mapping configuration*

On the **Summary** tab, review your OAuth assertion grant attribute mapping configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### **Reviewing OAuth assertion grant configuration**

On the **Summary** tab, review your OAuth assertion grant configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### **Configuring OpenID Connect policies**

This configuration allows you to define OpenID Connect policies for client access to attributes mapped according to OpenID specifications.

To begin configuring OpenID Connect policies, go to **Applications # OAuth # Openid Connect Policy Management**.

On the **OpenID Connect Policy Management** page, you can do the following:

- Configure a new OpenID Connect policy by clicking **Add Policy**.
- Modify an existing OpenID Connect policy by selecting its name under **Policy ID**.
- Review the usage of an existing OpenID Connect policy by clicking **Check Usage** under **Action**.
- Remove an existing OpenID Connect policy or cancel the remove request by clicking **Delete** or **Undelete** under **Action**.
- Choose an existing OpenID Connect policy to be the default policy by clicking **Set as Default** under **Action**.

### Configuring policy and ID token settings

Configure your OpenID Connect policy settings and the required and optional information for ID tokens.

#### Steps

1. Go to **Applications # OAuth # OpenID Connect Policy Management** and click **Add Policy**.
2. In the **Policy ID** field, enter the policy identifier.
3. In the **Name** field, enter the policy name.
4. In the **Access Token Manager** list, select an access token management instance.
5. Optional: In minutes, define the expiry information for ID tokens issued based on this policy in the **ID Token Lifetime** field.

The default value is 5 minutes.

6. Optional: Select the **Include Session Identifier in ID Token** check box to add a session identifier (`pi.sri`) in the ID tokens.  
Doing this might be useful for the relying parties, such as PingAccess, for client session management.
7. Optional: Select the **Include User Info in ID Token** check box to include additional attributes in the ID tokens.



#### Tip:

OAuth clients can also obtain additional attributes from the UserInfo endpoint at `/idp/userinfo.openid`. For more information, see [UserInfo endpoint](#).

8. Optional: Select the **Include State Hash in ID Token** check box to include the `s_hash` claim in ID tokens.



#### Note:

A state hash protects the state parameter by binding it to the ID token. For more information, see [Financial Services – Financial API - Part 2: Read and Write API Security Profile](#).

9. Optional: Select the **Return ID Token On Refresh Grant** check box to return an ID token for OpenID Connect to Salesforce and Kubernetes when the OAuth access token is refreshed.
10. Optional: Select the **Reissue ID Token In Hybrid Flow** check box to issue a new ID token at the token endpoint that is different from the first ID token issued for an authorization endpoint request.  
This is applicable only for OpenID Connect hybrid flows. For more information about hybrid flows, see [Protocol Elements](#) in the [OpenID Connect Basic Client Implementer's Guide](#).



#### Tip:

To modify the personally identifiable information (PII) in the ID token, see [Configuring ID token fulfillment](#).

## Configuring the policy attribute contract

In the **Attribute Contract** tab, you can define the list of attributes that PingFederate can return to the OAuth clients.

### About this task

Every new OpenID Connect policy contract begins with a list of standard attributes. These attributes or claims are defined in the OpenID Connect specification. You can optionally remove standard attributes, turn them into non-standard attributes, or add new non-standard attributes.



#### Note:

In OpenID Connect, scopes affect the list of attributes that PingFederate can return to the OAuth clients. The attributes that PingFederate returns to OAuth clients vary, depending on the scopes originally approved by the resource owner.

By default, all attributes defined on this window are deliverable through the UserInfo endpoint. If an implicit client makes a token request by providing `id_token` as the only **response\_type** parameter value, the client will only receive an ID token without an access token. As the client will not be able to retrieve additional attributes from the UserInfo endpoint without a valid access token, PingFederate includes the applicable attributes in the ID token instead.

If you have not selected the **Include User Info in ID Token** option in the **Manage Policy** tab for this policy, you can choose how attributes are delivered to clients. Similar to the default delivery behavior, in the scenario where an implicit client makes a token request by providing `id_token` as the sole **response\_type** parameter value, PingFederate includes the applicable attributes in the ID token regardless of any configured overrides.

### Steps

- To add a new attribute:
  - a. Enter the name of the attribute under **Extend the Contract**.
  - b. Optional: To choose how the attribute is delivered, select the **Override Default Delivery** check box .
    - To include this attribute in ID tokens, select the **ID Token** check box.
    - To include this attribute in Userinfo responses, select the **UserInfo** check box.
  - c. Optional: To always return this array in a token response, select the **Multi-Valued** check box.
  - d. Click **Add**.
- To modify an existing entry, use the **Edit**, **Update**, and **Cancel** buttons. Choose how the attribute is delivered, as needed.
- To remove an existing entry, click **Delete**.

### Configuring attribute scopes

With OpenID Connect, scopes affect the list of attributes that PingFederate can return to the OAuth clients. In the **Attribute Scopes** tab, you can optionally add associations between scopes and attributes beyond what is defined in the specification.

### Steps

1. Go to **Applications # OAuth # OpenID Connect Policy Management** and select your policy, or click **Add Policy**.

2. In the **Attribute Scopes** tab, add any number of scope-to-attributes associations.
  - a. Select a scope from the **Scope** list.  
Common and exclusive scopes are both available.
  - b. Select the relevant check boxes under **Attributes**.

 **Note:**

If you have selected a standard scope, its associated standard attributes are automatically selected and cannot be modified. You can select additional attributes to be associated with the selected scope.

If you have selected the **profile** scope, any non-standard attributes that are not associated with the **profile** scope become inaccessible to your OAuth clients. The administrative console displays a warning message with a list of inaccessible attributes. Select the relevant check boxes to make the non-standard attributes accessible, or ignore the message to leave them inaccessible for now.

- c. Click **Add**.
- d. Optional: Repeat these steps to define additional scope-to-attributes associations.  
Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

3. Click **Next**.

### Configuring policy attribute sources and user lookup

You can optionally set up datastore queries to supplement values returned from the policy attribute source.

#### Steps

1. Go to **Applications # OAuth # OpenID Connect Policy Management** and select your policy, or click **Add New Policy**.
2. On the **Attribute Sources & User Lookup** tab, perform one of the following actions.  
Choose from:
  - To set up datastore queries, click **Add Attribute Source**. Complete the setup on the **Attribute Sources & User Lookup** tab. For configuration steps, see [Datastore query configuration](#) on page 398.
  - To skip this optional configuration, click **Next**.

### Configuring ID token fulfillment

Map attributes from the access token or other sources to fulfill the attribute contract.

#### Steps

1. Go to **Applications # OAuth # OpenID Connect Policy Management** and select your policy, or click **Add Policy**.
2. On the **Contract Fulfillment** tab, select a source from the **Source** list and then select or enter a value for each attribute in the contract.

Map the subject attribute and all extended attributes from one of the following sources:

#### Context

Values are returned from the context of the transaction at runtime.

To enter an expression, select **Expression** under **Source**, and then click **Edit**.

 **Note:**

When modifying the personally identifiable information (PII) for hybrid flows, if the **RequestEndpoint** context value ends with a token endpoint path the actual value is populated and sent in the token response. If the field is blank, a null value is sent in the token response.

Because the **HTTP Request** context value is retrieved as a Java object rather than text, OGNL expressions are preferred to evaluate and return values.

If **Expression** is not available, you can enable it by editing the `org.sourceid.common.ExpressionManager.xml` file in the `<pf_install>/pingfederate/server/default/data/config-store` directory.

### Extended Client Metadata

Values are returned from the client record.

### LDAP/JDBC/Other

Values are returned from your datastore, if used. When selected, the **Value** list populates with attributes from the datastore.

### Expression

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.

### No Mapping

This option ignores the **Value** field.

### Text

The value is what you enter. This can be text only, or you can mix text with references to the unique user ID returned from the credentials validator, using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using the `${ds.attribute}` syntax, where `attribute` is any of the datastore attributes you have selected.



#### Tip:

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

### Access Token

The value is provided from the access token.

### Persistent Grant

Enables direct mapping from the grant to the ID Token and to user information attributes.

3. Click **Next**.

### Defining issuance criteria for policy mapping

Individual attributes within policy contracts can further determine whether PingFederate approves or rejects requests. You can define those criteria to satisfy or you can choose to skip this configuration.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.



Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.




**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

Steps

1. Go to **Applications # OAuth # OpenID Connect Policy Management** and select your policy, or click **Add Policy**.
2. On the **Issuance Criteria** tab, select the attribute's source from the **Source** list.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source  | Description   |
|---|---|
| Access Token  | Select to evaluate attributes from the access token.  |
| Context   | Select to evaluate properties returned from the context of the transaction at runtime.<br><br> <b>Note:</b><br>The HTTP Request context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values. |
| Extended Client Metadata                                | Select to evaluate OAuth client metadata.   |
| JDBC, LDAP, or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| Mapped Attributes                                       | Select to evaluate the mapped attributes.   |
| Persistent Grant  | Select to evaluate attributes from the persistent grant.  |

3. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The value of this field is used by the **error\_description** protocol field. Using an error code in the **Error Result** field allows an application to process the code in a variety of ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions

. For more information, see [Attribute mapping expressions](#) on page 225.

- a. Click **Show Advanced Criteria**.
- b. In the **Expression** field, enter the required expressions.
- c. Optional: In the **Error Result** field, enter an error code or message.



**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

### Reviewing your OpenID Connect policy

On the **Summary** tab, review your OpenID Connect policy.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

#### Result



**Note:**

If this is the first policy you are creating, you must click **Done** and designate this policy as the default before saving on the **OpenID Connect Policy Management** window. You can change the default when you create additional policies.

## Client Initiated Backchannel Authentication (CIBA)

Client Initiated Backchannel Authentication is an extension to OpenID Connect that improves the end-user experience during authentication and authorization in a federated environment.

The CIBA extension defines a new OAuth grant type where user consent can be requested through an out-of-band flow. CIBA improves the user experience, such as when making an online purchase from a merchant, because it does not require a browser redirect to a financial institution to authorize the purchase. Instead, the user can receive a push notification sent to the financial institution's native mobile app running on the user's phone to complete the authorization. For more information, see [openid.net/specs/openid-client-initiated-backchannel-authentication-core-1\\_0.html](https://openid.net/specs/openid-client-initiated-backchannel-authentication-core-1_0.html).



**Note:**

The PingOne MFA Integration Kit includes the PingOne MFA CIBA Authenticator, which works with PingFederate's CIBA feature. For instructions on configuring the PingOne MFA CIBA Authenticator, see [Configuring a CIBA authenticator instance](#).

A CIBA configuration consists of two components: a CIBA authenticator and a CIBA request policy.

CIBA authenticator

A CIBA authenticator is responsible for authenticating users through an out-of-band method.

You can use the SDK to implement a custom solution. For more information, see the Javadoc for the `OOBAuthPlugin` interface, the `SampleEmailAuthPlugin.java` file for a sample implementation, and the SDK developer's guide for build and deployment information.

Once deployed, you can create one or more instance configurations of the authenticator.

For more information, see [Configuring a CIBA authenticator instance](#) on page 637.

#### CIBA request policy

CIBA request policies process identity hints and authenticate users to receive consent. Each request policy is associated with an instance of a CIBA authenticator. The CIBA grant flow is initiated by a direct request from the client and involves an out-of-band interaction with the user to complete authentication and authorization. OAuth clients that support the CIBA grant type can be configured to use a specific CIBA request policy or a default.

For more information, see [Defining a request policy](#) on page 638.



#### Note:

Because the CIBA extension is an OAuth grant type, to enable CIBA for the client, you must select **CIBA** in the **Allowed Grant Types** setting. Once selected, you can configure more client CIBA-related settings.

For more information, see [Configuring OAuth clients](#) on page 566.

### Managing CIBA authenticators

Manage the Client Initiated Backchannel Authentication (CIBA) authenticators in PingFederate.

#### About this task

A CIBA authenticator is responsible for authenticating users through an out-of-band method.

You can use the SDK to implement a custom solution. For more information, see the Javadoc for the `OOBAuthPlugin` interface, the `SampleEmailAuthPlugin.java` file for a sample implementation, and the SDK developer's guide for build and deployment information.



#### Tip:

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

Once deployed, you can create one or more instance configurations of the authenticator.

#### Steps

- Go to **Authentication # OAuth # CIBA Authenticators** and create or select the instance you want to manage.
- To manage the CIBA authenticator, choose from the following options.

| Option                             | Description   |
|------------------------------------|---|
| <b>Configure a new instance</b>    | Click <b>Create New Instance</b>                              |
| <b>Modify an existing instance</b> | Click the name of instance in the <b>Instance Name</b> column |

| Option  | Description  |
|---|--|
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |

### Configuring a CIBA authenticator instance

The PingOne MFA Integration Kit includes the PingOne SDK client initiated backchannel authentication (CIBA) Authenticator, which works with PingFederate's CIBA feature.

About this task



#### Note:

For instructions on configuring the CIBA Authenticator for PingOne SDK, see [Configuring a CIBA authenticator instance](#).

### Steps

1. Go to **Authentication # OAuth # CIBA Authenticators** to open the **CIBA Authenticators** window.
2. On the **CIBA Authenticators** window, click **Create New Instance** to start the **Create CIBA Authenticator Instance** configuration workflow.
3. On the **Type** tab, configure the basics of this authenticator instance.
  - a. Enter a name and an ID in the **Instance Name** and **Instance ID** fields.
  - b. Select a CIBA authenticator from the **Type** list.

Selections vary depending on the deployed CIBA authenticators.

You can use the PingFederate SDK to implement a custom solution. For more information, see the Javadoc for the `OOBAuthPlugin` interface, the `SampleEmailAuthPlugin.java` file for a sample implementation and the [SDK developer's guide](#) for build and deployment information.



#### Tip:

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

4. On the **Instance Configuration** tab, follow the on-screen instructions to configure the authenticator instance.

Configuration requirements vary depending on the authenticator implementation.

5. On the **Actions** tab, follow the on-screen instructions to test the validity of the authenticator instance configuration or to perform secondary configuration tasks.

Availability of this tab and actions vary depending on the authenticator implementation.

6. On the **Extended Contracts** tab, follow the on-screen instructions to define additional attributes.

The authenticator contract is the list of input parameters used to challenge the user for authentication. Some authenticators support extending the contract for additional functionality, such as formatting the data presented to the user during the authentication challenge.

Availability of this window and supported attribute names vary depending on the authenticator implementation.

7. On the **Summary** tab, review your configuration, modify as needed, and click **Done** to exit the **Create CIBA Authenticator Instance** workflow.

- On the **CIBA Authenticators** window, click **Save** to retain the configuration of the authenticator instance.

If you want to exit without saving the configuration, click **Cancel**.

### Managing CIBA request policies

You can configure, modify, review, remove, and elect existing client initiated backchannel authentication (CIBA) request policies in the administrative console.

#### About this task

CIBA request policies process identity hints and authenticate users to receive consent. Each request policy is associated with an instance of a CIBA authenticator. The CIBA grant flow is initiated by a direct request from the client and involves an out-of-band interaction with the user to complete authentication and authorization. OAuth clients that support the CIBA grant type can be configured to use a specific CIBA request policy or a default.

#### Steps

- Go to **Applications # OAuth # CIBA Request Policies**. To configure a new CIBA request policy, click **Add Policy**.
- Select an action from the following options:  
Choose from:
  - To modify an existing CIBA request policy, select it by its name under **Policy ID**.
  - To review the usage of an existing CIBA request policy, click **Check Usage** under **Action**.
  - To remove an existing CIBA request policy or to cancel the removal request, click **Delete** or **Undelete** under **Action**.
  - To elect an existing CIBA request policy to be the default CIBA request policy, click **Set as Default** under **Action**.

### Defining a request policy


You can define the basics of your client-initiated backchannel authentication (CIBA) request policy in the PingFederate administrative console.

#### Steps

- Go to **Applications # OAuth # CIBA Request Policies**.
- On the **Manage Policy** tab, define the basics of your CIBA request policy.

For more information about each field, refer to the following table.

| Field                       | Description  |
|-----------------------------|--|
| Policy ID<br>(Required)     | The unique identifier of this request policy.                        |
| Name<br>(Required)          | The name of this request policy.                                     |
| Authenticator<br>(Required) | The CIBA authenticator instance associated with this request policy. |

| Field                                | Description   |
|--------------------------------------|---|
| User Code PCV                        | <p>The Password Credential Validator (PCV) instance that PingFederate uses to validate the <code>user_code</code> parameter values it receives from clients associated with this request policy.</p> <div style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>If a client is associated with a request policy that has been configured with a PCV instance, it can support user code in its configuration.</p> <p>A client supporting user code must not be associated with a request policy that is not configured with a PCV instance. For more information on CIBA client configuration, see <a href="#">Configuring OAuth clients</a> on page 566.</p> </div> |
| Transaction Lifetime (Seconds)       | <p>The validity, in seconds, of authentication requests PingFederate receives from clients associated with this request policy since the generation of their authentication request acknowledgments.</p> <p>The default value is 120.</p> <p>Clients can request a shorter lifetime by including the <code>requested_expiry</code> request parameter in their authentication requests.</p>  |
| Allow Unsigned Login Hint Token      | <p>Controls whether clients associated with this request policy can use unsigned JSON web tokens (JWT) as values of the <code>login_hint_token</code> request parameter in their authentication requests.</p> <p>This check box is not selected by default.</p>   |
| Require Token for Identity Hint      | <p>Controls whether clients associated with this request policy must use either the <code>id_token_hint</code> or <code>login_hint_token</code> as the identity hint in their authentication requests.</p> <p>This check box is not selected by default.</p> <p>When selected, clients associated with this request policy cannot use <code>login_hint</code> as the identity hint in their authentication requests.</p>  |
| Alternative Login Hint Token Issuers | <p>Alternative issuers that clients associated with this request policy can use in their signed login hint tokens. Furthermore, each additional issuer requires either the JWKS url or the actual JWKS so that PingFederate can verify the authenticity of the signed login hint tokens.</p>  |

3. Click **Next**.

### Configuring identity hint contract

You can configure the identity hint contract, which contains the set of attributes received in the client initiated backchannel authentication (CIBA) request that identifies the user.

About this task

`IDENTITY_HINT_SUBJECT` is a core attribute and is automatically populated by the `sub` attribute of an identity hint token, if found, or the attribute value of the `login_hint` request attribute.

A client can send an ID token, `id_token_hint`, or a login hint token, `login_hint_token`, as the identity hint token. If you extend the identity hint contract with attribute names from the identity token, PingFederate fulfills them with values found in the identity token.

 **Tip:**

As needed, all attributes can optionally be fulfilled differently on the **Identity Hint Contract Fulfillment** tab.

### Steps

1. Optional: Go to **Applications # OAuth # CIBA Request Policies**. On the **Identity Hint Contract Fulfillment** tab, enter an attribute name under **Extend the Contract**, and then click **Add**.
2. Repeat the previous step to define additional attributes. Click **Next**.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Click **Delete** to remove an entry.

### Example

### Example

Suppose the following JSON web token (JWT) matches the expected structure of the login hint tokens.

```
{
  "sub": "asmith",
  "attrs": {
    "mail": "asmith@example.com",
    "phone": "555-555-5555"
  }
}
```

To add both the **mail** and **phone** attributes, extend the contract with `login_hint_token.attrs.mail` and `login_hint_token.attrs.phone`, respectively.

### Configuring identity hint contract fulfillment

You can process the identity hint to further augment the identity data prior to contract fulfillment in the PingFederate administrative console.

### Steps

1. Go to **Applications # OAuth # CIBA Request Policies # Identity Hint Contract Fulfillment**.
2. Click **Manage Fulfillment** to begin the mapping configuration.
3. When the administrative console returns you to the **Identity Hint Contract Fulfillment** tab, click **Next**.

#### *Configuring attribute sources and user lookup*

You can configure the attribute sources and user lookup values in the PingFederate administrative console.

### About this task

You can set up datastore queries to supplement values returned from the source. This configuration to fulfill the identity hint's attribute contract is optional.

### Steps

1. Go to **Applications # OAuth # CIBA Request Policies**.



- Choose one of the following actions:

Choose from:

- On the **Attribute Sources & User Lookup** tab, to set up datastore queries, click **Add Attribute Source**.
- To skip this optional configuration, click **Next**.

Follow the configuration workflow to complete the setup. For configuration steps, see [Datastore query configuration](#) on page 398.

When the administrative console returns you to the **Attribute Sources & User Lookup** tab, click **Next**.

#### *Fulfilling identity hint contract*

You can fulfill identity hint contracts in PingFederate.

#### About this task


On the Identity Hint Contract Fulfillment tab, fulfill the identity hint contract with values from the original identity hint, datastores, dynamic text values, or attribute mapping expressions, if enabled.

#### Steps

- From the **Source** list, select a source.

For more information about the **Source** list, see the following table.

| Source  | Description   |
|---|---|
| Context   | Select <b>Context</b> to return specific information from the request.  |
| JDBC, LDAP, or other types of datastore (if configured) | Select an attribute source when PingFederate should retrieve attribute value from a datastore.<br><br>When you make this selection, the list under <b>Value</b> populates with attributes from your database, directory, or other datastore.<br><br>Applicable only if you have added at least one attribute source on the <b>Attribute Sources &amp; User Lookup</b> tab. For more information, see <a href="#">Configuring attribute sources and user lookup</a> on page 640.   |
| Request   | Select <b>Request</b> to use the attribute value PingFederate found in the CIBA request without customization.  |
| Expression (if enabled)                                 | Select <b>Expression</b> to support complex mapping requirements, such as transforming incoming values into different formats. Additionally, HTTP request is retrieved as a Java object rather than text. For this reason, select <b>Expression</b> as the source and use OGNL expressions to evaluate and return specific information from the HTTP request.<br><br>Applicable only if you have enabled the use of expressions in PingFederate. For more information, see <a href="#">Attribute mapping expressions</a> on page 225. |
| No Mapping  | Select <b>No Mapping</b> to ignore the <b>Value</b> field, making value selection unnecessary.  |

| Source | Description  |
|--------|--|
| Text   | <p>Select <b>Text</b> to return the value you enter under <b>Value</b>.</p> <p>You might use a static text value if the target web application provides a service based on the name of your organization.</p> <p>You can mix text with references to attributes from the identity provider (IdP) adapter contract by using the <code>\${&lt;attribute&gt;}</code> syntax.</p> <p><code>\${ds.&lt;attr-source-id&gt;.&lt;attribute&gt;}</code> You can also enter references to syntax, where <code>&lt;attr-source-id&gt;</code> is the <b>Attribute Source ID</b> value you entered on the <b>Data Store</b> tab and <code>&lt;attribute&gt;</code> is an attribute from the datastore.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>You can reference attribute values in the form of <code>\${attributeName:-defaultValue}</code>. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use <code> \${ and } </code> in the default value.</p> </div> |

2. Specify a value associated with the selected source.

Not applicable if you selected **Request**. You can also enter references to attributes from configured attribute sources by using the **Source** list.

3. Repeat these steps until all attributes are configured.
4. Click **Next**.

#### *Defining issuance criteria for identity hint contract*

You must define issuance criteria for an identity hint contract to further process a request in PingFederate.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.




#### **Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

## Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source  | Description   |
|---|---|
| <b>Context</b>  | Select to evaluate properties returned from the context of the transaction at runtime.<br><br><div data-bbox="565 474 1474 680" style="border: 1px solid black; padding: 5px;">  <b>Note:</b><br/>           Because the <b>HTTP Request</b> context value is retrieved as a Java object instead of text, attribute mapping expressions are more appropriate to evaluate and return values.         </div> |
| JDBC, LDAP, or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                | Select to evaluate the mapped attributes.   |
| Request   | Select to evaluate attributes from the CIBA request.  |

2. In the **Attribute Name** list, select the attribute to be evaluated.
3. In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**

 **Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.

**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.
- If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - For more information, see [Attribute mapping expressions](#) on page 225.
  - Click **Show Advanced Criteria**.
  - In the **Expression** field, enter the required expressions.
  - Optional: In the **Error Result** field, enter an error code or message.

**Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- Click **Add**.
  - Optional: Click **Test**, enter values in the applicable fields, and verify the results.
  - Optional: Repeat to add multiple criteria using attribute mapping expressions.
- Click **Next**.

*Reviewing identity hint contract fulfillment*

You can review, modify, or discard identity hint contract fulfillment configurations in PingFederate.

## About this task

On the **Summary** tab, review your configuration.

## Steps

Perform the following actions as needed.

| Action                          | How to accomplish it  |
|---------------------------------|---|
| <b>Amend your configuration</b> | Click the corresponding tab and follow the configuration workflow |
| <b>Keep your changes</b>        | Click <b>Done</b> and continue with the configuration             |
| <b>Discard your changes</b>     | Click <b>Cancel</b>   |

## Configuring attribute sources and user lookup for request policy contract

You can configure the attribute sources and user lookup for Client-Initiated Backchannel Authentication (CIBA) request policy contracts in the PingFederate administrative console.

### About this task

You can optionally set up datastore queries to supplement values returned from the source. This configuration to fulfill the request policy's attribute contract is optional.

### Steps

1. Go to **Applications # OAuth # CIBA Request Policies**.
2. Choose one of the following actions:  
Choose from:
  - On the **Attribute Sources & User Lookup** tab, to set up datastore queries, click **Add Attribute Source**.
  - To skip this optional configuration, click **Next**.

Follow the configuration workflow to complete the setup. For configuration steps, see [Datastore query configuration](#) on page 398.

When the administrative console returns you to the **Attribute Sources & User Lookup** tab, click **Next**.

## Configuring request policy contract fulfillment

You can fulfill the request policy contract in PingFederate.

### About this task

On the **Contract Fulfillment** tab, fulfill the request policy contract with values from the original identity hint, datastores, dynamic text values, or attribute mapping expressions (if enabled).


This contract is used to map into the OAuth grant (the **USER\_KEY** attribute), the Client Initiated Back channel Authentication (CIBA) authenticator (attributes vary depending on the authenticator), and the user code Password Credential Validator (PCV) (the **USER\_CODE\_USER\_NAME** attribute). The **USER\_CODE\_USER\_NAME** attribute is shown only if a PCV instance is selected on the **Manage Policy** window.

### Steps

1. Select a source from the **Source** list.

For more information about the **Source** list, see the following table.

| Source   | Description  |
|--|--|
| Context  | Select <b>Context</b> to return specific information from the request.   |
| JDBC, LDAP, or other types of datastores (if configured) | <p>Select an attribute source when PingFederate should retrieve attribute value from a datastore.</p> <p>When you make this selection, the list under <b>Value</b> is populated with attributes from your database, directory, or other datastore.</p> <p>Applicable only if you have added at least one attribute source on the <b>Attribute Sources &amp; User Lookup</b> window. For more information, see <a href="#">Configuring attribute sources and user lookup for request policy contract</a> on page 645.</p> |
| Request  | Select <b>Request</b> to use the attribute value PingFederate found in the CIBA request without customization.   |

| Source                  | Description  |
|-------------------------|--|
| Expression (if enabled) | <p>Supports complex mapping requirements, such as transforming incoming values into different formats. Additionally, the HTTP request is retrieved as a Java object rather than text. Therefore, select <b>Expression</b> as the source and use OGNL expressions to evaluate and return specific information from the HTTP request.</p> <p>Applicable only if you have enabled the use of expressions in PingFederate. For more information, see <a href="#">Attribute mapping expressions</a> on page 225.</p>  |
| No Mapping              | Select <b>No Mapping</b> to ignore the <b>Value</b> field, making value selection unnecessary.   |
| Text                    | <p>Select <b>Text</b> to return the value you entered under <b>Value</b>.</p> <p>You might use a static text value if the target web application provides a service based on the name of your organization. You can provide the attribute value as a constant.</p> <p>You can mix text with references to attributes from the identity provider (IdP) adapter contract by using the <code>\${&lt;attribute&gt;}</code> syntax.</p> <p>You can also enter references to attributes from configured attribute sources by using the <code>\${ds.&lt;attr-source-id&gt;.&lt;attribute&gt;}</code> syntax, where <code>&lt;attr-source-id&gt;</code> is the <b>Attribute Source ID</b> value you entered on the <b>Attribute Sources &amp; User Lookup # Data Store</b> tab and <code>&lt;attribute&gt;</code> is an attribute from datastore.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>You can reference attribute values in the form of <code>\${attributeName:-defaultValue}</code>. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use <code>\$(</code> and <code>)</code> in the default value.</p> </div> |

2. Specify a value associated with the selected source.
3. Repeat these steps until all attributes are configured.
4. Click **Next**.

### Defining issuance criteria for CIBA request policy

You must define the issuance criteria for PingFederate to further process a client-initiated backchannel authentication (CIBA) request policy.

#### About this task

On the **Issuance Criteria** tab, define the criteria to satisfy for to further process a request. Use this token authorization feature to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by choosing the source that contains the attribute to verify. Some sources are common to almost all use cases, such as **Mapped Attributes**. Other sources depend on the type of configuration, such as **JDBC**. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to verify. Depending on the selected source, the available attributes or properties vary. Specify the comparison condition and the desired value to compare to.

You can define multiple criteria, which must all be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value, depending on the chosen comparison method. The **multi-value contains ...** or **multi-**

**value does not contain ...** comparison methods are intended for attributes that can contain multiple values. Such a criterion is considered satisfied if one of the multiple values match or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Note:**

All criteria defined must be satisfied or evaluated as true for a request to move forward, regardless of how the criteria were defined. As soon as one criterion fails, rejects the request and returns an error message.

### Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source  | Description   |
|---|---|
| Context   | Select to evaluate properties returned from the context of the transaction at runtime.  |
|   | <div data-bbox="574 835 613 879" data-label="Image"> </div> <p><b>Note:</b></p> <p>The <b>HTTP Request</b> context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values.</p> |
| JDBC, LDAP, or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                | Select to evaluate the mapped attributes.   |
| Request   | Select to evaluate attributes from the CIBA request.  |

2. In the **Attribute Name** list, select the attribute to be evaluated.

3. In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

4. In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

5. In the **Error Result** field, enter a custom error message.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

6. Click **Add**.
7. Optional: Repeat to add more criteria.



8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
  - e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
  - f. Optional: Repeat to add multiple criteria using attribute mapping expressions.
9. Click **Next**.

### Reviewing your CIBA request policy

Client Initiated Backchannel Authentication (CIBA) is an extension to OpenID Connect that can improve the end-user experience during authentication and authorization in a federated environment. You can review the request policy in PingFederate.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

#### Result

 **Note:**

If this is the first policy you are creating, you must click **Done** and designate the first policy as the default before saving on the **CIBA Request Policies** window. You can change the default as needed when you create additional policies.

## OAuth attribute mapping using a datastore

Although an optional configuration, you can map OAuth attributes using a datastore in the PingFederate administrative console.

#### About this task

This optional configuration is the same for all OAuth grant mapping and token mapping configurations.

#### Steps

1. For grant mapping, go to **Authentication # OAuth # IdP Adapter Grant Mapping**. For more information, see [Grant contract mapping](#) on page 582.
2. For token mapping, go to **Applications # OAuth # Access Token Mapping**. For more information, see [Token mapping](#) on page 603.

## OAuth client session management

When an organization opens web-based protected resources to their remote employees, business partners, and customers, it has limited control over the end-user devices. To minimize security risk, both the IT administrators and end users desire session management with tight controls.

PingFederate provides an Asynchronous Front-Channel Logout endpoint and a Back-Channel Session Revocation Web Service to help OAuth clients, such as PingAccess, to terminate sessions when end users log out and to prevent unauthorized access until the end users log in again.

PingAccess works out-of-the-box with PingFederate, taking full advantages of these two features.

### Asynchronous Front-Channel Logout

Asynchronous Front-Channel Logout provides OAuth clients the capability to initiate single logout (SLO) requests to sign off associated SLO-enabled SAML 2.0 or WS-Federation sessions.

The Asynchronous Front-Channel Logout endpoint is `/idp/startSLO.ping`. Optionally, clients can add end-user sessions to a revocation list on logout and query the revocation list through the Back-Channel Session Revocation endpoint.



#### Tip:

The Asynchronous Front-Channel Logout endpoint is also published in the OpenID Connect metadata at the `/.well-known/openid-configuration` endpoint. Look for `ping_end_session_endpoint` in the metadata.

On a per-client basis, you can configure PingFederate to send logout requests, using the browser, to PingAccess and additional requests to other relying parties.

When you select the PingAccess option, PingFederate sends logout requests, using the browser, to the OpenID Connect logout endpoint on PingAccess (`/pa/oidc/logout.png`) to sign off other domains previously called by the session. For more information, see [OpenID Connect endpoints](#) in the PingAccess documentation.

In addition, when signing off an SLO-enabled SAML 2.0 or WS-Federation session, as the service provider (SP)-initiated logout request reaches the PingFederate identity provider (IdP) server, the same logout process applies as well. Depending on the enterprise architecture, this could further improve single sign-on (SSO) and logout use cases.

### Back-Channel Session Revocation

Back-Channel Session Revocation allows OAuth clients, such as PingAccess, to query the revocation status of their sessions by sending HTTP GET requests to the session revocation endpoint on PingFederate at `/pf-ws/rest/sessionMgmt/revokedSris`.

To access the session revocation endpoint, a client must be granted access to the Session Revocation API. It must also authenticate with its client secret or client certificate and include in the request the session identifier, which can be obtained from the access token or the ID token.

Back-Channel Session Revocation also allows the clients to revoke sessions by sending HTTP POST requests to the same session revocation endpoint. This gives application developers the flexibility to revoke sessions based on the logic of their applications.

For each session added to the revocation list, PingFederate retains its revocation status for a configurable lifetime. Access control and authentication requirements to revoke sessions are identical to those to query for the revocation status.

## OAuth token exchange

By configuring the OAuth authorization server to support OAuth token exchange, the authorization server can exchange a client's security token for another type of token.

The OAuth token exchange allows resource servers to exchange access tokens for other security tokens that are required to call additional APIs, much like what the microservices architecture requires. PingFederate's native support of subject tokens and actor tokens opens new use cases around delegation and impersonation that enrich the end-user experience as resources flow through seamlessly among the back-end services used by the user-facing applications.


An OAuth token exchange transaction begins when an OAuth client sends the authorization server a request with the token exchange grant type. Then the authorization server gets the token exchange processor policy specified in the client's configuration.

The token exchange processor policy specifies which parameters from the token exchange request, and optionally which attributes from other sources, will be used. The policy always uses the subject token, but it can use an actor token too. The policy also specifies which token processor instance to use based on the request's subject token type and actor token type when present. During the transaction, the token processor instance transforms the subject token and optionally the actor token, parameters, and attributes into a token exchange processor policy attribute contract.

Depending on the type of token requested and what will consume it, the authorization server sends the attribute contract to a token generator instance or access token manager instance to generate the requested token.

This feature uses the protocol defined in the specification for [OAuth 2.0 Token Exchange](#).

## Processing OAuth token exchange requests



### Notes:

- A token exchange processor policy (TEPP), includes a map of subject token types to token processor instances and a map of attributes from the request and other sources to a TEPP attribute contract.
- Optional resource parameters are used to identify an ATM instance or token generator instance.
- Optional audience parameters are used to identify another client that will use the new access token to get access to a resource. The OAuth server will select the ATM instance specified in that client's configuration.

### Configuring OAuth token exchange

Configuring the OAuth authorization server to support OAuth token exchange involves configuring token exchange processor policies, token generator instances and token exchange generator groups, access token manager instances, and OAuth clients.

#### About this task

To configure OAuth token exchange, see the included topic links to perform the necessary steps.

#### Steps

1. Define token exchange processor policies to handle incoming token exchange requests. See [Defining token exchange processor policies](#) on page 653.

2. If you need token generator instances to generate the requested tokens, complete the following tasks.
  - a. Configure the token generator instances. See [Managing token generators](#) on page 1066.
  - b. Create token exchange generator groups. See [Creating token exchange generator groups](#) on page 654.
  - c. Map the attributes from the token exchange processor policies to the attributes from the token generator instances. See [Mapping token exchange attributes to token generator attributes](#) on page 655.
3. Access token managers to generate the requested tokens.
  - a. Configure the access token manager instances. See [Managing access token management instances](#) on page 604.
  - b. Map the attributes from the token exchange processor policies to the attributes from the access token manager instances. See [Mapping token exchange attributes to access token manager attributes](#) on page 655.
4. Enable token exchange in the OAuth clients that will send the token exchange requests to the authorization server. See [Enabling token exchange in OAuth clients](#) on page 656.

### Defining token exchange processor policies

To exchange security tokens, the OAuth authorization server needs at least one token exchange processor policy.

Before you begin

Before you define a token exchange processor policy, create the necessary token processor instances. See [Managing token processors](#) on page 1043.

About this task

In the **Token Exchange Processor Policy Management** window, configure and define a token exchange processor policy.

Steps

1. Go to **Applications # Token Exchange # Processor Polices** to open the **Token Exchange Processor Policy Management** window.
2. Click **Add Processor Policy**.  
Result: The **Token Exchange Processor Policy** window opens.
3. On the **Manage Processor Policy** tab, enter the policy **ID** and **Name**. Click **Next**.  
Select the **Actor Token Required** check box if you want to specify whether the policy requires an actor token as well as a subject token in the token exchange requests from the clients.
4. On the **Attribute Contract** tab, add attributes to the attribute contract as needed. Click **Next**.

5. On the **Token Processor Mapping** tab, map a token processor to each subject token type or each combination of subject token type and actor token type:
  - a. Click the **Map New Token Processor** button.  
Result: The **Token Processor Mapping** window opens.
  - b. On the **Token Types** tab, from the **Subject Token Processor** list, select the instance.
  - c. In the **Subject Token Type** field, enter the identifier.
  - d. If an actor token processor is required, from the **Actor Token Processor** list, select the instance.
  - e. In the **Actor Token Type** field, enter the identifier. Click **Next**.
  - f. On the **Attribute Sources & User Lookup** tab, add additional attribute sources for contract fulfillment as needed. Click **Next**.
  - g. On the **Contract Fulfillment** tab, select the **Source** and **Value** for each attribute. Click **Next**.
  - h. On the **Issuance Criteria** tab, specify conditions that attributes must satisfy for PingFederate to exchange the token. Click **Next**.
  - i. On the **Summary** tab, review the token processor mapping. Click **Done**.  
Result: PingFederate returns you to the **Token Exchange Processor Policy** window.
6. On **Summary** tab, review the policy. Click **Done**.  
Result: The **Token Exchange Processor Policy Management** window opens.
7. If you want to make the new token exchange processor policy the default policy, click **Set as Default** on the corresponding row in the table.
8. Click **Save**.

### Creating token exchange generator groups

A token exchange generator group maps requested token types to your token generator instances. You can create multiple token exchange generator groups. If you assign resource URIs to the groups, clients can use the URI in the resource parameter of its requests to specify a group.

Before you begin

Before you create a token exchange generator group, configure the token generator instances. See [Managing token generators](#) on page 1066.

About this task

In the **Generator Groups** window, create a generator group for a token exchange instance.

Steps

1. Go to the **Applications # Token Exchange # Generator Groups** window.
2. Click the **Add Generator Group** button.  
The **Token Exchange Generator Group** window opens.
3. On the **Manage Generator Group** tab, enter the group **ID**, **Name**, and enter absolute **Resource URIs**.
4. On the **Requested Token Type Mapping** tab, from the **Token Generator** list, select an instance and enter the **Token Type**. Click **Add**.
5. Repeat step 4 for each type of token that you want the token exchange generator group to handle.



#### Important:

If this is the default token exchange generator group and clients will use the `requested_token_type` parameter to request specific types of tokens, then map all token types that clients can request.

6. On the **Summary** tab, review the token exchange generator group. Click **Done**.  
The **Generator Groups** window opens.

7. If you want to make the new token exchange generator group the default group, click **Set as Default** in the **Action** column.
8. Click **Save**.

### Mapping token exchange attributes to token generator attributes

When configuring the OAuth authorization server to exchange security tokens, if it uses token generator instances to create the requested tokens, then map the attributes in the attribute contract produced by the token exchange processor policy to the attributes created by the token generator instances.

Before you begin

Before you perform the following procedure:

- Define the token exchange processor policies. See [Defining token exchange processor policies](#) on page 653.
- Configure the token generator instances. See [Managing token generators](#) on page 1066.

About this task

In the **Token Generator Mappings** window, map the attributes from a token exchange processor policy to the attributes from a token generator instance.

Steps

1. Go to **Applications # Token Exchange # Token Generator Mappings** to open the **Token Generator Mappings** window.
2. From the **Source Instance** list, select a token exchange processor policy.
3. From the **Target Instance** list, select a token generator from a token exchange generator group. Click **Add Mapping** button.  
Result: The **Mapping Configuration** window opens.
4. On the **Attribute Sources & User Lookup** tab, add token generators additional attribute sources for contract fulfillment as needed. Click **Next**.
5. On the **Token Contract Fulfillment** tab, select a **Source** and **Value** for each attribute. Click **Next**.
6. On the **Issuance Criteria** tab, add and specify conditions that attributes must satisfy for PingFederate to exchange the token as needed. Click **Next**.
7. On the **Summary** tab, review the mapping configuration. Click **Done**.  
Result: The **Token Generator Mappings** window opens.
8. Click **Save**.

### Mapping token exchange attributes to access token manager attributes

When configuring the OAuth authorization server to exchange security tokens, if it uses an access token manager instances to generate requested tokens, then map the attributes in the attribute contract produced by the token exchange processor policy to the attributes in the tokens created by the access token manager instances.

Before you begin

Before you perform the following procedure:

- Define the token exchange processor policies. See [Defining token exchange processor policies](#) on page 653.
- Configure the access token managers instances. See [Managing access token management instances](#) on page 604.

About this task

In the **Access Token Mapping** window, map the attributes from a token exchange processor policy to the attributes from an access token manager instance.

### Steps

1. Go to **Applications # OAuth # Access Token Mapping**.
2. In the **Context** section, from the **Context** list, select a token exchange processor policy.
3. From the **Access Token Manager** list, select an access token manager. Click **Add Mapping**.  
Result: The **Access Token Mapping** configuration window wizard opens.
4. On the **Attribute Sources & User Lookup** tab, add access token manager attribute sources for contract fulfillment as needed. Click **Next**.
5. On the **Contract Fulfillment** tab, select a **Source** and **Value** for each attribute. Click **Next**.
6. On the **Issuance Criteria** tab, add and specify conditions that attributes must satisfy for PingFederate to exchange the token as needed. Click **Next**.
7. On the **Summary** tab, review the access token mapping. Click **Done**.  
Result: The **Access Token Mapping** window opens.
8. Click **Save**.

### Enabling token exchange in OAuth clients

After configuring the OAuth authorization server to exchange tokens, enable token exchange on each OAuth client that will send the authorization server token exchange requests.

#### Before you begin

Before you perform the following procedure, define the token exchange processor policy that the OAuth server uses when it receives a token exchange request from the client. See [Defining token exchange processor policies](#) on page 653.

#### About this task

In the **Client** window, enable OAuth token exchange in an OAuth client.

### Steps

1. Go to **Applications # OAuth # Clients** to open the **Clients** window. Click the link of the client in the **Client ID** column.  
Result: The **Client** window opens.
2. In the **Allowed Grant Types** section, select the **Token Exchange** check box.
3. In the **Token Exchange** section, from the **Processor Policy** list, select the token exchange processor policy.
4. Click **Save**.  
Result: This will take you back to the **Clients** window.
5. Click **Save**.

## Security management

---

The **Security** menu provides access to security and infrastructure-related settings. Depending on the setup of PingFederate, menu items vary.

Security management consists of the following sections:

- [Certificate and key management](#) on page 657
- [System integration](#) on page 693
- [Account lockout protection](#) on page 699
- [Password spraying prevention](#) on page 700
- [Implementing a MasterKeyEncryptor using AWS KMS](#) on page 701



## Certificate and key management

The PingFederate administrative console provides a suite of configuration wizards for administrators to manage keys and certificates.

Tasks include:

- Managing trusted certificate authorities (CAs)
- Managing server certificates for the administrative port and runtime ports
- Managing client certificates for mutual TLS authentication
- Managing signing and decryption keys and certificates
- Managing OAuth and OpenID Connect keys
- Managing certificates from partners
- Configuring certificate revocation settings
- Managing partner metadata URLs
- Rotating system keys



### Note:

For certificates that you own, you have two export options: certificate only or certificate and private key.

- Certificate only - PingFederate exports in PEM format with the file extension `.pem`.
- Certificate and private key - PingFederate exports in PEM or PKCS12 format with the file extension `.pem` or `.p12` respectively.

For features that use a certificate that you own, you can either create a new certificate or import an existing PEM or PKCS12 certificate file.

For partner certificates, you can only export the certificate. PingFederate exports the partner certificate in PEM format. You can also import a partner certificate in PEM format.

If you are running in BCFIPS mode, you can only import and export in PEM format.

You can configure to use a hardware security module (HSM) for cryptographic material storage and operations. When configured, private keys and their corresponding certificate are stored on the HSM. Related signing and decryption operations are processed there for enhanced security.



### Note:

Management of keys and certificates is restricted to administrative users with the **Crypto Admin** administrative role (see [Administrative accounts](#) on page 914).

See subsequent topics for configuration steps.

### Manage trusted certificate authorities

On the **Trusted CAs** window, you can import, export, review, and remove certificate authorities (CAs).

You can import your federation partner's CA certificate or self-signed certificates into PingFederate's global trust list on **Security # Certificate & Key Management # Trusted CAs**. If the CA is not one of the major authorities, you might also need to import the certificate from the CA that signed the partner certificate.



### Note:

If a required CA certificate is already available from the Java runtime, you do not need to import the same certificate into the PingFederate store.

### Importing trusted certificate authorities

Import your federation partner's certificate authority (CA) certificate or self-signed certificates into PingFederate's global trust list.

#### Steps

1. On the **Trusted CAs** window, click **Import**.
2. On the **Import Certificate** window, choose the applicable certificate file.



#### Note:

If PingFederate is integrated with a hardware security module (HSM) from Thales in hybrid mode, select the storage facility of the certificate from the **Cryptographic Provider** list.

- Select **HSM** to store the certificate in the HSM.
- Select **Local Trust Store** to store the certificate in the local trust store managed by PingFederate.

3. On the **Summary** window, review your configuration, amend as needed, and click **Save**.

### Exporting trusted certificate authorities

Export your federation partner's certificate authority (CA) certificate or self-signed certificates as desired.

#### Steps

1. On the **Trusted CAs** window, select **Action # Export** for the certificate.
2. On the **Export Certificate** window, click **Next**.
3. On the **Export & Summary** window, click **Export** to save the certificate file and then click **Done**.

### Reviewing trusted certificate authorities

Review certificates to ensure you've selected the correct ones.

#### Steps

1. On the **Trusted CAs** window, select the certificate by its serial number.
2. Review the selected certificate in the pop-up window.
3. When finished, close the pop-up window.

### Removing trusted certificate authorities

Remove certificates from the **Trusted CAs** window when necessary.

#### Steps

1. On the **Trusted CAs** window, select **Action # Delete** for the certificate.



#### Note:

To cancel the removal request, select **Action # Undelete** for the certificate.

2. Click **Save** to confirm your action.

### Manage SSL server certificates

On the **Security # Certificate & Key Management # SSL Server Certificates** window, you can establish and maintain the certificates presented for access to the PingFederate administrative console (or the administrative API) and for incoming HTTPS connections at runtime.

The first system-generated certificate is the default certificate for both the administrative console and the runtime server. As multiple certificates are created, you can activate or deactivate them for the administrative console, the runtime server, or both. Additionally, you can select any of them as the new default certificate for the administrative console, the runtime server, or both at a later time.

When creating a certificate, you can add additional domain names through the use of the **Subject Alternative Names** field. Furthermore, if a user agent includes the host name that it intends to reach as part of the TLS handshake, PingFederate selects the applicable certificate based on the provided Server Name Indication (SNI) information. The selection looks at the common name and subject alternative names of each activated certificate. If PingFederate finds no match, it serves the default certificate. If PingFederate finds multiple matches, it serves the certificate with the better match.



#### Note:

If PingFederate finds multiple certificates of the same matching quality, it returns one of them in the TLS handshake. This response should not impact the user agent because either the common name or one of the subject alternative names matches the host name of the request. If PingFederate should always serve a particular certificate for any given host name, ensure that the common name and any configured subject alternative names do not overlap among multiple certificates.

### SSL Server Certificates configuration

| Certificate | Common name           | Subject alternative names            | Activation status                                   |
|-------------|-----------------------|--------------------------------------|---|
| #1          | www.example.com       | (None)                               | Administrative console and runtime server           |
| #2          | www.example.org       | *.example.org and test.example.local | Administrative console and runtime server           |
| #3          | www.example.info      | *.example.info and *.example.com     | Administrative console and runtime server           |
| #4          | admin.example.local   | (None)                               | Administrative console (Default) and runtime server |
| #5          | runtime.example.local | (None)                               | Administrative console and runtime server (Default) |

### Runtime behavior

| Request type              | Host name from SNI | Certificate served  |
|---------------------------|--------------------|---|
| Administrative or runtime | www.example.com    | The host name from the SNI is an exact match to the common name of certificate #1 and a partial match to the second subject alternative name (*.example.org) of certificate #3.<br><br>An exact match is a better match, so PingFederate serves certificate #1. |
| Administrative or runtime | www.example.org    | The host name from the SNI is an exact match to the common name of certificate #2.<br><br>PingFederate serves certificate #2.   |
| Administrative or runtime | sso.example.org    | The host name from the SNI is a partial match to the first subject alternative name (*.example.org) of certificate #2. There is no other exact or partial match.<br><br>PingFederate serves certificate #2.   |

| Request type              | Host name from SNI | Certificate served  |
|---------------------------|--------------------|---|
| Administrative or runtime | sso.example.info   | The host name from the SNI is a partial match to the first subject alternative name (*.example.info) of certificate #3. There is no other exact or partial match.<br><br>PingFederate serves certificate #3.  |
| Administrative or runtime | sso.example.com    | The host name from the SNI is a partial match to the second subject alternative names (*.example.com) of certificate #3. There is no other exact or partial match.<br><br>PingFederate serves certificate #3. |
| Administrative            | www.example.local  | The host name from the SNI does not match any configured certificate.<br><br>PingFederate serves certificate #4, the default certificate for the administrative console.                                      |
| Runtime                   | localhost          | The host name from the SNI does not match any configured certificate.<br><br>PingFederate serves certificate #5, the default certificate for the runtime server.  |

### Creating a new certificate

On the **SSL Server Certificates** window, you can generate customized certificates.

#### Steps

1. On the **SSL Server Certificates** window, click **Create new**.
2. On the **Create Certificate** window, enter the required information.

For information about each field, refer to the following table.

| Field                     | Description  |
|---------------------------|--|
| Common Name               | The common name (CN) identifying the certificate.  |
| Subject Alternative Names | The additional DNS names or IP addresses that can be associated with the certificate.  |
| Organization              | The organization (O) or company name creating the certificate.   |
| Organizational Unit       | The specific unit within the organization (OU).  |
| City                      | The city or other primary location (L) where the company operates.   |
| State                     | The state (ST) or other political unit encompassing the location.  |
| Country                   | The country (C) where the company is based.  |
| Validity (days)           | The time during which the certificate is valid.  |
| Cryptographic Provider    | The storage facility of the certificate.<br><br>Applicable and visible only when PingFederate is integrated with an HSM in hybrid mode. <ul style="list-style-type: none"> <li>▪ Select <b>HSM</b> to store the certificate in the HSM.</li> <li>▪ Select <b>Local Trust Store</b> to store the certificate in the local trust store managed by PingFederate.</li> </ul> |

| Field               | Description   |
|---------------------|---|
| Key Algorithm       | A cryptographic formula used to generate a key. PingFederate uses either of two algorithms, RSA or EC.            |
| Key Size (bits)     | The number of bits used in the key. (RSA-1024, 2048 and 4096; and EC-256, 384 and 521.)                           |
| Signature Algorithm | The signing algorithm of the certificate. (RSA-SHA256, SHA384, and SHA512; and ECDSA-SHA256, SHA384, and SHA512.) |

- When finished, click **Next**.
- On the **Summary** window, review your configuration, amend as needed, and click **Save**.

### Importing a certificate and its private key

You can import certificates and their private keys in the **SSL Server Certificates** window.

#### About this task

This task describes how to import certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.

- Certificate and private key format:
  - In non-BCFIPS mode, we support PKCS12 and PEM formatted certificates and private keys, and automatically detect the format between PKCS12 and PEM.
  - In BCFIPS mode, we only support PEM formatted certificate and private keys. Only PBES2 and AES or Triple DES encryption is accepted and 128-bit salt is required. In practice, this may mean that only PEM files generated by can be imported.
  - For PEM, the private key must precede the certificates.
- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

#### Steps

- On the **SSL Server Certificates** window, click **Import**.
- On the **Import Certificate** window, choose the applicable certificate file and enter its password.



#### Note:

If PingFederate is integrated with a hardware security module (HSM) from Thales, you cannot use an elliptic curve (EC) certificate as an SSL server certificate. You must select a certificate that uses the RSA key algorithm.

- If PingFederate is integrated with an HSM in hybrid mode, select the storage facility of the certificate from the **Cryptographic Provider** list.
  - Select **HSM** to store the certificate in the HSM.
  - Select **Local Trust Store** to store the certificate in the local trust store managed by PingFederate.
- On the **Summary** window, review your configuration, amend as needed, and click **Save**.

### Creating a certificate-authority signing request (CSR)

On the **SSL Server Certificates** window, you can generate a CSR file for a certificate.

#### Steps

1. On the **SSL Server Certificates** window, select **Action # Certificate Signing** for the certificate.



#### Note:

This selection is inactive if you have not yet saved a newly created or imported certificate. Click **Save** and then return to this window to initiate the process.

The selection is also inactive if a previously signed certificate has been revoked. Because the revocation may indicate that the private key has been compromised, the best practice is to import or create a replacement certificate for certificate signing.

2. On the **Certificate Signing** window, select the **Generate CSR** option.
3. On the **Generate CSR** window, click **Export** to save the CSR file, and then click **Done**.



#### Note:

Once saved, you can submit this CSR file to a certificate authority (CA) for a CA-signed certificate.

### Importing a certificate-authority response (CSR response)

On the **SSL Server Certificates** window, you can import CSR response files for certificates.

#### Steps

1. On the **SSL Server Certificates** window, select **Action # Certificate Signing** for the certificate.
2. On the **Certificate Signing** tab, select the **Import CSR Response** option. Click **Next**.
3. On the **Import CSR Response** tab, click **Choose File**, and select the applicable CSR response file. Click **Next**.
4. On the **Summary** tab, review your configuration, and click **Save**.

### Exporting a certificate

On the **SSL Server Certificates** window, you can export a certificate with or without its private key.

#### About this task

This task describes how to export certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.

- Certificate and private key format:
  - In non-BCFIPS mode, when the **Certificate and Private Key** option is selected, a **Format** field displays allowing you to choose between exporting a PKCS12 or a PEM formatted certificate and private key.
  - In BCFIPS mode, you can only export PEM-formatted certificates and private keys.

If you need to convert from PEM to PKCS12 format, use the following command:

```
openssl pkcs12 -export -inkey keypair.pem -in keypair.pem -out keypair.p12
```

- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

### Steps

1. On the **SSL Server Certificates** window, select **Action # Export** for the certificate.
2. On the **Export Certificate** window, select the export type.
  - Select **Certificate Only** to export the selected certificate without its private key. This is the default choice.
  - Select **Certificate and Private Key** to export the selected certificate with its private key. If you are *not* running in BCFIPS mode, the **Format** section appears, and you must select either **PKCS12** or **PEM**.

You must also enter and confirm an **Encryption Password**, since this export contains the private key of the certificate.

If the selected certificate is stored in a hardware security module (HSM), the **Certificate and Private Key** option does not apply.

3. On the **Export & Summary** window, click **Export** to save the certificate file, and then click **Done**.

### Reviewing a certificate

On the **SSL Server Certificates** window, you can review a particular certificate.

### Steps

1. On the **SSL Server Certificates** window, select the certificate by its serial number.
2. Review the selected certificate in the pop-up window.
3. When finished, close the pop-up window.

### Activating or deactivating a certificate

On the **SSL Server Certificates**, you can configure whether to activate or deactivate a certificate.

### Steps

1. On the **SSL Server Certificates** window, select the relevant option under **Action** for the certificate.
 

Any certificate can be activated for the administrative console, the runtime server, or both. When multiple certificates are activated for the administrative console (or the runtime server), you can deactivate any of them as long as one certificate remains active. Additionally, you may select any of them as the default certificate.
2. Click **Save** to keep your configuration.

### Removing a certificate

On the **SSL Server Certificates** window, you can delete unwanted certificates.

### Steps

1. On the **SSL Server Certificates** window, select **Action # Delete** for the certificate.



#### Note:

If the selected certificate is activated for the administrative port, the runtime port, or both, the **Delete** option does not apply.

To cancel the removal request, select **Action # Undelete** for the certificate.

2. Click **Save** to confirm your action.

### Manage SSL client keys and certificates

On **Security # Certificate & Key Management # SSL Client Keys & Certificates**, you can create and manage your authentication private keys and the certificates your server presents as clients in an outbound SSL/TLS transaction.

The **SSL Client Keys & Certificates** window enables you to manage certificates and CSRs in multiple ways. The window's functionality allows you to create, import, export, review, and delete certificates, as well as create CSRs and import CSR responses.

#### Creating new certificates

Use the functionality found in the **SSL Client Keys & Certificates** window to create new, customized certificates.

#### Steps

1. On the **SSL Client Keys & Certificates** window, click **Create new**.
2. On the **Create Certificate** tab, enter the required information.

For information about each field, refer to the following table.

| Field                     | Description  |
|---------------------------|--|
| Common Name               | The common name (CN) identifying the certificate.  |
| Subject Alternative Names | The additional DNS names or IP addresses possibly associated with the certificate.                     |
| Organization              | The organization (O) or company name creating the certificate.   |
| Organizational Unit       | The specific unit within the organization (OU).  |
| City                      | The city or other primary location (L) where the company operates.                                     |
| State                     | The state (ST) or other political unit encompassing the location.                                      |
| Country                   | The country (C) where the company is based.  |
| Validity (days)           | The time during which the certificate is valid.  |
| Key Algorithm             | A cryptographic formula used to generate a key. PingFederate uses either of two algorithms, RSA or EC. |
| Key Size (bits)           | The number of bits used in the key. (RSA-1024, 2048 and 4096; and EC-256, 384 and 521.)                |
| Signature Algorithm       | The signing algorithm of the certificate. (RSA and ECDSA-SHA256, SHA384, and SHA512.)                  |

3. When finished, click **Next**.
4. On the **Summary** tab, review your configuration, amend as needed, and click **Done**.

#### Importing certificates and their private keys

You can import certificates and their private keys in the **SSL Client Keys & Certificates** window.

#### About this task

This task describes how to import certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.



- Certificate and private key format:
  - In non-BCFIPS mode, we support PKCS12 and PEM formatted certificates and private keys, and automatically detect the format between PKCS12 and PEM.
  - In BCFIPS mode, we only support PEM formatted certificate and private keys. Only PBES2 and AES or Triple DES encryption is accepted and 128-bit salt is required. In practice, this may mean that only PEM files generated by can be imported.
  - For PEM, the private key must precede the certificates.
- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

#### Steps

1. On the **SSL Client Keys & Certificates** window, click **Import**.
2. On the **Import Certificate** tab, choose the applicable certificate file and enter its password.



#### Note:

If PingFederate is integrated with an HSM in hybrid mode, select the storage facility of the certificate from the **Cryptographic Provider** list.

- Select **HSM** to store the certificate in the HSM.
- Select **Local Trust Store** to store the certificate in the local trust store managed by PingFederate.

3. On the **Summary** window, review your configuration, amend as needed, and click **Done**.

#### Creating a certificate signing request (CSR)

Use the **Certificate Signing** functionality to generate and save a CSR file to submit it to a certificate authority (CA) for a signed certificate.

#### Steps

1. On the **SSL Client Keys & Certificates** window, select **Certificate Signing** for the certificate.



#### Note:

This selection is inactive if you have not yet saved a newly created or imported certificate. Click **Save** and then return to this window to initiate the process.

The selection is also inactive if a previously signed certificate is revoked. Because the revocation could indicate that the private key is compromised, the best practice is to import or create a replacement certificate for certificate signing.

2. On the **Certificate Signing** tab, select the **Generate CSR** option.
3. On the **Generate CSR** tab, click **Export** to save the CSR file, and then click **Done**.



#### Note:

Once saved, you can submit this CSR file to a certificate authority for a CA-signed certificate.

#### Importing a certificate-authority response (CSR response)

Use the **Certificate Signing** functionality to import your own CSR response file into PingFederate.

#### Steps

1. On the **SSL Client Keys & Certificates** window, select **Certificate Signing** for the certificate.

2. On the **Certificate Signing** tab, select the **Import CSR Response** option.
3. On the **Import CSR Response** tab, choose the applicable CSR response file.
4. On the **Summary** tab, review your configuration, and click **Save**.

### Exporting certificates

On the **SSL Client Keys & Certificates** window, you can export a certificate with or without its private key.

#### About this task

This task describes how to export certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.

- Certificate and private key format:
  - In non-BCFIPS mode, when the **Certificate and Private Key** option is selected, a **Format** field displays allowing you to choose between exporting a PKCS12 or a PEM formatted certificate and private key.
  - In BCFIPS mode, you can only export PEM-formatted certificates and private keys.

If you need to convert from PEM to PKCS12 format, use the following command:

```
openssl pkcs12 -export -inkey keypair.pem -in keypair.pem -out
keypair.p12
```

- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

#### Steps

1. On the **SSL Client Keys & Certificates** window, select **Export** for the certificate.
2. On the **Export Certificate** tab, select the export type.
  - Select **Certificate Only** to export the selected certificate without its private key. This is the default choice.
  - Select **Certificate and Private Key** to export the selected certificate with its private key. If you are *not* running in BCFIPS mode, the **Format** section appears, and you must select either **PKCS12** or **PEM**.

You must also enter and confirm an **Encryption Password**, since this export contains the private key of the certificate.

If the selected certificate is stored in a hardware security module (HSM), the **Certificate and Private Key** option does not apply.
3. On the **Export & Summary** window, click **Export** to save the certificate file, and then click **Done**.

### Reviewing certificates

Take a closer look at individual certificates to ensure their properties match your needs.

#### Steps

1. On the **SSL Client Keys & Certificates** window, select the certificate by its serial number.
2. Review the selected certificate in the pop-up window.
3. When finished, close the pop-up window.

## Removing certificates

Delete certificates you no longer need.

### Steps

1. On the **SSL Client Keys & Certificates** window, select **Delete** for the certificate.



#### Note:

To cancel the removal request, select **Undelete** for the certificate.

2. Click **Save** to confirm your action.

## Manage digital signing certificates and decryption keys

On **Security # Certificate & Key Management # Signing & Decryption Keys & Certificates**, you can create and maintain certificates and their respective key pairs for the purpose of signing outgoing requests, responses, assertions, and access tokens, and for the purpose of decryption.

Use separate certificates for signing and decryption.

After creating your certificates, if they remain as self-signed certificates, you can enable automatic certificate rotation. See [Certificate rotation](#) on page 667.

### Certificate rotation

The optional automatic certificate rotation feature of PingFederate greatly reduces the cost of managing self-signed certificates.

PingFederate supports automatic certificate rotation for self-signed certificates created for signing SAML requests, responses, and assertions, or XML decryption for browser SSO and WS-Trust STS transactions on a per-certificate basis.



#### Note:

Certificate rotation is only available to self-signed certificates. Also, you can't enable rotation on certificates that are used as a secondary signing certificate in a connection, or are used as the primary certificate in a connection configured with a secondary signing certificate.

Certificate rotation happens over two stages, identified by the **Creation Buffer** and **Activation Buffer** settings.

- The **Creation Buffer** is the number of days ahead of expiry that PingFederate creates a new key pair and a new certificate.
- The **Activation Buffer** is the number of days ahead of expiry that PingFederate activates the certificate.

When you enable certificate rotation on a certificate, you can customize the values of the **Creation Buffer** and **Activation Buffer** settings. Alternatively, you can keep their default values, which are 25% and 10% of the original lifetime of the current certificate, respectively. The following examples illustrate the default values for both buffers based on a 100-day certificate and a 365-day certificate.

| Current certificate  | The default value for the Creation Buffer field | The default value for the Activation Buffer field | The rotation window                    |
|--|---|---|--|
| Self-signed certificate #1, valid for 100 days from January 1, 2017 to April 9, 2017 | 25 days ahead of expiry, which is March 16      | 10 days ahead of expiry, which is March 31        | 15 days from March 16 through March 30 |

| Current certificate  | The default value for the Creation Buffer field | The default value for the Activation Buffer field | The rotation window                        |
|--|---|---|--|
| Self-signed certificate #2, valid for 365 days from January 1, 2017 to December 31, 2017 | 91 days ahead of expiry, which is October 2     | 36 days ahead of expiry, which is November 26     | 55 days from October 2 through November 25 |

If the PingFederate server is shut down when the **Creation Buffer** threshold is reached for a given certificate, a new key pair and a new certificate are created if PingFederate is restarted during the rotation window.

In a clustered PingFederate environment, when the new signing certificate is ready, the administrative console displays a message to remind the administrators to replicate the new certificate to the engine nodes in **System # Server # Cluster Management**.

Although optional, you can turn on notifications for certificate events in **System # Monitoring & Notifications # Runtime Notifications**. When configured, notifies the configured recipient when a new certificate is available and when it is activated. Depending on the role of the certificate, you can update your partner accordingly.

#### *Connection and federation metadata*

Certificate rotation uses a number of inherent capabilities which enable it to deploy new certificates to replace current certificates in enabled connections.

Certificate rotation is a per-certificate configuration. When certificate rotation is enabled for a certificate and a new certificate using new key pairs becomes available, PingFederate deploys the new certificate to all enabled connections that use the original certificate. The actions taken by PingFederate vary depending on the role of the certificate.

#### Notifications

Although optional, you can turn on notifications for certificate events in **System # Monitoring & Notifications # Runtime Notifications**. When configured, notifies the configured recipient when a new certificate is available and when it is activated. Depending on the role of the certificate, you can update your partner accordingly.

#### Signing certificate

When the **Creation Buffer** threshold is reached, a new certificate is created. For all web browser single sign-on (SSO) (SAML and WS-Federation) connections using the same signing certificate, PingFederate starts including the new certificate (along with the current certificate) in their metadata. PingFederate keeps using the current certificate for signing until the remaining lifetime of the current certificate reaches the **Activation Buffer** threshold, at which point PingFederate starts signing with the new certificate and removes the previous certificate from the metadata.



#### **Important:**

To prevent SSO outages, partners must update their connections to use the new certificate to verify digital signatures before the **Activation Buffer** threshold is reached.

#### XML decryption

When a new certificate is made available, PingFederate performs the following tasks for all SAML 2.0 connections using the same decryption key:

- Pushes the current decryption key from primary to secondary
- Places the new certificate as the primary decryption key

- Updates the decryption key with the new certificate in the metadata
- Starts using the new decryption key to decrypt inbound messages. If the primary decryption key fails, PingFederate fails over to the secondary decryption key

When the remaining lifetime of the current certificate reaches the **Activation Buffer** threshold, the secondary decryption key is removed from the SAML 2.0 connections.

When PingFederate is configured to generate notifications for certificate events, PingFederate also notifies the configured recipient when the existing RSA decryption key is about to expire.



#### Important:

For XML decryption keys, only supports the RSA key algorithm. When **EC** (elliptic curve) is selected as the **Key Algorithm** value on the **Certificate Rotation** tab, does not update the SAML 2.0 connections and their metadata.



#### Important:

To prevent SSO outages, partners must update their connections to use the new certificate to encrypt messages before the **Activation Buffer** threshold is reached.

### Federation metadata for Browser SSO connections

PingFederate updates the metadata for the applicable web browser SSO connections as soon as a new certificate is available.

To ensure that your partners are aware of the new certificate, you can provide their respective federation metadata by URLs or exports.

#### Metadata by URL

PingFederate runtime engine provides an endpoint (`/pf/federation_metadata.ping`) to return metadata for web browser SSO connections. A service provider (SP) or an identity provider (IdP) is identified by its entity IDs using the **PartnerSpId** query parameter or the **PartnerIdpId** query parameter, respectively, as illustrated in the following examples.

| Partner                                   | Federation metadata URL to be given to the partner                                      |
|---|---|
| An SP partner with an entity ID of SP1.   | <code>https://www.example.com:9031/pf/federation_metadata.ping?PartnerSpId=SP1</code>   |
| An IdP partner with an entity ID of IdP1. | <code>https://www.example.com:9031/pf/federation_metadata.ping?PartnerIdpId=IdP1</code> |



#### Note:

The base URL for the PingFederate runtime engine is `https://www.example.com:9031`



#### Important:

In a clustered environment, because the console node is responsible for creating and applying the new certificates to all applicable connections, you must replicate the new certificate to the engine nodes in **System # Server # Cluster Management** when the new certificate is available, so that the federation metadata for these connections is updated accordingly.

The administrative console reminds you to replicate configuration when it detects configuration changes.

#### Metadata by manual export

Alternatively, you can export a metadata file for a connection from the **Connections Management** window or **System # Protocol Metadata # Metadata Export**.



#### Note:

PingFederate does not deploy new certificates or update metadata for inactive connections.

#### WS-Trust STS connections

For connections with only the WS-Trust security token service (STS) profile, you must export the new pending certificate and pass it to your partners out-of-band before the **Activation Buffer** threshold is reached.

If a connection contains both the Browser SSO and the WS-Trust STS profiles, the new certificate is included in the federation metadata for the Web Browser SSO profile. Your partner can reuse the certificate from the metadata by URL or manual export and apply it to its STS configuration.

#### *Managing certificate rotation settings*

Use the **Signing & Decryption Keys & Certificates** window to customize certificate rotation settings for your certificates.

#### About this task

Manage certificate rotation settings for self-signed certificates on **Security # Certificate & Key Management # Signing & Decryption Keys & Certificates**.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, select **Certificate Rotation** for the applicable certificate.



#### Note:


Certificate rotation is only available to self-signed certificates.

2. Select the check box to turn on certificate rotation for the selected certificate, then click **Next**.

If you want to turn off certificate rotation for the selected certificate, clear the check box and then click **Save**.

3. Optional: On the **Certificate Rotation** tab, modify the default values.

| Field             | Description   |
|-------------------|---|
| Creation buffer   | The number of days ahead of expiry that PingFederate creates a new key pair and a new certificate.<br>The default value is 25% of the original lifetime of the current certificate. |
| Activation buffer | The number of days ahead of expiry that PingFederate activates the certificate.<br>The default value is 10% of the original lifetime of the current certificate.                    |

| Field               | Description   |
|---------------------|---|
| Validity            | The time during which the certificate is valid.<br>The default value matches that of the current certificate.   |
| Key Algorithm       | A cryptographic formula used to generate a key. PingFederate uses either of two algorithms, RSA or EC.<br>The default value matches that of the current certificate.  |
|                     |  <b>Important:</b><br>For XML decryption keys, only supports the RSA key algorithm. When <b>EC</b> (elliptic curve) is selected as the <b>Key Algorithm</b> value on the <b>Certificate Rotation</b> tab, does not update the SAML 2.0 connections and their metadata. |
| Key Size            | The number of bits used in the key. (RSA-1024, 2048 and 4096; and EC-256, 384 and 521.)<br>The default value matches that of the current certificate.   |
| Signature Algorithm | The signing algorithm of the certificate. (RSA and ECDSA-SHA256, SHA384 and SHA512.)<br>The default value matches that of the current certificate.  |

4. On the **Certificate Rotation Summary** tab, review the rotation settings. Adjust as needed, and then click **Save** to turn on automatic certificate rotation for this certificate.

#### Managed SP connection to PingOne for Enterprise and signing certificate

Use managed service provider (SP) connections to PingOne for Enterprise to automatically rotate signing certificates being used by it.

PingFederate automatically rotates the signing certificate used by the managed SP connection to PingOne for Enterprise.



#### Note:

A managed SP connection to PingOne for Enterprise is a connection created either as part of the initial setup or the **System # External Systems # Connect to PingOne for Enterprise** configuration wizard in 8.0 or later.

The certificate rotation settings are as follows.

| Field                    | Values     |
|--------------------------|------------|
| Creation Buffer (days)   | 90         |
| Activation Buffer (days) | 30         |
| Validity (days)          | 1095       |
| Key Algorithm            | RSA        |
| Key Size                 | 2048       |
| Signature Algorithm      | RSA SHA256 |

If the signing certificate should be manually rotated instead, disable automatic certificate rotation. See [Managing certificate rotation settings](#) on page 670.

**Note:**

After making changes, the administrative console prompts for confirmation whether to update PingOne for Enterprise or to disconnect from PingOne for Enterprise in a banner message. See [Managing PingOne for Enterprise settings](#) on page 1005.

**Creating new certificates**

Use the functionality found in the **Signing & Decryption Keys & Certificates** window to create new, customized certificates.

## Steps

1. On the **Signing & Decryption Keys & Certificates** window, click **Create new**.
2. On the **Create Certificate** tab, enter the required information.

For information about each field, refer to the following table.

| Field                     | Description  |
|---------------------------|--|
| Common Name               | The common name (CN) identifying the certificate.  |
| Subject Alternative Names | The additional DNS names or IP addresses possibly associated with the certificate.                     |
| Organization              | The organization (O) or company name creating the certificate.   |
| Organizational Unit       | The specific unit within the organization (OU).  |
| City                      | The city or other primary location (L) where the company operates.                                     |
| State                     | The state (ST) or other political unit encompassing the location.                                      |
| Country                   | The country (C) where the company is based.  |
| Validity (days)           | The time during which the certificate is valid.  |
| Key Algorithm             | A cryptographic formula used to generate a key. PingFederate uses either of two algorithms, RSA or EC. |
| Key Size (bits)           | The number of bits used in the key. (RSA-1024, 2048 and 4096; and EC-256, 384 and 521.)                |
| Signature Algorithm       | The signing algorithm of the certificate. (RSA and ECDSA-SHA256, SHA384, and SHA512.)                  |

3. When finished, click **Next**.
4. On the **Summary** window, review your configuration, amend as needed, and click **Done**.

**Importing certificates and their private keys**

You can import certificates and their private keys in the **Signing & Decryption Keys & Certificates** window.

## About this task

This task describes how to import certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.



- Certificate and private key format:
  - In non-BCFIPS mode, we support PKCS12 and PEM formatted certificates and private keys, and automatically detect the format between PKCS12 and PEM.
  - In BCFIPS mode, we only support PEM formatted certificate and private keys. Only PBES2 and AES or Triple DES encryption is accepted and 128-bit salt is required. In practice, this may mean that only PEM files generated by can be imported.
  - For PEM, the private key must precede the certificates.
- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, click **Import**.
2. On the **Import Certificate** tab, choose the applicable certificate file and enter its password.



#### Note:

If PingFederate is integrated with an HSM in hybrid mode, select the storage facility of the certificate from the **Cryptographic Provider** list.

- Select **HSM** to store the certificate in the HSM.
- Select **Local Trust Store** to store the certificate in the local trust store managed by PingFederate.

3. On the **Summary** window, review your configuration, amend as needed, and click **Done**.

#### Creating a certificate signing request (CSR)

Use the **Certificate Signing** functionality to generate and save a CSR file to submit it to a certificate authority (CA) for a signed certificate.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, select **Certificate Signing** for the certificate.



#### Note:

This selection is inactive if you have not yet saved a newly created or imported certificate. Click **Save** and then return to this window to initiate the process.

The selection is also inactive if a previously signed certificate is revoked. Because the revocation could indicate that the private key is compromised, the best practice is to import or create a replacement certificate for certificate signing.

2. On the **Certificate Signing** tab, select the **Generate CSR** option.
3. On the **Generate CSR** tab, click **Export** to save the CSR file, and then click **Done**.



#### Note:

Once saved, you can submit this CSR file to a certificate authority for a CA-signed certificate.

### Importing a certificate-authority response (CSR response)

Use the **Certificate Signing** functionality to import your own CSR response file into PingFederate.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, select **Certificate Signing** for the certificate.
2. On the **Certificate Signing** tab, select the **Import CSR Response** option.
3. On the **Import CSR Response** tab, choose the applicable CSR response file.
4. On the **Summary** tab, review your configuration, and click **Save**.

### Exporting certificates

On the **Signing & Decryption Keys & Certificates** window, you can export a certificate with or without its private key.

#### About this task

This task describes how to export certificates and their private keys. Supported certificate and private key formats differ depending on whether you are running with BCFIPS enabled or disabled.

- Certificate and private key format:
  - In non-BCFIPS mode, when the **Certificate and Private Key** option is selected, a **Format** field displays allowing you to choose between exporting a PKCS12 or a PEM formatted certificate and private key.
  - In BCFIPS mode, you can only export PEM-formatted certificates and private keys.

If you need to convert from PEM to PKCS12 format, use the following command:

```
openssl pkcs12 -export -inkey keypair.pem -in keypair.pem -out keypair.p12
```

- Password requirement:
  - In BCFIPS mode, the password must contain at least 14 characters.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, select **Export** for the certificate.
2. On the **Export Certificate** tab, select the export type.
  - Select **Certificate Only** to export the selected certificate without its private key. This is the default choice.
  - Select **Certificate and Private Key** to export the selected certificate with its private key. If you are *not* running in BCFIPS mode, the **Format** section appears, and you must select either **PKCS12** or **PEM**.

You must also enter and confirm an **Encryption Password**, since this export contains the private key of the certificate.

If the selected certificate is stored in a hardware security module (HSM), the **Certificate and Private Key** option does not apply.
3. On the **Export & Summary** window, click **Export** to save the certificate file, and then click **Done**.

### Reviewing certificates

Take a closer look at individual certificates to ensure their properties match your needs.

#### Steps

1. On the **Signing & Decryption Keys & Certificates** window, select the certificate by its serial number.
2. Review the selected certificate in the pop-up window.

- When finished, close the pop-up window.

### Reviewing a certificate's usage

Take a look at a certificate's usage data to get a sense of how often it's used.

#### Steps

- On the **Signing & Decryption Keys & Certificates** window, select **Check Usage** for the certificate.



**Note:**

If the certificate is not used by any configuration, the **Check Usage** option does not apply.

- Review the information in the pop-up window.
- When finished, close the pop-up window.

### Removing certificates

Delete certificates you no longer need.

#### Steps

- On the **Signing & Decryption Keys & Certificates** window, select **Delete** for the certificate.



**Note:**

To cancel the removal request, select **Undelete** for the certificate.

- Click **Save** to confirm your action.

### Keys for OAuth and OpenID Connect

You can use keys to manage a number of security roles in PingFederate.

On **Security # Certificate & Key Management # OAuth & OpenID Connect Keys**, you can specify whether PingFederate should use static or dynamically rotating keys for OAuth and OpenID Connect.



**Note:**

When using dynamically rotating keys, the number of key sets in memory is set to three for both signing and encryption keys. This number is not configurable. The key sets include pending, active, and retired. At each rotation cycle, a new set of pending keys is generated. The original pending set becomes the active set, the active set becomes the retired set, and the old retired set goes away. All three sets are published for signing keys. For encryption keys, only the active key set is published. The rotation period and RSA key size are configurable in the file `<pf_install>/pingfederate/server/default/data/config-store/jwks-endpoint-configuration.xml`.

The keys are used in the following manner.

| PingFederate role         | Key usages  |
|---------------------------|---|
| Authorization Server (AS) | Sign self-contained access tokens for relying parties (RPs).  |
| OpenID Provider (OP)      | Sign ID tokens for RPs.   |
| Relying Party (RP)        | Sign JSON web tokens (JWTs) for authentication, sign OpenID Connect request objects, decrypt ID tokens, or any combination. |

## Configuring static signing keys

Determine when to use static and dynamically rotating keys to sign tokens as needed.

### About this task

Specify whether PingFederate should use static or dynamically rotating keys to sign self-contained access tokens, ID tokens, JSON web tokens (JWTs) for client authentication, and JWTs for OpenID Connect request objects.

### Steps

1. Go to **Security # Certificate & Key Management # OAuth & OpenID Connect Keys**.
2. Select the **Enable Static Keys** check box to use static keys for OAuth and OpenID Connect.



#### Note:

Clear this check box to let PingFederate generate and rotate keys automatically for OAuth and OpenID Connect.

The **Enable Static Keys** check box is not selected by default.

### Result:

Once selected, the administrative console displays the following fields under the **Signing Keys** heading.

| Key Type            | Active   | Previous | Publish Certificate |
|---------------------|----------|----------|---------------------|
| EC with P-256 curve | Optional | Optional | Optional            |
| EC with P-384 curve | Optional | Optional | Optional            |
| EC with P-521 curve | Optional | Optional | Optional            |
| RSA                 | Required | Optional | Optional            |

3. Follow these steps to complete the configuration under Signing Keys.
  - a. For the RSA key type, select an active signing key and optionally a previous signing key.

 **Note:**

If you don't find the desired signing key, click **Manage Certificates** to create it.  
There is no default selection.

Result:

The active signing key and the previous signing key (if configured) are published at the PingFederate JSON Web Key (JWK) Set endpoint `/pf/JWKS`.

- b. For each applicable EC (elliptic curve) key type, select an active signing key and optionally a previous signing key.

 **Note:**

If you don't find the desired signing key, click **Manage Certificates** to create it. Alternatively, complete the configuration, create the desired signing keys later, and then update the configuration afterward.

There is no default selection.

Result:

The active signing key and the previous signing key (if configured) are published at the PingFederate JWKS endpoint `/pf/JWKS`.

- c. Optional: For any key type for which you have selected an active signing key (with or without a previous signing key), select the **Publish Certificate** check box to publish the certificates associated with the active signing key and the previous signing key (if configured) at the PingFederate JWKS endpoint `/pf/JWKS`.

 **Tip:**

For each applicable signing key, its associated chain of certificates is published as the `x5c` parameter value.

The **Publish Certificate** check boxes are not selected by default.

4. Click **Save**.

Result

 **Important:**

When static keys are enabled, PingFederate uses only static signing keys to sign ID tokens for OAuth clients or to sign JWTs for authentication or request objects (or both) for authorization servers; dynamic keys are not used and are not returned by the PingFederate JWKS endpoint `/pf/JWKS`. Signing algorithms associated with EC key types not configured with an active static signing key are hidden.

For existing clients and identity provider (IdP) connections, if you have previously selected a certain signing algorithm associated with an EC key type (for example, **ECDSA using P256 Curve and SHA-256**) without enabling static keys and then subsequently decide to enable static keys without selecting an active signing key for such EC key type (**EC with P-256 curve** in this example), transactions that involve that signing

algorithm will fail. When you revisit the configuration, the administrative console displays an error message. Your options are as follows:

#### OAuth clients

- Click **Save** to update the value of the **ID Token Signing Algorithm** setting to **Default**, which is the equivalent of selecting **RSA using SHA-256** from the list.
- Select a different value from the **ID Token Signing Algorithm** list and save the configuration.
- Ignore the error and click **Cancel** without updating the configuration. Note that runtime errors persist until the configuration issue is resolved.

These options are applicable to individual clients on the **Client** window and the default setting configured for all clients created via the Dynamic Client Registration protocol on the **Client Configuration Defaults** window.

#### OpenID Connect IdP connections

- Select a different value from the **Authentication Signing Algorithm** list or the **Request Signing Algorithm** list (or both) and save the configuration.
- Ignore the error and click **Cancel** without updating the configuration. Runtime errors persist until the configuration issue is resolved.

These options are applicable to individual OpenID Connect IdP connections on the **OpenID Provider Info** window.

#### Configuring static decryption keys

You can specify whether PingFederate should use static or dynamically rotating keys to decrypt asymmetrically-encrypted ID tokens.

#### About this task



#### Note:

When static keys are enabled, you must also select an active signing key for the RSA key type.

#### Steps

1. Go to **Security # Certificate & Key Management # OAuth & OpenID Connect Keys**.
2. Select the **Enable Static Keys** check box to use static keys for OAuth and OpenID Connect.



#### Note:

Clear this check box to let PingFederate generate and rotate keys automatically for OAuth and OpenID Connect. The **Enable Static Keys** check box is not selected by default.

#### Result:

Once selected, the administrative console displays the following fields under "Decryption Keys".

| Key Type            | Active   | Previous | Publish Certificate |
|---------------------|----------|----------|---------------------|
| EC with P-256 curve | Optional | Optional | Optional            |
| EC with P-384 curve | Optional | Optional | Optional            |
| EC with P-521 curve | Optional | Optional | Optional            |
| RSA                 | Optional | Optional | Optional            |

3. Follow these steps to configure "Decryption Keys".
  - a. For each applicable key type, select an active decryption key and optionally a previous decryption key.

 **Note:**

If the desired decryption key is not found, click **Manage Certificates** to create it. Alternatively, complete the configuration, create the desired decryption keys later, and then update the configuration afterward. There is no default selection.

**Result:**

The active decryption key is published at the PingFederate JSON Web Key Set (JWKS) endpoint `/pf/JWKS`.

- b. Optional: For any key type for which you have selected an active decryption key (with or without a previous decryption key), select the **Publish Certificate** check box to publish the certificates associated with the active decryption key at the PingFederate JWKS endpoint `/pf/JWKS`.

 **Tip:**

Each applicable decryption key's associated chain of certificates is published as the `x5c` parameter value.

The **Publish Certificate** check boxes are not selected by default.

4. Under "Signing Keys", select an active key for the RSA key type.

 **Note:**

If the desired key is not found, click **Manage Certificates** to create it. There is no default selection.

**Result:**

The active signing key is published at the PingFederate JWKS endpoint `/pf/JWKS`.

5. Click **Save**.

**Result**

 **Important:**

When static keys are enabled, PingFederate uses only static decryption keys to decrypt asymmetrically-encrypted ID tokens it receives from OpenID providers. Dynamic keys are not used and are not returned by the PingFederate JWKS endpoint `/pf/JWKS`.

The following snippet illustrates a sample response returned by the PingFederate JWKS endpoint when dynamic keys are used.

```
$ curl -s https://localhost:8031/pf/JWKS |python -m json.tool
{
  "keys": [
    ...
    {
      "kty": "EC",
      "kid": "I-ZbqeLPG2O5qxSf3n8yKmcGbWI",
      "use": "enc",
```

```

    "x": "AUSx-2vdfCjU90KohVs1peISnNUeDmGo3m0_x42PucBr-Gd-
mHKXQ8EjTeYgLfB5SYMV5tntKiezayWkUt9Dodc",
    "y": "AIE6vQYcKdOfyQYzENYQ86MIAwSUo4GR_-
dn7m2MvRReXkotWosFT1WKXi_KjamqJIV2AwAUZL-IQj5mew451STM",
    "crv": "P-521"
  },
  {
    "kty": "EC",
    "kid": "S2BbNNK9PtG0nA-EhU5BGpZ-OG8",
    "use": "enc",
    "x": "IKXASh9aDPJ1YaeXUww1YZnZ3kum_WLKvZe8xiNW6W8",
    "y": "7_zp2AuY8MY4WEuneHEzV0cqW0buqcmMGVzRANQ0r2I",
    "crv": "P-256"
  },
  {
    "kty": "EC",
    "kid": "t4-jKfmhEHn3mRc-08Oh3WKA2zE",
    "use": "enc",
    "x": "RiQkv_ArGS7Zc8XsXp0VQpEWz9ZU1bLUWA0VbTcUjWIbOByceGhg-
tAj6dlFiorq",
    "y": "aHPQlrJPscdcuHtHokyr-70yBo4nUK-
BjWrJgisDxnKJQFLP6YK_dfuOpuVYhFJ5",
    "crv": "P-384"
  },
  {
    "kty": "RSA",
    "kid": "tVP7otNKgIWYep8LPBR3wD3tPNE",
    "use": "enc",
    "n":
      "hvHfiAmhV4wGC9JHppJZjdKG5K3MvhWwo6PBsSQowGOTeILAbzO8Jfmp7nRxuuJTE6k83RXNeWUvTwamGqShX
vjoNZD8Cv0Y9C3R4Ckj6dBL700sk_NfBR7MYmRA6dV0PJ5k4Lt_vQveXMkylD9XuLFP-
gqooMXk6FCClQzZAI0voi3WQ7ECzSta3ke9F5VF17-4zVjRtJHjM9gGEhd50kaZioqs9xBHeOrwhPbiPTsIA7ve
dpl_dKixFTdQYIBMmIWGUyuB43XYq106z9CWoOcw",
    "e": "AQAB"
  },
  ...
]
}

```

When static keys are used, the PingFederate JWKS endpoint `/pf/JWKS` returns only the configured active keys. The following snippet illustrates a sample response returned by the PingFederate JWKS endpoint when an active key was selected for the **EC with P-384 curve** and **EC with P-521 curve** key types.

```

$ curl -s https://localhost:8031/pf/JWKS |python -m json.tool
{
  "keys": [
    ...
    {
      "kty": "EC",
      "kid": "7xKkiMb-YpcK2PcrTUoTrYF8EOI",
      "use": "enc",
      "x": "4p_fZluiHS9qLXQi-
cqo11LP5nBrFPcXRRQN5yR3Tz51E0xfY9tmOzLqMQwKfDIh",
      "y": "kWh3up-U2mMYOuhzx4Ba7UX0P03EPLr82PdCUG6E3V53Pgnd2QU6ShWu91H4-
ugw",
      "crv": "P-384"
    },
    {
      "kty": "EC",
      "kid": "pE1XwX8Z6QYhAC7mjZ00Cn4DXAk",
      "use": "enc",
      "x": "ATCOsxcg6ce437qMv1rqCyHPDE76hC0wP7Wwv7V8heai60LIDDvIJt-
evxTOGn7IoIo9PYET8-Bjhu5Zg5MNxOkF-",

```



```

    "y":
      "AdvUA2YD2kn7COLkFIG2vL2k34CMv7VPxsvbgOJBL2exSziMGPw6YJp2eafuH1Bom7bkjv3iFy5dTUGB7B28Z
      "crv": "P-521"
    },
    ...
  ]
}

```

### Mapping ID token signing keys to virtual issuers

You can create sets of ID token signing keys in PingFederate, and map each set to one or more virtual issuers for OpenID Connect.

#### Before you begin

Before you map token signing keys to virtual issuers, configure the necessary static signing keys and virtual issuers. For more information, see [Configuring static signing keys](#) on page 676 and [Adding virtual issuers for OpenID Connect](#) on page 542.

#### About this task

When minting an ID token, PingFederate signs the ID token with a key from the right key set based on the authorization request, virtual issuers configuration, and token signing keys configuration. Because of these features, you do not need multiple PingFederate environments to support multiple brands, which especially helps if you participate in Open Banking in the UK or have similar requirements.

#### Steps

1. Go to **Security # Certificate & Key Management # Token Signing Keys**.
2. Click **Add Key Set**.
3. Enter the key set's **Name** and optional **Description**. Click **Next**.
4. Select at least one **Issuer**.
5. Select at an **RSA** signing key in the **Active** column.
6. Optional: Select one or more EC (elliptic curve) signing keys in the **Active** column.
7. Optional: Select **Previous** signing keys next to any of the **Active** keys.
8. Optional: Select the **Publish Certificate** check box next to the **Active** signing keys.  
PingFederate publishes the certificates associated with these active signing keys and previous signing keys (if selected) at the `/pfe/JWKS` endpoint.
9. Click **Save**.

### Managing certificates from partners

Manage certificates for various connections involving signature verification, encryption, and back-channel authentication to effectively process messages to and from partners.

#### About this task

You receive certificates from partners for signature verification, encryption, and back-channel authentication. They are managed within connections.



#### Note:

Depending on the use cases, your connection to the partner might not require signature verification, encryption, inbound (SOAP) back-channel authentication by client certificate, or any such combinations. If so, the **Activation & Summary** window does not display the related administrative window.

### Signature verification

Specify one or more certificates that PingFederate can use to validate the digital signatures found in inbound messages from your partners.

#### Steps

1. Select the connection to reach its **Activation & Summary** window.
2. Select **Signature Verification Certificate**.
3. Click **Manage Certificates**.

**Note:**

You can import, export, review, activate, deactivate, and remove certificates for signature verification on the **Certificate Management** window.

### Encryption

Specify a certificate that PingFederate uses to encrypt outbound messages before delivering them to your partners.

#### Steps

1. Select the connection to reach its **Activation & Summary** window.
2. Select **Select XML Encryption Certificate**.
3. Click **Manage Certificates**.

**Note:**

You can import, export, review, activate, and remove certificates for encryption on the **Certificate Management** window.

### Back-channel authentication

Specify a certificate that PingFederate uses to authenticate inbound (SOAP) messages from your partners by their client certificates.

#### Steps

1. Select the connection to reach its **Activation & Summary** window.
2. Select **SSL Verification Certificate**.
3. Click **Manage Certificates**.

**Note:**

You can import, export, review, activate, and remove certificates for back-channel authentication on the **Certificate Management** window.

### Configuring certificate revocation

You can choose whether to use certificate revocation list (CRL) checking or Online Certificate Status Protocol (OCSP) checking as your preferred verification method.


#### About this task

By default, OCSP revocation checking is enabled. Optionally, on **Security # Certificate & Key Management # Certificate Revocation Checking**, you can enable CRL checking as a backup method for failover. Alternatively, depending on your requirements, you can disable OCSP checking and rely only on CRL checking. For more information, see [Certificate validation](#) on page 96.

## Steps

## 1. Optional: Configure OCSP.



For more information about each field, see the following table.

| Field   | Description   |
|---|---|
| Enable OCSP   | Turns on OCSP certificate-revocation checking.<br><br>OCSP checking is enabled by default.  |
| Default OCSP Responder URL                                | A URL to use for certificate-revocation checking, a backup used only if the OCSP Responder URL is not contained in the certificate.   |
| Default OCSP Responder Signature Verification Certificate | Certificate used to verify that the returned certificate status was sent from the Default OCSP Responder—required if the certificate is not included in the response.<br><br>Click <b>Manage Certificates</b> to import the verification certificate.   |
| Do NOT allow Responder to use cached responses            | When not selected, the OCSP Responder uses cached responses when available for the subject certificate for an indicated period of time—see the description for <b>Next Update Grace Period</b> .<br><br>If checked, PingFederate sends a nonce in the request to the Responder, effectively requiring that the status of the certificate be determined in real time. This option is intended to enhance the prevention of Internet replay attacks (in addition to timestamping), where required.<br><br><div data-bbox="565 947 1472 1121" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b><br/>Making this selection might slow down OCSP response time for a request and will increase general processing overhead at the Responder site.</p> </div> <p>This check box is not selected by default.</p> |
| This Update Grace Period (min)                            | To consider the response valid, the PingFederate server-clock time must correspond to the <code>&lt;thisUpdate&gt;</code> timestamp in the OCSP response, plus or minus the number of minutes set for this field to compensate for clock variances.<br><br>The default value is 5 minutes.  |
| Next Update Grace Period (min)                            | If the response includes a <code>&lt;nextUpdate&gt;</code> timestamp indicating when updated certificate statuses are available, then PingFederate checks to ensure that the timestamp is not earlier than the current server time, adding this grace period to compensate for clock variances.<br><br>The default value is 5 minutes.  |
| Responder Timeout (sec)                                   | The allowable response time before the OCSP Responder URL is considered unavailable and processing continues. See the <b>OCSP Responder is Unavailable</b> setting.<br><br>The default value is 5 seconds.  |
| Response Caching Interval (hrs)                           | The number of hours that PingFederate caches the OCSP response.<br><br>The default value is 48 hours.   |

| Field                         | Description  |
|-------------------------------|--|
| Certificate is Unknown        | The certificate does not fall under the purview of the certificate authority (CA) associated with the OCSP Responder. The choices indicate whether an unknown certificate is considered valid, or whether to try CRL checking.<br><br>The default selection is <b>Treat as Revoked</b> . |
| OCSP Responder is Unavailable | Indicates what action to take if you cannot reach the Responder. The choices indicate whether an unknown certificate is considered valid, or whether to try CRL checking.<br><br>The default selection is <b>Treat as Valid</b> .  |
| OCSP Responder Returns Error  | Indicates what action to take if the Responder returns an error. The choices indicate whether an unknown certificate is considered valid, or whether to try CRL checking.<br><br>The default selection is <b>Treat as Revoked</b> .  |

2. Optional: Configure CRL checking.

For more information about each field, see the following table.

| Field/Selection                            | Description   |
|--|---|
| Enable CRL Checking                        | Enables CRL revocation checking.<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Note:</b><br/>CRL checking must remain enabled if any selections for OCSP Error Handling include failover. If OCSP is enabled and no CRL failover is specified, then this selection has no effect. </div><br>CRL revocation checking is disabled by default.  |
| Treat Unretrievable CRLs as Revoked        | If selected, PingFederate immediately aborts the processing associated with the certificate.<br><br>If not selected, the server treats the certificate as valid but continues trying to retrieve the CRL.<br><br>This check box is not selected by default.   |
| Next Retry on Resolution Failure (min)     | Specifies the number of minutes the server waits before trying to retrieve a CRL when the previous attempt failed—applies only when <b>Treat Unretrievable CRLs as Revoked</b> is unchecked.<br><br>The default value is 1440 minutes, which is 24 hours.   |
| Next Retry on Next Update Expiration (min) | How long the server waits before requesting a new CRL when the most recently retrieved CRL (in cache) has a next-update time in the past.<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Note:</b><br/>Certain actions in the administrative console, such as saving changes to an identity provider (IdP) adapter instance, reset the CRL cache. When this happens, PingFederate requests new CRLs for subsequent transactions as needed. </div><br>The default value is 60 minutes. |

| Field/Selection      | Description  |
|----------------------|--|
| Verify CRL Signature | When selected (recommended), PingFederate verifies the CRL signature using the public key of the issuer, which must be in the certificate chain or in the list of Trusted CAs.<br><br>This check box is selected by default. |
| Proxy Settings       | If CRL checking is routed through a proxy server, specify the server's host DNS name or IP address and the port number. The same proxy information applies to OCSP checking, when enabled.                                   |

### Transitioning to an HSM


Use the PingFederate administrator functionality to determine whether to store keys and certificates on a hardware security module (HSM) or a local trust store.

About this task


Administrators can enable the HSM hybrid mode, which provides the choice to store each relevant key and certificate on an HSM or the PingFederate-managed local trust store. This capability allows organizations to transition the storage of keys and certificates to a supported HSM to meet security requirements without the need to deploy a new PingFederate environment and mirror the setup.

The following images illustrate some general interactions between PingFederate and an HSM. Those interactions depend on whether you configure the HSM in hybrid mode.

PingFederate not in HSM hybrid mode



PingFederate in HSM hybrid mode



**Note:**

For a list of supported HSMs, see the "Hardware security modules" section under "Third-party cryptographic solutions" in [System requirements](#) on page 119.

When all relevant keys and certificates are stored on the HSM, administrators can turn off the HSM hybrid mode. When the HSM hybrid mode is disabled, PingFederate delegates the management of the relevant keys and certificates to the HSM.

**Important:**

After the HSM hybrid mode is disabled, for keys and certificates that should be stored on an HSM, PingFederate will only access those keys and certificates from the HSM, regardless of whether such keys and certificates exist on the local trust store.

Steps

1. Install and configure the HSM client and the existing PingFederate environment. See [Supported hardware security modules](#) on page 177.

**Important:**

When editing the `<pf_install>/pingfederate/bin/run.properties` file, set the `pf.hsm.hybrid` property to `true` to enable the HSM hybrid mode.

Result:

After PingFederate is integrated with your HSM, you can create (and store) new certificates on your HSM. Because the HSM hybrid mode is enabled, you can reconfigure connections or other

configuration items to use the new certificates over a period of time. As long as the HSM hybrid mode is enabled, PingFederate can use certificates stored on your HSM and the local trust store.

 **Important:**

When making changes to keys and certificates, you might need to coordinate with your partners. For more information, see [Digital signing policy coordination](#) on page 97.

2. Create a new SSL server certificate on your HSM and activate it for the administrative console and the runtime server on **Security # Certificate & Key Management # SSL Server Certificates**.

 **Note:**

You can also create separate certificates on your HSM and activate one certificate for the administrative console and the other certificate for the runtime server. For configuration steps, see [Manage SSL server certificates](#) on page 658.

3. Create new digital signing certificates and decryption keys on **Security # Certificate & Key Management # Signing & Decryption Keys & Certificates** and reconfigure connections or configuration items to use the new certificates and keys from your HSM.

 **Tip:**

Use **Check Usage** to locate the applicable connections or configuration items.

For configuration steps, see [Manage digital signing certificates and decryption keys](#) on page 667.

4. If your connections support outbound (SOAP) back-channel authentication by client certificates, create new SSL client certificates on **Security # Certificate & Key Management # SSL Client Keys & Certificates** and reconfigure connections to use the new certificates from your HSM.

 **Tip:**

Use **Check Usage** to locate the applicable connections or configuration items.

For configuration steps, see [Manage SSL client keys and certificates](#) on page 664.

5. If you are transitioning to an Entrust HSM, export the trusted certificate authority (CA) certificates from the local trust store and import them to your HSM on **Security # Certificate & Key Management # Trusted CAs** and reconfigure configuration items to use the new certificates and keys from your HSM.

 **Tip:**

Use **Check Usage** to locate the applicable configuration items.

For configuration steps, see [Manage trusted certificate authorities](#) on page 657.

6. If you are transitioning to an Entrust HSM, for connections using the unanchored trust model, export the partner certificate for back-channel authentication from the local trust store, import them to your HSM, and reconfigure the connections to use the new certificates from your HSM. For information about the unanchored trust model, see "Trust models" under [Digital signing policy coordination](#) on page 97.

For configuration steps, see [Managing certificates from partners](#) on page 681+.

### Manage Partner metadata URLs

On the **Security # Certificate & Key Management # Partner Metadata URLs** window, you can add, update, review, or remove SAML metadata URLs provided by your partners.

SAML metadata URLs streamline the process of establishing and maintaining SAML connections. If your partner provides SAML metadata by URL, you can use the metadata URL for the following scenarios:

- Creating a new SAML connection using the metadata URL and associating the metadata URL with the new connection
- Enabling or disabling automatic updates from the associated metadata URL
- Adding or updating the metadata URL associated with an existing SAML connection
- Updating an existing SAML connection using the metadata URL instantly



#### Tip:

You can quickly create connections with InCommon participants, update the connections automatically or manually as the InCommon participants update their metadata, and do so securely knowing PingFederate only commits changes to your connections after validating the digital signatures of the signed metadata.

When PingFederate accesses a digitally signed metadata URL for the first time, it validates the digital signature and stores the metadata URL and its verification certificate if the signature is correct. When an existing metadata URL is accessed, PingFederate validates the digital signature using the stored certificate. If there is a digital signature error, PingFederate aborts the process and provides an error with a recommended course of action. You can bypass the signature verification process.

### Adding a new metadata URL

Use the **Partner Metadata URLs** window's functionality to add a custom-configured metadata URL.

#### Steps

1. On the **Partner Metadata URLs** window, click **Add New URL**.
2. On the **URL** tab, define the metadata URL.
  - a. Configure each field.

| Field                       | Description   |
|-----------------------------|---|
| Name                        | A name of the metadata URL.   |
| URL                         | The metadata URL.   |
| Validate Metadata Signature | <p>Determines whether PingFederate should validate the digital signature of signed metadata.</p> <p>Select the check box to verify digital signatures.</p> <p>Clear the check box to skip the signature verification process.</p> <p>This check box is selected by default.</p> |

- b. Click **Load Metadata**.



3. On the **Certificate Summary** tab, review the certificate information.

**Note:**

This is shown and applicable only when the **Validate Metadata Signature** check box on the **URL** tab is selected.

- If the metadata is not digitally signed (unsigned), click **Verify** to confirm that the unsigned metadata is reachable at the time of the configuration.
- If the metadata is signed but the certificate is provided outside of the metadata, click **Import** to upload the verification certificate.

4. On the **Summary** tab, review the configuration. Click **Done** and **Save**.

**Updating an existing metadata URL**

Use the **Partner Metadata URLs** window's functionality to update and correct the configuration of existing metadata.

## Steps

1. On the **Partner Metadata URLs** window, select the applicable metadata by its name.
2. On the **URL** tab, update the name, URL, or digital signature verification option. Click **Next**.
3. On the **Certificate Summary** tab, click **Verify** to confirm that the unsigned metadata is reachable at the time of the configuration or update the verification certificate of a signed metadata.

**Note:**

This is shown and applicable only when the **Validate Metadata Signature** check box on the **URL** tab is selected.

4. If the metadata is signed but the certificate is provided outside of the metadata, click **Import** to upload the verification certificate. Click **Next**.
5. On the **Summary** tab, review the configuration, then click **Done** and **Save**.

**Reviewing a metadata URL usage**

Use the **Partner Metadata URLs** window's functionality to look over a piece of metadata's information.

## Steps

1. On the **Partner Metadata URLs** window, select **Check Usage** for the applicable metadata.

**Note:**

The **Check Usage** option is shown and applicable only when the metadata is used by at least one connection.

2. Review the information in the pop-up window.
3. When finished, close the pop-up window.

## Removing a metadata URL

Use the **Partner Metadata URLs** window's functionality to delete an unwanted piece of metadata.

### Steps

1. On the **Partner Metadata URLs** window, select **Delete** for the applicable metadata.



#### Note:

The **Delete** option is shown and applicable only when the metadata is not used by any connections.

To cancel the removal request, select **Undelete** for the certificate.

2. Click **Save** to confirm your action.

## Rotating system keys

On the **System Keys** window, you can manually rotate your PingFederate system keys to optimize your environment's security.

### About this task

System keys are used in cryptographic operations to generate and consume internal tokens. These tokens are leveraged in multiple use cases such as one-time links for self-service password reset and email ownership verification. Periodic rotation ensures optimal security of your environment.

### Steps

1. Go to **Security # Certificate & Key Management # System Keys**.
2. To rotate the system keys, click **Rotate**.
3. Click **Save**.

### Result

PingFederate generates a new **Pending** key. The key that was **Pending** becomes the **Current** key. The key that was **Current** becomes the **Previous** key.

## Managing configuration encryption keys

PingFederate maintains a set of configuration encryption keys to encrypt and decrypt sensitive information.

These keys encrypt and decrypt sensitive configuration information and runtime data like the following:

- Datastore passwords
- Adapter shared secrets
- Reversible secrets in OAuth clients
- Data encrypted using the `obfuscate.sh/bat` script, such as the cluster authentication password in the `run.properties` file
- User attributes in access grants and persistent sessions

PingFederate stores configuration encryption keys in the `pf.jwk` file in chronological order, starting with the newest key at the top. The `pf.jwk` file is in the `<pf_install>/pingfederate/server/default/data` directory.

```
{ "keys": [
  { "kty": "oct", "kid": "WTIsxFH5gE", "k": "FKDBYJ13ZHPpi_oLI2_4q_1FgKNi7J1fx8HTyTJINPc", "creationDate": 1639162773 },
  { "kty": "oct", "kid": "W31mrSXqnH", "k": "Keadc5M4cFoLKdWtR2zaEx8P0Dzs-L2U35JNGgLzDHI", "creationDate": 1639162773 }
]}
```

For encryption, PingFederate uses the newest, or primary, key in `pf.jwk`. For decryption, PingFederate tries each key in the file, starting with the primary key, until it succeeds or until there are no more keys to try.

Managing configuration encryption keys involves regularly rotating the keys and re-encrypting sensitive information with new keys. When `pf.jwk` accumulates keys that are no longer needed for decryption, you can delete them. Use the PingFederate administrative console and the `configkeymgr` utility to manage your configuration encryption keys.

The administrative console lets you rotate the keys. The `configkeymgr` utility lets you perform the following tasks:

- List all of the configuration encryption keys.
- Rotate the keys, creating a new key and setting it as the primary encryption key.
- Re-encrypt encrypted configuration data using the primary encryption key.
- Delete unused configuration encryption keys.

The utility, located in the `<pf_install>/pingfederate/bin` directory, comes in two variants:

- `configkeymgr.bat` for Windows
- `configkeymgr.sh` for Linux

When managing configuration encryption keys, PingFederate logs events in the `configkeymgr.log`, `admin.log`, or `admin-api.log`, depending on what you used to perform the tasks.

You should protect your configuration encryption keys with [AWS KMS](#) or a custom solution based on the [PingFederate SDK](#) (the `MasterKeyEncryptor` interface).

### Rotating configuration encryption keys

You can use the PingFederate administrative console to rotate configuration encryption keys.

#### About this task

To maintain security, you should regularly rotate the configuration encryption keys. Rotating keys involves generating a new key and making it the new primary key. PingFederate will use the new primary key to encrypt sensitive information.

To rotate configuration encryption keys:

#### Steps

1. In the administrative console, go to **Security # Certificate & Key Management # Configuration Encryption Keys**.
2. Click **Rotate**.

Result:

PingFederate generates a new key, inserts it into the top of the `pf.jwk` file, and displays it at the top of the **Configuration Encryption Keys** window.

#### Next steps

After you rotate the configuration encryption keys, you should use the `configkeymgr` utility to re-encrypt information that was encrypted with previous keys.

### Re-encrypting sensitive information with configuration encryption keys

You can use the `configkeymgr` command-line utility to re-encrypt sensitive configuration information and OAuth client secrets.

#### About this task

You should re-encrypt sensitive information after you rotate the configuration encryption keys.

To re-encrypt sensitive configuration information:

### Steps

1. Stop the PingFederate console node.
2. Run the `configkeymgr` utility on the console node:
  - If PingFederate is running on Windows, open a command prompt, go to `<pf_install>/pingfederate/bin`, and run `configkeymgr.bat`.
  - If PingFederate is running on Linux, open a terminal window, go to `<pf_install>/pingfederate/bin`, and run `configkeymgr.sh`.

#### Result:

The utility displays its usage help.

3. Run the `reencrypt` command.

The utility offers optional arguments for the `reencrypt` command.

#### Example:

For example, to perform a dry run of the `reencrypt` command in a Linux environment, enter the following command.

```
./configkeymgr.sh --reencrypt --dry-run
```

4. Restart the PingFederate console node.
5. If PingFederate is running in a cluster:
  - a. Replicate the configuration to the engine nodes.
  - b. Run the `configkeymgr` utility on the engine nodes to re-encrypt data that is not included in the replication archive, such as sensitive data defined in the `run.properties` file.

#### Note:

You can run the utility on engine nodes without stopping them.

### Deleting unused configuration encryption keys

When PingFederate accumulates configuration encryption keys that are no longer needed for decryption, you can delete them.

#### About this task

Unused keys accumulate in the `pf.jwk` file as keys are rotated. They also accumulate when data archives are imported. The `configkeymgr` utility lets you delete unused keys.

The utility lets you delete a specific unused key, all unused keys that were created before a specific time, or all unused keys that were created before a specific key was created. If you use the `--before-timestamp <arg>` parameter, where `<arg>` is a timestamp argument, specify the timestamp value in one of the following formats:

- The format on the **Configuration Encryption Keys** window, which looks like "Tue Dec 14 14:50:20 PST 2021"
- The format in the administrative API, which looks like `2021-12-14T22:50:20.000Z`
- The Unix timestamp format from the `pf.jwk` file, which looks like `1639522220`

For more information about the `delete` command's parameters, see the utility's usage help.

When you run the `delete` command, the utility first scans the configuration data, looking for in-use keys. If the utility finds any in-use keys within the scope defined by the command's parameters, it will not delete any keys.

**Important:**

The scan to determine if the keys are in use only works for keys used in PingFederate's configuration or in OAuth clients. The utility does not perform the in-use check on sessions and grants. If you delete in-use keys that are referenced by unexpired sessions or grants, users will need to re-authenticate or re-authorize.

Before you delete configuration encryption keys, you should wait until the sessions and grants that reference older keys expire. To do that, first determine when the configuration data was last re-encrypted with a new key. Next, find the lifetime of the sessions and grants. Then wait the lifetime of the sessions or grants, whichever is longer, after the re-encryption date. For example, if you re-encrypted the data on June 1st, sessions last 8 hours, and grants last 30 days, then wait at least 30 days after June 1st before you delete the encryption keys.

To delete unused configuration encryption keys:

**Steps**

1. Stop the PingFederate console node.
2. Run the configkeymgr utility on the console node:
  - If PingFederate is running on Windows, open a command prompt, go to `<pf_install>/pingfederate/bin`, and run `configkeymgr.bat`.
  - If PingFederate is running on Linux, open a terminal window, go to `<pf_install>/pingfederate/bin`, and run `configkeymgr.sh`.

**Result:**

The utility displays its usage help.

3. Run the `delete` command with one of the following scope parameters:
  - `--before-timestamp <arg>` deletes any keys that were created before the specified time.
  - `--keyid <arg>` deletes the key with the specified key ID.
  - `--before-keyid <arg>` deletes any keys that were created before the specified key.

**Example:**

For example, in a Linux environment, run the following command to delete unused keys that were created before a specific time.

```
./configkeymgr.sh --delete --before-timestamp "Tue Jun 15 14:00:00 PST 2021"
```

4. Restart the PingFederate console node.
5. If PingFederate is running in a cluster, replicate the configuration to the engine nodes.

**System integration**

You can configure PingFederate to act in accordance with your circumstances.

If PingFederate acts in a service provider (SP) role, you can configure redirect validation rules to ensure valuable information, such as user attribute values, is sent only to a list of designated target resources. If PingFederate is deployed behind a reverse proxy or a load balancer, you can configure whether and how PingFederate should extract contextual information from the requests. You can manage the availability and authentication requirements for the supporting services that PingFederate offers. You can find these menu items in the **Security** tab under the **System Integration** section.

## Configuring redirect validation

Ensure that a designated target exists by validating single sign-on (SSO), single logout (SLO) and self-service user account management transactions.

### About this task

You can configure several service provider (SP) adapters to pass security tokens or other user credentials from the PingFederate SP server to the target resource via HTTP query parameters, cookies, or POST transmittal. In all cases, these transport methods carry the risk that a third party (with specific knowledge of the identity provider (IdP), the SP, or both, PingFederate endpoints, and PingFederate configuration) could obtain and use valid security tokens to gain improper access to the target resource.

This potential security threat involves using a well-formed SSO or SLO link to start an SSO or SLO request for a resource at the SP site. However, the target resource designated in the link intercepts the security token by a redirection to a malicious website. This same threat also applies to self-service user account management endpoints when such requests include the **TargetResource** parameter.

To prevent such an attack, PingFederate provides a means of validating SSO, SLO, and self-service user account management transactions to ensure that the designated target resource exists through a list of configurable URLs. At minimum, an expected resource requires a domain name (or an IP address) and the selection of one or more applicable request types.



#### Note:

The following default target URLs are always allowed, and you don't need to enter them into the list manually:

- The default target URL for any IdP connections (see [Configuring default target URLs](#) on page 758)
- The default target URL for any adapter-to-adapter mappings (see [Configuring a default target URL \(optional\)](#) on page 411)
- The SP default URL for successful SSO (see [Configuring default URLs](#) on page 719)
- The IdP default URL for successful SLO (see [Configuring a default URL and error message](#) on page 437)

PingFederate can also validate the error resource parameter. For more information about the **InErrorResource** parameter, see [IdP endpoints](#) on page 1250, [SP endpoints](#) on page 1256 and [System-services endpoints](#) on page 1269.



#### Important:

PingFederate enables both target resource validation and error resource validation by default in new installations.

For backward compatibility, PingFederate upgrade tools do not enable these options if they aren't selected in the previous PingFederate installation. Although optional, we strongly recommend enabling validation for both target and error resources and entering all expected resources (including the HTTPS option) to prevent unauthorized access.

### Steps

1. Go to **Security # System Integration # Redirect Validation**.

## 2. Configure target resource validation options.

| Option        | Description   |
|---------------|---|
| SSO           | <p>When selected, PingFederate validates the requested target resource for IdP connections, adapter-to-adapter mappings, and SAML 2.0 IdP Discovery against a list of configurable resources.</p> <p>This check box is selected by default in new installations.</p> <p>Clear the check box to disable the feature.</p> |
| SLO and Other | <p>When selected, PingFederate validates the requested target resource for SLO and self-service user account management requests against a list of configurable resources.</p> <p>This check box is selected by default in new installations.</p> <p>Clear the check box to disable the feature.</p>                    |

## 3. Configure error resource validation.

**Note:**

Select the **Enable InErrorResource Validation** check box to validate the requested **InErrorResource** parameter value against a list of configurable resources.

This check box is selected by default in new installations.

Clear the check box to disable the feature.

## 4. Define a list of expected resources.

- a. Indicate whether to mandate secure connections when this resource is requested under **Require HTTPS**.

**Important:**

This selection is recommended to ensure that the validation will always prevent message interception for this type of potential attack, under all conceivable permutations.

This check box is selected by default.

- b. Enter the expected domain name or IP address of this resource under **Valid Domain Name**.

Enter a value without the protocol, such as `example.com` or `10.10.10.10`.

Prefix a domain name with a wildcard followed by a period to include subdomains using one entry. For instance, `*.example.com` covers `hr.example.com` or `email.example.com` but not `example.com`, the parent domain.

**Important:**

While using an initial wildcard provides the convenience of allowing multiple subdomains using one entry, consider adding individual subdomains to limit the redirection to a list of known hosts.

- c. Optional: Enter the exact path of this resource under **Valid Path**.

Start with a forward slash, without any wildcard characters in the path. If left blank, any path under the specified domain or IP address is allowed. This value is case-sensitive. For instance,

`/inbound/Consumer.jsp` allows `/inbound/Consumer.jsp` but rejects `/inbound/consumer.jsp`.

You can allow specific query parameters with or without a fragment by appending them to the path. For instance, `/inbound/Consumer.jsp?area=West&team=IT#ref1001` matches `/inbound/Consumer.jsp?area=West&team=IT#ref1001` but not `/inbound/Consumer.jsp?area=East&team=IT#ref1001`.

- d. Optional: Select the check box under **Allow Any Query/Fragment** to allow any query parameters or fragment for this resource.

Selecting this check box also means that no query parameter and fragment are allowed in the path defined under **Valid Path**.

This check box is not selected by default.

- e. Select one or more request types for this resource.
- Select the check box under **TargetResource for SSO** if this is an expected SSO target resource for one or more IdP connections, adapter-to-adapter mappings, or SAML 2.0 IdP Discovery.
  - Select the check box under **TargetResource for SLO and Other** if this is an expected target resource for SLO and self-service user account management requests.
  - Select the check box under **InErrorResource** if this is an expected **InErrorResource** parameter value.

These check boxes are not selected by default.

- f. Click **Add**.

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an existing entry. Use the **Delete** and **Undelete** workflow to remove an existing entry or cancel the removal request.

- g. Repeat these steps to define multiple expected resources.



**Note:**

The display order does not matter. A more specific match is considered a better match and an exact match is considered the best match.

5. Click **Save**.

### Managing partner redirect validation

PingFederate enables you to validate a parameter for single logout (SLO) to prevent unauthorized access.

#### About this task

Some of the parameters used to perform redirection represent locations at a partner site—for example, the **wreply** parameter in WS-Federation. To protect against session token hijacking through open redirections, PingFederate provides an option to validate **wreply** for single logout (SLO). Once enabled, the parameter value is managed within the connection on a per-partner basis. PingFederate amalgamates the entries from all active WS-Federation connections and validates **wreply** against the consolidated list.



**Important:**

PingFederate enables **wreply** validation for SLO by default in new installations.

For backward compatibility, PingFederate upgrade tools do not enable this option if it was not selected in the previous PingFederate installation. Although optional, enabling **wreply** validation for SLO and specifying the allowed domains and paths for each WS-Federation connection can prevent unauthorized access.



## Steps

1. Go to **Security # Redirect Validation # Partner Redirect Validation**.
2. Select the **Enable wreply Validation For SLO** check box to enable this feature.



### Note:

This check box is selected by default in new installations. Clear the check box to disable the feature.

3. Click **Save**.

## Configuring incoming proxy settings

Use the options in the **Incoming Proxy Settings** window to let PingFederate access the information it needs to construct correct responses for incoming requests.

When PingFederate is deployed behind an application load balancer (ALB), a network load balancer (NLB), a reverse proxy, or a similar network traffic management solution on-premises or in the cloud, the following options enable PingFederate to use information in HTTP headers added by the reverse proxy to construct correct responses. These options, configurable on **Security # System Integration # Incoming Proxy Settings**, apply globally to all incoming requests.

### HTTP header for client IP addresses

The **HTTP Header for Client IP Addresses** field allows you to globally specify the header name (for example, `X-Forwarded-For`) where PingFederate should attempt to retrieve the client IP address in all HTTP requests sent to PingFederate. Defining this field helps PingFederate identify the correct client IP address when PingFederate is operating behind a load balancer or something similar.



### Note:

By design, the `X-Forwarded-For` header exposes privacy-sensitive information, such as the IP address of the client. This header is untrustworthy when no trusted reverse proxy exists between the client and server. PingFederate assumes that a trusted proxy verifies any headers configured in the **Incoming Proxy Settings** rather than coming directly from the client. Therefore, we recommend that customers only configure headers in **Incoming Proxy Settings** that are proxied through a trusted source.

Load balancers and proxies commonly append the IP address from an incoming request to the `X-Forwarded-For` (or similar) header. If you enter `X-Forwarded-For` as the value of the **HTTP Header for Client IP Addresses** field, PingFederate combines multiple comma-separated header values in the same order that they are received. Define which IP address you want to use in the list box:

- Leave the default of **Use Last Value** to use the last value in the combined list.
- Select **Use First Value** to use the first value in the combined list.

### HTTP header for hostname

The **HTTP Header for Hostname** field allows you to globally specify the header name (for example, `X-Forwarded-Host`) where PingFederate should attempt to retrieve the hostname and port in all HTTP requests sent to PingFederate. Proxies commonly append the hostname and port from an incoming request to the `X-Forwarded-Host` (or similar) header. If you enter `X-Forwarded-Host` as the value of the **HTTP Header for Hostname** field, PingFederate combines multiple comma-separated header values into the same order that they are received. Define which hostname you want to use in the list box:

- Leave the default of **Use Last Value** to use the last value in the combined list.
- Select **Use First Value** to use the first value in the combined list.

Client certificate header name and chain header name

If you use mutual client certificate authentication and want to use the Apache HTTP Server with `mod_ssl` as the incoming proxy, configure the Apache HTTP Server to pass client certificates as HTTP request headers and enter the header names on the **Incoming Proxy Settings** window.

The following examples shows the Apache HTTP Server configured to pass the client leaf certificate and up to four intermediate certificates as headers.

```
...
SSLOptions +ExportCertData
RequestHeader set LEAF_CERT "%{SSL_CLIENT_CERT}s"
RequestHeader set CHAIN0 "%{SSL_CLIENT_CERT_CHAIN_0}s"
RequestHeader set CHAIN1 "%{SSL_CLIENT_CERT_CHAIN_1}s"
RequestHeader set CHAIN2 "%{SSL_CLIENT_CERT_CHAIN_2}s"
RequestHeader set CHAIN3 "%{SSL_CLIENT_CERT_CHAIN_3}s"
...
```



**Note:**

This configuration snippet is for demonstration purposes only.

To configure PingFederate to consume these HTTP request headers for the purpose of mutual client certificate authentication:

- Enter `LEAF_CERT` as the **Client Certificate Header Name**.
- Enter `CHAIN` as the **Client Certificate Chain Header Name**.



**Note:**

Do not enter the trailing number from the chain header names.



**CAUTION:**

Because HTTP request headers could potentially be forged, you should only specify a **Client Certificate Header Name** and a **Client Certificate Chain Header Name** if the Apache HTTP Server is immediately in front of your PingFederate environment. The specified values must match the header names used in the Apache HTTP Server configuration, omitting the trailing number from the chain header names.

Incoming proxy terminates HTTPS connections

The **Incoming proxy terminates HTTPS connections** option allows you to globally specify that connections to the reverse proxy are made over HTTPS even when HTTP is used between the reverse proxy and PingFederate.

### Configuring service authentication

Administrators with the **Admin** role can activate and configure authentication for Attribute Query, Java Management Extensions (JMX), and SSO Directory Service.

About this task

If you are using the SAML 2.0 Attribute Query profile as a service provider (SP), then the requesting applications at your site must authenticate to the PingFederate server. For more information, see [Attribute Query and XASP](#) on page 49 and the [/sp/startAttributeQuery.ping](#) on page 1259 SP application endpoint.

Authentication is required to access PingFederate runtime data via JMX (see [Runtime monitoring using JMX](#) on page 1097) or to make SOAP calls to the Connection Management Service. Authentication is optional for the SSO Directory Service. For more information, see [Web service interfaces and APIs](#) on page 1193 and [SSO Directory Service](#) on page 1198.



**Note:**

To help ensure network security, access to all of these services is deactivated when PingFederate is first installed.

To activate and configure authentication for the Connection Management Service, grant the administrators all three administrative roles: **Admin**, **Crypto**, and **User Admin**. For more information, see [Connection Management Service](#) on page 1195.

Steps

- To enable a service:
  - a. On **Security # System Integration # Service Authentication**, select **Action # Activate** for your desired service.
  - b. Enter or modify) the service account **ID** and define or reset the **Shared Secret**.  
You and the application developer must agree to these values.



**Tip:**

Authentication is optional for the SSO Directory Service.

- To disable a service, on **Security # Service Authentication**, select **Deactivate** under **Action** for your desired service.



**Note:**

Although not accessible when deactivated, the Connection Management Service and the SSO Directory Service are deployed by default with PingFederate. If your organization does not plan to use one or both of these services, you can remove the following WAR file or files:

- `<pf_install>/pingfederate/server/deploy2/pf-mgmt-ws.war` for the Connection Management Service
- `<pf_install>/pingfederate/server/deploy/pf-ws.war` for the SSO Directory Service

## Account lockout protection

Account lockout protection provides a level of security to the user and can operate in multiple ways based on the PingFederate environment.

Account lockout protection prevents user accounts from locking at the underlying user repository based on too many failed authentication attempts. It also adds a layer of protection against brute force and dictionary attacks because the user is locked out for a time period when the number of failed attempts exceeds the threshold. This protection is enabled in many areas of , including the HTML Form Adapter, the Username Token Processor, the OAuth resource owner password credentials grant type, and the native authentication scheme for the administrative console and API.



**Note:**

The HTML Form Adapter and the Username Token Processor provide a per-instance setting for the maximum number of failed attempts such that administrators can use unique values for different instances of the adapter or the token processor.

In a PingFederate clustered environment, depending on the chosen runtime state-management architecture, the account locking-state information is shared across a replica set, multiple replica sets, or all nodes in the cluster.

Settings for account lockout protection are stored in the `com.pingidentity.common.security.AccountLockingService.xml` configuration file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.


### Configuring account lockout protection

Use PingFederate's functionality to customize your account lockout protection settings.

#### Steps

1. Edit the `com.pingidentity.common.security.AccountLockingService.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.

For more information, see the inline comments and the following table.

| Property               | Description   |
|------------------------|---|
| MaxConsecutiveFailures | <p>The maximum number of failed attempts before a user is locked out for a time period.</p> <p>The default value is 3.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The per-instance setting in the HTML Form Adapter and the Username Token Processor overrides this property.</p> </div> |
| LockoutPeriod          | <p>The amount of time in minutes that a user is locked out when the <b>MaxConsecutiveFailures</b> threshold is reached.</p> <p>The default value is 1 minute.</p>   |

If you have a PingFederate clustered environment, edit this file on the console node.

2. Save the change.
3. Restart PingFederate.
4. If you have a PingFederate clustered environment, click **Replicate Configuration** in **System # Server # Cluster Management**.

### Password spraying prevention

Use password spraying prevention to mitigate against attacks which exploit weak or compromised passwords.

Password spraying prevention adds a layer of defense against the attack pattern where bad actors try to gain access to protected resources by using the same password, typically weak or compromised, against multiple accounts from multiple locations. When enabled, tracks the number of failed login attempts per password. When the number of failures for a particular password reaches a threshold, that password is temporarily locked out. Password spraying prevention applies to the HTML Form Adapter, the Username Token Processor, and the OAuth 2.0 resource owner password credentials grant type.

While password spraying prevention can help mitigate the risk of unauthorized access, we recommend that you also enforce a good password policy and a multifactor authentication solution, such as PingID, to protect your organization from password spraying attacks.

In a PingFederate clustered environment, depending on the chosen runtime state-management architecture, state information is shared across a replica set, multiple replica sets, or all nodes in the cluster.

Settings for password spraying prevention are stored in the `com.pingidentity.common.security.AccountLockingService.xml` configuration file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.

### Configuring password spraying prevention

Configure how password spraying prevention functions within your PingFederate environment to customize your login security experience.

#### Steps

1. Edit the `com.pingidentity.common.security.AccountLockingService.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.

For more information, see the inline comments and the following table.

| Property                           | Description   |
|------------------------------------|---|
| <code>DoPasswordLocking</code>     | Enable ( <code>true</code> ) or disable ( <code>false</code> ) password spraying prevention.<br>The default value is <code>false</code> .   |
| <code>MaxPasswordAttempts</code>   | The maximum number of failed attempts before a password is locked out for a time period.<br>Applicable only if password spraying prevention is enabled.<br>The default value is 5.                                      |
| <code>PasswordLockoutPeriod</code> | The amount of time in minutes that a password is locked out when the <b>MaxPasswordAttempts</b> threshold is reached.<br>Applicable only if password spraying prevention is enabled.<br>The default value is 5 minutes. |

If you have a PingFederate clustered environment, edit this file on the console node.

2. Save the change.
3. Restart PingFederate.
4. If you have a PingFederate clustered environment, click **Replicate Configuration** on **System # Server # Cluster Management**.

## Implementing a MasterKeyEncryptor using AWS KMS

During initial startup, PingFederate automatically generates a randomized master key, which by default is not encrypted. If you are running in Amazon Web Services (AWS), you can configure PingFederate to use Amazon Key Management Services (KMS) to encrypt the master key.

#### Before you begin

- Make sure that you have an active connection to AWS.
- Use AWS KMS to generate a key to use for the PingFederate master key encryption.

- See <https://docs.aws.amazon.com/kms/latest/developerguide/overview.html> for general information about how you can manage access rights to your keys using key policies or AWS Identity and Access Management (IAM).

### About this task

To configure the encryption of the PingFederate master key, modify two files: `hivemodule.xml` and `com.pingidentity.crypto.jwk.MasterKeySet.xml`.

### Steps

1. Stop PingFederate.
2. Open `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` in a text editor.
3. Locate the following lines near the bottom of the file.

```
<service-point id="MasterKeyEncryptor"
  interface="com.pingidentity.sdk.key.MasterKeyEncryptor">
  <create-instance
    class="com.pingidentity.crypto.jwk.NoOpMasterKeyEncryptor"/>
</service-point>
```

4. To enable master key encryption using AWS KMS, replace the lines shown in step 3 with the following lines.

```
<service-point id="MasterKeyEncryptor"
  interface="com.pingidentity.sdk.key.MasterKeyEncryptor">
  <create-instance
    class="com.pingidentity.pingcommons.aws.key.AwsKmsMasterKeyEncryptor"/>
</service-point>
```

5. Save and close the file.
6. Open `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.crypto.jwk.MasterKeySet.xml` in a text editor.

The contents of the file are shown here.

```
<?xml version="1.0" encoding="UTF-8"?>
<con:config xmlns:con="http://www.sourceid.org/2004/05/config">
  <!--
    Uncomment the below attribute to use an external key for
    encryption of PF Master Key.

    <con:item name="keyId"> put the key Id here </con:item>
  -->
  <con:item name="jwkEncrypted">>false</con:item>
</con:config>
```

7. Uncomment the `<con:item name="keyId">` attribute and specify the key that you generated using AWS KMS. For example, after you've made the change, the file might look like the following.

```
<?xml version="1.0" encoding="UTF-8"?>
<con:config xmlns:con="http://www.sourceid.org/2004/05/config">
  <con:item name="keyId">b3867a2c-4d15-8e0c-6f7b-0b1e61f7ad36</
con:item>
  <con:item name="jwkEncrypted">>false</con:item>
</con:config>
```

8. Save and close the file.
9. Start PingFederate.

## Result

After configuring and starting PingFederate, the PingFederate master key file, `pf.jwk`, is encrypted.

## Self-service user account management

---

As an administrator, you can enable certain self-service applications to let end users better manage their accounts and, by extension, lower identity management costs.

PingFederate provides various self-service applications for end users to manage their accounts. These optional capabilities lower the costs of identity management by freeing administrators from round-the-clock service requests to change passwords, reset passwords, unlock accounts, and recover usernames. Designed for ease of deployment, these capabilities are integrated into the HTML Form Adapter. Administrators can easily enable some or all capabilities with a few configuration changes on a per-adapter basis. Like other user-facing windows, you can customize and localize the user-facing templates to provide the desired user experience.

PingFederate also allows users to unlock their accounts without submitting a ticket to the IT department. When enabled with SSPR, if an account is locked, a user can initiate an account unlock request at the **Sign On** window or the per-adapter Password Reset endpoint. Through the HTML Form Adapter, PingFederate prompts the user to prove ownership of the account using the password reset flow.

When users succeed in proving account ownership, they are allowed to retain their current passwords or to reset their passwords as needed. Furthermore, self-service account unlock is only compatible with PingDirectory and Microsoft Active Directory. If the underlying datastore is connected to Oracle Unified Directory or Oracle Directory Server, users can only unlock their account by changing their current password through the password reset flow.



### Tip:

Similarly, when configuring customer identity and access management use cases, administrators can enable end users to manage their local accounts, connect or disconnect one or more social connections, and change or set the password for their local accounts. For more information, see [Customer IAM configuration](#) on page 357 and [Enabling profile management](#) on page 383.

## Configuring self-service password management

In the **IdP Adapters** window, create or modify an instance of the HTML Form Adapter to enable a customized self-service password management capability.

### About this task

PingFederate offers self-service username password management for users to change their network password. This optional capability is integrated into the HTML Form Adapter and the LDAP Username Password Credential Validator (PCV). You can configure PingFederate to generate notification messages when users successfully change the password associated with their accounts through the HTML Form Adapter or when their passwords are about to expire.

If you are validating credentials through the PingOne for Enterprise Directory PCV, you can also enable the change password capability. Notifications for change password and password expiry are not supported at this point.

### Steps

1. Go to **Authentication # Integration # IdP Adapters**.

- To create a new HTML Form Adapter instance, click **Create New Instance** or, to reuse one, select an existing HTML Form Adapter instance.

If you are reusing an existing HTML Form Adapter instance, skip to [step 1c](#) to configure your adapter instance to enable self-service password management.

- On the **Type** tab, configure your adapter instance settings. Click **Next**.
- On the **IdP Adapter** tab:
  - In the **Password Credential Validator Instance** section, select the PCV instance as the credential validator.
  - Optional: Update any default values or options.
  - Select the **Allow Password Changes** check box.

IdP Adapters | Create Adapter Instance

Type | **IdP Adapter** | Extended Contract | Adapter Attributes | Adapter Contract Mapping | Summary

Complete the configuration necessary to look up user security contexts in your environment. This configuration was designed into the adapter for use at your site.



Credential Validators ⓘ

**Password Credential Validator Instance** Action

[Add a new row to "Credential Validators"](#)

| Field Name             | Field Value  | Description  |
|------------------------|--|--|
| CHALLENGE RETRIES      | 3  | Number of failed user authentications after which the PingFederate account locking service blocks future attempts.   |
| SESSION STATE          | <input type="radio"/> Globally<br><input type="radio"/> Per Adapter<br><input checked="" type="radio"/> None | Determines how state is maintained within one adapter or between different adapter instances. To take advantage of additional features, it is recommended to use a PingFederate Authentication Session rather than this adapter's internal Session State capability. |
| SESSION TIMEOUT        | 60   | Session Idle Timeout (in minutes). If left blank the timeout will be the Session Max Timeout. Ignored if 'None' is selected for Session State.   |
| SESSION MAX TIMEOUT    | 480  | Session Max Timeout (in minutes). Leave blank for indefinite sessions. Ignored if 'None' is selected for Session State.  |
| ALLOW PASSWORD CHANGES | <input checked="" type="checkbox"/>  | Allows users to change their password using this adapter.  |

- Configure your adapter instance options. For more information, see the following table.

| Option                                | Effects  |
|---------------------------------------|--|
| <b>Change Password Notification</b>   | Select if you want PingFederate to generate a notification message for the user who has successfully changed their password through the HTML Form Adapter.<br><br> <b>Note:</b><br>The message is sent to the user's email address, specifically the mail attribute value returned by the LDAP Username PCV instance. |
| <b>Show Password Expiring Warning</b> | Select if you want the <b>Sign On</b> window to warn the user about an approaching password expiration.  |
| <b>Change Password Notification</b>   | Select to choose a notification publisher instance.<br><br> <b>Note:</b><br>If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b> .   |



| Option                      | Effects   |
|-----------------------------|---|
| <b>Show Advanced Fields</b> | Click to review or modify default values related to the change password capability. For example, update the <b>Change Password Template</b> field if you want to use a custom template to render the <b>Change Password</b> window. |

5. Optional: Customize and localize the on-window messages and notification messages.

### Result

You have created a new instance or modified an existing instance of the HTML Form Adapter with the self-service password management capability.

When a user signs on through this adapter instance, the user has the option to change the password associated with the account using the **Change Password** link.



#### Tip:

You can also provide your users the per-adapter Change Password endpoint `/ext/pwdchange/Identify`, which allows them to change their password through this HTML Form Adapter instance without submitting single sign-on (SSO) requests.

## Configuring self-service account recovery

PingFederate offers self-service password reset for users to recover their accounts if they forgot their passwords.

### About this task

Integrated into the HTML Form Adapter and Password Credential Validator (PCV) framework, users reset their passwords through one of the following mechanisms:

- Authentication policy
- One-time link through email
- One-time password through email
- One-time password through text message
- PingID - The PingID account recovery option requires users to already have a PingID account.

The self-service password reset capability relies on the HTML Form Adapter and the LDAP Username PCV to query the required attributes for the chosen reset mechanism. PingFederate supports PingDirectory, Microsoft Active Directory, Oracle Unified Directory, and Oracle Directory Server out-of-the-box. Custom PCV implementations can also be developed to offer the self-service password reset features for users stored in non-LDAP data sources. For more information, see the `ResettablePasswordCredential` interface in Javadoc.



#### Tip:

The Javadoc for is located in the `<pf_install>/pingfederate/sdk/doc` directory.

## Steps

1. Create a new LDAP datastore. For instructions, see [Configuring an LDAP connection](#) on page 942. You can also reuse an existing LDAP datastore connection.



### Important:


- When connecting to an Active Directory (AD) LDAP server, you must secure the datastore connection using LDAPS. AD requires this level of security to allow password changes.
- When connecting to PingDirectory, Oracle Unified Directory, or Oracle Directory Server, configure proxied authorization for the service account on the directory server. See [Proxied authorization](#) on page 949.
- When connecting to PingDirectory, you can configure the `pwdAccountLockedTime` attribute type for the service account on the directory server to allow PingFederate account recovery to unlock locked PingDirectory accounts. See [Allowing PingFederate to unlock PingDirectory accounts](#) on page 949.


2. Create an LDAP username password credential validator. For instructions, see [Configuring the LDAP Username Password Credential Validator](#) on page 982.

The advanced fields on the **Instance Configuration** tab allow you to configure self-service password reset, account unlock, and user name recovery through the HTML Form Adapter

3. Create a new HTML Form Adapter instance. For complete field descriptions, see [Configuring an HTML Form Adapter instance](#) on page 306 and [HTML Form Adapter advanced fields](#) on page 318.
  - a. Go to **Authentication # Integration # IdP Adapters**.
  - b. In the **IdP Adapters** window, click **Create New Instance**.
  - c. On the **Type** tab, enter an instance name and ID.
  - d. From the **Type** list, select **HTML Form IdP Adapter**, and click **Next**.
  - e. On the **IdP Adapter** tab, click **Add a new row to 'Credential Validators'** and select the LDAP Username PCF instance defined in [step 2](#).
  - f. Select the **Allow Password Changes** check box.
  - g. Select the **Change Password Notification** check box if you want PingFederate to generate a notification message for a user who has successfully changed their password through the HTML Form Adapter.

The message is sent to the user's email address, specifically the mail attribute value returned by the LDAP Username PCV instance.
  - h. Select a **Password Reset Type**. See the following table for more information.

| Field               | Description   |
|---------------------|---|
| Password Reset Type | <p>Select one of the following methods for self-service password reset.</p> <p><b>Authentication Policy</b></p> <p>Based on the policy contract selected from the <b>Password Reset Policy Contract</b> list, PingFederate finds the applicable authentication policy to handle self-service password reset requests. If the users are able to fulfill the authentication requirements as specified by the policy, PingFederate allows the users to reset their password.</p> <p><b>Email One-Time Link</b></p> <p>Users receive a notification with a URL to reset their password. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p> <p><b>Email One-Time Password</b></p> <p>Users receive a notification with a one-time password (OTP) to reset their password. If you have not yet configured the desired notification publisher instance, click <b>Manage Notification Publishers</b>.</p> <p><b>PingID</b></p> <p>Users are prompted to follow the PingID authentication flow to reset their password. Ensure the <b>PingID Username Attribute</b> field in the selected LDAP Username PCV instance is configured; otherwise, users will not be able to reset their password. You must also download the settings file from the PingOne admin portal and upload the file to the <b>PingID Properties</b> advanced field.</p> <div data-bbox="651 1209 1468 1608" style="border: 1px solid black; padding: 10px;"> <p> <b>Important:</b></p> <p>Do not use a method that is already part of a multi-factor authentication policy that includes a password challenge, as that would indirectly reduce that authentication policy to a single factor. For example, if users normally authenticate with a password challenge and then PingID, the self-service password reset method should not be PingID. Instead, choose the <b>Authentication Policy</b> option, select a policy contract from the <b>Password Reset Policy Contract</b> list, and configure an authentication policy for self-service password reset.</p> </div> <p><b>Text Message</b></p> <p>Users receive a text message notification with an OTP to reset their password. Ensure the <b>SMS Attribute</b> field in the selected LDAP Username PCV instance is configured; otherwise, users will not receive text message notification for password reset. If you have not yet configured SMS provider settings in PingFederate, click <b>Manage SMS Provider Settings</b>.</p> <p><b>None</b></p> <p>Users cannot reset password through this HTML Form Adapter instance.</p> <p>The default selection is <b>None</b>.</p> |

| Field                          | Description   |
|--------------------------------|---|
| Password Reset Policy Contract | <p>If you use an authentication policy to handle SSPR requests, you must select a policy contract here.</p> <p>This policy contract doesn't require any extended attributes because uses this policy only to find the applicable authentication policies for password resets.</p> <div style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>You must use a policy contract dedicated only to password reset. You can't use this policy contract for SSO anywhere else. To define a policy contract solely for password reset, click <b>Manage Policy Contracts</b>.</p> <p>An authentication policy that uses this contract allows users to reset their password. Ensure the policy uses strong authentication methods to securely identify the user who initiated the password reset operation. Map the <i>incoming user ID</i> for adapters in the policy to <b>Requested User</b> and confirm that adapters will only return success when this user is the one authenticating.</p> <p>For guidelines on designing adapters for use in password reset or password change authentication policies, see <a href="#">Developing IdP adapters</a> on page 1120.</p> </div> |

- i. Select the **Account Unlock** check box if you want to enable self-service account unlock as well.
  - j. Select a notification publisher instance from the list.
 

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.
  - k. Click **Show Advanced Fields** to review or modify the rest of the default values related to self-service password reset. For descriptions of all advanced fields, see [HTML Form Adapter advanced fields](#) on page 318
4. If you selected **Authentication Policy** as the password reset type, create a new authentication policy to handle self-service password reset requests.

Generally a password reset policy must authenticate users through means other than prompting for the forgotten passwords. It should also enforce multi-factor authentication for added security. Consider the following sample use case.

You have already created an authentication policy to protect single sign-on (SSO) requests. This policy uses an HTML Form Adapter instance to validate user credentials and an instance of the PingID Adapter for multi-factor authentication. If users satisfy both authentication requirements, the policy uses a policy contract to relay user attributes to partners. To learn more about this policy configuration, see [Defining authentication policies based on group membership information](#) on page 261.

Like SSO, you also want to protect self-service password reset with multi-factor authentication.

Knowing your company actively manages client certificates on company devices, you have decided to use an instance of the X.509 IdP Adapter (named X.509) as the first-factor authentication source in your password reset policy. You have extended the adapter contract with a **cn** attribute, through which the adapter exposes the username found in the client certificate. For added security, you intend to leverage PingID as the second-factor authentication source. Per step 3e, you have also created a

new policy contract (named SSPR APC) for the sole purpose of SSPR. At this point, you are ready to create your password reset policy.

- a. On **Authentication # Policies # Policies**, click **Add Policy**.
- b. On the **Policy** window, enter a name (and optionally a description) for the policy.
- c. Select the X.509 IdP Adapter instance.
- d. Configure each policy path out of the X.509 Adapter instance.

Fail

Select **Done**, which terminates the self-service password reset request.

For instance, if a user submits a self-service password reset request from a personal device, the request will fail because the browser on the personal device is not equipped with the company-managed client certificate issued to that user (that is only available on that user's company device).

Success

Select the same PingID Adapter instance that you have created and used in the SSO policy.

- e. Configure the incoming user ID for the PingID Adapter instance.
  1. Click **Options** to open the **Incoming User ID** dialog.
  2. Select **Adapter (X.509)** under **Source**.
  3. Select **CN** under **Attribute**.
  4. Click **Done** to close the **Incoming User ID** dialog.

For more information, see [Specifying incoming user IDs](#) on page 258.

- f. Configure each policy path out of the PingID Adapter instance.

Fail

Select **Done**, which terminates the self-service password reset request.

Success

Select **SSPR APC**, which is the policy contract created solely for password reset per step 3e.



**Important:**

You must not reuse this policy contract for SSO elsewhere.

- g. Configure the contract fulfillment for the selected policy contract.

Because the sole purpose of the selected policy contract is to route the SSPR requests through this password reset policy, the fulfillment of this contract does not matter. It is not used elsewhere. For instance, you can configure its mapping as follows.

| Contract Attribute | Source | Value  |
|--------------------|--------|--------|
| subject            | Text   | Benign |

- h. Click **Done** and then **Save**.

This sample use case demonstrates the capability and flexibility that a password reset policy offers. Depending on actual use cases, you can use a different series of authentication sources to authenticate users in a secure manner. For example, if your organization manages devices using AirWatch, you can add an instance of the AirWatch Adapter as one of the authentication sources in the password reset policy. Other similar solutions include MobileIron and Microsoft Intune.

5. Optional: Customize and localize the on-screen messages and notification messages.

## Result

You successfully created a new instance or modified an existing instance of the HTML Form Adapter with the SSPR and account unlock capabilities.

When a user signs on through this adapter instance, the user has the option to reset the password or unlock the account using the **Trouble Signing On** link.

Additionally, you can also provide your users the per-adapter Account Recovery endpoint `/ext/pwdreset/Identify`, which allows them to reset their password or unlock their account through this HTML Form Adapter instance without submitting SSO requests.

## Configuring self-service user name recovery

Use PingFederate's self-service user name recovery feature to enable users to recover their lost user names through their email addresses.

### About this task

PingFederate offers self-service user name recovery for users to recover their accounts through email if they forget their user names.

This optional capability is integrated into the HTML Form Adapter and the LDAP Username Password Credential Validator (PCV). PingFederate supports PingDirectory, Microsoft Active Directory, Oracle Unified Directory, and Oracle Directory Server out-of-the-box. Custom PCV implementations can also be developed to offer the same capability for users stored in non-LDAP data sources. For more information, see the `RecoverableUsername` interface in Javadoc.



### Tip:

The Javadoc for `RecoverableUsername` is located in the `<pf_install>/pingfederate/sdk/doc` directory.

## Steps

1. Go to **Authentication # Integration**. On the **IdP Adapters** window, create a new HTML Form Adapter instance.

You can also reuse an existing HTML Form Adapter instance. If you do, skip to [step 1c](#) to configure your adapter instance to enable the self-service user name recovery capability.

- a. Select the HTML Form Adapter instance as the credential validator.
- b. Optional: Update any default values or options.
- c. Select the **Enable Username Recovery** check box.
- d. Select a notification publisher instance from the list.



### Note:

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.

- e. Click **Show Advanced Fields** to review or modify default values related to self-service user name recovery.

Example:

Select the **Require Verified Email** check box if you want PingFederate to only send user name recovery email messages to users who have proven ownership of their email addresses.

2. Optional: Customize and localize the on-window messages and notification messages.

## Result

You successfully created a new instance or modified an existing instance of the HTML Form Adapter with the self-service user name recovery capability.

When a user signs on through this adapter instance, the user has the option to recover the user name using the **Trouble Signing On** link.

You can also provide your users the per-adapter username recovery endpoint `/ext/idrecovery/Recover`, which allows them to recover their user name through this HTML Form Adapter instance without submitting single sign-on (SSO) requests.

## Service provider SSO configuration

---

You can use the PingFederate administrative console as a service provider (SP) to configure local application-integration information and to manage connections to your identity provider (IdP)-partner sites.

Only one connection is needed per partner, even if integrating more than one web application.

While you define your entity ID on the **Federation Info** tab of the **Protocol Settings** window, you can identify your organization differently through the use of virtual server IDs on a per-connection basis. For more information, see [Multiple virtual server IDs](#) on page 115.

Additionally, you can deploy an SP connection to bridge a service provider to one or more identity providers through one or more authentication policy contracts. For more information, see [Federation hub use cases](#) on page 108 and [Federation hub and authentication policy contracts](#) on page 112.



### Note:

This topic applies to configuration settings needed for browser-based single sign-on (SSO). Although this information also applies to WS-Trust security token service (STS), if you are using PingFederate exclusively as an STS, start with [WS-Trust STS configuration](#) on page 1041.

## SP application integration settings

The integration of local applications with PingFederate is the essential "last-mile" configuration that allows end-users at your identity provider (IdP) partner's website to access your protected resources.

The use of application-integration kits and a robust SDK facilitates the integration of local applications with PingFederate. For more information, see [Bundled adapters and authenticators](#) on page 65.

You can configure the service provider (SP) adapters that PingFederate uses to create user sessions that allow single sign-on (SSO) access to your protected resources. You can also set Default URLs to which users can be directed during SSO or single logout (SLO) and look up system endpoints that application developers at your site need to access PingFederate's SSO/SLO services.



### Note:

If your PingFederate configuration enables the WS-Trust security token service (STS), you can configure plugin token generators on the **Applications** tab in the **Token Exchange # Token Generators** window. For more information, see [Service provider STS configuration](#) on page 1066.



## Managing SP adapters

A service provider (SP) adapter creates a local-application session for a user to provide single sign-on (SSO) access to your applications or other protected resources. You must configure at least one instance of an SP adapter to set up connections to identity provider (IdP) partners.

### About this task

You can configure multiple instances of adapters, based on one or more adapters, to accommodate the varying needs of your IdP partners.

PingFederate comes bundled with OpenToken Adapter. You can deploy additional integration kits from the Ping Identity Downloads website.

### Steps

1. Go to **Applications # Integration # SP Adapters**.
2. In the **SP Adapters** window, choose from the following options.

| Option  | Description  |
|---|--|
| <b>Configure a new instance</b>               | Click <b>Create New Instance</b>   |
| <b>Modify an existing instance</b>            | Click the name of instance in the <b>Instance Name</b> column              |
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |



#### Important:

After installing new adapter program files, you might be required to make additional configuration changes in areas such as adapter instances and connections as prompted by the administrative console.



#### Note:

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

## Creating an SP adapter instance

The first step in creating an adapter instance is choosing an adapter type.

### Steps

1. Go to **Applications # Integration # SP Adapters**.
2. On the **SP Adapters** window, click **Create New Instance**.

3. On the **Type** tab, configure the basics of this adapter instance:
  - a. Enter the **Instance Name** and **Instance ID**.
  - b. In the **Type** list, select the adapter type.
  - c. Optional: In the **Parent Instance** list, select an existing type.

If you are creating an instance that is similar to an existing instance, consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.

4. Click **Next**.

### Configuring an SP adapter instance

You are presented with different configuration parameters depending on the type of adapter that you selected.

About this task

Steps

- If this is a child instance, select the override check box to modify the configuration.
- If you are configuring an instance of the OpenToken SP Adapter, see [Configuring an OpenToken SP Adapter instance](#) on page 348 for configuration information.
- If you are configuring an adapter from an integration kit (including any SaaS connector), use the information in [Integration overview](#) on page 65 to configure the adapter instance.

### Invoking SP adapter actions

Adapters can perform configuration assistance or validation actions; for example, testing a connection to an LDAP server. Actions may also include generation of parameters that might need to be set manually in a configuration file.

Steps

- On the **Actions** tab, complete any actions required, and click **Next**.

### Extending an SP adapter contract

You can configure adapters with an option allowing administrators to add to the attributes required for creating usable sessions.

About this task

This feature might be needed by a legacy application that requires different authentication than other applications under the same enterprise identity-management system.



#### Note:

If this is a child instance, select the **Override** check box to modify the configuration.

Steps

1. On the **Extended Contract** tab, enter the name of an attribute and click **Add**.  
Repeat this step as needed to add another attribute.
2. Click **Next**.

### Identifying the target application

On the **Target App Info** tab, you can enter the name of the target application and the URL of the application icon.

About this task

The URL is accessible through the IdP Adapter interface, `IdpAuthenticationAdapterV2`, in the PingFederate Java SDK. For more information about the SDK, see [SDK Developer's Guide](#) on page 1115. Both fields are optional.



#### Note:

If this is a child instance, select the **Override** check box to modify the configuration.

Steps

1. Optional: Enter the application name in the **Application Name** field.
2. Optional: Enter the URL to the application icon in the **Application Icon URL** field.
3. Click **Next**.

### Reviewing an SP adapter configuration

You can review your SP adapter settings before completing the configuration.

Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

### Configuring target URL mapping

When you have more than one target session defined in an identity provider (IdP) connection, you must map the target URL to its target session.

About this task

When PingFederate receives a single sign-on (SSO) or single logout (SLO) request, it compares the target URL against the configured URLs until a match is found. If a match is not found, the SSO request fails.



#### Important:

For target URL mapping to work correctly, you must configure a target resource entry in the **Security # System Integration # Redirect Validation** settings. If you have not done this, follow the instructions in [Configuring redirect validation](#) on page 694.

For example, this mapping configuration might be necessary in an IdP-initiated SSO scenario that connects to multiple applications at your site. For transactions initiated at your site, this mapping is required for default situations where the target resource and the adapter instance are not specified in the SSO or SLO request. When this information is provided with the service provider (SP) request, the mapping table is ignored. For more information, see [SP services](#) on page 1256.

When bridging an identity provider to multiple service providers, for each service provider supporting the SAML IdP-initiated SSO profile, map the target URLs to the corresponding SP connection.



#### Tip:

In this scenario, PingFederate is a federation hub for the identity provider and the service providers. For more information, see [Federation hub use cases](#) on page 108.

Finally, if an IdP connection is associated with one or more SP adapters, authentication policy contracts, or both, you also need to map the target URLs to their respective target session.

You manage target URL mappings on the **Applications # Integration # Target URL Mapping** window. The configuration process involves entering a URL and select a target session for it. See the following table for more information.

The order of mapping is significant in that the first matching mapping, from top to bottom, determines which target session receives the request. For example, if two URLs are mapped in the following order.

| URL                                     | Session Target                                       |
|---|--|
| http://<br>www.example.com/<br>acct101/ | <b>OpenToken SP Adapter to an local training app</b> |
| http://<br>www.example.com/*            | <b>SP connection to SP SaaS</b>                      |

A target URL of `http://www.example.com/acct101/` will be mapped to **OpenToken SP Adapter to an local training app** because the target matches the first mapping in the configuration.

If the order of the mappings is reversed, the same target will be mapped to **SP connection to ACME SaaS** because the first mapping in the new configuration, `http://www.example.com/*`, matches the target URL.

## Steps

1. Enter a URL.

The target URLs that align with your configured target sessions. The URLs instruct the PingFederate SP server to route session-creation processing through an SP adapter instance or an SP connection.

You can use a wildcard (\*) to match multiple URLs to the same target session but you can use only one wildcard (\*) per URL.

If the target URL in the incoming request is not matched by the first entry in this table, subsequent entries are tried until a match is found.



### Note:

PingFederate tries the next entry if a target session is not allowed based on restrictions imposed. For more information, see [Restricting a target session to certain virtual server IDs](#) on page 741.

2. Select a target type from the list.

You can only select a target type from the list when the IdP role is activated with at least one protocol for browser-based SSO.

If the IdP role is not activated or is activated without any protocol for browser-based SSO, such as SAML or WS-Federation, the **Target Type** value defaults to **SP Adapter**.

3. Select a target session from the list.

The available values depends on the chosen the **Target Type** list.

4. Click **Add Mapping**.

5. Repeat these steps to add multiple mappings.

### Next steps

Use the up and down arrows to re-arrange the order of the mappings. Click **Edit**, **Update**, **Cancel** to make or undo a change to a mapping. Click **Delete** and **Undelete** to remove a mapping or cancel the removal request.

### Configuring Identity Store Provisioners

PingFederate allows you to create custom identity store provisioners to bridge the inbound system for cross-domain identity management (SCIM) processing of PingFederate to your own user store. For example, you might need to create a custom identity store provisioner that works with an application-specific user database schema.

Using the SDK for PingFederate, you can create and test these custom identity store provisioners. For more information, see the PingFederate [SDK Developer's Guide](#) on page 1115.

To support custom attributes, you must add the schema extension and the custom attributes to the identity provider (IdP) connection. Furthermore, you need to take the expected data structure of the custom attributes into consideration when implementing the `IdentityStoreProvisioner` interface and its methods. In other words, your methods must be able to create, read, update, and delete/deactivate the custom attributes and their sub-attributes if the custom attributes are complex attributes to and from your user store. For more information about custom attributes, complex attributes, and other attribute types, see [Defining custom SCIM attributes](#) on page 777 and [SCIM 1.1 Core Schema](#).



#### Note:

The identity store provisioner option is active only after you enable **Inbound Provisioning**.



#### Note:

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

### Creating an Identity Store Provisioner instance

On the **Type** tab, you begin creating an instance of an identity store that PingFederate uses to bridge the inbound System for Cross-domain Identity Management (SCIM) processing to an external user store using a custom implementation.

#### Steps

1. Go to **System # Data & Credential Stores # Identity Store Provisioners**.
2. Click **Create New Instance**.
3. On the **Type** tab, enter the a name and an ID in the **Instance Name** and **Instance ID** fields.
4. From the **Type** list, select a provisioner type.  
Available provisioner types are limited to those that are currently installed on your server.
5. Optional: Select a parent instance from the **Parent Instance** list.  
If you are creating an instance that is similar to an existing instance, you might consider making it a child instance by specifying a parent. A child instance inherits the configuration of its parent unless overridden. You can specify overrides during the rest of the setup.
6. Click **Next**.

### Defining the Identity Store Provisioner behavior

Different configuration parameters are available on the **Identity Store Provisioner** tab. These options are controlled by the provisioner plugin software (for more information, see topics about the Identity Store Provisioner interfaces in the [SDK Developer's Guide](#) on page 1115).

#### Steps

1. Configure the options as needed.
2. Click **Next**.

### Extending the Identity Store Provisioner contract

Identity Store Provisioners can be written with an option allowing administrators to add to the core attributes the plugin instance requires.

#### About this task

Both the core and extended contract attributes you define must be mapped when you configure Write Users within an inbound provisioning connection.



#### Tip:

To keep your plugin flexible across multiple connections, assuming a one-to-one connection-to-identity store provider setup, you might want to hard code a set of core attributes for all connections to fulfill, and then extend attributes on as needed when a partner connection depends on additional attributes.




#### Note:

If this is a child instance, select the override check box to modify the configuration.

#### Steps

1. On the **Extended Contract** tab, create and modify attributes as needed.

| Option                          | Action  |
|---------------------------------|---|
| <b>Add an attribute</b>         | Enter the attribute name in the text box and click <b>Add</b> .   |
| <b>Modify an attribute name</b> | <ol style="list-style-type: none"> <li>a. Click <b>Edit</b> under <b>Action</b> for the attribute.</li> <li>b. Make the change and click <b>Update</b>.</li> </ol> <div style="margin-top: 10px;">  <b>Note:</b><br/>           If you change your mind, click <b>Cancel</b> under <b>Action</b>.         </div> |
| <b>Delete an attribute</b>      | Click <b>Delete</b> under <b>Action</b> for the attribute.  |

2. Click **Next**.

## Extending the Identity Store Provisioner contract for groups

Identity Store Provisioners can be written with an option allowing administrators to add to the core group attributes the plugin instance requires.

About this task

Both the core and extended group attributes that you define must be mapped when you configure Write Groups within an inbound provisioning connection.



### Tip:

To keep your plugin flexible across multiple connections, assuming a one-to-one connection-to-identity store provider setup, you might want to hard code a set of core attributes for all connections to fulfill, and then extend attributes on as needed when a partner connection depends on additional attributes.



### Note:

If this is a child instance, select the override check box to modify the configuration.

Steps

1. On the **Extended Group Contract** tab, create and modify attributes as needed.

| Option                          | Action  |
|---------------------------------|---|
| <b>Add an attribute</b>         | Enter the attribute name in the text box and click <b>Add</b> .   |
| <b>Modify an attribute name</b> | <ol style="list-style-type: none"> <li>a. Click <b>Edit</b> under <b>Action</b> for the attribute.</li> <li>b. Make the change and click <b>Update</b></li> </ol> |
|                                 | <b>Note:</b><br>If you change your mind,click <b>Cancel</b> under <b>Action</b> .   |
| <b>Delete an attribute</b>      | Click <b>Delete</b> under <b>Action</b> for the attribute.  |

2. Click **Next**.

## Reviewing the Identity Store Provisioner configuration

On the **Summary** tab, review your Identity Store Provisioner configuration.

Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## Configuring default URLs

As a service provider (SP), you can supply a default URL that the end-user might see when a single sign-on (SSO) request succeeds, that is, a session is created at your site, but the target resource is not available or not specified.

To configure default URLs, go to **Applications # Integration # SP Default URLs**.

**Note:**

You can also specify default target SSO URLs for individual identity provider (IdP) connections, which take precedence over this global setting. For more information, see [Configuring default target URLs](#) on page 758.

Similarly, you can specify to prompt a default URL indicating a successful single logout (SLO) to the end-user if no other page is designated.

**Note:**

The error message is displayed only when the application calling the start-SSO endpoint does not explicitly provide its own error page URL. The default entry in this field is used to localize the message. For information about how to find and change the default English message and how use the PingFederate localization feature, see [Localizing messages for end users](#) on page 889. If localization is not needed, you can also specify a message directly in this field to change the default.

Your application or your partner's application can supply these URLs at runtime (see [SP services](#) on page 1256). However, if none are provided, PingFederate uses the default values you enter on this window unless, in the case of SSO, a default is also defined for the connection.

**Tip:**

If no default targets are specified here or at the connection level (for SSO), PingFederate provides built-in landing pages for the user. These web pages are is among the templates you can modify with your own branding or other information. For more information, [Customizable user-facing pages](#) on page 869.

**Viewing SP application endpoints**

Web-application developers at your site need to know the application endpoints to initiate transactions through PingFederate.

Go to **Help # SP Application Endpoints** to see a list of endpoints and descriptions applicable to your federation role.

**Note:**

These endpoints are built into PingFederate and cannot be changed.

For specific parameters required or allowed for these endpoints, see [SP services](#) on page 1256 and [System-services endpoints](#) on page 1269.

**Federation settings**

If your identity federation uses the SAML 2.0 X.509 attribute sharing profile (XASP), you might need to identify the identity provider (IdP) connection to which an attribute request applies.

If so, use the **System # Protocol Metadata # Attribute Requester Mapping** window to complete the configuration. For more information, see [Attribute Query and XASP](#) and [Managing attribute requester mappings](#) on page 721.

View endpoints that your federation partners need to know to access your services from the **Help** menu.



## Managing attribute requester mappings

If you are using the SAML 2.0 X.509 attribute sharing profile (XASP), applications at your site must supply the subject distinguished name (DN) to identify a user's X.509 authentication certificate.

About this task

Optionally, an application can also supply an issuer DN, which can be used to determine the correct identity provider (IdP) attribute authority to use for a set of users associated with an IdP. For more information, see [Attribute Query and XASP](#) on page 49.



### Note:

You must set the **Format** query parameter to a specified value for XASP. For more information, see [SP services](#) on page 1256.

You can map X.509 identifying information to connections and specify a default connection on the **System # Protocol Metadata # Attribute Requester Mapping** window.

At runtime, the issuer DN, if supplied, is evaluated against the entries under **Issuer DN Pattern** in hierarchical order until a match is found. If a match is found, the corresponding IdP connection is selected to issue a response to the attribute query request. If the issuer DN matches no entry or if it is not provided, the subject DN from the request is compared against the entries under **Subject DN Pattern** in a similar manner. If the subject DN matches no entry, then the default IdP connection is used.

You can use a regular expression to match different DNs to the same connection. Only one expression can be used in any single entry. DN values must be entered in all lower-case characters.

Steps

1. Map one or more issuer DNs to SAML 2.0 IdP connections, as needed.
  - a. Enter an issuer DN under **Issuer DN Pattern**.
  - b. Select an IdP connection under **IdP Connection Name**.
  - c. Click **Add**.
  - d. Repeat these steps to add more entries.
2. Map one or more subject DNs to SAML 2.0 IdP connections, as needed.
  - a. Enter a subject DN under **Subject DN Pattern**.
  - b. Select an IdP connection under **IdP Connection Name**.
  - c. Click **Add**.
  - d. Repeat these steps to add more entries.
3. Select a default IdP connection from the list.

Next steps

You can click **Edit**, **Update**, and **Cancel** to make or undo a change to an entry. Click **Delete** and **Undelete** to remove an entry or cancel the removal request.

## Viewing SP protocol endpoints



Your federation partners or security token service (STS) clients need to know the applicable service provider (SP) services endpoints to communicate with your PingFederate server. Configured service endpoints for SAML connections are included in metadata export files.

Go to **Help # SP Endpoints** to see a list of applicable OpenID Connect, SAML, WS-Federation, and WS-Trust STS endpoints. A pop-up window displays only those endpoints related to the federation protocols enabled on the **System # Server # Protocol Settings # Federation Info** tab. These endpoints are built into PingFederate and cannot be changed.

PingFederate provides a favorite icon for all protocol endpoints. For more information, see [Customizing the favicon for application and protocol endpoints](#) on page 908.

The table below describes each endpoint.

| Service  | URL and Description   |
|--|---|
| Third Party Initiated Login (OpenID Connect 1.0) | <p><code>/sp/init_login.ping</code></p> <p>The URL that receives and processes login requests initiated by an OpenID Provider (OP) or another party. This protocol endpoint supports HTTP GET and POST methods and the following parameters:</p> <ul style="list-style-type: none"> <li>▪ <b>iss</b>: the Issuer Identifier of the OP, to which sends the authentication requests.<br/>This parameter is always required.</li> <li>▪ <b>target_link_url</b>: the destination of the request after authentication.<br/>This parameter is required if no default target URL is specified in the SP configuration or the IdP connection. If specified, the parameter value always overrides the default target URL.</li> <li>▪ <b>login_hint</b>: a hint to the OP about the end user.<br/>This parameter is optional.</li> </ul> <p>If your use case supports a generic login, you can add the <b>login_hint</b> parameter with a default value to the IdP connection on the <b>OpenID Provider Info</b> window. Furthermore, you may select the check box under <b>Application Endpoint Override</b> so that the application can optionally override the login hint value by including the <b>login_hint</b> parameter in the URL.</p> <p>Other parameters if any are not sent to the OP unless they are defined with a default value (or default values) in the IdP connection. For more information, see .</p> <p>For more information about Third Party Initiated Login flow, see the OpenID Connect specification.</p> |
| Single Logout Service (SAML 2.0)                 | <p><code>/sp/SLO.saml2</code></p> <p>The URL that receives and processes logout requests and responses.</p>   |
| Assertion Consumer Service (SAML 2.0)            | <p><code>/sp/ACS.saml2</code></p> <p>A SAML 2.0 implementation that receives and processes assertions from an IdP. The numbers reflect the index value uses to handle each binding.</p>   |
| Artifact Resolution Service (SAML 2.0)           | <p><code>/sp/ARS.ssaml2</code></p> <p>The SOAP endpoint that processes artifacts returned from a federation partner to retrieve the referenced XML message on the back channel. See the note at the end of this table.</p>  |
| Assertion Consumer Service (SAML 1.x)            | <p><code>/sp/acs.saml1</code></p> <p>A SAML 1.x implementation URL that receives and processes assertions from an IdP.</p>  |
| Single Sign-on Service (WS-Federation)           | <p><code>/sp/prp.wsf</code></p> <p>The WS-Federation implementation URL that receives and processes security tokens and SLO messages.</p>   |

| Service  | URL and Description   |
|--|---|
| WS-Trust STS (two endpoints)   | <p><code>/sp/sts.wst</code></p> <p>The SOAP endpoint that receives and processes SAML security-token requests from STS clients (web service providers at the SP site), validating SAML tokens or validating and exchanging SAML tokens based on the configured IdP connection.</p> <p><code>/pf/sts.wst</code></p> <p>Initiates direct STS token-to-token exchange and token validation, from an IdP token processor to an SP token generator, when that feature is configured. For more information, see .</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>If you configure multiple token-generator instances of the same type for the connection or token-to-token mapping, a query parameter, <b>TokenGeneratorId</b>, must be added to either of these endpoints. For more information, see .</p> </div> <p>See the note at the end of this table.</p> |
| <p> <b>Important:</b></p> <p>If mutual SSL/TLS is used for authentication, you must configure a secondary listening partner for use by partners or STS clients for the relevant endpoints such as <code>*.ssaml*</code> and <code>*.wst</code>. For more information, see .</p> |   |

#### Virtual server ID support

For SAML connections using multiple virtual server IDs, each virtual server ID has its own set of protocol endpoints. For more information, see [Multiple virtual server IDs](#) on page 115. You can export a connection metadata for your partner on the **System # Protocol Metadata # Metadata Export** window. For more information, see [Exporting connection-specific SAML metadata](#) on page 932.

For WS-Federation and SAML connections using multiple virtual server IDs, you can provide your partner the federation metadata endpoint (`/pf/federation_metadata.ping`) with the **PartnerIdpId** and **vsid** parameters. See the table below for an example.

| Partner's entity ID | Your virtual server ID | Federation metadata URL  |
|---------------------|------------------------|--|
| SP                  | idev1                  | <code>https://www.example.com/pf/sts_mex.ping?PartnerIdpId=IdP&amp;vsid=idev1</code> |
|                     | idev2                  | <code>https://www.example.com/pf/sts_mex.ping?PartnerIdpId=IdP&amp;vsid=idev2</code> |

In this example, the base URL and the runtime port of your PingFederate server are `www.example.com` and `443`, respectively.

The federation metadata endpoint returns information that is specific for a given virtual server ID when the request includes the **vsid** parameter.

For WS-Trust STS, you can provide your partner the STS metadata endpoint (`/pf/sts_mex.ping`) with the `PartnerIdpId` and `vsid` parameters. The STS metadata endpoint returns information that is specific for a given virtual server ID when the STS metadata request includes the `vsid` parameter.

For more information about these metadata endpoints, see [System-services endpoints](#) on page 1269.

The virtual server ID concept does not apply to the `/pf/sts.wst` endpoint because token-to-token exchange does not involve any connections. As needed, you can pass the token-to-token endpoint to your partners as-is.

## Managing IdP connections

As a service provider (SP) site, you can manage connection settings to support the exchange of federation-protocol messages, such as OpenID Connect, SAML, WS-Federation, or WS-Trust, with an identity provider (IdP), OAuth client, OpenID Provider (OP), or security token service (STS) client application at your site.

These settings include:

- User attributes that you expect to receive in an SSO token such as a SAML assertion or WS-Trust STS SAML token.
- User attributes that you expect the OP to return in an ID token or through its user information, UserInfo, endpoint on-demand.
- User attributes that may be requested using the SAML Attribute Query profile if that profile is used.
- The protocol, profiles, and bindings of the connection, including detailed security specifications such as the use of back-channel authentication, digital signatures, signature verification, and XML encryption.

To establish a connection, you and your partner must have decided this information in advance. For more information, see .

As an SP site, you respond to user requests for single sign-on (SSO) and single logout (SLO) by creating or closing user sessions, respectively, in local applications. You integrate these applications with PingFederate by configuring them with SP adapter instances. Furthermore, in preparation for configuring a new SSO connection, you need to know which adapter instance or authentication policy contract to use. For more information, see [Managing target session mappings](#) on page 739.

No adapter instance or authentication policy contract is required for a connection that uses only the Attribute Query profile. For more information, see [Manage the Attribute Query profile in an IdP connection](#) on page 762.

If you intend to pass attribute values to an adapter instance from a local datastore, you must define the datastore during this configuration. If you have not done so already, see [Datastores](#) on page 936.

### Administrative interface

You manage connection settings in the **Authentication # Integration # IdP Connections** window, which organizes the settings into a series of primary tasks. Some primary tasks have one or more levels of sub tasks. Each primary or sub task has its own tab, where you manage one or more settings. You can move to a sibling task using the **Next** or **Previous** button. If you are on a sub task, you can also move to its parent task using the **Done** button.

When creating a new connection, you can save your progress using the **Save Draft** button. Note that not all tabs offer this option. When you reach the **Activation & Summary** tab, you must click **Save** to complete the new connection.

When editing an existing connection, you can make changes and then click **Save** to commit your changes. In other words, you are not required to step through all tabs to reach the **Activation & Summary** tab before you can save your changes.



#### Note:

The **Save** button is available on most tabs. If a tab does not show a **Save** button, click **Next** or **Done** until you reach to a tab where you can use the **Save** button to commit your changes.

### Accessing IdP connections

In the **IdP Connections** window, you can create or import a connection, or edit a recently modified connection by clicking on its connection name.

About this task

The **IdP Connections** window displays 20 connections at a time. As needed, use the pagination controls to navigate through the rest of your connections. You can also search connections by their names or connection IDs.



#### Tip:


A connection is included in the search results so long as its name or ID is a partial, case-insensitive match to a search term.

You can sort by connection name, partner connection ID, and default virtual server ID; narrow by protocol and status; and perform various connection-related tasks.

Steps

Go to the **Authentication # Integration # IdP Connections**.

| Choice                     | Action   |
|----------------------------|--|
| <b>Edit a connection</b>   | Select the connection by its name. For the setting you want to change, select the corresponding tab and follow the configuration wizard to complete the task.  |
| <b>Create a connection</b> | Click <b>Create Connection</b> , then follow the configuration wizard to create a new connection to your identity provider (IdP) partner.  |
| <b>Copy a connection</b>   | Click <b>Select action # Copy</b> , then follow the configuration wizard to create a new connection based on an existing (source) connection.<br><br>This is most useful if the new connection and the source connection share many common setting values. |
| <b>Export a connection</b> | Click <b>Select Action # Export Connection</b> , then save the XML file as prompted.<br><br>This is useful in situations where you want to make a backup of a connection prior to making changes to it.  |
| <b>Import a connection</b> | Click <b>Import Connection</b> , then follow the on-screen instructions to complete the task.<br><br>If the connection already exists, you have the option to overwrite the existing connection.   |
|                            | <b>Note:</b>   |

| Choice   | Action   |                 |             |     |   |    |   |
|--|--|-----------------|-------------|-----|---|----|---|
|  | <p>Prior to the import, you can modify the XML file to suit your needs. The XML file can also be imported to another PingFederate environment acting in the same federation role (SP) at your site. The source and the target must run the same version of PingFederate.</p>   |                 |             |     |   |    |   |
| <b>Export metadata for any SAML browser single sign-on (SSO) connection</b>          | <p>Click <b>Select Action # Export Metadata</b>, then follow the on-window instructions to complete the task.</p>  |                 |             |     |   |    |   |
| <b>Update a SAML browser SSO connection</b>  | <p>Click <b>Select Action # Update with Metadata</b>, then follow the on-screen instructions to complete the task.</p> <p>You can update a connection via a metadata XML file or a metadata URL.</p> <div data-bbox="852 758 1468 961" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>The update operation might require additional configuration. Review the connection after the update operation.</p> </div>   |                 |             |     |   |    |   |
| <b>toggle the status of a connection</b>   | <p>Slide the toggle switch to enable or disable a connection.</p>  |                 |             |     |   |    |   |
| <b>remove a connection</b>   | <p>Click <b>Select Action # Delete</b>.</p>  |                 |             |     |   |    |   |
| <b>Override the verbosity of runtime transaction logging for all IdP connections</b> | <p>Click <b>Show Advanced Fields</b> and the select the desired override option.</p> <table border="1" data-bbox="852 1199 1455 1755"> <thead> <tr> <th data-bbox="852 1199 1003 1276">Override option</th> <th data-bbox="1003 1199 1455 1276">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="852 1276 1003 1514">Off</td> <td data-bbox="1003 1276 1455 1514"> <p>Select this option and let the per-connection <b>Logging Mode</b> configuration determine the amount of information PingFederate records in the runtime transaction log.</p> <p>This is the default selection.</p> </td> </tr> <tr> <td data-bbox="852 1514 1003 1755">On</td> <td data-bbox="1003 1514 1455 1755"> <p>Select this option, followed by one of the four logging modes, to set the verbosity of runtime transaction logging for all IdP connections. This is most useful when troubleshooting an issue that affects multiple connections.</p> </td> </tr> </tbody> </table> | Override option | Description | Off | <p>Select this option and let the per-connection <b>Logging Mode</b> configuration determine the amount of information PingFederate records in the runtime transaction log.</p> <p>This is the default selection.</p> | On | <p>Select this option, followed by one of the four logging modes, to set the verbosity of runtime transaction logging for all IdP connections. This is most useful when troubleshooting an issue that affects multiple connections.</p> |
| Override option  | Description  |                 |             |     |   |    |   |
| Off  | <p>Select this option and let the per-connection <b>Logging Mode</b> configuration determine the amount of information PingFederate records in the runtime transaction log.</p> <p>This is the default selection.</p>  |                 |             |     |   |    |   |
| On   | <p>Select this option, followed by one of the four logging modes, to set the verbosity of runtime transaction logging for all IdP connections. This is most useful when troubleshooting an issue that affects multiple connections.</p>  |                 |             |     |   |    |   |
| <b>Turn off automatic multi-connection error checking</b>                            | <p>Click <b>Show Advanced Fields</b> and the select the <b>Disable Automatic Connection Validation</b> check box.</p> <p>This check box is not selected by default.</p>  |                 |             |     |   |    |   |

| Choice                      | Action   |
|-----------------------------|--|
|                             | Once selected or cleared, the state of this setting is reflected on <b>Applications # Integration # SP Connections</b> as well.<br><br>For more information about this advanced setting and its impact, see <a href="#">Configuring automatic connection validation</a> on page 860. |
| <b>Keep your changes</b>    | Click <b>Save</b> .  |
| <b>Discard your changes</b> | Click <b>Cancel</b> .  |

## Resolving IdP connection errors

About this task

automatically validates configured connections before displaying them on the **IdP Connections** window. This validation ensures these connections have not been adversely affected by any subsequent changes in the supporting components, such as an adapter instance or an authentication policy contract.

If errors are found, the administrative console displays a visual cue next to the applicable connections.

Steps

- To resolve the error, select the connection and follow the on-window instructions to modify the configuration, one connection at a time.

## Choosing an IdP connection type

You can use the administrative console to choose an identity provider (IdP) connection type.

About this task

You can indicate on the **Connection Type** tab whether the connection to this partner is for browser single sign-on (SSO), WS-Trust security token service (STS), OAuth, SAML, inbound provisioning, or a combination of them.



### Note:

You can add STS, OAuth, and outbound provisioning support to any existing SSO connection, or vice versa, at any time. However, when OpenID Connect is the chosen protocol for browser SSO, the other types become unavailable.

Select the applicable protocol on the **Connection Type** tab when establishing a new connection.




### Note:

If your partner's deployment also supports multiple protocols and you intend to communicate using more than one, you must set up a separate connection for each protocol. Each connection must use a unique partner connection ID.

## Steps

- On the **Connection Type** tab, indicate the desired type of connection to your partner.

| Choice   | Action  |
|--|---|
| <b>Configure a connection for secure browser-based SSO</b>   | PingFederate[pingfed]<br>Select the <b>Browser SSO Profiles</b> check box and a protocol from the list, if necessary.   |
| <b>Configure an STS connection</b>   | Select the <b>WS-Trust STS</b> check box and the default token type from the list.  |
| <b>Configure a connection that exchanges SAML assertions or JSON web tokens (JWTs) for access tokens</b> | Select the <b>OAuth Assertion Grant</b> check box.  |
|  |  <b>Note:</b><br>The <b>OAuth Assertion Grant</b> option is available only if at least one Access Token Manager instance has been configured on the <b>Applications # OAuth # Access Token Management</b> window<br><br>For more information about these standards, see <a href="#">Security Assertion Markup Language (SAML) 2.0 Profile for OAuth 2.0 Client Authentication and Authorization Grants</a> and <a href="#">JSON Web Token (JWT) Profile for OAuth 2.0 Client Authentication and Authorization Grants</a> . |
| <b>Configure an inbound provisioning connection</b>  | Select the <b>Inbound Provisioning</b> check box and choose to support provisioning of users only ( <b>User Support</b> ) or users and groups ( <b>User and Group Support</b> ). For groups, nested group membership, if any, is preserved.   |

- Optional: If your PingFederate license manages connections by groups, you can select a group for this connection.  
This option is not displayed for unrestricted or other types of licenses.

**Choosing IdP connection options**

On the **Connection Options** tab, shown only for browser-based single sign-on (SSO) connections, you can enable browser-based SSO in conjunction with Just-in-Time (JIT) provisioning. Additionally, you can also choose to map user attributes for persistent grants used by the optional PingFederate OAuth authorization server.

About this task

For SAML 2.0, you can configure the **Attribute Query** profile with or without the browser-based SSO.

## Steps

- On the **Connection Options** tab, make the appropriate selections for your configuration.

| Choice  | Action   |
|---|--|
| <b>Create a connection for browser-based SSO.</b>                 | Select the <b>Browser SSO</b> check box.   |
| <b>Enable JIT provisioning, OAuth attribute mapping, or both.</b> | Select the appropriate check box after selecting the <b>Browser SSO</b> check box. |



| Choice   | Action   |
|--|--|
| <b>Create a connection to facilitate the SAML 2.0 Attribute Query profile.</b> | Select the <b>Attribute Query</b> check box. For more information, see <a href="#">Attribute Query and XASP</a> on page 49 |

### Importing IdP metadata

You can use the PingFederate administrative console to import and update identity provider (IdP) metadata.

#### About this task

If you are using one of the SAML protocols without a connection template, you can expedite the setup by one of the following actions:

- Import a metadata file
- Select a metadata URL

When you select a metadata URL, also enables the automatic update option and checks the metadata periodically. If detects changes in the partner's signing certificates for digital signature verification, encryption key, or contact information, it updates the connection automatically. For better housekeeping, the update process removes verification certificates from the connection when the partner no longer maintains them in its metadata. In a clustered environment, automatically replicates verification certificates and encryption key changes to all engine nodes. Offline engine nodes will also consume these changes as they restart and rejoin the cluster. If you prefer to update the connection manually, you can clear the **Enable Automatic Reloading** check box.

You can configure reload frequency at **System # Protocol Metadata # Metadata Settings # Metadata Lifetime** tab. The default reload frequency is daily.

We recommend you turn on notifications for SAML metadata update events at **System # Monitoring & Notifications # Runtime Notifications**.



#### Note:

The notification message provides a list of the applicable items if the metadata contains changes that require additional configuration.

After creating the connection, you can add, remove, or change the metadata URL associated with the connection in the **Metadata URL** tab. In addition, you can toggle the **Enable Automatic Reloading** check box for the connection.







#### Tip:



Using a metadata URL with automatic reloading streamlines the configuration process. For example, you can quickly establish a browser SSO connection to an InCommon-participating partner. For more information, see [www.incommon.org/participants](http://www.incommon.org/participants).

### Steps

1. Select from one of the following steps to import or update metadata.

| Metadata medium      | Steps  |
|----------------------|--|
| <b>Metadata file</b> | a. On the <b>Import Metadata</b> tab, select the <b>File</b> option. |

| Metadata medium | Steps  |
|-----------------|--|
|                 | <p>b. Choose the metadata file, and then click <b>Next</b>.</p> <div data-bbox="917 283 1469 493" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If the metadata contains multiple entries, select the desired partner from the <b>Select Entity ID</b> list and click <b>Next</b>.</p> </div> <div data-bbox="917 504 1469 766" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If the metadata file is digitally signed but the verification certificate is provided outside of the metadata, import the metadata verification certificate on the <b>Import Certificate</b> tab, and then click <b>Next</b>.</p> </div> <p>c. On the <b>Metadata Summary</b> tab, review the signature information to evaluate the authenticity of the metadata.</p>  |
| Metadata URL    | <p>a. On the <b>Import Metadata</b> tab, select the <b>URL</b> option.</p> <p>b. Select the metadata from the <b>Metadata URL</b> list.</p> <div data-bbox="917 1050 1469 1291" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>If the metadata you want is not shown in the list, click <b>Manage Partner Metadata URLs</b>. For more information, see <a href="#">Manage Partner metadata URLs</a> on page 688.</p> </div> <p>c. Optionally, clear the <b>Enable Automatic Reloading</b> check box to disable automatic update.</p> <div data-bbox="917 1407 1469 1701" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>A warning will display if you do not have runtime notifications enabled. To enable these notifications, go to <b>System # Monitoring &amp; Notifications # Runtime Notifications</b> and select the <b>Notification for SAML Metadata Update Events</b> box.</p> </div> |

| Metadata medium | Steps   |
|-----------------|---|
|                 | <p>d. Click <b>Load Metadata</b>.</p> <div data-bbox="917 247 1466 457" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>If the metadata contains multiple entries, select the desired partner from the <b>Select Entity ID</b> list and click <b>Next</b>.</p> </div> <div data-bbox="917 472 1466 672" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>If there is a digital signature error, click <b>Manage Partner Metadata URLs</b> to resolve the issue.</p> </div> |

2. Click **Next**.

### Identifying the partner

When creating an identity provider (IdP) connection, you must identify your partner and provide basic information about them.

#### About this task

On the **General Info** tab, you provide your partner's unique federation identifier, the display name of the connection, and some other optional information, such as virtual server IDs, contact information, and logging mode for runtime transaction logging.


In addition, on this tab you can define a default error message that end users see in the event that single sign-on (SSO) fails.

#### Steps

1. Provide the basic information to identify your partner.

See the following table for more information.

| Field  | Description  |
|--|--|
| <p><b>Partner's Entity ID, Issuer, Partner's Realm, or Connection ID</b></p> <p>(Required)</p> | <p>The published, protocol-dependent, unique identifier of your partner.</p> <p>For a SAML 2.0 connection, this is your partner's SAML Entity ID. For a SAML 1.x connection, this is the audience your partner advertises. This ID might have been obtained out-of-band or through a SAML metadata file.</p> <p>For a WS-Federation connection, this is your partner's Realm.</p> <p>For an OpenID Connect connection, this is the Issuer Identifier of the OpenID Provider (OP).</p> <p>For a security token service (STS)-only connection, this ID can be any unique identifier.</p> |

| Field   | Description  |
|---|--|
| <b>Enable Additional Issuers</b><br>(Applicable only to OpenID Connect connection)                | <p>When selected, PingFederate takes into consideration additional issuers when validating ID tokens obtained through this connection.</p> <div style="border: 1px solid black; padding: 5px; margin: 5px 0;">  <b>Tip:</b><br/>           Enable this option if you want to support multi-tenant OpenID providers, such as Microsoft Azure AD.         </div> <p>This check box is not selected by default.</p> <p>Issuer information is defined on the <b>Additional Issuers</b> tab.</p> |
| <b>Connection Name</b><br>(Required)  | <p>A plain-language identifier for the connection: for example, a company or department name. This name is displayed in the connection list on the administrative console.</p>   |
| <b>Virtual Server IDs</b><br>(Not applicable to OpenID Connect connections)                       | <p>If you want to identify your server to this connection partner using an ID other than the one you specified on the <b>Federation Info</b> tab, enter a virtual server ID in this field and click <b>Add</b>.</p> <p>Enter additional virtual server IDs as needed.</p>  |
| <b>Client ID and Client Secret</b><br>(Applicable to and required for OpenID Connect connections) | <p>The client ID and the client secret to communicate with the OP.</p> <p>This client represents and is created and managed at the OP. For more information, see the documentation provided by the OP.</p>   |
| <b>Base URL</b>   | <p>The fully qualified hostname and port on which your partner's federation deployment runs (for example, <code>https://www.example.com:9031</code>). This entry is an optional convenience, allowing you to enter relative paths to specific endpoints, instead of full URLs, during the configuration process.</p>   |
| <b>Company</b>  | <p>The name of the partner company to which you are connecting.</p>  |
| <b>Contact Name</b>   | <p>The contact person at the partner company.</p>  |
| <b>Contact Number</b>   | <p>The phone number of the contact person at the partner company.</p>  |
| <b>Contact Email</b>  | <p>The email address for the contact person at the partner company.</p>  |
| <b>Error Message</b><br>(Applicable only to SAML or OpenID Connect connections)                   | <p>If an error occurs on this server, the end user's browser might be redirected in a default situation to an error page hosted within PingFederate.</p> <p>The default entry <code>errorDetail.spSsoFailure</code> is a variable from the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/language-packs/pingfederate-messages.properties</code> file, which is part of the PingFederate localization framework. If localization is not needed, you can also specify a message directly in this field to change the default.</p>                                  |
| <b>Logging Mode</b>   | <p>The level of transaction logging applicable for this connection.</p> <p>The default selection is <b>Standard</b>.</p>   |

If the OP supports the OpenID Connect Discovery specification, the connection setup is expedited by loading the metadata from the OP. Based on the discovery specification, makes a direct HTTP GET request to the `/.well-known/openid-configuration` endpoint at the OP and populates the

attribute contract and the protocol settings of the connection automatically. Manual adjustments can be made during the connection setup or at a later time.

Additionally, you can refresh the protocol settings by reloading the metadata from the OP at any time. If additional claims are supported, adds them to the attribute contract, so that they can be mapped to the target applications later. In the event that the previously supported claims have been dropped by the OP from the metadata, they remain in the attribute contract. While the existing mapping configuration might not be adversely affected, runtime errors might occur if certain attributes are no longer available to the target applications. If runtime errors occur, review the server log and modify the mapping configuration accordingly.

2. Optional: Click **Load Metadata**.

This step is not applicable to an STS-only connection.

### Populating extended property values for IdP connections

Add, remove, or update extended property values.

#### Steps

Optional: On the **System** tab, add, remove, or update one or more values for any extended properties defined in **System # Server # Extended Properties**.



#### Note:

Any values defined for these extended properties will be passed to all applicable velocity templates and as a request context parameter in the authentication API.

Extended property values can serve as metadata. They can also help drive authentication requirements. For more information, see [Extended properties](#) on page 929.

### Defining additional issuers

You can define additional issuers when creating an identity provider (IdP) connection.

#### About this task

On the **Additional Issuers** tab, define additional issuers that PingFederate can accept when validating ID tokens obtained through this connection. This tab appears only when the **Enable Additional Issuers** check box on the **General Info** tab is selected.

#### Steps

1. Go to the **Additional Issuers** tab.
2. Optional: Select the **Accept All Issuers (Not Recommended)** check box if you want PingFederate to accept any issuers when validating ID tokens obtained through this connection.



#### CAUTION:

As suggested by the property name, we do not recommend accepting any issuers.

This check box is not selected by default.

### 3. Optional: Define additional issuers.

Applicable only when the **Accept All Issuers (Not Recommended)** check box is not selected.

- a. Enter the issuer under **Additional Issuer**.
- b. Optional: Enter information about the issuer under **Description**.

The **Primary Issuer** field represents the issuer defined on the **General Info** tab and is always accepted.

### Configure SP Browser SSO

PingFederate supports multiple configurations for browser single sign-on (SSO) with different federation standards. You can configure these options from the **Browser SSO** tab.

Browser single sign-on (SSO) relies on a user's web browser and HTTP requests to broker identity-federation messaging in XML or JSON web tokens (JWT) between an identity provider (IdP) and a service provider (SP). In contrast, WS-Trust security token service (STS) messaging is typically application-driven across the back channel and does not require browser mediation.



#### Tip:

Many steps involved in setting up a federation connection are protocol-independent; that is, they are required steps for all connections, regardless of the associated standards. For more information, see [Federation roles](#) on page 35. Also, for any given connection, some configuration steps are required under the applicable protocol, while others are optional. Still others are required only based on certain selections. The administrative console determines the required and optional steps based on the protocol and dynamically presents additional requirements or options based on selections.

The following sections provide sequential information about every step you might encounter while configuring browser-based SSO, regardless of the protocol you are using for a particular connection.

### SAML 2.0 configuration steps

- [Selecting SAML profiles](#) on page 735
- [Configuring user-session creation](#) on page 736
  - [Choosing an identity mapping method for SP SSO](#) on page 736
  - [Defining an attribute contract](#) on page 737
  - [Managing target session mappings](#) on page 739
- [Configuring protocol settings](#) on page 748
  - [Specifying SSO service URLs \(SAML\)](#) on page 749
  - [Defining SLO service URLs \(SAML 2.0\)](#) on page 751
  - [Selecting allowable SAML bindings \(SAML\)](#) on page 751
  - [Specifying an artifact lifetime \(SAML 2.0\)](#) on page 752
  - [Defining artifact resolver locations \(SAML\)](#) on page 752
  - [Configuring default target URLs](#) on page 758
  - [Overriding authentication context in an IdP connection](#) on page 759
  - [Configuring signature policy](#) on page 760
  - [Specifying XML encryption policy \(for SAML 2.0\)](#) on page 760

### SAML 1.x configuration steps

- [Selecting SAML profiles](#) on page 735

- [Configuring user-session creation](#) on page 736
  - [Choosing an identity mapping method for SP SSO](#) on page 736
  - [Defining an attribute contract](#) on page 737
  - [Managing target session mappings](#) on page 739
- [Configuring protocol settings](#) on page 748
  - [Specifying SSO service URLs \(SAML\)](#) on page 749
  - [Selecting allowable SAML bindings \(SAML\)](#) on page 751
  - [Defining artifact resolver locations \(SAML\)](#) on page 752
  - [Configuring default target URLs](#) on page 758
  - [Configuring signature policy](#) on page 760

#### WS-Federation configuration steps

- [Configuring user-session creation](#) on page 736
  - [Choosing an identity mapping method for SP SSO](#) on page 736
  - [Defining an attribute contract](#) on page 737
  - [Managing target session mappings](#) on page 739
- [Configuring protocol settings](#) on page 748
  - [Specifying a service URL \(WS-Federation\)](#) on page 749
  - [Configuring default target URLs](#) on page 758
  - [Configuring signature policy](#) on page 760

#### OpenID Connect configuration steps

- [Configuring user-session creation](#) on page 736
  - [Choosing an identity mapping method for SP SSO](#) on page 736
  - [Defining an attribute contract](#) on page 737
  - [Managing target session mappings](#) on page 739
- [Configuring protocol settings](#) on page 748
  - [Configuring OpenID Provider information](#) on page 754
  - [Configuring default target URLs](#) on page 758
  - [Overriding authentication context in an IdP connection](#) on page 759

After configuring SSO settings, you will need to configure authentication credentials, the range of which depends on your SSO selections. For more information, see [Configuring security credentials](#) on page 796. Also, other configuration tasks might remain to be configured for new or modified connections, depending on the selected options on the **Connection Options** tab.

#### Selecting SAML profiles

A SAML profile is the message-interchange scenario that you and your federation partner agree to use. It defines the settings that support SAML usage for applications.

#### About this task

For SAML 2.0, PingFederate supports all identity provider (IdP) and service provider (SP)-initiated single sign-on (SSO) and single logout (SLO) profiles. For SAML 1.x, PingFederate supports both the standard IdP-initiated SSO profile and a proprietary "destination-first" SP-initiated SSO profile.



#### Note:

When configuring a local loopback connection, in which one PingFederate instance is both the identity provider and the service provider, disable the IdP-Initiated SLO and SP-Initiated SLO options on the Browser SSO window's SAML Profiles tab. These options determine whether SAML logout requests

should be sent to the partner during the SLO flow. Those requests aren't necessary and can cause unexpected behavior when the partner connection exists locally. All local sessions for loopback connections are terminated during the SLO flow without the need to send SAML requests.

For information on typical SAML SSO and SAML 2.0 SLO profile configurations, including illustrations, see [SAML 1.x profiles](#) on page 37 and [SAML 2.0 profiles](#) on page 40.



**Note:**

The **SAML Profiles** tab does not apply to OpenID Connect and WS-Federation IdP connections.

### Steps

- Select the applicable profiles based on your partner agreement.

For SAML 2.0, you must select at least one SSO profile.

For SAML 1.x, IdP-initiated SSO is assumed and the specifications do not support SLO; the only choice on this tab is **SP-initiated SSO**.

### Configuring user-session creation

You must create and configure user sessions when configuring service provider (SP) browser single sign-on (SSO).

#### About this task

As an SP, you must specify how uses information sent from the IdP in SSO tokens to create user sessions for enabling access to protected resources at your site.

If you are a federation hub, bridging an identity provider to one or more service providers, you can associate one or more authentication policy contracts to the IdP connection. For more information, see .

The configuration involves choosing an identity-mapping method, establishing an attribute contract as needed, and optionally mapping one or more SP adapter instances, authentication policy contracts, or both.

### Steps

- On the **User-Session Creation** tab, click **Configure User-Session Creation**.

#### *Choosing an identity mapping method for SP SSO*

When configuring service provider (SP) single sign-on (SSO), PingFederate offers two methods of identity mapping you can choose from: account mapping or account linking.

#### About this task

allows an SP to use either account linking or account mapping to associate remote users with local accounts for SSO between business partners. For more information, see . On the **Identity Mapping** tab, you choose which method to use in this IdP connection. You and your partner should decide in advance which option to use. For more information, see .

If your site is using account linking, then establishing an attribute contract is not required. Depending on your partner agreement, you can choose to supplement the account link with an attribute contract. In this configuration the account link is used to determine the user's identity, while the additional attributes might be used for authorization decisions, customized web pages, and so on, at the your site. For more information, see .



**Important:**



If you have previously set up a configuration to use an attribute contract and want to change the configuration to use account linking without additional attributes, then the existing attribute contract will be discarded.

Account linking can be used with either a clear, standard name identifier or an opaque pseudonym.

### Steps

1. Choose which identity mapping method to use in this IdP connection.

Choose from:

- If you want to dynamically associate remote users with local accounts using a known attribute to identify a user, such as a username or email address, select **Account Mapping**

Account mapping uses the user identifier, **SAML\_SUBJECT** in a SAML assertion or **sub** in an ID token, and associated user attributes to create an association between a remote user and a local account.



#### Tip:

If you are using PingFederate's JIT provisioning, choose **Account Mapping**. For more information, see [Configuring just-in-time provisioning](#) on page 763.

- If you want to create a long-term association between a remote user and a local account, select **Account Linking**



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

To set up an attribute contract to use in conjunction with account linking, select the ... **includes attributes in addition to the unique name identifier** check box.

2. If you have selected only the SP-initiated SSO profile and you intend to enforce additional authentication requirements by placing this IdP connection in an SP authentication policy, select **No Mapping**.
3. Additionally, select **No Mapping** if you are deploying an IdP connection solely for OAuth attribute mapping without the use of an authentication policy contract. For more information, see [Configuring IdP connection grant mapping](#) on page 587.

### Defining an attribute contract

An attribute contract is the set of user attributes that you and your partner have agreed will be sent in single sign-on (SSO) tokens for this connection.

### About this task

You can extend the attribute contract with additional attributes. Optionally, you can configure PingFederate to mask individual extended attributes in its logs. For more information, see [Attribute contracts](#) on page 101 and [Attribute masking](#) on page 104.



#### Tip:

If you are creating or updating a SAML or an OpenID Connect identity provider (IdP) connection, consider using the partner's metadata to do so. If the metadata contains the required information, PingFederate automatically populates the attribute contract for you.

## Steps

1. On the **Attribute Contract** tab, enter the attribute name in the text box.

Attribute names are case-sensitive and must correspond to the attribute names expected by your partner.



### Tip:

If you are configuring a SAML connection to an InCommon participant, the assertion might contain attributes such as `urn:oid:0.9.2342.19200300.100.1.3` and `urn:oid:2.5.4.42`, which are standard names under various specifications, such as [RFC4524](#) and [RFC4519](#). For more information, see [www.incommon.org/participants](http://www.incommon.org/participants). The following table describes a subset of the object IDs (OIDs) referenced by the most common attributes used by InCommon participants.

| OID value                 | Description                |
|---------------------------|----------------------------|
| 0.9.2342.19200300.100.1.3 | mail                       |
| 1.3.6.1.4.1.5923.1.1.1.1  | eduPersonAffiliation       |
| 1.3.6.1.4.1.5923.1.1.1.6  | eduPersonPrincipalName     |
| 1.3.6.1.4.1.5923.1.1.1.7  | eduPersonEntitlement       |
| 1.3.6.1.4.1.5923.1.1.1.9  | eduPersonScopedAffiliation |
| 1.3.6.1.4.1.5923.1.1.1.10 | eduPersonTargetedID        |
| 2.5.4.3                   | cn                         |
| 2.5.4.4                   | sn                         |
| 2.5.4.10                  | o                          |
| 2.5.4.42                  | givenName                  |
| 2.16.840.1.113730.3.1.241 | displayName                |

For other attributes, see the metadata from your partner. The **FriendlyName** values, if available, should provide additional information about the attributes. Alternatively, third-party resources, such as [www.ldap.com/ldap-oid-reference](http://www.ldap.com/ldap-oid-reference) and [www.oid-info.com](http://www.oid-info.com), might help as well.

2. Optional: Select the check box under **Mask Values in Log**.
3. Click **Add**.
4. Repeat until all desired attributes are defined.

## Next steps

Click **Edit**, **Update**, and **Cancel** to make or undo a change to an item. Click **Delete** and **Undelete** to remove an item or cancel the removal request.

### Managing target session mappings

You can map a service provider (SP) adapter instance to an identity provider (IdP) connection and complete its mapping configuration through a series of sub tasks.

#### About this task

When PingFederate receives an SSO token, the corresponding SP adapter is triggered to fulfill its adapter contract based on the connection settings for the purpose of completing the "last-mile" integration with your application. As needed, you can map multiple SP adapter instances to an IdP connection, the same SP adapter instance to multiple IdP connections, or a combination of them.

Alternatively, if you use authentication policies to route users through a series of authentication sources and end each successful policy path with an authentication policy contract (APC), you can skip the mapping of an APC to an IdP connection and configure an APC-to-SP adapter instance mapping configuration.



#### Tip:

To learn more about authentication policies, see [Authentication policies](#) on page 231.

Furthermore, you can map one or more APCs to an IdP connection to bridge an identity provider to one or more service providers. In this scenario, PingFederate is a federation hub for both sides. PingFederate uses APCs to associate this IdP connection with the applicable SP connections to the service providers; each APC has its own set of attributes to which you can map values from the SSO tokens.



#### Tip:

To learn more about federation hub, see [Federation hub use cases](#) on page 108.

On the **Target Session Mapping** tab, if presented, you must associate at least one target session, an SP adapter instance or an authentication policy contract, with an IdP connection. If you have multiple integration requirements, for example, if you are using more than one IdM system or an application not covered by a centralized system, multiple SP adapter instances. If you are bridging an identity provider to multiple service providers, map multiple authentication policy contracts.

The **Target Session Mapping** configuration does not apply when the **No Mapping** option is selected on the **Identity Mapping** tab.

#### Steps

- On the **Target Session Mapping** tab:

| Choice  | Action   |
|---|--|
| Map an SP adapter instance  | Click <b>Map New Adapter Instance</b> .  |
| Map an APC  | Click <b>Map New Authentication Policy</b> .   |
| Edit the mapping configuration of an SP adapter instance or APC                                     | Open it by clicking on its name, select the setting that you want to reconfigure, and complete the change. |
| Remove an SP adapter or APC or cancel the removal request   | Click <b>Delete</b> followed by <b>Save</b> or <b>Undelete</b> .   |
| If you are creating a new connection and you are finished with mapping the required target sessions | Click <b>Done</b> .  |

| Choice   | Action              |
|--|---------------------|
| If you are editing an existing configuration and want to keep your changes | Click <b>Save</b> . |

### Result

When target sessions are restricted to certain virtual server IDs, the allowed IDs are displayed under **Virtual Server IDs**.



#### Note:

If you configure multiple target sessions for a connection, PingFederate selects the applicable adapter instance or authentication policy contract at runtime based on the target resource information in the requests and your configuration. For more information, see [Configuring target URL mapping](#) on page 715.

### Selecting a target session

The first step of the mapping configuration is to map an adapter instance or an authentication policy contract to your connection.

### Steps

1. Select an adapter instance from the **Adapter Instance** list.

If you do not see the desired adapter instance, click **Manage Adapter Instances** to create a new instance of any deployed adapter.

2. If you want to customize adapter settings for this connection alone, select the **Override Instance Settings** check box.

Result:

When selected, the administrative console adds a new set of sub tasks: the **Override Instance** tab and its sub tasks.



#### Tip:

Alternatively, you can create child adapter instances of a base adapter instance with overrides so that such customized settings can be applied to several connections. For more information, see [Hierarchical plugin configurations](#) on page 99.

3. Optional: To map an authentication policy contract (APC), select an adapter instance from the list.
4. Optional: If you do not see the desired APC, click **Manage Authentication Policy Contracts** to create a new policy contract.

### Result

If you are editing a currently mapped adapter instance, you can select the **Override Instance Settings** check box. Clearing it removes all previously overridden settings for this connection. Selecting it provides you the opportunity to customize adapter settings specifically for this connection.

If you are editing a currently mapped APC, no changes can be made on this tab.

### Overriding an SP adapter instance

When configuring service provider (SP) browser single sign-on (SSO), you can override the adapter instance settings.

About this task

On the **Override Instance** tab, you start a series of sub tasks to override adapter settings specifically for this connection.



**Note:**

Any changes to the base adapter instance are propagated to a connection provided the same changes are not overridden for the connection.

Steps

- Click **Override Instance Settings**.

On each of the setting tabs, select the **Override** check box, make your changes, then click **Next**. When you are finished, click **Done** to continue with the rest of the mapping configuration.



**Note:**

The override setting tabs are functionally identical to those used for creating a new adapter instance. For more information, see [Managing SP adapters](#) on page 713.

Next steps

If you are editing a currently mapped adapter instance, click **Override Instance Settings** to reconfigure any overridden settings for this connection. You can also remove all overridden settings on a per-tab basis by clearing the **Override** check box near the top of the tab.

Restricting a target session to certain virtual server IDs

You can enforce integration requirements by restricting a target session to certain virtual server IDs when you multiplex one connection for multiple environments.

About this task

For more information, see [Multiple virtual server IDs](#) on page 115. On the **Virtual Server IDs** tab, follow these steps to restrict a target session to a certain virtual server ID. By default, no restriction is imposed.

Steps

1. Select the **Restrict Virtual Server IDs** check box.
2. Select the virtual server IDs that you want to allow for this target session.

Result

If you are editing a currently mapped adapter instance or authentication policy contract (APC), you can toggle the **Restrict Virtual Server IDs** setting. You can also change the allowed virtual server IDs.

Choosing an attribute mapping method

You can select if and how PingFederate should query a local datastore to help fulfill the attribute contract in conjunction with attribute values from the single sign-on (SSO) token.

#### Before you begin

To determine whether you need to look up additional values, compare the attribute contract against the adapter contract or the authentication policy contract. If the attribute contract does not contain the required information, determine whether a local datastore can supply it.

Alternatively, you can configure datastore queries as part of the fulfillment configuration for the applicable APC if you use authentication policies to route users through a series of authentication sources and end each successful policy path with an APC.

#### About this task

You make selections on the **Adapter Data Store** tab for service provider (SP) adapter mapping or the **Attribute Retrieval** tab for authentication policy contract (APC) mapping.



#### Tip:

To learn more about authentication policies, see [Authentication policies](#) on page 231.

#### Steps

- If the attribute contract contains all the attributes that your application requires, click **Use only the attributes available in the SSO assertion**.
- To set up a datastore query, click **Use the SSO assertion to look up additional information**, and then follow a series of sub tasks to complete the configuration. See [Choosing a datastore](#) on page 398 for step-by-step instructions.

#### Result

If you are editing a currently mapped adapter instance or APC, you can change the mapping method, which might require additional configuration changes in subsequent tasks.

#### Configuring target session fulfillment

Map values to the attributes defined for the contract. These are the values that the target application requires to create a local session for the user.

#### Before you begin

If you are bridging an identity provider (IdP) to one or more service providers, the values mapped to the authentication policy contracts are used by the associated service provider (SP) connections to create assertions for the service providers. For more information, see [Federation hub use cases](#) on page 108.

At runtime, a single sign-on (SSO) operation fails if PingFederate cannot fulfill the required attribute.

#### Steps

1. On the **Adapter Contract Fulfillment** tab, for each attribute, select a source from the **Source** list and then choose or enter a value. You must map all attributes.
  - **AccountLink**  
When selected, the **Value** list populates with **Local User ID**. Normally, you would map **Local User ID** to an adapter attribute that represents the user identifier at the target. This source is not

applicable to authentication policy contracts. This source appears only if you have elected to use account linking for a target session on the **Identity Mapping** tab.

- **Assertion or Provider Claims**

When selected, the **Value** list populates with attributes from the SSO token. Select the desired attribute from the list.

For example, to map the value of **SAML\_SUBJECT** from a SAML assertion as the value of the `subject` user identifier on the contract, select **Assertion** from the **Source** list and **SAML\_SUBJECT** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.



**Note:**

As the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.



**Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added `PERSISTENT_GRANT_LIFETIME` as an extended attribute in the **Authorization Server Settings** window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **LDAP, JDBC, or Other**

When selected, the **Value** list populates with attributes that you have selected from the datastore. Select the desired attribute from the list.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under

**Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

When selected, the text you enter is used at runtime. You can mix text with references to any of the values from the SSO token, using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using this syntax:

```
${ds.attribute}
```

where `attribute` is any attribute that you have selected from the datastore.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

Two other text variables are available. **SAML\_SUBJECT** is the initiating user or other entity. **TargetResource** is a reference to the protected application or other resource for which the user requested SSO access. The `${TargetResource}` text variable is available only if specified as a query parameter for the relevant endpoint, either as **TargetResource** for SAML 2.0 or **TARGET** for SAML 1.x.

You might hard-code a text value for a variety of reasons. For example, if your web application provides a consumer service, you might want to supply a particular promotion code for the partner.



**Note:**

If you are editing a currently mapped adapter instance or authentication policy contract (APC), you can update the mapping configuration, which might require additional configuration changes in subsequent tasks.

2. Click **Next** to continue configuration.

## Defining issuance criteria for SP Browser SSO

You can define issuance criteria when configuring service provider (SP) browser single sign-on (SSO) for PingFederate.

### Before you begin

Begin this optional configuration by adding a criterion. Choose the source that contains the attribute to be verified. Some sources, such as **Mapped Attributes**, are common to almost all use cases. Other sources, such as **JDBC**, depend on the type of configuration. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to be verified. Depending on the selected source, the available attributes or properties vary. Finally, specify the comparison method and the desired, compared-to, value.

### About this task

On the **Issuance Criteria** tab, define the criteria that must be satisfied in order for to process a request further. This token authorization feature provides the capability to conditionally approve or reject requests based on individual attributes.



If you define multiple criteria, all criteria must be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value depending on the chosen comparison method. The multi-value contains and multi-value does not contain comparison methods are intended for attributes that might contain multiple values. Such criterion is considered satisfied if one of the multiple values matches or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



#### Important:

When you multiplex one connection for multiple environments, consider using attribute mapping expressions to verify the virtual server ID in conjunction with other conditions, such as group membership information, to protect against unauthorized access. For more information, see [Multiple virtual server IDs](#) on page 115 and [Issuance criteria and multiple virtual server IDs](#) on page 229.



#### Note:

All criteria defined must be satisfied or evaluated as true for a request to move forward. As soon as one criterion fails, rejects the request and returns an error message.

### Steps

1. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

| Source   | Description   |
|--|---|
| <b>AccountLink</b>   | Select to evaluate the <b>Local User ID</b> value of the user.<br><br>Displayed only if <b>Account Linking</b> is the selected identity mapping method. For more information, see <a href="#">Choosing an identity mapping method for SP SSO</a> on page 736.   |
| <b>Assertion or Provider Claims</b>                            | Select to evaluate attributes from the IdP connection.  |
| Context  | Select to evaluate properties returned from the context of the transaction at runtime.  |
|  | <div data-bbox="574 1455 621 1501" data-label="Image"> </div> <div data-bbox="623 1467 698 1501" data-label="Section-Header"> <h4>Note:</h4> </div> <div data-bbox="568 1516 1459 1612" data-label="Text"> <p>The <b>HTTP Request</b> context value is retrieved as a Java object rather than text. For this reason, attribute mapping expressions are more appropriate to evaluate and return values.</p> </div> |
| <b>JDBC, LDAP, or other types of datastore (if configured)</b> | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>                                       | Select to evaluate the mapped attributes.   |

2. In the **Attribute Name** list, select the attribute to be evaluated.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

Error results are handled in one of the two ways:

**Redirect**

When an **InErrorResource** URL is provided, the value of the **Error Result** field is used by the query parameter **ErrorDetail** in the redirect URL.

**Template**

When an **InErrorResource** URL is not provided, the value of the **Error Result** field is used by the variable `$errorDetail` in the `sp.sso.error.page.template.html` template file.

Using an error code in the **Error Result** field allows the error template or an application to process the code in a variety of ways, for example, display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

8. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

#### Reviewing the target session mapping

You can review your target session mapping configuration and settings before completing.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### Reviewing the session creation summary

You can review your session creation settings before completing configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Configuring protocol settings

The **Protocol Settings** tab on the **Browser SSO** window provides the launching point for configuring partner endpoints, message customizations, and other protocol-specific settings for browser-based single sign-on (SSO) connections.

### About this task

The settings available on the **Protocol Settings** tab depend on the connection's protocol. The availability of the settings also depends on the connection's other previously configured settings.

#### SAML 2.0

- Outbound SSO bindings (POST, redirect, artifact) and the corresponding SSO service URLs
- Outbound single logout (SLO) bindings (POST, redirect, artifact, SOAP) and the corresponding protocol endpoints
- Inbound bindings (POST, redirect, artifact, SOAP)
- Artifact lifetime
- Artifact resolution location
- Default target URL
- Authentication context mappings
- Signature policy
- Encryption policy

#### SAML 1.x

- Outbound SSO service URL, also known as the Intersite Transfer Service, if the service provider (SP)-Initiated SSO profile is enabled
- Inbound bindings (POST, artifact)
- Artifact resolution location
- Default target URL
- Signature policy

#### WS-Federation

- Protocol endpoint
- Default target URL
- Signature policy

#### OpenID Connect

- The scopes PingFederate sends to the OpenID provider (OP) in its authorization and token requests
- The OpenID Connect login type and authentication scheme used by PingFederate when communicating with the OP
- The authorization endpoint, the token endpoint, the user information, UserInfo, endpoint, and the JWKS URL
- Default target URL
- Authentication context mappings

To start configuring the connection's protocol setting:

### Steps

1. On the **Protocol Settings** tab, click **Configure Protocol Settings**.  
Result: The **Protocol Settings** window opens.
2. Use the window's tabs to continue configuring the connection's protocol settings.

### Specifying SSO service URLs (SAML)

The single sign-on (SSO) service endpoint is where PingFederate sends requests when SSO is initiated at your site according to partner requirements. It applies to all SAML versions when the service provider (SP)-initiated SSO profile is enabled.

#### About this task

For SAML 2.0 connections, associate bindings to the endpoints where your identity provider (IdP) partner wants PingFederate to send authentication requests when SSO is initiated at your site.

For SAML 1.x, only one endpoint is allowed, and the binding selection is not required.

Some federation use cases might require additional customizations in the authentication requests sent from the PingFederate SP server to the IdP, such as including the optional **Extensions** element in the authentication requests. You can use OGNL expressions to fulfill these use cases.

#### Steps

1. Enter an SSO service endpoint.

- a. Enter the SSO service endpoint in the **Endpoint URL** field.

You can enter a relative path, starting with a forward slash, if you have provided a base URL on the **General Info** tab.

For SAML 1.x connections, this is the only configurable item on the **SSO Service URL** tab.

The remaining steps on the **SSO Service URLs** tab only apply to SAML 2.0 connections.

- b. Select a SAML binding from the list; for example, **POST**.
  - c. Click **Add**.
  - d. Optional: Repeat to add additional SSO service endpoints.
2. Optional: Customize messages using OGNL expressions.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225. Additionally, message customization does not apply to SAML 1.x connection.

- a. Click **Show Advanced Customizations**.
  - b. Select a message type from the list.
  - c. Enter an OGNL expression to fulfill your use case.



#### Note:

For more information about **Message Type**, available variables, and sample OGNL expressions, see [Customizing assertions and authentication requests](#) on page 390.

- d. Click **Add**.
  - e. Optional: Repeat to add another message customization.

### Specifying a service URL (WS-Federation)

The service endpoint URL is where PingFederate sends request for security token (RST) and single log-out (SLO) messages.

#### About this task

To protect against session token hijacking, PingFederate provides an option to validate wreply for SLO. When this option is enabled, you can specify additional allowed domains and paths on this tab. PingFederate validates the locations against a consolidated list of allowed domains and paths from all active WS-Federation connections before redirecting the end users to their destinations.

**Note:**

The settings to enter additional allowed domains and paths appear only if the option to validate wreply for SLO is enabled. For more information, see [Managing partner redirect validation](#) on page 696.

## Steps

1. Enter the WS-Federation protocol endpoint at the identity provider (IdP) site in the **Endpoint URL** field.

You can enter a relative path, starting with a forward slash, if you have provided a base URL on the **General Info** tab.

2. Optional: Specify additional allowed domains and paths.
  - a. Indicate whether to mandate secure connections when this resource is requested under **Require HTTPS**.

**Important:**

This selection is recommended to ensure that the validation will always prevent message interception for this type of potential attack, under all conceivable permutations.

This check box is selected by default.

- b. Enter the expected domain name or IP address of this resource under **Valid Domain Name**.

Enter a value without the protocol, such as `example.com` or `10.10.10.10`.

Prefix a domain name with a wildcard followed by a period to include subdomains using one entry. For instance, `*.example.com` covers `hr.example.com` or `email.example.com` but not `example.com`, the parent domain.

**Important:**

While using an initial wildcard provides the convenience of allowing multiple subdomains using one entry, consider adding individual subdomains to limit the redirection to a list of known hosts.

- c. Optional: Enter the exact path of this resource under **Valid Path**.

Start with a forward slash, without any wildcard characters in the path. If left blank, any path under the specified domain or IP address is allowed. This value is case-sensitive. For instance, `/inbound/Consumer.jsp` allows `/inbound/Consumer.jsp` but rejects `/inbound/consumer.jsp`.

You can allow specific query parameters with or without a fragment by appending them to the path. For instance, `/inbound/Consumer.jsp?area=West&team=IT#ref1001` matches `/inbound/Consumer.jsp?area=West&team=IT#ref1001` but not `/inbound/Consumer.jsp?area=East&team=IT#ref1001`.

- d. Optional: Select the check box under **Allow Any Query/Fragment** to allow any query parameters or fragment for this resource.

Selecting this check box also means that no query parameter and fragment are allowed in the path defined under **Valid Path**.

This check box is not selected by default.

*Defining SLO service URLs (SAML 2.0)*

On the **SLO Service URLs** tab, associate bindings to the endpoints where your identity provider (IdP) receives logout requests when single logout (SLO) is initiated at your site and where PingFederate sends SLO responses when it receives SLO requests from the IdP.

## About this task

This process only applies to SAML 2.0 connections when either SLO profile is selected on the **SAML Profiles** tab.

## Steps

1. Go to **Applications # Integrations # SP Connections**.
2. Click on any SAML 2.0 connection, and then click the **Browser SSO** tab.
3. Click **Configure Browser SSO**, and then click the **SAML Profiles** tab.
4. Select a SAML binding from the list; for example, **POST**.
5. Enter the SLO endpoint URL in the **Endpoint URL** field.

You can enter a relative path, starting with a forward slash, if you have provided a base URL on the **General Info** tab.

6. Optional: Enter a URL in the **Response URL** field.

When specified, it is the location where SLO logout response messages are sent based on your partner agreement. When omitted, PingFederate sends logout responses to the SLO endpoint URL.

You can enter a relative path, starting with a forward slash, if you have provided a base URL on the **General Info** tab.

7. Click **Add**.
8. Optional: Repeat to add additional SLO endpoints.

## Result

If you are editing an existing connection, you can reconfigure the SLO endpoints, which might require additional configuration changes in subsequent tasks.

*Selecting allowable SAML bindings (SAML)*

On the **Allowable SAML Bindings** tab, select the one or more bindings that your identity provider (IdP) partner can use to send SAML assertions or SAML 2.0 single logout (SLO) messages.

## About this task

This configuration applies to all SAML connections.

## Steps

Select the check boxes for only the applicable SAML bindings based on your partner agreement. Choose from:

- **Artifact**
- **Post**
- **Redirect**
- **SOAP**

**Note:**

If you have specified a single sign-on (SSO) or SLO endpoint using the artifact outbound binding, you must include SOAP as one of the allowable inbound binding.

## Result

If you are editing an existing connection, you can reconfigure the allowable bindings, which might require additional configuration changes in subsequent tasks.

### *Specifying an artifact lifetime (SAML 2.0)*

When PingFederate sends an artifact to your identity provider's (IdP's) single sign-on (SSO) or single logout (SLO) service endpoint, an element in the message indicates how long it should be considered valid.

## About this task

On the **Artifact Lifetime** tab, specify the expiry information in seconds.

You can change the default value to meet your requirements. You should also consider synchronizing your server clock with your partner's SAML gateway server. If clocks are not synchronized, you might need to set the artifact lifetime to a higher value to prevent latency issues.

This step applies only to SAML 2.0 connections.

## Steps

- Optional: Override the default value of the **Artifact Lifetime** field.

The default value is 60 seconds.

## Result

You can update the artifact lifetime if you are editing an existing connection.

### *Defining artifact resolver locations (SAML)*

When you enable the artifact binding as one of the allowable bindings on the **Allowable SAML Bindings** tab, you must provide an artifact resolution service (ARS) endpoint.

## About this task

The ARS endpoint is the location where PingFederate sends back-channel requests to resolve artifacts received from the identity provider (IdP).

SAML 2.0 connections allow multiple ARS endpoints. For SAML 1.x connections, you can only enter one ARS endpoint.



## Steps

### 1. Enter an ARS endpoint.

#### a. Enter the ARS endpoint URL.

You can enter a relative path, starting with a forward slash, if you provide a base URL on the **General Info** tab.

Result:

If you are configuring a SAML 1.x connection, you can only enter one ARS endpoint on the **Artifact Resolver Location** tab.

#### b. Optional: Enter an integer in the **Index** field for this ARS endpoint.

This is applicable only to SAML 2.0 connections.

The administrative console automatically assigns an index value for each ARS endpoint, starting from 0. If you want to define your own index values, you must make sure the index values are unique.

#### c. Click **Add**.

#### d. Optional: Repeat to add additional ARS endpoints.

This is applicable only to SAML 2.0 connections.



#### **Note:**

When specifying multiple ARS endpoints, each endpoint must share the same transport protocol. That is, if one endpoint uses HTTPS, then all must use HTTPS. Similarly, if one endpoint uses HTTP, then all must use HTTP.

### 2. Optional: Enter your partner's source ID.

The source ID is usually a generated value based on a federation partner's connection ID; the PingFederate service provider (SP) server will correctly generate the source ID. If that is the case for this partner, then leave this field blank. If your partner uses a Source ID that is not based on the Issuer ID, then enter the Source ID supplied by your IdP partner.

## Result

You can reconfigure any ARS endpoint or the source ID value for SAML 1.x if you are editing an existing connection.

### Configuring OpenID Provider information

You must configure OpenID Provider (OP) settings and information when configuring service provider (SP) browser single sign-on (SSO).

#### Steps


1. On the **OpenID Provider Info** tab, provide the scopes, the endpoints, and the authentication scheme.




|   |   |
|---|---|
| SCOPES                                    | <input type="text" value="openid"/>   |
| AUTHORIZATION ENDPOINT                    | <input type="text" value="https://localhost:9031/as/authorization.oauth2"/>   |
| OPENID CONNECT LOGIN TYPE                 | <input checked="" type="radio"/> CODE <input type="radio"/> FORM POST <input type="radio"/> FORM POST WITH ACCESS TOKEN |
| AUTHENTICATION SCHEME                     | <input type="radio"/> BASIC <input type="radio"/> POST <input checked="" type="radio"/> PRIVATE KEY JWT                 |
| AUTHENTICATION SIGNING ALGORITHM          | <input type="text" value="- SELECT -"/>   |
| ENABLE PROOF KEY FOR CODE EXCHANGE (PKCE) | <input checked="" type="checkbox"/>   |
| TOKEN ENDPOINT                            | <input type="text" value="https://localhost:9031/as/token.oauth2"/>   |
| USER INFO ENDPOINT                        | <input type="text" value="https://localhost:9031/idp/userinfo.openid"/>   |
| JWKS URL                                  | <input type="text" value="https://localhost:9031/pf/JWKS"/>   |
| SIGN REQUEST                              | <input checked="" type="checkbox"/>   |
| REQUEST SIGNING ALGORITHM                 | <input type="text" value="- SELECT -"/>   |





#### Note:

If you clicked **Load Metadata** from the OpenID Provider (OP) on the **General Info** tab, the **Scopes** field and all endpoints are pre-populated, provided that the metadata contains the information.

| Field                            | Description  |
|----------------------------------|--|
| <b>Scopes</b>                    | <p>The scopes to be included in the OpenID Connect authentication and OAuth token requests to the OP. Multiple space-separated values are allowed.</p> <p>The default value, without loading metadata from the OP, is <code>openid</code>.</p> <div data-bbox="565 380 1468 617" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>For a list of OpenID Connect defined scopes, see the section about requesting claims using scope values in the OpenID Connection specification at <a href="https://openid.net/specs/openid-connect-core-1_0.html#ScopeClaims">openid.net/specs/openid-connect-core-1_0.html#ScopeClaims</a>.</p> </div>   |
| <b>Authorization Endpoint</b>    | <p>The authorization endpoint at the OP.</p> <p>You can enter a relative path, starting with a forward slash, if you provide base URL on the <b>General Info</b> tab.</p> <p>There is no default value without loading metadata from the OP.</p>   |
| <b>OpenID Connect Login Type</b> | <p>The OpenID Connect client profile of the client. This client represents and is created and managed at the OP.</p> <ul style="list-style-type: none"> <li>▪ If the client is configured to support the Basic Client profile, select <b>Code</b>.<br/>The resulting value of the <code>response_type</code> parameter is <code>code</code>.</li> <li>▪ If the client is configured to support the Implicit Client profile, select <b>Form POST</b>.<br/>The resulting value of the <code>response_type</code> parameter is <code>id_token</code>.</li> <li>▪ If the client is configured to support the Implicit Client profile and the target application requires the associated access token, select <b>Form POST with access token</b>.<br/>The resulting values of the <code>response_type</code> parameter are <code>id_token</code> and <code>token</code>.</li> </ul> <p>The default selection, without loading metadata from the OP, is <b>Code</b>.</p> |
| <b>Authentication Scheme</b>     | <p>The client authentication method that uses. Applicable and visible only to clients supporting the Basic Client profile.</p> <ul style="list-style-type: none"> <li>▪ Select <b>Basic</b> to submit credentials with HTTP Basic authentication.</li> <li>▪ Select <b>POST</b> to submit credentials with POST.</li> <li>▪ Select <b>Private Key JWT</b> to authenticate with the <code>private_key_jwt</code> Client Authentication method. For more information, see Client Authentication in the OpenID Connect specification.</li> </ul> <p>The default selection, without loading metadata from the OP, is <b>Basic</b>.</p>   |

| Field  | Description   |
|--|---|
| <b>Authentication Signing Algorithm</b>          | <p>Select the algorithm that uses to sign the JSON web token (JWT). <b>Private Key JWT</b> is the chosen authentication scheme.</p> <p>If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div data-bbox="565 520 1468 835" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p>Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <div data-bbox="565 856 1468 1360" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>Based on the chosen signing algorithm, selects the signing JSON Web Key (JWK) from its JWK Set (JWKS) at runtime.</p> <p>For the OP to validate the signed JWT, ensure that the OP can access the JWKS endpoint, which returns the current JWKS. The JWKS endpoint is located at <code>&lt;Base URL&gt;/pf/JWKS</code>, where <b>Base URL</b> is defined on <b>System # Server # Protocol Settings # Federation Info</b>.</p> <p>For example, if the <b>Base URL</b> field value is <code>https://www.example.com</code>, the JWKS endpoint is <code>https://www.example.com/pf/JWKS</code>. You can pass the JWKS endpoint directly to the OP or have the OP contact the OP configuration endpoint to obtain the information.</p> <p>For more information, see .</p> </div> |
| <b>Enable Proof Key for Code Exchange (PKCE)</b> | <p>Select this check box to enable to send a SHA256 code challenge and corresponding code verifier as a Proof Key for Code Exchange (PKCE) to the OP during the Code authentication flow.</p> <p>This check box is applicable and visible only when the <b>OpenID Connect Login Type</b> is <b>Code</b>.</p> <div data-bbox="565 1585 1468 1791" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>When <b>Load Metadata</b> on the <b>General Info</b> tab is clicked, displays the <b>Enable PKCE</b> check box if S256 is listed as a supported method in the <code>code_challenge_methods_supported</code> by the OP.</p> </div>  |

| Field  | Description   |
|--|---|
| <b>Token Endpoint, UserInfo Endpoint, and JWKS URL</b> | <p>OAuth 2.0 and OpenID Connect 1.0 endpoints at the OP. For more information, see <a href="https://openid.net/connect">openid.net/connect</a>.</p> <p>Token Endpoint</p> <p>The <b>Token Endpoint</b> field is only visible and required for clients supporting the Basic Client profile. In other words, the <b>OpenID Connect Login Type</b> field is set to <b>Code</b>.</p> <p>UserInfo Endpoint</p> <p>The <b>UserInfo Endpoint</b> field is optional. If omitted, only has access to the end-user claims from the ID tokens.</p> <p>JWKS URL</p> <p>The <b>JWKS URL</b> is required for to validate the inbound ID tokens from the OP. If the OP signs its JWTs using an RSASSA-PSS signing algorithm, must be deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively. .</p> <p>There are no default values without loading metadata from the OP.</p> |
| <b>Sign Request</b>                                    | <p>Select this check box to send request parameters as claims in a request object, a self-contained, signed JWT as one <code>request</code> query parameter to the OP.</p> <p>When this optional configuration is enabled, the OP can validate the integrity of the request parameters based on the digital signature found in the signed JWT. For more information, see the section explaining passing a request object by value in the OpenID Connect specification at <a href="https://openid.net/specs/openid-connect-core-1_0.html#RequestObject">openid.net/specs/openid-connect-core-1_0.html#RequestObject</a>.</p> <p>This check box is not selected by default, in which case sends request parameters with multiple query parameters, unsigned.</p>  |

| Field                            | Description  |
|----------------------------------|--|
| <b>Request Signing Algorithm</b> | <p>Select the algorithm that uses to sign the request object.</p> <p>Applicable and visible only when the <b>Sign Request</b> check box is selected.</p> <p>If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p>Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>automatically selects the signing JSON web key (JWK) based on the selected signing algorithm from its JWK Set (JWKS).</p> <p>In order for the OP to validate the signed request object, ensure that the OP can access your 's JWKS URL, which returns the current set of JSON web keys. The JWKS URL is located at <code>&lt;Base URL&gt;/pf/JWKS</code>, where <b>Base URL</b> is defined on <b>System # Server # Protocol Settings # Federation Info</b>.</p> <p>For example, if the <b>Base URL</b> field value is <code>https://www.example.com</code>, the JWKS URL is <code>https://www.example.com/pf/JWKS</code>. You can pass the JWKS URL directly to the OP or have the OP contact the OpenID Provider configuration endpoint for it. For more information, see .</p> </div> |

- Optional: Remain on the **OpenID Provider Info** tab and specify the request parameters that are allowed to be included in the authentication requests to the OP under **Request Parameters**. For more information, see .

#### Configuring default target URLs

You can define default target URLs for identity provider (IdP) connections.

#### About this task

Use the **Protocol Settings # Overrides** tab to assign a default target URL for this IdP connection.

#### Steps

Optional: Enter a URL in the **Default Target URL** field.

If specified, the value overrides the default target setting defined in the **Applications # Integration # SP Default URLs** window.

 **Note:**

The SAML 1.x specifications for IdP-initiated single sign-on (SSO) require a target URL to be specified. If the target application is specified in the URL parameter to the `/sp/startSSO.ping` application endpoint, any URL specified in the **Default Target URL** field in this window will not be used for those transactions.

### Overriding authentication context in an IdP connection

You can map authentication context values between the local and remote values in an OpenID Connect or a SAML 2.0 identity provider (IdP) connection.

#### About this task

This optional configuration overrides how authentication context values are communicated with partners in both the authentication or authorization requests and their responses. Any values that are not defined in this configuration are passed through as-is.

As needed, you can use an asterisk, `*`, to match any values, a blank value for a scenario where the partner or the local request does not specify an authentication value, or both.

#### Steps

1. Go to **Authentication # Integration # IdP Connections**.
2. Click the name of the connection to open it in the **IdP Connection** window.
3. On the **Activation & Summary** tab, scroll down to the **Protocol Settings** section, then click **Overrides**.
4. On the **Overrides** tab, specify the **Local** and **Remote** entry, then click **Add**.
5. Repeat the previous step to define additional mappings.
 

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.
6. Click **Save** to complete the configuration.

Alternatively, click **Next** to carry on with the rest of the connection settings.

#### Example

#### Example

Suppose you are the service provider (SP) and your target application requires either the `urn:oasis:names:tc:SAML:2.0:ac:classes:Kerberos` or `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified` authentication context. While the IdP is capable of authenticating its users using a Kerberos-based authentication system, a proprietary identity management system, and a few internal web portals, the authentication context values are different than what your application supports. The authentication context values from the IdP are as follows.

| Authentication method                  | AuthnContext values                               |
|--|---|
| Kerberos-based authentication system   | KerberosAuth                                      |
| Internal web portals                   | password, portal, or web                          |
| Proprietary identity management system | No authentication context information is provided |

To override the **AuthnContext** values from the IdP, you can configure the IdP connection with the following authentication context mappings.

| Local   | Remote                    |
|---|---------------------------|
| <code>urn:oasis:names:tc:SAML:2.0:ac:classes:Kerberos</code>    | <code>KerberosAuth</code> |
| <code>urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified</code> | <code>*</code>            |

| Local | Remote   |
|-------|--|
|       | urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified |

The first entry maps `KerberosAuth` to `urn:oasis:names:tc:SAML:2.0:ac:classes:Kerberos`. The second entry maps any authentication context values including `password` and `portal` to `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified`. The last entry overrides the authentication value to `urn:oasis:names:tc:SAML:2.0:ac:classes:unspecified` in the event that the assertion does not contain any authentication context information.

#### *Configuring signature policy*

The **Signature Policy** tab provides options controlling how digital signatures are used for SAML and WS-Federation single sign-on (SSO) messages.

#### About this task

The choices made on this tab depend on your partner agreement. For more information, see [Digital signing policy coordination](#) on page 97.

Digital signing is required for SAML response messages sent from the identity provider (IdP) through POST or redirect for SAML 2.0. The SAML specifications allow the signing of the entire SAML response message or the assertion portion inside the SAML response message. If you and your partner agree on the latter, select the **Specify additional signature requirements** and **Require signed SAML Assertions** options on this tab. When the latter is selected, only the assertion portion of the SAML response message is signed, not the entire SAML response message. This is the only option that appears for SAML 1.x and WS-Federation connections.

SAML 2.0 authentication requests from the service provider (SP) can also be signed to enforce security. This option appears only for SAML 2.0 connections and when the SP-initiated SSO profile is enabled on the **SAML Profiles** tab.

Select **Always Sign Artifact Response** if you want the SAML ArtifactResponse to be signed regardless of the protocol being used to transport it.

#### Steps

- To continue, select the options based on your partner agreement.

#### Result

If you are editing an existing connection, you can reconfigure the digital signature policy, which might require additional configuration changes in subsequent tasks.

#### *Specifying XML encryption policy (for SAML 2.0)*

For SAML 2.0 configurations, in addition to using signed assertions to ensure authenticity, you and your partner can also agree to encrypt all or part of an assertion to improve privacy.

#### About this task

You can configure these settings on the **Encryption Policy** tab.



#### **Note:**

For WS-Fed connections with SAML 2.0 assertions, you cannot encrypt the entire assertion.



| Option                         | Name identifier (SAML_SUBJECT) | Other attributes                           | Encrypt the SAML_SUBJECT in SLO messages to the IdP   | Allow encrypted SAML_SUBJECT in SLO messages from the IdP   |
|--------------------------------|--------------------------------|--|---|---|
| None                           | No encryption.                 | No encryption.                             | No encryption.  | No encryption.  |
| The entire assertion           | Encryption allowed.            | Encryption allowed.                        | Encryption allowed as an available option.  | Encryption allowed as an available option.  |
| SAML_SUBJECT (Name Identifier) | Encryption allowed.            | Encryption allowed as an available option. | Encryption allowed as an available option.  | Encryption allowed as an available option.  |
| One or more attributes         | Encryption allowed.            | Encryption allowed as an available option. | Encryption allowed as an available option only if you select to allow the entire assertion or the SAML_SUBJECT to be encrypted. | Encryption allowed as an available option only if you select to allow the entire assertion or the SAML_SUBJECT to be encrypted. |

To enable encryption:

#### Steps

1. Click the **Allow encrypted SAML Assertions and SLO messages** option.
2. Choose whether this identity provider (IdP) partner will encrypt the entire assertion, the **SAML\_SUBJECT** name identifier, one or more other attributes, or some combination.
3. If your partner is encrypting the name identifier, indicate whether you will encrypt this attribute in outbound SAML 2.0 single logout (SLO) messages, allow its encryption for inbound messages, or both.

#### Result

If you are editing an existing connection, you can reconfigure the XML encryption policy, which might require additional configuration changes in subsequent tasks.

#### *Reviewing protocol settings for SP browser SSO*

You should confirm your protocol settings for browser-based single sign-on (SSO) before completing configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Reviewing Browser SSO settings

You can review your browser single sign-on (SSO) settings before completing configuration.

### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Manage the Attribute Query profile in an IdP connection

At the attribute query step, you configure your connection to request user attributes from your partner identity provider (IdP), if you chose this option.

For more information on IdP connection options, see [Choosing IdP connection options](#) on page 728. Attribute queries do not depend on single sign-on (SSO), but can be used independently or in conjunction with browser SSO or provisioning to provide flexibility in how a user authenticates with service provider (SP) applications. For more information, see [Attribute Query and XASP](#) on page 49 and the [/sp/startAttributeQuery.ping](#) on page 1259 SP application endpoint.

### Setting the Attribute Authority Service URL

The attribute authority service URL corresponds to the endpoint location where your identity provider (IdP) provider receives attribute query requests.

#### About this task

Attribute authority is the term used to refer to an IdP that provides user attributes to an attribute requester or your service provider (SP) site. For more information, see [Attribute Query and XASP](#) on page 49.

### Steps

- Enter the fully qualified URL or a relative path if you have defined a base URL on the **General Info** tab. For more information, see [Identifying the partner](#) on page 731.

## Mapping attribute names for Attribute Query

If the application at your site uses different names for user attributes than the names defined by the attribute authority, you must map them on the **Attribute Name Mapping** tab.

#### About this task


When the service provider (SP) receives a request from a local application to send an attribute query to this attribute authority partner, the requested user attributes are replaced with the names mapped here.

You must predetermine this information in your agreement with this connection partner.

### Steps

To map an attribute, configure the **Local Name** and **Remote Name** fields for the attribute, then click **Add**.

| Choice                          | Action   |
|---------------------------------|--|
| <b>Modify an attribute name</b> | Click <b>Edit</b> under <b>Action</b> for the attribute, make the change, then click <b>Update</b> . |

| Choice                     | Action   |
|----------------------------|--|
|                            |  <b>Note:</b><br>If you change your mind, ensure that you click <b>Cancel</b> under <b>Actions</b> and not the <b>Cancel</b> button, which discards any other changes you might have made in the configuration steps. |
| <b>Delete an attribute</b> | Click <b>Delete</b> under <b>Action</b> for the attribute.   |

### Configuring security policy for Attribute Query

The **Security Policy** tab allows you to specify the digital signing and encryption policy to which you and your partner have agreed.

About this task

These selections will trigger requirements for setting up credentials. For more information, see [Configuring security credentials](#) on page 796.

This tab also allows you to mask incoming attribute values in log files. For more information, see [Attribute masking](#) on page 104. When you enable this selection, all user attributes returned from this identity provider (IdP) are masked.

Steps

- Select or clear the check boxes the relevant check boxes.

### Reviewing the Attribute Query settings

You can review your attribute query settings before completing configuration.

Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Configuring just-in-time provisioning

PingFederate's just-in-time (JIT) provisioning allows service providers (SPs) to create user accounts on the fly during single sign-on (SSO) events, based on attributes received in SSO tokens from identity providers (IdPs).

About this task

An SP can also use JIT provisioning to update existing user records.



#### Note:

This configuration task is presented in the administrative console only when the **JIT Provisioning** check box is selected on the **Connection Options** tab.

## Steps

1. Go to **Authentication # Integration # IdP Connections**.
2. Create a new IdP connection or select an existing IdP connection .
3. On the **Connection Type** tab, select the **Browser SSO Profiles** check box and a protocol from the list.
4. On the **Connection Options** tab, select the **Browser SSO** check box and then the **JIT Provisioning** check box.
5. Complete the **Browser SSO** configuration.
6. On the **JIT Provisioning** tab, click **Configure User Provisioning** to begin the configuration of JIT provisioning.

### Selecting attribute sources (SAML 2.0)

For SAML 2.0 connections, the server can be configured to use only assertion attributes for user provisioning, or to retrieve more attributes from the identity provider (IdP) in a follow-on attribute query transaction.

### About this task

The **User Attributes** tab displays the attributes expected in the assertion from this IdP.



### Note:

The attribute query is a SAML 2.0 profile. For OpenID Connect, SAML 1.x, and WS-Federation connections, this tab is not presented. PingFederate uses only attributes from the assertion for user provisioning.

## Steps

- If you and your IdP partner have agreed to use the Attribute Query profile for provisioning, select that option before leaving this tab.

You configure the attribute query profile later in the task flow.

## Identifying the user repository

PingFederate's just-in-time (JIT) provisioning supports several directory servers and Microsoft SQL Server.

About this task

For more information on versions and requirements supported by PingFederate, see [System requirements](#) on page 119.



### Note:

was tested with vendor-specific JDBC drivers. For more information, see [Compatible database drivers](#) on page 124.

## Steps

- On the **User Repository** tab, select a datastore from the **Active Data Store** list.



### Tip:

If the desired datastore is not shown in the list, PingFederate has not been configured to access it. Click **Manage Data Stores** to configure your datastore.

- If you are using an LDAP store, see the sections immediately following:
  - [Specifying an LDAP user-record location](#) on page 765
  - [Entering an LDAP filter](#) on page 766
  - [Identifying provisioning attributes for LDAP](#) on page 767
- If you are using a Microsoft SQL Server, skip to this section:
  - [Choose a SQL method](#)

## Specifying an LDAP user-record location

After choosing a datastore, indicate where in the store PingFederate should write new user records or update existing ones.

About this task



### Note:

The **Location** tab appears only when an LDAP datastore is chosen on the **User Repository** tab.

Steps

Enter the base distinguished name (DN) in the **Base DN** field.


A base DN is the DN of the tree structure in which the search begins. Leave this field blank if records are located at the LDAP root.

### Entering an LDAP filter

On the **Unique User ID** tab, create an LDAP filter to identify user accounts to be provisioned or updated during single sign-on (SSO) events.

#### About this task

PingFederate uses this expression in conjunction with the **Base DN** value defined on the **Location** tab to locate existing account records and to add new ones.



#### Note:

This tab appears only when an LDAP datastore is chosen on the **User Repository** tab.

#### Steps

- Enter the statement in the **Filter** field.

The filter is in the form: `attribute=${value}`.



#### Note:

Unlike filters used to retrieve LDAP attributes for adapter mapping, do not enclose the statement in parentheses.

The left-side variable is an attribute in your user-datastore. Click the link near the lower-left corner of the tab to see a list of available attributes.

The right side of the filter uses one or more attribute values passed in from the SSO token. Variables for these attributes, including the correct syntax, are listed under **JIT Attributes**.



#### Tip:

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `${` and `}` in the default value.



#### Tip:

If you are unfamiliar with writing LDAP queries, see the documentation accompanying your LDAP installation.

## Identifying provisioning attributes for LDAP

On the **Attributes** tab, you can select the datastore attributes to be provisioned.

### About this task



#### Note:

This tab appears only when an LDAP datastore is chosen on the **User Repository** tab.

### Steps

1. Select a root object class and an attribute from the lists, and then click **Add Attribute**.
2. Repeat for each attribute requiring provisioning.

### Choosing a SQL method

PingFederate allows you to map attributes directly to a single database table, the default, or to SQL stored-procedure parameters for Java Database Connectivity (JDBC) datastores,

### About this task

Choose and configure the preferred method on the **SQL Method** tab.



#### Note:

This tab appears only when you specify Microsoft SQL Server datastore on the **User Repository** tab.

### Steps

- Make a selection as needed and click **Next**.

Depending on the selection, different steps appear under the **JIT Provisioning** task. See the sections indicated for more information.

- If mapping attributes directly to a table, see the topics sections immediately following:
  - [Specifying a database user-record location](#) on page 767
  - [Specifying a unique ID database column](#) on page 768
- If using a stored procedure, skip to [Specifying a stored procedure location](#) on page 769

### Specifying a database user-record location

For database provisioning to a table, you must indicate where PingFederate should write new user records or update existing ones.

### About this task

Configure the location settings on the **Location** tab.

**Note:**

This tab appears only when you choose a Microsoft SQL Server datastore on the **User Repository** tab and select the **Table** option on the **SQL Method** tab.

**Steps**

- On the **Location** tab, select the database schema and the table.

| Field                     | Description   |
|---------------------------|---|
| <b>Schema</b>             | Select the table structures that store information within the database.   |
| <b>Table</b>              | Select the name of the database table that contains user records.   |
| <b>Columns to fulfill</b> | <p>For the selected table, all attributes and their data types are displayed.</p> <p>If the list of columns is not current due to any recent changes, click <b>Refresh</b>.</p> <p>On the <b>Attribute Fulfillment</b> tab, all attributes must be mapped for the database insertion to succeed, although a null entry can be used for optional attributes.</p> |

**Tip:**

Click the link near the lower-left corner of the tab to see a list of available attributes from the single sign-on (SSO) token.

**Specifying a unique ID database column**

PingFederate uses the database column you specify on the **Unique ID** tab to check whether a user record already exists for the incoming single sign-on (SSO) token.

**About this task**
**Note:**

This tab only appears if you have chosen a Microsoft SQL Server datastore on the **User Repository** tab and you selected the **Table** option on the **SQL Method** tab.

**Steps**


- Select a column that represents a unique characteristic about the database entry for a particular user.



## Specifying a stored procedure location

If you are using a stored procedure for provisioning the user database, specify its location on the **Stored Procedure Location** tab.

### About this task



#### Note:

This window appears only when you have chosen a Microsoft SQL Server datastore on the **User Repository** tab and the you have selected the **Stored Procedure** option on the **SQL Method** tab.

### Steps

1. From the **Schema** menu, select the table structure that contains stored procedure within the database.
2. From the **Stored Procedure** menu, select the stored procedure needed to provision the user database.



#### Important:

The database account used by PingFederate must have access to the schema in which the stored procedure is located and execute permission for the procedure.

Result: For the selected procedure, all parameters and their data types display in the **Procedure parameters to fulfill** section.



#### Note:

To see a list of available attributes from the single sign-on (SSO) token, click **View Attribute Contract**.

You map attribute values from the SSO token to the parameters on the **Attribute Fulfillment** tab.

Troubleshooting:

If the list of parameters is not current due to any recent procedure revisions, click **Refresh**.

## Mapping attributes to a user account

Map incoming attributes to the account attributes on an LDAP server, the columns in a database table on a Microsoft SQL Server, or the parameters of a Microsoft SQL Server stored procedure.

### About this task

In addition to values obtained from the single sign-on (SSO) token, you can map attributes from the context of the SSO token text, with or without reference values from the SSO token, and expression if enabled.

If you select a Microsoft SQL Server datastore on the **User Repository** tab, then on the **Attribute Fulfillment** tab you can test the insertion of attribute values into the database table or the stored procedure. When mapping to a database column of the **datetime** or **smalldatetime** data type, if you are not using a stored procedure to convert the incoming string value, you can use a PingFederate Java conversion method through OGNL expressions.

## Steps

1. On the **Attribute Fulfillment** tab, select a source from the list for each target attribute or parameter. Choose from:

- **Assertion or Provider Claims**

Values are contained in the SSO token from this identity provider (IdP). When you select this, the associated **Value** list is populated by the attribute contract.

- **Context**

Values are returned from the context of the transaction at runtime.

 **Note:**

As the HTTP Request is retrieved as a Java object rather than text, OGNL expressions are more appropriate to evaluate and return values. Choose **Expression** from the list and then click **Edit** to enter an expression.

- **Attribute Query**

This choice appears only if you choose the **Attribute Query** profile for provisioning.

To map an attribute-query value, use the syntax `${query_attribute}`. You can combine attribute-query values with references to attributes in the attribute contract; for example, `${query_attribute}+${attribute}`.

References to attributes not contained in the attribute contract result in an attribute query back to the IdP partner.

- **Expression**

 **Tip:**

Enable OGNL expression by editing the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.ExpressionManager.xml` file. Restart after saving the change.

For a clustered environment, edit the `org.sourceid.common.ExpressionManager.xml` file on the console node, sign on to the administrative console to replicate this change to all engine nodes in the **System # Server # Cluster Management** window, and restart all nodes.

This option provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.

 **Tip:**

If you need to map multiple attribute values from one or multiple sources to one attribute value, use an OGNL expression to create it.

For database mapping, if the data type of a target parameter is **datetime** or **smalldatetime**, you can use an expression to convert date-time strings from the SSO token. After selecting **Expression**, click **Datetime OGNL Examples** for syntax information and examples.

- **System Managed**

This mapping option appears only when any automatically assigned attributes are among columns to be provisioned, such as an identity or a timestamp column on the Microsoft SQL Server.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the SSO token, using the `${attribute}` syntax.

 **Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use  `${ }` in the default value.

 **Note:**

For LDAP mapping, choose **Text** as the **Source** for the `objectClass` attribute.

For mapping into a database, if no entry is required for a column, you can leave the field blank. A blank entry results in an empty string in the database for string data types and null for all other data types. Alternatively, for string types, you can enter `null` in the field to explicitly set `null` in the column.

2. Select or enter an attribute value.

All values must be mapped. For optional table columns, you can leave the field blank or, for string data types, enter `null` to avoid empty strings.

No value is required for **System Managed** attributes.

 **Note:**

For **Active Directory**, enter `user` in the `objectClass` field. For Oracle Directory Server or Oracle Unified Directory, enter `inetOrgPerson`.

3. Optional: When mapping to a Microsoft SQL Server datastore, test the insertion.  
Choose from:

- If testing from a table:
  - a. Click **Test insert into** <table>.
  - b. Enter values for each applicable target parameter.
  - c. Click **Test Insert**.

If the test succeeds, a confirmation displays along with the values inserted.



#### CAUTION:

Unless you want to keep the test values in the database, click **Roll Back All Test Inserts**.

- If testing from a stored procedure:
  - a. Click **Test call to** <procedure>.
  - b. Enter values for each applicable target parameter.
  - c. Click **Test Stored Procedure Call**.

For stored procedures, only a confirmation displays if the test is successful, indicating that the procedure was populated with parameter values.



#### CAUTION:

No roll back feature is provided because PingFederate does not know the result of the procedure. Database rollback must be handled manually.


When finished, click **Return to Attribute Fulfillment**.

### Choosing an event trigger

Choose whether PingFederate initiates user provisioning only when the user identifier is new, or every time your site receives a single sign-on (SSO) token.

#### About this task

If you choose to have PingFederate initiate user provisioning every time your site receives an SSO token, for all SSO tokens, an existing user account is always updated with incoming attributes.



#### Note:

This tab does not appear for a Microsoft SQL Server datastore if provisioning is accomplished using a stored procedure, because the procedure is always called for all SSO tokens. The procedure should handle both provisioning new users and updating existing ones.

## Steps


- On the **Event Trigger** tab, in the **Specify the trigger that initiates a user-provisioning event** section, select one of the following:  
Choose from:
  - Only SAML Assertions Containing a New User ID**
  - All SAML Assertions**

## Configuring an error handling method

If user provisioning fails for any reason during single sign-on (SSO) events, you can choose to continue the process by passing the user's attributes to your target application or to abort the SSO transaction.

## About this task

When SSO is aborted, the user is redirected to an error page and the failure is written to the server log.



## Steps

- On the **Error Handling** tab, in the **How should the server handle a failure in a user provisioning request?** section, select one of the following:  
Choose from:
  - Send the User's Attributes to the Target Application**
  - Abort the SSO Transaction**

## Reviewing the JIT provisioning configuration

You can review your just-in-time (JIT) provisioning settings before completing configuration.

## Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Configuring SCIM inbound provisioning

In the **IdP Connections** window, configure System for Cross-domain Identity Management (SCIM) inbound provisioning to provide a two-way mapping of attributes.

## About this task


The first way facilitates SCIM operations used to create and update records in the datastore. The second way allows the same SCIM client to retrieve those records and have the attribute values mapped back to their corresponding designation in the client store. The dual mapping provides greater flexibility, especially for OGNL-expression transformations (for example, converting two attributes into one multivalued attribute and then back again). For more information, see [Writing user information to the datastore](#) on page 781 and [Configuring a SCIM response](#) on page 784.

**Note:**

SCIM-client requests must include authentication credentials, which you configure on the **Credentials # Back-Channel Authentication** tab. The same credentials needed for single sign-on (SSO), are also used for SCIM transactions.

## Steps

1. On the **Authentication # Integration # IdP Connections** window, create a new IdP connection or select an existing IdP connection.
2. On the **Connection Type** tab, select the **Inbound Provisioning** check box and one of the following options:  
Choose from:
  - **User Support**
  - **User and Group Support**
3. On the **Inbound Provisioning** tab, click **Configure Inbound Provisioning** to begin the configuration of SCIM inbound provisioning.

**Specifying the user repository**

PingFederate supports Active Directory (AD) user stores and custom identity store provisioners for inbound provisioning.

## About this task

Manage the datastore serving as the local repository on the **Repository** tab.

**Note:**

Active Directory user stores require an LDAPS connection to the datastore.

## Steps

- Choose one of the following options, and then specify the datastore from the list.  
Choose from:
  - Active Directory Data Store**
  - Identity Store Provisioner**



### Tip:

If the correct datastore is not shown in the list, then PingFederate is not configured to access the store. Click **Manage Data Stores** to set up the desired datastore.

## Identifying an LDAP user-record location

After choosing a datastore, you can indicate where in the datastore user and group records exist so PingFederate can create, read, update, or delete or disable them.

### About this task

These settings can be configured on the **Location** tab.



### Note:

This tab appears only if you are configuring an LDAP user store for provisioning.

## Steps

- Enter the base distinguished name (DN) of the tree structure where user records are stored in the **Base DN** field.



### Note:


PingFederate looks only at this node level or below it for user accounts that need provisioning

## Defining a unique user ID

On the **Unique user ID** tab, you can create an LDAP filter to resolve user accounts for System for Cross-domain Identity Management (SCIM) operations.

About this task

PingFederate uses LDAP filter in conjunction with the **Base DN** value, defined on the **Location** tab, to add new account records.



### Note:

This tab only appears if you are configuring an LDAP user store for provisioning.

## Steps

- Enter the statement in the **Filter** text field.

The filter is in the form: `attribute=${value}` where *attribute* is an attribute in your user-datastore and *value* is the attribute value or values passed in from the SCIM request. To see a list of available attributes in your user-datastore, click **View List of Available LDAP Attributes**. Variables for these attributes, including the correct syntax, are listed under **SCIM Attributes**.



### Note:

Unlike filters used to retrieve LDAP attributes for adapter mapping, do not enclose the statement in parentheses.



### Tip:

You can reference attribute values in the form of `${attributeName:-defaultValue}`. When specified, it is used at runtime if the attribute value is not available. Do not use `${` and `}` in the default value. This is optional.

If you are unfamiliar with writing LDAP queries, see the documentation accompanying your LDAP installation.


## Defining a unique group ID

On the **Unique Group ID** tab, you can create an LDAP filter to resolve groups for System for Cross-domain Identity Management (SCIM) operations.

About this task

PingFederate uses this LDAP filter in conjunction with the **Base DN** value, defined on the **Location** tab, to add new groups.



**Note:**

This tab appears only if you are configuring an LDAP user store for provisioning and you have selected the **User and Group Support** option on the **Connection Type** tab.

**Steps**

- Enter the statement in the **Filter** text field.

The filter is in the form: `attribute=${value}` where *attribute* is an attribute in your user-datastore and *value* is the attribute value or values passed in from the SCIM request. To see a list of available attributes in your user-datastore, click **View List of Available LDAP Attributes**. Variables for these attributes, including the correct syntax, are listed under **SCIM Attributes**.

**Note:**

Unlike filters used to retrieve LDAP attributes for adapter mapping, do not enclose the statement in parentheses.

**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value. This is optional.

If you are unfamiliar with writing LDAP queries, see the documentation accompanying your LDAP installation.

**Defining custom SCIM attributes**

When configuring System for Cross-domain Identity Management (SCIM) inbound provisioning, you can define custom attributes.

**About this task**

supports SCIM attributes in the core schema and custom attributes through a schema extension.

**Note:**

Custom attributes are optional. If your use case does not require any additional attributes, click **Next** on the **Custom SCIM Attributes** tab.

To support custom attributes, you must specify the schema extension and the custom attributes in the connection. There are four attribute types:


- Simple attributes
- Simple multivalued attributes

- Complex attributes
- Complex multivalued attributes

The following fragment illustrates a SCIM message supporting schema extension `urn:scim:schemas:extension:custom:1.0` with four attributes, one of each attribute type. The table afterward describes the details of each attribute.

```
{
  "userName": "CBrown",
  "active": true,
  "schemas": [
    "urn:scim:schemas:core:1.0",
    "urn:scim:schemas:extension:custom:1.0"
  ],
  ...
  "urn:scim:schemas:extension:custom:1.0": {
    "supervisor": "JSmith",
    "territories": [
      "Montana",
      "Idaho",
      "Wyoming"
    ],
    "options": {
      "quantity": "10000",
      "strike": "5.25",
      "first": "2017-12-01",
      "last": "2025-03-31"
    },
    "tablets": [
      {
        "model": "8086",
        "serial": "5500-2020-965",
        "type": "office"
      },
      {
        "model": "8088",
        "serial": "5500-2040-151",
        "type": "remote"
      }
    ]
  }
}
```

| Attribute Name     | Attribute Type      | Sub-Attributes (Complex)   |
|--------------------|---------------------|--|
| <b>supervisor</b>  | Simple              | Not applicable   |
| <b>territories</b> | Simple multivalued  | Not applicable   |
| <b>options</b>     | Complex             | <b>quantity</b> , <b>strike</b> , <b>first</b> , and <b>last</b> |
| <b>tablets</b>     | Complex multivalued | <b>model</b> , <b>serial</b> , and <b>type</b> .                 |

 **Note:**


**type** is a reserved sub-attribute for a complex multivalued attribute.

 **Tip:**

For more information about SCIM and attribute types, see the website [www.simplecloud.info](http://www.simplecloud.info).

## Steps

Go to the **Custom SCIM Attributes** tab.



Choose from:

- To specify a schema extension, enter the URI of the schema extension in the **Extension Namespace** field



### Tip:

The default value is `urn:scim:schemas:extension:custom:1.0`. You can keep this value if your partner identifies custom attributes by this URI in its SCIM messages.

- To add a custom attribute, enter an attribute name and click **Add**. Repeat this step to add more custom attributes as needed.
- To delete a custom attribute, click **Delete** next to the custom attribute.
- To undo the deletion, click **Undelete**.
- To edit a custom attribute, click **Edit** next to the custom attribute.

Result:

The administrative console displays the **Custom SCIM Attribute Options** tab, where you can:

- Change the attribute name.
- Set the attribute as a simple multivalued attribute.
- Add sub-attributes to make it a complex attribute.
- Add sub-attributes and set the attribute as a complex multivalued attribute.

For more information, see [Configuring custom SCIM attribute options](#) on page 779.

### *Configuring custom SCIM attribute options*

After choosing a custom System for Cross-domain Identity Management (SCIM) attribute on the **Custom SCIM Attribute** tab, you can use the **Custom SCIM Attribute Options** tab to configure the attribute.

### About this task

On this tab you can change the attribute name, set the attribute as a simple multivalued attribute, add sub-attributes to make it a complex attribute, and add sub-attributes and set the attribute as a complex multivalued attribute.

## Steps

Go to the **Custom SCIM Attribute Options** tab.

Choose from:

- To change the name of the custom attribute, replace the current value in the **Name** field, and then click

Custom SCIM Attribute Configuration. You are presented with options to make the attribute complex and/or multi-valued.

NAME: [text field] Action: [Edit | Delete]

Sub-Attributes: [text field] Action: [Add]

IS MULTI-VALUED

Cancel Done

**Done.**

- To define the custom attribute as a simple multi-valued attribute, select the **Is Multi-valued** check box,

Custom SCIM Attribute Configuration. You are presented with options to make the attribute complex and/or multi-valued.

NAME: [text field] Action: [Edit | Delete]

Sub-Attributes: [text field] Action: [Add]

IS MULTI-VALUED

Types: [text field] Action: [Add]

Cancel Done

and then click **Done.**

- To define the custom attribute as a complex attribute, enter a sub-attribute, and then click **Add**. Repeat this step to add more sub-attributes as needed, and then click **Done**.



**Tip:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to the name of a sub-attribute. Click **Delete** or **Undelete** to remove a sub-attribute or cancel the deletion.

Custom SCIM Attribute Configuration. You are presented with options to make the attribute complex and/or multi-valued.

NAME: [text field] Action: [Edit | Delete]

Sub-Attributes:

- quantity: [text field] Action: [Edit | Delete]
- write: [text field] Action: [Edit | Delete]
- read: [text field] Action: [Edit | Delete]
- test: [text field] Action: [Add]

IS MULTI-VALUED

Cancel Done

- To define the custom attribute as a complex multi-valued attribute, follow these steps.
  - a. Enter a sub-attribute, and then click **Add**. Repeat this step to add more sub-attributes as needed.



**Tip:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to the name of a sub-attribute. Click **Delete** or **Undelete** to remove a sub-attribute or cancel the deletion.

- b. Select the **Is Multi-valued** check box.
- c. If you have chosen Active Directory as your user store, you must specify at least one value in the **Types** section for `type`, a reserved sub-attribute for a complex multi-valued attribute. For more information, see [Specifying the user repository](#) on page 774
- d.

Custom SCIM Attribute Configuration. You are presented with options to make the attribute complex and/or multi-valued.

NAME: [text field] Action: [Edit | Delete]

Sub-Attributes:

- model: [text field] Action: [Edit | Delete]
- serial: [text field] Action: [Add]

IS MULTI-VALUED

Types:

- type: [text field] Action: [Edit | Delete]
- [text field] Action: [Add]

Cancel Done Save


Click **Done.**

## Writing user information to the datastore

To configure how PingFederate completes create and update operations for user accounts from a System for Cross-domain Identity Management (SCIM) request, identify incoming attributes and map them to datastore attributes.

### Steps

On the **Write Users** tab, click **Configure Write Users** to continue.



### Identifying inbound provisioning attributes for LDAP

When configuring System for Cross-domain Identity Management (SCIM) inbound provisioning, you must identify the attributes you want to provision.


### About this task

You can select the datastore attributes you want to provision on the **Attributes** tab.



#### Note:

This tab appears only if you are configuring an LDAP user store for provisioning.



The following attributes are managed internally by PingFederate and do not require mapping:

- **objectClass**
- **unicodePwd**
- **objectGUID**
- **userAccountControl**


You can override the internal management of **objectClass** and **unicodePwd** by selecting these attributes and mapping them to SCIM attributes on the **Attribute Fulfillment** tab. In this case, the values you supply are used. The **objectGUID** and **userAccountControl** attributes cannot be overridden and are ignored if selected.

### Steps

1. Select a root object class and an attribute from the lists, then click **Add Attribute**.

 **Important:**

Do not add **cn** as one of the attributes.



2. Repeat the previous step for each attribute requiring provisioning.

### Mapping attributes to user accounts

Map attribute values in the System for Cross-domain Identity Management (SCIM) request to user-account attributes.

#### About this task

IdP Connection | Inbound Provisioning | Write Users

Attribute Fulfillment

Map attribute Sources and Values for each user repository attribute that should be populated.

| Target Attribute | Source | Value | Actions        |
|------------------|--------|-------|----------------|
| displayName      | SELECT |       | None available |
| givenName        | SELECT |       | None available |
| mail             | SELECT |       | None available |
| sn               | SELECT |       | None available |

Cancel Save Previous Next

#### Steps

1. On the **Attribute Fulfillment** tab, for each attribute, select a source from the **Source** list and then choose or enter a value. You must map all attributes.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.



**Note:**

As the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.



**Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added `PERSISTENT_GRANT_LIFETIME` as an extended attribute in the **Authorization Server Settings**

window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **Expression**



**Tip:**

Enable OGNL expression by editing the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.ExpressionManager.xml` file. Restart after saving the change.

For a clustered environment, edit the `org.sourceid.common.ExpressionManager.xml` file on the console node, sign on to the administrative console to replicate this change to all engine nodes in the **System # Server # Cluster Management** window, and restart all nodes.

This option provides more complex mapping capabilities, such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.



**Tip:**

If two attribute values from a SCIM request need to be mapped to one LDAP attribute value, use an OGNL expression to create it.

- **SCIM User**

When you make this selection, the associated **Value** list populates with defined components of the SCIM request.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the SCIM request using the `${attribute}` syntax.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

2. Click **Done**.

### *Reviewing user mapping (Write Users) configuration*

You can review your user mapping settings before completing configuration.

About this task

The **Summary** tab provides an overview of the inbound provisioning configuration for request mapping.

Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.


- To discard your changes, click **Cancel**.

## **Configuring a SCIM response**

To configure a System for Cross-domain Identity Management (SCIM) response to a request to read and return provisioned SCIM attributes, identify and map the user account attributes you want to include.

About this task

Begin this process on the **Read Users** tab.



Steps

On the **Read Users** tab, click **Configure Read Users** to continue.


### *Identifying expected user attributes for the SCIM response*

An attribute contract is a set of user attributes that you and your partner agree will be sent in a System for Cross-domain Identity Management (SCIM) response for this connection.

About this task

On the **Attribute Contract** tab, the attributes you mapped to user account attributes on the **Write Users** tab appear under **Attribute Contract**.






Optionally, you can mask the values of attributes in the log files that PingFederate writes when it sends the SCIM response.

There are multiple SCIM attributes that are managed internally by PingFederate and are unavailable for inclusion in the attribute contract:

- **id**
- **active**

### Steps


Click **Available SCIM Attributes** near the lower-left corner of the tab to include additional attributes you want to map in the SCIM response.

| Option  | Action  |
|---|---|
| <p><b>Add an attribute</b></p>                              | <p>Enter the attribute name in the text box, select the check box under <b>Mask Values in Log</b> as needed, then click <b>Add</b>.</p> <p>Attribute names are case-sensitive and must correspond to the attribute names expected by your partner. To see a list of available attributes, click <b>Available SCIM attributes</b>.</p>   |
| <p><b>Modify an attribute name or masking selection</b></p> | <p>Click <b>Edit</b> under <b>Action</b> for the attribute, make the change, then click <b>Update</b>.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If you change your mind, make sure you click <b>Cancel</b> under <b>Actions</b>, not the <b>Cancel</b> button, which discards any other changes you might have made in the configuration steps.</p> </div> |
| <p><b>Delete an attribute</b></p>                           | <p>Click <b>Delete</b> under <b>Action</b> for the attribute.</p>   |

### Identifying LDAP attributes for the SCIM response

On the **Attributes** tab, you can select the LDAP attributes you want to map to attributes in the System for Cross-domain Identity Management (SCIM) response.

### About this task



 **Note:**

This tab appears only if you are configuring an LDAP user store for provisioning.

#### Steps

1. Select a root object class and an attribute from the lists, then click **Add Attribute**.
2. Repeat for each attribute requiring provisioning.

#### *Mapping attributes into the SCIM response*

Map outgoing user-account attributes to System for Cross-domain Identity Management (SCIM) responses to READ requests.

#### Steps

1. On the **Attribute Fulfillment** tab, for each target attribute, select a source from the **Source** list, then choose or enter a value. All target attributes must be mapped.  
Choose from:

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.

**Note:**

Because the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.

**Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added `PERSISTENT_GRANT_LIFETIME` as an extended attribute in the **Authorization Server**

**Settings** window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **Expression**

This option provides more complex mapping capabilities, such as transforming outgoing values into different formats. All of the variables available for text entries are also available for expressions.



**Tip:**

If you need to map an LDAP attribute to two attributes in a SCIM response, use an OGNL expression to create them.



**Tip:**

Enable OGNL expression by editing the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.ExpressionManager.xml` file. Restart after saving the change.

For a clustered environment, edit the `org.sourceid.common.ExpressionManager.xml` file on the console node, sign on to the administrative console to replicate this change to all engine nodes in the **System # Server # Cluster Management** window, and restart all nodes.

- **LDAP**

Values are returned from your query. When you make this selection, the **Value** list populates with the LDAP attributes you identified for this datastore.

- **Identity Store**

Values are returned from your query. When you make this selection, the **Value** list populates with the Identity Store attributes you identified for this datastore.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the SCIM request, using the `${attribute}` syntax.

**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use ``${` and `}`` in the default value.

2. Click **Done**.*Reviewing SCIM response (Read Users) configuration*

You can review your System for Cross-domain Identity Management (SCIM) response mapping before completing configuration.

## About this task

The **Summary** tab provides an overview of the inbound provisioning configuration for SCIM response mapping.

## Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.


**Configuring the handling of SCIM delete requests**

You can use the **Delete/Disable Users** tab to define how System for Cross-domain Identity Management (SCIM) delete requests are handled within your user datastore.

## About this task

**Important:**

If the group support option is enabled, when PingFederate receives a SCIM delete request for a group, it always removes the specified group from the datastore.

**Note:**

This tab appears only if you are configuring an LDAP user store for provisioning.

## Steps

Click one of the two available options for **SCIM DELETE message behavior**.  
Choose from:

- Click **Disable User** to make the user inactive within the datastore. This approach is preferred in situations where accounts must be retained for auditing reasons.

To be SCIM compliant when deleting users, PingFederate returns an HTTP 404 response code for all subsequent operations related to the user-effectively treating the user as if they have been deleted from the LDAP user store. For more information, see [SCIM specifications](#).



### CAUTION:

If the user is disabled through another method, PingFederate still treats that user as if they have been deleted and returns HTTP 404 response codes for all subsequent requests.


- Click **Permanently Delete User** to remove the user from the datastore.

## Writing group information to the datastore

To configure how PingFederate completes create and update operations for groups from a System for Cross-domain Identity Management (SCIM) request, identify incoming attributes and map them to datastore attributes.

### About this task

You can identify and map these attributes on the **Write Groups** tab.



### Steps


Click **Configure Write Groups** to continue.

### Identifying inbound provisioning group attributes for LDAP

You must identify the datastore attributes you want to provision when writing group information to the datastore.

### About this task

You can identify these attributes on the **Attributes** tab.



### Note:

This tab only appears if you are configuring an LDAP user store for provisioning and the **User and Group Support** option is selected on the **Connection Type** tab.

PingFederate internally manages several attributes that do not require mapping:

- **objectClass**
- **objectGUID**
- **member**

You can override the internal management of **objectClass** by selecting and mapping it to a System for Cross-domain Identity Management (SCIM) attribute on the **Attribute Fulfillment** tab. In this case,

the values you supply are used. The `objectGUID` and member attributes cannot be overridden and are ignored if selected.

#### Steps

1. Select a root object class and an attribute from the lists, and then click **Add Attribute**.
2. Repeat the previous step for each attribute requiring provisioning.

#### *Mapping attributes to groups*

Map attribute values in the System for Cross-domain Identity Management (SCIM) request to group attributes.

#### About this task

#### Steps

1. On the **Attribute Fulfillment** tab, for each attribute, select a source from the list and then choose or enter a value. You must map all target attributes.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.



**Note:**

As the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.



**Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added `PERSISTENT_GRANT_LIFETIME` as an extended attribute in the **Authorization Server Settings**

window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **Expression**

This option provides more complex mapping capabilities ,such as transforming incoming values into different formats. All of the variables available for text entries are also available for expressions.



**Tip:**

If you need to map two attribute values from a SCIM request to one LDAP attribute value, use an OGNL expression to create the LDAP attribute.



**Tip:**

Enable OGNL expression by editing the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.ExpressionManager.xml` file. Restart after saving the change.

For a clustered environment, edit the `org.sourceid.common.ExpressionManager.xml` file on the console node, sign on to the administrative console to replicate this change to all engine nodes in the **System # Server # Cluster Management** window, and restart all nodes.

- **SCIM Group**

When you make this selection, the associated **Value** list populates with the defined components of the SCIM request.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the SCIM request, using the `${attribute}` syntax.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

2. Click **Done**.

### Reviewing group mapping (Write Groups) configuration

You can review your group mapping settings before completing configuration.

### About this task

The **Summary** tab provides an overview of the inbound provisioning configuration for request mapping.

### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.


- To discard your changes, click **Cancel**.

## Configuring a SCIM response for groups

To configure a System for Cross-domain Identity Management (SCIM) response to a request to read and return provisioned SCIM attributes, identify and map the group attributes you want to include.

### About this task

You can begin to identify and map these attributes on the **Read Groups** tab.



### Steps


- Click **Configure Read Groups** to continue.

### Identifying expected group attributes for the SCIM response

On the **Attribute Contract** tab, you can identify the group attributes for you and your partner.

### About this task

An attribute contract is a set of group attributes that you and your partner have agreed will be sent in a System for Cross-domain Identity Management (SCIM) response for this connection. The attributes you mapped to group attributes on the **Write Groups** tab appear at the top of the tab.





Click **Available SCIM Attributes** near the lower-left corner of the tab to include additional attributes you want to map in the SCIM response.

Optionally, you can mask the values of attributes in the log files that PingFederate writes when it sends the SCIM response.

There are several SCIM attributes that are managed internally by PingFederate and are unavailable for inclusion in the attribute contract:

- **id**
- **members**

### Steps

To add an attribute, enter the attribute name in the text box, select the check box under **Mask Values in Log** as needed, and click **Add**.



#### Note:


Attribute names are case-sensitive and must correspond to the attribute names expected by your partner. To see a list of available attributes, click **Available SCIM attributes**.

| Choice   | Action   |
|--|--|
| <b>Modify an attribute name or masking selection</b> | Click <b>Edit</b> under <b>Action</b> for the attribute, make the change, then click <b>Update</b> .<br><br><b>Note:</b><br>If you change your mind, ensure that you click <b>Cancel</b> under <b>Actions</b> and not the <b>Cancel</b> button, which discards any other changes you might have made in the configuration steps. |
| <b>Delete an attribute</b>                           | Click <b>Delete</b> under <b>Action</b> for the attribute.   |

### Identifying LDAP group attributes for the SCIM response

On the **Attributes** tab, select the LDAP attributes you want to map to attributes in the System for Cross-domain Identity Management (SCIM) response.

### About this task



#### Note:

This tab only appears if you are configuring an LDAP user store for provisioning and the **User and Group Support** option is selected on the **Connection Type** tab.

### Steps

1. Select a root object class and an attribute from the lists, and then click **Add Attribute**.

2. Repeat the previous step for each attribute requiring provisioning.

### Mapping group attributes into SCIM response

Map outgoing group attributes to System for Cross-domain Identity Management (SCIM) responses to READ requests.

#### About this task

#### Steps

1. On the **Attribute Fulfillment** tab, for each attribute, select a source from the **Source** list and then choose or enter a value. You must map all attributes.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list.



**Note:**

As the **HTTP Request** context value is retrieved as a Java object rather than text, use OGNL expressions to evaluate and return values.



**Note:**

If you are configuring an **OAuth Attribute Mapping** configuration and have added `PERSISTENT_GRANT_LIFETIME` as an extended attribute in the **Authorization Server Settings**

window, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions or the per-client **Persistent Grants Max Lifetime** setting.

- To set lifetime based on the per-client **Persistent Grants Max Lifetime** setting, select **Context** from the **Source** list and **Default Persistent Grant Lifetime** from the **Value** list.
- To set lifetime based on the outcome of attribute mapping expressions, select **Expression** as the source and enter an OGNL expression in the **Value** field.

If the expression returns a positive integer, the value represents the lifetime of the persistent grant in minutes.

If the expression returns the integer 0, does not store the grant and does not issue a refresh token.

If the expression returns any other value, sets the lifetime of the persistent grant based on the per-client **Persistent Grants Max Lifetime** setting.

- To set a static lifetime, select **Text** from the **Source** list and enter a static value in the **Value** field.

This is suitable for testing purposes, or cases where the persistent grant lifetime must always be set to a specific value.

- **Expression**



**Tip:**

Enable OGNL expression by editing the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.common.ExpressionManager.xml` file. Restart after saving the change.

For a clustered environment, edit the `org.sourceid.common.ExpressionManager.xml` file on the console node, sign on to the administrative console to replicate this change to all engine nodes in the **System # Server # Cluster Management** window, and restart all nodes.

This option provides more complex mapping capabilities, transforming outgoing values into different formats. All of the variables available for text entries are also available for expressions.



**Tip:**

If an LDAP attribute needs to be mapped to two attributes in a SCIM response, use an OGNL expression to create them.

- **LDAP**

Values are returned from your query. When you make this selection, the **Value** list populates with the LDAP attributes you identified for this datastore.

- **Identity Store**

Values are returned from your query. When you make this selection, the **Value** list populates with the Identity Store attributes you identified for this datastore.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

The value is what you enter. This can be text only, or you can mix text with references to any of the values from the SCIM request, using the `${attribute}` syntax.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.

## 2. Click **Done**.

### *Reviewing SCIM response for groups (Read Groups) configuration*

You can review your System for Cross-domain Identity Management (SCIM) settings before completing configuration.

#### About this task

The **Summary** tab provides an overview of the inbound provisioning configuration for SCIM response mapping.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### **Reviewing the inbound provisioning configuration**

You can review your inbound provisioning settings before completing the configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### **Configuring security credentials**

You can configure security credentials and requirements as needed.

#### About this task

The **Credentials** tab provides the launching point for configuring security requirements you might need depending on the federation protocol you are using and the choices you have made.

## Steps

- To continue, click **Configure Credentials**.

For more information and configuration steps see:

- [Configuring back-channel authentication for outbound messages](#) on page 797
- [Configuring back-channel authentication for inbound messages](#) on page 798
- [Configuring digital signatures for identity provider connections](#) on page 800
- [Managing signature verification settings](#) on page 801
- [Choosing an encryption certificate \(SAML 2.0\)](#) on page 803
- [Choosing a decryption key \(SAML 2.0\)](#) on page 804
- [Reviewing IdP credential settings](#) on page 804
- [Reviewing an IdP connection](#) on page 804

## IdP connection management

When configuring a profile for the inbound artifact binding, outbound SOAP binding, or provisioning, you must specify back-channel authentication information for sending SOAP messages, artifact resolution requests, and provisioning requests to your partner identity provider (IdP).

Similarly, if you send artifacts, SOAP messages, or provisioning messages to your partner IdP, then you must configure SOAP authentication requirements for receiving SOAP responses, artifact resolution requests, or provisioning requests from your partner.

Back-channel authentication also applies to attribute-request configurations, because this profile always uses the SOAP back channel.

See [Configuring back-channel authentication for outbound messages](#) on page 797 and [Configuring back-channel authentication for inbound messages](#) on page 798 for configuration steps.

### *Configuring back-channel authentication for outbound messages*

You can add and edit configuration settings for back-channel authentication for outbound messages.

## Steps

1. On the **Back-Channel Authentication** tab, in the **Send to your partner** section, click **Configure**.
2. On the **Outbound SOAP Authentication Type** tab, choose one or more authentication methods.

### HTTP Basic

When selected, the administrative console prompts you to enter the credentials on the **Basic SOAP Authentication (Outbound)** tab.

You must obtain these credentials from your partner.

### SSL Client Certificate

Applicable only if you specify an endpoint that uses HTTPS.

When selected, the administrative console prompts you to specify your client certificate on the **SSL Authentication Certificate** tab. If you have not yet created or imported the client certificate, click **Manage Certificates** to do so. For more information, see .



### **Important:**

When exporting this client certificate for your partner, choose the **Certificate Only** option.

### Digital Signature (Browser SSO profile only)

You select a signing certificate on the **Digital Signature Settings** tab.

This option leverages on the digital signature of the message.

Perform validation on partner's SSL server certificate when SSL used

By default, validates your partner's HTTPS server certificate, verifying that the certificate chain is rooted by a trusted certificate authority (CA) and that the hostname matches the certificate's common name (CN).

Clear the associated check box if you do not want this validation to occur.

These options can be used in any combination or independently.

3. On the **Summary** tab, review your configuration and perform one of the following tasks:

Choose from:

- Amend your configuration by clicking the corresponding tab title, then follow the configuration wizard to complete the task.
- Keep your changes by clicking **Done** and continue with the rest of the configuration.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- Discard your changes by clicking **Cancel**.

#### *Configuring back-channel authentication for inbound messages*

You can add and edit configuration settings for back-channel authentication for inbound messages.

#### Steps

1. On the **Back-Channel Authentication** tab, in the **Received from your partner** section, click **Configure**.
2. On the **Inbound Authentication Type** tab, choose one or more authentication methods.

#### HTTP Basic

When selected, the administrative console prompts you to enter the credentials on the **Basic SOAP Authentication (Inbound)** tab.



**Important:**

If you are configuring more than one connection that uses the artifact or HTTP profile, you must ensure that the username is unique for each connection. You must communicate these credentials to your partner out-of-band.

#### SSL Client Certificate

When selected, the administrative console prompts you to specify the trust model and the related certificate settings on subsequent windows. See the next step.

#### Digital Signature (Browser SSO profile only)

You select a signing certificate on the **Signature Verification Settings** tab.

This option leverages on the digital signature of the message.

#### Require SSL

When selected, incoming HTTP transmissions must use a secure channel. This option is selected by default.

You can clear the check box if you do not require a secure channel and client certificate authentication.

For SAML 2.0, use these options in any combination or independently. For SAML 1.x, you must enable HTTP Basic authentication, client certificate authentication, or both. You can also add digital signing to ensure message integrity.

3. If you chose **SSL Client Certificate** in the previous step, select a trust model on the **Certificate Verification Method** tab.

#### Anchored

The partner certificate must be signed by a trusted certificate authority (CA). Optionally, you can also restrict the issuer to a specific Trusted CA to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections. The CA's certificate must be imported into the Trusted CA store on the **Trusted CAs** window..

#### Unanchored

The partner certificate is self-signed or you want to trust a specified certificate.



#### Note:

When anchored certificates are used between partners, certificates can be changed without sending the update to your partner. If the certificate is unanchored, any changes must be promulgated.

For more information, see .

| Trust model | Subsequent steps   |
|-------------|--|
| Anchored    | <p>On the <b>Subject DN</b> tab:</p> <ol style="list-style-type: none"> <li>Enter the <b>subject DN</b> of the certificate.</li> <li>Optionally, select the <b>Restrict Issuer</b> check box and enter the <b>Issuer DN</b> of the certificate.</li> </ol> <div data-bbox="625 1201 667 1247" data-label="Image"> </div> <div data-bbox="672 1213 813 1247" data-label="Section-Header"> <h4>Important:</h4> </div> <div data-bbox="618 1260 1461 1354" data-label="Text"> <p>Consider enabling this option to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections.</p> </div> |
| Unanchored  | <p>On the <b>SSL Verification Certificate</b> tab, select the client certification from your partner.</p> <p>If you have not yet imported the client certificate from your partner, click <b>Manage Certificates</b> to do so. For more information, see .</p>   |

4. On the **Summary** tab, review your configuration and perform one of the following tasks:

Choose from:

- Amend your configuration by clicking the corresponding tab title, then follow the configuration wizard to complete the task.
- Keep your changes by clicking **Done** and continue with the rest of the configuration.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- Discard your changes by clicking **Cancel**.

### Configuring digital signatures for identity provider connections

Managing digital signature settings defines the private key you will use to sign single sign-on (SSO) authentication or attribute requests (optionally) or SAML 2.0 single logout (SLO) messages for this identity provider (IdP).

#### About this task

This process allows you to include Key Info with the XML message if you and your partner have agreed to this option.

Digital signing applies to service provider (SP)-initiated SSO under SAML 2.0, when specified by your partner agreement, and to either SLO profile using the POST or redirect bindings. Digital signing also applies if you are configuring an Attribute Query profile and have specified that you will sign attribute requests.

The step is not required for SAML 1.x IdP connections.

#### Steps

1. On the **Digital Signature Settings** tab, select a signing certificate from the **Signing Certificate** list.  
If you have not yet created or imported your certificate into PingFederate, click **Manage Certificates**. For more information, see [Manage digital signing certificates and decryption keys](#) on page 667.
2. Optional: Select a **Secondary Signing Certificate** for inclusion in the connection metadata.



**Note:**

You can't add a secondary certificate if the primary certificate has certificate rotation enabled. Also, you can't use a certificate that has rotation enabled as the secondary signing certificate.

3. Optional: Select the **Include the certificate in the signature <KeyInfo> element** check box if you have agreed to send your public key with the message.

Select the **Include the raw key in the signature <KeyValue> element** check box if your partner agreement requires it.

4. Optional: Select the signing algorithm from the list.

The default selection is **RSA SHA256** or **ECDSA SHA256**, depending on the **Key Algorithm** value of the selected digital signing certificate. Make a different selection if you and your partner have agreed to use a stronger algorithm.



## Managing signature verification settings

Under SAML 2.0 specifications, when your site receives any SAML 2.0 messages with the POST or Redirect bindings, the messages must be digitally signed.

### About this task

Signing is also always required for the SAML 1.x POST binding and for WS-Federation assertions, as well as incoming SAML 1.1 or 2.0 tokens for WS-Trust STS processing.

Depending on your agreement with this identity provider (IdP), single sign-on (SSO) assertions, SAML 2.0 artifacts, or SOAP messages might also require signatures.

### Steps

1. On the **Signature Verification Settings** tab, click **Manage Signature Verification Settings**.
2. On the **Trust Model** tab, select a trust model on the **Certificate Verification Method** tab.

#### Anchored

The partner certificate must be signed by a trusted certificate authority (CA). Optionally, you can also restrict the issuer to a specific Trusted CA to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections. The CA's certificate must be imported into the PingFederate Trusted CA store in the **Security # Certificate & Key Management # Trusted CAs** window.



#### Important:

If you are using the redirect binding for single logout (SLO) or establishing an OAuth assertion grant connection to exchange JSON web tokens (JWTs) for access tokens, you cannot use anchored certificates because SAML 2.0 does not permit certificates to be included using this transport method and the signature verification process for JWTs requires the public keys to validate the digital signatures.




#### Unanchored

The partner certificate is self-signed or you want to trust a specified certificate.

 **Note:**

When anchored certificates are used between partners, certificates can be changed without sending the update to your partner. If the certificate is unanchored, any changes must be promulgated.

For more information, see [Digital signing policy coordination](#) on page 97.

| Trust model | Subsequent steps  |
|-------------|---|
| Anchored    | <p>On the <b>Subject DN</b> window:</p> <ol style="list-style-type: none"> <li>Enter the <b>Subject DN</b> of the certificate or extract it from your service provider (SP) partner's certificate if the certificate is stored on an accessible file system.</li> <li>(Optional) Select the <b>Restrict Issuer</b> check box and enter the <b>Issuer DN</b> of the certificate. Alternatively, extract it from your partner's certificate.</li> </ol> <div data-bbox="617 766 1474 974" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>Consider enabling this option to mitigate potential man-in-the-middle attacks and to provide a means to isolate certificates used by different connections.</p> </div>  |
| Unanchored  | <p>On the <b>Signature Verification Certificate</b> window:</p> <ol style="list-style-type: none"> <li>Select a certificate from the list.</li> </ol> <p>If you have not yet imported the certificate from your partner, click <b>Manage Certificates</b> to do so. See <a href="#">Managing certificates from partners</a> on page 681.</p> <ol style="list-style-type: none"> <li>(Optional) Select additional certificates.</li> </ol> <div data-bbox="617 1239 1474 1446" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When configured, PingFederate considers a digital signature valid so long as it can verify the signature using one of the certificates from this list.</p> </div> <div data-bbox="617 1459 1474 1852" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>This is useful in situations where your partner has sent you a certificate to replace the current certificate. Adding this second certificate allows PingFederate to continue validating digital signatures as the partner switches to the new signing certificate.</p> <p>It also adds support for the scenario where your partner uses a pool for certificates to sign its messages. Adding these certificates ensures digital signatures can be validated as the partner rotates its signing certificates.</p> </div> |

- On the **Summary** tab, review your configuration and perform one of the following tasks.

Amend your configuration

Click the corresponding tab title and then follow the configuration wizard to complete the task.

Keep your changes

Click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

Discard your changes

Click **Cancel**.

### Choosing an encryption certificate (SAML 2.0)

If **SAML\_SUBJECT** is encrypted, either by itself or as part of a whole assertion, then all references to this name identifier in SAML 2.0 single logout (SLO) requests from your site might also be encrypted if the connection uses service provider (SP)-initiated SLO.

About this task

You must also choose a certificate if encryption of the name identifier is required for an Attribute Request profile. For more information, see [Specifying XML encryption policy \(for SAML 2.0\)](#) on page 760.

Steps

- Optional: Select an option under **Block Encryption Algorithm**.

 **Important:**

Because of the import restrictions of some countries, Oracle Server Java SE Runtime Environment (JRE) 8 has built-in restrictions on available cryptographic strength (key size). To use larger key sizes, enable the Java Cryptography Extension (JCE) unlimited strength jurisdiction policy. For more information, see the Java 8 release notes in Oracle's documentation.

For Oracle Java SE Development Kit 11, the JCE jurisdiction policy defaults to unlimited strength. For more information, see the Oracle JDK Migration Guide in Oracle's documentation.

The default selection is **AES-128**.

For more information about XML block encryption and key transport algorithms, see XML Encryption Syntax and Processing from W3C.

- Select an option under **Key Transport Algorithm**.

 **Note:**

Due to security risks associated with the RSA-v1.5 algorithm used for key transport, it is no longer available for new connections. Existing connections in which this algorithm is configured continue to support it. However, you should upgrade such connections to use the newer algorithm **RSA-OAEP**.

The default selection is **RSA-OAEP**.

3. Select a partner certificate from the list.

If you have not imported the certificate from your partner, click **Manage Certificates** to do so. For more information see [Managing certificates from partners](#) on page 681.

### Choosing a decryption key (SAML 2.0)

As part of XML encryption, you must identify a certificate and key for PingFederate to use to decrypt incoming assertions or assertion elements.

About this task

For more information on XML encryption, see [Specifying XML encryption policy \(for SAML 2.0\)](#) on page 760.

Steps

1. Select the primary XML decryption key from the list.

If you have not created or imported your certificate into , click **Manage Certificates**. For more information, see .

2. Optional: Select the secondary XML decryption key from the list.

### Reviewing IdP credential settings

You can review chosen credential settings before completing configuration.

Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Reviewing an IdP connection

When you finish creating or modifying a connection, you can review the connection settings and toggle the connection status on the **Activation & Summary** tab.

About this task



#### Important:

When creating a new connection, the default connection status is **Enabled** when you reach the **Activation & Summary** tab.

Regardless of whether you choose to disable a new connection now or later, you must click **Save** on the **Activation & Summary** tab if you want to keep the new connection.

Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## Result

The **SSO Application Endpoint** provides a sample URL at the `/sp/startSSO.ping` application endpoint that webmasters or web application developers at your site might use to invoke single sign-on (SSO) for the connection. For a list of supported parameters, see [Viewing SP application endpoints](#) on page 720.

If you have selected the **No Mapping** option on the **Identity Mapping** tab, the **Summary & Activation** tab does not show the **SSO Application Endpoint** sample URL.

## OpenID Connect Relying Party support

PingFederate can leverage identities from OpenID Providers (OPs) to complete browser single sign-on (SSO) requests.

In this use case, PingFederate is an OAuth client, specifically a relying party (RP) to the OP. PingFederate supports both the Basic Client and the Implicit Client profiles.

The setup involves establishing an IdP connection to the OP. PingFederate retrieves identity information from the OP and passes the end-user claims, which are user attributes in an ID token, to one or more target applications. This configuration allows administrators to take advantage of their existing last-mile integration and expand the horizon of their applications to additional partners using the OpenID Connect protocol.

If the OP supports the OpenID Connect Discovery specification, the connection setup is expedited by loading the metadata from the OP. PingFederate makes a direct HTTP GET request to the `/.well-known/openid-configuration` endpoint at the OP and populates the attribute contract and the protocol settings of the connection automatically. Manual adjustments can be made during the connection setup or at a later time.

Additionally, you can refresh the protocol settings by reloading the metadata from the OP at any time. If additional claims are supported, PingFederate adds them to the attribute contract, so that they can be mapped to the target applications later. In the event that the previously supported claims have been dropped by the OP from the metadata, they remain in the attribute contract. While the existing mapping configuration might not be adversely affected, runtime errors might occur if certain attributes are no longer available to the target applications. If runtime errors occur, review the server log and modify the mapping configuration accordingly.

If applicable, administrators can define additional request parameters, which can be included in the authentication requests to support OP-specific use cases. Administrators can restrict the values to those defined in the configuration. Alternatively, administrators can allow the target applications to optionally override the values at runtime. As an added security measure, administrators can protect the requested authentication context, `acr_values`, and authentication requirement, `prompt`, so that these parameters in the authentication requests cannot be overridden by the target applications. By default, PingFederate sends these request parameters through multiple query parameters unsigned. Optionally, administrators can configure PingFederate to send request parameters through a request object by value, in which case request parameters are represented by individual claims in a signed JSON Web Token (JWT). When the OP receives the authentication request, it can validate the integrity of the request parameters based on the digital signature in the JWT. For more information, see the section explaining passing a request object by value in the OpenID Connect specification at [openid.net/specs/openid-connect-core-1\\_0.html#RequestObject](https://openid.net/specs/openid-connect-core-1_0.html#RequestObject).

## Processing steps

1. A user starts a browser SSO request at the `/sp/startSSO.ping` service provider (SP) application endpoint or the `/sp/init_login.ping` SP protocol endpoint.
2. The relying party, PingFederate, sends to the OP an authentication request through the browser containing the desired request parameters, such as `response_type`, `scope` and `redirect_uri`, with or without any custom query parameters.
3. The OP prompts the user to authenticate and authorize, as needed.

4. The OP sends the user back to PingFederate, at the `redirect_uri` parameter value, through the browser with an authorization code for the Basic Client profile, or an ID token and an access token if specified in the configuration for the Implicit Client profile.
5. Applicable only to the Basic Client profile, PingFederate sends a token request with the authorization code to the OP at its token endpoint, directly through a back-channel HTTP POST request. The OP returns to PingFederate an access token and an ID token.
6. PingFederate validates the ID token.
7. PingFederate passes the end-user claims to the target application through an SP adapter instance or an authentication policy contract through the browser.

The access token, if any, can also be passed to the target application, so that API security use cases can be layered on top of the browser-based SSO request.



**Note:**

If the UserInfo endpoint is included as part of the connection settings and an access token is provided by the OP, PingFederate also retrieves claims from the OP before the last step.

For more information about OpenID Connect, see [openid.net/connect](https://openid.net/connect).

### Creating an OpenID Connect IdP connection

In the **IdP Connections** window, create an OpenID Connect identity provider (IdP) connection to take advantage of your existing last-mile integration and expand the horizon of your applications to additional partners using the OpenID Connect protocol.

#### Steps

1. Go to **Authentication # Integration # IdP Connections**, and then create a new IdP connection.
2. On the **Connection Type** tab, select the **Browser SSO Profiles** check box, and in the **Protocol** list, select **OpenID Connect**. Click **Next**.



**Note:**

When OpenID Connect is the chosen protocol, the other types become unavailable.

3. On the **Connection Options** tab, you can enable just-in-time (JIT) provisioning, OAuth attribute mapping, which requires the OAuth 2.0 authorization server role, or both. Click **Next**.



**Note:**

For simplicity, this topic focuses on managing OpenID Connect IdP connection settings.

4. On the **General Info** tab:
  - a. Provide the required information, including:

**Issuer**

The Issuer Identifier of the OpenID Provider (OP).

**Connection Name**

A plain-language identifier for the connection; for example, a company or department name. This name is displayed in the connection list on the administrative console.

**Client ID**

The client ID to communicate with the OP.

This client represents and is created and managed at the OP. For more information, see the documentation provided by the OP.

#### Client Secret

The client secret to communicate with the OP.

Applicable only when the client representing PingFederate supports the Basic Client profile. For more information, see [step 12](#).

- b. Optional: Click **Load Metadata**.



#### Tip:

Loading metadata from the OpenID Provider (OP) expedites the connection setup. You can also update an existing connection by reloading metadata.

5. On the **Browser SSO** tab, click **Configure Browser SSO**.
6. On the **User-Session Creation** tab, click **Configure User-Session Creation**.
7. On the **Identity Mapping** tab, you have three choices:  
Choose from:
  - Select the **No Mapping** check box if you plan on passing end-user claims to the target application through an authentication policy contract in an SP authentication policy.
  - Select the **Account Mapping** check box if you plan on passing end-user claims to the target application through an SP adapter instance or an authentication policy contract if your PingFederate server is a federation hub that bridges an OP to an SP.
  - Select the **Account Linking** check box if your target application requires account linking.



#### Tip:

End-user claims are basically user attributes found in ID tokens or obtained from the UserInfo endpoint at the OP.

For illustration, this topic uses the **Account Mapping** configuration.

8. On the **Attribute Contract** tab, extend the attribute contract.

To mask the attribute values in the log, select the relevant check box for each applicable end-user claim.



#### Note:

If you have chosen to load the metadata from the OP on the **General Info** tab, the attribute contract is populated automatically.

9. On the **Target Session Mapping** tab, click **Map New Adapter Instance** to map end-user claims to the target application through an SP adapter instance or an authentication policy contract.

Follow the administrative console to fulfill the SP adapter contract or the authentication policy contract. Like other IdP connections, you can query additional attributes from a datastore, specify issuance

criteria, or both. When mapping an attribute, select **Provider Claims** from the **Source** list to map the attribute to an end-user claim.

If your target application requires the associated access token, select **Context** as the source and **Access Token** as the value.



**Note:**

If the client representing PingFederate supports the Basic Client profile, PingFederate always receives an access token from the OP to retrieve an ID token.

If the client supports the Implicit Client profile, you must select the **Form POST with access token** option in [step 12](#), such that the OP will return an access token and an ID token as part of the authentication and authorization flow.

The **Target Session Mapping** configuration does not apply when the **No Mapping** option is selected on the **Identity Mapping** tab.

10. On the **Protocol Settings** tab, click **Configure Protocol Settings**.



11. On the **OpenID Provider Info** tab, provide the scopes, the endpoints, and the authentication scheme.

|   |   |
|---|---|
| SCOPES                                    | <input type="text" value="openid"/>   |
| AUTHORIZATION ENDPOINT                    | <input type="text" value="https://localhost:9031/as/authorization.oauth2"/>   |
| OPENID CONNECT LOGIN TYPE                 | <input checked="" type="radio"/> CODE <input type="radio"/> FORM POST <input type="radio"/> FORM POST WITH ACCESS TOKEN |
| AUTHENTICATION SCHEME                     | <input type="radio"/> BASIC <input type="radio"/> POST <input checked="" type="radio"/> PRIVATE KEY JWT                 |
| AUTHENTICATION SIGNING ALGORITHM          | <input type="text" value="- SELECT -"/>   |
| ENABLE PROOF KEY FOR CODE EXCHANGE (PKCE) | <input checked="" type="checkbox"/>   |
| TOKEN ENDPOINT                            | <input type="text" value="https://localhost:9031/as/token.oauth2"/>   |
| USER INFO ENDPOINT                        | <input type="text" value="https://localhost:9031/idp/userinfo.openid"/>   |
| JWKS URL                                  | <input type="text" value="https://localhost:9031/pf/JWKS"/>   |
| SIGN REQUEST                              | <input checked="" type="checkbox"/>   |
| REQUEST SIGNING ALGORITHM                 | <input type="text" value="- SELECT -"/>   |






**Note:**



If you clicked **Load Metadata** from the OpenID Provider (OP) on the **General Info** tab, the **Scopes** field and all endpoints are pre-populated, provided that the metadata contains the information.

| Field         | Description  |
|---------------|--|
| <b>Scopes</b> | <p>The scopes to be included in the OpenID Connect authentication and OAuth token requests to the OP. Multiple space-separated values are allowed.</p> <p>The default value, without loading metadata from the OP, is <code>openid</code>.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>For a list of OpenID Connect defined scopes, see the section about requesting claims using scope values in the OpenID Connection specification at <a href="https://openid.net/specs/openid-connect-core-1_0.html#ScopeClaims">openid.net/specs/openid-connect-core-1_0.html#ScopeClaims</a>.</p> </div> |

| Field                            | Description  |
|----------------------------------|--|
| <b>Authorization Endpoint</b>    | <p>The authorization endpoint at the OP.</p> <p>You can enter a relative path, starting with a forward slash, if you provide base URL on the <b>General Info</b> tab.</p> <p>There is no default value without loading metadata from the OP.</p>   |
| <b>OpenID Connect Login Type</b> | <p>The OpenID Connect client profile of the client. This client represents and is created and managed at the OP.</p> <ul style="list-style-type: none"> <li>▪ If the client is configured to support the Basic Client profile, select <b>Code</b>.<br/>The resulting value of the <code>response_type</code> parameter is <code>code</code>.</li> <li>▪ If the client is configured to support the Implicit Client profile, select <b>Form POST</b>.<br/>The resulting value of the <code>response_type</code> parameter is <code>id_token</code>.</li> <li>▪ If the client is configured to support the Implicit Client profile and the target application requires the associated access token, select <b>Form POST with access token</b>.<br/>The resulting values of the <code>response_type</code> parameter are <code>id_token</code> and <code>token</code>.</li> </ul> <p>The default selection, without loading metadata from the OP, is <b>Code</b>.</p> |
| <b>Authentication Scheme</b>     | <p>The client authentication method that uses. Applicable and visible only to clients supporting the Basic Client profile.</p> <ul style="list-style-type: none"> <li>▪ Select <b>Basic</b> to submit credentials with HTTP Basic authentication.</li> <li>▪ Select <b>POST</b> to submit credentials with POST.</li> <li>▪ Select <b>Private Key JWT</b> to authenticate with the <code>private_key_jwt</code> Client Authentication method. For more information, see Client Authentication in the OpenID Connect specification.</li> </ul> <p>The default selection, without loading metadata from the OP, is <b>Basic</b>.</p>   |

| Field  | Description  |
|--|--|
| <b>Authentication Signing Algorithm</b>          | <p>Select the algorithm that uses to sign the JSON web token (JWT).</p> <p><b>Private Key JWT</b> is the chosen authentication scheme.</p> <p>If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div data-bbox="565 520 1466 835" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p>Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <div data-bbox="565 856 1466 1360" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>Based on the chosen signing algorithm, selects the signing JSON Web Key (JWK) from its JWK Set (JWKS) at runtime.</p> <p>For the OP to validate the signed JWT, ensure that the OP can access the JWKS endpoint, which returns the current JWKS. The JWKS endpoint is located at <code>&lt;Base URL&gt;/pf/JWKS</code>, where <b>Base URL</b> is defined on <b>System # Server # Protocol Settings # Federation Info</b>.</p> <p>For example, if the <b>Base URL</b> field value is <code>https://www.example.com</code>, the JWKS endpoint is <code>https://www.example.com/pf/JWKS</code>. You can pass the JWKS endpoint directly to the OP or have the OP contact the OP configuration endpoint to obtain the information.</p> <p>For more information, see .</p> </div> |
| <b>Enable Proof Key for Code Exchange (PKCE)</b> | <p>Select this check box to enable to send a SHA256 code challenge and corresponding code verifier as a Proof Key for Code Exchange (PKCE) to the OP during the Code authentication flow.</p> <p>This check box is applicable and visible only when the <b>OpenID Connect Login Type</b> is <b>Code</b>.</p> <div data-bbox="565 1591 1466 1791" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>When <b>Load Metadata</b> on the <b>General Info</b> tab is clicked, displays the <b>Enable PKCE</b> check box if S256 is listed as a supported method in the <code>code_challenge_methods_supported</code> by the OP.</p> </div>   |

| Field  | Description   |
|--|---|
| <b>Token Endpoint, Userinfo Endpoint, and JWKS URL</b> | <p>OAuth 2.0 and OpenID Connect 1.0 endpoints at the OP. For more information, see <a href="https://openid.net/connect">openid.net/connect</a>.</p> <p>Token Endpoint</p> <p>The <b>Token Endpoint</b> field is only visible and required for clients supporting the Basic Client profile. In other words, the <b>OpenID Connect Login Type</b> field is set to <b>Code</b>.</p> <p>Userinfo Endpoint</p> <p>The <b>Userinfo Endpoint</b> field is optional. If omitted, only has access to the end-user claims from the ID tokens.</p> <p>JWKS URL</p> <p>The <b>JWKS URL</b> is required for to validate the inbound ID tokens from the OP. If the OP signs its JWTs using an RSASSA-PSS signing algorithm, must be deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively. .</p> <p>There are no default values without loading metadata from the OP.</p> |
| <b>Sign Request</b>                                    | <p>Select this check box to send request parameters as claims in a request object, a self-contained, signed JWT as one <code>request</code> query parameter to the OP.</p> <p>When this optional configuration is enabled, the OP can validate the integrity of the request parameters based on the digital signature found in the signed JWT. For more information, see the section explaining passing a request object by value in the OpenID Connect specification at <a href="https://openid.net/specs/openid-connect-core-1_0.html#RequestObject">openid.net/specs/openid-connect-core-1_0.html#RequestObject</a>.</p> <p>This check box is not selected by default, in which case sends request parameters with multiple query parameters, unsigned.</p>  |

| Field                            | Description  |
|----------------------------------|--|
| <b>Request Signing Algorithm</b> | <p>Select the algorithm that uses to sign the request object.</p> <p>Applicable and visible only when the <b>Sign Request</b> check box is selected.</p> <p>If is deployed to run in a Java 8 or Java 11 runtime environment, or is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, additional RSASSA-PSS signing algorithms become available for selection. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If static keys for OAuth and OpenID Connect are enabled, Elliptic-curve cryptography (EC) algorithms that have not been configured with an active static keys are hidden.</p> <p>Changes made in the static-key configuration might affect runtime transactions and require additional changes here. For more information, see <a href="#">Keys for OAuth and OpenID Connect</a> on page 675.</p> </div> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>automatically selects the signing JSON web key (JWK) based on the selected signing algorithm from its JWK Set (JWKS).</p> <p>In order for the OP to validate the signed request object, ensure that the OP can access your 's JWKS URL, which returns the current set of JSON web keys. The JWKS URL is located at <code>&lt;Base URL&gt;/pf/JWKS</code>, where <b>Base URL</b> is defined on <b>System # Server # Protocol Settings # Federation Info</b>.</p> <p>For example, if the <b>Base URL</b> field value is <code>https://www.example.com</code>, the JWKS URL is <code>https://www.example.com/pf/JWKS</code>. You can pass the JWKS URL directly to the OP or have the OP contact the OpenID Provider configuration endpoint for it. For more information, see .</p> </div> |

12. Optional: Remain on the **OpenID Provider Info** tab and specify the request parameters that are allowed to be included in the authentication requests to the OP under **Request Parameters**. For more information, see .
13. Optional: On the **Overrides** tab, specify a default target URL and authentication context overrides.
14. On the **Activation & Summary** tab, review your connection settings.

When you finish setting up a connection, you can choose to activate it immediately.

 **Important:**

Regardless of whether you choose to activate a new connection now or later, you must click **Save** on the **Summary & Activation** tab for a new connection if you want to keep the configuration.

You can deactivate a connection at any time. When a connection is inactive, all transactions to or from this partner are disabled.

In this use case, because PingFederate is an OAuth client, you are likely required by the authorization server at the OP to register the **Redirect URI** as shown on the **Summary & Activation** tab. This

registration should be associated with the client that represents PingFederate, the client that you have provided on the **General Info** tab. For more information, see the documentation provided by the OP.

The **SSO Application Endpoint** provides a sample URL at the `/sp/startSSO.ping` application endpoint that webmasters or web application developers at your site can use to invoke SSO for the connection. For a list of supported parameters, see [Viewing SP application endpoints](#) on page 720.

If you have selected the **No Mapping** option on the **Identity Mapping** tab, the **Summary & Activation** tab does not show the **SSO Application Endpoint** sample URL.

The target application can also invoke SSO requests by contacting the `/sp/init_login.ping` SP protocol endpoint. For more information, see [Configuring request parameters and SSO URLs](#) on page 814.

### Configuring request parameters and SSO URLs

On the **OpenID Provider Info** tab of the **Protocol Settings** window, you can define request parameters under **Request Parameters**.

About this task

You can define request parameters for the following purposes:

- Allow custom request parameters to be include in the authentication requests to support OpenID provider (OP)-specific use cases.
- Define the default values for the request parameters.
- Specify whether the default values, if any, can be overridden at runtime.
- Allow the target application to request different scopes at runtime. The OP can reject the requested scopes based on its client configuration.
- Protect the requested authentication request, `acr_values`, the authentication requirement, `prompt`, or both so that none of them can be overridden at runtime by the application endpoint parameters - `RequestedAuthnCtx`, `IsPassive`, and `ForceAuthn`.

Direct mapping is available for types of parameters with a contract or text value:

- Client ID
- Client IP
- Extended properties
- SP Connection Entity ID
- OAuth scopes
- Tracked HTTP parameters

Use the No Mapping parameter type to capture "no default value".

You can use the following types of parameters in expressions:

- Signed request object claims
- Chained attributes
- SAML authentication request
- HTTP Request

Steps

1. Enter the request parameter's **Name**.

2. Select the request parameter's **Type**

- **Context**
- **Expression**
- **Extended Properties**
- **No Mapping**
- **Text**
- **Tracked HTTP Parameters**

3. Enter the request parameter's default **Value**.

If you selected the **Context** type, the following are available for direct mapping:

- **Client ID**
- **Client IP**
- **OAuth scopes**
- **SP Connection Entity ID**

This is optional if the target application is allowed to override the parameter value at runtime. When no default value is specified, any value provided by the target application is accepted by the `/sp/startSSO.ping` service provider (SP) application endpoint and the authentication endpoint. If the target application does not provide the parameter in its single sign-on (SSO) URL and no default value is specified, the parameter is not included in the authentication requests.

This is required if the target application is not allowed to override the parameter value at runtime.

When specified, the request parameter is always included in the authentication requests. If the target application is not allowed to override the parameter value at runtime, the default value is sent.

4. Optional: To let the target application override the request parameter's default value during runtime, select the **Application Endpoint Override** check box.

When this check box is selected, during runtime:

- If the target application provides the parameter in its SSO URL to the `/sp/startSSO.ping` SP application endpoint or the authentication endpoint, the value in the SSO URL is used.
- If the target application does not provide the parameter in its SSO URL, the default value is used. However, if the parameter doesn't have a default value, then the parameter is not included in authentication requests.



**Note:**

The `/sp/init_login.ping` SP endpoint does not accept overridden values. The `login_hint` parameter is the only exception. The default value, if any, is used. See the note at the end of this topic for more information.

5. Click **Add**.

## Example

Consider the following examples of request

### REQUEST PARAMETERS

| Name                     | Type   | Value  | Application Endpoint Override       |
|--------------------------|--|--|-------------------------------------|
| hd                       | Text   | example.com  | <input type="checkbox"/>            |
| customMultiValued        | Text   | value one  | <input type="checkbox"/>            |
| customMultiValued        | Text   | value two  | <input type="checkbox"/>            |
| customOverridableOne     | Text   | value can be overridden  | <input checked="" type="checkbox"/> |
| customOverridableTwo     | No Mapping   |  | <input checked="" type="checkbox"/> |
| scope                    | Text   | address phone edit openid profile admin email  | <input checked="" type="checkbox"/> |
| acr_values               | Text   | PasswordProtectedTransport   | <input type="checkbox"/>            |
| prompt                   | Text   | login  | <input type="checkbox"/>            |
| extendPropsOne           | Extended Properties  | extProperty1   | <input type="checkbox"/>            |
| scopeParam               | Context  | Scope  | <input type="checkbox"/>            |
| trackedHTTPParamOne      | Tracked HTTP Parameters  | param1   | <input type="checkbox"/>            |
| entityIDOne              | Context  | SP Connection Entity ID  | <input type="checkbox"/>            |
| issuerSignedRequestClaim | Expression   | #signedMap=<br>#this.get("context.SignedRequestObjectClaims").getObjectValue(),<br>#signedMap.get("iss") | <input type="checkbox"/>            |
| paramABC                 | <div style="border: 1px solid #ccc; padding: 2px;">           - SELECT -<br/>           Context<br/>           Expression<br/>           Extended Properties<br/>           No Mapping<br/>           Text<br/>           Tracked HTTP Parameters         </div> |  | <input type="checkbox"/>            |

parameters:\_\_\_\_\_

- The **hd** parameter is defined with a default value that cannot be overridden at runtime. The parameter is always included in the authentication requests and the value is always `example.org`.
- The **customMultiValued** parameter is defined with two default values that cannot be overridden at runtime. This multivalued parameter is always included in the authentication requests. The values are always as defined.
- The **customOverridableOne** parameter is defined with a default value that can be overridden at runtime. This parameter is always included in the authentication requests. If the target application



provides the parameter in its SSO URL, the value in the SSO URL is used. If the target application does not provide the parameter in its SSO URL, the default value is used.

- To override the value, configure the target application to append the request parameter and the desired value to the **SSO Application Endpoint**, as shown on the **Summary & Activation** tab, as in the following example.

```
https://sso.example.com/sp/startSSO.ping?PartnerIdpld=https%3A%2F%2Fsso.alpha.local%3A9031 and customOverridableOne=foo
```

- To construct a multivalued request parameter, append the request parameter multiple times with different values, as in the following example.

```
https://sso.example.com/sp/startSSO.ping?PartnerIdpld=https%3A%2F%2Fsso.alpha.local%3A9031 and customOverridableOne=foo and customOverridableOne=bar
```

https%3A%2F%2Fsso.alpha.local%3A9031 is the URL-encoded value of https://sso.alpha.local:9031, the issuer value of the OP.

- The **customOverridableTwo** parameter is defined without a default value. Parameters without default values require the **No Mapping** parameter type. Any value provided by the target application in the SSO URL is accepted. To include this parameter in the authentication requests to the OP, configure the target application to append the request parameter and the desired value to the **SSO Application Endpoint**.
  - To construct a multivalued request parameter, append the parameter multiple times with different values.

If the target application does not provide the parameter in its SSO URL, the parameter is not included in the authentication requests.

- The **scope** (standard) parameter is defined with a value matching that of the **Scopes** field, on the same tab, and with the option to allow the target application to override the value at runtime. In essence, the target application is allowed to dynamically change the scope it requires at runtime by appending the **scope** parameter and the desired scopes to the **SSO Application Endpoint**.



**Note:**

While the target application can request different scopes, the OP can reject the requested scopes based on its client configuration. Work with the OP to understand which scopes are applicable to your use case to prevent runtime errors.

- The **acr\_values** (standard) parameter is defined with a default value that cannot be overridden at runtime. As a result, the **RequestedAuthnCtx** parameter, if supplied in the SSO URL by the target application, is ignored. In the authentication requests, the value of the **acr\_values** parameter is always set to the default value specified in the configuration. Define the **acr\_values** parameter if you want to protect the requested authentication context from the target application.
- The **prompt** (standard) parameter is defined with a default value of **login** that cannot be overridden at runtime. As a result, the target application will not be able to suppress the reauthentication requirement by including **IsPassive=true** in the SSO URL. In the authentication requests, the value of the **prompt** parameter is always set to **login**.

Similarly, if the **prompt** parameter is defined with a default value of **none** that cannot be overridden at runtime, the target application will not be able to request the end users to reauthenticate by including **ForceAuthn=true** in the SSO URL. In the authentication requests, the value of the **prompt** parameter is always set to **none**.

- The **issuerSignedRequestClaim** parameter uses an OGNL expression to extract the **iss** claim from an incoming signed request.



**Note:**

These examples use the `/sp/startSSO.ping` SP application endpoint. You can also use the `/sp/init_login.ping` SP protocol endpoint to invoke the Third Party Initiated Login flow. For more information, see [View SP protocol endpoints](#).



### Important:

For information about URL encoding, see third-party resources, such as [HTML URL-encoding Reference](#).

### Query parameters versus request object

By default, PingFederate sends all request parameters through multiple query parameters, unsigned.

If the **Sign Request** check box is selected, PingFederate creates a signed JSON web token (JWT) that contains claims representing the request parameters and passes the signed JWT as one query parameter, `request`, to the OpenID provider (OP). The `client_id`, `response_type`, and `scope` request parameters are always passed to the OP as individual query parameter as well.

Consider the following authentication requests based on the previous sample configuration. The client authenticates through the HTTP Basic authentication scheme and initiates single sign-on (SSO) request without providing overrides for any request parameters.

#### Request parameters via query parameters

```
https://sso.alpha.local:9031/as/authorization.oauth2
?acr_values=PasswordProtectedTransport
&customMultiValued=value+one
&customMultiValued=value+two
&customOverridableOne=value+can+be+overridden
&hd=example.org
&prompt=login
&nonce=ykulMjpwAFk79R1rBOBwm5
&redirect_uri=https://www.example.com/sp/
eyJpc3MiOiJodHRwczpcL1wvc3NvLmFscGhhLmxvY2FsOjkwMzEifQ/cb.openid
&state=e75nI1VU6Wa5TMmOwegDPSEI2iO9zd
&client_id=RP
&response_type=code
&scope=address+phone+edit+openid+profile+admin+email
```

#### Request parameters via a request object by value

```
https://sso.alpha.local:9031/as/authorization.oauth2
?request=eyJhbG...ZTMifQ.eyJhdW...lJQIn0.IAOpuf...IqCftg
&client_id=RP
&response_type=code
&scope=address+phone+edit+openid+profile+admin+email
```



### Note:

The `client_id`, `response_type`, and `scope` request parameters are always passed to the OP as individual query parameters as defined in the OpenID Connect specification.

The value of the `request` query parameter, truncated for readability, is the request object, a signed JWT that contains the request parameters as individual claims, illustrated in the following decoded payload.

```
{
  "aud": "https://sso.alpha.local:9031",
  "exp": 1495645410,
```

```

"acr_values": "PasswordProtectedTransport",
"customMultiValued": [
  "value one",
  "value two"
],
"customOverridableOne": "value can be overridden",
"hd": "example.org",
"prompt": "login",
"nonce": "vhW2VJc7eZ6r6vfpiAwepd",
"redirect_uri": "https://sso.rp.local:9021/sp/eyJpc3MiOiJodHRwczpcL1wvc3NvLmFscGhhLmxvY2FsOjkwMzEifQ/cb.openid",
"state": "nFVzgFirZtg3kBXMFpWt5RNhO4oDuA",
"client_id": "RP",
"response_type": "code",
"scope": "address phone edit openid profile admin email"
}

```

For more information, see the section explaining passing a request object by value in the OpenID Connect specification at [openid.net/specs/openid-connect-core-1\\_0.html#RequestObject](https://openid.net/specs/openid-connect-core-1_0.html#RequestObject).

## Configuring IdP discovery using a persistent cookie

PingFederate's proprietary identity provider (IdP)-discovery method makes use of an IdP persistent reference cookie (IPRC) to track the identity provider with whom a user last authenticated.

About this task

There are three significant differences between standard IdP discovery and the IPRC method:

- Standard IdP discovery can be used only with SAML 2.0, but the IPRC can be used with any federation protocol.
- The common domain cookie (CDC) can be configured as a temporary, session-based cookie. The IPRC always persists for a configurable period of time.
- The CDC is set by the IdP and is readable by both federation partners. The IPRC is set by the service provider (SP), using information in the SAML assertion, and cannot be accessed by the IdP.

The deployed connection configuration between SP and IdP partners must include SP-initiated single sign-on (SSO).

Steps

- Edit the `org.sourceid.websso.profiles.sp.IdpIdCookieSupport.xml` file located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
- Set the value of **EnableIdpIdCookie** to `true`.
- Optional: Modify the remaining elements in the configuration, as described in the following table.

| Field                            | Description  |
|----------------------------------|--|
| <b>IdpIdCookieName</b>           | The name of the IPRC set by the SP installation. The default is <code>IdPIId</code> . The cookie name cannot contain any of the following characters: <code>&amp;</code> , <code>&gt;</code> , <code>&lt;</code> , <code>;</code> , a comma, or a space. |
| <b>IdpIdCookieLifetimeInDays</b> | Days lifetime for the cookie. The default is 365 days and a maximum of 24855 days. The browser will delete the cookie when the period is expired.  |
| <b>ShowIdpSelectionList</b>      | If set to <code>true</code> , the default, the SP displays a list of IdPs that can be used to initiate the SSO event if the cookie is not set. If set to <code>false</code> , the SP installation generates an error page.                               |

4. Start or restart PingFederate.



**Note:**

After an IPRC cookie is set, the only way to change the IdP to whom the SP will send Authentication Requests for the user is to do one of the following: wait for the cookie to expire, delete the cookie, or perform IdP-initiated SSO using the new IdP.

## System administration

This section describes general administrative functions for PingFederate.

### Configuring PingFederate properties

The default administrative console and runtime behavior of PingFederate is controlled in part by configuration properties set in the `run.properties` file, located in the `<pf_install>/pingfederate/bin` directory.

About this task

The most common properties are documented in the following table. For the rest of the properties, including various cookie-encoding options, see the `run.properties` file.






**Tip:**

The clustering configuration options are also maintained in the `run.properties` file. For more information, see [Deploying cluster servers](#) on page 208.

| Property                             | Description   |
|--------------------------------------|---|
| <code>pf.admin.https.port</code>     | Defines the port on which the PingFederate administrative console runs. The default value is 9999.  |
| <code>pf.admin.baseurl</code>        | <p>Defines the URL that PingFederate's administrative node uses to populate resource references in Administrative API responses. The administrative node also uses it for the redirect URL it sends to an OpenID Provider for administrator OIDC login (for example, <code>https://pingfederate-admin.example.com</code> or, if the load balancer uses a custom port, <code>https://pingfederate-admin.example.com:8443</code>). The default value is blank.</p> <p>Use <code>pf.admin.baseurl</code> instead of <code>pf.admin.hostname</code>, which has been deprecated. If <code>run.properties</code> defines both, PingFederate ignores <code>pf.admin.hostname</code>. But if <code>run.properties</code> defines only <code>pf.admin.hostname</code>, PingFederate constructs the URL the same way it does in versions of PingFederate before 10.3.</p> |
| <code>pf.console.bind.address</code> | Defines the IP address over which the PingFederate administrative console communicates. Use for deployments where multiple network interfaces are installed on the machine running PingFederate.  |
| <code>pf.console.title</code>        | Defines the browser window or tab title for the administrative console. It makes separate instances easily identifiable.  |

| Property                                       | Description   |
|--|---|
| <code>pf.console.environment</code>            | Defines the name of the PingFederate environment that will be displayed in the administrative console. It makes separate environments easily identifiable.  |
| <code>pf.console.show.background.images</code> | Enables or disables the background images on the dashboard of the administrative console. The images are enabled by default.  |
| <code>pf.console.session.timeout</code>        | Defines the length of time in minutes until an inactive administrative console times out. The minimum setting is 1 minute, and maximum is 8 hours (480 minutes). Default is 30 minutes.   |
| <code>pf.log.eventdetail</code>                | Enables or disables (the default) detailed event logging for actions performed by administrative console users.   |
| <code>pf.console.login.mode</code>             | Indicates whether more than one administrative user may access the administrative console at one time. Supported values: Single   Multiple. The default value is Multiple.  |
| <code>pf.console.authentication</code>         | Indicates whether administrators sign on to PingFederate using credentials managed internally by PingFederate or externally by other systems.   |
| <code>pf.admin.api.authentication</code>       | Defines the authentication method of the PingFederate administrative API.   |
| <code>pf.pingone.admin.url.region</code>       | <p>These properties set the URL of the PingOne unified admin icon in the PingFederate administrative console. This property should be set based on the region of your PingOne organization.</p> <p>Choose one of the following region-specific values for your environment.</p> <p>com<br/>console.pingone.com</p> <p>eu<br/>console.pingone.eu</p> <p>asia<br/>console.pingone.asia</p> <p>ca<br/>console.pingone.ca</p> |
| <code>pf.pingone.admin.url.environment</code>  | Defines the ID of your PingOne organization's environment.  |
| <code>ldap.properties.file</code>              | When LDAP administrative console authentication is enabled, indicates the name of the file containing configuration properties.   |
| <code>cert.properties.file</code>              | When certificate-based console authentication is enabled, indicates the name of the file containing configuration properties.   |

| Property   | Description   |
|--|---|
| <code>radius.properties.file</code>                            | When RADIUS-based console authentication is enabled, indicates the name of the file containing configuration properties.  |
| <code>oidc.properties.file</code>                              | When OIDC administrative-console authentication is enabled, indicates the name of the file containing configuration properties.   |
| <code>pf.http.port</code>                                      | <p>Defines the port on which PingFederate listens for unencrypted HTTP traffic at runtime. For security reasons, this port is turned off by default.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>CAUTION:</b><br/>           This port should remain disabled in production if your deployment configuration directly exposes the PingFederate server to the Internet.         </div>   |
| <code>pf.https.port</code>                                     | Defines the port on which PingFederate listens for encrypted HTTPS (SSL/TLS) traffic. The default value is 9031.  |
| <code>pf.secondary.https.port</code>                           | <p>Defines a secondary HTTPS port that can be used for mutual SSL/TLS (client X.509 certificate) authentication for both end users and protocol requests (SAML, WS-Trust, and OAuth). Set its value to the desired inbound listening TCP port. A value of -1 disables this feature.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Important:</b><br/>           If you are using client X.509 certificates for either WS-Trust STS authentication or for SAML back-channel authentication, you must use this port, or a similarly configured new listener, with either the <b>WantClientAuth</b> or <b>NeedClientAuth</b> parameter set to <code>true</code> in the <code>jetty-runtime.xml</code> file.<br/>           For more information, see the note at the end of this table.         </div> |
| <code>pf.engine.bind.address</code>                            | Defines the IP address over which the PingFederate server communicates with partner federation gateways. Use for deployments where multiple network interfaces are installed on the machine running PingFederate.   |
| <code>pf.monitor.bind.address</code>                           | Defines the IP address over which Java Management Extensions (JMX) communicate with PingFederate. Use for deployments where multiple network interfaces are installed on the machine running PingFederate.  |
| <code>pf.engine.prefer_ipv4</code>                             | Defines the protocol to be used by PingFederate. <code>True</code> , the default, enables use of IPv4 only. <code>False</code> enables use of both IPv4 and IPv6.   |
| <code>http.proxyHost</code> and<br><code>http.proxyPort</code> | Specifies the hostname, or the IP address, and the port number of the forward proxy server that HTTP traffic originating from PingFederate must go through.   |

| Property                            | Description  |
|-------------------------------------|--|
| https.proxyHost and https.proxyPort | Specifies the hostname, or the IP address, and the port number of the forward proxy server that HTTPS traffic originating from PingFederate must go through.   |
| http.nonProxyHosts                  | <p>Specifies one or more destinations where PingFederate is not required to proxy its HTTP and HTTPS traffic through the forward proxy server configured by the <code>http[s].proxyHost</code> and <code>http[s].proxyPort</code> properties. This property supports multiple values separated by the pipe character ( ) and the wildcard character (*) for pattern matching. See the example below.</p> <p><code>*.example.com localhost</code></p>   |
| pf.runtime.context.path             | <p>Allows customization of the server path for PingFederate endpoints.</p> <div data-bbox="716 695 1468 926" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If this property is changed, the path must also be added to the base URL for your PingFederate environment. Base URL is defined on <b>System # Server # Protocol Settings # Federation Info</b> .</p> </div> <p>The <code>pf.runtime.context.path</code> property is also compatible with virtual host names. Unlike the base URL configuration, the virtual host names configuration does not require any context path. Virtual host names are defined on <b>System # Server # Virtual Host Names</b>.</p> <p>For example, suppose the base URL is <code>https://www.example.com:9031</code> and the virtual host names are <code>www.example.org</code> and <code>www.example.info</code>. To configure the <code>pf.runtime.context.path</code> property value as <code>/sso</code>, you must update the base URL to <code>https://www.example.com:9031/sso</code> but leave the virtual host names as they are. Once configured, you can access the runtime server at the following endpoints:</p> <p>Base URL</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.com:9031/sso</code></li> </ul> <p>Virtual host names</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.org:9031/sso</code></li> <li>▪ <code>https://www.example.info:9031/sso</code></li> </ul> |
| pf.runtime.http.maxRequestSize      | Sets the maximum request size in bytes for inbound runtime requests. The default value is 200000 bytes.  |
| pf.log.dir                          | Network path to the output location of log files. The default is <code>&lt;pf_install&gt;&gt;/pingfederate/log</code>  |
| pf.hsm.mode                         | Enables or disables (the default) a FIPS-compliance Hardware Security Module (HSM).  |

| Property                                 | Description   |
|--|---|
| pf.hsm.hybrid                            | <p>Enables or disables the HSM hybrid mode. Applicable only when the <code>pf.hsm.mode</code> property is configured to use an HSM.</p> <p>When set to <code>true</code>, keys and certificates can be stored on either the HSM or the local trust store. When set to <code>false</code>, the default setting, keys and certificates are stored on the HSM when applicable.</p> <p>The HSM hybrid mode allows an organization to move the storage of keys and certificates from the local trust store to an HSM over time without deploying a new PingFederate installation and mirroring the setup. For more information, see <a href="#">Transitioning to an HSM</a> on page 685.</p> |
| org.bouncycastle.fips.approved_only      | <p>When the <code>pf.hsm.hybrid</code> property is set to <code>true</code>, this property can be set to <code>true</code> or <code>false</code>. In this case, the recommended setting is <code>false</code>.</p> <p>If <code>pf.hsm.hybrid</code> is set to <code>false</code>, this property must be set to <code>true</code>.</p> <p>In FIPS-approved mode only, the module will provide approved algorithms only. For more information, see <a href="https://www.bouncycastle.org/fips-java/">https://www.bouncycastle.org/fips-java/</a>.</p> <p>The default setting is <code>true</code>.</p>  |
| pf.provisioner.mode                      | <p>Enables or disables (the default) outbound provisioning. Also used to enable provisioning failover.</p>  |
| pf.heartbeat.system.monitoring           | <p>Enables or disables (the default) the heartbeat endpoint, <code>/pf/heartbeat.ping</code>, to return detailed system monitoring information through a customizable Velocity template file. For more information, see <a href="#">Customizing the heartbeat message</a> on page 907.</p> <p>When set to <code>false</code>, the <code>/pf/heartbeat.ping</code> endpoint returns OK.</p> <p>When set to <code>true</code>, the <code>/pf/heartbeat.ping</code> endpoint returns all available stats.</p>  |
| org.apache.xml.security.ignoreLineBreaks | <p>Determines whether PingFederate omits line breaks in XML digital signatures. If omitted, this setting defaults to <code>false</code>. Set this property to <code>true</code> for improved interoperability with Microsoft products.</p>  |
| sun.net.client.defaultConnectTimeout     | <p>Determines the default connect timeout for outbound <code>java.net.URL</code> connections in milliseconds.</p> <p>The default setting is 10000.</p>  |
| sun.net.client.defaultReadTimeout        | <p>Determines the default read timeout for outbound <code>java.net.URL</code> connections in milliseconds.</p> <p>The default setting is 10000.</p>   |



| Property                                | Description  |
|---|--|
| <code>pf.admin.threads.min</code>       | The minimum number of threads in HTTP server thread pools for the administrative console. The default value is 1.  |
| <code>pf.admin.threads.max</code>       | The maximum number of threads in HTTP server thread pools for the administrative console. The default value is 10. |
| <code>pf.runtime.threads.min</code>     | The minimum number of threads in HTTP server thread pools for the runtime engine nodes. The default value is 10.   |
| <code>pf.runtime.threads.max</code>     | The maximum number of threads in HTTP server thread pools for the runtime engine nodes. The default value is 200.  |
| <code>pf.admin.acceptQueueSize</code>   | The queue size of the HTTP connector for the administrative console. The default value is 512.                     |
| <code>pf.runtime.acceptQueueSize</code> | The queue size of the HTTP connector for the runtime engine nodes. The default value is 512.                       |

**Note:**

Additional configuration of the listener ports, including adding new listeners, is available through the `<pf_install>/pingfederate/etc/jetty-runtime.xml` file. For example, options include the **WantClientAuth** and **NeedClientAuth** flags, which indicate that a client certificate is either requested or required, respectively, for mutual SSL/TLS. For the pre-configured SSL secondary port, the **WantClientAuth** parameter is set to `true` and the **NeedClientAuth** parameter is set to `false` by default.

**Steps**

1. Edit the `<pf_install>/pingfederate/bin/run.properties` file.  
You should consider creating a backup copy of the file.
2. Modify the applicable properties.
3. Restart PingFederate.

**Result****Important:**

You must manually configure the runtime server-related properties on each engine node. The `run.properties` file is not copied from the console node to the engine nodes automatically. Also, it is not part of the **Replicate Configuration** process. If running, restart PingFederate.

**Configuring size limits**

You can configure size limits, which include values in the IdP Session Registry, the SP Session Registry, the Inter-Request State management service, and others.

**Steps**

1. To configure a size limit, edit the `<pf_install>/pingfederate/server/default/conf/size-limits.conf` file.

2. Modify the applicable settings. The settings are described in the following table.

| Setting  | Description   |
|--|---|
| The IdP Session Registry stores SLO-related session information for IdP adapters, as well as for IdP and SP connections that a user has interacted with. It also stores sessions for PingFederate's Authentication Sessions feature. |   |
| IdpSessionRegistryMapImpl.max.sessions   | This setting controls the maximum number of user sessions (for SLO or Authentication Sessions) kept in memory. When this limit is reached, sessions are removed on a least-recently-used basis.<br><br>The default setting is 10000.            |
| IdpSessionRegistryMapImpl.max.individual.sessions  | This setting controls the maximum number of IdP adapter or IdP connection sessions per user session. When this limit is reached, sessions are removed on a first-in first-out basis.<br><br>The default setting is 500.                         |
| IdpSessionRegistryMapImpl.max.partner.sessions   | This setting controls the maximum number of SP connection sessions per IdP adapter or IdP connection session. When this limit is reached, sessions are removed on a first-in first-out basis.<br><br>The default setting is 500.                |
| IdpSessionRegistryMapImpl.max.user.keys  | This setting defines the maximum number of unique user keys that can be tracked. When this limit is reached, user keys are removed on a least-recently-used basis.<br><br>The default setting is 50000.   |
| IdpSessionRegistryMapImpl.max.user.key.sris  | This setting defines the maximum number of SRIs (browser sessions) that can be tracked for a given unique user key. When this limit is reached, SRIs are removed and revoked on a least-recently-used basis.<br><br>The default setting is 100. |
| IdpSessionRegistryMapImpl.expiry.mins  | This setting defines the expiry period for user sessions in minutes. If no activity has been seen for a given user session for this period, it will be removed.<br><br>The default setting is 1440  |
| The SP Session Registry stores SLO-related session information for SP adapters and IdP connections that a user has interacted with.  |   |
| SpSessionRegistryMapImpl.max.sessions  | This setting controls the maximum number of user sessions kept in memory. When this limit is reached, sessions are removed on a least-recently-used basis.<br><br>The default setting is 10000.   |

| Setting  | Description  |
|--|--|
| SpSessionRegistryMapImpl.max.individual.sessions   | <p>This setting controls the maximum number of SP adapter sessions per user session. When this limit is reached, sessions are removed on a first-in first-out basis.</p> <p>The default setting is 500.</p>                    |
| SpSessionRegistryMapImpl.expiry.mins   | <p>This setting defines the expiry period for user sessions in minutes. If no activity has been seen for a given user session for this period, it will be removed.</p> <p>The default setting is 1440.</p>                     |
| <p>The Inter-Request State Management service has two maps. The 'state' map is used to store short-lived state information between requests within an SSO or SLO transaction. The 'attr' map is used by adapters (such as the HTML form adapter) to store user session attributes.</p> |  |
| InterReqStateMgmtMapImpl.max.size.state.map  | <p>This setting controls the maximum number of user sessions in the state map. When this limit is reached, sessions are removed on a least-recently-used basis.</p> <p>The default setting is 10000.</p>                       |
| InterReqStateMgmtMapImpl.expiry.mins.state.map   | <p>This setting controls the expiry period for user sessions in the state map. If no activity has been seen for a given user session for this period, it will be removed.</p> <p>The default setting is 30.</p>                |
| InterReqStateMgmtMapImpl.max.size.attr.map   | <p>This setting controls the maximum number of user sessions in the attribute map. When this limit is reached, sessions are removed on a least-recently-used basis.</p> <p>The default setting is 10000.</p>                   |
| InterReqStateMgmtMapImpl.expiry.mins.attr.map  | <p>This setting controls the expiry period for user sessions in the attribute map. If no activity has been seen for a given user session for this period, it will be removed.</p> <p>The default setting is 1440.</p>          |
| InterReqStateMgmtMapImpl.max.session.attrs   | <p>This setting controls the maximum number of attributes stored in the attribute map for a given user session.</p> <p>The default setting is 500.</p>   |
| SessionRevocationServiceMapImpl.max.revoked.sessions   | <p>This setting controls the maximum number of revoked session identifiers kept in memory. When this limit is reached, revoked identifiers are removed on a first-in first-out basis.</p> <p>The default setting is 50000.</p> |

| Setting                                       | Description  |
|---|--|
| MetadataDirectory.max.size.idp.conn.map       | This setting controls the maximum number of IdP connections kept in memory. When this limit is reached, connections are removed on a least-recently-used basis.<br><br>The default setting is 10000. |
| MetadataDirectory.max.size.sp.conn.map        | This setting controls the maximum number of SP connections kept in memory. When this limit is reached, connections are removed on a least-recently-used basis.<br><br>The default setting is 10000.  |
| ClientManagerXmlFileImpl.max.size.clients.map | This setting controls the maximum number of OAuth clients kept in memory. When this limit is reached, clients are removed on a least-recently-used basis.<br><br>The default setting is 10000.       |

- Restart PingFederate.

## PingFederate log files

PingFederate records document server events depending on your configuration preferences.

PingFederate generates these logs that document server events:

`admin.log`

Records actions performed by administrative console users.

`admin-event-detail.log`

Records detailed information about each applicable administrative console event performed by administrative console users if detailed event logging is enabled.

`admin-api.log`

Records actions performed by administrative-API users.

`runtime-api.log`

Records actions performed by API users using the OAuth Client Management Service, the OAuth Access Grant Management Service, and the Session Revocation API.

`transaction.log`

Records individual identity-federation runtime transactions at specified levels of detail.

`audit.log`

Records a selected, configurable subset of transaction log information plus additional details, intended for security-audit and regulatory compliance purposes.

`provisioner-audit.log`

Records outbound provisioning events, intended for security-audit purposes.

`provisioner.log`

Records only provisioning activity.

`server.log`

Records PingFederate runtime and administrative server activities.

`init.log`

Records only Jetty messages generated prior to PingFederate start up.

These log files are written to the PingFederate log directory. The default location is the `<pf_install>/pingfederate/log` directory. As needed, administrators can change the log directory by modifying the `pf.log.dir` property in the `<pf_install>/pingfederate/bin/run.properties` file.

### Log4j 2 logging service and configuration

PingFederate uses the Log4j 2 logging service to generate its log files.

Configurations are maintained in the `log4j2.xml` file, located in the `<pf_install>/pingfederate/server/default/conf` directory.



#### Note:

The `log4j2.xml` configuration file is individually managed per PingFederate server. This flexibility allows multiple PingFederate nodes to write different level of messages to different destinations.

If you want all PingFederate servers to use the same logging configuration, manually synchronize the `log4j2.xml` file across multiple PingFederate servers.

### Log levels and verbosity

Log messages are categorized into six log levels:

1. FATAL
2. ERROR
3. WARN
4. INFO
5. DEBUG
6. TRACE

only records messages tagged with log level `INFO`, `WARN`, `ERROR`, and `FATAL` to the server log and the provisioner log. Messages with `DEBUG`, or `TRACE` tags, are not recorded to optimize performance. Console logging is also disabled for the same reason.

For troubleshooting purposes, you can adjust the log level to `DEBUG` in the `log4j2.xml` file and re-enable console logging.



#### Important:

When you no longer require debug messages and console logging, turn them off. On Windows, never highlight the console output because it might slow or stop from processing requests.

For the audit log, the provisioner audit log, and the transaction log, any setting lower than `INFO` (`WARN`, `ERROR`, or `FATAL`) turns logging off.

For more information, see [Enabling debug messages and console logging](#).

Changes, such as adding a `Logger` or adjusting log levels, are activated within half a minute. You do not need to restart .

### Fields (and attributes)

You can customize some logs, such as the audit log and the administrative API log, to log additional or less information by modifying their `pattern` elements. The `log4j2.xml` file documents available fields inline.

**Tip:**

You can configure PingFederate to log user attributes, if they are present, in the audit log, transaction log, and server log. When you require privacy for sensitive user attributes, select the corresponding check boxes under **Mask Log Values** to mask their values in these logs.

In addition, messages in the audit log and the server log are recorded with a tracking ID, which can be used to identify subsequent, related transactions. The tracking ID can be used for troubleshooting and support purposes, to aggregate and analyze log entries tied to the same original request. The tracking ID, `%X{trackingid}`, can also be added to the configuration for the transaction log, or removed from the audit log and the server log by modifying the `pattern` element for the logs in the `log4j2.xml` configuration file.

**Log formats**

The audit log and the provisioner audit log can be written in Common Event Format (CEF). Furthermore, the audit log can also be written in a format used in conjunction with Splunk and the Splunk App for PingFederate. The `log4j2.xml` file comes preset with configuration samples to ease the setup.

**Log destinations**

The audit log, the provisioner audit log, the provisioner log, and the server log can be written to databases. PingFederate installation includes setup scripts for various tables, located in the `<pf_install>/pingfederate/server/default/conf/log4j/sql-scripts` directory, and configuration samples in the `log4j2.xml` file.

**Log rotation**

Most PingFederate-generated log files roll over at midnight each day. The system keeps all of the resulting historical log files. Some log files, such as the `audit.log` file, the `audit-event-detail.log` file (if enabled), the `provisioner-audit.log` file (when applicable), and the `transaction.log`, can become quite large, depending on your production load and settings. You might want to back up or remove older files on a routine basis.

The `server.log` file is rolled over when it reaches 10 MB. Five old log files are kept before the oldest file is removed. Administrators can adjust the file size and the number of files to be retained in the `log4j2.xml` configuration file, as needed.

For more information about Log4j 2, see the [Log4j 2 open-source project](#).

**HTTP request logging**

HTTP requests to the runtime engine and the administrative console are logged to the `<date>.request.log` file and `<date>.request2.log`, respectively, by the Pingfederate web container.

Like other PingFederate-generated log files, the HTTP request logs are written to the default PingFederate log directory. Properties controlling request logging are contained in the web-container configuration files:

- `jetty-runtime.xml` for the runtime engine (the `<date>.request.log` files)
- `jetty-admin.xml` for the administrative console (the `<date>.request2.log` files)

You can find these files in the `<pf_install>/pingfederate/etc` directory, and you can independently manage them on a per-server basis.

**Administrator audit logging**

PingFederate records actions performed by server administrators.

This information is recorded in the `<pf_install>/pingfederate/log/admin.log` file. The events themselves are not configurable, but you can adjust Log4j 2 configuration settings to deliver the desired

level of detail surrounding each event in the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.

Events logged by PingFederate include but are not limited to:

- Sign on attempt
- Explicit user logout (no time-outs)
- Account activation or deactivation
- Password change or reset
- Role change
- System settings management
- Certificate management
- OAuth settings management
- Metadata export
- XML file signatures applied
- Configuration archive export and import
- Identity provider (IdP)/service provider (SP) adapter, IdP token processor, or SP token generator created, modified, or deleted
- IdP/SP default URLs modified
- IdP/SP connection created, modified, or deleted
- Adapter-to-Adapter mapping or token exchange mapping created, modified, or deleted
- Authentication policy contract created, modified, or deleted
- IdP Discovery management
- SP Affiliation created, modified, or deleted
- PingOne for Enterprise account connected, modified, or disconnected
- Session timeout event for the following two scenarios:
  - When an administrator's session has timed out and they subsequently sign on again, then the session timeout event is retroactively logged.
  - When an administrator's session is invalidated due to inactivity and a session clean-up is performed by the server's session management on the administrative console node. The timeout event is logged 10 - 15 minutes after the timeout occurred.

Each entry in the `admin.log` file is on a separate line and represents a single administrator action. The general format of each entry is the same, though specific events are recorded with information relevant to each type. Events are recorded when you click the corresponding **Save** button in the administrative console. Each log entry contains information relating to the event, including:

- The time the event occurred on the PingFederate server
- The username of the administrator performing the action
- The roles assigned to the administrator at the time the event occurred
- The type of event that occurred
- Basic information about the event

Each of these fields is separated by a vertical pipe (|) for easier parsing.

#### Detailed event logging

You can also configure PingFederate to log additional event information to a separate log file. When you enable detailed event logging, besides writing basic information to `<pf_install>/pingfederate/log/admining.log`, PingFederate logs detailed information about each event to `admin-event-detail.log` in the same log directory.



**Important:**

Events recorded in the log are limited to changes stored in XML files. For example, the log does not record changes to OAuth clients stored in external datastores, such as LDAP directories or Java Database Connectivity (JDBC) databases. Additionally, not all events have detailed information. For instance, sign on attempts are only logged to the `admin.log` file.

PingFederate links events between `admin.log` and `admin-event-detail.log` by a unique event ID. Each entry in the `admin-event-detail.log` file contains:

- The ID of the event
- The name of the file involved
- The type of event that occurred
- The line number where the change occurred
- The changes made

To enable detail event logging, set the `pf.log.eventdetail` property to `true` in the `<pf_install>/pingfederate/bin/run.properties` file.

### API audit logging

PingFederate provides API endpoints and management services on the administrative port (9999) and the runtime port (9031) that are logged for auditing purposes.

Actions performed through these endpoints are logged for auditing purposes, as described in the following table.

| API                                   | Port                | Log File                     |
|---------------------------------------|---------------------|------------------------------|
| Administrative API                    | Administrative Port | <code>admin-api.log</code>   |
| OAuth Client Management Service       | Runtime Port        | <code>runtime-api.log</code> |
| OAuth Access Grant Management Service | Runtime Port        | <code>runtime-api.log</code> |
| Session Revocation API                | Runtime Port        | <code>runtime-api.log</code> |

### Administrative API audit log

PingFederate records actions performed through the administrative API in the `<pf_install>/pingfederate/log/admin-api.log` file.

While the events are not configurable, Log4j 2 configuration settings in the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file can be adjusted to deliver the desired level of detail surrounding each event.

Each log entry contains information relating to the event, including:

- Time the event occurred on the PingFederate server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of these fields is separated by a vertical pipe (`|`) for ease of parsing.



### Runtime APIs audit log

PingFederate records actions performed through the OAuth Client Management Service, the OAuth Access Grant Management Service, and the Session Revocation API in the `<pf_install>/pingfederate/log/runtime-api.log` file.

While the events are not configurable, Log4j 2 configuration settings in the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file can be adjusted to deliver the desired level of detail surrounding each event.

Each log entry contains information relating to the event, including:

- Time the event occurred on the PingFederate server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of these fields is separated by a vertical pipe (|) for ease of parsing.

### Runtime transaction logging

PingFederate provides for flexible, scalable logging of all federated-identity transactions, for both inbound and outbound messages.

About this task

Administrators can configure transaction logging to any of the four modes on a per-connection basis or override the logging mode for all service provider (SP) connections, identity provider (IdP) connections, or both for troubleshooting or as a one-step means of raising or lowering all connection logging modes to the same level. The log file is `transaction.log`, located in the `<pf_install>/pingfederate/log` directory.

The following table describes the four transaction logging modes.

| Mode     | Description   |
|----------|---|
| None     | No transaction logging.   |
| Standard | (Default) Summary information for each transaction message, including: <ul style="list-style-type: none"> <li>▪ Time stamp</li> <li>▪ Hostname and port</li> <li>▪ Log mode</li> <li>▪ Connection ID</li> <li>▪ SAML status code, for SAML responses only</li> <li>▪ Context</li> <li>▪ Message type</li> <li>▪ SAML ID, for SAML messages only</li> <li>▪ Endpoint, for outbound messages only</li> <li>▪ Target URL, if single sign-on (SSO) transaction</li> </ul> |

| Mode     | Description  |
|----------|--|
| Enhanced | <p>Includes everything logged at the <b>Standard level</b> including:</p> <ul style="list-style-type: none"> <li>▪ SAML_SUBJECT*</li> <li>▪ Binding</li> <li>▪ Relay state, if available</li> <li>▪ Signature policy</li> <li>▪ Signature status</li> <li>▪ HTTP request parameters, for outbound messages only</li> </ul> <p>* Only when available in a SAML assertion, a single logout (SLO) request, an STS Request Security Token Response (RSTR), or an authentication request (AuthnRequest)</p> |
| Full     | Includes everything logged at the <b>Enhanced level</b> plus the complete XML message for every transaction.   |

Each field is separated by a vertical pipe (|) for parsing.

#### Steps

- To configure transaction logging mode on a per connection basis:
  - a. Select the applicable connection on the **IdP Connections** window (**Authentication # Integration # IdP Connections**) or the **SP Connections** window (**Applications # Integration # SP Connections**).
  - b. On the **General Info** tab, select one of the logging modes.
- To override transaction logging mode for all SP or IdP connections:
  - a. On the **IdP Connections** window or **SP Connections** window, click **Show Advanced Fields**.
  - b. On the **Logging Mode Override** setting, click **On**.
  - c. Select a logging mode for the IdP or SP connections.

#### Security audit logging

PingFederate records a subset of transaction log information with additional details at runtime, intended to facilitate security auditing and regulatory compliance.

The system records activities from single sign-on (SSO), single logout (SLO), OAuth, WS-Trust STS, and System for Cross-domain Identity Management (SCIM) inbound provisioning transactions in the security audit log, the `audit.log` file, located in the `<pf_install>/pingfederate/log` directory. You can output security audit log information to different formats, including databases, CEF, and Splunk.



#### Note:

Outbound provisioning transactions are not included in the security audit log. Instead, they are recorded in the outbound provisioning audit log, the `provisioner-audit.log` file, located in the `<pf_install>/pingfederate/log` directory.

The following tables describe the default and available fields. PingFederate separates each field by a vertical pipe (|). As needed, fields are configurable by editing the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.


#### Default fields, in the order that PingFederate records them in the security audit log


| Field | Description           |
|-------|-----------------------|
| %d    | The transaction time. |


| Field        | Description  |
|--------------|--|
| trackingid   | The tracking ID values uniquely identify user sessions, useful for correlating log messages in the audit and server logs.  |
| event        | <p>The type of transaction. For example, SSO, OAuth, AUTHN_ATTEMPT, AUTHN_REQUEST, AUTHN_SESSION_CREATED, AUTHN_SESSION_USED, AUTHN_SESSION_DELETED, and SRI_REVOKED.</p> <p>AUTHN_ATTEMPT and AUTHN_REQUEST indicate an authentication attempt against an identity provider (IdP) adapter instance and an authentication request sent to another IdP partner, through an IdP connection, respectively.</p> <p>AUTHN_SESSION_CREATED and AUTHN_SESSION_USED indicate the creation and employing of a PingFederate session, respectively.</p> <p>AUTHN_SESSION_DELETED indicates that a PingFederate session has been removed as a result of a front-channel browser-based logout request via the SAML 2.0 or WS-Federation protocol.</p> <p>SRI_REVOKED indicates that a PingFederate session has been added to the session revocation list.</p> <p>USER_KEY_AND_SRI_ASSOCIATED indicates a unique user key is associated with a PingFederate session.</p> |
| subject      | The subject of the transaction or authentication attempt.  |
| ip           | The incoming IP address.   |
| app          | The target service provider (SP) application, the email verification endpoint, or the profile management page, when applicable and available.  |
| connectionid | The partner identifier associated with the transaction. The OAuth client ID value for OAuth transactions. The ID of the authentication policy contract referenced by the local identity profile that has been invoked for the purpose of accessing the email verification endpoint or the profile management page.   |
| protocol     | The associated identity protocol; for example, SAML20 or OAuth20.  |
| host         | The host name or IP address of the PingFederate server.  |
| role         | The role PingFederate played for the transaction.  |
| status       | The status of the transactions.  |
| adapterid    | <p>The ID of an adapter instance.</p> <p>Consider adding the <b>authenticationsourceid</b> and <b>targetsessionid</b> fields to record additional information about the request.</p>   |
| description  | The description of an authentication failure, when such information is available from the authentication source, or an authorization failure from an erroneous OAuth authorization request.  |
| responsetime | The time elapsed in milliseconds from when the system receives a final request for a transaction, to when the system writes the audit message. This value serves as an approximation of total transaction processing time and can be useful for monitoring trends.   |

#### Other available fields, in alphabetical order

| Field           | Description   |
|-----------------|---|
| accessgrantguid | The GUID of the OAuth access grant, for OAuth transactions. |

| Field                       | Description   |
|-----------------------------|---|
| assertionid                 | The unique ID for the SAML assertion.   |
| atrackingid                 | The tracking ID for OAuth access token. You can use this ID to analyze the flow of OAuth access tokens in the audit log and between PingFederate and PingAccess.  |
| attributes                  | The user attributes received (for an SP log), sent (for an IdP log), or provided by the user through the self-service registration or profile management page.  |
| authenticationsourceid      | An array of one or more IdP adapters, one or more IdP connections, and identity profile, if any, invoked in an authentication or logout flow. For example, [adapter.HTMLFormSimplePCV, idpConnection.IdP, localIdentity.A8me9rySDn1aIM48]   |
| authnsessionexpiry          | The expiry of an authentication session that has just been created or used.   |
| connectionname              | The partner name associated with the transaction. The OAuth client name for OAuth transactions. The name of the authentication policy contract referenced by the local identity profile that has been invoked for the purpose of accessing the email verification endpoint or the profile management page.  |
| granttype                   | The OAuth grant type.   |
| header{anHttpRequestHeader} | <p>The HTTP request header value identified by the header name. The header name is case-insensitive. For example, header{user-agent} and header{User-Agent} are equivalent.</p> <p>To record multiple headers, repeat the <b>header</b> field, as illustrated in the following sample pattern.</p> <pre>&lt;pattern&gt;...  %header{accept-language}  %header{dnt} %n&lt;/pattern&gt;</pre> <p>Given this partial sample, PingFederate includes both the <b>accept-language</b> and <b>dnt</b> HTTP request header values when recording entries in the audit log.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>To record values from all HTTP request headers, look for the <code>org.sourceid.servlet.filter.HttpRequestHeaderFilter</code> Logger in the <code>log4j2.xml</code> file.</p> <p>This capability is turned off by default and is likely suitable only for testing and troubleshooting purposes.</p> </div> |
| httprequestid               | The ID of the HTTP request. This can be used for correlation across external systems (like PingDirectory) and for debugging purposes in the server log. This field is optional.   |
| initiator                   | The federation role that initiated the SSO or SLO: <i>SP</i> or <i>IDP</i> .<br>Applicable only to SAML 2.0 transactions.   |
| inmessagetype               | The incoming message type.<br>Possible values are <i>Request</i> or <i>Response</i> .   |
| inresponseto                | The value of the <b>InResponseTo</b> attribute of an SSO or SLO response.   |

| Field                                      | Description   |
|--|---|
| inxmlmsg                                   | The incoming message. For example, a SAML AuthnRequest or the information pertaining to an OAuth request.   |
| localuserid                                | The local ID used for the transaction, when account linking is enabled at the SP.   |
| outurl                                     | The URL where the protocol response was sent. For security reason, parameters and fragments are excluded.   |
| outxmlmsg                                  | The outgoing message. For example, a SAML Response or the information pertaining to a response for an OAuth request.  |
| parameter( <i>anHttpRequestParameter</i> ) | <p>The name of the HTTP request parameter identified by the parameter name. The parameter name is case-sensitive.</p> <p>To record multiple parameters, repeat the <b>parameter</b> field, as illustrated in the following sample pattern.</p> <pre>&lt;pattern&gt;...   %parameter{foo1}  %parameter{Foo3} %n&lt;/pattern&gt;</pre> <p>Given this partial sample, PingFederate includes both the <b>foo1</b> and <b>Foo3</b> HTTP request parameter values when recording entries in the audit log.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>To record values from all HTTP request parameter, look for the <code>org.sourceid.servlet.filter.HttpServletRequestParameterFilter</code> Logger in the <code>log4j2.xml</code> file.</p> <p>This capability is turned off by default and is likely suitable only for testing and troubleshooting purposes.</p> </div> |
| pfversion                                  | The PingFederate version.   |
| requestid                                  | The ID of a SAML request.   |
| requeststarttime                           | The start time of the request in milliseconds since midnight, January 1, 1970 UTC.  |
| responseid                                 | The ID of a SAML response.  |
| sessiongroupid                             | The internal ID for a group of persistent authentication sessions associated with a single browser instance through the PF.PERSISTENT cookie. It is only set if the request has triggered a session lookup.   |
| sri  | The session reference identifier (SRI) for the user, which can be passed to the session revocation API to revoke the user's sessions. It is only set if the request has triggered a session lookup.   |
| stspuginid                                 | The ID for the token processor or token generator instance.<br>Applicable only to WS-Trust STS transactions.  |
| targetsessionid                            | An array of one or more SP adapters or SP connections invoked in an authentication or logout flow.  |

| Field                                    | Description  |
|--|--|
| trackedparameter{anHttpRequestParameter} | <p>The value of the tracked HTTP request parameter identified by the parameter name. The parameter name is case-sensitive.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Tip:</b></p> <p>The PingFederate policy engine is capable of tracking HTTP request parameters that it receives from the initial request and making them available to authentication sources, selector instances, and contract mappings throughout the policy. As needed, parameters can be configured as such on the <b>Tracked HTTP Parameters</b> window. For more information about tracked parameters, see <a href="#">Policies</a> on page 251.</p> </div> <p>To record multiple parameters, repeat the <code>trackedparameter</code> field, as illustrated in the following sample pattern.</p> <pre style="background-color: #f0f0f0; padding: 5px; margin: 10px 0;">&lt;pattern&gt;...   %trackedparameter{foo2}  %trackedparameter{Foo4} %n&lt;/pattern&gt;</pre> <p>Given this partial sample, PingFederate includes both the <code>foo2</code> and <code>Foo4</code> HTTP request parameter values when recording entries in the audit log.</p> <p>If the parameter, as indicated by <code>&lt;anHttpRequestParameter&gt;</code>, has not been configured as a parameter to be tracked by the policy engine, PingFederate does not record the parameter value in the audit log.</p> |
| uniqueuserkey                            | The unique user key tied to the user's authentication sessions. It is only set if the user authenticated using an IdP adapter that has configured a unique user key attribute.   |
| validatorid                              | The ID of the Password Credential Validator (PCV) instance, for the successful attempts.   |
| virtualserverid                          | The virtual server ID of a request, if applicable.   |

### Outbound provisioning audit logging

The PingFederate `provisioner-audit.log` file records outbound provisioning transactions, intended to facilitate security auditing.

The `provisioner-audit.log` log file is located in the `<pf_install>/pingfederate/log` directory. Outbound provisioning audit log information can be output to different formats, including database and Splunk.

The following table describes all recorded elements. Optionally, you can configure elements by editing the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.

| Item       | Description  |
|------------|--|
| %d         | Transaction time.  |
| cycle_id   | The unique ID for each provisioning cycle.                           |
| channel_id | The unique ID of the provisioning channel between source and target. |
| event_type | The type of provisioning events, such as CREATE and UPDATE.          |
| source_id  | The provisioning Source ID.  |
| target_id  | The provisioning Target ID.  |

| Item              | Description   |
|-------------------|---|
| is_success        | A flag to show whether the event was successful or not. If the attempt succeeded, the value is <code>true</code> ; otherwise, the value is <code>false</code> . |
| non_success_cause | Description of failure cause.   |

### Server logging

When PingFederate is configured to log `DEBUG` messages for troubleshooting purposes, it records all runtime and administrative events that can be used for troubleshooting in the `<pf_install>/pingfederate/log/server.log` file, including status and error messages.

Server log information can be output to a database server.



#### Note:

`DEBUG` messages are turned off by default. For troubleshooting purpose, you can re-enable it by editing the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.

The following table describes the recorded elements. Optionally, you can configure elements by editing the `log4j2.xml` file as well.

| Item           | Description   |
|----------------|---|
| %d             | Event date and time.  |
| %X{trackingid} | The tracking ID values uniquely identify user sessions, useful for correlating log messages in the audit and server logs. |
| %p             | Logging level.  |
| %c             | The Java class issuing the status or error message, when applicable.  |
| %m             | Status or error message.  |

To facilitate troubleshooting, administrators can use a filter utility to aggregate related events using the log filter tool.

### Server log filter

PingFederate provides a utility, `logfilter`, that administrators can use to filter server logs.

The `logfilter` utility is located in the `<pf_install>/pingfederate/bin` directory, `logfilter.bat` for Windows, and `logfilter.sh` for Linux.

The utility sorts through all the server logs in the log directory. Administrators can move or copy one or more server log files to a different directory that can be specified as an input parameter.

The log filter returns lists of log entries based on either:

- Entity ID and subject
- Tracking ID
- Session cross-reference ID

The following table describes the utility's command options. The table afterward describes optional parameters available for all of the commands.

## Server log filter command parameters

| Command parameter                                     | Description   |
|---|---|
| -entityid <b>entity ID</b><br>-subject <b>subject</b> | These two commands must be used together and return a list of transactions for the specified federation partner's entity ID and transaction subject.  |
| -trackingid <b>tracking ID</b>                        | This command returns a list of transactions with the same tracking ID.  |
| -sessionxrefid <b>session cross-reference ID</b>      | This command returns a list of transactions for an ID assigned by PingFederate to associate different transactions according to the user session under which they occurred. The value of <b>session cross-reference ID</b> can be the value of any of the following transaction tags in the target server logs: <ul style="list-style-type: none"> <li>▪ Artifact</li> <li>▪ Session Index</li> <li>▪ Assertion ID</li> </ul> |

## Server log filter parameters (optional)

| Parameter                                 | Description  |
|---|--|
| -logsdirectory <b>log files directory</b> | Full or relative path to source directory for the logs.<br>Default: all <code>server.log</code> files are written to the <code>&lt;pf_install&gt;/pingfederate/log</code> directory, a setting that can be adjusted by the <code>pf.log.dir</code> property in the <code>&lt;pf_install&gt;/pingfederate/bin/run.properties</code> file. |
| -outputfile <b>output file</b>            | Output path and file for the returned list.<br>Default: <code>\$(pf.log.dir)/logfilter_output.log</code> .   |
| -outputtoconsole                          | Returns list to the command console rather than to a file.   |

The log filter creates its own log file, `logfilter.log`, located in the log directory. Optionally, administrators can control settings for this log in the `<pf_install>/pingfederate/bin/logfilter.log4j2.xml` file.

### Logging in other formats

PingFederate provides the option of writing the audit log, the provisioner audit log, the provisioner log, and the server log to commonly used databases with failover to file logging.

For the audit log and the provisioner audit log, administrators can choose instead to write the information to the Common Event Format (CEF), a differently formatted log file that can be used by Splunk, or both.

### Writing logs to databases

Database logging replaces file logging. For each qualified database server, PingFederate provides scripts to create database tables for the audit log, the provisioner audit log, the provisioner log, and the server log.

### About this task

You can find these scripts in the `<pf_install>/pingfederate/server/default/conf/log4j/sql-scripts` directory.



#### Note:



was tested with vendor-specific JDBC drivers. For more information, see [Compatible database drivers](#) on page 124. To obtain the database driver .jar file, contact your database vendor. Install the database driver file to the `<pf_install>/pingfederate/server/default/lib` directory, and then restart the server.

Failover file logging is provided in the event that database logging fails for any reasons. By default, PingFederate retries database logging every minute. Messages written to log files during failover periods are not copied over to the database server.

You enable database logging for the audit log, the provisioner audit log, the provisioner log, and the server log in the `log4j2.xml` file.

## Steps

1. Edit `<pf_install>/pingfederate/server/default/conf/log4j2.xml`.
2. After the `Preserve messages in a local file` section, for each log that you want to enable database logging, uncomment the preset Java Database Connectivity (JDBC) appender configuration based on the choice of your database server.

### Audit log

- Oracle MySQL - `SecurityAuditToMySQLDB`
- Oracle Database - `SecurityAuditToOracleDB`
- PostgreSQL - `SecurityAuditToPostgreSQLDB`
- Microsoft SQL Server - `SecurityAuditToSQLServerDB`

### Provisioner audit log

- Oracle MySQL - `OutboundProvisionerEventToMySQLDB`
- Oracle Database - `OutboundProvisionerEventToOracleDB`
- PostgreSQL - `OutboundProvisionerEventToPostgreSQLDB`
- Microsoft SQL Server - `OutboundProvisionerEventToSQLServerDB`

### Provisioner log

- Oracle MySQL - `ProvisionerLogToMySQLDB`
- Oracle Database - `ProvisionerLogToOracleDB`
- PostgreSQL - `ProvisionerLogToPostgreSQLDB`
- Microsoft SQL Server - `ProvisionerLogToSQLServerDB`

### Server log

- Oracle MySQL - `ServerLogToMySQLDB`
- Oracle Database - `ServerLogToOracleDB`
- PostgreSQL - `ServerLogToPostgreSQLDB`

- Microsoft SQL Server - `ServerLogToSQLServerDB`

**Note:**

Each `JDBC` appender is followed by two related appenders, `PingFailover` and `RollingFile`. Together, they create a running `*-failover.log` file in the log directory in the event that database logging fails for any reason. Both appenders must also be enabled (uncommented).

**Tip:**

For more information about each appender, review inline comments and notes in the `log4j2.xml` file.

3. Replace placeholder parameter values in `log4j2.db.properties` in the same `conf` directory for the applicable Java Database Connectivity (JDBC) servers.

The parameter values provide access to the database. Test and validate access prior to production deployment. Like `log4j2.xml`, `log4j2.db.properties` is also individually managed per `PingFederate` server. This flexibility allows multiple `PingFederate` nodes in a clustered environment to write messages to different destinations, as needed.

**Tip:**

You can obfuscate the password used to access the database by running the `obfuscate` utility, located in the `<pf_install>/pingfederate/bin` directory: `obfuscate.bat` for Windows or `obfuscate.sh` for Linux. Use the actual password as an argument and copy the entire result into the value for the password parameter in `log4j2.db.properties`.

4. Uncomment the appender reference, `<AppenderRef/>`, in the associated logger elements, as described inline in the `log4j2.xml` file.

**Audit log**

Uncomment the corresponding `PingFailover` appender references from the following `Logger` elements located under the `Loggers` section:

- Browser SSO SP and adapter-to-adapter - `org.sourceid.websso.profiles.sp.SpAuditLogger`
- Browser SSO IdP and adapter-to-adapter - `org.sourceid.websso.profiles.idp.IdpAuditLogger`
- OAuth authorization server - `org.sourceid.websso.profiles.idp.AsAuditLogger`
- Dynamic Client Registration - `org.sourceid.websso.profiles.idp.ClientRegistrationAuditLogger`
- WS-Trust STS, IdP, and SP - `org.sourceid.wstrust.log.STSAuditLogger`

**Provisioner audit log**

Uncomment the corresponding `PingFailover` appender reference from the `ProvisionerAuditLogger` `Logger` element located under the `Set up the Outbound provisioner audit logger` section.

**Provisioner log**

Uncomment the corresponding `PingFailover` appender reference from the `com.pingidentity.provisioner.AsyncLogger` element located under the `Loggers` section.

## Server log

Uncomment the corresponding `PingFailover` appender reference from the `root` element located under the `Set up the Root Logger` section, near the end of the file.



### Important:

As indicated in the IMPORTANT comments for the loggers, you must also remove some of the existing appender references.

- Optional: For the audit log and the provisioner audit log, you can configure elements for database logging in the `ConversionPattern` appender parameter, as needed.

## Logging in Common Event Format

You can use `PingFederate` to write from logs using the Common Event Format (CEF) open standard.

CEF is an open logging standard. `PingFederate` provides an option of writing elements from the audit log, the provisioner audit log, or both at runtime to a syslog receiver for parsing and analysis using `ArcSight` from Micro Focus. Alternatively, administrators can write the information to a flat file in CEF. However, you should use syslog when available.



### Note:

`PingFederate` is tested with `ArcSight` for interoperability using the default elements defined in `log4j2.xml`. Any additions to these elements might render your CEF logging incompatible with `ArcSight`.

### Writing audit log in CEF

You can write the audit log in Common Event Format (CEF) in `PingFederate`.

## Steps

- Edit `<pf_install>/pingfederate/server/default/conf/log4j2.xml`.
- Under the `Security Audit log : CEF Formatted syslog appender` section, uncomment one of the preset appender configurations:
  - `SecurityAuditToCEFSyslog` - a `Socket` appender
  - `SecurityAuditToCEFFile` - a `RollingFile` appender



### Note:

The `SecurityAuditToCEFSyslog` `Socket` appender is followed by two related appenders, `PingFailover` and `RollingFile`. Together, they create a running `audit-cef-syslog-failover.log` file in the `log` directory in the event that CEF logging fails for any reason. Both appenders must also be enabled and uncommented.



### Tip:

Review inline comments and notes in the `log4j2.xml` file for more information about each appender.

- If you are configuring the `SecurityAuditToCEFSyslog` `Socket` appender, replace the placeholder parameter values for the syslog host.

4. If you are configuring the `SecurityAuditToCEFSyslog Socket` appender, uncomment the `PingFailover` appender reference (`<appender-ref ref="SecurityAuditToCEFSyslog-FAILOVER"/>`) from the following `Logger` elements located under the `Loggers` section:
  - `Browser SSO SP and adapter-to-adapter` -  
`org.sourceid.websso.profiles.sp.SpAuditLogger`
  - `Browser SSO IdP and adapter-to-adapter` -  
`org.sourceid.websso.profiles.idp.IdpAuditLogger`
  - `OAuth authorization server` - `org.sourceid.websso.profiles.idp.AsAuditLogger`
  - `Dynamic Client Registration` -  
`org.sourceid.websso.profiles.idp.ClientRegistrationAuditLogger`
  - `WS-Trust STS, identity provider (IdP), and service provider (SP)` -  
`org.sourceid.wstrust.log.STSAuditLogger`



#### Important:

As indicated in the IMPORTANT comments for the loggers, you must also remove some of the existing appender references.

#### Writing provisioner audit log in CEF

You can write provisioner audit logs in Common Event Format (CEF) for `PingFederate`. `PingFederate` provides an option of writing elements from the audit log and the provisioner audit log at runtime to a syslog receiver for parsing and analysis using `ArcSight` from `Micro Focus`.

#### Steps

1. Edit `<pf_install>/pingfederate/server/default/conf/log4j2.xml`.
2. Uncomment one of the preset appender configurations:
  - `OutboundProvisionerEventToCEFSyslog` (a `Socket` appender under the `Outbound provisioner audit log : CEF Formatted syslog appender` section)



#### Note:

This `Socket` appender is followed by two related appenders, `PingFailover` and `RollingFile`. Together, they create a running `provisioner-audit-cef-syslog-failover.log` file in the log directory in the event that CEF logging fails for any reason. Both appenders must also be enabled (uncommented).

- `OutboundProvisionerEventToCEFFile` (a `RollingFile` appender under the `Outbound provisioner audit log for CEFFile` section)



#### Tip:

Review inline comments and notes in the `log4j2.xml` file for more information about each appender.

3. If you are configuring the `OutboundProvisionerEventToCEFSyslog Socket` appender, replace the placeholder parameter values for the syslog host.
4. If you are configuring the `OutboundProvisionerEventToCEFSyslog Socket` appender, uncomment the `PingFailover` appender reference (`<appender-ref ref="OutboundProvisionerEventToCEFSyslog-FAILOVER"/>`) from the

ProvisionerAuditLogger Logger elements located under the Set up the Outbound provisioner audit logger section.

**Important:**

As indicated in the IMPORTANT comments for the loggers, you must also remove some of the existing appender references.

**Writing audit logs for Splunk**

Ping Identity provides a custom Splunk App for PingFederate to process audit logs generated by a PingFederate deployment. Splunk is an enterprise software that allows for monitoring, reporting, and analysis of consolidated log files.

Before you begin

- Download and install Splunk

About this task

Splunk captures and indexes real-time data into a single searchable repository where reports, graphs, and other data visualization can be generated.

The PingFederate Splunk App provides rich system monitoring and reporting, including:

- Current transaction and system reports
- Service reports, such as a daily usage report, and identity provider (IdP) and service provider (SP) reports per connection
- Trend reports, such as weekly and monthly usage reports, and trend analysis

Splunk uses a specially formatted version of the audit log `splunk-audit.log`, which you can write to the PingFederate log directory when you complete the setup steps.

**Note:**

The Splunk App for PingFederate is available separately. It requires enterprise-licensed, or trial installation of the Splunk software and the Splunk Universal Forwarder, which is needed to collect data from the PingFederate audit log for Splunk. The application includes additional documentation on installation and available features. To download the free application, go to [splunkbase.splunk.com](https://splunkbase.splunk.com) and search for PingFederate.

Steps

1. Set up your Splunk server.
  - a. Enable a receiver to listen for data from the PingFederate server.  
For more information, see the [Splunk documentation](#).
  - b. Install Splunk App for PingFederate.

2. Configure PingFederate to write audit log messages to the `<pf_install>/pingfederate/log/splunk-audit.log` file.
  - a. Edit `<pf_install>/pingfederate/server/default/conf/log4j2.xml`.
  - b. Locate the following Logger elements located under the Loggers section:
    - Browser single sign-on (SSO) SP and adapter-to-adapter - `org.sourceid.websso.profiles.sp.SpAuditLogger`
    - Browser SSO IdP and adapter-to-adapter - `org.sourceid.websso.profiles.idp.IdpAuditLogger`
    - OAuth authorization server - `org.sourceid.websso.profiles.idp.AsAuditLogger`
    - Dynamic Client Registration - `org.sourceid.websso.profiles.idp.ClientRegistrationAuditLogger`
    - WS-Trust STS, IdP, and SP - `org.sourceid.wstrust.log.STSAuditLogger`
    - Provisioner Audit Logger - `ProvisionerAuditLogger`
  - c. Uncomment the `SecurityAudit2Splunk RollingFile appender` reference, `<appender-ref ref="SecurityAudit2Splunk"/>`, from one or more of the Logger elements.

Example:

For example, the default logger for an IdP audit log reads as follows.

```
<Logger name="org.sourceid.websso.profiles.idp.IdpAuditLogger"
  level="INFO" additivity="false" includeLocation="false">
  <appender-ref ref="SecurityAudit2File" />
  <!--
    <appender-ref ref="SecurityAuditToCEFSyslog-FAILOVER"/>
    <appender-ref ref="SecurityAuditToCEFFile"/>
    <appender-ref ref="SecurityAuditToMySQLDB-FAILOVER"/>
    <appender-ref ref="SecurityAuditToPostgreSQLDB-FAILOVER" />
    <appender-ref ref="SecurityAuditToSQLServerDB-FAILOVER"/>
    <appender-ref ref="SecurityAuditToOracleDB-FAILOVER"/>
    <appender-ref ref="SecurityAudit2Splunk"/>
  -->
</Logger>
```

To log Browser SSO IdP audit log messages to `splunk-audit.log`, update the Logger element as follows.

```
<Logger name="org.sourceid.websso.profiles.idp.IdpAuditLogger"
  level="INFO" additivity="false" includeLocation="false">
  <b>appender-ref ref="SecurityAudit2Splunk"/>
  <!--
    <appender-ref ref="SecurityAuditToCEFSyslog-FAILOVER"/>
    <appender-ref ref="SecurityAuditToCEFFile"/>
    <appender-ref ref="SecurityAuditToMySQLDB-FAILOVER"/>
    <appender-ref ref="SecurityAuditToPostgreSQLDB-FAILOVER" />
    <appender-ref ref="SecurityAuditToSQLServerDB-FAILOVER"/>
    <appender-ref ref="SecurityAuditToOracleDB-FAILOVER"/>
    <appender-ref ref="SecurityAudit2Splunk"/>
    <b>appender-ref ref="SecurityAudit2File" />
  -->
```

```
</Logger>
```

**Note:**

For auditing of adapter-to-adapter events, you must enable both the IdP and SP loggers.

- d. Uncomment the following section:

```
<RollingFile name="SecurityAudit2Splunk" fileName="${sys:pf.log.dir}/
splunk-audit.log"
filePattern="${sys:pf.log.dir}/splunk-audit.%d

{yyyy-MM-dd}
.log"
ignoreExceptions="false">
<PatternLayout>
<pattern>%d trackingid="%X

{trackingid}
" event=%X

{event}
subject="%X

{subject}
" ip=%X

{ip}
app=%X

{app}
connectionid=%X

{connectionid}
protocol="%X

{protocol}
" pfhost=%X

{host}
role=%X

{role}
status=%X

{status}
adapterid=%X

{adapterid}
description="%X

{description}
" responsetime=%X

{responsetime}
inmessagetype="%X

{inmessagetype}
" %n</pattern>
</PatternLayout>
<Policies>
<TimeBasedTriggeringPolicy />
```

```
</Policies>
</RollingFile>
```

3. Set up Splunk Universal Forwarder.
  - a. Download the Splunk Universal Forwarder from [Splunk](#) and install it on the PingFederate server.
  - b. Configure the Splunk Universal Forwarder to monitor the `splunk-audit.log` file and forward the data to the receiver configured in [step 1b](#).

For detailed installation and configuration instructions, see the [Splunk Universal Forwarder documentation](#).


## Alternative console authentication

As an alternative to using PingFederate's own internal datastore for authentication to the administrative console, you can configure PingFederate to use your network's LDAP user-datastore, the RADIUS protocol, client certificates, or OIDC-based authentication.

You can configure any of these alternative console authentication methods at any time. Most user-management functions are handled outside the scope of the PingFederate administrative console when alternative authentication is enabled.

Unlike native authentication, for which you configure local accounts and their privileges in **System # Server # Administrative Accounts**, you must define roles in configuration files when using an alternative authentication scheme. Similar to native authentication, PingFederate provides two account types and three administrative roles for role-based access control, as shown in the following table.

### User Access Control

| Account type   | Administrative role | Access privileges  |
|--|---------------------|--|
| Admin  | User Admin          | Create users, deactivate users, change or reset passwords, and install replacement license keys.   |
| Admin  | Admin               | Configure partner connections and most system settings, except the management of local accounts and the handling of local keys and certificates. |
| Admin  | Expression Admin    | Map user attributes by using the expression language, Object-Graph Navigation Language (OGNL).   |
| <div style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>Only Administrative users who have both the Admin role and the Expression Admin role:</p> <ul style="list-style-type: none"> <li>▪ Can be granted the User Admin role. This restriction prevents non-Expression Admin users from granting themselves the Expression Admin Role.</li> <li>▪ Can be granted write access to the file system or directory where is installed. This restriction prevents a non-Expression Admin user from placing a <code>data.zip</code> file containing expressions into the <code>&lt;pf_install&gt;/pingfederate/server/default/deploy</code> directory, which would introduce expressions into .</li> </ul> </div> |                     |  |
| Admin  | Crypto Admin        | Manage local keys and certificates.  |
| Auditor  | Not applicable      | View-only permissions for all administrative functions. When the <b>Auditor</b> role is assigned, no other administrative roles can be set.      |



**Note:**

All four administrative roles are required to access and make changes through the following services:

- The `/bulk`, `/configArchive`, and `/configStore` administrative API endpoints
- The **Configuration Archive** window, accessed from **System # Server**, in the administrative console
- The **Connection Management** configuration item on the **Service Authentication** window, accessed from **Security # System Integration**

**Enabling OIDC-based authentication**

You can enable OIDC-based authentication to the administrative console by setting a property in the `run.properties` file, and by configuring other properties in the `oidc.properties` file.

About this task

**Important:**

All endpoints must be HTTPS.

**Steps**

1. On your OIDC provider, configure an OAuth client to represent the PingFederate administrative console. Specify the following redirect URI for the client:

`https://<pf_admin_hostname>:<pf_admin_port>/pingfederate/app?service=finishsso`

or, if using `pf.admin.baseurl`:

`https://<pf.admin.baseurl>/pingfederate/app?service=finishsso`

You need the client's credentials in the following steps.

2. Edit the `<pf_install>/pingfederate/bin/run.properties` file, and set the `pf.console.authentication` property to `OIDC`.

**Note:**

You might need to configure the `pf.admin.baseurl` property as well. This property defines the URL that PingFederate's administrative node uses to populate resource references in Administrative API responses. The administrative node also uses it for the redirect URL it sends to an OpenID Provider for administrator OIDC login (for example, `https://pingfederate-admin.example.com` or, if the load balancer uses a custom port, `https://pingfederate-admin.example.com:8443`). The default value is blank.

Use `pf.admin.baseurl` instead of `pf.admin.hostname`. If `run.properties` defines both, PingFederate ignores `pf.admin.hostname`. But if `run.properties` defines only `pf.admin.hostname`, PingFederate constructs the URL the same way it does in versions of PingFederate before 10.3.

3. Edit the `<pf_install>/pingfederate/bin/oidc.properties` file, and modify the applicable properties as described in the following table.

| Property               | Description   |
|------------------------|---|
| <code>client.id</code> | The client ID to communicate with the OpenID Provider (OP).<br>This property is required. |

| Property               | Description  |
|------------------------|--|
| client.secret          | <p>The client secret used to communicate with the OpenID Provider.</p> <p>The client secret should be in obfuscated format. We recommend that the secret be obfuscated using one of the following utilities in the <code>../bin</code> directory:</p> <ul style="list-style-type: none"> <li>On Windows: <code>obfuscate.bat</code></li> <li>On Linux: <code>./obfuscate.sh</code></li> </ul> <p>For example: <code>obfuscate.bat secret</code></p> <p>This property is required when the client authentication is either <code>client_secret_basic</code> or <code>client_secret_post</code>.</p> |
| client.authn.method    | <p>The type of client authentication that is expected by the token endpoint in the OpenID Provider. Supported values include:</p> <ul style="list-style-type: none"> <li><code>client_secret_basic</code> – Client credentials using the HTTP Basic authentication scheme.</li> <li><code>client_secret_post</code> – Client Credentials included in the request body.</li> <li><code>private_key_jwt</code> – Client authenticates in accordance with JSON Web Token (JWT).</li> </ul> <p>This property is required.</p>  |
| authorization.endpoint | <p>The authorization endpoint at the OpenID Provider.</p> <p>This property is required.</p>  |
| token.endpoint         | <p>The token endpoint at the OpenID Provider. PingFederate OIDC login only supports the authorization code flow.</p> <p>This property is required.</p>   |
| user.info.endpoint     | <p>The endpoint that is accessed when the required claims are not present in the ID tokens.</p> <p>This property is optional.</p>  |
| end.session.endpoint   | <p>The end session endpoint at the OpenID Provider. When no value is provided, the administrator will be redirected to the default PingFederate logout page.</p> <p>This property is optional.</p>   |
| issuer                 | <p>The issuer identifier of the OpenID Provider. The value provided is matched with the <code>iss</code> claims in the obtained ID token.</p> <p>This property is required.</p>  |
| acr.values             | <p>The authentication context class reference values that will be used by the OpenID Provider.</p> <p>This property is optional.</p>   |
| scopes                 | <p>The authorization endpoint at the OpenID Provider. The default setting is <code>openid</code>.</p> <p>This property is required.</p>  |

| Property   | Description   |
|--|---|
| username.attribute.name  | The name of the claim that represents the username of the administrator. The default setting is <code>sub</code> .<br><br>This property is required.  |
| role.attribute.name  | The name of the claim that is used to determine the role for administrators.<br><br>This property is required.  |
| role.map.admin. <i>n</i>   | Used when multiple values need to be mapped to a single PingFederate role. In this case, multiple properties must be created using a numeric, incremental suffix, starting with 1. For example:<br><br>role.map.admin.1=<br>role.map.admin.2=<br>role.map.admin.3=  |
| role.admin=<br>role.cryptoManager=<br>role.userAdmin=<br>role.expressionAdmin= | The administrator role claim value mapping. For example, assume that <code>admin_role</code> is a claim and the possible values for it are:<br><br>role.admin=admin<br>role.cryptoManager=crypto<br>role.userAdmin=uadmin<br>role.expressionAdmin=eadmin<br><br>When the claim <code>admin_role</code> has more than one value, for example, <code>admin_role : ["admin", "crypto", "uadmin"]</code> , the user will be granted <code>admin</code> , <code>crypto</code> , and <code>user administrator</code> roles.<br><br>When the claim <code>admin_role</code> has a single value, for example, <code>admin_role: "admin"</code> , the user will be granted <code>admin</code> role.<br><br>This property is required. |
| role.auditor   | The auditor role claim value mapping.<br><br>This property is optional.   |

- Restart PingFederate.

### Enabling LDAP authentication

You can enable LDAP authentication by using the configuration files located in the `<pf_install>/pingfederate/bin` directory.

#### About this task

When LDAP authentication is configured, PingFederate does not lock out administrative users based upon the number of failed sign-on attempts. Instead, responsibility for preventing access is delegated to the LDAP server and enforced according to its password lockout settings.

#### Steps

- In the `<pf_install>/pingfederate/bin/run.properties` file, change the value of the **pf.console.authentication** property as shown.  
`pf.console.authentication=LDAP`

2. In the `<pf_install>/pingfederate/bin/ldap.properties` file, change property values as needed for your network configuration.

For more information, see the comments in the file.

The roles configured in the properties file apply to both the administrative console and the administrative API.



#### Important:

Remember to assign LDAP users or designated LDAP groups to at least one of the PingFederate administrative roles as indicated in the properties file.



#### Tip:

You can also use this configuration file in conjunction with RADIUS authentication to determine permissions dynamically through an LDAP connection.

3. Start or restart PingFederate.

### Enabling RADIUS authentication

You can enable RADIUS authentication using the configuration files located in the `<pf_install>/pingfederate/bin` directory. The RADIUS protocol provides a common approach for implementing strong authentication in a client-server configuration.

#### About this task

PingFederate supports the protocol scenarios for one-step authentication, such as appending a one-time passcode obtained from an authenticator to the password, and two-step authentication, such as through a challenge-response process.



#### Note:

When RADIUS authentication is configured, PingFederate does not lock out administrative users based on the number of failed sign-on attempts. Instead, responsibility for preventing access is delegated to the RADIUS server and enforced according to its password lockout settings.



#### Note:

The NAS-IP-Address attribute is added to all Access-Request packets sent to the RADIUS server. The value is copied from the `pf.engine.bind.address` property in `run.properties`. Only IPv4 addresses are supported.

#### Steps

1. In the `<pf_install>/pingfederate/bin/run.properties` file, change the value of the `pf.console.authentication` property as shown.  
`pf.console.authentication=RADIUS`

2. In the `<pf_install>/pingfederate/bin/radius.properties` file, change property values as needed for your network configuration.

For more information, see the comments in the file.

The roles configured in the properties file apply to both the administrative console and the administrative API.



**Important:**

Be sure to assign RADIUS users or designated RADIUS groups to at least one of the PingFederate administrative roles as indicated in the properties file. Alternatively, you can set the `use.ldap.roles` property to `true` and use the LDAP properties file, also in the `bin` directory, to map LDAP group-based permissions to PingFederate roles.

3. Start or restart PingFederate.

### Multi-factor console authentication using PingID

PingID is a cloud service that enables multi-factor authentication (MFA) using a mobile application.

The PingFederate administrative console supports authentication through the RADIUS protocol, which provides a common approach for implementing strong authentication in a client-server configuration.

By combining these two capabilities, you can configure PingID to provide MFA to protect access to the PingFederate administrative console, which meets the requirement of stronger authentication for administrators accessing security-related software products.



**Note:**

PingID requires a separate license. Please contact [sales@pingidentity.com](mailto:sales@pingidentity.com) or request a trial license at [pingidentity.com](https://pingidentity.com).

### Requirements


The following components are required to enable MFA to the administrative console using PingID:

- PingFederate with external access to the PingID cloud service
- A PingID license
- A directory server where the administrative credentials and group membership are stored

### Solution overview

You can enable multi-factor console authentication using PingID.

When PingID is the second authentication factor for the PingFederate administrative console, the administrators must authenticate successfully against the first factor, such as a directory server, and subsequently respond to the request for authentication from the PingID app on their mobile devices.



## Multi-factor Console Authentication using PingID

### Processing steps

1. An administrator opens a browser and accesses the PingFederate administration console.
  - a. The administrative console displays the Sign On page.
  - b. The administrator enters the correct username and password.
2. PingFederate invokes the PingID Password Credential Validator (PCV) to validate the username and password against your directory server.
 

The PingID PCV comes with a built-in RADIUS server, which can be used as the point of authentication for the PingFederate administration console using RADIUS authentication.
3. Upon successful validation of the user credentials, the PingID PCV invokes the PingID service with the username.
 

The PingID service looks for the username in its datastore.

If the administrator has not registered a device for use with PingID, the PingID service returns a “username unknown” message. The administrative console displays a device registration window. The administrator must register the mobile device.
4. If the administrator has a registered device, the PingID service notifies the PingID app on the device or sends a text message (SMS) or voice callback message, depending on the configuration for that user account.
  - a. The administrator responds to the request for authentication from PingID.
  - b. If the administrator has successfully authenticated to the PingID notification, the PingID service returns a “success” message to the PingID PCV.
5. The administrative console menu opens.

### Configuring your PingID account

To use PingID as the second factor to authenticate into the PingFederate administrative console, you need a PingID or PingOne account. You must also configure the account to allow the PingID Password Credential Validator (PCV) to use the PingID service.

#### Steps

1. Register a PingID account.
  - a. Contact [sales@pingidentity.com](mailto:sales@pingidentity.com) for a registration key.
  - b. Register at [PingOne admin portal](#).
  - c. Select **PingOne for Enterprise** and then click **Next**.  
 Let the PingOne admin portal guide you through the registration process. At the end, a confirmation email is sent to your email address.
  - d. Open the confirmation email and follow the instructions to activate your PingOne for Enterprise account.
2. Enable PingID client integration.
  - a. Sign on to the [PingOne admin portal](#).
  - b. Go to **Setup # PingID # Client Integration**.
  - c. Under **Integrate with PingFederate and other Clients**, click **Download** and save the `pingid.properties` file for a subsequent task.
  - d. Sign off of the PingOne admin portal.

### Creating an LDAP Username Password Credential Validator instance

You can create an LDAP username password credential validator (PCV) in the PingFederate administrative console to create a second factor for multi-factor authentication (MFA).

#### About this task

Administrators must authenticate successfully against the first factor, such as a directory server where the administrator accounts, credentials and group memberships are stored. To fulfill this requirement, you need an LDAP connection from PingFederate to your directory server, and an instance of the LDAP Username Password Credential Validator.

#### Steps

1. Go to **System # Data & Credential Stores # Password Credential Validators**. On the **Password Credential Validators** window, click **Create New Instance**.
2. On the **Type** tab, from the **Type** list, select the **LDAP Username Password Credential Validator** and complete the **Instance Name** and **Instance ID** fields.
3. On the **Instance Configuration** tab, from the **LDAP datastore** list, select the datastore and complete the **Search Base** and **Search Filter** fields.

For more information about each field, see the following table.

| Field                        | Description   |
|------------------------------|---|
| LDAP Datastore<br>(Required) | The LDAP datastore configured in PingFederate.<br><br>If you have not configured the server to communicate with the LDAP directory server you need, click <b>Manage Data Stores</b> .<br><br>There is no default selection. |
| Search Base<br>(Required)    | The location in the directory server where the search begins.<br><br>This field has no default value.   |

| Field                       | Description   |
|-----------------------------|---|
| Search Filter<br>(Required) | <p>The LDAP query to locate a user record.</p> <p>If your use case requires the flexibility of allowing users to identify themselves using different attributes, you can include these attributes in your query. For instance, the following search filter allows users to sign on using either the <b>sAMAccountName</b> or <b>employeeNumber</b> attribute value through the HTML Form Adapter:</p> <pre>(   (sAMAccountName=\${username}) (employeeNumber=\${username}))</pre> <p>This field has no default value.</p> |
| Scope of Search             | <p>The level of search to be performed in the search base.</p> <p><b>One Level</b> indicates a search of objects immediately subordinate to the base object, not including the base object itself. <b>Subtree</b> indicates a search of the base object and the entire subtree within the base object distinguished name.</p> <p>The default selection is <b>Subtree</b>.</p>   |
| Case-Sensitive Matching     | <p>The option to enable case-sensitive matching between the LDAP error messages returned from the directory server and the <b>Match Expression</b> values specified on this window.</p> <p>This check box is selected by default.</p>   |

4. On the **Extended Contract** tab, click **Next** to skip to the **Summary** tab.
5. On the **Summary** tab, review the configuration, modify as needed, and then save the configuration.

#### *Configuring a PingID Password Credential Validator instance*

You can create and configure an instance of the PingID Password Credential Validator in the PingFederate administrative console.

Before you begin

Open the previously downloaded `pingid.properties` file in a text editor, copy its content, and then close the file.

Steps

1. Go to **System # Data & Credential Stores # Password Credential Validators**, and then click **Create New Instance**.
2. On the **Type** tab, from the **Type** list, select **PingID PCV (with integrated RADIUS server)** and complete the **Instance Name** and **Instance ID** fields.



3. On the **Instance Configuration** tab, configure the required fields as follows.
  - a. Click **Add a new row to 'RADIUS Clients'**, enter `127.0.0.1` as the RADIUS IP address and a value in the **Client Shared Secret** field. Click **Update**.

 **Tip:**

`127.0.0.1` represents the local RADIUS client, the PingFederate administrative console, which calls the RADIUS server bundled in the PingID PCV for authentication.

The **Client Shared Secret** value is required for the next task.

- b. Click **Add a new row to 'Delegate PCV's'**, select the previously created LDAP Username Credential Validator instance, and then click **Update**.
  - c. Paste the content from the `pingid.properties` file into the **PingID Properties File** field.
  - d. Review the rest of the default settings. Modify as needed to meet your requirements, and click **Next**.
4. On the **Extended Contract** tab, click **Next** to skip to the **Summary** tab.
5. On the **Summary** tab, review, modify if needed, and save the configuration.

#### Configuring PingFederate to use RADIUS authentication

You can enable RADIUS authentication in the PingFederate administrative console.

#### About this task

In this multi-factor console authentication use case, the PingFederate administrative console is a RADIUS client that calls the local RADIUS server bundled in the PingID Password Credential Validator (PCV) for the second factor authentication.

 **Note:**

For a clustered PingFederate environment, perform these steps on the console node.

#### Steps

1. Open the `<pf_install>/pingfederate/bin/run.properties` file in a text editor and set the **pf.console.authentication** property to RADIUS.

```
pf.console.authentication=RADIUS
```

2. Obfuscate the **Client Shared Secret** value using a PingFederate command-line tool.

Example:

Windows: `<pf_install>\pingfederate\bin\obfuscate.bat clientSharedSecret`

Linux: `<pf_install>/pingfederate/bin/obfuscate.sh clientSharedSecret`

Result:

The output should be a long line of text.

3. Copy the output for the next step.
4. Open the `<pf_install>/pingfederate/bin/radius.properties` file in a text editor and modify as follows.

```
host=<host>
shared.secret=obfuscatedClientSharedSecret
```

```
timeout=10000
```



#### Tip:

For a clustered PingFederate environment, the `host` value must be a runtime engine IP address or a hostname.

The `timeout` value is the number of milliseconds to wait for the second authentication factor to complete before timing out the login attempt. In this use case, ten seconds, or 10000 ms, should be sufficient for PingID.

In addition, assign one or more RADIUS users or designated RADIUS groups to at least one of the PingFederate administrative roles as indicated in the `radius.properties` file. Alternatively, you can set the `use.ldap.roles` property to `true` and use the LDAP properties file, `ldap.properties` in the same `bin` directory, to map LDAP group-based permissions to PingFederate roles.

5. Save your changes, and restart PingFederate.

#### Verifying your setup

Verify your setup after you have completed the required configuration.

#### Steps

1. Start PingFederate.

In a clustered PingFederate environment, start PingFederate on the console node.

2. Start a web browser.
3. Browse to the URL.

`https://<pf_host>:9999/pingfederate/app` where `<pf_host>` is the network address of your PingFederate server. It can be an IP address, a host name, or a fully qualified domain name. It must be accessible from your computer.

4. Authenticate using your directory user credentials.

Upon successful validation, the PingFederate administrative console prompts you to authenticate using PingID if you have a registered device. If you do not have a registered device, follow the steps shown on-screen to register a device.

5. Respond to the authentication request from PingID, and the PingFederate administrative console menu will display.

#### Result



#### Important:

Access to the PingFederate administrative console can now only be performed by using directory user credentials, followed by a PingID authentication.

### Enabling certificate-based authentication

You can enable certificate-based authentication in the PingFederate administrative console.

#### Before you begin

- Have a PingFederate username and password.
- Import the necessary client key and certificate into the web browser you use to access PingFederate.

### About this task

To enable client-certificate authentication, PingFederate administrative users must import an X.509 key and a suitable certificate for user authentication into their web browsers. In addition, the corresponding root certificate authority (CA) certificates must be contained in the Java runtime or the PingFederate trusted store. Other setup steps, including designating user permissions, must be completed by using configuration files located in the `<pf_install>/pingfederate/bin` directory.

The roles configured in the properties file apply to both the administrative console and the administrative API.

### Steps

1. Sign on to the PingFederate console as a user with permissions that include the **Crypto Admin** role.
2. Ensure the client-certificate's root CA and any intermediate CA certificates are contained in the trusted store, either for the Java runtime or PingFederate.



#### Note:

You can import a certificate to PingFederate in **Security # Certificate & Key Management # Trusted CAs**.



#### Tip:

You might want to click the Serial Number and copy the Issuer distinguished name (DN) to use in later steps.

3. In the `<pf_install>/pingfederate/bin/run.properties` file, change the value of the **pf.console.authentication** property as shown.
 

```
pf.console.authentication=cert
```
4. In the `<pf_install>/pingfederate/bin/cert_auth.properties` file, enter the Issuer DN for the client certificate as a value for the property **rootca.issuer.x**, where **x** is a sequential number starting at 1.



#### Note:

If you copied the Issuer DN after step 2, paste this value. For more information, see the comments in the file.

The roles configured in the properties file apply to both the administrative console and the administrative API.

5. Repeat the previous step for any additional CAs as needed.
6. Enter the certificate user's Subject DN for the applicable PingFederate permission roles, as described in the properties file.



#### Important:

The configuration values are case-sensitive.

7. Repeat the previous step for all users as needed.

**Note:**

Other settings in the properties file are used to display the user's ID (Subject DN) in abbreviated form in the administrative console.

8. Start or restart PingFederate.

## Configuring automatic connection validation

The intent of automatic multi-connection error checking is to verify that all configured connections have not been adversely affected by subsequent changes in supporting components.

### About this task

Automatic multi-connection error checking occurs when you access certain supporting components, such as the **SP Adapters** and **IdP Adapters** windows, the **Token Processors** window, the **Token Generators** window, the **Password Credential Validators** window, and the **Identity Store Provisioners** window.

As the number of connections and supporting components increases, so does the validation time. If you experience noticeable delays in accessing adapters, token translators, password credential validators, or identity store provisioner, you can turn off automatic connection validation.

**Note:**

When automatic connection validation is turned off, error checking is deferred until you access the connection lists on the administrative console. You can make configuration changes without being prompted to fix all dependency errors immediately, but remember that the configuration changes can potentially cause service disruption.

For example, if you remove a configured source-attribute in an attribute fulfillment configuration in a connection, users will be unable to complete single sign-on (SSO) requests until you reconfigure such connections.

When you access the **Connections** window, if the administrative console detects one or more dependency error conditions, it displays a visual cue to indicate the errors. To resolve each error, select the applicable connection and follow the on-screen instructions to modify the configuration.

This setting does not affect the validation of a connection being configured or modified. Also, individual connections are always validated automatically when you access them on the **Connections** window, regardless of the configuration of this setting.

To manage this setting for SP, go to **Applications # Integration # SP Connections** on the **SP Connections** window.

To manage this setting for IdP, go to **Authentication # Integration # IdP Connections** on the **IdP Connections** window.

## Steps

- To turn off automatic multi-connection error checking, go to **System # Server # General Settings**, and select the **Disable Automatic Connection Validation** check box. This check box is not selected by default.

For more information, see [Configuring general settings](#) on page 1023.

### Result:

After you select or clear the check box, the state of this setting is reflected on both the **SP Connections** window and the **IdP Connections** window.

## Automating configuration migration

PingFederate provides a configuration-migration tool for scripting the transfer of administrative-console configurations and configuration property files from one PingFederate server to another.

The `configcopy` tool can migrate your configurations, such as from a test environment to production. It can also manage certificates for the target server.



### Note:

As of PingFederate 10.2, the `configcopy` tool has been deprecated and will be removed in a future release.

The command-line utility, `configcopy`, in the `<pf_install>/pingfederate/bin` directory, uses PingFederate's built-in Connection Management Service in conjunction with an internal Web Service to export and import connections and other configurations, and to obtain lists. For more information, see [Connection Management Services](#).



### Important:

The Connection Management Service must be activated for both the source and target servers before you can use the `configcopy` tool. For more information, see [Configuring service authentication](#) on page 698.



### CAUTION:

For security reasons, you should disable the Connection Management Service whenever it is not in use.

## Copying the key from the source to the target server

You must copy the key from the source server to the target server before you migrate data using the `configcopy` tool.

### About this task



### Note:

As of PingFederate 10.2, the `configcopy` tool has been deprecated and will be removed in a future release.

To copy the key from the source to the target server, you copy the needed keys from the `pf.jwk` file on the source server and append it to the last key in the `pf.jwk` file on the target server, and then restart that target server. This step only needs to be completed before the first migration.

## Steps

1. In your PingFederate installation on the source server, open the `pf.jwk` file in the `<pf_install>/pingfederate/server/default/data` directory.
2. Copy the key in the file.

Make sure you copy the entire key JSON message, as in the following example.

```
{ "keys": [{"kty": "oct", "kid": "j0PUEdAb95", "k": "AGi8Lg_ewdl-
_30Cx83kDMQE9oNIhgJSa_Pc4I8JTU8"}] }
```

3. In your PingFederate installation on the target sever, open the `pf.jwk` file.
4. Insert a comma at the end of the last key in the file and append the source key.

For example, if the `pf.jwk` on the target server reads as follows.

```
{ "keys":
[ {"kty": "oct", "kid": "wER9zEpaPe", "k": "i0HQr9JmsqjAX4o_BQU1qGJzoLQI-
nmwp8u3GyHzTB8"} ] }
```

Insert the comma and the source key as shown.

```
{ "keys":
[ {"kty": "oct", "kid": "wER9zEpaPe", "k": "i0HQr9JmsqjAX4o_BQU1qGJzoLQI-
nmwp8u3GyHzTB8"},
{"kty": "oct", "kid": "j0PUEdAb95", "k": "AGi8Lg_ewdl-
_30Cx83kDMQE9oNIhgJSa_Pc4I8JTU8"}] }
```



### Note:

This is a well-formed JSON document in one line.

5. Save the `pf.jwk` file and restart the target server.
6. If applicable, repeat the steps above for each target PingFederate server.

## Administrative console migration

Use the `configcopy` tool to migrate data in the administrative console.



### Note:

As of PingFederate 10.2, the `configcopy` tool has been deprecated and will be removed in a future release.

For migrating data configured with the source server's administrative console, the `configcopy` tool performs these overall processing steps:

1. Retrieves specified connection and other configuration data (XML) from a source PingFederate server
2. Modifies the configuration with any changes required for the target environment, according to settings in one or more properties files, command-line arguments, or both
3. Imports the updated configuration into the PingFederate target server

The `configcopy` tool can perform these functions in real time, from server to server, or by using an intermediate file. The latter option is useful when both the source and target PingFederate servers are either not running at the same time or not accessible from the same operating system command window.



### Important:

For one-time configuration transfers from one version of PingFederate to a newer version, use a complete configuration archive, either with **configcopy** archive export/import commands, or manually through the administrative console, or the administrative API. Other **configcopy** commands are not supported for this purpose.

Operational capabilities include:

- Listing of source partner connections, adapter or STS token-translator instances, outbound-provisioning channels, or datastore connections.

List commands include optional filter settings, when applicable.

- Copying one or more partner connections, outbound-provisioning channels, or instances of adapters or token translators.
- Copying one or more datastore connections.
- Copying server settings.
- Exporting and importing full configuration archives.

Copying configuration files

The **configcopy** tool supports copying configuration files containing runtime properties, including those needed for server clustering, that might have been manually customized for the source configuration and need to be migrated. The file-copy command can also copy the PingFederate internal, HSQLDB database when needed.



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

Managing Certificates

Administrators can use the **configcopy** tool to perform the following certificate-management tasks on the target PingFederate server:

- List source trusted certificate authorities (CAs) and target key aliases
- Copy one or all trusted CAs from the source server
- Create certificates
- Create Certificate Signing Requests (CSRs)
- Import CA-signed and PKCS-12 certificates

**Using the migration tool**

The migration tool, **configcopy**, can be used in conjunction with one or more property files to define the operational command and other parameters, including the source and target PingFederate servers, and to modify configuration settings as needed for the target environment.

About this task



#### Note:

As of PingFederate 10.2, the **configcopy** tool has been deprecated and will be removed in a future release.

Property-file templates are available for each command option in the `<pf_install>/pingfederate/bin/configcopy_templates` directory.



**Note:**

See the `README.txt` file in the `configcopy_templates` directory for a list of all commands and summary information. See the template files for parameters associated with each command or with use cases, as well as lists of Override Properties, which are configuration settings that can be modified in transit, where applicable.

Copies of the templates can be configured as needed and then used together, or combined into one file. Use the applicable file names as an argument when running `configcopy.bat` or `configcopy.sh`, depending on your operating system, for particular configurations, using the following command syntax.

(On Windows)

```
configcopy.bat -Dconfigcopy.conf.file=<properties_file1>;
<properties_file2>;...
```



**Note:**

When paths are included with the file names, you cannot use backslashes (`\`). Use forward slashes (`/`) or escape the backslash (`\\`).

(On Linux)

```
configcopy.sh -
Dconfigcopy.conf.file=<properties_file1>:<properties_file2>;...
```



**Note:**

The file separators are platform specific, corresponding to the syntax used for system-level path separators.

Also, you can specify any property values through command-execution arguments, using the following syntax

```
configcopy[.sh] -D<property>=<value> ...
```

where `<property>` is any property named in the properties file and `<value>` is the value. Command-line property designations take precedence over any values set in the properties file.



**Note:**

Access to the Connection Management Service is password-protected. The usernames and passwords might be set in the properties file for both the source and target web services, and passwords can be obfuscated. If passwords are set in the properties file, they cannot be overridden using the command line. If a password is not set, the `configcopy` tool prompts for it. Usernames must always be supplied where applicable, either in the command line or in the properties file.

The `configcopy` utility generates its own log file, `configcopy.log`, located in the `<pf_install>/pingfederate/log` directory. You can control settings for this log, as needed, in the file `configcopy.log4j2.xml`, located in the `bin` directory.



**CAUTION:**

Importing connections or other discrete configurations at the target server is not subject to the same rigorous data validation performed by the administrative console during manual configuration. Although some checks are made, it is possible to create invalid connections using the connection-migration process. Therefore, you should not use the **configcopy** tool to create settings at the target that do not exist at the source. For connections and other configurations copied separately, the tool is designed only for modifying the values of existing source settings to make them applicable to the target environment.

To avoid errors and prevent unstable target configurations due to missing components or faulty cross-component references, such as invalid ID references from connection configurations to datastore configurations, adhere closely to the instructions provided in the following procedure.

**Steps**

1. Enable access to the Connection Management Service for both the source and target PingFederate servers. For more information, see [Configuring service authentication](#) on page 698.
2. Determine which component configurations need to be copied, including plugins.

For example, connection configurations always reference either adapter or token-translator configurations, or both, and may reference datastore configurations. These are all separate configurations, and must be copied separately in conjunction with copying connection configurations, unless they already exist at the target.

Server Settings, unless pre-configured at the target, also need to be copied over separately.

Provisioning settings can be copied separately to update target connections, as needed.

3. Determine whether any configuration property files or other supporting files need to be copied.
4. Ensure necessary plugin JAR files are installed on the target server.

The **configcopy** tool does not copy over these files, which include libraries for adapters, token translators, and JDBC or any custom database drivers.

The JAR files are located in either `<pf_install>/pingfederate/server/default/deploy` or `<pf_install>/pingfederate/server/default/lib`.

5. On the target server, ensure that signing certificates, or certificates used for XML decryption, are already in place. For more information, see [Certificate and key management](#) on page 657.

Private keys are not copied from server to server, public certificates can be copied. However, you can use **configcopy** to upload keys and certificates to the target server.

Look for identifying information about the target keys so you can reference the certificates in connection-copy properties.

6. If you have not yet installed your organization's CA-issued SSL server certificate on both the target and source servers, you can do so with a `configcopy` command. Otherwise, use one of the following methods to ensure that `configcopy` can contact both servers:
  - (Recommended) Install the Issuer certificate for the PingFederate SSL certificate in a separately managed trust store. Then the location of the file can be specified when running `configcopy` using the property `configcopy.connection.trust.keystore`.
  - Install the Issuer certificate for the PingFederate SSL certificate into the trust store for the Java runtime where `configcopy` runs.

 **Note:**

If different SSL certificates are installed on the two servers, the `configcopy` tool must be able to trust both. In this case, both certificates must be installed in the trust store used by `configcopy`, or in the trust store for the Java runtime where `configcopy` runs.

7. Create properties files for the necessary commands, and for associated command-parameter values needed to copy the required configurations and any additional files.

See the `README.txt` file and to the properties-file templates in the `<pf_install>/pingfederate/bin/configcopy_templates` directory.

 **Note:**

This step and those following assume the use of properties files based on the templates provided. You can also use command-line parameters. For more information, see previous steps in this section.

8. If you are copying connections, override ID properties referencing adapter, datastores or other plugin configurations, as needed see [step 2](#).

 **Important:**

Ensure that the plugin configurations are either previously defined at the target or are part of the same `configcopy` process used to copy the connections that depend on them.

9. Create a script or run a command, or command series, that executes `configcopy` for each of the prepared properties files.

See the previous discussion for syntax requirements, or the `README.txt` file.

## Outbound provisioning CLI



PingFederate provides a command-line interface (CLI) to help manage automated outbound provisioning at identity provider (IdP) sites.



Administrators can use the CLI to view the status of user provisioning, either globally or one provisioning channel at a time, and to rectify unusual situations where provisioning at the service provider (SP) might be out of sync with the enterprise user store.


The CLI tool, `provmgr.bat` or `provmgr.sh`, is located in the directory `<pf_install>/pingfederate/bin`. The tool interacts with the PingFederate internal datastore to maintain provisioning synchronization between the LDAP user store and the target service.

The tool creates its own log file, located at `<pf_install>/pingfederate/log/provmgr.log`. You can control settings for this log, as needed, in the `<pf_install>/pingfederate/bin/provmgr.log4j2.xml` file.

The following table describes the available global and channel-specific command arguments.

| Command argument   | Description   |
|--|---|
| Global options   |   |
| --help   | Describes the available options. The help also displays if you run the command with no arguments.   |
| --show-channels  | Lists all channels in a table format, showing for each: <ul style="list-style-type: none"> <li>▪ ID: A numeric channel ID (channel-specific commands need this ID)</li> <li>▪ Name: The channel name</li> <li>▪ Connection ID</li> <li>▪ Status: active   inactive (both the connection and the channel status are shown)</li> <li>▪ User count/dirty-user-record count, such as 5000/12, which means 5000 users and 12 dirty records</li> <li>▪ Source, as LDAP URL</li> <li>▪ Target code</li> </ul>      |
| --show-nodes   | Shows all the provisioning-server nodes with their status and the last timestamp. Applicable only when failover provisioning is configured in the <code>&lt;pf_install&gt;/pingfederate/bin/run.properties</code> file.   |
| --force-node-backup  | Sets the provisioner mode to FAILOVER for the associated PingFederate server node.  |
| Use with node number: -n <node ID>   |   |
| <b>Channel-specific options</b>  |   |
|  <b>Note:</b> <p>With each command, specify the channel with the <code>-c &lt;channel-id-number&gt;</code> argument. For example:</p> <pre>provmgr -c 1 --show-source</pre> <p>You can determine channel ID numbers by using the global command <code>provmgr --show-channels</code>.</p> |   |
| --reset-group-timestamp  | <p>Deletes the user-group timestamp, which forces the provisioner to process the provisioning group on the next cycle, even if the timestamp on that group did not actually change.</p> <p>Depending on your LDAP server and administrative practices, you might want to schedule this command to run periodically to catch up with any users that may have been deleted, rather than deactivated, in the directory server. Some directory servers do not update the group timestamp for deleted users.</p> |
|  <b>Important:</b> <p>You should rarely need this option if users are deactivated rather than deleted. If you do need it, you might want to schedule it when other network activity is low.</p>   |   |

| Command argument             | Description   |
|------------------------------|---|
| --reset-attribute-sync       | <p>Sets the attribute sync timestamp to 1, which forces the provisioner to look at all users for changes, not only those that have a newer timestamp on their LDAP entry.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>This is rarely needed and might consume considerable network resources, depending on the number of users. If it is needed, you might want to schedule it when other network activity is low.</p> </div>  |
| --reset-values-hash          | <p>Removes the values hash for all users. The database stores a hash of attribute values for users to determine whether any values have been changed.</p> <p>This argument forces users that have a newer timestamp on their LDAP entry to be updated at the service provider, regardless of the actual field values. However, users whose recorded timestamp is unchanged are not updated.</p>   |
| --reset-all                  | Equivalent to using all three of the previous arguments.  |
| --show-dirty-records         | Lists all users or groups that have not been provisioned or updated at the SP site. This option is rarely needed and might consume considerable network resources, depending on the number of users. If it is needed, you might want to schedule it when other network activity is low.   |
| --show-dirty-group-records   | List groups that have not been provisioned or updated at the SP site.   |
| --show-dirty-user-records    | List all users that have not been provisioned or updated at the SP site.  |
| --show-group                 | Shows all internal database fields related to the specified user or group, including transitory mapping fields, which are fields waiting to be pushed to the SP. For a user, shows all LDAP attributes retrieved from the directory server.   |
| --show-user                  |   |
| Use with:                    | <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can obtain user or group names and GUIDs for dirty records, as needed, using any of the <code>--show-dirty-*</code> options, described above.</p> </div> <p>The LDAP GUID, if used and if it is binary, should be entered in hexadecimal format, as shown in log files.</p> <pre style="background-color: #f0f0f0; padding: 5px; margin-top: 10px;"> provmgr.sh --show-user -u user@example.com provmgr.sh --show-user -g ffd448643f812b43a0bee2504173f0 </pre> |
| -u <provider name>           |   |
| Or:                          |   |
| -g <LDAP GUID>               |   |
| --clear-dirty-records        | Clears the dirty flag on all records.   |
| --clear-dirty-group-records  | Clears the dirty flag on all group records.   |
| --clear-dirty-user-records   | Clears the dirty flag on all user records.  |
| --delete-dirty-records       | Removes all dirty records from the internal store.  |
| --delete-dirty-group-records | Removes all dirty group records from the internal store.  |

| Command argument            | Description   |
|-----------------------------|---|
| --delete-dirty-user-records | Removes all dirty user records from the internal store.   |
| --delete-all                | <p>The <code>delete-all</code> parameter removes all users and groups from the internal store and deletes the provisioning group timestamp and the last attribute-sync timestamp.</p> <p>The <code>delete-all-users</code> parameter deletes users and timestamps but retains groups.</p> <p>The effect of either command is to reset the channel to its initial state for user provisioning. All user metadata is lost and provisioning for the channel will start from the beginning, picking up all users, and groups if deleted, and pushing them to the SP when the synchronization frequency interval has expired. The synchronization frequency interval is defined on <b>System # Server # Protocol Settings # Outbound Provisioning</b>.</p> |
| --delete-all-users          |   |
|                             | <div style="border: 1px solid black; padding: 5px;">  <b>Important:</b><br/>           You should rarely need these options. If needed, you might want to schedule the operation when other network activity is low.         </div>  |
| --show-target               | Displays the target configuration.  |
| --show-source               | Displays all source LDAP configuration parameters, including settings and location.   |

## Customizable user-facing pages

PingFederate supplies HTML templates, located in the `<pf_install>/pingfederate/server/default/conf/template` directory, to provide information to the end-users or to request user input when processing their requests.


The PingFederate HTML templates utilize the Velocity template engine, an open-source Apache project. For more information about Velocity, please refer to the Velocity project documentation on the Apache website at <https://velocity.apache.org>.

You can modify most of these pages in a text editor to suit the particular branding and informational needs of your PingFederate installation. CSS and images for these pages are included in the `template/assets` subdirectory. Each page contains both Velocity constructs and standard HTML. The Velocity engine interprets the commands embedded in the template page before the HTML is rendered in the user's browser. At runtime, PingFederate supplies values for the Velocity variables used in the template.

Each template contains specific variables that can be used for rendering the associated web page. You can see the variables and usage examples in the comments of each template.

The following table describes variables that are available across all templates.

| Variable                          | Description and Usage   |
|-----------------------------------|---|
| <code>utils-</code> utility class | The utility method to display JSON String arrays.<br><code>\$utils.toJsonArray(Collection&lt;Object&gt;)</code> - Use this method to convert a collection into a JSON string. |

| Variable                             | Description and Usage  |
|--------------------------------------|--|
| <code>\$escape</code>                | <p>A utility class that can be used to escape String variables inserted into the template, such as <code>\$escape.escape(\$client.name)</code> where <code>\$client.name</code> is one of the variables available in the <code>oauth.approval.page.template.html</code> template file.</p> <p>Use <code>\$escape.forJavaScript(\$variable)</code> when passing String variables into a JavaScript code block or an event handler within a template, such as <code>window.location.replace("\$escape.forJavaScript(\$wreply)")</code> as seen in the <code>sourceid-wsfed-idp-signout-cleanup-template.html</code> template file.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>Use the <code>\$escape</code> variable to escape external data, such as request parameters, to mitigate the risk of potential cross-site scripting (XSS) attacks.</p> </div> |
| <code>\$HttpServletRequest</code>    | A Java object instance of <code>javax.servlet.http.HttpServletRequest</code> . Used to add additional knowledge about the request that is otherwise unavailable in the template, such as the <i>User-Agent</i> HTTP header.  |
| <code>\$HttpServletResponse</code>   | A Java object instance of <code>javax.servlet.http.HttpServletResponse</code> . Used to modify the response in the template, such as setting additional browser cookies.   |
| <code>\$locale</code>                | A Java object instance of <code>java.util.Locale</code> that represents a user's country and language. Used to customize the end-user experience. For example, the locale is used to display content in the user's preferred language.   |
| <code>\$CurrentPingFedBaseURL</code> | The host name found in the request, provided that it matches either the PingFederate's base URL or one of the configured virtual host names.   |
| <code>\$PingFedBaseURL</code>        | The PingFederate base URL.   |
|                                      | For most deployments, use the <code>\$CurrentPingFedBaseURL</code> variable instead of the <code>\$PingFedBaseURL</code> variable.   |
| <code>\$templateMessages</code>      | Used to localize messages in the template, based on user's Locale, an instance of <code>com.pingidentity.sdk.locale.LanguagePackMessages</code> . For more information, see the Javadoc for the <code>LanguagePackMessages</code> class in the directory <code>&lt;pf_install&gt;/pingfederate/sdk/doc</code> .  |
| <code>\$TrackingId</code>            | The user's session tracking ID.  |

The following describes variables that are available on some templates.

| Variable                      | Description  |
|-------------------------------|--|
| <code>\$entityId</code>       | The entity ID (connection ID) of the SP connection used in this SSO transaction. |
| <code>\$connectionName</code> | The name of the SP Connection used in this SSO transaction.                      |
| <code>\$client_id</code>      | The ID of the OAuth client used in this transaction.                             |
| <code>\$spAdapterId</code>    | The SP Adapter ID used in this transaction.                                      |

| Variable                    | Description   |
|-----------------------------|---|
| <i>\$baseUrl</i>            | The base URL of PingFederate instance.  |
| <i>\$adapterId</i>          | The IdP Adapter ID used in this transaction.  |
| <i>\$oidcUiLocales</i>      | The value of the OpenID Connect <code>ui_locales</code> parameter that conveys the user's preferred languages and scripts for the user interface. |
| <i>\$extendedProperties</i> | The extended properties defined on either the connection or OAuth client.   |



### Important:

Changing Velocity or JavaScript code is not recommended.

At runtime, the user's browser is directed to the appropriate page, depending on the operation being performed and where the related condition occurs. For example, if a single sign-on (SSO) error occurs during identity provider (IdP)-initiated SSO, the user's browser is directed to the IdP's SSO error-handling page.

Applications can override the PingFederate server-hosted pages provided specifically for SSO and single logout (SLO) errors by specifying a URL value in the relevant application endpoint's **InErrorResource** parameter. Administrators can override SSO and SLO success pages by specifying default URLs on the **SP Default URLs** window (**Applications # Integration # SP Default URLs**) or the **IdP Default URL** window (**Authentication # Integration # IdP Default URL**).

The Velocity templates retrieve titles and other text from a message-property file, `pingfederate-messages.properties`, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory. You can also localize these messages using the PingFederate localization framework.



### Note:

If you have a clustered PingFederate environment, copy the customized, and localized, templates to each node.

## IdP user-facing pages

PingFederate has a variety of customizable user-facing page templates that apply to identity provider (IdP) pages. The templates are organized by HTML Form Adapter, Kerberos Adapter, single sign-on (SSO), single logout (SLO), WS-Federation, and OpenID Connect (OIDC).

### HTML Form Adapter

| Page title and template file name                              | Purpose  | Type   | Action              |
|--|--|--------|---------------------|
| Sign On or Choose an Account<br>identifier.first.template.html | Prompts a user to provide their username when an Identifier First Adapter instance is invoked to handle a sign on request. | Normal | User input required |

| Page title and template file name   | Purpose  | Type   | Action              |
|---|--|--------|---------------------|
| Sign On<br>html.form.login.template.html                                    | <p>Displays a customizable user sign-on form when an HTML Form Adapter instance is invoked to handle a sign on request.</p> <p>If the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to support authentication using third-party identity providers, those identity providers are displayed on the sign-on page as well.</p> <p>This is a core HTML template.</p> | Normal | User input required |
| Change Password<br>html.form.change.password.template.html                  | <p>Displayed when a user attempts to change their password through the HTML Form Adapter.</p>  | Normal | User input required |
| Change Password<br>html.form.message.template.html                          | <p>Displayed when a user successfully changes their password.</p> <p>This is a core HTML template.</p>   | Normal | User input required |
| Password Expiring<br>html.form.password.expiring.notification.template.html | <p>Displayed to warn an authenticated user that the password associated with the account is about to expire.</p> <p>This is a core HTML template.</p>  | Normal | User input required |
| Password Management System Message<br>html.form.message.template.html       | <p>Displayed when a user is being redirected to a password management system to change their password.</p> <p>This is a core HTML template.</p>  | Normal | User input required |
| Account Recovery<br>forgot-password.html                                    | <p>Displayed when a user attempts to reset their password through the HTML Form Adapter.</p> <p>If the user enters a username in the sign-on form, the username carries over to this form. Otherwise, the user must enter their username to begin the self-service password reset process.</p>   | Normal | User input required |



| Page title and template file name                            | Purpose  | Type   | Action              |
|--|--|--------|---------------------|
| Account Recovery<br>forgot-password-resume.html              | <p>Displayed to prompt a user to enter the one-time password sent through a notification or to notify a user to refer to the notification for password reset instructions.</p> <p>This template is applicable when the password reset type is <b>Email One-Time Link</b>, <b>Email One-Time Password</b>, or <b>Text Message</b> for the invoked HTML Form Adapter instance.</p> | Normal | User input required |
| Reset Your Password<br>forgot-password-change.html           | Displayed to prompt a user to define a new password.   | Normal | User input required |
| Account Recovery<br>forgot-password-success.html             | Displayed when a user successfully resets their password.  | Normal | User input required |
| Account Recovery<br>forgot-password-error.html               | Displayed when a password reset attempt fails.   | Error  | None                |
| Unlock Your Account<br>account-unlock.html                   | <p>Displayed when a user successfully unlocks their account through the HTML Form Adapter.</p> <p>This page also prompts the user to retain the current password, or reset it.</p>   | Normal | User input required |
| Security Question<br>html.form.login.challenge.template.html | <p>Displays a configurable challenge form for two-step authentication. For example, this template can be used to create a RADIUS challenge form when using the RADIUS Username/Password Credential Validator.</p> <p>This is a core HTML template.</p>   | Normal | User input required |
| User Consent<br>consent-form-template.html                   | Displayed when a request requires a user's consent for an SSO to an SP.  | Normal | User input required |
| Logout Confirmation<br>idp.slo.confirm.page.template.html    | <p>Displayed when a user initiates a logout request.</p> <p>Applicable only if such confirmation is required, as configured on the <b>Authentication # Integration # IdP Default URL</b> window.</p>   | Normal | User input required |

| Page title and template file name                                 | Purpose   | Type   | Action              |
|---|---|--------|---------------------|
| Sign Off<br>idp.logout.success.page.template.html                 | Displayed when a user successfully signs off in a configuration where the <b>Logout Path</b> field is configured but the <b>Logout Redirect</b> field is not.   | Normal | None                |
| Create Your Account<br>local.identity.registration.html           | Displays a configurable challenge form for two-step authentication. Displayed when a user requests to register for a local account.<br><br>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to support self-service registration.   | Normal | User input required |
| Manage Your Profile<br>local.identity.profile.html                | Displayed when an authenticated user accesses the profile management endpoint.<br><br>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to support self-service profile management.  | Normal | User input required |
| Email Verification<br>local.identity.email.verification.sent.html | Displays a notification that an email ownership verification message has been sent when an authenticated user accesses the email ownership verification endpoint.<br><br>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to offer users the opportunity to verify the ownership of the email address associated with the accounts. | Normal | None                |

| Page title and template file name  | Purpose  | Type   | Action  |
|--|--|--------|---|
| Email Verified<br>local.identity.email.verification.success.html         | <p>Displays a confirmation that the user has successfully verified the ownership of the email address associated with the account.</p> <p>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to offer users the opportunity to verify the ownership of the email address associated with the accounts.</p> | Normal | None  |
| Email Verification Error<br>local.identity.email.verification.error.html | <p>Displays that the user failed to verify the ownership of the email address associated with the account.</p> <p>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that is configured to offer users the opportunity to verify the ownership of the email address associated with the accounts.</p>                         | Error  | <p>User can request another verification email by accessing the email ownership verification endpoint or the profile management page (if enabled). Authentication is required.</p> <p>Alternatively, the user can contact their IT administrators for further assistance.</p> |
| Username Recovery<br>username.recovery.template.html                     | <p>Displays to prompt the user to enter an email address to recover the username associated with the account.</p> <p>Applicable only if the invoked HTML Form Adapter instance is configured to support self-service username recovery.</p>  | Normal | User input required   |

| Page title and template file name                         | Purpose   | Type   | Action   |
|---|---|--------|--|
| Username Recovery<br>username.recovery.info.template.html | Displays to notify the user to retrieve the notification message with the recovered username.<br><br>Applicable only if the invoked HTML Form Adapter instance is configured to support self-service username recovery. | Normal | User should retrieve the notification message with the recovered username. |

## Kerberos Adapter

| Page title and template file name        | Purpose  | Type   | Action      |
|--|--|--------|-------------|
| Error<br>kerberos.error.template.html    | Displays an error page to provide standardized information to the end user when the authentication attempt fails.  | Error  | Consult log |
| (No title)<br>meta.refresh.template.html | Facilitates the failover mechanism from a Kerberos Adapter instance to the next phase when it is part of a Composite Adapter instance configuration or an authentication policy. | Normal | None        |

## Single sign-on and logout

| Page title and template file name  | Purpose  | Type   | Action                        |
|--|--|--------|-------------------------------|
| Select Authentication System<br>sourceid-choose-idp-adapter-form-template.html | Displayed when multiple authentication sources are applicable and no preference is submitted as part of the request. | Normal | User input required           |
| Sign On Error<br>idp.sso.error.page.template.html                              | Displayed when IdP-initiated or adapter-to-adapter SSO fails and no other SSO error landing page is specified.       | Error  | Consult log and web developer |
| Sign Off Successful<br>idp.slo.success.page.template.html                      | Displayed when an SLO request succeeds and no other SLO success landing page is specified.                           | Normal | None                          |
| Sign Off Error<br>idp.slo.error.page.template.html                             | Displayed when an SLO request fails and no other SLO error landing page is specified.                                | Error  | User should close the browser |

## WS-Federation and OpenID Connect

| Page title and template file name  | Purpose  | Type   | Action |
|--|--|--------|--------|
| Working . . .<br>sourceid-wsfed-http-post-template.html                        | Used to auto-submit a WS-Federation assertion to the SP. If JavaScript is disabled, the user is prompted to click a button to POST the assertion directly.<br><br>This page is normally not displayed if JavaScript executes properly.   | Normal | None   |
| Signing off. . .<br>sourceid-wsfed-idp-signout-cleanup-invisible-template.html | WS-Federation and OIDC client IdP sign-out processing page.<br><br>No HTML is rendered in the browser.   | Normal | None   |
| Sign Off Successful<br>sourceid-wsfed-idp-signout-cleanup-template.html        | Indicates user signed out of the IdP under the WS-Federation protocol and lists each successful SP logout, when applicable.<br><br>Also displays when an OIDC client sends a logout request to the /idp/startSLO.ping endpoint to initiate an Asynchronous Front-Channel Logout process. | Normal | None   |

**SP user-facing pages**

PingFederate has a variety of customizable user-facing page templates that apply to service provider (SP) pages. Each template contains specific variables that can be used for rendering the associated web page.

## Account linking

| Page title and template file name                                    | Purpose   | Type   | Action |
|--|---|--------|--------|
| <b>Link Your Account</b><br>LocalIdPasswordLookup.form.template.html | Used to authenticate a user at the SP when an account link needs to be established. | Normal | None   |
| Account Unlinked<br>TerminateAccountLinks.page.template.html         | Communicates a user's successful defederation operation.                            | Normal | None   |

## Single sign-on and logout

| Page title and template file name                                      | Purpose   | Type   | Action                                       |
|--|---|--------|--|
| Select Identity Provider<br>sourceid-saml2-idp-selection-template.html | The user requested SP-initiated single sign-on (SSO), but the identity provider (IdP) partner was not specified in the appropriate query parameter or cookie. This page allows the user to select the IdP manually. Based on the user's selection, the server redirects the browser to the appropriate IdP partner's SSO service. | Normal | User must make selection                     |
| Please Specify Target<br>sp.sso.success.page.template.html             | Displayed when an SSO request succeeds but no target-resource parameter is specified by the incoming URL, and no default URL is set on the <b>Applications # Integration # SP Default URLs</b> window.  | Error  | Consult web developer or specify default URL |
| Sign On Error<br>sp.sso.error.page.template.html                       | Displayed when SP-initiated SSO fails, or IdP-initiated SSO fails on the SP side, and no other SSO error landing page is specified.   | Error  | Consult log and web developer                |
| Sign Off Successful<br>sp.slo.success.page.template.html               | Displayed when a single logout (SLO) request succeeds and no other SLO success landing page is specified.   | Normal | None   |
| Sign Off Error<br>sp.slo.error.page.template.html                      | Displayed when an SLO request fails and no other SLO error landing page is specified.   | Error  | User should close the browser                |

## WS-Federation

| Page title and template file name                                    | Purpose   | Type   | Action                        |
|--|---|--------|-------------------------------|
| Signed Off<br>sourceid-wsfed-sp-signout-cleanup-template.html        | Displays the user's sign-out status.  | Normal | None                          |
| Unable to Authenticate<br>sourceid-wsfed-idp-exception-template.html | Displayed when an authentication challenge fails during WS-Federation processing. | Error  | Consult log and web developer |

**Either IdP or SP user-facing pages**

PingFederate allows customizable user-facing windows that can be applied to both the identity provider (IdP) and service provider (SP) pages.

| Page title and template file name                             | Purpose   | Type   | Action   |
|---|---|--------|--|
| Sign On<br>AbstractPasswordIdpAuthnAdapter.form.template.html | Challenges user for credentials when authentication can take place via HTTP Basic authentication or an HTML form, depending on the operational mode.  | Normal | User must sign on  |
| Submit Form<br>form.autopost.template.html                    | Whenever the server posts a form, this template is used to auto-submit the form. If JavaScript is disabled, the user is prompted to click a button to post the form manually.<br><br>This page is normally not displayed if JavaScript executes properly. | Normal | None   |
| Multiple Sign-On Delay<br>speed.bump.template.html            | Displayed to indicate that simultaneous single sign-on requests from multiple browser tabs are in progress.   | Normal | User can switch to the browser tab that is actively waiting for the user to complete the authentication requirement or resubmit the request. |
| Error<br>general.error.page.template.html                     | Indicates that an unknown error has occurred and provides a error reference number and, optionally, an error message.   | Error  | Consult log<br><br>Contact Ping Identity <a href="#">Support</a> if unresolved   |
| Error<br>generic.error.msg.page.template.html                 | General error, with error code.   | Error  | Consult log and check configuration<br><br>Contact Ping Identity <a href="#">Support</a> if unresolved                                       |
| Error<br>http.error.page.template.html                        | Indicates that an HTTP error has occurred and provides the HTTP status code.  | Error  | Consult log<br><br>Contact Ping Identity <a href="#">Support</a> if unresolved   |

| Page title and template file name                        | Purpose  | Type  | Action |
|--|--|-------|--------|
| Page Expired<br>state.not.found.error.page.template.html | Displayed when simultaneous single sign-on (SSO) requests from multiple tabs using the same PingFederate cookie cause a user session to be overwritten or deleted and remaining requests attempt to retrieve the state fail. | Error | None   |

### OAuth user-facing pages

The PingFederate OAuth authorization server provides five windows that are presented to end-users, or resource owners, during certain OAuth transactions. You can customize and brand these windows as needed..

| Page title and template file name                       | Purpose   | Message type | Action              |
|---|---|--------------|---------------------|
| Client Access<br>oauth.access.grants.page.template.html | Provides a means for the end users, or resource owners, to revoke persistent access grants. | Normal       | User input required |



| Page title and template file name  | Purpose  | Message type | Action                               |
|--|--|--------------|--------------------------------------|
| Request for Approval<br>oauth.approval.page.template.html                        | <p>Advises resource owners that their information is being requested by the identified OAuth client when the default, internal, consent user interface is used. Resource owners can approve or deny individual scopes.</p> <p>Consent approval is applicable to the Device Authorization, Implicit, and Authorization Code grant types. For the latter two, PingFederate might prompt once at first or repeatedly depending on the <b>Reuse Existing Persistent Access Grants for Grant Types</b> setting in <b>System # OAuth Settings # Authorization Server Settings..</b></p> <p>In addition, the OAuth client configuration provides an option to bypass this approval page entirely, as needed for trusted clients. When applicable, select the <b>Bypass Authorization Approval</b> check box in the client configuration window.</p> <p>When an external consent user interface is used, PingFederate does not make use of this template file.</p> | Normal       | User input required                  |
| Connect a device (user code prompt)<br>oauth.device.user-code.page.template.html | <p>This page appears for the OAuth device authorization grant type. It allows resource owners to identify an authorization session that was initiated by the device client.</p> <p>This page appears after the resource owner goes to the OAuth verification URL and logs in. The user types the user code that they received from the device client, and then clicks <b>Submit</b>.</p>   | Normal       | User input and confirmation required |

| Page title and template file name  | Purpose   | Message type | Action                     |
|--|---|--------------|----------------------------|
| Connect a device (pre-populated user code prompt)<br>oauth.device.user-code-confirm.page.template.html | <p>This page appears for the OAuth device authorization grant type. It allows resource owners to identify an authorization session that was initiated by the device client.</p> <p>This page appears after the resource owner goes to the OAuth verification URL and logs in. The user confirms the pre-populated user code by clicking <b>Confirm</b>.</p> | Normal       | User confirmation required |
| Connect a device (result)<br>oauth.device.messages.page.template.html                                  | <p>This page appears for the OAuth device authorization grant type. It advises resource owners whether the OAuth device authorization was successful and provides any relevant error messages.</p> <p>By default, this page does not link to any other pages.</p>   | Normal       | No action                  |

## Customizable email notifications

PingFederate delivers messages to administrators and end-users based on customizable notification publisher settings.

Each component that is capable of triggering or handling events can use a different notification publisher instance to deliver its messages. For example, you can select an SMTP Notification Publisher instance to deliver messages to your end users in an HTML Form Adapter instance and another SMTP Notification Publisher instance to deliver licensing messages to your fellow administrators.

When a component is configured to deliver its messages based on an SMTP Notification Publisher instance configuration, PingFederate creates notification messages based on template files located in the `<pf_install>/pingfederate/server/default/conf/template/mail-notifications` directory. Each template file is a combination of variables and HTML codes. You can modify these template files in a text editor to suit the particular branding requirements, as needed.



### Note:

If you have a clustered PingFederate environment, copy the customized templates to each node.



### Tip:

You can also configure a component to use an Amazon SNS Notification Publisher instance to deliver notification messages. If so, refer to [Configuring an Amazon SNS Notification Publisher instance](#) on page 1010 and [Event types and variables](#) on page 1011 for more information about this messaging model and the handling of notification messages.

### Local administrative account management events

PingFederate generates a variety of email notifications for local administrative account management events.

Notification for account management events is configurable from **System # Server** in the **Administrative Accounts** window.



#### Note:

Account management events are only applicable when native authentication is enabled for the administrative console, the administrative API, or both in the `<pf_install>/pingfederate/bin/run.properties` file. If you are using an alternative console authentication, notifications, if any, such as password changes, are handled by the third-party system.

| Email subject and template file name  | Event  | Action   |
|---|--|--|
| PingFederate Notification Settings Change Notification<br>message-template-notifications.html | An administrator has turned off the <b>Notify Administrator of Account Changes</b> option.<br><br>PingFederate generates a notification message to all administrators.<br><br>The message includes the username of the administrator who made the change.  | Ensure this change is approved and legitimate. |
| PingFederate Email Change Notification<br>message-template-email.html                         | An administrator's email address has been updated by another administrator.<br><br>PingFederate generates a notification message to the previous email address and another notification to the new email address.<br><br>The message includes the username of the administrator who made the change. | Ensure this change is approved and legitimate. |
| PingFederate Password Change Notification<br>message-template-password.html                   | An administrator's password has been changed.<br><br>PingFederate generates a notification to the administrator whose password has been changed.<br><br>The message includes the username of the administrator who made the change.  | Ensure this change is approved and legitimate. |

### Certificate events

PingFederate sends email notifications for the creation, update, and expiration of certificates.

PingFederate also sends email notifications for the creation and activation of new pending certificates when automatic rotation for self-signed certificates is enabled in the **Security # Certificate & Key**

**Management # Signing & Decryption Keys & Certificates** window. It sends notifications to the email address that has been configured for certificate events on the **Runtime Notifications** window.

| Email subject and template file name   | Event   | Action   |
|--|---|--|
| A PingFederate Certificate Is About to Expire<br>message-template-cert-warning.html    | <p>A certificate is about to expire. PingFederate generates a notification based on settings defined on the <b>Runtime Notifications</b> window.</p> <p>The message includes the details of the certificate and the connections associated with it.</p>   | <p>Create a new certificate and work with the applicable partners to update the expiring certificate.</p> <p>If a self-signed certificate is used for signing or decryption, consider enabling certificate rotation while creating the new certificate.</p> <p>For a clustered PingFederate environment, replicate the configuration using the administrative console.</p> |
| A PingFederate Certificate Has Expired<br>message-template-cert-expire.html            | <p>A certificate expired. PingFederate generates a notification upon the expiration of a certificate.</p> <p>The message includes the details and the connections associated with the certificate.</p>  | <p>Create a new certificate and work with the applicable partners to update the expiring certificate.</p> <p>If a self-signed certificate is used for signing or decryption, consider enabling certificate rotation while creating the new certificate.</p> <p>For a clustered PingFederate environment, replicate the configuration using the administrative console.</p> |
| A New PingFederate Certificate Has Been Created<br>message-template-cert-rotation.html | <p>A new pending certificate has been created for signing or decryption. PingFederate generates a notification when a new pending certificate is created.</p> <p>The message includes the details of the current certificate, the details of the new certificate, the activation date, and the connections that will be affected when the new certificate is activated.</p> | <p>Work with the applicable partners to update the expiring certificate.</p> <p>PingFederate supports providing metadata for Browser SSO connections.</p> <p>For a clustered PingFederate environment, replicate the configuration using the administrative console.</p>   |

| Email subject and template file name   | Event  | Action  |
|--|--|---|
| A PingFederate Certificate Has Been Updated<br>message-template-cert-deactivation.html | A new certificate for signing or decryption is activated.<br>PingFederate generates a notification when the new certificate is activated.<br>The message includes the details of the new certificate and the affected connections. | None, unless the applicable partners have not been notified or configuration has not been replicated in a clustered PingFederate environment. |

### SAML metadata update events

When notification for SAML metadata update events is enabled in the **Runtime Notifications** window, PingFederate sends the notifications to the email address that has been configured for the event.

PingFederate supports automatic reloading of SAML metadata, which streamlines the maintenance of SAML connections.

| Email subject and template file name  | Event   | Action  |
|---|---|---|
| Your \${CONNECTION_NAME} \${SP_IDP} Connection in PingFederate Has Been Updated<br>message-template-metadata-updated.html                     | PingFederate has updated a connection based on the partner's SAML metadata.   | For a clustered PingFederate environment, replicate the configuration using the administrative console.   |
| Please Review Your Updated \${CONNECTION_NAME} \${SP_IDP} Connection in PingFederate<br>message-template-metadata-updated-out-of-sync.html    | PingFederate has updated a connection based on the partner's SAML metadata. However, some settings are out of sync.             | Review the settings that are out of sync and make changes as needed.<br>For a clustered PingFederate environment, replicate the configuration using the administrative console. |
| Your \${CONNECTION_NAME} \${SP_IDP} Connection in PingFederate Is Out of Sync<br>message-template-metadata-out-of-sync.html                   | A connection is out of sync with the changes found in the partner's SAML metadata.  | Review the settings that are out of sync and make changes as needed.<br>For a clustered PingFederate environment, replicate the configuration using the administrative console. |
| Your Metadata Couldn't Be Downloaded from \${METADATA_URL_NAME}<br>message-template-metadata-url-notification.html                            | PingFederate failed to download the SAML metadata from the partner or could not validate the digital signature of the metadata. | Consult log. Verify and update the metadata URL and its corresponding verification certificate.   |
| Your Metadata for PingFederate \${SP_IDP} Connection \${CONNECTION_NAME} Wasn't Found<br>message-template-metadata-url-entity-id-missing.html | The partner's metadata URL did not return the expected metadata for a given connection.   | Consult log. Verify and update the metadata URL.  |

## Licensing events

There is a list of different licensing events and different actions you can take to resolve each event.

When you enable notifications for licensing events, PingFederate sends license expiry information to the recipient configured for the event on the **Runtime Notifications** window.



### Tip:

To check the details of your license, sign on to the administrative console, navigate to the user icon in the upper-right corner of the administrative console, and click **About** the list. The license summary displays in a pop-up browser window.



### Important:

If the license specifies an expiration date, the license expires at the beginning of that day.

| Email subject and template file name   | Event  | Action   |
|--|--|--|
| Your PingFederate License Is About to Expire<br>message-template-warn.html       | The current license is about to expire.<br><br>The email notification is sent 60 days ahead of the expiration.<br><br>Applicable to licenses without connection groups.                              | Contact sales@pingidentity.com to renew the license before the expiration. |
| Your PingFederate License Is About to Expire<br>message-template-group-warn.html | One of the connection groups in the current license is about to expire.<br><br>The email notification is sent 60 days ahead of the expiration.<br><br>Applicable to licenses with connection groups. | Contact sales@pingidentity.com to renew the license before the expiration. |
| PingFederate License Expiration Notification<br>message-template-grace.html      | The current license expired.<br><br>The email notification is sent upon the expiration.<br><br>Applicable to licenses without connection groups.   | Contact sales@pingidentity.com to renew the license.                       |
| Your PingFederate License Has Expired<br>message-template-group-grace.html       | One of the connection groups in the current license expired.<br><br>The email notification is sent upon the expiration.<br><br>Applicable to licenses with connection groups.                        | Contact sales@pingidentity.com to renew the license.                       |

| Email subject and template file name   | Event  | Action   |
|--|--|--|
| PingFederate Has Stopped Processing Requests<br>message-template-shutdown.html | The current license and the grace period, if any, had lapsed.<br><br>Applicable to licenses without connection groups. | Contact sales@pingidentity.com to renew the license. |

### HTML Form Adapter events

The HTML Form Adapter offers self-service account management tools for password management, account recovery, username recovery, and email ownership verification.

When you configure an HTML Form Adapter instance to deliver its messages based on an SMTP Notification Publisher instance configuration, administrators can optionally customize and localize the following template files with branding controls to provide a consistent brand experience to end users across multiple user populations.

| Email subject and template file name   | Event   | Action  |
|--|---|---|
| Password Change Notification<br>message-template-end-user-password-change.html | A user's password has been changed successfully through an instance of the HTML Form Adapter.   | Users should contact their IT administrators if they have not made any attempts to change their password. |
| Password Reset<br>message-template-forgot-password-link.html                   | A user has initiated a self-service password reset request.<br><br>Applicable when the password reset type for the invoked HTML Form Adapter instance is set to <b>Email One-Time Link</b> .                                    | Users should contact their IT administrators if they have not made any attempts to reset their password.  |
| Password Reset<br>message-template-forgot-password-code.html                   | A user has initiated a self-service password reset request.<br><br>Applicable when the password reset type for the invoked HTML Form Adapter instance is set to <b>Email One-Time Password</b> or <b>Text Message</b> .         | Users should contact their IT administrators if they have not made any attempts to reset their password.  |
| Password Reset Completed<br>message-template-forgot-password-complete.html     | A user's password has been reset successfully through an instance of the HTML Form Adapter.<br><br>Applicable when the password reset type for the invoked HTML Form Adapter instance is set to any method except <b>None</b> . | Users should contact their IT administrators if they have not made any attempts to reset their password.  |

| Email subject and template file name   | Event  | Action   |
|--|--|--|
| <p>Account Unlocked<br/>message-template-account-unlock-complete.html</p>        | <p>A user account has been unlocked successfully through an instance of the HTML Form Adapter.</p> <p>Applicable when the <b>Account Unlock</b> option is enabled for the invoked HTML Form Adapter instance.</p>  | <p>Users should contact their IT administrators if they have not made any attempts to unlock their account.</p>  |
| Account Unlock Email Template  |  |  |
| <p>Password Reset Failed<br/>message-template-forgot-password-failed.html</p>    | <p>An attempt to reset the end-user's password has failed.</p>   | <p>Users should contact their IT administrators if they have not made any attempts to reset their password, or to seek help in resetting their password.</p> |
| <p>Email Verification<br/>message-template-email-ownership-verification.html</p> | <p>A user has provided an email address on the registration page, updated an existing email address with a new one on the profile management page, requested a resend of the verification email on the profile management page, or accessed the email ownership verification endpoint.</p> <p>Applicable only if the invoked HTML Form Adapter instance is associated with a local identity profile that has been configured to offer users the opportunity to verify the ownership of the email address associated with the accounts.</p> | <p>Users should contact their IT administrators if they have not made any attempts to update the email address associated with their accounts.</p>           |



| Email subject and template file name                         | Event   | Action  |
|--|---|---|
| Username Recovery<br>message-template-username-recovery.html | <p>A user has initiated a self-service username recovery request and provided an email address through an instance of the HTML Form Adapter. If PingFederate can locate the user record using such email address and other requirements are met, PingFederate uses this template to generate an email message containing the recovered username and sends it to the user at the email address provided by the user.</p> <p>Applicable only if the invoked HTML Form Adapter instance is configured to support self-service username recovery.</p> | Users should contact their IT administrators if they have not made any attempts to recover the username associated with their accounts. |

## Customizable text message

You can customize text messages in PingFederate for a unique experience.

If you have configured your self-service password reset and, optionally, your self-service account unlock to use the text message option, you can customize and localize the text message for a unique experience. The default message is stored as a property in the `<pf_install>/pingfederate/server/default/conf/language-packs/pingfederate-sms-messages.properties` file.



### Note:

If you have a clustered PingFederate environment, copy the customized, and localized, templates to each node.

## Localizing messages for end users

PingFederate supports localization for several types of messages for end users.

About this task

Administrators can localize the following message types:

- on-screen messages
- email messages
- text messages (SMS)
- authentication API error messages

The English contents for each message type are in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

| Message type       | Default message file                                |
|--------------------|---|
| On-screen messages | <code>pingfederate-messages.properties</code>       |
| Email messages     | <code>pingfederate-email-messages.properties</code> |

| Message type                      | Default message file                              |
|-----------------------------------|---|
| Text messages (SMS)               | <code>pingfederate-sms-messages.properties</code> |
| Authentication API error messages | <code>authn-api-messages.properties</code>        |

### Steps

1. Create a copy of the associated default message file in the `language-packs` directory.
2. Provide translated text in place of English and then append the standard language tag to the base file name, as indicated in the browser settings.

For example, to localize the user-facing window messages in French, rename the translated copy of the localization file to `pingfederate-messages_fr.properties`.

If the system language of the PingFederate server is not English, copy the default (English) message file and append `_en` at the end of the file name for any English users, such as from `pingfederate-messages.properties` to `pingfederate-messages_en.properties`, translate the default message file for the local users, and provide additional translations as needed.

3. If you want to include a region, append the capitalized abbreviation to the standard language tag with an underscore between them.

For example, to localize the text messages in Canadian French, rename the translated copy to `pingfederate-sms-messages_fr_CA.properties`.



#### Note:

The capitalization and underscore usage might not correspond to the way regions are listed in browser settings. However, the usage is required by the Java-based localization implementation.

4. If you have a clustered PingFederate environment, copy the localized message files to each node.

### Result

For on-screen and email messages, developers can also customize the look and feel of the templates by using localization variables in logic statements to control fonts, color, and other style elements. For more information, see the template files for examples.



#### Tip:

To maximize performance, PingFederate caches localized UI strings on start-up. For testing new localization implementations, an administrator can temporarily turn off caching by changing the value of the `cache-language-pack-messages` element to `false` in the `<pf_install>/pingfederate/server/default/data/config-store/locale-options.xml` file.

Return the value to `true` when testing is complete. You must restart the server after changes to configuration files.

### Locale overrides by cookies

An administrator or web developer might want to provide end-users a means of overriding browser language preferences temporarily by setting cookies, such as creating a company web portal link for users to click instead of manually changing their browser options.

By default, the PingFederate localization framework supports overriding the locale using a cookie named `pf-accept-language`. The cookie value must conform to the guidelines defined under [IETF BCP 47](#). For more information about the Java core method that PingFederate uses to parse the cookie, see [Locale.forLanguageTag\(String languageTag\)](#).

This locale-override behavior is the default implementation of the Java interface, `LocaleOverrideService`, defined in the PingFederate SDK. For more information, see the Javadoc for that interface in the `<pf_install>/pingfederate/sdk/doc` directory.

PingFederate displays the language indicated in the cookie if the language is supported in the `language-packs` directory. If the matching localization file is not found, PingFederate defaults to the browser settings.

### Retrieval of localized messages

Retrieval of localized messages is supported through the `LanguagePackMessages` class available in the PingFederate SDK. An instance of this class is passed into every template file and made available for use there. For more information, see the Javadoc for the class in the `<pf_install>/pingfederate/sdk/doc` directory.

## Configuring a password policy

PingFederate applies a configurable policy to passwords, pass phrases, and shared secrets defined by administrators in the administrative console.

About this task

These fields include, but are not limited to:

- Passwords used by HTTP Basic authentication for:
  - Inbound SOAP messages from partners via back-channel calls
  - WS-Trust STS
- Shared secrets used by the credentials defined for:
  - Attribute Query
  - Java Management Extensions (JMX)
  - Connection Management
  - Single sign-on (SSO) Directory Service
- Passwords used by instances of the Simple Username Password Credential Validator (PCV)
- Passwords used for encrypting certificates exported with their private keys
- Pass phrases used by identity provider (IdP) Discovery
- Passwords used by administrative console credentials when native authentication is used



#### Note:

Passwords external to PingFederate, such as passwords used by instances of the datastores, are not subject to this password policy.

Steps

1. Edit the `<pf_install>/pingfederate/server/default/data/config-store/password-rules.xml` file.
2. Save the changes.
3. Restart PingFederate.

For a clustered PingFederate environment, perform these steps on the console node. You do not have to change or restart PingFederate on the engine nodes.

## Managing cipher suites

You can enable, disable, and re-order cipher suites in PingFederate.

### About this task

The SSL/TLS server-client handshake involves negotiating cipher suites to use for encryption and decryption on each side of a secured transaction. You can find cipher suites in the following configuration files:

- `com.pingidentity.crypto.SunJCEManager.xml`
- `com.pingidentity.crypto.AWSCloudHSMJCEManager.xml`
- `com.pingidentity.crypto.LunaJCEManager.xml`
- `com.pingidentity.crypto.NcipherJCEManager.xml`
- `com.pingidentity.crypto.BCFIPSJCEManager.xml`

These cipher-suite configuration files are located in the `<pf_install>/server/default/data/config-store` directory. These files comment out weaker cipher suites. To ensure the most secure transactions, retain this cipher-suite configuration.



### Important:

Because of the import restrictions of some countries, Oracle Server Java SE Runtime Environment (JRE) 8 has built-in restrictions on available cryptographic strength (key size). To use larger key sizes, enable the Java Cryptography Extension (JCE) unlimited strength jurisdiction policy. For more information, see the Java 8 release notes in Oracle's documentation.

For Oracle Java SE Development Kit 11, the JCE jurisdiction policy defaults to unlimited strength. For more information, see the Oracle JDK Migration Guide in Oracle's documentation.

Starting with 9.1, cipher suites are selected based on the order that they are listed in the cipher-suite configuration file for new installations. For upgrades, you can enable the same selection mechanism as well.

### Steps

- Choose one of the following actions.  
Choose from:
  - Edit the applicable cipher-suite configuration file.
  - Save your changes.
  - Restart PingFederate.
- a. Edit the applicable cipher-suite configuration file.
- b. Save your changes.
- c. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**.



### Important:

For each engine node, restart PingFederate to load the changes made in the cipher-suite configuration file after the configuration is replicated.

- To enable cipher-suite selection based on listing order after an upgrade, follow these steps.
  - a. Create a new text file with the following content.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item name="prefer-server-cipher-suites">true</c:item>
</c:config>
```

- b. Save this file as `cipher-suite-settings.xml` in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
- c. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration on System # Server # Cluster Management**.



#### Important:

For each engine node, restart PingFederate to load the changes made in the `cipher-suite-settings.xml` file after the configuration is replicated.

## Manage externally stored authentication sessions

Authentication sessions control when previously authenticated users are redirected back to the authentication sources on subsequent requests for browser-based single sign-on (SSO) and PingFederate user-facing applications.

When you enable authentication sessions, PingFederate maintains session data in memory. PingFederate also supports maintaining session data both in memory and on an external storage. This optional capability allows your organization to support use cases where a longer session duration or a greater resilience against restarts of PingFederate and browsers is desired.

PingFederate supports storing persistent authentication sessions on a database server or a PingDirectory server. When stored on a database server, the default cleanup task removes expired authentication sessions once a day. If stored on a PingDirectory server, configure a cleanup plugin in PingDirectory to suit the needs of your organization.

### Managing authentication sessions stored in the database

PingFederate uses a cleanup task to remove expired authentication sessions from the configured database once a day. The cleanup task determines whether a session can be removed by looking at the session's expiration timestamp and the current time.

#### About this task

Any session that has an expiration timestamp older than the current time by a configurable offset is subject to removal. As needed, the cleanup task can look at the session's last activity timestamp instead. The cleanup task removes 500 expired sessions at a time until all expired sessions are removed. If expired sessions are growing rapidly, you can optionally increase the frequency of the cleanup task.



#### Note:

Increasing the frequency of the cleanup task or the number of expired sessions to be removed per batch (or both) adds more workload to your storage server. Make changes gradually to observe the impact.



#### Important:

In a clustered PingFederate environment, the cleanup task runs only on the console node. If adjustments are required, make them on the console node. No changes are required on any of the engine nodes.

## Steps

1. Optional: Adjust the frequency of the cleanup task.
  - a. Edit the `<pf_install>/pingfederate/server/default/data/config-store/timer-intervals.xml` file.
  - b. Update the **StoredSessionCleanerInterval** value, in milliseconds.  
The default value is 86400000, which is 24 hours.
  - c. Save your changes.
2. Optional: Configure other cleanup options.
  - a. Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl.xml` file.

See the following table for more information about each field.

| Field                        | Description  |
|------------------------------|--|
| ExpiredSessionGroupBatchSize | <p>The number of expired authentication sessions to be removed per batch.</p> <p>The default value is 500.</p> |

| Field                    | Description  |
|--------------------------|--|
| ExpirationTimeColumnName | <p>The column of which its value determines whether an authentication session has expired in the context of the cleanup task. Valid options are <code>expiry_time</code> and <code>last_activity_time</code>.</p> <p><code>expiry_time</code></p> <p>Set to <code>expiry_time</code> if the cleanup task should only remove persistent authentication sessions that have expired.</p> <p>The cleanup task determines if a session can be removed by looking at the session's expiration timestamp and the current time. If the expiration timestamp is older than the current time by the number of minutes specified by the <b>ExpirationTimeOffsetMins</b> field, the session is subject to removal.</p> <p><code>last_activity_time</code></p> <p>Set to <code>last_activity_time</code> if the clean task should remove persistent authentication sessions that have been left idle.</p> <p>The cleanup task determines if a session can be removed by looking at the session's last activity timestamp and the current time. If the last activity timestamp is older than the current time by the number of minutes specified by the <b>ExpirationTimeOffsetMins</b> field, the session is subject to removal.</p> <p>For example, if PingFederate should remove persistent authentication sessions for which the last activity time is more than three weeks ago, set the <b>ExpirationTimeColumnName</b> value to <code>last_activity_time</code> and the <b>ExpirationTimeOffsetMins</b> value to 30240.</p> <p>The default value is <code>expiry_time</code>.</p> |
| ExpirationTimeOffsetMins | <p>The offset, in minutes, relative to the current time.</p> <p>The default value is 10.</p>   |

- b. Save your changes.
  3. If you have made any changes, restart PingFederate.
- In a clustered PingFederate environment, you do not have to change or restart PingFederate on any of the engine nodes.

## Managing authentication sessions stored in PingDirectory

When storing persistent authentication sessions on a PingDirectory server, you must also configure a cleanup plugin in PingDirectory to remove expired authentication sessions from your directory server.

### Steps

1. Disable the PingFederate cleanup task.



#### Important:

For a clustered PingFederate environment, make these changes on the console node. None of the engine nodes require any changes.

- a. Edit the `<pf_install>/pingfederate/server/default/data/config-store/timer-intervals.xml` file.
  - b. Update the `StoredSessionCleanerInterval` value to 0.
  - c. Save your changes.
  - d. Restart PingFederate.
2. Sign on to the PingDirectory administrative console.
  3. Go to **Configuration # Plugin Root**.
  4. On the **Plugin Root** window, click **New Plugin**, and then select **Purge Expired Data Plugin**.
  5. Configure a new instance of the **Purge Expired Data Plugin**.

See the following table for information about each required field.

| Field   | Description   |
|---------|---|
| Name    | The name of this plugin instance.   |
| Enabled | <p>The status of this plugin instance.</p> <p>Select the check box to enable this plugin instance. Clear the check box to disable this plugin instance.</p> <p>This check box is not selected by default.</p> |



| Field              | Description  |
|--------------------|--|
| Datetime Attribute | <p>The attribute value determines whether an authentication session has expired in the context of this plugin instance. Valid options are <code>pf-authn-session-group-expiry-time</code> and <code>pf-authn-session-group-last-activity-time</code>.</p> <p><code>pf-authn-session-group-expiry-time</code></p> <p>Set to <code>pf-authn-session-group-expiry-time</code> if this plugin instance should only remove persistent authentication sessions that have expired.</p> <p>This plugin instance determines if a session can be removed by looking at the session's expiration timestamp and the current time. If the expiration timestamp is older than the current time by the number of minutes specified by the <b>Expiration Offset</b> field, the session is subject to removal.</p> <p><code>pf-authn-session-group-last-activity-time</code></p> <p>Set to <code>pf-authn-session-group-last-activity-time</code> if the clean task should remove persistent authentication sessions that have been left idle.</p> <p>This plugin instance determines if a session can be removed by looking at the session's last activity timestamp and the current time. If the last activity timestamp is older than the current time by the number of minutes specified by the <b>Expiration Offset</b> field, the session is subject to removal.</p> <p>For example, if PingFederate should remove persistent authentication sessions for which the last activity time is more than three weeks ago, set the <b>Datetime Attribute</b> value to <code>pf-authn-session-group-last-activity-time</code> and the <b>Expiration Offset</b> value to 3 w.</p> |
| Datetime Format    | <p>The format of the attribute specified in the <b>Datetime Attribute</b> field.</p> <p>Select <b>generalized-time</b> from the list.</p> <p>The default selection is <b>generalized-time</b>.</p>   |
| Expiration Offset  | <p>The offset relative to the current time.</p> <p>Enter an integer to indicate the time value, followed by its unit of measurement.</p> <p>This field has no default value.</p>   |
| Purge Behavior     | <p>The method how this plugin instance removes expired data.</p> <p>Select <b>subtree-delete-entries</b> from the list.</p> <p>This field has no default selection.</p>  |
| Polling Interval   | <p>The frequency of which this plugin instance should be run.</p> <p>Enter an integer to indicate the time value, followed by its unit of measurement.</p> <p>This field has no default value.</p>   |

| Field                  | Description  |
|------------------------|--|
| Max Updates Per Second | <p>This setting smooths out the performance impact on the server by throttling the purging to the specified maximum number of updates per second. To avoid a large backlog, this value should be set comfortably above the average rate that expired data is generated.</p> <p>When you select <b>subtree-delete-entries</b> from the <b>Purge Behavior</b> list, deletion of the entire subtree is considered a single update for the purposes of throttling.</p> <p>This field has no default value.</p> |

6. Click **Save**.

## OAuth persistent grants cleanup

PingFederate provides two cleanup tasks for persistent grants. One task manages expired grants, while another task caps the number of grants based on a combination of user, client, grant type, and authentication context.

Persistent authorizations include those obtained by OAuth clients in the following ways:

- Grants obtained or updated using the authorization code, resource owner credentials, or device authorization grant type, in conjunction with the refresh token grant type

 **Note:**

If the use cases involve mapping attributes from authentication sources, such as IdP adapter instances or IdP connections, or password credential validator (PCV) instances to the access tokens, directly or through persistent grant-extended attributes, storing these attributes from authentication sources and their values along with the persistent grants maintains them for reuse when clients subsequently present refresh tokens for new access tokens.

- Grants obtained or updated by using the implicit grant type, for which is configured to reuse existing persistent grants

 **Note:**

If the use cases involve mapping attributes from authentication sources or PCV instances to the access tokens, runtime procedures obtain attribute values for each token request, but persistent grants do not store with attributes or their values.

Persistent grants and any associated attributes and their values remain valid until the grants expire or until explicitly revokes or cleans them up. PingFederate's persistent grant cleanup routine manages expired grants based on the **Persistent Grant Max Lifetime** policy setting.

 **Note:**

PingFederate does not factor in the **Persistent Grant Idle Timeout** setting during grant cleanup. Ensure the grant datastore has the disk space needed to store expired grants because they exceeded the **Persistent Grant Idle Timeout** setting.

## Managing expired persistent grants

PingFederate removes expired persistent grants once a day. The cleanup task removes 500 expired grants at a time until all expired grants are removed.

About this task

If expired grants are growing rapidly, you can optionally increase the frequency of the cleanup task.



### Note:

Increasing the frequency of the cleanup task or the number of expired sessions to be removed per batch adds more workload to your storage server. Make gradual changes, if any, to observe the impact.



### Important:

In a clustered PingFederate environment, the cleanup task runs only on the console node. If adjustments are required, make them on the console node. No changes are required on any of the engine nodes.

When storing persistent grants on a PingDirectory server that is version 7.0 or later, you can use the PingFederate cleanup task or configure a cleanup plugin in PingDirectory instead. The plugin allows fine-grained control over various aspects of the cleanup task, which might improve the performance impact. For more information and configuration steps, see [Managing expired persistent grants in PingDirectory](#) on page 900.

## Steps

1. Optional: Adjust the frequency of the cleanup task.
  - a. Edit the `timer-intervals.xml` `<pf_install>/pingfederate/server/default/data/config-store` directory.
  - b. Update the `AccessGrantCleanerInterval` value, in milliseconds.
 

The default value is 86400000, which is 24 hours.
  - c. Save your changes.
2. Optional: Adjust the number of expired grants to be removed per batch.
  - a. Edit the configuration file relevant to your storage platform.

This configuration file is located in the `<pf_install>/pingfederate/server/default/data/config-store` directory, as described in the following table.

| Storage platform           | Configuration file   |
|----------------------------|--|
| Database server            | <code>org.sourceid.oauth20.token.AccessGrantManager</code> |
| PingDirectory              | <code>org.sourceid.oauth20.token.AccessGrantManager</code> |
| Microsoft Active Directory | <code>org.sourceid.oauth20.token.AccessGrantManager</code> |
| Oracle Unified Directory   | <code>org.sourceid.oauth20.token.AccessGrantManager</code> |

- b. Update the `ExpiredGrantBatchSize` value.

The following example shows an updated value of 400.

```
file, located in the<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  ...
  <c:item name="ExpiredGrantBatchSize">400</c:item>
  ...
```

```
</c:config>
```

The default value is 500.

- c. Save your changes.
3. After you have made changes, restart PingFederate.

In a clustered PingFederate environment, you do not have to change or restart PingFederate on any of the engine nodes.

### Managing expired persistent grants in PingDirectory

When storing OAuth persistent grants on a PingDirectory server that is version 7.0 or later, you can configure a cleanup plugin in PingDirectory to remove expired data from your directory server.

#### About this task

This PingDirectory plugin allows fine-grained control over various aspects of the cleanup task. For example, you can configure the maximum number of updates per second to improve the performance impact.

#### Steps

1. Disable the PingFederate cleanup task.



#### Important:

For a clustered PingFederate environment, make these change on the console node. No changes are required on any of the engine nodes.

- a. Edit the `<pf_install>/pingfederate/server/default/data/config-store/timer-intervals.xml` file.
- b. Update the `AccessGrantCleanerInterval` value to 0.
- c. Save your changes.
- d. Restart PingFederate.
2. Configure an instance of the PingDirectory plugin to clean up expired data.
  - a. Sign on to the PingDirectory administrative console.
  - b. Go to **Configuration # Plugin Root**.
  - c. Click **New Plugin** and then select **Clean up Expired PingFederate Persistent Access Grants Plugin**.
  - d. Configure a new instance of the **Clean up Expired PingFederate Persistent Access Grants Plugin**.

See the following table for information about each required field.

| Field   | Description  |
|---------|--|
| Name    | The name of this plugin instance.  |
| Enabled | The status of this plugin instance.<br><br>Select the check box to enable this plugin instance. Clear the check box to disable this plugin instance.<br><br>This check box is not selected by default. |

| Field                  | Description  |
|------------------------|--|
| Base DN                | The distinguished name (DN) that points to the access grants location.<br><br>For more information, see the inline comment and the <code>access-grant-ldap-pingdirectory.ldif</code> file in the <code>&lt;pf_install&gt;/pingfederate/server/default/conf/access-grant/ldif-scripts</code> directory. |
| Polling Interval       | The frequency of which this plugin instance should be run.<br><br>Enter an integer to indicate the time value, followed by its unit of measurement.<br><br>The default value is 5 m.   |
| Max Updates Per Second | This setting smooths out the performance impact on the server by throttling the purging to the specified maximum number of updates per second. To avoid a large backlog, this value should be set above the average rate that expired data is generated.<br><br>The default value is 100.              |

e. Click **Save**.

### Managing cleanup of persistent grants

PingFederate is capable of capping the number of persistent grants based on a combination of user, client, grant type, and authentication context.

#### About this task

Capping the number of persistent grants helps limit the data stored for persistent grants, especially in scenarios where clients frequently request authorization in a single context.

When PingFederate needs to record a new grant, it checks whether such creation will push the number of grants beyond the limit. If it does, PingFederate creates the grant and then removes just enough grants so that the number of grants is capped at the limit. This cleanup task starts from the oldest grant, expired or not, and continues forward if it needs to remove multiple grants. For performance reasons, this cleanup task also limits the number of grants it can remove per attempt. If it cannot remove all grants in excess of the limit, it removes what it can and repeats the process when PingFederate needs to record a new grant.

This cleanup runs on every engine node in a clustered PingFederate environment. Also, it does not replace the cleanup task or the PingDirectory plugin engineered to manage expired grants. Working together, they keep the size of the grant datastore under control.

The default limit is 100 grants per user, client, grant type, and authentication context. Depending on the storage platform, the default maximum number of grants that this cleanup task can remove per attempt varies.

This cleanup task is enabled on new installations. When upgrading from version 9.1 or an earlier version, it is disabled. You can enable it by editing an XML configuration file.

#### Steps

1. Edit the configuration file relevant to your storage platform.

This configuration file is located in the `<pf_install>/pingfederate/server/default/data/config-store` directory, as described in the following table.

| Storage platform | Configuration file   |
|------------------|--|
| Database server  | <code>org.sourceid.oauth20.token.AccessGrantManagerJd</code> |

| Storage platform           | Configuration file                              |
|----------------------------|---|
| PingDirectory              | org.sourceid.oauth20.token.AccessGrantManagerLD |
| Microsoft Active Directory | org.sourceid.oauth20.token.AccessGrantManagerLD |
| Oracle Unified Directory   | org.sourceid.oauth20.token.AccessGrantManagerLD |

2. Locate for the following comments.

```

...
<!--
    Maximum number of persistent grants allowed to store in the database
    per user,
    client and grant type and authentication context qualifier.

    Setting this to a value <= 0 will turn this limit off
    Default configuration:
    <c:item name="maxPersistentGrants">100</c:item>
-->
<c:item name="maxPersistentGrants">100</c:item>
<!--
    Maximum number of persistent grants to delete when max allowed is
    reached
    during new grant creation.

    Setting this to a value <= 0 will turn this limit off
    Default configuration:
    <c:item name="maxPersistentGrantsToRemoveBatchSize">n</c:item>
-->
<c:item name="maxPersistentGrantsToRemoveBatchSize">n</c:item>
...

```

The **maxPersistentGrants** value represents the maximum number of grants based on a combination of user, client, grant type, and authentication context.

The **maxPersistentGrantsToRemoveBatchSize** value represents the maximum number of grants that the cleanup task would remove per attempt. Its default value (*n*) varies depending on the storage platform, 50 for a database server and 10 for a directory server.



**Note:**

The **maxPersistentGrants** and **maxPersistentGrantsToRemoveBatchSize** items exist only on new installations starting with version 9.2. When upgrading from version 9.1 or an earlier version, the upgrade tools only insert the comments for reference.

3. Optional: Adjust the **maxPersistentGrants** and **maxPersistentGrantsToRemoveBatchSize** values.

Use integers only.

4. To enable this cleanup task after upgrading from version 9.1 or an earlier version, insert the **maxPersistentGrants** and **maxPersistentGrantsToRemoveBatchSize** items into the configuration file.

You can use the default values based on the inline comment. You can also adjust the values to suit the needs of your organization.

5. Save your changes.

## 6. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.

## Specifying the domain of the PF cookie

PingFederate identifies sessions by their respective PingFederate cookie. You can specify the domain of these cookies.

### About this task

By default, the PingFederate cookie is set without domain information in the HTTP header.

```
Set-Cookie: PF=zOv4xxmzDI2rx1TFBFy78X;Path=/;Secure;HttpOnly
```

You can configure PingFederate to return the Set-Cookie HTTP header with domain information, as needed.

### Steps

1. Edit the `<pf_install>/pingfederate/server/default/data/config-store/session-cookie-config.xml` file.
2. Modify the `cookie-domain` element.

Example:

```
<c:item name="cookie-domain">.example.com</c:item>
```

3. Save the change.
4. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.

### Result

After you activate this change, PingFederate includes domain information in its Set-Cookie HTTP header.

```
Set-Cookie: PF=aDfPx6uwbbWGFhwE6zEhEG;Path=/;Domain=.example.com;Secure;HttpOnly
```

## Specifying the domain of the PF.PERSISTENT cookie

PingFederate identifies persistent authentication sessions by their respective PF.PERSISTENT cookie. You can specify the domain of this cookie.

### About this task

By default, the PF.PERSISTENT cookie is set without domain information in the HTTP header.

```
Set-Cookie: PF.PERSISTENT=UoBlPlf16V2oYAEPot2DnpUOXxitK7au;Path=/;Expires=Sat, 06-Nov-2021 00:48:08 GMT;Max-Age=94608000;Secure;HttpOnly
```

You can configure PingFederate to return the Set-Cookie HTTP header with domain information, as needed.

### Steps

1. Edit the `<pf_install>/pingfederate/server/default/data/config-store/persistent-session-cookie-config.xml` file.

2. Modify the `cookie-domain` element.

Example:

```
<c:item name="cookie-domain">.example.com</c:item>
```

3. Save the change.
4. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.

## Result

After you activate this change, PingFederate includes domain information in its Set-Cookie HTTP header.

Set-Cookie:

```
PF.PERSISTENT=tOYwPM7VFMeluUyeu0EKQLL0DCJyVOqG;Path=/;Domain=.example.com;Expires=Sat,06-Nov-2021 01:00:34 GMT;Max-Age=94608000;Secure;HttpOnly
```

## Extending the lifetime of the PingFederate cookie

PingFederate identifies sessions by their respective PingFederate cookies. You can manually extend the lifetime of these cookies.

### About this task

Some adapters, such as the HTML Form Adapter, also utilize the PingFederate cookie to manage their adapter-sessions. The PingFederate cookie is a session cookie by default. You can extend the lifetime of the PingFederate cookie by making it a persistent cookie. Unlike session cookies, persistent cookies are saved to disk, enabling the browser to reuse them when restarted.



### Tip:

Alternatively, you can configure PingFederate to store authentication sessions externally and leverage them as users request protected resources after restarting their browsers. For more information, see [Sessions](#) on page 292.

## Steps

1. Edit the `session-cookie-config.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
2. Modify the `cookie-max-age` value.

The default value, `-1`, makes the PingFederate cookie a session cookie. A positive integer defines the age of the persistent cookie in seconds.

3. Save the change.
4. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.



## Configuring forward proxy server settings

You can configure PingFederate to send web traffic, such as HTTP and HTTPS, so that it initiates through a forward proxy server.

### Steps

1. Edit the `<pf_install>/pingfederate/bin/run.properties` file.
2. Locate for the following properties.

```
#http.proxyHost=<HTTP_PROXY_HOST>
#http.proxyPort=<HTTP_PROXY_PORT>
#https.proxyHost=<HTTPS_PROXY_HOST>
#https.proxyPort=<HTTPS_PROXY_PORT>
#http.nonProxyHosts=*.internal.com|localhost
```

3. Optional: Configure forward proxy server settings for HTTP traffic.
  - a. Remove the number sign (#) in front of `http.proxyHost` and `http.proxyPort`.
  - b. Enter the hostname or the IP address of the forward proxy server.
4. Optional: Configure forward proxy server settings for HTTPS traffic.
  - a. Remove the number sign in front of `https.proxyHost` and `https.proxyPort`.
  - b. Enter the hostname or the IP address of the forward proxy server.
5. Optional: Configure an exclusion list.
  - a. Remove the number sign in front of `http.nonProxyHosts`.
  - b. Specify one or more destinations where PingFederate is not required to proxy its HTTP and HTTPS traffic through the forward proxy server.

This property supports multiple values separated by the pipe character (|) and the wildcard character (#) for pattern matching.

```
*.example.com|localhost
```

6. Save your changes.
7. Restart PingFederate.

For a clustered environment, repeat these steps on each node.

## Adding custom HTTP response headers

The PingFederate administrative console and runtime server are capable of returning custom HTTP response headers, such as HTTP Strict-Transport-Security (HSTS), to enforce HTTPS-based access and P3P.

### Steps

1. Edit the `response-header-admin-config.xml` file or the `response-header-runtime-config.xml` file, or both, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
2. Save your changes.
3. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.

## Configuring validation for the AudienceRestriction element

You can configure validation for the **AudienceRestriction** value in a SAML response.

About this task

For any identity provider (IdP) connection configured with multiple virtual server IDs, the **AudienceRestriction** value in a SAML response must match the virtual server ID information embedded in the protocol endpoint at which PingFederate receives the message.

You can disregard this validation condition on a per-connection basis.

Steps

1. Edit the `org.sourceid.saml20.util.VirtualIdentityUtil.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
2. Optionally, if you want to disregard the validation condition for an IdP connection, add its **Partner's Entity ID** value as an entry inside the `c:map` element.

Example:

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:map name="AllowAnyVirtualServerIdInAudience">
    <c:item name="www.example.com"/>
    <c:item name="www.example.org"/>
  </c:map>
</c:config>
```

Result:

In this example, the first entry adds the IdP connection with a **Partner's Entity ID** of `www.example.com` to the list. This is so that PingFederate no longer returns an error if the **AudienceRestriction** value in a SAML response does not match the virtual server ID information embedded in the protocol endpoint at which PingFederate receives the message. The second entry has the same effect for the IdP connection with a **Partner's Entity ID** of `www.example.org`.

3. Save your changes.
4. Restart PingFederate.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**. You do not have to restart on any running engine node.

## Customizing the OpenID Provider configuration endpoint response

The OpenID Provider (OP) configuration endpoint at `/.well-known/openid-configuration` provides configuration information for the OAuth clients to interface with PingFederate using the OpenID Connect (OIDC) protocol.

About this task

As needed, you can customize the amount of configuration information by modifying a template file. You can also add conditional statements to return different responses, based on information from the requests to suit multiple use cases simultaneously.

## Steps

1. Edit the `openid-configuration.template.json` file, located in the `<pf_install>/pingfederate/server/default/conf/template` directory, to specify the desired information to be returned by the OP configuration endpoint.

Multiple samples are provided, including sample statements using the `$HttpServletRequest` and `$HttpResponse` objects to get and set values.

2. Save your changes.

Template customization does not require a restart of PingFederate. For a clustered environment, repeat these steps on each node.

## Customizing the heartbeat message

The heartbeat endpoint, `/pf/heartbeat.ping`, returns a customizable OK browser message and an HTTP 200 status indication if the PingFederate server is running.

### About this task

You can customize the message by modifying the `pf.heartbeat.system.monitoring` PingFederate property.



#### Note:

If a GET request receives a connection error or an HTTP status code other than 200, the server associated with the endpoint is down or malfunctioning.

## Steps

1. Set the `pf.heartbeat.system.monitoring` property in the `<pf_install>/pingfederate/bin/run.properties` file to `true` or `false`.

When `pf.heartbeat.system.monitoring` is set to `false`, the `/pf/heartbeat.ping` endpoint returns OK. When set to `true`, the `/pf/heartbeat.ping` endpoint returns all available statistics.



#### CAUTION:

Before exposing these additional statistics on the heartbeat endpoint, ensure the endpoint cannot be reached beyond the load balancer so that this information isn't publicly available.

2. Restart PingFederate.
3. If you want to customize the information returned by the heartbeat endpoint, edit the `heartbeat.page.template` file, located in the `<pf_install>/pingfederate/server/default/conf/template` directory.

Template customization does not require a restart of PingFederate. For a clustered PingFederate environment, repeat these steps on each node.

4. If you want to specify percentiles in addition to, or in place of, the default 90th percentile in the statistics reported on the heartbeat:
  - a. Edit the `com.pingidentity.monitoring.MonitoringService.xml` file located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.
  - b. Change the value of the `StatisticsPercentilesList` item to the preferred percentile. You can enter a single value, such as `99.9`, or multiple values separated by commas, such as `80,90,99.5`.

 **Note:**

The `StatisticsPercentilesList` item allows you to customize the percentiles displayed in the heartbeat endpoint response of the metrics ending in `.<StatisticsPercentilesList>.percentile`. Percentiles can be a helpful way to understand a metric's distribution and identify patterns or trends over time. They can also be used to set performance targets or to identify bottlenecks in a system.

In the context of server response metrics, you can use percentiles to compare a server's response time to other servers or previous periods. For more information, including a complete list of server metrics and their descriptions, see [Liveliness and responsiveness](#).

Example: Setting the `StatisticsPercentilesList` item to `50` will display the 50th percentile of a server's response time in the heartbeat endpoint response. A value of `200` milliseconds for the 50th percentile means that 50% of the server's responses were faster than 200 milliseconds, while 50% were slower. Similarly, a value of `500` milliseconds for the 95th percentile means that 95% of the server's responses were faster than 500 milliseconds, while 5% were slower.

- c. Save your changes.

## Customizing the favicon for application and protocol endpoints

PingFederate provides a favorite icon (favicon) for its application, such as `/idp/startSSO.ping`, and protocol endpoints, such as `/idp/SSO.saml2`.

### Steps

1. In the `<pf_install>/pingfederate/server/default/conf/template/assets/images` directory, replace the `favicon.ico` file.
2. Restart PingFederate.

For a clustered environment, repeat these steps on each node.

## Configuring the behavior of searching multiple datastores with one mapping

If a datastore uses results from previous queries as input, and if the previous queries return no result, PingFederate records a warning message in the server log and continues with the request by querying the next datastore in the attribute source setup.

### About this task

This default behavior applies to all lookup configurations using multiple datastores in one mapping. For more information, see [Attribute mapping with multiple data sources](#) on page 397.

If you prefer PingFederate to abort the request immediately, which is the default behavior of many earlier versions of PingFederate, you can override the behavior by modifying a configuration file. Like the default behavior, this override also applies to all lookup configurations using multiple datastores in one mapping.

## Steps

1. Edit the `org.sourceid.saml20.domain.AttributeMapping.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.



### Note:

If this file does not exist, you must create it.

2. To override the default behavior, change the value of the **AbortOnAttrLookupFailure** element from `false`, the default value, to `true`.

The following is an example of a modified

`org.sourceid.saml20.domain.AttributeMapping.xml` file.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item name="AbortOnAttrLookupFailure">true</c:item>
</c:config>
```



### Note:

Removing the `org.sourceid.saml20.domain.AttributeMapping.xml` file from the `<pf_install>/pingfederate/server/default/data/config-store` directory also has the same effect as setting the value of the **AbortOnAttrLookupFailure** element to `true`.

For a clustered environment, perform these steps on the console node, and then click **Replicate Configuration** on **System # Server # Cluster Management**.

## Example

Expected result when this override is set

If a datastore uses results from previous queries as input, and if the previous queries return no result, PingFederate records an error message in the server log, aborts the request immediately, and returns an error message to the user, the application, or the partner.

## System settings

---

The **System** menu provides access to system-related settings.

Depending on the setup of PingFederate, menu items vary. Menu items are organized into four groups:

- **Server**
- **Metadata**
- **Monitoring & Notifications**
- **External Systems**

### Server

You can configure various PingFederate settings.

On the **Extended Properties** window, you can configure protocol settings and local administrative accounts, import your license file, export or import a configuration archive, review other runtime servers in the same cluster and replicate configuration from the administrative server to the clustered runtime servers. You can also configure virtual host names, and configure extended properties for connections and OAuth clients. See the following topics for more information:

- [Administrative accounts](#) on page 914
- [License management](#) on page 919
- [Configuration archive](#) on page 922
- [Cluster management](#) on page 926
- [Virtual host names](#) on page 928
- [Extended properties](#) on page 929

### Protocol settings

On the **Protocol Settings** window, you can configure the base URL of your PingFederate environment, and settings for WS-Trust STS authentication, outbound provisioning, and IdP discovery.

#### Specifying federation information

Federation information identifies your federation deployment to your partners, according to the protocols you support.

#### About this task

You must provide an ID that uniquely identifies your federation gateway for each protocol you support. For WS-Trust security token service (STS), IDs are required for both SAML 2.0 and SAML 1.x, regardless of browser-based single sign-on (SSO) protocol support or the type of token expected to be issued, to ensure that the STS will perform correctly under all conditions.



#### Note:

Each ID normally applies across all connection partners for a given protocol. However, if your implementation requires different IDs for the same protocol, you can use virtual server IDs. For more information, see [Federation planning checklist](#) on page 113.

#### Steps

1. Go to **System # Server** to open the **Protocol Settings** window.
2. On the **Federation Info** tab, provide the required information.

For more information, see the following table.

| Field                           | Description  |
|---------------------------------|--|
| <b>Base URL</b>                 | The fully qualified host name, port, and path (if applicable) on which the PingFederate server runs. This field is used to populate configuration settings in metadata files. For more information, see <a href="#">Metadata export</a> on page 932.   |
| <b>SAML 2.0 Entity ID</b>       | This ID defines your organization as the entity operating the server for SAML 2.0 transactions. It is usually defined as an organization's URL or a DNS address, for example: <code>pingidentity.com</code> . The SAML SourceID used for artifact resolution is derived from this ID using SHA1. |
| <b>SAML 1.x Issuer/Audience</b> | This ID identifies your federation server for SAML 1.x transactions. As with SAML 2.0, it is usually defined as an organization's URL or a DNS address. The SourceID used for artifact resolution is derived from this ID using SHA1.  |
| <b>SAML 1.x Source ID</b>       | (Optional) If supplied, the Source ID value entered here is used for SAML 1.x, instead of being derived from the SAML 1.x Issuer/Audience.   |
| <b>WS-Federation Realm</b>      | The URI of the realm associated with the PingFederate server. A realm represents a single unit of security administration or trust.  |

3. Click **Next** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

### Configuring WS-Trust settings

You can configure PingFederate to require that client applications provide credentials to access the security token service (STS).

#### About this task

While this is an optional configuration, it is recommended for identity provider (IdP) configurations using the Username Token Processor. For other token processors and token generators, trust in the identity of the client is conveyed within the token itself and verified as part of processing. However, you can still configure authentication requirements to add another layer of security by limiting access to only authenticated clients.

 **Note:**

You can configure STS authentication to either apply globally to all token formats and for all IdP and service provider (SP) partner connections, or token-to-token mappings, using more fine-grained controls at the connection level through issuance criteria.

 **Note:**

WS-Trust STS settings can also be configured through the PingFederate Administrative API platform. For more information, see [Accessing the API interactive documentation](#).

#### Steps

1. Go to **System # Server** to open the **Protocol Settings** window
2. On the **WS-Trust STS Settings** tab, click **Configure WS-Trust STS Authentication**.  
Follow the configuration wizard to complete the task. For more information, see [Configuring STS authentication](#) on page 1042
3. Click **Next** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

### Configuring outbound provisioning settings

You can select the database that PingFederate should use internally to facilitate provisioning for service providers when PingFederate is configured as an identity provider (IdP).

#### Before you begin

Before configuring outbound provisioning settings, you must enable outbound provisioning through the `pf.provisioner.mode` property in the `<pf_install>/pingfederate/bin/run.properties` file. For more information, see [Configuring PingFederate properties](#) on page 820.

If you want to use failover provisioning, configure the `provisioner.node.id` and `provisioner.failover.grace.period` properties, which are also located in `<pf_install>/pingfederate/bin/run.properties`. These properties are described in [Deploying provisioning failover](#) on page 221.

#### About this task

The database stores the state of synchronization between the source datastore and the target datastore, enabling periodic checking to determine whether updates are required at the target site. PingFederate checks the source datastore for changes every minute by default. As needed, you can change the provisioning synchronization frequency on this tab as well.



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.



#### Note:

PingFederate is tested with Amazon Aurora (MySQL and PostgreSQL), Microsoft SQL Server, Oracle Database, Oracle MySQL, and PostgreSQL as internal provisioning datastores. A demonstration-only, embedded HSQLDB database is installed by default. Scripts to aid setup are in the directory `<pf_install>/pingfederate/server/default/conf/provisioner/sql-scripts`.

#### Steps

1. Go to **System # Server # Protocol Settings**.
2. On the **Outbound Provisioning** tab, from the **Provisioning Data Store** list, select a datastore.  
If the datastore you want is not shown in the list, PingFederate is not yet configured to access the store. Click **Manage Data Stores** to create a connection to the datastore.
3. Change the **Synchronization Frequency** value.  
The default value is 60 seconds.
4. Click **Next** and continue with the rest of the configuration.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

### Configuring standard IdP Discovery

SAML 2.0 identity provider (IdP) Discovery provides a cookie-based look-up mechanism to identify a user's IdP dynamically during a service provider (SP)-initiated single sign-on (SSO) event when the IdP is not otherwise specified.

#### About this task

This mechanism can be helpful in cases where an SP might be a hub for several IdPs in an identity federation.

In addition to supporting SAML 2.0 IdP Discovery, PingFederate provides a cross-protocol, proprietary mechanism allowing a PingFederate SP server to write a persistent browser cookie. The cookie contains



a reference to the IdP partner with whom the user previously authenticated for SSO. For more information, see [Configuring IdP discovery using a persistent cookie](#) on page 819.



**Tip:**

An SP can also include the discovery mechanism within the application. For instance, an SP can provide vanity URLs to isolate one set of end users from the others based on the URL of the requested resources. Another possible solution is to provide a user interface for the end users to enter information about their identity providers. With this approach, the application can start an SP-initiated SSO request with information about the IdP.

In the standard scenario, when a user requests access to a protected resource on the SP, common-domain browser cookies are used to determine where a user has authenticated in the past. Using this information, a PingFederate server can determine which IdP connection to use for sending an authentication request.

As an IdP Discovery provider, PingFederate can serve in up to three different roles: common domain server, common domain cookie writer, and common domain cookie reader. Each of these roles is necessary to support IdP Discovery. The roles can be distributed across multiple servers at different sites.

**Common domain server**

In this role the PingFederate server hosts a domain that its federation partners share in common. The common domain server allows partners to manipulate browser cookies that exist within that common domain. PingFederate can serve in this role exclusively or as part of either an IdP or an SP federation role, or both.

**Common domain cookie writer**

When PingFederate is acting in an IdP role and authenticates a user, it can write an entry in the common domain cookie, including its federation entity ID. An SP can look up this information on the common domain, not the same location as the common domain server described above.

**Common domain cookie reader**

When PingFederate is acting as an SP and needs to determine the IdPs with whom the user has authenticated in the past, it reads the common domain cookie. Based on the information contained in the cookie, PingFederate can then initiate an SSO authentication request using the correct IdP connection.

**Steps**

1. Go to the **Protocol Settings** window.
2. On the **IdP Discovery** tab, click **Configure IdP Discovery**.
3. On the **Domain Cookie Settings** tab, choose the discovery role or roles of your PingFederate server.
4. On the **Common Domain Service** tab, configure as follows.

| Field   | Description   |
|---|---|
| <b>Base URL of the PingFederate Common Domain Service</b> | Enter the base URL of the PingFederate common domain service.<br><br>A common domain service is where PingFederate reads or writes authentication information contained in shared cookies, as determined by whether your site is an SP or IdP, respectively. The service is shared if your PingFederate server is acting in both roles. You must use HTTPS for the common domain. |
| <b>Pass Phrase and Confirm Pass</b>                       | Enter and confirm the pass phrase that web applications must use to access the domain.  |

- On the **Local Common Domain Server** tab, configure the required settings.

A local common domain server is where PingFederate reads (as an SP) or writes (as an IdP) a common domain cookie (CDC) for IdP Discovery.

| Field                               | Description  |
|-------------------------------------|--|
| <b>Common Domain</b>                | Enter the common domain.<br><br>Your entry must include an initial period (.), as in the following example.<br><br><code>.example.com</code> |
| <b>Cookie Lifetime (Days)</b>       | Enter the lifetime of the CDC in days. The range is 1 to 1825 days. To indicate a non-persistent session cookie, enter -1.                   |
| <b>Pass Phrase and Confirm Pass</b> | Enter and confirm the pass phrase that web applications must use to access the domain.   |

- On the **Summary** tab, review and modify settings as needed. Then click **Save**.

Result:

The administrative console brings you back to the **IdP Discovery** tab.

- Click **Next** and continue with the rest of the configuration.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- Perform one of the following actions to enable the setting of the common domain cookie at runtime: Choose from:
  - Make sure that, prior to launching any SSO events, the web application that implements IdP Discovery sets the cookie using the `/idp/writetcdc.ping` application endpoint intended for that purpose.
  - Enable setting the cookie at runtime during SSO events by selecting the **IdP Discovery** check box on the **Connection Options** tab for the desired SP connection.

### Reviewing protocol settings

You can review your protocol settings before saving them.

#### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

### Administrative accounts


PingFederate supports five authentication schemes.

The authentication schemes are:

- Native authentication
- LDAP authentication
- RADIUS authentication
- Certificate-based authentication
- OIDC-based authentication

For role-based access control, PingFederate provides two account types and four administrative roles, as shown in the following table.

### PingFederate User Access Control

| Account type | Administrative role | Access privileges  |
|--------------|---------------------|--|
| Admin        | User Admin          | Create users, deactivate users, change or reset passwords, and install replacement license keys.   |
| Admin        | Admin               | Configure partner connections and most system settings, except the management of local accounts and the handling of local keys and certificates.   |
| Admin        | Expression Admin    | Map user attributes by using the expression language, Object-Graph Navigation Language (OGNL).   |
|              |                     |  <b>Important:</b><br>Only Administrative users who have both the Admin role and the Expression Admin role: <ul style="list-style-type: none"> <li>▪ Can be granted the User Admin role. This restriction prevents non-Expression Admin users from granting themselves the Expression Admin Role.</li> <li>▪ Can be granted write access to the file system or directory where PingFederate is installed. This restriction prevents a non-Expression Admin user from placing a <code>data.zip</code> file containing expressions into the <code>&lt;pf_install&gt;/pingfederate/server/default/deploy</code> directory, which would introduce expressions into PingFederate.</li> </ul> |
| Admin        | Crypto Admin        | Manage local keys and certificates.  |
| Auditor      | Not applicable      | View-only permissions for all administrative functions. When the <b>Auditor</b> role is assigned, no other administrative roles can be set.  |

For native authentication, access and authorization are controlled by the local accounts defined on the **Administrative Accounts** window.

As needed, you can switch from native authentication to an alternative console authentication. Access and authorization are defined in the respective configuration file.

An administrative user can sign on from more than one browser or location. Moreover, multiple administrative users can sign on to the PingFederate administrative console at a time. You can optionally restrict the administrative console to one administrative user at a time by modifying the `pf.console.login.mode` property in the `<pf_install>/pingfederate/bin/run.properties` file. Regardless of the property configuration, any number of auditors can sign on at any time.



#### Note:

For security, after three failed sign-on attempts from the same location within a short time period, the administrative console and the administrative API will temporarily lock out further attempts by the same user. The user must wait one minute to try again.

Local accounts defined on the **Administrative Accounts** window are shared between the administrative console and the administrative API if they are both configured to use native authentication, the default. If

the administrative console is configured to use an alternative console authentication, the **Administrative Accounts** window appears only if the administrative API is left to use native authentication, and vice versa.



**Tip:**

If you have connected PingFederate to PingOne for Enterprise, you can also single sign-on from the PingOne admin portal to the administrative console.

### Enabling native authentication for the administrative console

When the administrative console is protected by native authentication, access is restricted to the local accounts you have defined.

#### Steps

1. Go to **System # Server** to open the **Administrative Accounts** window.
2. In the `<pf_install>/pingfederate/bin/run.properties` file, change the value of the `pf.console.authentication` property to `pf.console.authentication=native`
3. Start or restart PingFederate.




### Managing local accounts and role assignments

You can create, modify, update, or deactivate accounts in the **Administrative Accounts** window.

#### Steps

1. Go to **System # Server # Administrative Accounts**, and then perform any of the following actions.

| Task                                 | Steps   |
|--------------------------------------|---|
| <p><b>Create a local account</b></p> | <ol style="list-style-type: none"> <li>a. On the <b>Administrative Accounts</b> window, click <b>Create User</b>.</li> <li>b. On the <b>User Information</b> tab, enter a username and other optional information. <div data-bbox="917 1157 1464 1360" style="border: 1px solid black; padding: 5px; margin: 5px 0;"> <p> <b>Note:</b></p> <p>If you want PingFederate to notify the user about password changes via email, you must supply an email address.</p> </div> </li> <li>c. On the <b>Password Generation</b> tab, enter a password or click <b>Generate one-time password</b> to generate a random password for the account. <div data-bbox="917 1507 1464 1711" style="border: 1px solid black; padding: 5px; margin: 5px 0;"> <p> <b>Note:</b></p> <p>Upon successful authentication, the user will be required to change the password of the account immediately.</p> </div> </li> <li>d. On the <b>Summary</b> tab, review your configuration, modify as needed, and then click <b>Done</b>.</li> <li>e. On the <b>Administrative Accounts</b> window, select the applicable account type, <b>Auditor</b></li> </ol> |

| Task  | Steps   |
|---|---|
|   | <p>or <b>Admin</b>, and one or more administrative roles for an <b>Admin</b> account.</p> <p>f. Repeat these steps to create additional accounts.</p>   |
| <p><b>Modify user information</b></p>         | <p>a. On the <b>Administrative Accounts</b> window, select the account by its username.</p> <div data-bbox="915 443 1466 590" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>Applicable only to active accounts.</p> </div> <p>b. On the <b>User Information</b> window, update the record, and then click <b>Done</b>.</p> <p>c. Repeat these steps to update other accounts.</p>   |
| <p><b>Update role assignments</b></p>         | <p>a. Select a different account type, <b>Auditor</b> or <b>Admin</b>, for one or more accounts.</p> <p>b. Select or clear the check boxes that correspond to the three administrative roles, <b>User Admin</b>, <b>Admin</b>, and <b>Crypto Admin</b> for one or more accounts.</p> <div data-bbox="915 968 1466 1115" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>Applicable only to the <b>Admin</b> accounts.</p> </div> |
| <p><b>Deactivate or reactive a native</b></p> | <p>a. Click <b>Deactivate</b> or <b>Activate</b> under <b>Action</b>.</p> <p>b. Repeat this step to deactivate or reactive other accounts.</p> <div data-bbox="915 1262 1466 1493" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>For traceability and accountability purposes, local accounts cannot be deleted Their records are retained and they can be reactivated if needed.</p> </div>                                  |

2. To keep your configuration, click **Save**.

### Enabling notification messages for account management events

Administrators can optionally enable notifications for account management events. If enabled, PingFederate generates notification messages based on the following events.

About this task

See the following table for a description of an event and the corresponding alert.

| Event   | Alert   |
|---|---|
| An administrator turns off the <b>Notify Administrator of Account Changes</b> option. | PingFederate generates a notification message to all administrators.<br>The message includes the username of the administrator who made the change.   |
| An administrator's email address is updated by another administrator.                 | PingFederate generates a notification message to the previous email address and another notification to the new email address.<br>The message includes the username of the administrator who made the change. |
| An administrator's password is changed.   | PingFederate generates a notification to the administrator whose password has been changed.<br>The message includes the username of the administrator who made the change.                                    |

**Note:**

Account management events are only applicable when native authentication is enabled for the administrative console, the administrative API, or both in the `<pf_install>/pingfederate/bin/run.properties` file. If you are using an alternative console authentication, notifications, if any, such as password changes, are handled by the third-party system.

**Steps**

1. Go to **System # Server** to open the **Administrative Accounts** window.
2. Select the **Notify Administrator of Account Change** check box.

An email address must be provided for the applicable accounts.

3. Select a notification publisher instance from the list.

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.

4. To keep your configuration, click **Save**.

**Setting or resetting passwords**

On the **Password Generation** tab, you can generate temporary passwords as you create local accounts for new users.

**About this task**

You can also assign temporary passwords for existing users who forget their passwords. Upon successful authentication, the users are required to change their passwords immediately.

**Steps**

1. Go to **System # Server # Administrative Accounts**.
2. To generate a random password for the account, on the **Password Generation** tab, enter a password or click **Generate one-time password**, and then click **Next**.

## Changing passwords

Administrative users and auditors can change the passwords of their local accounts at any time.

About this task



### Note:

If you sign on to PingFederate using your network ID and password, you can change your password only at the network level. The new password will apply to PingFederate automatically the next time you log on.

## Steps

1. Go to **System # Server** to open the **Administrative Accounts** window.
2. Click **Change Password** under **Action** for your account.
3. Enter your current password and new password twice in the related fields.



### Important:

If you are the sole user administrator, take steps to ensure that you do not forget your new password.

4. To keep your configuration, click **Save**.

## License management

PingFederate licensing is handled differently depending on whether you are installing and setting up PingFederate for the first time, or upgrading your existing PingFederate installation to a later version.

### Initial PingFederate installations

During the initial setup for a new PingFederate installation, you are prompted to upload a license file.

Depending on your licensing agreement, your license might have an expiration date. If your license key is going to expire, or has expired recently, you can import a new license file to replace the existing license key through the administrative console.

The administrative console displays a warning message ahead of the expiry of your license. Optionally, you can configure PingFederate to notify the administrators ahead of the license expiration date.

### PingFederate upgrades

If you choose to upgrade PingFederate using the Upgrade Utility, your current PingFederate license is automatically copied to the target installation if it is valid. If your current license is not valid, you must obtain a new license and specify its full path and filename when performing the upgrade.

If you choose not to use the Upgrade Utility, you must specify the full path and filename of a valid license when performing the upgrade.

## Reviewing license information

You can review a summary of your PingFederate license in the **License** window.

About this task



### Important:

If the license specifies an expiration date, the license expires at the beginning of that day.

## Steps

1. On the Help menu, click **About**.
2. In the dialog box, click **View / Update License**. The **License** window opens.



### Tip:

Another way to open the **License** window is to go to **System # Server # License**.

## Requesting a new license key

You can request a new license key if needed.

## Steps

1. Go to the Ping Identity licensing website.
2. Sign on, provide the required information, and then submit your request.

## Result

You will hear from our licensing team as the team processes your request.

## Installing a license key on a new or upgraded PingFederate server

You can install a license key on the PingFederate server from the administrative console.

## Steps

1. Start and sign on to the administrative console.
2. Go to **System # Server** to open the **License Management** window, and then click **Choose file** to select the license file. Click **Import**.

### Result:

If the license is for the wrong version of PingFederate or is found to be invalid for some other reason, PingFederate displays an error message.

When the license file is verified for use with your instance, the license information is saved in the `<pf_install>/pingfederate/server/default/conf/pingfederate.lic` file.

3. If you have a clustered PingFederate environment, go to **System # Server** to open the **Cluster Management** window, and then click **Replicate Configuration**.



### Note:

You must use the **Replicate Configuration** window to initiate the transmission of the license file from the console node to all engine nodes. As an added measure, the administrative console reminds you to do so as well.

When an engine node receives the license information from the console node, it saves the new license information to the `<pf_install>/pingfederate/server/default/conf/pingfederate.lic` license file.

For any engine node that was offline at the time of the import, when it restarts and joins the cluster, it consumes the new license information from the console node and applies the same processing logic.



### Note:

no longer maintains its license information in the `<pf_install>/pingfederate/server/default/data/.pingfederate.lic` file, which is referred to as the secondary license file in the previous versions of . The `.pingfederate.lic` file, if any, is ignored.



### Installing a replacement license key

You can replace your existing PingFederate license key by importing a new license file using the PingFederate administrated console.

#### Steps

1. Start and sign on to the administrative console.
2. Go to **System # Server # License**.
3. In the **License** window, click **Choose File**, select the license file, and click **Import**.

#### Result:

If the license is for the wrong version of PingFederate or is found to be invalid for some other reason, PingFederate displays an error message and keeps the existing license regardless of whether the existing license has expired.

If the new license does not include support for features found in your existing license, or if there is some other potential problem with the license, PingFederate advises and prompts you on whether to continue.

When the license file is verified for use with your instance, the license information is saved in the `<pf_install>/pingfederate/server/default/conf/pingfederate.lic` file.

The previous license file is renamed with a timestamp in the same `conf` directory.

4. If you have a clustered PingFederate environment, go to **System # Server # Cluster Management** and click **Replicate Configuration**.



#### Note:

You must use the **Replicate Configuration** window to initiate the transmission of the license file from the console node to all engine nodes.

When an engine node receives license information from the console node, if the issue date of the new license is not as recent as that of the existing license, the engine node ignores the new license from the console and logs the following warning message in the server log.

```
License from Console node ignored as Engine node has recently obtained
license.
```



#### Tip:

If you prefer to use the license from the console node, even the existing license on the engine node is more recent in terms of the issue date, manually remove or rename the `<pf_install>/`

`pingfederate/server/default/conf/pingfederate.lic` license file on the engine node, then click **Replicate Configuration** on the **Cluster Management** window again.

If the issue date of the new license is more recent than or equal to that of the existing license, the engine node saves the new license information to the `<pf_install>/pingfederate/server/default/conf/pingfederate.lic` license file and activates it immediately. No restart is required.

For any engine node that was offline at the time of the import, when it restarts and joins the cluster, it consumes the new license information from the console node and applies the same processing logic.



**Note:**

PingFederate no longer maintains its license information in the `<pf_install>/pingfederate/server/default/data/.pingfederate.lic` file, which is referred to as the secondary license file in the previous versions of PingFederate. The `.pingfederate.lic` file, if any, is ignored.

### Configuring notification for licensing events

If your PingFederate license has an expiration date, you can configure PingFederate to notify the administrators ahead of the license expiration date to minimize potential service disruptions.

About this task

Steps

1. Go to **System # Monitoring & Notifications** to open the **Runtime Notifications** window.
2. Select the **Notification for Servers Licensing Events** check box.



**Note:**

This check box appears only if your PingFederate license has an expiration date.

3. Enter the email address of the intended recipient.
4. Select a notification publisher instance from the list.

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.

5. To keep your configuration, click **Save**.

### Configuration archive

You can use configuration archives as backup files for the current PingFederate installation.



**Note:**

In addition to backup, you can use configuration archives for disaster recovery purposes.

- If the console server is still functional, you can import a recent configuration archive to solve the problem.
- In a clustered PingFederate

Using a configuration archive is not necessary in a clustered environment where the console server is still functional and some of the engine nodes are gone. In this case, create new engine nodes and then replicate the configuration from the console node. environment, if the console server and the engine nodes are all gone, you can import a recent configuration archive to a new console server and then replicate the configuration to new engine nodes. All other configurations that occurred outside of the archive will have to be redone manually.

PingFederate automatically creates a time-stamped configuration (.zip) archive every time an administrator signs on to the administrative console and before an existing archive is imported. The archives are stored in the `<pf_install>/pingfederate/server/default/data/archive` directory.

The automatic backup process typically completes without delays. For deployments with hundreds of connections or OAuth clients, or both, administrators can configure PingFederate to create configuration archives periodically instead.

Additionally, administrators can export the current configuration to a .zip file in the **Configuration Archive** window. This window is only available to administrators whose accounts have been assigned the User Admin, Admin, Crypto Admin, and Expression Admin roles.



**Note:**

The Expression Admin role must be assigned to give administrators sufficient permissions to create configuration archives.



**Warning:**

The backup file contains your complete configuration. To protect your data, confirm the backup file is protected with appropriate security controls in place before exporting it.

Sharing the archive is a security risk because the private keys are stored in the archive. An archive should only be shared if the security of that instance is not important, such as a development or test environment.

On the **Configuration Archive** window, administrators can import an existing archive for immediate deployment into a running PingFederate server.

Administrators can also deploy a configuration archive manually by copying the .zip file to the `environment,<pf_install>/pingfederate/server/default/data/drop-in-deployer` directory. After copying the .zip file, it must be renamed to `data.zip`.



**Attention:**

If you use the drop-in deployment process:

- PingFederate will not let you import the configuration archive of an older or newer version, and to ensure successful importation of the configuration archive file with this process, you must rename the file `data.zip`.
- On startup, the heartbeat endpoint will not return 200 until the archive import completes. If you have configured a health check or probe that can trigger a restart of the server, crash loop behavior can result. Review the configuration of these checks to ensure time thresholds are set appropriately.

Configuration archives are intended for administrative-console configuration only. The following files are not included in the archives:

- Launch scripts in the `<pf_install>/pingfederate/bin` and `<pf_install>/pingfederate/sbin` directories.
- Web container configuration files in the `<pf_install>/pingfederate/etc` directory.
- Log files in the `<pf_install>/pingfederate/log` directory.
- Database drivers and program files from adapters and any other plugins in the `<pf_install>/pingfederate/server/default/lib` and `<pf_install>/pingfederate/server/default/deploy` directories.
- Other files, including the license file, the advanced cluster configuration files, and the user-facing email and HTML templates, in the `<pf_install>/pingfederate/server/default/conf` directory.

If any changes have been made to files that are not part of the configuration archive, those files must be preserved manually.



**Tip:**

You can export a configuration archive, extract the .zip file, and determine whether specific files are part of the configuration archive, or not.



**Important:**

Draft connections in archives are not imported. Complete any unfinished partner connections if you want to include them in a full backup archive or in an archive to be used for configuration migration.

### Configuring a backup schedule

For deployments with hundreds of connections or OAuth clients, or both, administrators can configure PingFederate to create configuration archives periodically.

#### Steps

Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.saml20.domain.mgmt.impl.DataArchiveBackup.xml` file. See the following table for each property.

| Property                            | Description  |
|-------------------------------------|--|
| <b>ScheduledBackupEnabled</b>       | When set to <code>true</code> , PingFederate creates a configuration archive daily if configuration has changed since the creation of the last archive. This is true regardless of the backup method used.<br><br>The default value is <code>false</code> .  |
| <b>BackupTime</b>                   | The local time at which PingFederate creates a configuration archive when the <b>ScheduledBackupEnabled</b> property is set to <code>true</code> .<br><br>Ignored when the <b>ScheduledBackupEnabled</b> is set to <code>false</code> .<br><br>The default value is <code>00:00:00</code> , which represents midnight.   |
| <b>NumTriesWithIntegrityFailure</b> | Upon the creation of the scheduled configuration archive, if PingFederate detects a configuration change during the scheduled backup process, it retries immediately. The <b>NumTriesWithIntegrityFailure</b> property indicates the maximum number of attempts.<br><br>Ignored when the <b>ScheduledBackupEnabled</b> is set to <code>false</code> .<br><br>The default value is 3. |
| <b>BackupOnAdminLogin</b>           | When set to <code>false</code> , PingFederate does not create a configuration archive when an administrator signs on. Regardless of the value of this property,  |

| Property                  | Description  |
|---------------------------|--|
|                           | PingFederate always creates a configuration archive before an archive is imported.<br>The default value is <code>true</code> .                               |
| <b>MaxOldArchiveFiles</b> | The number of older configuration archives that PingFederate keeps. When the limit is reached, the oldest file is removed.<br>The default value is 25 files. |

The **ScheduledBackupEnabled** and **BackupOnAdminLogin** properties are not mutually exclusive. For example, if your deployment has 50 connections, you can enable both automatic and scheduled backup processes.



**Note:**

If you have a clustered PingFederate environment, edit the `org.sourceid.saml20.domain.mgmt.impl.DataArchiveBackup.xml` file on the console node.

### Exporting an archive

On the **Configuration Archive** window, you can export the current administrative-console configuration to a `.zip` file. This window is only available to administrators whose accounts have been assigned the User Admin, Admin, Expression Admin, and Crypto Admin roles.

#### Steps

- On the **Export** tab, click **Export**, then save the `.zip` file.



**Warning:**

The backup file contains your complete configuration. To protect your data, confirm the backup file is protected with appropriate security controls in place before exporting it.

Sharing the archive is a security risk because the private keys are stored in the archive. An archive should only be shared if the security of that instance is not important, such as a development or test environment.

### Importing and deploying administrative console configuration data

On the **Configuration Archive** window, you can import and deploy administrative-console configuration data from a `.zip` file.

#### About this task

When you import and deploy configuration data using the **Import** tab, PingFederate displays error messages if there are any missing plugin components, such as adapters, database drivers, or token translators, on which the archive depends, or any mismatches of PingFederate licensing authorization. You can choose to force the deployment and then install the missing components later.



**Note:**

Installation of any missing database drivers or other third-party libraries will require a restart of PingFederate.

**CAUTION:**

Deploying a configuration archive, either manually or by using the administrative console, always overwrites all existing configuration data.

To import and deploy administrative-console configuration data from an archive:

## Steps

1. On the **Configuration Archive** window's **Import** tab, choose the desired configuration archive from your system.
2. Optional: If you want PingFederate to deploy the archive regardless of whether dependency errors are detected, select the **Force Import** check box.

**Important:**

If you enable this feature, consult the server start-up console or the server log for any messages concerning missing plugin components or other errors.

3. Optional: To re-encrypt imported configuration data, select the **Re-encrypt Data** check box. PingFederate will re-encrypt sensitive imported information, such as datastore passwords and adapter shared secrets, with the primary *configuration encryption key*. This is most useful when you don't want to share configuration encryption keys between the two environments.

**Important:**


If you re-encrypt an archive, you might lose access to external OAuth clients and runtime state, such as grants or sessions, that were encrypted with keys from the archive. PingFederate will not import configuration encryption keys in the data archive. Also, it will not re-encrypt data stored externally, such as OAuth clients, persistent grants, or persistent sessions in an external datastore.

4. Click **Import**.

**Cluster management**

When multiple PingFederate servers are running as a cluster, the administrative console provides a **Cluster Management** window that you can use to ensure the all the nodes have the same configuration and license.

When you change the configuration of PingFederate on the administrative console, a notification banner appears at the top of the console, reminding you to go to the **Cluster Management** window and *replicate the configuration* of the administrative console node to all engine nodes in the cluster. The replication procedure generates new replication data that the engine nodes use to replicate from the administrative node's configuration. Another notification banner appears when a cluster node is out-of-date or has



Each node periodically reaches out to a random node in the cluster to see if newer replication data is available. If a node finds newer data, it attempts to retrieve and apply it. By default, the nodes poll another node every 60 seconds. You can change the replication poll interval by editing the value of the `replication.poll.interval` property in the `<pf_install>/pingfederate/server/default/conf/cluster-config-replication.conf` file.

The **Cluster Management** window also shows the version of each node.

## Replicating configurations

Use the **Cluster Management** window to replicate the configuration and license settings from the PingFederate administrative console node to the cluster's engine nodes.

### About this task

The replication process takes only a moment. The engine nodes continue to process requests coming while they load updated replication data into memory. When the reload is complete, the updated configuration is activated for new requests.

### Steps

1. Go to **System # Server # Cluster Management**.

## Cluster Management

From here you can replicate the configuration and license settings from the console to all server nodes in the cluster.

| ADDRESS            | INDEX | VERSION  | CONFIGURATION TIMESTAMP      | LAST REPLICATION STATUS | NODE TAGS | NODE   |
|--------------------|-------|----------|------------------------------|-------------------------|-----------|--------|
| 10.101.51.131:7600 | 30101 | 11.1.0.0 | Thu Mar 31 17:07:44 PDT 2022 | Succeeded               | demoTag1  | North  |
| 10.101.51.132:7600 | 30102 | 11.1.0.0 | Thu Mar 31 17:07:44 PDT 2022 | Succeeded               | demoTag4  | Arctic |
| 10.101.51.133:7600 | 30103 | 11.1.0.0 | Thu Mar 31 17:07:44 PDT 2022 | Succeeded               | demoTag4  | Arctic |

Last Modified: Thu Mar 31 17:00:45 PDT 2022

Last Replicated: Thu Mar 31 17:07:44 PDT 2022



The configuration has not been replicated or it has changed since it was last replicated.

Replic

2. Click **Replicate**.

Result:

PingFederate generates new replication data, updates the **Last Replicated** timestamp, and notifies the engine nodes that a new configuration is available. Then each node retrieves and applies the replication data, quickly going through the following **Replication Status** states:

- Out-of-Date
- Retrieving
- Applying
- Succeeded

### Troubleshooting

If, after a few minutes, the **Replication Status** of any node is Failed, investigate if a network communication failure, improper file permissions at the node, or another problem is causing the replication failure.

## Virtual host names

You can optionally define a list of alternate domain names at which PingFederate receives application and protocol messages.

This is done in the **Virtual Host Names** window. When configured, PingFederate honors the originally requested host throughout all browser redirects and metadata retrieval if the requested host matches one of the virtual host names. This capability allows you to fully support any number of branded URLs regardless of configured use cases within a single PingFederate environment.

Furthermore, virtual host names allow more flexibility for validating protocol elements, such as the **Destination** and **Recipient** elements in SAML inbound messages and the **aud** claim in JSON web tokens (JWTs) received from OAuth clients for client authentication purpose.

### SAML inbound message

In certain contexts, the SAML specifications require that XML messages include a URL identifying the host name to which the sender directed the message. As the recipient of such messages, PingFederate validates that the value matches the location where the message is received, which is the **Base URL** value defined in the **Protocol Settings** window on the **Federation Info** tab.

When virtual host names are configured, PingFederate takes them into consideration as part of its message-security validation process, in addition to its base URL.

### OAuth client authentication using the private\_key\_jwt client authentication method

An OAuth client can authenticate with an authorization server by presenting a signed JWT. Per specification, the client must include the intended recipient as the **aud** claim value in its JWT. When acting as the authorization server, PingFederate verifies that the destination of the **aud** claim value matches either its base URL or the **Token Endpoint Base URL** value defined in the **Authorization Server Settings** window.

When virtual host names are configured, PingFederate uses them in its verification process as well.



### Note:

Virtual host names and virtual server IDs serve different purposes. The latter provides separate unique identifiers on a per-connection basis for a federation deployment, normally in the same domain. For more information, see [Multiple virtual server IDs](#) on page 115. Virtual host names and virtual server IDs are not mutually exclusive. Depending on your use cases and infrastructure, you can configure both virtual server IDs and virtual host names in your PingFederate environment.

### Multiple site certificates

When multiple domain names are involved, you can configure PingFederate with multiple site certificates so that PingFederate can serve a different site certificate based on the requested host. For more information, see [Manage SSL server certificates](#) on page 658.

## Configuring virtual host names

Use the PingFederate administrative console to configure and manage virtual host names.

### Steps

1. Go to **System # Server** to open the **Virtual Host Names** window.
2. Perform any of the following actions.

| Option                          | Action                                       |
|---------------------------------|--|
| <b>Add a new entry</b>          | Enter the desired value and click <b>Add</b> |
| <b>Modify an existing entry</b> | Click <b>Edit</b> or <b>Update</b>           |



| Option                   | Action              |
|--------------------------|---------------------|
| Remove an existing entry | Click <b>Delete</b> |
| Keep your changes        | Click <b>Save</b>   |
| Discard your changes     | Click <b>Cancel</b> |

### Extended properties

Add any number of extended properties to store additional information about connections, OAuth clients, or both.

You add these extended properties on the **Extended Properties** page as described in [Defining extended properties](#) on page 929. When adding an extended property, you can define it as a single-value property or a multivalued property. These extended properties become available to all connections and clients and, if defined, will be passed to all applicable velocity templates and as a request context parameter in the authentication API. As you create or update a connection or a client, you can populate values for any of them. For OAuth clients, if dynamic client registration is configured and enabled, developers can populate extended property values by including them in the client registrations.

### Authentication policies

You can leverage extended properties to drive authentication experience and requirements by configuring an instance of the Extended Property Authentication Selector for each property that matters, placing this selector instance in an authentication policy, and defining a policy path for each selector result value. At runtime, PingFederate routes browser-based single sign-on (SSO) requests, OAuth authorization requests, and OAuth grant management requests to the desired authentication sources based on the applicable policy.

For more information, see [Configuring the Extended Property Authentication Selector](#) on page 237.

### OAuth attributes fulfillment and issuance criteria

You can use extended properties as attribute sources when fulfilling persistent grants and token contracts. You can also define issuance criteria to verify extended property values.

### Defining extended properties

You can define extended properties using the PingFederate administrative console.

### Steps

1. Go to **System # Server # Extended Properties**.
2. Add the extended properties.
  - a. Enter the applicable property name under **Name**.

After being added and saved, the name cannot be modified, but you can delete the extended property completely.

- b. Optional: In the **Description** field, enter a description for the extended property.
- c. If the extended property should allow multiple values, select the **Multivalued** check box .

#### Note:

If you have initially added a single-valued extended property, you can make it a multivalued extended property by selecting the **Multivalued** check box later.

If you have initially added a multivalued extended property and you clear the **Multivalued** check box later, when you try to make changes to a connection or an OAuth client that has been

configured with multiple values for this extended property, the administrative console prompts you to reconfigure the connection or the client until only one value exists for this extended property.

- d. Click **Add**.
- e. Optional: Repeat these steps to define additional extended properties.

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

## Metadata

You can configure metadata settings, export metadata, or sign metadata XML files.

These menu items are located in the **Protocol Metadata** window.

### Metadata settings

Configure metadata settings using the Pingfederate administrative console.

In the **Metadata Settings** window, you can configure the contact information to be included in your SAML metadata, and the metadata signing policy for metadata provided by the `/pf/federation_metadata.ping` federation metadata endpoint. You can also configure the validity of manual metadata exports and metadata provided by the metadata endpoint, and the frequency of automatic reloading of SAML metadata from partners.

### Entering system information

Provide the contact information to be included in your SAML metadata.

#### Steps

1. Go to **System # Protocol Metadata**.
2. In the **Metadata Settings** window, on the **System Info** tab, enter the desired information.
3. Click **Next**.



#### Tip:

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

#### Result

PingFederate includes the contact information in the manual metadata exports and metadata provided by the `/pf/federation_metadata.ping` federation metadata endpoint.

### Configuring metadata signing

Configure metadata signing using the PingFederate administrative console.

#### About this task

PingFederate generates publicly available metadata for partners through the federation metadata endpoint, `/pf/federation_metadata.ping`. Although optional, signing the the metadata is recommended so that partners can verify the authenticity of the metadata.

#### Steps

1. Go to **System # Protocol Metadata**.

2. In the **Metadata Settings** window, on the **Metadata Signing** tab select a certificate from the **Signing Certificate** list.

If you have not yet created or imported your certificate into PingFederate, click **Manage Certificates** and use the **Certificate Management** configuration wizard to complete the task.

3. Optional: Select a signing algorithm from the list.

The default selection is **RSA SHA256** or **ECDSA SHA256** depending on the key algorithm of the chosen signing certificate. Make a different selection if you and your connection partner have agreed to use a stronger algorithm.

The public key of the metadata signing certificate is included as part of the metadata.

4. Click **Next**.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

### Configuring metadata lifetime

Configure the lifetime of metadata to optimize cache performance in your environment.

#### About this task

PingFederate provides metadata for SAML and WS-Federation connections and supports automatic update for SAML connections by reloading metadata URLs provided by the partners

#### Metadata publication

PingFederate includes expiration information in metadata. It indicates to partners whether they have reasonably up-to-date information about your server.

#### Metadata consumption

PingFederate supports automatic reloading of metadata by URL for SAML connections.

#### Steps

1. Go to **System # Protocol Metadata**.
2. In the **Metadata Settings** window, on the **Metadata Lifetime** tab, configure your metadata.

| Option  | Action   |
|---|--|
| <b>Adjust the validity of your metadata</b>                         | Modify the <b>Cache Duration</b> field value, in minutes.<br>The default value is 1440 or 1 day. |
| <b>Adjust the frequency of automatic reloading of SAML metadata</b> | Modify the <b>Reload Delay</b> field value, in minutes.<br>The default value is 1440 or 1 day.   |

3. Click **Next**.



**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers you the opportunity to do so.

## Reviewing metadata settings

Review your metadata settings before completing configuration.

### Steps

- To amend your configuration, click the corresponding tab title and then follow the steps to complete the task.
- To keep your changes, click **Save**.
- To discard your changes, click **Cancel**.

## Metadata export

Use the Pingfederate administrative console to export metadata.

The SAML standards define a metadata exchange schema for conveying XML-formatted information between two SAML entities. Metadata includes endpoint URLs, binding types, attributes, and security-policy information, which helps federation partners expedite their configurations.

In the **Metadata Export** window, you can export metadata to an XML file by selecting any SAML browser single sign-on (SSO) connection or specifying the desired information manually. The former is also available as a per-connection action item on the **Connections** window. The latter addresses the scenarios where you have not yet created a SAML connection, or you want to generate one SAML metadata XML file for multiple partners.

To export a SAML metadata file, select the role your PingFederate server plays, configure the export options and metadata signing policy, and then save the SAML metadata to an XML file.

For more information on exporting metadata for any SAML Browser SSO connection to an XML file, see [Exporting connection-specific SAML metadata](#) on page 932.

For more information on manually selecting specific information and exporting a metadata XML file, see [Exporting selected SAML metadata](#) on page 933.

### Exporting connection-specific SAML metadata

You can export metadata for any SAML browser single sign-on (SSO) connection to an XML file.

### About this task

This is useful in a situation where you have already created a SAML browser SSO connection to your partner and the partner prefers consuming SAML metadata by file.

### Steps

1. Go to **System # Protocol Metadata # Metadata Export**.
2. On the **Metadata Role** tab, select the applicable role, and click **Next**.
3. On the **Metadata Mode** tab, select the **Use a connection for metadata generation** option.

If the secondary HTTPS port is configured and you want to use it for the SOAP channel, select the **Use the secondary port for SOAP channel** check box.



#### Note:

If certificate-based authentication is configured for the SOAP channel, you must configure the `pf.secondary.https.port` property in the `<pf_install>/pingfederate/bin/run.properties` file and select this check box.

4. On the **Connection Metadata** tab, select the applicable SAML browser SSO connection from the list. Choose from:
  - **Virtual Server ID**

If the selected connection contains two or more virtual server IDs, you must select the virtual server ID that you want to use during the export. The protocol endpoints in the metadata file are specific to the selected virtual server ID. If you decide to update the virtual server ID at a later time, re-export the connection metadata for your partners
  - **Virtual Host Name**

If PingFederate is configured with one or more virtual server host names, you can select the applicable virtual host name from the list. If a selection is made, PingFederate uses that virtual host name when generating the metadata file. If left blank, PingFederate uses its base URL in the metadata file. If you decide to update one or more virtual host names at a later time, re-export the connection metadata for your partners.
5. Optional: On the **Metadata Signing** tab, select a certificate to use for signing the metadata XML file.
  - a. Select a certificate from the **Signing Certificate** list.
 

If you have not yet created or imported your certificate into , click **Manage Certificates** and use the **Certificate Management** configuration wizard to complete the task.
  - b. Optional: Select the related check boxes to include the public key information and the raw key in the signed XML file.
  - c. Select a signing algorithm from the list.
 

The default selection is **RSA SHA256** or **ECDSA SHA256**, depending on the key algorithm of the chosen signing certificate. Make a different selection if you and your connection partner have agreed to use a stronger algorithm.
6. On the **Export & Summary** tab, click **Export** to save the metadata XML file, then click **Done**.
7. Pass the metadata XML file to your partner.

### Exporting selected SAML metadata

You can manually select the desired information and export a metadata XML file.

#### About this task

This type of export is useful for the following situations:

- You have not yet created a SAML browser single sign-on (SSO) connection to the partner but would like to help your partner with its configuration by including selected information in a metadata XML file.
- You want to export a SAML metadata with selected information, which can be passed to multiple partners to expedite their configurations.

#### Steps

1. Go to **System # Protocol Metadata # Metadata Export**.
2. On the **Metadata Role** tab, select the applicable role.
3. On the **Metadata Mode** tab, select the **Select information to include in metadata manually** option.

If the secondary HTTPS port is configured and you want to use it for the SOAP channel, select the **Use the secondary port for SOAP channel** check box.



#### Note:

If certificate-based authentication is configured for the SOAP channel, you must configure the **pf.secondary.https.port** property in the `<pf_install>/pingfederate/bin/run.properties` file and select this check box.

4. On the **Protocol** tab, select the desired version of the SAML protocol from the list.
5. On the **Virtual Host Name** tab, select the applicable virtual host name from the list.

This tab is shown and applicable only if PingFederate is configured with one or more virtual server host names.

If a selection is made, PingFederate use that virtual host name when generating the metadata file. If left blank, PingFederate uses its base URL in the metadata file. If you decide to update one or more virtual host names at a later time, re-export the connection metadata for your partners.

6. Optional: On the **Attribute Contract** tab, you can perform the following actions.

| Action        | Description   |
|---------------|---|
| <b>Add</b>    | Add an attribute contract by entering the contract's name and clicking <b>Add</b> .   |
| <b>Edit</b>   | Modify an existing attribute contract by clicking <b>Edit</b> . To save your change, click <b>Update</b> . To cancel your change, click <b>Cancel</b> . |
| <b>Delete</b> | Delete an existing attribute contract by clicking <b>Delete</b> .   |

7. On the **Signing Key** tab, do the following:

- a. Optional: If you want to include a public key that this system uses for digital signatures, select a key from the **Digital Signature Keys/Certs** list.

If you have not yet created or imported a digital signature key to PingFederate, click **Manage Certificates** and use the **Digital Signature Settings** wizard to complete the task.

- b. Optional: If you want to give partners an alternative key, select another key from the **Secondary Digital Signature Keys/Certs** list.

 **Note:**

You can't configure a secondary signing certificate if the primary certificate has certificate rotation enabled. You also can't use a certificate that has rotation enabled as the secondary signing certificate.

8. Optional: On the **Metadata Signing** tab, select a certificate to use for signing the metadata XML file.
  - a. Select a certificate from the **Signing Certificate** list.

If you have not yet created or imported your certificate into , click **Manage Certificates** and use the **Certificate Management** configuration wizard to complete the task.

- b. Optional: Select the related check boxes to include the public key information and the raw key in the signed XML file.
- c. Select a signing algorithm from the list.

The default selection is **RSA SHA256** or **ECDSA SHA256**, depending on the key algorithm of the chosen signing certificate. Make a different selection if you and your connection partner have agreed to use a stronger algorithm.

9. Optional: On the **XML Encryption Certificate** tab, select the certificate that your partner can use to encrypt XML content.

Applicable only when you have selected **SAML 2.0** on the **Protocol** tab.

If you have not created or imported your certificate into PingFederate, click **Manage Certificates** and use the **Certificate Management** configuration wizard to complete the task.

10. On the **Export & Summary** tab, click **Export** to save the metadata XML file, then click **Done**.
11. Pass the metadata XML file to your partner or partners.

## File signing

Applying a digital signature to an XML file assures the authenticity and integrity of the original source.

If you have previously exported an unsigned metadata XML file, you can create a new signed metadata XML file based on the unsigned metadata in the **File Signing** window.

## Signing XML files

Use the PingFederate administrative console to sign XML files.

### Steps

1. Go to **System # Protocol Metadata # File Signing**.
2. On the **Select Metadata File** tab, choose your metadata file.
3. On the **Digital Signature Settings** tab, select a signing certificate from the list.

If you have not yet created or imported your certificate into PingFederate, click **Manage Certificates** and use the **Certificate Management** configuration wizard to complete the task.

- a. Clear the related check boxes to exclude the public key information and the raw key from the signed XML file.
- b. Select a signing algorithm from the list.

The default selection is **RSA SHA256** or **ECDSA SHA256**, depending on the key algorithm of the chosen signing certificate. Make a different selection if you and your connection partner have agreed to use a stronger algorithm.

4. On the **Export & Summary** tab, click **Export** to save the digitally signed file.
5. Click **Done**.

## Monitoring and notifications

You can set up notifications for licensing events, certificate events, and SAML metadata update events. These menu items are located in **System # Monitoring & Notifications**.

### Runtime notifications

You can configure PingFederate to generate notification messages for various events.

Complete this configuration on the **Runtime Notifications** window.

#### Licensing events

Depending on your licensing agreement, your PingFederate license might have an expiration date. You can configure PingFederate to generate notification messages when your license is about to expire. This option does not appear when you have a perpetual license.

#### Certificate events

When enabled, PingFederate can generate notification messages when a certificate is about to expire or has expired. If you have also configured PingFederate to rotate self-signed certificates, PingFederate can generate notification messages after generating a certificate and after its activation.

#### SAML metadata update events

If you have enabled automatic reloading of partner metadata in any SAML browser single sign-on (SSO) connections, you can configure PingFederate to generate notification messages when it detects changes after pulling the metadata from the partners.



### Note:

In a clustered PingFederate environment, notification messages for licensing and certificate events are generated by only one of the nodes. If that node leaves the cluster, planned or not, another node picks up this task automatically.

Regardless of runtime notification settings, PingFederate always records license expiration events, certificate events, and SAML metadata update events in the server log. For more information, see [PingFederate log files](#) on page 828.

### Configuring runtime notifications

Use the PingFederate administrative console to configure and manage runtime notifications.

#### Steps

1. Go to **System # Monitoring & Notifications # Runtime Notifications**.
2. Optional: Configure licensing events.
  - a. Select the **Notification for Servers Licensing Events** check box.

 **Note:**

This check box appears only if your PingFederate license has an expiration date.

- b. Enter the email address of the intended recipient.
  - c. Select a notification publisher instance from the list.
 

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.
3. Optional: Configure certificate events.
  - a. Select the **Notification for Certificate Events** check box.
  - b. Enter the email address of the intended recipient.
  - c. Optional: Enter the initial warning time period (in days) in the **Initial Warning Event** field.
  - d. Optional: Enter the final warning time period (in days) in the **Final Warning Event** field.
  - e. Select a notification publisher instance from the list.
 

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.
4. Optional: Configure SAML metadata update events.
  - a. Select the **Notification for SAML Metadata Update Events** check box.
  - b. Enter the email address of the intended recipient.
  - c. Select a notification publisher instance from the list.
 

If you have not yet configured the desired notification publisher instance, click **Manage Notification Publishers**.

### Datstores

Datstores represent external systems where user attributes and other data are stored. Once defined, you can configure PingFederate to retrieve user attributes from datstores for contract fulfillment and token authorization in various use cases.

To manage datstores, go to **System # Data & Credential Stores # Data Stores**.

- To create a new datastore, click **Add New Data Store** and then follow the configuration wizard to complete the task.
- To modify an existing datastore, select the datastore and then follow the configuration wizard to complete the task.
- To review usage of an existing datastore, click **Check Usage** under **Action**.



- To remove an existing datastore or cancel the removal request, click **Delete** or **Undelete** under **Action**.

**Note:**

You can only remove datastores that are not currently in use.

- To fine-tune the caching interval for datastore validation, update the **Data-Store Validation Interval** field value to the desired amount of time in seconds.

**Note:**

As you configure various components on the administrative console, PingFederate performs connectivity tests against the applicable datastores. By default, PingFederate stores successful test results for five minutes. This design improves the performance of the administrative console by reducing the number of calls it makes to the target servers and the amount of time it takes to move from one configuration window to another.

**Note:**

The default value is 300 seconds (five minutes). A value of 0 turns off the caching and validation tests are executed with each access. This setting applies to all datastores.

### Adding a new datastore

On the **Data Stores** window, you can create and configure a new datastore.

#### Steps

1. Go to **System # Data & Credential Stores # Data Stores**.
2. Click **Add New Data Store**.
3. Enter a name for the datastore.
4. From the **Type** list, select the type of datastore.  
Available types are limited to the ones currently installed on your server.
5. Optional: To mask attribute values returned from this datastore in PingFederate logs, select the **Mask Values in Log** check box.
6. Click **Next**.

### Configuring a PingOne LDAP Gateway datastore

The PingOne LDAP Gateway reduces the complexity of moving to the cloud while maintaining connectivity to on-premise end-user data.

#### Before you begin

Make sure you have the following in place:

- A PingOne environment configured with an LDAP gateway. See [Gateways](#) and [Adding a Gateway](#).
- A connection between PingFederate and PingOne. See [Creating connections to PingOne](#) on page 998.

#### About this task

When PingFederate is deployed off-premise, as a PingOne Advanced Service or in your own cloud deployment, you can configure the PingOne LDAP Gateway datastore to enable PingFederate to access

an on-premise LDAP directory for HTML Form Adapter functionality, provisioning, customer identity access management (CIAM), and other areas.



**Note:**

Currently, you cannot use the PingOne LDAP Gateway for grant storage, persistent authentication sessions, and OAuth client records. All other LDAP datastore functionality works in the same way as the direct LDAP datastore.

Steps

1. Go to **System # Data & Credential Stores # Data Stores**.
2. In the **Data Stores** window, click **Add New Data Store**.
3. On the **Data Store Type** tab, enter a name for the datastore in the **Name** field.
4. In the **Type** list, select **PingOne LDAP Gateway**.
5. Optional: To mask attribute values returned from this datastore in PingFederate logs, select the **Mask Values in Log** check box.
6. Click **Next**.
7. In the **LDAP Gateway Configuration** window, configure your LDAP Gateway as follows.
  - a. In the **PingOne Environment** list, select your PingOne environment.
  - b. In the **PingOne LDAP Gateway** list, select your PingOne LDAP gateway.
8. Click **Test Connection** to determine whether the administrative node can communicate with the specified datastore.



**Note:**

Datastore validation is no longer enabled during configuration. This feature lets you configure datastores without requiring a successful connection between the administrative node and the datastore. You can also save the datastore even if the connection is not currently successful.

9. Click **Advanced** if you want to configure LDAP attributes to be handled as binary data.
10. Click **Next** to view the summary of your LDAP gateway datastore configuration.
11. Click **Save**.

**Configuring a JDBC connection**

You can establish a Java Database Connectivity (JDBC) connection to your database server.

About this task




**Note:**



was tested with vendor-specific JDBC drivers. For more information, see [Compatible database drivers](#) on page 124. To obtain the database driver .jar file, contact your database vendor. Install the database driver file to the `<pf_install>/pingfederate/server/default/lib` directory, and then restart the server.

Steps

1. Go to **System # Data & Credential Stores # Data Stores**.
2. On the **Data Stores** window, click **Add New Data Store**.
3. On the **Data Store Type** tab, type a name for the datastore.

4. From the **Type** list, select **Database (JDBC)**. Click **Next**.
5. Optional: To mask attribute values returned from this datastore in PingFederate logs, select the **Mask Values in Log** check box.
6. Click **Next**.
7. In the **Database Config** window, configure your JDBC connection. Information about each field is provided in the following table.

| Field                          | Description   |
|--------------------------------|---|
| <b>JDBC URL</b>                | <p>The location of the database server and the database. The structure of the JDBC URL varies depending on the vendor. You can add multiple JDBC URLs. You can also specify which node is the default by clicking <b>Set as Default</b> under <b>Action</b>.</p> <p>For regional deployments, specify region-specific URLs on different rows, along with the node tags for the region. Tag the nodes that will use the URL with the <code>node.tags</code> property in the <code>run.properties</code> file. Failover may be supported within a single region via driver-specific URL parameters. Failover is not supported across different rows.</p> <p> <b>Tip:</b></p> <p>For Oracle MySQL, to enable automatic reconnection attempts when the connection is not available at runtime, enter a SQL statement in the <b>Validate Connection SQL</b> field and add the following query string to the JDBC URL:</p> <pre>?autoReconnect=true</pre>                              |
| <b>Tags</b>                    | <p>Tags are defined in the <code>node.tags</code> property in the <code>&lt;pf_install&gt;/pingfederate/bin/run.properties</code> file. For a description of the <code>node.tags</code> property, see <a href="#">Deploying cluster servers</a> on page 208.</p> <p>In PingFederate deployments that are regional, you can enter one or more tags for a JDBC URL, which specifies with which datastore that particular PingFederate node should communicate. If none of the tags match what is defined for the <code>node.tags</code> property, the default node is used.</p> <p>The following rules apply to tags:</p> <ul style="list-style-type: none"> <li>▪ You must separate multiple tags specified for one node with spaces.</li> <li>▪ You can't use a tag more than once per datastore.</li> <li>▪ Tags are optional. If needed, you can configure a non-default node without tags. Doing this is useful if you are not yet ready to tag the node, or if you are still in the planning stage but want to enter the address for the node now.</li> </ul> |
| <b>Driver Class</b>            | The name of the driver class used to communicate with the source database. The driver class name should be supplied by the database software vendor in a JAR file.  |
| <b>Username</b>                | The name that identifies the user when connecting to the database.  |
| <b>Password</b>                | The password needed to access the database.   |
| <b>Validate Connection SQL</b> | A simple SQL statement used by the PingFederate runtime server to verify that the database connection is still active and to reconnect if needed.   |

| Field                               | Description   |
|-------------------------------------|---|
| <b>(Optional but recommended)</b>   | If a SQL statement is not provided here, PingFederate might not reconnect to the database if the connection is broken.  |
|                                     |  <b>Important:</b><br>Ensure that the SQL statement is valid for your database. For example: <ul style="list-style-type: none"> <li>▪ <code>SELECT 1 from dual</code> (for Oracle Database or Oracle MySQL)</li> <li>▪ <code>SELECT getdate()</code> (for Microsoft SQL Server)</li> <li>▪ <code>SELECT 1</code> (for PostgreSQL)</li> </ul> |
|                                     |  <b>Tip:</b><br>To use this feature for Oracle MySQL, you must also add the ?<br><code>autoReconnect=true</code> query parameter to the JDBC URL.  |
| <b>Mask Values in Log</b>           | Determines whether all attribute values returned through this datastore should be masked in PingFederate logs.<br><br>Applicable only when editing an existing datastore.   |
| <b>Allow Multi-Value Attributes</b> | When selected, indicates that the JDBC datastore can select more than one record from a column and return the results as a multivalued attribute. Otherwise, a query returns only the first value in the column.  |

8. Click **Test Connection** to determine whether the administrative node can communicate with the specified datastore.

 **Note:**

Datastore validation is no longer enabled during configuration. This feature lets you configure datastores without requiring a successful connection between the administrative node and the datastore. You can also save the datastore even if the connection is not currently successful.



9. Click **Advanced** to configure additional settings.
  - a. On the **Advanced Database Options** window, click **Apply Defaults** to view or restore default values.

 **Tip:**

The default values are conservative based on the server thread pool settings configured in the `<pf_install>/pingfederate/etc/jetty-runtime.xml` file. If any changes are made to thread pooling, we recommend updating settings as outlined in the next step.

- b. Configure advanced settings.

For more information about each field, see the following table.

| Field                 | Description  |
|-----------------------|--|
| Minimum Pool Size     | <p>The smallest number of database connections that can remain in the pool for the given datastore. A minimum value of 0 means that the minimum number of connections in the pool is zero.</p> <div data-bbox="613 751 735 793" data-label="Section-Header"> <p> <b>Note:</b></p> </div> <p>For optimal performance, the value for this setting should equal 50% of the <b>maxThreads</b> value in the Jetty server configuration (see <a href="#">Configuring connection pools to datastores</a> on page 1084).</p> <p>Note that PingFederate does not establish the connection pool for the given datastore until it receives a request that requires one or more attributes from that datastore.</p> <p>The default value (after clicking on <b>Apply Defaults</b>) is 10.</p> |
| Maximum Pool Size     | <p>The largest number of database connections that can remain in the pool for the given datastore.</p> <div data-bbox="613 1220 735 1262" data-label="Section-Header"> <p> <b>Note:</b></p> </div> <p>For optimal performance, the value for this setting should equal 75% to 100% of the <b>maxThreads</b> value in the Jetty server configuration (see <a href="#">Configuring connection pools to datastores</a> on page 1084).</p> <p>The default value (after clicking on <b>Apply Defaults</b>) is 100.</p>   |
| Blocking Timeout (ms) | <p>The amount of time a request waits to get a connection from the connection pool before it fails. A value of -1 means that a request waits indefinitely for the connection pool to return a connection.</p> <p>The default value (after clicking on <b>Apply Defaults</b>) is 5000.</p>  |
| Idle Timeout (min)    | <p>The length of time the connections can sit idle in the pool before it closes them. A value of -1 means that the connection pool does not close its connections (once established).</p> <p>Note that PingFederate maintains the minimum connection pool for the given datastore once the pool is established.</p> <p>The default value (after clicking on <b>Apply Defaults</b>) is 5.</p>   |


10. Click **Save** to save your configuration.




## Configuring an LDAP connection




In the **Data Stores** configuration window, establish an LDAP connection to your directory server.

### Steps


1. Go to **System # Data & Credential Stores # Data Stores**.
2. On the **Data Stores** window, click **Add New Data Store**.
3. On the **Data Store Type** tab, type a name for the datastore.
4. From the **Type** list, select **Directory (LDAP)**.
5. Optional: To mask attribute values returned from this datastore in PingFederate logs, select the **Mask Values in Log** check box.
6. Click **Next**.
7. On the **LDAP Configuration** tab, configure your LDAP connection as described in the following table.

| Field                            | Description  |
|----------------------------------|--|
| <b>Data Store Name</b>           | The name of the datastore.<br><br>Applicable only when editing an existing datastore.  |
| <b>Hostname(s)</b><br>(Required) | The network address of the directory server, either an IP address, a host name, or a fully qualified domain name. The entry might include a port number; for example, <code>10.10.10.101:1389</code> . For failover, enter multiple directory servers, each separated by a space. In addition to network error conditions, PingFederate also fails over to the next server if the current server returns an LDAP system error.<br><br><div data-bbox="565 982 1474 1192" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If multiple directory servers are specified, each server must be accessible by using the same user distinguished name (DN) and password (unless the <b>Bind Anonymously</b> check box is selected).</p> </div> <p>You can add multiple hostnames. You can also specify which node is the default by clicking <b>Set as Default</b> under <b>Action</b>.</p> <p>PingFederate can also leverage DNS service records to locate the directory server (when the <b>Use DNS SRV Record</b> check box is selected), in which case the value of this field must be a single domain; for example, <code>example.com</code>.</p> |

| Field                            | Description   |
|----------------------------------|---|
| <p><b>Tags</b></p>               | <p>Tags are defined in the <code>node.tags</code> property in the <code>&lt;pf_install&gt;/pingfederate/bin/run.properties</code> file. See <a href="#">Deploying cluster servers</a> on page 208 for a description of the <code>node.tags</code> property.</p> <p>In regional PingFederate deployments, you can enter one or more tags for a host name, which specify with which datastore that particular PingFederate node should communicate. If none of the tags match what is defined for the <code>node.tags</code> property, the default node is used.</p> <p>The following rules apply to tags:</p> <ul style="list-style-type: none"> <li>▪ You must separate multiple tags specified for one node with spaces.</li> <li>▪ You cannot use a tag more than once per datastore.</li> <li>▪ Tags are optional. If needed, you can configure a non-default node without tags. This is useful if you are not yet ready to tag the node, or if you are still in the planning stage but want to enter the address for the node now.</li> </ul>                                     |
| <p><b>Use LDAPS</b></p>          | <p>When selected, PingFederate connects to the directory server using LDAPS. This selection applies equally to all servers specified in the <b>Hostname(s)</b> field.</p> <div data-bbox="560 840 1466 987" style="border: 1px solid black; padding: 5px; margin-bottom: 10px;"> <p> <b>Important:</b></p> <p>We recommend securing all LDAP connections by using LDAPS.</p> </div> <div data-bbox="560 997 1466 1270" style="border: 1px solid black; padding: 5px; margin-bottom: 10px;"> <p> <b>Note:</b></p> <p>To enable the password changes, password reset, or account unlock features in the HTML Form Adapter against Microsoft Active Directory, you must secure the connection to your directory server using LDAPS; Microsoft Active Directory requires this level of security to allow password changes.</p> </div> <p>This check box is not selected by default.</p>                               |
| <p><b>Use DNS SRV Record</b></p> | <p>Used in conjunction with the domain information defined in the <b>Hostname(s)</b> field and the preference of LDAP or LDAPS, PingFederate uses DNS SRV records to locate the directory server when this check box is selected. You can fine-tune the TTL value and the record prefixes on the <b>Advanced LDAP Options</b> window.</p> <div data-bbox="560 1522 1466 1858" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>When the DNS returns multiple SRV records, PingFederate uses the record with the lowest-numbered priority value and fails over to the record with the next lowest priority value. If multiple records share the same priority value, PingFederate uses the records with the highest-numbered weight value.</p> <p>PingFederate repeats this exercise until it establishes a connection or fails to connect to any directory server after taking all records into consideration.</p> </div> <p>This check box is not selected by default.</p> |

| Field                          | Description  |
|--------------------------------|--|
| <b>Follow LDAP Referrals</b>   | <p>Select this check box to let the datastore follow LDAP referrals on Microsoft Active Directory or Oracle Unified Directory.</p> <div data-bbox="565 289 1469 457" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>PingFederate always follows LDAP referrals from PingDirectory based on the recommended PingDirectory configuration.</p> </div>   |
| <b>LDAP Type</b><br>(Required) | <p>If you are using this datastore for outbound provisioning and your directory server is PingDirectory, Microsoft Active Directory or Oracle Unified Directory, select the applicable type from the list, such that PingFederate can pre-populate many provisioning settings on <b>Outbound Provisioning # Channel # Source Settings</b>.</p> <div data-bbox="565 657 1469 863" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>If your directory server is not PingDirectory, Microsoft Active Directory, or Oracle Unified Directory, you can define a custom LDAP Type to streamline the outbound provisioning configuration.</p> </div> <p>The LDAP type is also used to enable password-change messaging between Microsoft Active Directory and PingFederate when an HTML Form Adapter instance is used.</p> |
| <b>Bind Anonymously</b>        | <p>Select this check box if your directory server supports anonymous binding and if no credentials are needed to access the directory server. When selected, user DN and password are not required.</p> <div data-bbox="565 1108 1469 1409" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>For inbound provisioning, because PingFederate needs to manage local user records, your directory server might require a specific service account to handle the communication between PingFederate and the target directory server. If you choose an anonymous binding, ensure that this access level provides permission to search the directory for user-account information.</p> </div> <p>This check box is not selected by default.</p>   |



| Field                     | Description  |
|---------------------------|--|
| <b>User DN</b>            | <p>The user name credential required to access the directory server.</p> <div style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>The service account must have permission to search the directory for user-account information. If your use cases involve reading from the directory server without creating, updating, or deleting any records, consider using a service account with read-only access.</p> <p>For inbound provisioning, a service account with permission to create, read, update, and delete users and groups is required.</p> <p>When connecting to a Microsoft Active Directory server, enter a Microsoft Active Directory user account. Do not use a computer account.</p> <p>When connecting to PingDirectory or Oracle Unified Directory, configure proxied authorization for the service account on the directory server if you intend to enable self-service password reset in any HTML Form Adapter instances that use this datastore. For more information, see <a href="#">Proxied authorization</a> on page 949.</p> </div> |
| <b>Password</b>           | The password credential required to access the directory server.   |
| <b>Mask Values in Log</b> | <p>Determines whether all attribute values returned through this datastore should be masked in PingFederate logs.</p> <p>Applicable only when editing an existing datastore.</p>   |

- Click **Test Connection** to determine whether the administrative node can communicate with the specified datastore.

 **Note:**

Datastore validation is no longer enabled during configuration. This feature lets you configure datastores without requiring a successful connection between the administrative node and the datastore. You can also save the datastore even if the connection is not currently successful.

- Optional: Click **Advanced**. If you choose an anonymous binding, configure additional settings in the **Advanced LDAP Options** window. Click **Save**.  
Result: You are directed back to the **LDAP Configuration** tab.
- On the **Summary** tab, click **Save**.

### Setting advanced LDAP options

PingFederate lets you customize the default settings of both the search pool and the bind pool for each LDAP datastore.

#### About this task

PingFederate maintains a search pool and a bind pool for each LDAP datastore for optimal performance. The search pool is for LDAP directory searches. The bind pool is for LDAP bind authentication purposes. Use the **Advanced LDAP Options** window to change default pool settings. These settings are applicable to both the search pool and the bind pool.

When configuring PingFederate to locate the directory server based on DNS SRV record, you can fine-tune the TTL value and the SRV record prefixes.

On the **LDAP Binary Attributes** tab, can also specify attributes that have values PingFederate must handle as binary data for use in attribute contract fulfillment. Binary attributes are typically used for certificates and images.



**Note:**

You cannot use binary data in an assertion. You must apply and handle encoding on a per-connection basis. When binary attributes are selected for attribute mapping, the administrative console prompts you to select an encoding type for each binary attribute.

### Steps

1. On the **Data Store** window's **LDAP Configuration** tab, click **Advanced**.

Result: The **Advanced LDAP Options** window opens.





Data Stores | Data Store | Advanced LDAP Options


| Advanced LDAP Options  | LDAP Binary Attributes                   |
|--|--|
| Manage LDAP connection-pooling settings for the selected data store. PingFederate manages both a bind and a search pool for every LDAP data store instance. The settings on this page are applied to both connection pools separately. |  |
| <input type="checkbox"/>   | TEST CONNECTION ON BORROW                |
| <input type="checkbox"/>   | TEST CONNECTION ON RETURN                |
| <input checked="" type="checkbox"/>  | CREATE NEW CONNECTIONS IF NECESSARY      |
| <input checked="" type="checkbox"/>  | VERIFY LDAPS HOSTNAME                    |
| MINIMUM CONNECTIONS  | <input type="text" value="10"/>          |
| MAXIMUM CONNECTIONS  | <input type="text" value="100"/>         |
| MAXIMUM WAIT (MILLI)   | <input type="text" value="-1"/>          |
| TIME BETWEEN EVICTION (MILLI)  | <input type="text" value="60000"/>       |
| READ TIMEOUT (MILLI)   | <input type="text" value="3000"/>        |
| CONNECTION TIMEOUT (MILLI)   | <input type="text" value="3000"/>        |
| DNS TTL (MILLI)  | <input type="text" value="60000"/>       |
| LDAP DNS SRV RECORD PREFIX   | <input type="text" value="_ldap._tcp"/>  |
| LDAPS DNS SRV RECORD PREFIX  | <input type="text" value="_ldaps._tcp"/> |
| <input type="button" value="Apply Defaults"/>  |  |

2. Optional: To view or restore default values, click the **Apply Defaults** button on the **Advanced LDAP Options** tab.

The default values are conservative based on the server thread pool settings configured in the `<pf_install>/pingfederate/etc/jetty-runtime.xml` file. If any changes are made to thread pooling, update the settings as outlined in the following step.

3. Configure the advanced settings. For more information about each field, see the following table.

| Field                                     | Description  |
|---|--|
| <b>Test Connection on Borrow</b>          | Indicates whether to validate objects before they are borrowed from the pool.<br><br>This check box is not selected by default.  |
| <b>Test Connection on Return</b>          | Indicates whether to validate objects before they return to the pool.<br><br>This check box is not selected by default.  |
| <b>Create New Connection If Necessary</b> | Indicates whether you can create temporary connections when the <b>Maximum Connections</b> threshold is reached. Temporary connections are managed automatically.<br><br> <b>Note:</b><br><br>If disabled, when the <b>Maximum Connections</b> value is reached, subsequent requests relying on this LDAP datastore instance might fail.<br><br>This check box is selected by default   |
| <b>Verify LDAPS Hostname</b>              | Indicates whether to verify that the host name of the directory server matches the subject (CN) or one of the subject alternative names (SANs) from the certificate.<br><br> <b>Important:</b><br><br>Verify the LDAPS host name for all LDAPS connections.<br><br>This check box is selected by default.   |
| <b>Minimum Connections (Required)</b>     | The smallest number of connections that can remain in each pool. A minimum value of 1 creates two connections, one connection in the search pool and one connection in the bind pool. The default value is 10.<br><br> <b>Note:</b><br><br>For optimal performance, the value for this setting should equal 50% of the <b>maxThreads</b> value in the Jetty server configuration. For more information see <a href="#">Configuring connection pools to datastores</a> on page 1084.<br><br> <b>Note:</b> |

| Field   | Description   |
|---|---|
|   | PingFederate does not establish the connection pool for the given datastore until it receives a request that requires one or more attributes from that datastore.   |
| <b>Maximum Connections (Required)</b>           | <p>The largest number of active connections that can remain in each pool (not including the temporary connections that are managed automatically when the <b>Create New Connection If Necessary</b> check box is selected). The value must exceed or equal the <b>Minimum Connections</b> value.</p> <p> <b>Note:</b><br/>For optimal performance, the value for this setting should equal 75% to 100% of the <code>maxThreads</code> value in the Jetty server configuration. For more information, see <a href="#">Configuring connection pools to datastores</a> on page 1084.</p> <p>The default value is 100.</p> |
| <b>Maximum Wait (Milli) (Required)</b>          | <p>The maximum number of milliseconds the pool waits for an available connection when trying to obtain a connection from the pool. A value of -1 causes the pool not to wait at all and to either create a new connection or produce an error (when no connections are available).</p> <p>The default value is -1.</p>  |
| <b>Time Between Eviction (Milli) (Required)</b> | <p>The number of milliseconds between periodic background health checks against the available connections in this pool. A value of -1 disables the evictor.</p> <p>The default value is 60000.</p>  |
| <b>Read Timeout (Milli) (Required)</b>          | <p>The maximum number of milliseconds a connection waits for a response to return before producing an error. A value of -1 causes the connection to wait indefinitely.</p> <p>The default value is 3000.</p>  |
| <b>Connection Timeout (Milli) (Required)</b>    | <p>The maximum number of milliseconds that a connection attempt can continue before returning an error. A value of -1 causes the pool to wait indefinitely.</p> <p>The default value is 3000.</p>   |
| <b>DNS TTL (Milli) (Required)</b>               | <p>The amount of time in milliseconds that a previously obtained DNS SRV record remains valid. When this threshold is reached, PingFederate contacts the DNS for a new SRV record to locate the directory server.</p> <p>The default value is 60000.</p>  |
| <b>LDAP DNS SRV Record prefix (Required)</b>    | <p>The prefix that PingFederate uses in its DNS queries for SRV records to locate an LDAP-capable directory server.</p> <p>The default value is <code>_ldap._tcp</code>.</p>  |

| Field   | Description  |
|---|--|
| <b>LDAPS DNS SRV Record prefix (Required)</b> | The prefix that PingFederate uses in its DNS queries for SRV records to locate an LDAPS-capable directory server.<br><br>The default value is <code>_ldaps._tcp</code> . |

4. Optional: To specify LDAP binary attributes:
  - a. Click **Next** on the **Advanced LDAP Options** tab.
  - b. On the **LDAP Binary Attributes** tab, add, edit, or remove binary attributes.
5. Click **Save**.

### Proxied authorization

When connecting to PingDirectory or Oracle Directory Server, configure proxied authorization for the service account on the directory server if you intend to enable self-service password reset in any HTML Form Adapter instances that use this datastore.

By configuring proxied authorization for the service account on the directory server, users are not allowed to reset their passwords if their accounts are disabled or if they were not granted permission to change their passwords.

For information on configuring proxied authorization for service accounts, see the following table.

| Directory server         | Reference   |
|--------------------------|---|
| PingDirectory            | See <a href="#">Working with Proxied Authorization</a> in the PingDirectory Administration Guide.   |
| Oracle Directory Server  | Go to Oracle's <a href="#">Oracle Fusion Middleware Deployment Planning Guide</a> and search for "Proxy Authorization".   |
| Oracle Unified Directory | Go to Oracle's online guide <a href="https://docs.oracle.com/cd/E52734_01/oud/OU DAG/toc.htm">https://docs.oracle.com/cd/E52734_01/oud/OU DAG/toc.htm</a> Fusion Middleware Administering Oracle Unified Directory and search for "proxied authorization control" in its glossary . |



#### Note:

Microsoft Active Directory does not support proxied authorization. See [https://docs.microsoft.com/en-us/openspecs/windows\\_protocols/ms-adts/faf0b8c6-8c59-439f-ac62-dc4c078ed715?redirectedfrom=MSDN](https://docs.microsoft.com/en-us/openspecs/windows_protocols/ms-adts/faf0b8c6-8c59-439f-ac62-dc4c078ed715?redirectedfrom=MSDN).

For general information about proxied authorization, see [RFC4370](#).

### Allowing PingFederate to unlock PingDirectory accounts

When connecting to PingDirectory, you can give the service account access to specific attributes that PingFederate reads or modifies when unlocking user accounts.

#### Steps

1. Create an LDIF file to capture the following ACI information.

OID

1.3.6.1.4.1.42.2.27.8.1.17

Name

pwdAccountLockedTime

Permission

all

**Example:**

For more information, see the following example file named `aci.ldif`.

```
dn: ou=People,dc=example,dc=com
changetype: modify
add: aci
aci: (targetattr="ds-pwp-auth-failure|pwdAccountLockedTime")
(version 3.0; acl "Allow unlock admin to lock and
unlock user accounts"; allow (all) userdn="ldap:///
uid=ServiceAccount,ou=Applications,dc=example,dc=com";)
```

2. Use the `ldapmodify` command to configure the required ACI.

**Example:**

```
$ ldapmodify -f <path>/aci.ldif
-h <host name>
-p <LDAP port>
-D <LDAP bind username>
-w <LDAP bind password>
```



**Note:**

Line breaks are inserted for readability only.

### Configuring the password validation details request control ACI

When connecting to PingDirectory, configure the password validation details request control Access Control Instruction (ACI) to provide user-friendly messages when users fail to change or reset their passwords through the self-service account management capabilities in any HTML Form Adapter instances that use the datastore.

#### About this task

For self-service password management, where the user knows the current password and wants to update it, the service account of the datastore must have the password validation details request control ACI. For self-service account recovery, where the user wants to define a new password after forgetting the current password, the user account needs the same ACI.

#### Steps

1. Create LDIF files to capture the following ACI information.

OID

1.3.6.1.4.1.30221.2.5.40

Name

Password Validation Details Request Control

Permission

read

The following examples show the example file contents for change password and password reset.

**Example:** `aci_toSvcAccount_forChangePassword.ldif`

```
# ACI to service account for change password
dn: uid=ssoDataStore,ou=ServiceAccounts,dc=example,dc=local
```

```
changetype: modify
add: aci
aci: (targetcontrol="1.3.6.1.4.1.30221.2.5.40") (version
  3.0; acl "Access to the Password Validation Details
  Request Control"; allow (read) userdn="ldap:///
  uid=ssaDataStore,ou=ServiceAccounts,dc=example,dc=local");)
```

**Example:** aci\_toUsrAccount\_forPasswordReset.ldif

```
# ACI to a user account for password reset
dn: uid=user.7,ou=People,dc=example,dc=local
changetype: modify
add: aci
aci: (targetcontrol="1.3.6.1.4.1.30221.2.5.40") (version 3.0; acl "Access
  to the Password Validation Details Request Control"; allow (read)
  userdn="ldap:///uid=user.7,ou=People,,dc=example,dc=local");)
```



**Note:**

For demonstration purposes, this sample LDIF file only targets one user. You can use other LDIF syntax to widen its coverage to include multiple users.

2. Use the `ldapmodify` command to configure the required ACI.

**Example:**

```
$ ldapmodify -f <path>/aci_toSvcAccount_forChangePassword.ldif
-h <host name>
-p <LDAP port>
-D <LDAP bind username>
-w <LDAP bind password>
```

```
$ ldapmodify -f <path>/aci_toUsrAccount_forPasswordReset.ldif
-h <host name>
-p <LDAP port>
-D <LDAP bind username>
-w <LDAP bind password>
```



**Note:**

Line breaks are inserted for readability only.

### Defining a custom LDAP type for outbound provisioning

If you are using outbound provisioning and your directory server is not PingDirectory, Microsoft Active Directory, Oracle Unified Directory, or Oracle Directory Server, you can define a custom LDAP type for PingFederate to use to streamline the provisioning configuration.

#### Steps

1. Copy and rename `<pf_install>/pingfederate/server/default/conf/template/ldap-templates/sample.template.txt` file.
2. Change the `template.name` property value in the new template file.  
This property value appears in the **LDAP Type** list on the **LDAP Configuration** window when you save the template.

3. Modify other property values in the file to match the corresponding configuration of your directory server.

These properties correspond to the fields shown on **Outbound Provisioning # Channel # Source Settings**. They help the provisioner determine when user records are added, changed, or removed.

4. Save the new template file.

For a clustered PingFederate environment, perform these steps on the console node. No changes or restart of the PingFederate service is required on any nodes.

#### Next steps

After you have configured the LDAP type, you can create a new LDAP datastore using the newly defined LDAP type. To streamline outbound provisioning configuration, select the LDAP data store that uses the newly-defined LDAP type in the **Source** window.

#### Configuring other types of datastores

Besides connecting to a directory server using LDAP or a database server using Java Database Connection (JDBC), PingFederate can connect to other types of datastores, such as REST API-enabled data sources that return user attributes in JavaScript Object Notation (JSON).

See the following topics for configuration steps:

- [Configuring a REST API datastore](#) on page 952
- [Configuring a custom datastore](#) on page 956

#### Configuring a REST API datastore

To retrieve attribute data from a JSON-based REST API, you must first create a REST API datastore.

#### Steps

1. Go to **System # Data & Credential Stores # Data Stores**.
2. On the **Data Stores** window, click **Add New Data Store**.
3. On the **Data Store Type** tab, type a name for the datastore.
4. From the **Type** list, select **Rest API**.
5. Optional: To mask attribute values returned from this datastore in PingFederate logs, select the **Mask Values in Log** check box.
6. Click **Next**.



7. On the **Configure Data Store Instance** tab, click **Add a new row to 'Base URLs and Tags'**.
  - a. Enter the **Base URL** of the data source offering REST API access to its data. You can enter multiple base URLs.

 **Tip:**

If you configure multiple URLs, nodes use the first URL with a tag that matches one of the `node.tags` in the `run.properties` file.

- b. Optional: Enter one or more tags per base URL.

Tags are defined in the `node.tags` property in the `<pf_install>/pingfederate/bin/run.properties` file. For a description of the `node.tags` property, see [Deploying cluster servers](#) on page 208.

In PingFederate deployments that are regional, you can enter one or more tags for a Base URL, which specifies the PingFederate node the datastore should communicate with. If none of the tags match what is defined for the `node.tags` property, the default node is used.

The following rules apply to tags:

- You must separate multiple tags specified for one node with spaces.
  - Tags must be unique per base datastore.
  - You cannot use a tag more than once per datastore.
  - Tags are optional. If needed, you can configure a non-default node without tags. Doing this is useful if you are not yet ready to tag the node, or if you are still in the planning stage but want to enter the address for the node now.
- c. Click **Update** under **Action**.
    - d. Select **Set as Default** under **Action** beside the Base URL and Tags that you want to use as the default. The first Base URL and Tags configured is set as the default automatically.

 **Note:**

If the data source exposes multiple paths or requires specific query parameters to retrieve user records, enter the base URL here and then specify the path and query parameters in the attribute source configuration.

For more information, see [Specifying data source filters for REST API datastores](#) on page 405.

8. If the data source requires specific HTTP request headers, click **Add a new row to 'HTTP Request Headers'**.

 **Note:**

If configured, PingFederate includes the configured HTTP request headers and their values when contacting the data source.

- a. Enter the applicable name and value under **Header Name** and **Header Value**.
  - b. Click **Update** under **Action**.

Repeat these steps to define additional HTTP request headers and their values.

9. Click **Add a new row to 'Attributes'** to define local attribute names and map them to the data returned by the data source.

Map each attribute to a path representing an attribute in the JSON response. This path follows the syntax defined in the [JavaScript Object Notation \(JSON\) Pointer](https://tools.ietf.org/html/rfc6901) specification at tools.ietf.org/html/rfc6901.

You must define at least one attribute.

- Enter the **Local Attribute** name and **JSON Response Attribute Path**.
- Click **Update** under **Action**.

Repeat these steps to define additional attributes.



**Tip:**

Define only the attributes required by other configuration items, such as contract fulfillment or token authorization. Provide meaningful attribute names so that you can easily recognize them at a later time.

10. Select one of the following authentication methods:

| Option                        | Description   |
|-------------------------------|---|
| <b>None</b>                   | PingFederate makes unauthenticated REST API requests to the data source. No credential information is required. This is the default setting.  |
| <b>Basic Authentication</b>   | PingFederate authenticates via the HTTP Basic authentication scheme. Enter the required credentials in the <b>Username</b> and <b>Password</b> fields.  |
| <b>OAuth 2.0 Bearer Token</b> | PingFederate authenticates by presenting an OAuth 2.0 access token. In this scenario, PingFederate is an OAuth client, specifically a client that uses the client credential grant type to obtain access token from an authorization server and presents the access token to the data source for authentication. Enter the client credentials in the <b>Client ID</b> and <b>Client Secret</b> fields. Then enter the token endpoint URL at the authorization server and the applicable scope (or scopes) in the <b>OAuth Token Endpoint</b> and <b>OAuth Scope</b> fields. |

11. Select the **HTTP Method** to call the REST API service: **GET** or **POST**.

Both methods support the JSON and x-www-form-urlencoded body types, among others, but PingFederate can parse only JSON responses.



**Tip:**


When configuring data source filters for attribute sources and user lookup, you can define the body sent in GET or POST requests to the REST API data store.

12. Optional: To mask attribute values returned through this datastore in the PingFederate log, select the **Mask Values in Log** check box.

This check box is visible only when editing an existing datastore and is not checked by default.

13. Optional: Click **Show Advanced Fields** to configure additional settings.

The following table describes the advanced fields.

| Field                                 | Description  |
|---------------------------------------|--|
| Enable HTTPS<br>Hostname Verification | <p>Indicates whether to verify that the hostname of the data source matches the subject (CN) or one of the subject alternative names (SANs) from the certificate.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;">  <b>Important:</b><br/>           You should verify the hostname for all connections.         </div> <p>This check box is selected by default.</p> |
| Read Timeout (MS)                     | <p>Defines the socket timeout in milliseconds.</p> <p>Enter 0 to set an infinite timeout.</p> <p>Enter a negative integer to use the default value set by the operating system.</p> <p>The default value is 10000 in milliseconds, which is 10 seconds.</p>  |
| Connection Timeout (MS)               | <p>Determines the timeout in milliseconds until a connection is established.</p> <p>Enter 0 to set an infinite timeout.</p> <p>Enter -1 to use the default value set by the operating system.</p> <p>The default value is 10000 in milliseconds, which is 10 seconds.</p>  |
| Max Payload Size (KB)                 | <p>Defines the maximum allowed size in kilobytes (KB) of the returned JSON response payload.</p> <p>Enter 0 to configure an unrestricted payload size.</p> <p>The default value is 1024 in KB.</p>   |
| Retry Request                         | <p>Determines whether to retry a user data retrieval request if the data source returns an HTTP status code found in the <b>Retry Error Codes</b>.</p> <p>This check box is selected by default.</p>   |
| Maximum Retries Limit                 | <p>Defines the maximum number of retry attempts if the data source returns an HTTP status code found in the <b>Retry Error Codes</b>.</p> <p>The default value is 5.</p>   |
| Retry Error Codes                     | <p>Enter a comma-separated list of HTTP status codes, for which if received from the data source, PingFederate might retry the request.</p> <p>For example, you can enter 429 for "Too Many Request" or 503 for "Service Unavailable".</p> <p>The default value is 429.</p>  |
| Test Connection URL                   | <p>Determines the URL to which PingFederate sends requests to test the datastore connection on the <b>Actions</b> tab.</p> <p>When not specified (the default), PingFederate sends requests to the base URL of the datastore.</p>  |

14. On the **Actions** tab, verify the datastore configuration.
  - a. Click **Test Connection** to test the connectivity between PingFederate and the data source.  
Result:  
The administrative console displays the results returned by the data source. The PingFederate server log may contain additional messages as well.
  - b. Review the results.
  - c. Optional: Click **Reset** and repeat the test.
15. On the **Summary** tab, review your configuration, amend as needed, click **Save** to keep your configuration or click **Cancel** to discard it.

### Example

You have two use cases that can leverage user attributes obtained through REST APIs. The data source returns user records in JSON:

```
{
  "uid": "asmith",
  "office": {
    "city": "Denver",
    "state": "CO",
    "zipCode": 80202
  },
  "telephoneNumbers": [
    "+1 303-555-1234",
    "+1 303-555-5678"
  ],
  "department": "Engineering"
}
```

The first use case requires the user's department, while the second use case requires the first telephone number and the ZIP code.

To address both use cases, create a REST API datastore with the following attributes.

| Local Attribute | JSON Response Attribute Path |
|-----------------|------------------------------|
| Dept            | /department                  |
| Telephone       | /telephoneNumbers/0          |
| Zip             | /office/zipCode              |

Once set up, you can fulfill various contracts or configure issuance criteria based on the attribute data from the data source.

### Configuring a custom datastore

You can configure your own custom datastore instance to perform specified actions.

#### About this task

Developers can use the PingFederate SDK to create specific drivers for non-Java Database Connectivity (JDBC), LDAP datastores, or more sophisticated JDBC or LDAP queries, including flat files or SOAP-connected databases. You can write datastores to perform configuration assistance or validation actions, such as testing a connection to a database. Actions can also include generation of parameters that might need manual setting in a configuration file.

For more information, see the Javadoc for the `CustomDataSourceDriver` interface, the `SamplePropertiesDataStore.java` file for a sample implementation, and the [SDK Developer's Guide](#) on page 1115 for build and deployment information.

**Tip:**

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

## Steps

1. After the data store driver (JAR) file is written and installed, select it in the **Data Store** window when creating a new instance of your data store.
2. On the **Configure Data Store Instance** tab, configure your data store instance.

**Note:**

Depending on the data store implementation, configuration requirements vary.

## Example:

After building and deploying the sample from the `<pf_install>/pingfederate/sdk/plugin-src/custom-data-store-example` directory, you can create an instance of the **Sample SDK Properties Data Store** and configure the rest, as shown in the following images.

**Note:**

When editing an existing instance, you can modify the name of the data store instance and toggle the option for if PingFederate should mask attribute values returned from this data store instance in PingFederate logs.

3. On the **Actions** window, follow the on-screen instructions provided by the developer to complete any required tasks.

**Note:**

Depending on the datastore implementation, configuration requirements vary. If no action is required, this window is not shown.

4. Click **Save** to keep your configuration.

**Defining a datastore for persistent authentication sessions**

When enabling PingFederate authentication sessions, you can select the persistent option so that PingFederate can leverage previous sessions as users request protected resources after restarting their browsers.

## About this task

This optional persistent configuration requires external storage of session-state data, as opposed to in-memory alone. By default, PingFederate uses its internal HSQLDB database to maintain persistent authentications. You can configure PingFederate to maintain persistent authentication sessions externally on a database server or a PingDirectory server. Also, the PingFederate SDK lets you use [custom solutions for persistent session storage](#).

**CAUTION:**

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

### Steps

1. Create the required data structure on the external storage medium.
2. Modify two PingFederate configuration XML files.

### Configuring an external database for authentication sessions

Set up various tables so that PingFederate can store authentication sessions on corresponding database servers.

### About this task

Specific tables are required in order for PingFederate to store authentication sessions on your database server. Table-setup scripts are provided for supported database servers.

### Steps

1. Run the table-setup scripts, provided in the `<pf_install>/pingfederate/server/default/conf/authentication-session/sql-scripts` directory, for your database server.
2. If you have not already done so, go to **System # Data & Credential Stores**. In the **Data Stores** window, create a Java Database Connection (JDBC) datastore for your database server.
3. Copy the system ID of the applicable JDBC datastore from the **Data Stores** window.
4. Edit the `org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory.



#### Note:

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your data store connection and save the file.

#### Example:

For example, if the system ID is `JDBC-123456789ABCDEF123456789ABCDEF123456A0A6`, update the

`org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl.xml` file as follows.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item
    name="PingFederateDSJNDIName">JDBC-123456789ABCDEF123456789ABCDEF123456A0A6</c:item>
</c:config>
```

5. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.

Example: If the system ID is `SessionStorageManager`, locate the `SessionStorageManager` service point, set the value of the `class` attribute to

`org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl` (the default value), then save the file.

```
<!-- Service for storing Authentication Sessions. -->
<service-point id="SessionStorageManager"
  interface="org.sourceid.saml20.service.session.data.SessionStorageManager">
  <invoke-factory>
    ...
    <construct
      class="org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl"
    >
    </invoke-factory>
  </service-point>
```



**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

6. Start or restart the PingFederate service.



**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

## Result

PingFederate removes expired authentication sessions from the database once a day. To fine-tune the frequency and the number of expired authentication sessions to remove, see [Managing authentication sessions stored in the database](#) on page 893.

## Configuring PingDirectory for authentication sessions

Use specific schema objects to enable PingFederate to store authentication sessions on your directory server. For PingDirectory, LDIF scripts are provided for this purpose.

## Steps

1. Update the LDAP schema.
  - a. Sign on to the PingDirectory administrative console.
  - b. Go to **LDAP Schema # Schema Utilities**.
  - c. Click **Import Schema Element**.
  - d. Copy the schema changes from the `authentication-session-attributes-ldap-pingdirectory.ldif` file and paste them into the text area.
 

The file is located in the `<pf_install>/pingfederate/server/default/conf/authentication-session/ldif-scripts` directory.

Replace the placeholder values with relevant information from your directory server.
  - e. Click **Import**.
2. Create the following indexes.

| Attribute name  | Index type |
|---|------------|
| <code>pf-authn-session-group-hashed-session-id</code> | equality   |

| Attribute name                            | Index type |
|---|------------|
| pf-authn-session-group-user-ids           | equality   |
| pf-authn-session-group-expiry-time        | ordering   |
| pf-authn-session-group-last-activity-time | ordering   |

Create these indexes with PingDirectory's `dsconfig` utility. The `dsconfig` utility is interactive. You can also provide inputs as command arguments. The following examples create the indexes.

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name pf-authn-session-group-hashed-session-id \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name pf-authn-session-group-user-ids \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name pf-authn-session-group-expiry-time \
  --set index-type:ordering
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name pf-authn-session-group-last-activity-time \
  --set index-type:ordering
```

After adding the indexes, use the `rebuild-index` utility to build the indexes. The following example builds the required indexes.

```
$ bin/rebuild-index \
  --baseDN "dc=example,dc=com" \
  --index pf-authn-session-group-hashed-session-id \
  --index pf-authn-session-group-user-ids \
  --index pf-authn-session-group-expiry-time \
  --index pf-authn-session-group-last-activity-time
```

For more information, see [Working with Indexes](#) in the Administration Guide.

3. If you have not already done so, create an LDAP data store for your directory server on **System # Data & Credential Stores # Data Stores**.
4. Copy the system ID of the applicable LDAP data store from the **Data Stores** window.



5. Edit the `/pingfederate/server/default/data/config-store/org.sourceid.saml20.service.session.data.impl.SessionStorageManagerLdapImpl.xml` file.

**Note:**

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

- a. Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your data store connection.

Example:

For example, if the system ID is `LDAP-123456789ABCDEF123456789ABCDEF123456A0AC`, update the configuration file as follows.

```
...
<!-- Data store id -->
<c:item
  name="PingFederateDSJNDIName">LDAP-123456789ABCDEF123456789ABCDEF123456A0AC</
c:item>
...
```

- b. Enter a value for the `<c:item name="SearchBase"/>` element.

**Tip:**

This is the distinguished name (DN) that points to the client location. For more information, see the inline comment and the LDIF scripts in the `<pf_install>/pingfederate/server/default/conf/authentication-session/ldif-scripts` directory.

- c. Update the attribute names only if you have changed attribute names in the LDIF scripts located in the `<pf_install>/pingfederate/server/default/conf/authentication-session/ldif-scripts` directory.
  - d. Save the file.
6. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
    - a. Locate the `SessionStorageManager` service point.

```
<!-- Service for storing Authentication Sessions. -->
<service-point id="SessionStorageManager"
  interface="org.sourceid.saml20.service.session.data.SessionStorageManager">
  <invoke-factory>
    <!--
      Supported classes are

      org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcImpl :
      Use this service-point for a Jdbc implementation.

      org.sourceid.saml20.service.session.data.impl.SessionStorageManagerLdapImpl :
      Use this service-point for an LDAP implementation.
    -->
    <construct
      class="org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcIm
    >
  </invoke-factory>
```

```
</service-point>
```

- b. Set the value of the `class` attribute to `org.sourceid.saml20.service.session.data.impl.SessionStorageManagerLdapImpl`.
- c. Save the file.

**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

7. Start or restart the PingFederate service.

**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

**Note:**

When storing persistent authentication sessions on a PingDirectory server, you must also configure a cleanup plugin in PingDirectory to remove expired authentication sessions from your directory server. For more information, see [Managing authentication sessions stored in PingDirectory](#) on page 896.

### Using custom solutions for persistent session storage

The PingFederate SDK supports custom storage for persistent authentication sessions.

#### Steps

1. Implement the `SessionStorageManager` interface.

**Note:**

For more information, see the Javadoc for the `SessionStorageManager` interface. The Javadocs for PingFederate are in the `<pf_install>/pingfederate/sdk` directory.

2. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file:
  - a. Locate the `SessionStorageManager` service point:

```
<!-- Service for storing Authentication Sessions -->
<service-point id="SessionStorageManager"
  interface="org.sourceid.saml20.service.session.data.SessionStorageManager">
  <invoke-factory>

    <construct
      class="org.sourceid.saml20.service.session.data.impl.SessionStorageManagerJdbcIm
    >

  </invoke-factory>
```

```
</service-point>
```

- b. Update the **construct** attribute value to the name of your class.
- c. Save the file.

**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

3. Deploy the required program files of your custom implementation to all PingFederate servers.
4. Start or restart PingFederate.

**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

**OAuth grant datastores**

Learn about persistent grant data stores and persistent authorizations.

PingFederate uses a built-in HSQLDB as its persistent grant datastore after the initial setup.

**CAUTION:**

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it may cause various problems due to its limitations and HSQLDB involved cases are not supported by PingIdentity.

Persistent authorizations include those obtained by OAuth clients in the following ways:

- Grants obtained or updated using the authorization code, resource owner credentials, or device authorization grant type, in conjunction with the refresh token grant type

**Note:**

If the use cases involve mapping attributes from authentication sources, such as IdP adapter instances or IdP connections, or password credential validator (PCV) instances to the access tokens, directly or through persistent grant-extended attributes, storing these attributes from authentication sources and their values along with the persistent grants maintains them for reuse when clients subsequently present refresh tokens for new access tokens.

- Grants obtained or updated by using the implicit grant type, for which is configured to reuse existing persistent grants

**Note:**

If the use cases involve mapping attributes from authentication sources or PCV instances to the access tokens, runtime procedures obtain attribute values for each token request, but persistent grants do not store with attributes or their values.

Persistent grants and any associated attributes and their values remain valid until the grants expire or until explicitly revokes or cleans them up.

**Note:**

Attribute values are always stored encrypted when a directory is used. If a database server is used (including the built-in HSQLDB database), attribute values are also stored encrypted by default.

**Configuring external databases for grant storage**

Specific tables are required in order for PingFederate to store grants, the associated attributes, and their values (if any), on your database server. Table-setup scripts are provided for supported database servers.

**About this task**

Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl.xml` file and the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.

**Steps**

1. Run the table-setup scripts for your database server provided in the `<pf_install>/pingfederate/server/default/conf/access-grant/sql-scripts` directory.
2. If you have not already done so, create a JDBC data store for your database server on **System # Data & Credential Stores # Data Stores**.
3. Copy the **System ID** of the applicable Java Database Connection (JDBC) data store from the **Data Stores** window.
4. Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl.xml` file.

**Note:**

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

- a. Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your data store connection and save the file.

**Example:**

If the system ID is `JDBC-123456789ABCDEF123456789ABCDEF123456A0A6`, update the `org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl.xml` file as follows.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item
    name="PingFederateDSJNDIName">JDBC-123456789ABCDEF123456789ABCDEF123456A0A6</c:item>
</c:config>
```

5. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - a. Locate the `AccessGrantManager` service point.

```
<!-- Service for storage of access grants -->
<service-point id="AccessGrantManager"
  interface="com.pingidentity.sdk.accessgrant.AccessGrantManager">
  ...
  <create-instance
    class="org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl"/>
```

```
</service-point>
```

- b. Set the value of the `class` attribute to `org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl`, the default value.
- c. Save the file.

**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

6. Start or restart PingFederate.

**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

**Result**

PingFederate provides two cleanup tasks for persistent grants. One task manages expired grants, while another task caps the number of grants based on a combination of user, client, grant type, and authentication context. For more information, see [OAuth persistent grants cleanup](#) on page 898.

**Configuring directories for grant storage**

PingFederate requires specific schema objects to store grants, the associated attributes, and their values (if any) on your directory server. LDIF scripts are provided for supported directory servers.

**Steps**

1. Review the LDIF scripts for your directory server provided in the `<pf_install>/pingfederate/server/default/conf/access-grant/ldif-scripts` directory.
2. Replace placeholder values with relevant information from your directory server.
3. Run the LDIF scripts to update your LDAP schema.

**Note:**

For Active Directory, run the script to create the attributes, then run the script to create the object class.

For Ping Directory, run the `ldapmodify` command. For example:

```
ldapmodify --defaultAdd --filename "<path to ldif file>\access-grant-ldap-pingdirectory.ldif" -h <hostname> -p <port> -D "<adminDN>" -w <adminPassword>
```

4. If you have not already done so, create an LDAP datastore for your directory server on **System # Data & Credential Stores # Data Stores**.
5. Copy the system ID of the applicable LDAP datastore from **System # Data & Credential Stores # Data Stores**.

## 6. Edit the configuration file relevant to your directory server.

**Note:**

This configuration file is located in the `<pf_install>/pingfederate/server/default/data/config-store` directory, as described in the following table.

| Directory server           | Configuration file  |
|----------------------------|---|
| PingDirectory              | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPPingDirecto</code> |
| Microsoft Active Directory | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPADImpl.xml</code>  |
| Oracle Unified Directory   | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPOracleImpl</code>  |

**Note:**

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

- Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your datastore connection.

Example:

If the system ID is `LDAP-123456789ABCDEF123456789ABCDEF123456A0A6`, update the configuration file as follows.

```
...
<!-- Data store id -->
<c:item
  name="PingFederateDSJNDIName"LDAP-123456789ABCDEF123456789ABCDEF123456A0A6/>
c:item>
...
```

- Enter a value for the `<c:item name="SearchBase"/>` element.

**Tip:**

This is the distinguished name (DN) that points to the access grants location. For more information, see the inline comment and the LDIF scripts in the `<pf_install>/pingfederate/server/default/conf/access-grant/ldif-scripts` directory.

- Update the attribute names only if you have changed attribute names in the LDIF scripts located in the `<pf_install>/pingfederate/server/default/conf/access-grant/ldif-scripts` directory.
  - Save the file.
- Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
    - Locate the `AccessGrantManager` service point.

```
<!-- Service for storage of access grants -->
<service-point id="AccessGrantManager"
  interface="com.pingidentity.sdk.accessgrant.AccessGrantManager">
  <create-instance
    class="org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl"/>
```

```
</service-point>
```

- b. Update the `class` attribute value to one of the following values.

| Directory server           | Class value  |
|----------------------------|--|
| PingDirectory              | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPPingDire</code> |
| Microsoft Active Directory | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPADImpl</code>   |
| Oracle Unified Directory   | <code>org.sourceid.oauth20.token.AccessGrantManagerLDAPOracleIm</code> |

- c. Save the file.



**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

8. Start or restart PingFederate.



**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

9. In the directory, create indexes for the following OAuth grant attributes. If you are using Active Directory, skip this step because the script for Active Directory creates these indexes. If you are using PingDirectory, see [Indexing grant attributes in PingDirectory](#) on page 967 for more information.

| Attribute name                                  | Index type |
|---|------------|
| <code>accessGrantGuid</code>                    | equality   |
| <code>accessGrantUniqueUserIdentifier</code>    | equality   |
| <code>accessGrantHashedRefreshTokenValue</code> | equality   |
| <code>accessGrantClientId</code>                | equality   |
| <code>accessGrantExpires</code>                 | ordering   |

## Result

PingFederate provides two cleanup tasks for persistent grants. One task manages expired grants, while another task caps the number of grants based on a combination of user, client, grant type, and authentication context. For more information, see [OAuth persistent grants cleanup](#) on page 898.

### *Indexing grant attributes in PingDirectory*

If you use PingDirectory, or another directory, to store OAuth persistent grants for PingFederate, you must index the grant attributes.

## About this task

Index these OAuth grant attributes using the procedure below.

| Attribute name                     | Index type |
|------------------------------------|------------|
| accessGrantGuid                    | equality   |
| accessGrantUniqueUserIdentifier    | equality   |
| accessGrantHashedRefreshTokenValue | equality   |
| accessGrantClientId                | equality   |
| accessGrantExpires                 | ordering   |

## Steps

1. Create the indexes using the PingDirectory **dsconfig** utility.

The **dsconfig** utility is interactive, letting you enter command arguments. The following examples create the required indexes.

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name accessGrantGuid \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name accessGrantUniqueUserIdentifier \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name accessGrantHashedRefreshTokenValue \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name accessGrantClientId \
  --set index-type:equality
```

```
$ bin/dsconfig create-local-db-index \
  --backend-name userRoot \
  --index-name accessGrantExpires \
  --set index-type:ordering
```

2. After adding the indexes, build the indexes using the **rebuild-index** utility.

The following example builds the required indexes.

```
$ bin/rebuild-index \
  --baseDN "dc=example,dc=com" \
  --index accessGrantGuid \
  --index accessGrantUniqueUserIdentifier \
  --index accessGrantHashedRefreshTokenValue \
  --index accessGrantClientId \
  --index accessGrantExpires
```



### Note:

You can configure a PingDirectory plugin to handle the cleanup of expired persistent grants and the associated attributes. The plugin allows fine-grained control over various aspects of the cleanup task,



which can smooth out the performance impact. For more information, see [Managing expired persistent grants in PingDirectory](#) on page 900.

### Using custom solutions for grant storage

Use the PingFederate SDK to implement a custom solution for grant storage.

#### Steps

1. Implement the `AccessGrantManager` interface.



#### Note:

For more information, see the Javadoc for the `AccessGrantManager` interface, the `SampleAccessGrant.java` file for a sample implementation, and the [SDK Developer's Guide](#) on page 1115 for build and deployment information.



#### Tip:

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.

2. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - a. Locate the `AccessGrantManager` service point.

```
<!-- Service for storage of access grants -->
<service-point id="AccessGrantManager"
  interface="com.pingidentity.sdk.accessgrant.AccessGrantManager">
  <create-instance
    class="org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl"/>
</service-point>
```

- b. Update the `class` attribute value to the name of your class.
- c. Save the file.



#### Note:

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

3. Deploy the required program files of your custom implementation to all PingFederate servers.
4. Start or restart PingFederate.



#### Note:

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

### Configuring an Amazon Dynamo database for persistent grants

#### About this task

Maintain access grants in Amazon Web Services (AWS) native DynamoDB.

Global secondary indexes:

- "AccessGrantsUniqueUserId-index" Hash: UniqueUserID
- "AccessGrantsHashedRefreshToken-index" Hash: HashedRefreshToken
- "AccessGrantsClientId-index": Hash ClientID
- "AccessGrantsLimitCheck-index" Hash: UniqueUserID, Range: ClientID

## Steps

1. To create a table in the DynamoDB to contain access grants, run the commands located in the `access-grant-dynamodb.txt` file in the `server/default/conf/access-grant/nosql-scripts` directory.

This file contains the create table command, the key, global secondary indexes, and the attributes needed for the key and index, as well as the command to enable the TTL expires attribute.

2. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file:
  - a. Add `org.sourceid.oauth20.token.AccessGrantManagerDynamoDBImpl` to the available Access Grant managers in `server/default/conf/META-INF/hivemodule.xml`.
  - a. Locate the `AccessGrantManager` service point.

```
<!-- Service for storage of access grants -->
<service-point id="AccessGrantManager"
interface="com.pingidentity.sdk.accessgrant.AccessGrantManager">
<create-instance
class="org.sourceid.oauth20.token.AccessGrantManagerJdbcImpl"/>
</service-point>
```

- b. Update the `class` attribute value to one of the following values.

| Directory server | Class value  |
|------------------|--|
| AWS Dynamodb     | <code>org.sourceid.oauth20.token.AccessGrantManagerDynamoDBImpl</code> |

- c. Save the file.



### Note:

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

3. Edit the `server/default/data/config-store/org.sourceid.oauth20.token.AccessGrantManagerDynamoDBImpl.xml` file.

## PingFederate Access Grants

| Access Grants                                     | Description   |
|---|---|
| <code>AccessGrantsUniqueUserId-index</code>       | The name of the user ID index.<br>This is the default value.              |
| <code>AccessGrantsHashedRefreshToken-index</code> | The name of the hashed refresh token index.<br>This is the default value. |
| <code>AccessGrantsClientId-index</code>           | The name of the client ID index.<br>This is the default value.            |

| Access Grants                | Description   |
|------------------------------|---|
| AccessGrantsLimitCheck-index | The name of the limits check index.<br>This is the default value.   |
| EndpointOverride             | An optional endpoint URL which should not be used in production but allows for testing with a local development DynamoDB instance.<br><br>By default, this value is empty. To test DynamoDB running locally, specify <b>EndpointOverride</b> to point to a local endpoint. For example, <code>&lt;c:item name="EndpointOverride"&gt;http://localhost:8000&lt;/c:item&gt;</code> . For more information, see <a href="#">DynamoDB local usage notes</a> in the AWS DynamoDB documentation. |

4. Export the AWS region.

See the following for a sample command `export AWS_REGION=us-east-2`.

5. Start or restart PingFederate.

### OAuth client datastores

Change the default storage method of XML files in PingFederate to make it easier to register clients or manage their records through the OAuth Client Management Service.

stores client records in XML files by default. On-disk storage allows you to manage clients using the administrative console and the administrative API. Client records are part of the configuration archive.

You can configure to store client records externally, which provides the flexibility to manage client records through the OAuth Client Management Service, or enable dynamic client registration for your partner-developers. In this scenario, client records are not part of the configuration archive. They are stored on a database server, a directory server, or some other storage medium through the use of the SDK.

### Configuring external databases for client storage

Specific tables are required in order for PingFederate to store OAuth client records on your database server. Table-setup scripts are provided for supported database servers.

About this task



#### CAUTION:

does not migrate client records from one storage medium to another. You must recreate your clients after updating the client storage configuration. If you need only a few clients, you can recreate them using the administrative console.

If you need a large number of clients, use the administrative API to retrieve your client records before updating the client storage. Update the client storage configuration and recreate your clients using the administrative API based on the retrieved records. For more information, see .



#### CAUTION:

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by Ping Identity.

## Steps

1. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - a. Locate the `ClientManager` service point.

```
<!-- Service for storing OAuth client configuration. -->
<service-point id="ClientManager"
  interface="org.sourceid.oauth20.domain.ClientManager">
  <invoke-factory>
    <!--
      Supported classes are
      org.sourceid.oauth20.domain.ClientManagerXmlFileImpl ...
      org.sourceid.oauth20.domain.ClientManagerJdbcImpl ...
      org.sourceid.oauth20.domain.ClientManagerLdapImpl ...
      org.sourceid.oauth20.domain.ClientManagerGenericImpl ...
    -->
    <construct
      class="org.sourceid.oauth20.domain.ClientManagerXmlFileImpl"/>
  </invoke-factory>
</service-point>
```

- b. Update the `class` attribute value to `org.sourceid.oauth20.domain.ClientManagerJdbcImpl`.
- c. Save the file.



### Important:

You must set up an external database because you cannot share the bundled HSQLDB database across multiple PingFederate engine nodes. For production standalone deployments, we recommend you store the client records in an external secured database.

2. Run the table-setup scripts for your database server provided in the `<pf_install>/pingfederate/server/default/conf/oauth-client-management/sql-scripts` directory.
3. If you have not already done so, create a Java Database Connectivity (JDBC) datastore for your database server. Go to **System # Data & Credential Stores**.
4. In the **Data Stores** window, copy the system ID of the applicable JDBC datastore.
5. Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.oauth20.domain.ClientManagerJdbcImpl.xml` file.



### Note:

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your datastore connection and save the file.

Example:

If the system ID is `JDBC-123456789ABCDEF123456789ABCDEF123456A0AC`, update the `org.sourceid.oauth20.domain.ClientManagerJdbcImpl.xml` file as follows.

```
<?xml version="1.0" encoding="UTF-8"?>
```

```
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item
    name="PingFederateDSJNDIName">JDBC-123456789ABCDEF123456789ABCDEF123456A0AC</
  c:item>
</c:config>
```

## 6. Start or restart PingFederate.



### Note:

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

## Configuring directories for client storage

Specific schema objects are required in order for PingFederate to store OAuth client records on your directory server. LDIF scripts are provided for supported directory servers.

### About this task



### CAUTION:

does not migrate client records from one storage medium to another. You must recreate your clients after updating the client storage configuration. If you need only a few clients, you can recreate them using the administrative console.

If you need a large number of clients, use the administrative API to retrieve your client records before updating the client storage. Update the client storage configuration and recreate your clients using the administrative API based on the retrieved records. For more information, see .

### Steps

1. Review the LDIF scripts for your directory server provided in the `<pf_install>/pingfederate/server/default/conf/oauth-client-management/ldif-scripts` directory.
2. Replace placeholder values with relevant information from your directory server.
3. Run the LDIF scripts to update your LDAP schema.



### Note:

For Active Directory, run the script to create the attributes, then run the script to create the object class.

For Ping Directory, run the `ldapmodify` command. For example:

```
ldapmodify --defaultAdd --filename "<path to ldif file>\oauth-client-
management-pingdirectory.ldif" -h <hostname> -p <port> -D "<adminDN>" -w
<adminPassword>
```

4. If you have not already done so, create an LDAP datastore for your directory server on **System # Data & Credential Stores # Data Stores**.
5. Copy the system ID of the applicable LDAP datastore from **System # Data & Credential Stores # Data Stores**.

6. Edit the `<pf_install>/pingfederate/server/default/data/config-store/org.sourceid.oauth20.domain.ClientManagerLdapImpl.xml` file.



**Note:**

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

- a. Replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your datastore connection.

Example:

If the system ID is `LDAP-123456789ABCDEF123456789ABCDEF123456A0AC`, update the configuration file as follows.

```
...
<!-- Data store id -->
<c:item
  name="PingFederateDSJNDIName">LDAP-123456789ABCDEF123456789ABCDEF123456A0AC</
c:item>
...
```

- b. Enter a value for the `<c:item name="SearchBase"/>` element.



**Tip:**

This is the distinguished name (DN) that points to the client location. For more information, see the inline comment and the LDIF scripts in the `<pf_install>/pingfederate/server/default/conf/oauth-client-management/ldif-scripts` directory.

- c. Update the attribute names only if you have changed attribute names in the LDIF scripts located in the `<pf_install>/pingfederate/server/default/conf/oauth-client-management/ldif-scripts` directory.
- d. Save the file.
7. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
- a. Locate the `ClientManager` service point.

```
<!-- Service for storing OAuth client configuration. -->
<service-point id="ClientManager"
  interface="org.sourceid.oauth20.domain.ClientManager">
  <invoke-factory>
    <!--
      Supported classes are
      org.sourceid.oauth20.domain.ClientManagerXmlFileImpl ...
      org.sourceid.oauth20.domain.ClientManagerJdbcImpl ...
      org.sourceid.oauth20.domain.ClientManagerLdapImpl ...
      org.sourceid.oauth20.domain.ClientManagerGenericImpl ...
    -->
    <construct
      class="org.sourceid.oauth20.domain.ClientManagerXmlFileImpl"/>
  </invoke-factory>
```

```
</service-point>
```

- b. Update the `class` attribute value to `org.sourceid.oauth20.domain.ClientManagerLdapImpl`.
- c. Save the file.

**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

8. Start or restart PingFederate.

**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

9. In the directory, create indexes for the following OAuth client attributes. If you are using Active Directory, skip this step because the script for Active Directory creates these indexes. If you are using PingDirectory, see [Indexing client attributes in PingDirectory](#) on page 975 for more information.

| Attribute name                             | Index type |
|--|------------|
| <code>pf-oauth-client-id</code>            | equality   |
| <code>pf-oauth-client-id</code>            | ordering   |
| <code>pf-oauth-client-id</code>            | substring  |
| <code>pf-oauth-client-name</code>          | equality   |
| <code>pf-oauth-client-name</code>          | ordering   |
| <code>pf-oauth-client-name</code>          | substring  |
| <code>pf-oauth-client-last-modified</code> | ordering   |

**Indexing client attributes in PingDirectory**

If you use PingDirectory, or another directory, to store OAuth client records for PingFederate, you must index the client attributes.

## About this task

Index these OAuth client attributes using the procedure below.

| Attribute name                    | Index type |
|-----------------------------------|------------|
| <code>pf-oauth-client-id</code>   | equality   |
| <code>pf-oauth-client-id</code>   | ordering   |
| <code>pf-oauth-client-id</code>   | substring  |
| <code>pf-oauth-client-name</code> | equality   |
| <code>pf-oauth-client-name</code> | ordering   |

| Attribute name                | Index type |
|-------------------------------|------------|
| pf-oauth-client-name          | substring  |
| pf-oauth-client-last-modified | ordering   |

### Steps

1. Create the indexes using the PingDirectory **dsconfig** utility.

The **dsconfig** utility is interactive, letting you enter command arguments. The following example creates the three indexes for the `pf-oauth-client-id` attribute.

```
$ bin/dsconfig create-local-db-index \
    --backend-name userRoot \
    --index-name pf-oauth-client-id \
    --set index-type:equality \
    --set index-type:ordering \
    --set index-type:substring
```

2. After creating the indexes, build them using the **rebuild-index** utility.

The following example builds the required indexes.

```
$ bin/rebuild-index \
    --baseDN "dc=example,dc=com" \
    --index pf-oauth-client-id \
    --index pf-oauth-client-name \
    --index pf-oauth-client-last-modified
```

### Using custom solutions for client storage

Use the PingFederate SDK to implement a custom solution for client storage.

#### About this task



#### CAUTION:

does not migrate client records from one storage medium to another. You must recreate your clients after updating the client storage configuration. If you need only a few clients, you can recreate them using the administrative console.

If you need a large number of clients, use the administrative API to retrieve your client records before updating the client storage. Update the client storage configuration and recreate your clients using the administrative API based on the retrieved records. For more information, see .

### Steps

1. Implement the `ClientStorageManagerV2` interface.

This interface includes a `search()` method, allowing developers to provide efficient implementations of the pagination and search functions exposed in the administrative console.

For more information, see the Javadoc for the `ClientStorageManagerV2` interface, the `SampleClientStorage.java` file for a sample implementation, and the [SDK Developer's Guide](#) on page 1115 for build and deployment information.



#### Tip:

The Javadoc for and the sample implementation are in the `<pf_install>/pingfederate/sdk` directory.



2. Edit the `<pf_install>/pingfederate/server/default/conf/META-INF/hivemodule.xml` file.
  - a. Locate the `ClientStorageManager` service point.

```

<!-- Service for storing OAuth client configuration. -->
<service-point id="ClientManager"
  interface="org.sourceid.oauth20.domain.ClientManager">
  <invoke-factory>
    <!--
      Supported classes are
      org.sourceid.oauth20.domain.ClientManagerXmlFileImpl ...
      org.sourceid.oauth20.domain.ClientManagerJdbcImpl ...
      org.sourceid.oauth20.domain.ClientManagerLdapImpl ...
      org.sourceid.oauth20.domain.ClientManagerGenericImpl ...
    -->
    <construct
      class="org.sourceid.oauth20.domain.ClientManagerXmlFileImpl"/>
    </invoke-factory>
  </service-point>

```

- b. Update the `class` attribute value with the name of the class implementing the `ClientStorageManagerV2` interface.
- c. Save the file.

**Note:**

For a clustered environment, you must edit the `hivemodule.xml` file on each node manually as cluster replication can't replicate this change to other nodes.

3. Start or restart `PingFederate`.

**Note:**

For a clustered environment, replicate this new configuration to other engine nodes on **System # Server # Cluster Management**. Start or restart the service on each engine node to activate the change.

**Account-linking datastores**

Configure where you want to store account links, either internally or externally.

When a service provider (SP) is configured to use account linking for an identity provider (IdP) connection, by default `PingFederate` uses the built-in Hyper SQL Database (HSQLDB) as the account-link repository. You can also configure `PingFederate` to store account links on an external database server or directory server. For specific instructions on how to configure these options, see the following topics:

- [Configuring external databases for account-link storage](#) on page 978
- [Configuring directories for account-link storage](#) on page 978

**CAUTION:**

Use the built-in HSQLDB only for trial or training environments. For testing and production environments, always use a secured external storage solution for proper functioning in a clustered environment.

Testing involving HSQLDB is not a valid test. In both testing and production, it might cause various problems due to its limitations and HSQLDB involved cases are not supported by `Ping Identity`.

## Configuring external databases for account-link storage

A specific table is required in order for PingFederate to store account links on your database server. Table-setup scripts are provided for supported database servers.

### Steps

1. Create a database for account linking using one of the table-setup scripts located in the `<pf_install>/pingfederate/server/default/conf/account-linking/sql-scripts` directory.
2. Go to **System # Data & Credential Stores # Data Stores** and create a new datastore to connect PingFederate to the database. For more information, see [Configuring a JDBC connection](#) on page 938.
3. On the **Data Stores** window, copy the system ID of the new account-linking datastore.
4. In the `org.sourceid.saml20.service.impl.AccountLinkingServiceDBImpl.xml` file, located in the `<pf_install>/pingfederate/server/default/data/config-store` directory, replace the `<c:item name="PingFederateDSJNDIName"/>` element value with the system ID of your datastore connection and save the file.



#### Note:

For a clustered environment, edit this file on the administrative console node first, and then replicate to other engine nodes using **System # Server # Cluster Management** as explained in later steps.

#### Example:

For example, if the system ID is `JDBC-123456789ABCDEF123456789ABCDEF123456A0AC`, update the `org.sourceid.saml20.service.impl.AccountLinkingServiceDBImpl.xml` file as follows.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">
  <c:item
    name="PingFederateDSJNDIName">JDBC-123456789ABCDEF123456789ABCDEF123456A0AC</
  c:item>
</c:config>
```

5. Start or restart PingFederate.
6. If you are running PingFederate in a cluster, go to **System # Server # Cluster Management** and replicate this change to other runtime servers.

## Configuring directories for account-link storage

You can create and configure a directory server to store account linking data.

Before you begin



#### Note:

User accounts for linking must exist in the directory prior to establishing the account link. The Account Linking Service does not add users to the directory server, it only updates `AccountLinkDataAttribute` for a given user.

### Steps

1. Go to **System # Data & Credential Stores # Data Stores** and create a new datastore to connect PingFederate to the directory. For more information, see [Configuring an LDAP connection](#) on page 942.

2. Copy the system ID of the new account-linking datastore.
3. Edit the `hivemodule.xml` file.

The file is located in the `<pf_install>/pingfederate/server/default/conf/META-INF` directory.

Locate the `service-point` for the Account Linking Service, as shown in the following example.

```
...
<!-- Service/adaptor for storage of account linking -->
<service-point id="AccountLinkingService"
  interface="org.sourceid.saml20.service.AccountLinkingService">
<!--
Supported classes are
org.sourceid.saml20.service.impl.AccountLinkingServiceDBImpl      : Use
  this service-point for a database implementation
org.sourceid.saml20.service.impl.AccountLinkingServiceLDAPImpl    : Use
  this service-point for an LDAP implementation
-->
  <create-instance
    class="org.sourceid.saml20.service.impl.AccountLinkingServiceDBImpl"/>
</service-point>
...
```

Update the `class` value to

`org.sourceid.saml20.service.impl.AccountLinkingServiceLDAPImpl`, as shown in the following example.

```
...
<!-- Service/adaptor for storage of account linking -->
<service-point id="AccountLinkingService"
  interface="org.sourceid.saml20.service.AccountLinkingService">
...
  <create-instance
    class="org.sourceid.saml20.service.impl.AccountLinkingServiceLDAPImpl"/>
</service-point>
...
```

Locate the Service-Point ID for `AccountLinkingService` and change the value of the `create-instance class` to

`org.sourceid.saml20.service.impl.AccountLinkingServiceLDAPImpl`.

4. Edit the `<pf_install>/org.sourceid.saml20.service.impl.AccountLinkingServiceLDAPImpl.xml` file.

The following example shows the default content of the file.

```
<?xml version="1.0" encoding="UTF-8"?>
<c:config xmlns:c="http://www.sourceid.org/2004/05/config">

  <!-- Data store id -->
  <c:item name="PingFederatedDSJNDIName"></c:item>

  <!-- LDAP search base -->
  <c:item name="UserSearchBase"></c:item>


  <!-- LDAP username attribute. ex: sAMAccountName -->
  <c:item name="UsernameAttribute"></c:item>

  <!-- Attribute on user object to place Account Linking data -->
  <c:item name="AccountLinkDataAttribute"></c:item>
```

```
</c:config>
```

Insert the applicable values between the XML tags as shown in the following table.

| Item name                | Element value  |
|--------------------------|--|
| PingFederateDSJNDI       | The system ID of new account-linking datastore.                    |
| UserSearchBase           | The location in the directory server from which the search begins. |
| UsernameAttribute        | The attribute that represents the user identifier.                 |
| AccountLinkDataAttribute | The attribute to store account linking data.                       |

 **Note:**

The `AccountLinkDataAttribute` can be any multivalued string attribute on a user object class. We recommend that you extend the LDAP schema with a custom attribute for use here. For more information on extending the Active Directory schema, see [Extending the Schema](#) from Microsoft.

5. Start or restart PingFederate.
6. If you are running PingFederate in a cluster, go to **System # Server # Cluster Management** and replicate this change to the other runtime servers.

 **Note:**

You must also manually apply the changes made in the `hivemodule.xml` file and then start or restart PingFederate on each runtime server.

7. In the directory, create equality indexes on the LDAP attribute types you specified for the configuration properties `UsernameAttribute` and `AccountLinkDataAttribute`.

**Example:** For example, you would need to create equality indexes on `sAMAccountName` and `AccountLink` if you had specified the following in step 4:

```
<!-- LDAP username attribute. ex: sAMAccountName -->
<c:item name="UsernameAttribute">sAMAccountName</c:item>

<!-- Attribute on user object to place Account Linking data -->
<c:item name="AccountLinkDataAttribute">AccountLink</c:item>
```

## Password Credential Validators

PingFederate provides an authentication mechanism using plugin password credential validators (PCVs). This feature provides centralized credential validation for various PingFederate components and configurations.

To manage Password Credential Validators, go to **System # Data & Credential Stores # Password Credential Validators**.

For each instance of the HTML Form Adapter, the HTTP Basic Adapter, and the Username Token Processor, you can select the same PCV instance, a unique PCV instance, or multiple PCV instances. When you select multiple PCV instances for a given adapter or token processor instance, if the first PCV instance fails to authenticate a user, the PCV returns control to the adapter or the token processor. The adapter or the token processor then tries the next PCV instance. The cycle stops until a PCV instance succeeds or the last PCV instance also fails.

For OAuth clients using the Resource Owner Password Credentials grant type, you configure a grant-mapping configuration to fulfill the persistent grant contract using the attribute values from the applicable PCV instances.



**Note:**

You can only create one grant-mapping configuration per applicable PCV instance.

If you want to manage OAuth client records using the OAuth Client Management Service or persistent grants using the OAuth Access Grant Management Service, you must select a PCV instance when configuring authorization server settings. When accessing these services, you must include in the requests valid credentials via HTTP Basic authentication scheme.

PingFederate is distributed with the following plugin PCVs.

LDAP Username Password Credential Validator

Validates credentials based on an LDAP look-up in an organization's user-datastore.

PingID PCV (with integrated RADIUS server)

Validates credentials from a VPN RADIUS client based on an LDAP look-up in an organization's user-datastore. For more information, see [Integrate PingID with your VPN](#).

PingOne for Enterprise Directory Password Credential Validator

Validates credentials stored in PingOne for Enterprise Directory.

RADIUS Username Password Credential Validator

Validates credentials based on the RADIUS protocol on an organization's RADIUS server.

Simple Username Password Credential Validator

Validates credentials maintained by PingFederate.



**Note:**

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

### Choosing a Password Credential Validator

You can choose the type of Password Credential Validator (PCV) that you want to use in PingFederate. You must also specify the PCV's name, ID, and whether it uses a parent instance.

#### About this task

Available PCV types are determined by plug-in `.jar` files loaded in the `<pf_install>/pingfederate/server/default/deploy` directory. Several validator plugins are bundled with PingFederate. You can add other plugins from the Ping Identity Downloads website.

#### Steps

1. On the **Type** tab, enter a name and an ID for the instance.
2. Select the type of the PCV from the **Type** list.

- Optional: Select a **Parent Instance** from the list.

Use this option when creating an instance that is similar to an existing one. The child instance inherits the configuration of its parent. You can also override one or more settings during the setup. Select the **Override ...** check box and make the adjustments as needed in one or more subsequent windows.

### Password Credential Validator instance configurations

The instance configuration of a Password Credential Validator (PCV) varies depending on the credential validators deployed on your server.

For PCVs bundled with PingFederate, see the following topics:

- [Configuring the LDAP Username Password Credential Validator](#) on page 982
- [Configuring the PingOne for Enterprise Directory Password Credential Validator](#) on page 988
- [Configuring the RADIUS Username Password Credential Validator](#) on page 989
- [Configuring the Simple Username Password Credential Validator](#) on page 990

### Configuring the LDAP Username Password Credential Validator

The LDAP Username Password Credential Validator (PCV) verifies credentials using an organization's LDAP datastore.

#### About this task

When an authentication error occurs, PingFederate automatically parses the messages returned by PingDirectory, Microsoft Active Directory (AD), Oracle Unified Directory (OUD), or Oracle Directory Server (ODS) and categorizes them with error conditions.

When validating against a directory server other than PingDirectory, AD, OUD, or ODS, administrators can define custom message categorization by mapping specific error messages with wildcard support to the desired error conditions.

The error messages are returned to the HTML Form Adapter instances and the OAuth clients using the Resource Owner Password Credential grant type. The HTML Form Adapter is designed to show the error message it receives from the LDAP Username PCV. OAuth-client developers can create custom experiences based on the error responses, which contain the error messages. The HTML Form Adapter uses the relevant error conditions to determine the LDAP password-change scenarios and to present the relevant messages to the end users.



#### Tip:

These customizable messages are stored in the message file, `pingfederate-messages.properties`, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

You can localize these messages by using the localization framework for an international audience. For more information, see [Localizing messages for end users](#) on page 889.

#### Steps

- Go to the **Instance Configuration** tab.

## 2. Optional: Override the authentication error messages.

**Note:**

You might require this option in order for a directory server other than PingDirectory, AD, OUD, or ODS to support the password change function in the HTML Form Adapter or to alter the end-user messages associated with that function.

- a. Click **Add a new row to 'Authentication Error Overrides'**.
- b. Enter an applicable LDAP error message under **Match Expression**.

**Tip:**

You can use wildcard asterisks to match messages returned from your directory server. For example, `*expired*`.

- c. Select a relevant error condition from the **Error** list.
- d. Optional: Enter a key name or an error message under **Message Properties Key**.

No value

If you skip this field, PingFederate returns the default message based on the selected error condition.

A unique key name

If you enter a key name in this field and then add the key name with a key value (the desired error message) to the PingFederate message file, PingFederate returns that key value.

The key name must be unique. Furthermore, you may localize these messages by using the PingFederate localization framework for an international audience.

An error message

If you enter an error message in this field (without defining it in the PingFederate message file), PingFederate returns your message verbatim.

- e. Click **Update** under **Action**.
- f. Repeat these steps to add more overrides as needed.


**Note:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.


Use the up and down arrows to change the display order. The display order does not affect runtime processing.

3. Select the LDAP datastore and enter information into the required fields.



For more information about each field, see the following table.

| Field                               | Description   |
|-------------------------------------|---|
| <b>LDAP Datastore</b><br>(Required) | <p>The LDAP datastore configured in PingFederate.</p> <p>If you have not yet configured the server to communicate with the directory server you need, click <b>Manage Data Stores</b>.</p> <div data-bbox="565 422 1472 690" style="border: 1px solid black; padding: 5px;"><p> <b>Note:</b></p><p>When connecting to an AD LDAP server, if you want to enable the password changes, password reset, or account unlock features in the HTML Form Adapter, you must secure the datastore connection to your AD LDAP server using LDAPS. AD requires this level of security to allow password changes.</p></div> |
| <b>Search Base</b><br>(Required)    | <p>The location in the directory server from which the search begins.</p>   |



| Field   | Description   |
|---|---|
| <p><b>Search Filter</b></p> <p>(Required)</p> | <p>The LDAP query to locate a user record.</p> <p>If your use case requires the flexibility of allowing users to identify themselves using different attributes, you can include these attributes in your query. For instance, the following search filter allows users to sign on using either the <b>sAMAccountName</b> or <b>employeeNumber</b> attribute value through the HTML Form Adapter.</p> <pre>(   (sAMAccountName=\${username}) (employeeNumber=\${username}))</pre> <div data-bbox="565 512 1466 1570" style="border: 1px solid black; padding: 10px;"> <p> <b>Important:</b></p> <p>To ensure that your service providers (SPs) always get the expected attribute, select a specific user attribute as the source of the subject identifier when configuring the applicable SP connections. There are several ways to do so:</p> <ul style="list-style-type: none"> <li>▪ Extend the PCV contract and fulfill the subject identifier through the HTML Form Adapter. For more information, see <a href="#">Extending the contract for the credential validator</a> on page 991.</li> <li>▪ Add a data source in the SP connection and fulfill the subject identifier through a datastore query. For more information, see <a href="#">Configuring attribute sources and user lookup</a> on page 468.</li> <li>▪ If you use authentication policy in conjunction with a policy contract, you can add a data source in the contract mapping configuration and fulfill the subject identifier in an SP connection through the authentication policy contract. For more information, see <a href="#">Applying policy contracts or identity profiles to authentication policies</a> on page 263.</li> </ul> <p>When configuring multifactor authentication using PingID, where you chain an instance of the PingID Adapter behind an HTML Form Adapter instance, ensure that you also select a specific user attribute as the incoming user attribute for the PingID Adapter instance. For example, if you have set up PingFederate as the identity bridge for your PingOne for Enterprise account and have selected <b>sAMAccountName</b> as the subject identifier in the SP connection, you should also select <b>sAMAccountName</b> as the incoming user attribute for your PingID Adapter instance. You can accomplish this through an instance of the Composite Adapter or an authentication policy.</p> <p>For more information, see <b>Input User ID Mapping</b> in <a href="#">Configuring a Composite Adapter instance</a> on page 300 or <b>Incoming User ID</b> in <a href="#">Specifying incoming user IDs</a> on page 258, respectively.</p> </div> |
| <p><b>Scope of Search</b></p>                 | <p>The level of search to perform in the search base.</p> <p><b>One Level</b> indicates a search of objects immediately subordinate to the base object, not including the base object itself. <b>Subtree</b> indicates a search of the base object and the entire subtree within the base object distinguished name.</p> <p>The default selection is <b>Subtree</b>.</p>  |

| Field   | Description   |
|---|---|
| <b>Case-Sensitive Matching</b>  | <p>The option to enable case-sensitive matching between the LDAP error messages returned from the directory server and the <b>Match Expression</b> values specified on this window.</p> <p>This check box is selected by default.</p>   |
| Advanced fields for self-service password reset, account unlock, and user name recovery through the HTML Form Adapter   |   |
| <b>Display Name Attribute</b>   | <p>The LDAP attribute used for personalizing messages to the users.</p> <p>This field is applicable for all password reset types (other than <b>None</b>), account unlock, and user name recovery.</p> <p>The default value is <code>displayName</code>.</p>  |
| <b>Mail Attribute</b><br>(for password reset)   | <p>The LDAP attribute containing the email address of the users.</p> <p>This field is required when password reset using one-time link or one-time password is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p>                      |
| <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>When configuring in conjunction with user name recovery, this attribute should correspond to the attribute specified on the left side of the <b>Mail Search Filter</b> field.</p> </div>                          |   |
|   | The default value is <code>mail</code> .  |
| <b>SMS Attribute</b><br>(for password reset)  | <p>The LDAP attribute containing the telephone number of the users.</p> <p>This field is required when password reset using text message is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p> <p>This field has no default value.</p> |
| <b>PingID Username Attribute</b><br>(for password reset)  | <p>The LDAP attribute containing the PingID user name of the users.</p> <p>This field is required when password reset using <b>PingID</b> is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p>  |
| <b>Mail Search Filter</b><br>(for user name recovery)   | <p>The LDAP query to locate a user record using an email address, such as <code>mail=\${mail}</code>.</p> <p>This field is required when user name recovery is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p>                      |
| <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>When configuring in conjunction with password reset, the attribute specified on the left side of this search filter should correspond to the attribute specified in the <b>Mail Attribute</b> field.</p> </div> |   |

| Field  | Description  |
|--|--|
| <p><b>Username Attribute</b><br/>(for user name recovery)</p>  | <p>The LDAP attribute containing the user identifier of the users.</p> <p>This field is required when user name recovery is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This attribute should correspond to the attribute specified on the left side of the <b>Search Filter</b> field.</p> </div>   |
| <p><b>Mail Verified Attribute</b><br/>(for user name recovery)</p>   | <p>The LDAP attribute indicating whether the user's email address is verified. The expected value of this user attribute is either <code>true</code> or <code>false</code> (case insensitive).</p> <p>This field is required when user name recovery using only verified email addresses is enabled in any HTML Form Adapter instances that validate credentials against this LDAP Username PCV instance.</p>  |
| <p><b>Enable PingDirectory Detailed Password Policy Requirement Messaging</b><br/>(for change password and password reset)</p> | <p>For password changes through an LDAP PCV backed by PingDirectory, this option indicates whether PingDirectory should return detailed password policy violations to PingFederate so that the invoking authentication source, namely the HTML Form Adapter, can present them to the end-users.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>The <b>User DN</b> associated with the selected LDAP Datastore must be granted the proper access control instruction (ACI) in PingDirectory. For more information, see <a href="#">Configuring the password validation details request control ACI</a>.</p> </div>  |
| <p><b>Expect Password Expired Control</b><br/>(for password expiry)</p>  | <p>When selected, PingFederate expects the LDAP datastore to return the password expired control when a user presents valid credentials but their password has expired.</p> <p>PingFederate can use this control in the bind response to distinguish between the following cases:</p> <ul style="list-style-type: none"> <li>▪ An expired password with valid credentials</li> <li>▪ An expired password with invalid credentials</li> </ul> <p>By default, the checkbox is cleared.</p> <p>When using PingDirectory as the credential store, if a user's password has expired, the following settings ensure PingFederate doesn't direct the user to the Change Password form when they enter an invalid password:</p> <ul style="list-style-type: none"> <li>▪ Select the <b>Expect Password Expired Control</b> checkbox.</li> <li>▪ Set the <b>return-password-expiration-controls</b> setting in the PingDirectory password policy to <b>always</b>.</li> </ul> |

## Configuring the PingOne for Enterprise Directory Password Credential Validator

The PingOne for Enterprise Directory Username Password Credential Validator (PCV) verifies credentials stored in your PingOne for Enterprise Directory.

Before you begin

To use the PingOne for Enterprise PCV, you must have:

- A PingOne for Enterprise account
- A PingFederate account

For more information, see [Managing PingOne for Enterprise Directory users](#) in the PingOne for Enterprise documentation.

Steps

On the **Instance Configuration** tab, enter your account information in **Client ID** and **Client Secret**.

For more information about each field, refer to the following table. All fields are required.

| Field                               | Description   |
|-------------------------------------|---|
| <b>Client ID</b>                    | The REST API client ID is a unique identifier PingFederate uses to identify itself to the PingOne for Enterprise Directory API.<br><br>For more information, see <a href="#">View or renew directory API credentials</a> in the PingOne for Enterprise documentation. |
| <b>Client Secret</b>                | The client secret is used to authenticate the client ID against the PingOne for Enterprise Directory API.<br><br>For more information, see <a href="#">View or renew directory API credentials</a> in the PingOne for Enterprise documentation.                       |
| Advanced Fields                     |   |
| <b>PingOne URL</b>                  | The PingOne for Enterprise Directory API.<br><br>The default value is <code>https://directory-api.pingone.com/api</code> .  |
| <b>Authenticate by Subject URL</b>  | The relative path for user authentication.<br><br>The default value is <code>/directory/users/authenticate?by=subject</code> .  |
| <b>Reset Password URL</b>           | The relative path for password reset.<br><br>The default value is <code>/directory/users/password-reset</code> .  |
| <b>SCIM User URL</b>                | The relative path for searching users requesting password reset.<br><br>The default value is <code>/directory/user</code> .   |
| <b>Connection Pool Size</b>         | The maximum size of the connection pool to PingOne for Enterprise Directory.<br><br>The default value is 100.   |
| <b>Connection Pool Idle Timeout</b> | The maximum time (in milliseconds) that a connection can remain idle before it is closed and removed from the connection pool.<br><br>The default value is 4000.  |

## Configuring the RADIUS Username Password Credential Validator

The RADIUS Username Password Credential Validator verifies credentials using the RADIUS protocol.

### About this task

RADIUS supports strong authentication with both one-step (a combination of regular password and a one-time password in one field) and two-step (challenge-response) authentication. Two-step authentication is supported in the HTML Form Adapter.



#### Important:

If your RADIUS server is a Microsoft Network Policy Server (NPS), passwords containing special characters will not be encoded and decoded properly due to limitations with NPS.



#### Tip:

RADIUS server messages are used by the HTML Form Adapter to determine the two-step authentication scenarios and to present a sign on window to the end users.

### Steps

1. On the **Instance Configuration** tab, configure one or more RADIUS servers.
  - a. Click **Add a new row to 'RADIUS Servers'**.
  - b. In each field, enter the required information.

For more information about each field, refer to the following table. All fields are required.

| Field                          | Description   |
|--------------------------------|---|
| <b>Hostname</b>                | The IP address of the RADIUS server.<br><br>For failover, enter one or more backup RADIUS servers by adding each server in its own row of the table. Each row represents a distinct RADIUS server that can be used for failover. PingFederate attempts to make a connection to each server in the order listed until a successful connection is obtained. |
| <b>Authentication Port</b>     | The UDP port used to authenticate to the RADIUS server.<br><br>The default value is 1812.   |
| <b>Authentication Protocol</b> | The protocol used to authenticate to the RADIUS server.<br><br>The available choices are Password Authentication Protocol (PAP) and Challenge Handshake Authentication Protocol (CHAP). Select the protocol expected by your RADIUS server.<br><br>The default selection is <b>PAP</b> .  |

| Field                | Description  |
|----------------------|--|
| <b>Shared Secret</b> | The password shared between PingFederate and the RADIUS server used to encrypt the attribute identifying the NAS (Network Access Server) originating the request for access. |

 **Note:**

The NAS-IP-Address attribute is added to all Access-Request packets sent to the RADIUS server. The value is copied from the `pf.engine.bind.address` property in the `<pf_install>/pingfederate/bin/run.properties` file. Only IPv4 addresses are supported.

- c. Click **Update** in the **Action** column.
- d. Repeat these steps to add more RADIUS servers as needed.

 **Note:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

Use the up and down arrows to adjust the order in which you want PingFederate to attempt credential authentication. If an earlier RADIUS server fails to validate the credentials, PingFederate moves sequentially through the list until credential validation succeeds. If none of the RADIUS servers is able to authenticate the user's credentials, the credential validation process fails.

2. Optional: Click **Show Advanced Fields** to reconfigure default settings.  
For more information about each field, refer to the following table. All fields are required.

| Field                 | Description  |
|-----------------------|--|
| <b>NAS Identifier</b> | The password shared between PingFederate and the RADIUS server used to encrypt the attribute identifying the NAS (Network Access Server) originating the request for access.<br><br>The default value is <code>PingFederate</code> . |
| <b>Timeout</b>        | The maximum number of milliseconds before a connection timeout to the RADIUS server.<br><br>The default value is <code>3000</code> .   |
| <b>Retry Count</b>    | The number of times to retry a failed connection before moving to the next host.<br><br>The default value is <code>3</code> .  |

### Configuring the Simple Username Password Credential Validator

The Simple Username Password Credential Validator verifies credentials maintained by PingFederate. This validator is best used for testing purposes or for an organization with few accounts.

#### Steps

1. On the **Instance Configuration** tab, click **Add a new row to 'Users'**.
2. Enter a user name, followed by a password (twice).
3. Click **Update** in the **Action** column.

- Repeat these steps to add more user credentials as needed.

**Note:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

Use the up and down arrows to adjust the order in which you want PingFederate to attempt credential authentication. PingFederate moves sequentially through the list until credential validation succeeds or no match is found.

**Extending the contract for the credential validator**

You can extend Password Credential Validator (PCV) instance contracts to return attribute values relevant to authenticated users.

## About this task

In some use cases, you might want to extend the contracts of the PCV instance. For example, you might use extended attributes to map into a `USER_KEY` for an OAuth persistent grant configuration.

This capability allows the validator to return attribute values pertaining to the authenticated users from PingOne for Enterprise Directory, a directory server, or a RADIUS server.

**Tip:**

If you are configuring an HTML Form Adapter instance with an instance of the LDAP Username Password Credential Validator, extend the contract of the adapter by the same attribute names in order for the credential validator to pass extended attribute values to the HTML Form Adapter instance.

If you are configuring the HTML Form Adapter instance with an instance of the RADIUS Username Password Credential Validator, you only need to extend the contract of the HTML Form Adapter instance itself.

## Steps

- Copy the vendor-specific attribute dictionaries into the `pingfederate/server/default/conf/radius` directory.

**Note:**

The format of the dictionaries must use the [FreeRadius dictionary syntax](#).

- Edit the existing `dictionary` file to include each of the dictionaries.
- Optional: On the **Extended Contract** tab, enter an attribute name and click **Add**.

**Note:**

Click **Edit**, **Update**, or **Cancel** to make or undo a change to an existing entry. Click **Delete** or **Undelete** to remove an existing entry or cancel the removal request.

## Finishing the Password Credential Validator instance configuration

On the **Summary** tab, you can review your configuration.

### Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

## Active Directory and Kerberos

You can configure PingFederate to authenticate users through the following identity provider (IdP) adapters or token processors.

| Adapter or Token Processor                       | Description   |
|--|---|
| PingFederate integrated Kerberos Adapter         | Using the built-in Kerberos Adapter with a configured AD domain allows a PingFederate identity provider (IdP) server to perform single sign-on (SSO) to service provider (SP) applications based on Kerberos tickets. |
| PingFederate integrated Kerberos Token Processor | The built-in Kerberos Token Processor accepts and validates Kerberos tokens through a configured Kerberos Realm from a web service client.  |



### Important:

As of version 10.3 and above, PingFederate no longer supports the IWA integration kit. For more information about Migrating from the IWA Integration Kit to the PingFederate Kerberos adapter, see <https://support.pingidentity.com/s/article/Migrating-from-the-Integrated-Windows-Authentication-integration-kit-to-the-PingFederate-Kerberos-adapter> in the Ping Identity Support Portal.

## Configuring Active Directory domains or Kerberos realms

You can configure an Active Directory (AD) domain or Kerberos realm to authenticate users.

### Steps

1. Go to **System # Data & Credential Stores # Active Directory Domains/Kerberos Realms**.
2. From the **Manage AD Domains/Kerberos Realms** window, configure the AD environment to integrate with PingFederate. For more information, see [Configuring the Active Directory environment](#) on page 993.
3. Click **Add Domain/Realm** to create an AD domain.



### Important:

Do not configure subdomains if the parent domain in the same forest is already configured. For more information, see [Multiple-domain support](#) on page 993.



### Note:

Click the name of an existing domain to edit it. Use the **Delete** and **Undelete** links to remove a domain or cancel a removal request.



## Multiple-domain support

If your network uses multiple domains in a single server forest, you can configure one domain within PingFederate if there is a trust relationship with the other domains you want to use.

This configuration requires a trust relationship among domains, which is established by default when subdomains or separate domains are created within the same forest. For more information, see [https://docs.microsoft.com/en-us/previous-versions/windows/it-pro/windows-server-2003/cc773178\(v=ws.10\)?redirectedfrom=MSDN](https://docs.microsoft.com/en-us/previous-versions/windows/it-pro/windows-server-2003/cc773178(v=ws.10)?redirectedfrom=MSDN).



### Note:

If you are configuring only one domain, then you also need to configure only one Service Principal Name. For more information, see [Configuring the Active Directory environment](#) on page 993.

If your network topology consists of multiple forests without a trust relationship between them, you must configure multiple adapter or token processor instances. Map each instance to a separate domain and then map these adapter or token processor instances to your service provider (SP) connections that authenticate using the integrated Kerberos Adapter or the integrated Kerberos Token Processor.

For information about configuring Kerberos authentication for multiple-domain Active Directory trusts, see <https://support.pingidentity.com/s/article/How-to-configure-IWA-with-multiple-Active-Directory-trusts> in the Ping Identity Support Portal.

## Configuring the Active Directory environment

You can configure Active Directory to access a domain and enable Kerberos as an authentication option for it.

About this task

To enable Kerberos authentication, you must make several Active Directory configuration changes to grant PingFederate access to the domain and add the domain to PingFederate.



### Important:

Do not configure subdomains if the parent domain in the same forest is already configured. For more information, see [Multiple-domain support](#) on page 993.



### Note:

You must have Domain Administrator permissions to make the required changes.

Steps

1. Create a domain user account that PingFederate can use to contact the Kerberos Key Distribution Center (KDC). The account should belong to the Domain Users group. We recommend that you set the password with no expiration.
2. Use the Windows utility `setspn` to register Service Principal Name (SPN) directory properties for the account by executing the following command on the domain controller.

```
setspn -s HTTP/<pf-idp.domain.name> <pf-server-account-name> , where <pf-idp.domain.name> is the canonical name of the PingFederate server and <pf-server-account-name>
```

is the domain account you want to use for Kerberos authentication. For more information on canonical name, see <https://tools.ietf.org/html/rfc2181#section-10>.



**Note:**

When executing the `setspn` command, you must capitalize `HTTP` and follow it with a forward slash (`/`).

3. Verify that the registration was successful by executing the following command.

```
setspn -l <pf-server-account-name>
```

This gives you a list of SPNs for the account. Verify that `HTTP/<pf-idp.domain.name>` is one of them.



**Note:**

After making an SPN change, any authenticated end users must re-authenticate by closing the browser or signing off and back on before attempting single sign-on (SSO).

### Adding Active Directory domains and Kerberos realms

You can configure Active Directory domains or Kerberos realms that PingFederate uses to contact the domain controllers or the key distribution centers (KDCs) for verifying user authentication.

About this task

The procedure for adding an Active Directory domain or Kerberos realm depends on whether PingFederate is deployed on-premise or in a cloud. Perform the procedure on one of the following tabs.



#### Adding domains and realms when PingFederate is on-premise

When PingFederate is deployed on-premise, use the following procedure.

Steps

1. In the **Manage Domain/Realm** window, configure the following settings.

| Field                        | Description   |
|------------------------------|---|
| <b>Connection Type</b>       | Select <b>Directly</b> .  |
| <b>Domain/Realm Name</b>     | The fully-qualified domain or realm name. For example, companydomain.com. |
| <b>Domain/Realm Username</b> | The ID for the domain or realm account name.                              |
| <b>Domain/Realm Password</b> | The password for the domain or realm account.                             |

| Field   | Description   |
|---|---|
| <b>Retain Previous Keys on Password Change</b>                            | <p>Select this check box and click <b>Save</b> to avoid locking out end users with existing Kerberos tickets when the service account password is updated.</p> <p>PingFederate retains each previous key for the period specified in the <b>Key Set Retention Period</b> field on the <b>Manage Domain/Realm Settings</b> tab of the <b>Active Directory Domains/Kerberos Realms</b> window. The default period is 610 minutes. For more information, see <a href="#">Managing domain connectivity settings</a> on page 996.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>To clear the previous keys from PingFederate, clear the check box and click <b>Save</b>.</p> </div> <p>This check box is selected by default.</p>   |
| <b>Domain Controller/Key Distribution Center Host Names</b><br>(optional) | <p>Specify the host name or IP address of your domain controller or KDC, such as <code>dc01-yvr</code>, and then click <b>Add</b>. Repeat this step to add multiple servers.</p> <p>If a host name is used, PingFederate appends the domain to the host name to formulate the fully qualified domain name (FQDN) of the server unless the <b>Suppress DC/Domain Concatenation</b> check box is selected.</p> <p>If unspecified, PingFederate uses a DNS lookup.</p>   |
| <b>Suppress DC/Domain Concatenation</b>                                   | <p>Select this check box to specify the desired FQDNs under <b>Domain Controller/Key Distribution Center Host Names</b>. When selected, PingFederate does not append the domain to the host names.</p>  |
| <b>Test Domain/Realm Connectivity</b>                                     | <p>Tests access to the domain controller or KDC from the administrative-console server.</p> <p>When a connection to any of the configured controllers or KDCs is successful, the message <code>Test Successful</code> appears. Otherwise, the test returns error messages near the top of the window.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Tip:</b></p> <p>For help resolving connectivity issues, select the <b>Debug Log Output</b> check box on the <b>Manage Domain/Realm Settings</b> window, run the test again, and review the debug messages in the PingFederate server log.</p> </div> <p>This test stops at the first successful result when multiple domain controllers or KDCs are specified, so not all servers are necessarily verified. Depending on the network architecture, the engine nodes deployed in a cluster might establish connections differently. As a result, the engine nodes and the console node might connect to different domain controllers or KDCs.</p> |

2. Click **Save**.

## Adding domains and realms when PingFederate is in a cloud

When PingFederate is deployed in a cloud, use the following procedure.

Before you begin

Ensure that PingFederate has a connection to a PingOne LDAP Gateway. For more information, see [Gateways](#) in the documentation for the PingOne Cloud Platform.

Steps

1. In the **Manage Domain/Realm** window, configure the following settings.

| Field                                  | Description   |
|--|---|
| <b>Connection Type</b>                 | Select <b>Through PingOne LDAP Gateway</b> .  |
| <b>Domain/Realm Name</b>               | The fully-qualified domain or realm name. For example, companydomain.com.   |
| <b>PingOne LDAP Gateway Data Store</b> | Select the datastore that was configured for the PingOne LDAP Gateway.  |
| <b>Test Domain/Realm Connectivity</b>  | Tests access to the domain controller or KDC from the administrative console server. When a connection to the configured PingOne LDAP Gateway is successful, the message <code>Test Successful</code> appears. Otherwise, the test returns error messages near the top of the window. |


2. Click **Save**.


## Managing domain connectivity settings

You can change the default security and logging settings for all configured Active Directory domains and Kerberos realms.

Steps

- On the **Manage Domain/Realm Settings** tab, change the default transport protocol, the debug option, the timeout value, and the number of retry attempts. For more information, refer to the following table.

| Field                   | Description   |
|-------------------------|---|
| <b>Force TCP</b>        | When selected, requires use of the Transmission Control Protocol instead of the default User Datagram Protocol. Use this option when firewall or network configurations require acknowledgment that packets are properly received.<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Note:</b><br/>If you choose this option, you must restart PingFederate after saving the configuration. </div> |
| <b>Debug Log Output</b> | When selected, sends verbose messages to the PingFederate server log for all interactions with the domain controllers or the Key Distribution Centers (KDCs).   |

| Field  | Description   |
|--|---|
| <b>AD Domain Controller/Key Distribution Center Timeout (secs)</b> | <p>The number of seconds that PingFederate waits for a network response from a domain controller or KDC. The default is 3.</p> <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This value applies to each attempt PingFederate makes to contact the domain controller or KDC.</p> <p>The new timeout takes effect only after you save the configuration and restart PingFederate..</p> </div>   |
| <b>AD Domain Controller/Key Distribution Center Retries</b>        | <p>Specifies the number of times PingFederate tries contacting the domain controller or KDC. The default is 3.</p>  |
| <b>Key Set Retention Period (mins)</b>                             | <p>The number of minutes that PingFederate retains the encryption keys associated with the previous password of the Kerberos service account. The allowed range is 0 to 10080 minutes (seven days) and the default value is 610 minutes.</p> <p>PingFederate only retains the key sets associated with previous passwords if you select the <b>Retain Previous Keys on Password Change</b> check box on the <b>Manage Domain/Realm</b> window. For more information, see <a href="#">Adding Active Directory domains and Kerberos realms</a> on page 994.</p> |

## External systems

Many use cases require communications between PingFederate and other systems, such as PingOne or a database server. **System # External Systems** is where you can set up and maintain such integrations.

### Connections to PingOne

Some PingFederate plugins that access services provided by PingOne can leverage a secure connection between PingFederate and PingOne.

For example, when configuring instances of PingFederate's PingOne MFA and PingOne Risk plugins, you can select a connection and one of the connection's PingOne environments. You do not need to enter credentials and other connection details for each instance. Also, you do not need to update each plugin instance individually when, for example, you replace the connection's credential.

The central element of a connection is its credential, which an administrator generates on PingOne and copies to PingFederate when they create the connection. During runtime, a PingFederate plugin instance that was configured to use the connection gets the credential and uses it to access a PingOne environment.

Administrators with access to both PingFederate and PingOne create the connection. For more information, see [Creating connections to PingOne](#) on page 998.

You can create multiple connections but most deployments require only one enabled connection. Typically, you use only one connection from a PingFederate cluster to a given PingOne organization. A single connection can be configured to provide access to multiple environments in PingOne.

Cards on PingFederate's **System # External Systems # PingOne Connections** window display information about each connection to PingOne. When the card is collapsed, it shows only the connection's name, ID, and status toggle switch. Use the toggle switch to enable and disable the connection on PingFederate.

**Note:**

Administrators can disable a connection on PingFederate or PingOne. Plugins can use a connection only if it is enabled on both PingFederate and PingOne.

When a connection card is expanded, it shows more information about the connection on tabs, including the status of the main connection and the plugin connections, if any.

| Tab                 | Description   |
|---------------------|---|
| <b>Summary</b>      | <p>In the <b>Summary</b> tab's <b>Summary Details</b> section, the <b>Description</b> and <b>Created</b> time come from PingFederate. The <b>Connection ID in PingOne</b>, <b>Credential ID</b>, <b>Organization Name</b>, and <b>Region</b> come from the connection credential.</p> <p>In the <b>Summary</b> tab's <b>Configuration</b> section, the image shows:</p> <ul style="list-style-type: none"> <li>▪ the status of the connection between PingFederate and PingOne</li> <li>▪ which plugin types can use this kind of connection and are installed on PingFederate, if any</li> <li>▪ which service on PingOne each of those plugin types is designed to use</li> <li>▪ whether any instances of those plugin types are configured to use this particular connection</li> </ul> |
| <b>Usage</b>        | The <b>Usage</b> tab lists each plugin instance on PingFederate that is configured to use this connection. The instances are grouped by plugin category.  |
| <b>Environments</b> | The <b>Environments</b> tab shows which environments on PingOne the connection is able to access. You assign environments to connections in PingOne. In PingFederate, when you configure a plugin to use a connection, you select the connection and one of its environments.   |

**Creating connections to PingOne**

Administrators can create connections between PingFederate and PingOne that some PingFederate plugins can use to access services provided by PingOne.

## About this task

In the following procedure, you create a connection profile and credential in PingOne. Then you use the credential in PingFederate to establish the connection. So you need administrative access to both applications.

**Note:**

You cannot use the same credential in multiple extant connections.

After creating the connection, you can use it to configure PingFederate plugins that support connections to PingOne, such as the PingOne MFA and PingOne Protect plugins.

For more information about these connections, see [Connections to PingOne](#) on page 997 in the PingFederate documentation and [PingFederate connections](#) in the PingOne documentation.

## Steps

1. In PingOne, create a connection profile and credential:
  - a. Go to **Connections # Product Platform # PingFederate**.
  - b. Click **+ Add Connection**.
  - c. On the **Create Connection Profile** window, enter a **Connection Name** and **Description**.
  - d. Click **Save and Continue**.
  - e. On the **Establish Connection with PingFederate** window, copy the connection credential by clicking **Copy to Clipboard**.
  - f. If you will not perform step 2 now, paste and save the credential in a text file because this is the only time you can view and copy the credential.
2. In PingFederate, establish the connection:
  - a. Go to **System # External Systems # PingOne Connections**.
  - b. On the **PingOne Connections** window, click **+ Add Connection**.
  - c. On the **Add Connection** window, paste the credential that was created in step 1.
  - d. Enter a new **Connection Name** or keep the auto-populated name, which is the name of your organization on PingOne. Ensure the name is unique.
  - e. Enter a **Connection Description**.
  - f. Click **Save**. The **PingOne Connections** window shows the new connection. The connection is enabled by default.
3. Optional: Configure the PingOne unified admin icon in the navigation menu to access your PingOne admin console from PingFederate.
  - a. Edit the `<pf_install>/pingfederate/bin/run.properties` file.
  - b. Modify the `pf.pingone.admin.url.region` and `pf.pingone.admin.url.environment.id` properties for your environment.  
For more information on these properties, see [Configuring PingFederate properties](#) on page 820.
  - c. Restart PingFederate.

## Next steps

After you create a connection, you can:

- use the connection to configure PingFederate plugins that support these kinds of connections
- change which environments in PingOne the connection can access
- replace or revoke the connection's credentials
- disable the connection
- change the connection's name or description

For more information, see [Modifying connections to PingOne](#) on page 999.

## Modifying connections to PingOne

Administrators can modify a connection between PingFederate and PingOne by, for example, adding a PingOne environment to it, replacing its credential, changing its description, or disabling it



### Note:

If you have multiple connections to PingOne, to avoid confusion, you can identify a connection by its connection ID in both PingFederate and PingOne. The connection ID never changes, whereas its name can be changed.

*Editing connection names and descriptions*

You can change the names and descriptions of connections between PingFederate and PingOne.

## About this task

The following procedure describes how to change the name and description of the connection in PingFederate. You can also change them in PingOne.

**Note:**

Changing the name and description in PingFederate does not change them in PingOne, and vice versa. You cannot change a connection's ID.

## Steps

1. In PingFederate, go to **System # External Systems # PingOne Connections**.
2. On the **PingOne Connections** window, open the connection's card by clicking its expand icon.
3. Click the pencil icon.
4. Change the **Connection Name**, **Connection Description**, or both.
5. Click **Save**.

*Disabling and enabling connections*

You can disable a connection between PingFederate and PingOne in either of those applications; however, to enable a connection, it must be enabled in both applications.

## Steps

1. To disable or enable a connection in PingFederate:
  - a. Go to **System # External Systems # PingOne Connections**.
  - b. On the connection's card, click the toggle switch to change the connection's state.
2. To disable or enable a connection in PingOne:
  - a. Go to **Connections # Product Platform # PingFederate**.
  - b. On the connection's card, click the toggle switch to change the connection's state.

*Replacing connection credentials*

You can replace or revoke the credential of a connection between PingFederate and PingOne.

## About this task

The following procedure describes how to replace a connection's credential, which requires administrative access to both applications.

## Steps

1. In PingOne:
  - a. Go to **Connections # Product Platform # PingFederate**.
  - b. On the **PingFederate Connections** window, open the connection's card and go to the **Configuration** tab.
  - c. Click the pencil icon.
  - d. Click **+ Add**.  
Result: PingOne generates a new credential, adds it to the tab, and opens a dialog box.
  - e. In the dialog box, click the credential to save it to the clipboard.
  - f. Close the dialog box.
  - g. If you will not perform step 2 now, paste and save the credential in a text file because this is the only time you can view and copy the credential.



2. In PingFederate:
  - a. Go to **System # External Systems # PingOne Connections**.
  - b. On the **PingOne Connections** window, open the connection's card.
  - c. Click the pencil icon.
  - d. Paste the new credential that you created in step 1 in the **Credential** field.
  - e. Click **Save**.

#### Next steps

After you replace a connection's credential, you can go to PingOne and revoke the old credential.

*Modifying which environments connections can access*

PingOne administrators can specify which environments in PingOne a connection can access.

In PingOne, environments are assigned to roles and roles are assigned to connections. When a connection is created, PingOne assigns it default roles and environments. A connection can access all the environments assigned to its roles. For more information, see [Edit a connection: Add roles and responsibilities](#) in the documentation for PingOne.

### Connections to PingOne for Enterprise

Integrating PingOne for Enterprise with PingFederate provides a powerful solution combining the benefits of an on-premise deployment with the flexibility of a cloud solution.

#### Steps

1. Go to **System # External Systems # Connect to PingOne for Enterprise**.
2. On the **Connect to PingOne for Enterprise** window, click **Sign on to PingOne to get your activation key**.
3. Sign on to PingOne for Enterprise using your PingOne Admin Portal credentials.



#### Tip:

If you do not have an account, you can register for a free trial.

4. Copy the **Activation Key** value from the PingOne admin portal.
5. Return to the PingFederate administrative console.
6. On the **PingOne Account** tab, paste the key value in the **Activation Key** field. Click **Next**.

### Configuring identity repository settings

Set up a customized directory configure identity repository settings either immediately or at a later time.

#### About this task

On the **Identities** tab, you can optionally connect to a directory server.

#### Steps

- Go to **System # External Systems # Connect to PingOne for Enterprise** and access the **Identities** tab.
- To enable directory integration, select **Yes, Connect a Directory Server**.

You can create a new datastore or reuse an existing datastore in this configuration.

#### Create a new datastore

Provide the required information to connect to a directory server, and then click **Next**.

More information about each field is provided in the following table.

| Field                     | Description  |
|---------------------------|--|
| <b>Directory Type</b>     | Select the type of directory server from the list.<br><br>See <a href="#">System requirements</a> on page 119 for a list of supported directory servers.   |
| <b>Data Store Name</b>    | Enter the name of the datastore.   |
| <b>Hostname</b>           | Enter the location of the directory server.<br><br>It can be the IP address, the host name, or the fully qualified domain name of the directory server. The entry might include a port number.   |
| <b>Service Account DN</b> | Enter the distinguished name (DN) of the service account that PingFederate can use to communicate with the directory server.   |
| <b>Password</b>           | Enter the password associated with the service account.  |
| <b>Search Base</b>        | Enter the DN of the location in the directory where PingFederate begins its datastore queries.   |
| <b>Search Filter</b>      | Enter the LDAP query to locate a user record for attribute lookup and potentially credential validation.<br><br>The default value is either <code>sAMAccountName=\${username}</code> or <code>uid=\${username}</code> , depending on the selected directory type.<br><br>If you require a more advanced search filter, ensure the value is a valid LDAP filter. For more information, consult your directory administrators. |

When you click **Next**, PingFederate tries to establish a secure (LDAPS) connection to the directory server.

If the directory server does not support LDAPS, the **Unsecure Connection** window appears. If you want to continue without a secure connection, click **Next**. Alternatively, you can go back to the **Identities** tab and specify a different directory server.

If the certificate presented by the directory server is not trusted by PingFederate, the **Certificate Error** window appears. You can import the certificate used by the directory server to establish a secure connection, and then click **Next** in the **Identities** tab and specify a different directory server.

Use an existing datastore

Click **Begin**, and then follow the on-screen instructions to create a service provider (SP) connection to PingOne for Enterprise.

- Optional: To set up a directory later, select **No, Don't Connect a Directory Server** and then click **Next**.



**Tip:**

This setup scenario is suitable for proof of concept. Multiple local test accounts are created as a result.

## Use Cases

On the **Use Cases** tab, select what you plan to use PingFederate to do.

### PingOne SSO

Select this option and click **Next** if you want to enable single sign-on with PingOne for Enterprise and your configured identity store. For more information about using PingOne SSO, see the *PingOne for Enterprise Administration Guide*.



#### Note:

If you have not connected to an LDAP directory, the system configures test user accounts.

Optionally, you can enable Kerberos authentication (if you are using Active Directory). You can also enable user provisioning. To do this, select **Additional SSO Features**, and click **Begin**. After you have finished the Kerberos and provisioning configuration, you will be returned to the **Use Cases** tab.

### PingID VPN (RADIUS)

Select this option and click **Next** if you want to configure PingFederate to integrate with a RADIUS server to support PingID multifactor authentication through your virtual private network. When you select this option, a **Begin** button appears. Click **Begin**.

For more information about using PingID VPN, see the *PingID Administration Guide*.

*Configuring the RADIUS server to integrate PingID with your VPN*

On the **Basic Settings** tab, you enable the built-in RADIUS server to integrate PingID with your VPN.

## Steps

1. To configure the RADIUS client and server information, fill out the required fields.

For information about each field, see the following table.

| Field                      | Description   |
|----------------------------|---|
| Client IP                  | Enter the IP address of the VPN server.   |
| Client Shared Secret       | Enter the password shared between the VPN server and PingFederate.                      |
| Server Authentication Port | Enter the listening port of the integrated RADIUS server.<br>The default value is 1812. |

2. If you are connecting PingFederate to a directory server, select the **Validate with LDAP** check box to enable first-factor credential validation against the directory server. This check box is selected by default.
3. If you are connecting PingFederate to a directory server and have updated the **Search Filter** value to compare user input against another user attribute, enter that user attribute name in the **PingID Username Attribute** field. Click **Next**.

Example:

If you have updated the **Search Filter** value from `uid=${username}` to `mail=${username}`, enter `mail` in the **PingID Username Attribute** field.

### Configuring provisioning to PingID

If you have chosen to connect PingFederate to a directory server, the **Provisioning** tab becomes available.

#### About this task

On the **Provisioning** tab, you have the option to enable provisioning of users from your directory server to PingID. In this configuration, specify the group where PingFederate should look for member users and update PingID when their email address, first name, or last name has changed.



#### Note:

This provisioning capability is designed to manage existing PingID accounts. It does not create new PingID users. When PingFederate detects that a user has been removed from the specified group or disabled in the directory server, PingFederate sends an update to PingID to disable the PingID service for that account.

#### Steps

1. Select the **Configure Provisioning** check box.
2. In the **PingID Group DN** field, enter the distinguished name (DN) of the applicable group.



#### Note:

The specified group must reside under the hierarchy of the previously-defined **Search Base** value.

3. If you want PingFederate to monitor changes for users through nested group membership, select the **Nested** check box. Click **Next**.

### Reviewing the PingID VPN (RADIUS) configuration

On the **Summary** tab, review your configuration.

#### Steps

Perform one of the following actions.

Choose from:

- To edit your configuration, click the corresponding tab and follow the wizard.
- To keep your changes, click **Done** and continue with the configuration.
- To discard your changes, click **Cancel**.

#### Confirmation

The **Confirmation** tab displays a summary of the configuration that will be applied to PingFederate.

Click **Next** to apply the configuration.

#### Complete

The **Complete!** tab congratulates you on successfully setting up PingFederate.

#### Steps

1. Make a note of the instructions under **What's Next?** You will need to complete these tasks when you begin configuring PingFederate.
2. Click **Done**.

## Managing PingOne for Enterprise settings

You can configure PingOne for Enterprise's general settings and single sign-on (SSO) settings, and enable and configure a RADIUS server to integrate PingID with a VPN.

About this task



Go to **System # External Systems # PingOne for Enterprise Settings**, configure various PingOne for Enterprise integration settings and optionally enable and configure a built-in RADIUS server to integrate PingID with your VPN.

### Configuring PingOne for Enterprise settings

To configure the PingOne for Enterprise settings, adjust the various integration settings.

### Steps

1. Go to **System # PingOne for Enterprise Settings**.
2. Configure the PingOne for Enterprise integration settings. For more information, see the following table.

| Field  | Description   |
|--|---|
| <b>Enable Single Sign-On from PingOne to the PingFederate Administrative Console</b> | Toggles the ability to sign on to the administrative console using the PingOne admin portal credentials.  |
| <b>Enable Monitoring of PingFederate from PingOne</b>                                | Toggles the ability to monitor your PingFederate server (or servers in a clustered environment) from the PingOne admin portal   |
| <b>Rotate Key</b>  | Update the authentication key that PingFederate uses to communicate with PingOne for Enterprise.  |
|  |  <b>Note:</b><br>Periodic rotation can ensure optimal security of your environment.  |
|  |  <b>Note:</b><br>PingFederate also automatically rotates the signing certificate used by the managed service provider (SP) connection. For more information, see <a href="#">Managed SP connection to PingOne for Enterprise and signing certificate</a> on page 671.  |
| <b>Launch PingOne Admin Portal</b>   | Use to access the PingOne admin portal.   |
| <b>Disconnect from PingOne</b>   | <p>Use to disconnect PingFederate from your PingOne account.</p> <p>This is applicable if you have made changes that you should not propagate to your account.</p> <p>For instance, you have two environments, testing and production. The production server is configured with a managed SP connection to , but the test server is not. You have just exported a configuration archive from the production server and imported it to the test server. As soon as the configuration archive is imported, the administrative console prompts you to decide whether to update or to disconnect from . In this example, you should disconnect the test server from so that nothing is uploaded to your account from the test server.</p> |

3. Save your configuration.

### *Configuring PingOne for Enterprise SSO settings*

#### About this task

Use PingOne for Enterprise to enable single sign-on (SSO) and upload configuration changes to your account.

#### Steps

- To enable single sign-on (SSO) through PingOne for Enterprise, click **Identity Repository Configuration**.



#### **Note:**

This is applicable if you have not yet completed the **PingOne SSO** configuration in the past, which would have created a managed service provider (SP) connection to PingOne for Enterprise.

- To upload configuration changes to your PingOne account, go to the **PingOne for Enterprise settings** window and select **Update PingOne Identity Repository**, then confirm your decision.

This is applicable if you have made changes that you should propagate to your account.

For example, you are about to set up a new SAML application on that requires a telephone number of the user. Because the current attribute contract in the managed SP connection does not include an attribute for telephone number, you extend the attribute with a new attribute, `PrimaryTelephone`. After the connection is saved, the administrative console prompts you to decide whether to update or to disconnect from . In this example, you should upload the new configuration to so that the new `PrimaryTelephone` attribute is made available when you set up the new SAML application in .

### *Enabling and configuring the built-in RADIUS server to integrate PingID with your VPN*

#### About this task

Use the **PingID VPN (RADIUS)** configuration wizard to merge PingID with your own VPN.

#### Steps

1. Click **PingID Configuration** to open the **PingID VPN (RADIUS)** configuration wizard.

This is applicable if you have not completed the **PingID VPN (RADIUS)** configuration in the past, which would have created a PingID provisioning connection, an instance of the PingID password credential validator (PCV), or both.

2. Use the wizard to configure the server.

### **Configuring SSO from the PingOne for Enterprise admin portal to the PingFederate administrative console**

You can single sign-on (SSO) to the PingFederate administrative console from PingOne for Enterprise and configure authentication procedures as desired.

#### About this task

In PingFederate 10.1 and later, you can connect to PingOne for Enterprise after the initial PingFederate setup by going to **System # External Systems # Connect to PingOne for Enterprise**.

Additionally, you can continue to sign on to the administrative console through native or alternative console authentication using the direct sign on page. You can also disable the direct sign on page to enforce the policy that administrators must SSO to the administrative console from the PingOne admin portal.

## Steps

- To SSO to the administrative console:
  - a. Start a web browser.
  - b. Browse to the URL `https://<pf_host>:9999/pingfederate/app`, where `<pf_host>` is the network address of your PingFederate server, either an IP address, a host name, or a fully qualified domain name reachable from your computer.

### Result:

If the SSO option is enabled on the **PingOne for Enterprise Settings** window and you have signed on to the PingOne admin portal, the PingFederate administrative console is made available. If you are not signed on to the PingOne admin portal, you are prompted to enter your PingOne admin portal credentials. Upon verification, the PingFederate administrative console is made available.

- To sign on through native or alternative console authentication:
  - a. Start a web browser.
  - b. `<pf_host>:9999/pingfederate/app?service=page/directLogin`, where `<pf_host>` is the network address of your PingFederate server, either an IP address, a host name, or a fully qualified domain name reachable from your computer.
- To disable native and alternative console authentication:
  - a. Edit the `<pf_install>/pingfederate/bin/run.properties` file.
  - b. Change the `pf.console.authentication` property value to `Browse to the URL https://none`.
  - c. Save the change and then restart PingFederate .



### Note:

In a clustered PingFederate environment, you only need to modify the `run.properties` file on the console node.

### Result:

After restart, the direct login page is disabled. Administrators can only SSO to the PingFederate administrative console from the PingOne admin portal at `https://Browse to the URL<pf_host>:9999/pingfederate/app`.

To re-enable native or alternative console authentication, update the `pf.console.authentication` property accordingly and then restart PingFederate.

## Monitoring PingFederate from the PingOne for Enterprise admin portal

After connecting PingFederate to PingOne for Enterprise, you can monitor PingFederate from the PingOne admin portal.

### About this task

The PingOne admin portal displays your PingFederate server (or servers if you have a clustered PingFederate environment) with basic information such as the node index number, the IP address, and the connection status with the date last seen. For each server, you can also collect additional information such as CPU load, Java virtual machine (JVM) memory information, and system memory information.

## Steps

1. Go to **System # External Systems # PingOne for Enterprise Settings**.
2. Optional: If you do not want to monitor PingFederate using the PingOne admin portal, clear the **Enable Monitoring of PingFederate From PingOne** check box and click **Save**.

## Updating the PingOne for Enterprise identity repository

You can upload configuration changes to your connected PingOne for Enterprise account's admin portal or disconnect from your PingOne for Enterprise account if needed.

About this task

After a managed service provider (SP) connection to PingOne for Enterprise admin portal is established, PingFederate monitors configuration changes that can impact the connection, such as updates to the base URL or imports of configuration archives that include managed SP connections to PingOne for Enterprise. When PingFederate detects such changes, the administrative console prompts you to decide whether to update PingOne for Enterprise or to disconnect from PingOne for Enterprise in a banner message.

Steps

Go to **System # External Systems # PingOne for Enterprise settings**.

Choose from:

- To upload configuration changes to your PingOne for Enterprise account, click **Update PingOne Identity Repository**.



### Note:

This is applicable if you have made changes that you should propagate to your account.

For example, you are about to set up a new SAML application on that requires a telephone number of the user. Because the current attribute contract in the managed SP connection does not include an attribute for telephone number, you extend the attribute with a new attribute, `PrimaryTelephone`. After the connection is saved, the administrative console prompts you to decide whether to update or to disconnect from . In this example, you should upload the new configuration to so that the new `PrimaryTelephone` attribute is made available when you set up the new SAML application in .

- To disconnect PingFederate from your PingOne for Enterprise account, click **Disconnect from PingOne**.



### Note:

This is applicable if you have made changes that you should not propagate to your account.

For instance, you have two environments, testing and production. The production server is configured with a managed SP connection to , but the test server is not. You have just exported a configuration archive from the production server and imported it to the test server. As soon as the configuration archive is imported, the administrative console prompts you to decide whether to update or to disconnect from . In this example, you should disconnect the test server from so that nothing is uploaded to your account from the test server.

## Managing CAPTCHA settings

Use PingFederate's functionality to enter and install Google CAPTCHA.

About this task

PingFederate supports invisible reCAPTCHA from Google.

Steps

1. Go to **System # External Systems # CAPTCHA Settings**, and enter the site key assigned to your account by Google.
2. Enter the associated secret key.



3. Click **Save**.

### Managing SMS provider settings

To connect PingFederate to Twilio as an SMS provider through which PingFederate can send text message notifications for self-service password reset requests, enter the required information based on your Twilio account.

#### Steps

1. Go to **System # External Systems # SMS Provider Settings**.
2. Click **Manage SMS Provider Settings**.
3. On the **SMS Provider Settings** window, enter the required information.

| Field              | Description   |
|--------------------|---|
| <b>Account SID</b> | The account number assigned to your account by Twilio.  |
| <b>Auth Token</b>  | The password assigned to your account by Twilio. Used in conjunction with the account number to authenticate with Twilio when PingFederate makes outbound API calls for the purpose of sending text message notifications to the intended recipients. |
| <b>From Number</b> | The sender number in the text message notifications.  |



#### Tip:

For additional information about each field or Twilio, see <http://support.twilio.com>.

4. Click **Save**.

#### Result

After you have saved them, these SMS provider settings apply to all services using text message notifications.

### Managing notification publisher instances

Use PingFederate's functionality to create, edit, review, delete, or set as a default any notification publisher instance.

#### About this task

PingFederate delivers messages to administrators and end users based on notification publisher settings. Depending on your use cases, you can create one or more notification publisher instances. For example, you might select an SMTP notification publisher instance to deliver messages to your end users in an HTML Form Adapter instance, another SMTP notification publisher instance to deliver licensing messages to your fellow administrators, and an Amazon SNS notification publisher instance to deliver messages regarding SAML metadata updates.

## Steps

- Go to **System # External Systems # Notification Publishers**.  
Choose from:
  - To configure a new instance, click **Create New Instance**.
  - To modify an existing instance, select it by its name under **Instance Name**.
  - To review the usage of an existing instance, click **Check Usage** under **Action**.
  - To remove an existing instance or to cancel the removal request, click **Delete** or **Undelete** under **Action**.
  - To make an instance the default notification publisher instance, click **Set as Default** under **Action**.

## Defining a notification publisher instance

Define a notification publisher instance.

## Steps

1. Go to **System # External Systems # Notification Publishers**.
2. Click **Create New Instance**.
3. On the **Type** tab, enter an instance name and an instance ID.
4. From the **Type** list, select the type of the notification publisher instance that you want to use.
5. Click **Next**.

## Notification publisher instance configurations

You can configure a notification publisher instance based on its type.

This configuration varies depending on the type of the notification publisher.

For specific configuration steps, see the following topics..

- [Configuring an Amazon SNS Notification Publisher instance](#) on page 1010
- [Configuring an SMTP Notification Publisher instance](#) on page 1015

### *Configuring an Amazon SNS Notification Publisher instance*

Create and configure an Amazon SNS notification publisher instance to help subscribers effectively direct their messages to their intended audiences.

## About this task

When using an Amazon SNS notification publisher, PingFederate is the publisher, and the intended recipients are the subscribers. Topics are the destinations to which PingFederate publishes messages. When configuring an Amazon SNS notification publisher instance, you must specify an Amazon SNS topic.

For more information about Amazon SNS and topic management, see the AWS documentation on <https://docs.aws.amazon.com/sns/latest/dg/welcome.html>.

## Steps

1. On the **Instance Configuration** tab, configure the notification publisher instance as follows.

| Field                | Description  |
|----------------------|--|
| <b>SNS Topic ARN</b> | The Amazon Resource Name (ARN) topic to which PingFederate publishes messages. Enter an ARN in the following format.<br><br>arn:aws:[service]:[region]:[accountid]:[resourceType/resourcePath] |

| Field                   | Description   |
|-------------------------|---|
| <b>Max Payload Size</b> | The maximum payload size in kilobytes. Enter a value between 1 and 8192.<br><br>Click <b>Show Advanced Fields</b> to reveal this field. The default value is 256. |

2. Click **Next** to view the **Summary** tab, and then click **Save**.

## Result

PingFederate categorizes notification messages into various event types. Each event type comes with a set of relevant information to help subscribers craft the final message for the intended audience.

## Event types and variables

This lists the various event types and their respective keys (variables) used within the PingFederate Amazon SNS notification publisher instance configuration.

## Message payload

As a publisher, PingFederate creates notification messages in JSON format and sends them to the configured topic. This JSON message body contains two top-level keys: **data** and **configuration**, as illustrated in the following snippet.

```
{
  "data": {
    "USERNAME": "jdoe",
    ...
  },
  "configuration": {
    "com.pingidentity.notification.config.locale": "en-US",
    ...
    "com.pingidentity.notification.config.event.type":
    "ADMIN_PASSWORD_CHANGED"
  }
}
```

For all events, PingFederate provides relevant information by including various *key:value* pairs in the message body, located inside the value of the **data** key.


The value of the **com.pingidentity.notification.config.event.type** key, located inside the value of the **configuration** key, indicates the event type. In this example, the event type is **ADMIN\_PASSWORD\_CHANGED**.

For end user-oriented events, the value of the **com.pingidentity.notification.config.locale** key, also located inside the value of the **configuration** key, indicates the locale of the end user who initiates the request.

Review the following sections for more information on event types and their respective keys, which are referred to as variables.

## Events for administrators

### Local administrative account management events

| Event type                            | Variables   |
|---------------------------------------|---|
| ADMIN_ACCOUNT_CHANGE_NOTIFICATION_OFF | <ul style="list-style-type: none"> <li>• <b>USERNAME</b> represents the username of the local administrative account who has turned off the <b>Notify Administrator of Account Changes</b> option.</li> <li>• <b>RECEIVER</b> represents the email addresses of all the local administrative accounts configured with an email address.</li> <li>• <b>NOTIFY</b> represents the <b>Notify Administrator of Account Change</b> option on the <b>Administrative Accounts</b> window.</li> <li>• <b>CURRENT_USER_MESSAGE</b> represents the username of the administrator who initiated the change.</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;">  <b>Note:</b><br/>           Unless otherwise noted, the rest of the variables in the <b>Administrative Accounts</b> section are either self-explanatory or identical to those mentioned here.         </div> |
| ADMIN_EMAIL_CHANGED                   | <ul style="list-style-type: none"> <li>• <b>USERNAME</b></li> <li>• <b>RECEIVER</b></li> <li>• <b>DEPARTMENT</b></li> <li>• <b>DESCRIPTION</b></li> <li>• <b>PHONE_NUMBER</b></li> <li>• <b>CURRENT_USER_MESSAGE</b></li> </ul> <p>PingFederate sends two messages for this event type. Variables and their values remain the same, except for the <b>RECEIVER</b> value. They are intended to notify the end user at both the previous email address and the new email address.</p>  |
| ADMIN_PASSWORD_CHANGED                | <ul style="list-style-type: none"> <li>• <b>USERNAME</b></li> <li>• <b>RECEIVER</b></li> <li>• <b>DEPARTMENT</b></li> <li>• <b>DESCRIPTION</b></li> <li>• <b>PHONE_NUMBER</b></li> <li>• <b>CURRENT_USER_MESSAGE</b></li> </ul>   |

Certificate, SAML metadata update, and licensing events


| Event type  | Variables   |
|---|---|
| CERTIFICATE_EVENT_ACTIVATED<br>and<br>CERTIFICATE_EVENT_CREATED | <ul style="list-style-type: none"> <li>• <b>SERIAL_NUMBER</b></li> <li>• <b>SUBJECT_DN</b></li> <li>• <b>EX_DATE</b></li> <li>• <b>PENDING_CERT_SERIAL_NUM</b></li> <li>• <b>PENDING_EX_DATE</b></li> <li>• <b>ACTIVE_CONNECTIONS</b> represents the connections impacted by the creation of the pending certificate and the activation of it.</li> <li>• <b>ACTIVATION_DATE</b></li> </ul> |

| Event type  | Variables  |
|---|--|
| CERTIFICATE_EVENT_EXPIRED,<br>and<br>CERTIFICATE_EVENT_INITIAL_WARN   | <ul style="list-style-type: none"> <li>▪ <b>SERIAL_NUMBER</b></li> <li>▪ <b>SUBJECT_DN</b></li> <li>▪ <b>EX_DATE</b></li> <li>▪ <b>EX_TYPE</b></li> <li>▪ <b>CONN_NAME</b> represents the connection impacted by any of the three certificate expiration events.</li> <li>▪ <b>DAYS_LEFT</b></li> <li>▪ <b>ACTION</b></li> </ul> |
| SAML_METADATA_UPDATE_EVENT_ENTITY_ID_NOT_FOUND  | <ul style="list-style-type: none"> <li>▪ <b>ENTITY_ID</b></li> <li>▪ <b>CONNECTION_NAME</b></li> <li>▪ <b>METADATA_URL</b></li> <li>▪ <b>METADATA_URL_NAME</b></li> </ul>  |
| SAML_METADATA_UPDATE_EVENT_FAILED   | <ul style="list-style-type: none"> <li>▪ <b>METADATA_URL</b></li> <li>▪ <b>METADATA_URL_NAME</b></li> </ul>  |
| SAML_METADATA_UPDATE_EVENT_UPDATED  | <ul style="list-style-type: none"> <li>▪ <b>ENTITY_ID</b></li> <li>▪ <b>CONNECTION_NAME</b></li> <li>▪ <b>METADATA_URL</b></li> <li>▪ <b>UPDATED</b> represents any updated connection settings.</li> <li>▪ <b>OUT_OF_SYNC</b> represents any out-of-sync connection settings.</li> </ul>  |
| SERVER_LICENSING_EVENT_WARNING,<br>and<br>SERVER_LICENSING_EVENT_EXPIRED,<br>and<br>SERVER_LICENSING_EVENT_SHUTDOWN | <ul style="list-style-type: none"> <li>▪ <b>EX_DATE</b></li> <li>▪ <b>DAYS_LEFT</b></li> </ul>   |

Events for end users

Self-service password management, account recovery, and username recovery

| Event type       | Variables  |
|------------------|--|
| ACCOUNT_UNLOCKED | <ul style="list-style-type: none"> <li>▪ <b>USERNAME</b> represents the user name of the end user where the request is made.</li> <li>▪ <b>RECEIVER</b> represents the email address of the end user where the request is made.</li> <li>▪ <b>ADAPTER_ID</b> represents the <b>Instance ID</b> of the invoking HTML Form Adapter instance.</li> <li>▪ <b>PCV_ID</b> represents the <b>Instance ID</b> of the Password Credential Validator (PCV) instance involved.</li> </ul> |

 **Note:**

Unless otherwise noted, the rest of the variables in the HTML Form Adapter instances section are either self-explanatory or identical to those mentioned here.

| Event type  | Variables   |
|---|---|
| PASSWORD_CHANGED  | <ul style="list-style-type: none"> <li>▪ GIVEN_NAME</li> <li>▪ USERNAME</li> <li>▪ RECEIVER</li> <li>▪ ADAPTER_ID</li> <li>▪ PCV_ID</li> </ul>  |
| PASSWORD_RESET  | <ul style="list-style-type: none"> <li>▪ USERNAME</li> <li>▪ RECEIVER</li> <li>▪ ADAPTER_ID</li> <li>▪ PCV_ID</li> <li>▪ STATUS</li> </ul>  |
| PASSWORD_RESET_FAILED   | <ul style="list-style-type: none"> <li>▪ USERNAME</li> <li>▪ RECEIVER</li> <li>▪ ADAPTER_ID</li> <li>▪ PCV_ID</li> </ul>  |
| PASSWORD_RESET_ONE_TIME_CODE<br>and<br>PASSWORD_RESET_ONE_TIME_LINK | <ul style="list-style-type: none"> <li>▪ USERNAME</li> <li>▪ RECEIVER</li> <li>▪ ADAPTER_ID</li> <li>▪ PCV_ID</li> <li>▪ CODE represents the one-time code or hyperlink that the end user can use to reset the password associated with the account.</li> </ul> |
| USERNAME_RECOVERY   | <ul style="list-style-type: none"> <li>▪ USERNAME</li> <li>▪ RECEIVER</li> <li>▪ ADAPTER_ID</li> <li>▪ PCV_ID</li> <li>▪ DISPLAY_NAME</li> </ul>  |

## Customer IAM email ownership verification

| Event type                           | Variables   |
|--------------------------------------|---|
| OWNERSHIP_VERIFICATION_ONE_TIME_LINK | <ul style="list-style-type: none"> <li>▪ USERNAME represents the user name of the end user who should receive an email ownership verification request.</li> <li>▪ RECEIVER represents the email address to which the email ownership verification request is sent.</li> <li>▪ CODE represents the one-time hyperlink that the end user can use to verify the ownership of the email address associated with the account.</li> </ul> |

*Configuring an SMTP Notification Publisher instance*


Set up an instance of the SMTP Notification Publisher for PingFederate to notify administrators and end users about various events. You can configure multiple instances, each with different settings as needed.

## Steps

1. On the **Instance Configuration** tab, provide the required information or update any default or previously configured setting values.

For more information about each field, refer to the following table.

| Field   | Description   |
|---|---|
| <b>From Address</b><br>(Required)   | The email address that appears in the "From" header line in email messages generated by PingFederate. The address needs a valid format but does not need to be set up on your system.   |
| <b>Email Server</b><br>(Required)   | The IP address or host name of your email server.   |
| <b>SMTP Port</b>  | The SMTP port on your email server.<br>The default value is 25.   |
| <b>Encryption Method</b>  | Select <b>SSL/TLS</b> to establish a secure connection to the email server at the SMTPS port.<br><br>Select <b>STARTTLS</b> to establish an unencrypted connection to the email server at the SMTP port and initiate a secure channel afterward.<br><br>Select <b>None</b> , the default value, to establish an unencrypted connection to the email server at the SMTP port.                |
| <b>SMTPS Port</b>   | The secure SMTP port on your email server. Not applicable unless <b>SSL/TLS</b> is the chosen encryption method.<br>The default value is 465.   |
| <b>Verify Hostname</b>  | Indicates whether to verify the host name of the email server matches the <b>Subject (CN)</b> or one of the <b>Subject Alternative Names</b> from the certificate. Not applicable unless either <b>SSL/TLS</b> or <b>STARTTLS</b> is the chosen encryption method.<br><br>This check box is selected by default.  |
| <b>UTF-8 Message Header Support</b>   | Indicates whether the email server supports UTF-8 encoding in message headers; for example, in the recipient email address. Enable this option only if your email server supports this feature.<br><br>With this option enabled, PingFederate supports UTF-8 characters in the sender and recipient email addresses. It does not support Emojis in the domain portion of the email address. |
| <b>Username</b>   | Authorized email account.   |
| <b>Password</b>   | Password for the authorized email account.  |
| <b>Test Address</b>   | Enter an email address PingFederate should use to verify connectivity with the configured email server.   |
| Click <b>Show Advanced Fields</b> to review the following settings. Modify as needed. |   |

| Field                                 | Description  |
|---------------------------------------|--|
| <b>Connection Timeout</b>             | The amount of time in seconds that PingFederate waits before it times out connecting to the SMTP server.<br><br>The default value is 30.   |
| <b>Enable SMTP Debugging Messages</b> | Turns on detailed error messages for the PingFederate server log to help troubleshoot SMTP issues.   |
|                                       |  <b>CAUTION:</b><br><br>This setting is disabled by default. When enabled, PingFederate logs email messages, which can contain sensitive information, to the server log. Consider enabling debug messages solely for troubleshooting purposes and disabling this option when debug messages are no longer required. |

2. Click **Next**.

#### Next steps

You can modify email-notification template files to suit the particular branding requirements. For more information, see [Customizable email notifications](#) on page 882.

#### *Finalizing actions for a notification publisher instance*

Finish any required tasks presented to you on the **Actions** tab to complete configuration for your notification publisher instance.

#### About this task



#### Note:

Depending on the data store implementation, configuration requirements vary. If no action is required, the **Actions** tab is not shown.

#### Steps

- On the **Actions** tab, perform any required tasks, and click **Next**.

#### *Reviewing a notification publisher instance configuration*

On the **Summary** tab, review your configuration.

#### Steps

Perform the following actions as needed.

| Action                          | How to accomplish it  |
|---------------------------------|---|
| <b>Amend your configuration</b> | Click the corresponding tab and follow the configuration workflow |
| <b>Keep your changes</b>        | Click <b>Done</b> and continue with the configuration             |
| <b>Discard your changes</b>     | Click <b>Cancel</b>   |

#### Result

Once set up and saved, you can select this notification publisher instance in any component that is capable of triggering or handling events.



## Secret managers

If you have a third-party secret management system (secret manager), you can configure instances of the PingFederate secret manager plugin, and use the instances to generate reference codes for your secret manager's contents.

In the secret manager, you can store the passwords and other credentials that PingFederate needs to access LDAP, JDBC, and REST API datastores. If you have a secret manager, you can integrate it with PingFederate and then configure one or more instances of the secret manager plugin. After using an instance to generate a reference code for a specific datastore credential in the secret manager, you can add the reference code to a PingFederate datastore plugin instance, allowing PingFederate to get the credential from your secret manager.

Storing datastore credentials in a secret manager is not only secure, it also lets you change the credentials in the secret manager without needing to change the configuration of the datastore plugins because the credential reference codes do not change. This is particularly useful when you rotate credentials.

You can [integrate PingFederate with the CyberArk Credential Provider](#) out-of-the-box. If you have a different secret manager, you can use the SecretManager interface in the [PingFederate SDK](#) to build a custom solution that connects PingFederate to your secret manager.

## Integrating with the CyberArk Credential Provider

You can integrate PingFederate out-of-the-box with the CyberArk Credential Provider, an external secret management system (secret manager).

Before you begin

Install the Credential Provider and note the path to the CyberArk Java Application Password SDK file. The CyberArk website provides more information about the [CyberArk Credential Provider](#) and how to install it.


About this task

The [Credential Provider supports the following authentication methods](#): allowed machines, OS user, path, and hash.



### Note:

Whenever you upgrade the CyberArk Credential Provider installation, replace the CyberArk Java Application Password SDK file with the latest version.



To integrate PingFederate with the CyberArk Credential Provider:

#### Steps

1. Copy the CyberArk Java Application Password SDK file to the `<pf_install>/pingfederate/server/default/deploy/` directory:
  - In Windows environments, copy the `JavaPasswordSDK.jar` file.
  - In Linux environments, copy the `javapasswordsdk.jar` file.
2. Restart the PingFederate server.

#### Next steps

After integrating PingFederate with the CyberArk Credential Provider, you can:

- [Configure instances of the secret manager](#) in PingFederate.
- Configure authentication methods between the CyberArk Credential Provider and its CyberArk Vault. For more information, see [CyberArk's authentication methods](#) on page 1018.

#### CyberArk's authentication methods

CyberArk administrators can configure one or more authentication methods between the CyberArk Credential Provider and its Vault.

The Credential Provider supports any combination of the following authentication methods:

- Hash
- OS user
- Allowed machines
- Path

For information about CyberArk's authentication methods, see [Application authentication methods](#) in the CyberArk documentation.

The following sections provide additional information specific to using the hash authentication method and OS user authentication method with PingFederate.

#### Hash authentication method

For information about using the hash authentication method, see [Authenticate with a hash value](#) in the CyberArk documentation.



#### Important:

The hash changes when you perform a major or minor upgrade, or a maintenance update, of PingFederate. So you must regenerate the hash after an upgrade or update, otherwise PingFederate won't be able to retrieve credentials from CyberArk.

The following syntax and examples show how to use CyberArk's aimgetappinfo utility to generate a hash in Linux and Windows environments.

#### Linux syntax

```
aimgetappinfo GetHash -FilePath "<path to>/pf-core-plugins.jar"
```

#### Linux example command and its output

```
/opt/CARKaim/bin$ ./aimgetappinfo GetHash
-FilePath "/home/imok/Downloads/pingfederate-11.0.0/pingfederate/server/
default/lib/pf-core-plugins.jar"
<generated hash>
Command ended successfully
```

#### Windows syntax

```
AIMGetAppInfo GetHash /FilePath "<path to>\pf-core-plugins.jar"
```

#### Windows example command and its output

```
C:\Program Files (x86)\CyberArk\ApplicationPasswordProvider
\Utils>AIMGetAppInfo GetHash
/FilePath "C:\Users\Administrator\Downloads
\pingfederate-11.0.0\pingfederate\server\default\lib\pf-core-plugins.jar"
<generated hash>
Command ended successfully
```

#### OS user authentication method

For information about the OS user authentication method, see [OS user authentication](#) in the CyberArk documentation.



#### Note:

In a Windows environment, if the PingFederate Windows service is installed or configured with Log On As: Local System, the CyberArk admin must enter NT AUTHORITY\SYSTEM as the OS user entry.

## Configuring instances of the secret manager plugin for the CyberArk Credential Provider

To give PingFederate access to datastore credentials stored in your CyberArk Credential Provider, configure an instance of the CyberArk Credential Provider secret manager plugin.

Before you begin

Install the CyberArk Credential Provider and integrate it with PingFederate. For more information, see [Integrating with the CyberArk Credential Provider](#) on page 1017.



### Note:

When configuring instances of the secret manager plugin, you need information about your secret manager's configuration. You also need information about the contents of your secret manager to generate reference codes for its contents.

About this task

To configure an instance of the secret manager plugin that provides access to the CyberArk Credential Provider:

Steps

1. In the PingFederate administrative console, go to **System # External Systems # Secret Managers**.  
Result:  
The **Secret Managers** window opens.
2. Click **Create New Instance**.  
Result:  
The **Create Secret Manager Instance** window opens.
3. Configure the **Type** tab settings:
  - a. Enter an **Instance Name** and a unique **Instance ID**.
  - b. In the **Type** menu, select **CyberArk Credential Provider**.
  - c. Optional: To make this new secret manager instance the child of an existing instance, select the **Parent Instance**.
4. Configure the **Instance Configuration** tab according to the settings of your CyberArk Credential Provider.  
  
The **App ID** is the unique ID of the PingFederate application configured in the CyberArk Credential Provider.

5. Optional: On the **Actions** tab, verify that you can generate a valid reference code for a credential stored in the CyberArk Credential Provider:

- a. In the **Generate** section, enter each **Parameter Value** that PingFederate needs to retrieve a specific secret.

The values depend on the name and location of the secret in the CyberArk Credential Provider. Optionally, you can specify in the reference code that PingFederate will also retrieve the username for the datastore account.

- b. Click **Generate**.

Result:

PingFederate generates and displays the secret's reference code. The code is composed of obfuscation prefix `OBF:MGR`, the plugin instance's ID, and the parameters you specify on this tab.

- c. Copy the reference code.
- d. In the **Validate** section, paste the code into the **Secret Reference** field.
- e. Click **Validate**.

Result:

PingFederate uses the reference code to request the secret from the CyberArk Credential Provider and then displays whether the request succeeded.



**Tip:**

To clear the fields and the generated reference code on the **Actions** tab, click **Reset**.

6. On the **Summary** tab, review the settings. Then, if needed, change the settings on the previous tabs.
7. Click **Save**.

Result:

The **Secret Managers** window opens, showing the new instance in the table.

#### Next steps

After configuring an instance of the secret manager plugin, use it to generate a reference code for a specific password in the CyberArk Credential Provider. Then you can add the reference code to the following places in PingFederate:

- An instance of a datastore plugin for an LDAP directory, JDBC database, or REST API. For more information, see [Using passwords in secret managers to access datastores](#) on page 1021.
- The `ldap.properties` file, `oauth2.properties` file, and the `oidc.properties` file.

#### Using passwords in secret managers to access datastores

You can configure instances of PingFederate's datastore plugins to retrieve datastore account passwords that are stored in an external secret management system (secret manager).

#### Before you begin

Before performing this task, you must:

- Install the CyberArk Credential Manager or another secret manager
- Integrate the secret manager with PingFederate
- Add the datastore passwords to the secret manager
- Configure an instance of PingFederate's secret manager plugin to access the secret manager

#### About this task

Instead of storing passwords for LDAP directories, JDBC databases, and REST API datastores in PingFederate, you can securely store the passwords in a secret manager for maintaining passwords and

other secrets. When PingFederate needs to access a datastore, it uses a reference code to request the password from the secret manager. However, before that can happen, you must generate a reference code for the datastore password and add it to the datastore plugin instance.

To generate a reference code for a datastore password and add it to a datastore plugin instance:

#### Steps

1. Use an instance of the secret manager plugin to generate a reference code for the datastore's password:
  - a. In the PingFederate administrative console, go to **System # External Systems # Secret Managers**.  
Result:  
The **Secret Managers** window opens.
  - b. Click the name of the secret manager plugin instance.  
Result:  
The **Secret Manager** window opens.
  - c. Go to the **Actions** tab.
  - d. In the **Generate** section, enter each **Parameter Value** that PingFederate needs to retrieve the datastore password.  
The values depend on the name and location of the password in the CyberArk Credential Provider. Optionally, you can specify in the reference code that PingFederate will also retrieve the username for the datastore account.
  - e. Click **Generate**.  
Result:  
PingFederate generates and displays the password's reference code. The code is composed of obfuscation code `OBF:MGR`, the plugin instance's ID, and the parameters you specify on this tab.
  - f. Copy the reference code.
  - g. Optional: To verify that PingFederate can use the reference code to retrieve a password, paste the code into the **Secret Reference** field. Then click **Validate**.  
Result:  
PingFederate requests the password from the CyberArk Credential Provider and then displays whether the request succeeded.
2. Add the password's reference code to the datastore plugin instance using one of the following methods, depending on whether the plugin is for an LDAP directory, JDBC database, or REST API datastore:  
Choose from:
  - For an LDAP directory, go to the plugin instance's **LDAP Configuration** tab, set **Credential Storage** to **Secret Manager**, and enter the **Password Reference** code that you generated above.
  - For a JDBC database, go to the plugin instance's **Database Config** tab, set **Credential Storage** to **Secret Manager**, and enter the **Password Reference** code that you generated above.
  - For a REST API datastore, go to the plugin instance's **Configure Data Store Instance** tab, and enter the **Password Reference** code that you generated above.

If you configured the reference code with **Retrieve Username** enabled, PingFederate will ignore the username defined in the datastore plugin instance.

## Configuring general settings

The **General Settings** window lets you change some of the general system-wide settings for your PingFederate servers.

About this task

The settings in this window are independent of one another.

Steps

1. Go to **System # Server # General Settings**.
2. Change any of the following settings:
  - To turn off automatic multi-connection error checking, select the **Disable Automatic Connection Validation** check box. This check box is not selected by default.
  - To override the verbosity of runtime transaction logging for all identity provider connections, select an option on the **IdP Connection Transaction Logging Override** menu. The default setting is **Don't Override**.
  - To override the verbosity of runtime transaction logging for all service provider connections, select an option on the **SP Connection Transaction Logging Override** menu. The default setting is **Don't Override**.
  - To fine tune the caching interval for datastore validation, change the number of seconds in the **Data-Store Validation Interval** field. A value of 0 turns off the caching and validation tests are executed with each access. The default value is 300 seconds (five minutes). This setting applies to all datastores.

 **Note:**

As you configure components on the administrative console, PingFederate performs connectivity tests against the applicable datastores. By default, PingFederate saves successful test results for five minutes. This design improves the performance of the administrative console by reducing the number of calls it makes to the target servers and the amount of time it takes to move from one configuration window to another.

- To let PingFederate use the value of a specific request header for the request ID instead of generating a request ID, enter the name of the request header in the **Request Header for Correlation ID** field. By default, the field is empty.

 **Note:**

When a PingFederate endpoint receives HTTP requests, it records request IDs at the DEBUG level of the server log. When the **Request Header for Correlation ID** field specifies a request header, if a PingFederate endpoint receives a request that includes that header, and if the header's value contains 1 to 50 alphanumeric characters and hyphens, then PingFederate uses that value for the request ID. Otherwise, PingFederate uses a unique value that it generates for the request ID.

If the request causes PingFederate to send an LDAP call to PingDirectory, PingFederate includes the request ID in the LDAP call. For auditing and troubleshooting, you can correlate the request ID in the PingFederate log with the request ID in the PingDirectory log. For more information, see [Correlating PingFederate events with PingDirectory LDAP activities](#) on page 1034.

3. Save the changes.

## Troubleshooting

Basic troubleshooting tips are provided here to help you overcome common difficulties with PingFederate.

- [Enabling debug messages and console logging](#)
- [Resolving startup issues](#)
- [Troubleshooting data store issues](#)
- [Resolving URL-related errors](#)
- [Resolving service-related errors](#)
- [Troubleshooting authentication policy issues](#)
- [Troubleshooting registration and profile management issues](#)
- [Troubleshooting runtime errors](#)
- [Troubleshooting OAuth transactions](#)
- [Other runtime issues](#)
- [Collecting support data](#)

Help is also available from the [Support Center](#).

### Enabling debug messages and console logging

Make changes to the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file to enable debug messages and console logging.

About this task

For troubleshooting purposes, you can adjust the log level to `DEBUG` in the `log4j2.xml` file and re-enable console logging.



#### Important:

When you no longer require debug messages and console logging, turn them off. On Windows, never highlight the console output because it might slow or stop from processing requests.

#### Steps

1. Edit the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.
  - a. To enable verbose messages, look for `Limit` categories inside the `Loggers` element, particularly the five logger names shown in bold in the following snippet.

```

...
<Loggers>

  <!-- ===== -->
  <!-- Limit categories -->
  <!-- ===== -->

  ...
  <Logger name="org.sourceid" level="INFO" />
  <Logger name="org.sourceid.saml20.util.SystemUtil" level="INFO"
additivity="false">
    <AppenderRef ref="CONSOLE" />
    <AppenderRef ref="FILE" />
  </Logger>
  ...
  <Logger name="com.pingidentity" level="INFO" />
  <Logger name="com.pingidentity.common.util.ErrorHandler" level="INFO"
additivity="false">

```



```

        <AppenderRef ref="CONSOLE" />
        <AppenderRef ref="FILE" />
    </Logger>
    ...
    <Logger name="com.pingidentity.appserver.jetty.PingFederateInit"
level="INFO" additivity="false" includeLocation="false">
        <AppenderRef ref="FILE" />
    </Logger>
    ...
</Loggers>
...

```

Then update the five loggers as shown in bold in the following snippet.

```

...
<Loggers>

    <!-- ===== -->
    <!-- Limit categories -->
    <!-- ===== -->

    ...
    <Logger name="org.sourceid" level="DEBUG" />
    <Logger name="org.sourceid.saml20.util.SystemUtil" level="DEBUG"
additivity="false">
        <AppenderRef ref="CONSOLE" />
        <AppenderRef ref="FILE" />
    </Logger>
    ...
    <Logger name="com.pingidentity" level="DEBUG" />
    <Logger name="com.pingidentity.common.util.ErrorHandler"
level="DEBUG" additivity="false">
        <AppenderRef ref="CONSOLE" />
        <AppenderRef ref="FILE" />
    </Logger>
    ...
    <Logger name="com.pingidentity.appserver.jetty.PingFederateInit"
level="INFO" additivity="false" includeLocation="false">
        <AppenderRef ref="FILE" />
        <AppenderRef ref="CONSOLE" />
    </Logger>
    ...
</Loggers>
...

```

 **Note:**

In this snippet, console logging is enabled for loggers  
org.sourceid.saml20.util.SystemUtil,

`com.pingidentity.common.util.ErrorHandler`, and  
`com.pingidentity.appserver.jetty.PingFederateInit`.

Console logging can be resource intensive. If you do not require console logging or prefer to review the server log instead, comment out the `<AppenderRef ref="CONSOLE" />` entry for these three loggers.



**Tip:**

As needed, you can update the log level for other loggers.

- b. To enable console logging, look for the `Set up the Root logger` section as shown in the following example.

```
...
<!-- ===== -->
<!-- Set up the Root logger -->
<!-- ===== -->
...
<AsyncRoot level="INFO" includeLocation="false">
  <!-- <AppenderRef ref="CONSOLE" /> -->
  <AppenderRef ref="FILE" />
</AsyncRoot>
```

Then, update as shown in bold in the following snippet.

```
...
<!-- ===== -->
<!-- Set up the Root logger -->
<!-- ===== -->
...
<AsyncRoot level="INFO" includeLocation="false">
  <AppenderRef ref="CONSOLE" />
  <AppenderRef ref="FILE" />
</AsyncRoot>
```



**Important:**

When you no longer require console logging, comment out the `<AppenderRef ref="CONSOLE" />` entry for the `AsyncRoot` logger.

2. Save any changes made.
3. In a clustered PingFederate environment, repeat these steps on each applicable node.

### Result

Changes, such as adding a `Logger` or adjusting log levels, are activated within half a minute. You do not need to restart .

## Resolving startup issues

Resolve PingFederate startup issues related to Java runtime and the license file installs.

### PingFederate startup problems and solutions

| Problem   | Solution   |
|---|--|
| PingFederate does not start.  | Make sure that a supported Java runtime is installed. For more information, see <a href="#">Installing Java</a> on page 129. |
| The server starts but indicates the license file is not found or invalid. | Ensure a current license is installed. For more information, see <a href="#">Reviewing license information</a> on page 919.  |

## Troubleshooting data store issues

Resolve PingFederate data store issues related to failing to establish a connection to a data store and directory.

### Data store connection problems and solutions

| Problem  | Solution   |
|--|--|
| When setting up the JDBC data store, a connection cannot be established. | <p>Verify that the proper drivers and connectors have been installed.</p> <p>Also, verify the connection URL, user name, and password. If unsuccessful, contact your database administrator.</p> <p>For more information, see <a href="#">Configuring a JDBC connection</a> on page 938.</p>   |
| Cannot connect to a Directory Service with the LDAP protocol.            | <p>Verify the connection URL, port, principal, and credentials. If unsuccessful, contact your system administrator. For more information, see <a href="#">Configuring an LDAP connection</a> on page 942.</p> <p>If using LDAPS, ensure the LDAP server's SSL certificate is signed by a trusted certificate authority or is imported into PingFederate. For more information, see <a href="#">Manage trusted certificate authorities</a> on page 657.</p> |

## Resolving URL-related errors

Review and update the URL of the identity provider (IdP) initiated single sign-on to resolve the `404 Not Found` and `System Error` error messages.

If a user encounters a `404 Not Found` status or a `System Error` message, check the URL of the request.

Example

Examples

404 Not Found

`https://sso.idp.local/idp/startSSO.ping&PartnerSpId=sp1&TargetResource=https%3A%2F%2Fapp.sp1.local%2F` causes a `404 Not Found` error, because the separator between the path of the URL and the first query parameter is incorrect. The correct separator is a question mark `?` and not an ampersand `&`.

System Error

`https://sso.idp.local/idp/startSSO.ping?PartnerSpId=sp1?TargetResource=https%3A%2F%2Fapp.sp1.local%2F` causes a `System Error` message, because the second query parameter separators are incorrect. The correct separator is an ampersand `&` and not a question mark `?`.

 **Tip:**

You must also use ampersands for all subsequent separators between additional query parameters in the URL.

In addition, you must URL-encode query parameter values that contain restricted characters. For information about URL encoding, see, for example, [HTML URL-encoding Reference](#).

For both sample issues, update the URL of the IdP-initiated single sign-on (SSO) to the following URL.

`https://sso.idp.local/idp/startSSO.ping?PartnerSpId=sp1&TargetResource=https%3A%2F%2Fapp.sp1.local%2F`

## Resolving service-related errors

Resolve the `Unexpected System Error` message and `partner not active status`.

If a user encounters an `Unexpected System Error` message with a reference code, ask the user for the reference code and search for the value in the server log. The log message should help determine the root cause, which usually requires a configuration change.

If a user encounters a `partner not active status`, select `Active` in the **Connection Status** section and click **Save** on the **Activation & Summary** window for the connection.

Example

Example

### Unexpected System Error

When a PingFederate identity provider (IdP) server receives a SAML AuthnRequest message through the redirect binding, but such SAML profile is not selected in the applicable service provider (SP) connection, PingFederate replies with an `Unexpected System Error` response with a reference code and logs an error message similar to the following entry.

```
2015-12-03 15:43:52,936 ERROR [org.sourceid.servlet.ErrorServlet]
Top level error (ref#kwlqbn): javax.servlet.ServletException:
org.sourceid.saml20.bindings.BindingException: Incoming binding
urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect is not enabled for
(SP) ::: sp1
```

 **Tip:**

In this sample log message, `kwlqbn` is the reference code.

### Solution

Update the applicable SP connection to allow the Redirect binding for inbound messages from the SP. This works if the redirect binding is one of the mutually-agreed SAML bindings that both parties use. Alternatively, the SP can send SAML AuthnRequest messages through an allowable SAML binding based on the configuration of your SP connection.

## Troubleshooting authentication policy issues

Authentication policies, an optional configuration in PingFederate, help implement complex authentication requirements. Having a complex policy or multiple policies can result in unintended runtime behaviors. The `org.sourceid.util.log.PolicyTreeLogger` logger makes it easier to troubleshoot such issues.

### About this task

Identify and resolve authentication policy issues.

### Steps

1. Enable debug messages for the `org.sourceid.util.log.PolicyTreeLogger` class.



#### Tip:

If you have enabled debug messages for the `org.sourceid` logger, you have already enabled debug messages for the `org.sourceid.util.log.PolicyTreeLogger` class. Skip to step 3.

- a. Edit the `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file.
- b. Look for `Limit` categories inside the `Loggers` element, as shown in bold in the following example.

```

...
<Loggers>

    <!-- ===== -->
    <!-- Limit categories -->
    <!-- ===== -->

    ...
    <!--
    <Logger name="org.sourceid.util.log.PolicyTreeLogger" level="DEBUG" />
    -->
    ...
</Loggers>
...

```

- c. Uncomment the `org.sourceid.util.log.PolicyTreeLogger` logger, as shown in the following example. Note that the `<!--` and `-->` markers have been removed.

Example:

```

...
<Loggers>

    <!-- ===== -->
    <!-- Limit categories -->
    <!-- ===== -->

    ...

    <Logger name="org.sourceid.util.log.PolicyTreeLogger" level="DEBUG" />

    ...
</Loggers>
...

```

This change is activated within a minute. No restart of PingFederate is required.

2. Save any changes made.

For a clustered PingFederate environment, repeat these steps on each applicable node.

- Repeat the request that demonstrates the authentication policy issue.

**Tip:**

It is most useful to initiate this request in a browser without any cookies from prior sessions.

- After you have replicated the issue, correlate server log messages using the PF cookie and tracking ID values. For more information, see [Troubleshooting runtime errors](#).

Look for `DEBUG` messages from the `org.sourceid.util.log.PolicyTreeLogger` class.

Example:

For example, suppose the tracking ID value is `wXzQbS8MfHG40wpsQPiREIenJjc` for a given request. The following server log messages demonstrate the authentication flow.

```
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Selector | generalClients | Yes
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | idFirst
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | idFirst
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | idFirst | Rule | Alpha
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | idFirst | Alpha
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | https://sso.alpha.local:8031
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Authn Policy Tree setting
User ID from attribute 'subject' from Source type 'Adapter' and source
ID 'idFirst'
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authn Source | https://sso.alpha.local:8031 | Success
DEBUG [org.sourceid.util.log.PolicyTreeLogger] Policy 'General clients
policy' | Authentication Policy Contract | APC | Finished
```

**Note:**

For readability, this sample ignores the time stamp and the tracking ID information. In other troubleshooting scenarios, such information can be valuable.

Log messages are interpreted as follows:


- PingFederate finds an applicable policy named `General clients policy`. The first checkpoint is an OAuth Client Set Authentication Selector instance `generalClients`. PingFederate routes this request to the `Yes` policy path because the client that submits the authorization request matches one of the clients defined authentication selector instance.
- PingFederate routes this request to an instance of the Identity First Adapter `idFirst` because that adapter instance is the next authentication source of the `Yes` policy path.
- Based on the user's provided user identifier, PingFederate determines that the `Alpha` rule applies and routes this request to the `Alpha` policy path.
- PingFederate routes this request to an identity provider (IdP) connection `https://sso.alpha.local:8031` because that IdP connection is the next authentication source of the `Alpha` policy path. PingFederate also populates the `subject` attribute in the `AuthnRequest` message with the user identifier obtained from the Identity First Adapter instance.
- PingFederate receives a valid security token from the IdP `https://sso.alpha.local:8031`. PingFederate routes the request to the `Success` policy path, which ends with an authentication policy contract `APC` and concludes the authentication flow.

## Troubleshooting registration and profile management issues

Certain browser extensions and their default settings can block a user's alternative authentication options configured to display on a third-party registration and profile management page. Review what browser a user currently employs and, if necessary, disable and fine-tune the extension settings of the browser.

### About this task

Consider the following example. You have enabled third-party identity providers (IdP) to provide users with an alternative authentication option. Because you have enabled profile management, users can connect and disconnect their accounts with the third-party identity providers on the profile management page. However, some users are reporting that they do not see any such options on the sign-on page and the profile management page. The following screen captures illustrate what they see.



Browser extensions, particularly those designed to block ads or social network components, might block the user interface elements representing the third-party identity providers you enabled.

### Steps

- Verify if users are using browser extensions that might have caused this issue. Disable or fine-tune the browser extension to resolve the issue.

## Troubleshooting runtime errors

Users might encounter runtime errors when trying to connect to your partners. To troubleshoot these errors, investigate the user's activities, particularly the requests and the responses between the client and the PingFederate server, to determine the root cause.

### Client side

Use built-in developer tools from the browsers to analyze HTTP traffic. Alternatively, you can use third-party tools, such as [Fiddler](#) and [Charles](#).

### Server side

Review server log messages to investigate what PingFederate has received from the client.

On rare occasions, you can also use third-party tools, such as [Wireshark](#), or tools from the operating systems, such as [Tcpdump](#), to capture network traffic on the PingFederate server.

For instructions of third-party tools, see their documentation.

To correlate server log messages to user activities, you can use one of the following:

- The tracking ID, which can be configured to show in the user-facing error pages in PingFederate.

- The PF cookie value, which requires capturing the HTTP headers on the client side.
- Real-time monitoring of the server log, which works well if the issues can be replicated reliably and involves using tools from the operating systems or third-party vendors.

### Activating tracking ID in templates

You can configure PingFederate to display the tracking ID in the user-facing error Velocity templates. When an error occurs, use the tracking ID to look for the related log messages.

#### About this task

You can find the Velocity template files in the `<pf_install>/pingfederate/server/default/conf/template` directory.

The Velocity variable is `$TrackingId` and is available in the following templates:

- `general.error.page.template.html`
- `generic.error.msg.page.template.html`
- `idp.slo.error.page.template.html`
- `idp.sso.error.page.template.html`
- `sourceid-wsfed-idp-exception-template.html`
- `sp.slo.error.page.template.html`
- `sp.sso.error.page.template.html`
- `state.not.found.error.page.template.html`

#### Steps

1. Open the applicable Velocity template file.
2. Search for the `$TrackingId` variable.
3. Follow the inline instructions to activate the variable.




#### Note:

Template customization does not require a restart of PingFederate.

4. For a clustered PingFederate environment, repeat these steps on each engine node.

#### Result

The following screen capture demonstrates the user experience after the `$TrackingId` variable is activated and an error has occurred. In this example, `V3IwuUsy8PQp-9ZbE9UfUjOEo9c` is the tracking ID.





### Correlating log messages by PF cookie

If you do not want to activate the tracking ID in the user-facing error templates, you can capture the HTTP traffic and use the PF cookie value to find related server log messages for a given request.

#### About this task

Search the HTTP traffic server log and use the PF cookie value to review server log messages.

#### Steps

1. Capture HTTP traffic and look for the PF cookie value.
2. Search for the PF cookie value in the server log.
3. Because all server log messages, except the contents of the inbound requests and the outbound responses, are prefixed with their respective tracking IDs, use the tracking ID to review log messages and payloads pertaining to this transaction.

#### Result

In general, the most useful log messages are the ones tagged with `WARN`, `ERROR`, or prefixed with `Caused by`.

#### Example

#### Example

Suppose an error occurred and the associated the PF cookie value was `OaxBwPGw50BeHVXe1sgifB7iZR5Rz2VI4rhJwqUSIXV`. Based on the cookie value, you found the following log message.

```
2015-12-03 11:13:33,784 tid:V3IwuUsy8PQp-9ZbE9UfUjOEo9c DEBUG
[org.sourceid.servlet.HttpServletRespProxy] adding lazy cookie
Cookie{PF=OaxBwPGw50BeHVXe1sgifB7iZR5Rz2VI4rhJwqUSIXV; path=/; maxAge=-1;
domain=null} replacing null
```

After reviewing the related log messages based on the tracking ID `V3IwuUsy8PQp-9ZbE9UfUjOEo9c`, you found the next few messages.

```
2015-12-03 12:36:21,176 tid:V3IwuUsy8PQp-9ZbE9UfUjOEo9c ERROR
[org.sourceid.saml20.profiles.idp.HandleAuthnRequest] Exception occurred
during request processing
org.sourceid.websso.profiles.RequestProcessingException: Unexpected Runtime
Authn Adapter Integration Problem.
```

...

```
Caused by: org.sourceid.saml20.adapter.AuthnAdapterException: Could not obtain
attributes from the IdP Authentication Service.
```

Based on these log messages, the remedy is to review and update the configuration of the applicable identity provider (IdP) adapter instance.

### Correlating log messages by tracking ID

All server log messages, except the contents of the inbound requests and the outbound responses, are prefixed with their respective tracking IDs, which helps with locating related log messages and payloads for a given transaction for troubleshooting.

#### About this task

Review the server log messages using the `Tracking ID` value provided by the user.

## Steps

1. Ask the user for the `Tracking ID` value in the error message.
2. Search for the tracking ID in the server log.
3. Review the log messages and payloads pertaining to the transaction that is associated with the tracking ID.

## Result

In general, the most useful log messages are the ones tagged with `WARN`, `ERROR`, or prefixed with `Caused by`.

## Example

### Example

Suppose an error occurred and the associated the tracking ID was `V3IwuUsy8PQp-9ZbE9UfUjOEo9c`. Based on the tracking ID, you found the following log message.

```
2015-12-03 11:13:33,784 tid:V3IwuUsy8PQp-9ZbE9UfUjOEo9c DEBUG
[org.sourceid.servlet.HttpServletRespProxy] adding lazy cookie
Cookie{PF=OaxBwPGw50BeHVXeIsgifB7iZR5Rz2VI4rhJwqUSIXV; path=/; maxAge=-1;
domain=null} replacing null
```

After reviewing the related log messages, you found the next few messages.

```
2015-12-03 12:36:21,176 tid:V3IwuUsy8PQp-9ZbE9UfUjOEo9c ERROR
[org.sourceid.saml20.profiles.idp.HandleAuthnRequest] Exception occurred
during request processing
org.sourceid.websso.profiles.RequestProcessingException: Unexpected Runtime
Authn Adapter Integration Problem.
```

...

```
Caused by: org.sourceid.saml20.adapter.AuthnAdapterException: Could not obtain
attributes from the IdP Authentication Service.
```

Based on these log messages, the remedy is to review and update the configuration of the applicable identity provider (IdP) adapter instance.

### Correlating PingFederate events with PingDirectory LDAP activities

When enabled on PingDirectory, you can correlate events in PingFederate with LDAP activities in PingDirectory by looking for the matching session and request tracking IDs in their logs.

PingFederate can receive many requests during a session. The session ID is consistent throughout a session, but the request ID is unique for every request. You can use the request ID to search for specific events within a session.

PingFederate records runtime requests in its audit log and gives them tracking IDs. When PingFederate sends an LDAP call to PingDirectory, PingFederate also sends the request's tracking ID.



#### Important:

For PingFederate to send the tracking ID to PingDirectory, the Intermediate Client Request Control (OID=1.3.6.1.4.1.30221.2.5.2) must be enabled in PingDirectory. Also, there cannot be any access control instructions that prevent the PingFederate service account accessing PingDirectory from using this OID.

PingDirectory records the tracking ID as a session ID or request ID value in its access log. In the log, the ID is a property of a `via` element.

For example, if you see the following via elements in the PingDirectory access log, you can match them with PingFederate events by looking for session ID `kkLivppizq1RvbaYBAuBlr9z-Y8'` and request ID `FhM15Lz0KwsQphYU1UVHS4xkC5s` in the PingFederate audit log.

```
via="app='PingFederate' sessionID='tid:kkLivppizq1RvbaYBAuBlr9z-Y8'"
via="app='PingFederate' requestID='tid:FhM15Lz0KwsQphYU1UVHS4xkC5s'"
```




#### Note:

When a PingFederate endpoint receives a request, it records a request ID at the DEBUG level of the server log. When the **Request Header for Correlation ID** field in the **General Settings** window specifies a request header, if the request includes that header, and the header's value contains 1 to 50 alphanumeric characters and hyphens, then PingFederate uses that value for the request ID. Otherwise, PingFederate uses a unique value that it generates for the request ID. For more information, see [Configuring general settings](#) on page 1023.

## Troubleshooting OAuth transactions

This troubleshooting guide walks through an OAuth request by inspecting the parameters provided by the client in different stages of an OAuth transaction. It then compares the parameter values against the corresponding settings defined in the PingFederate administrative console.

Troubleshooting OAuth use cases involves reviewing the OAuth requests and various OAuth settings.



While the guide focuses on an OAuth authorization code use case, in which the end user authenticates through an identity provider adapter, it provides a general guidance for other OAuth use cases with or without OpenID Connect in terms of which part of the configuration comes into play and how a request might fail at which stage.

## Reviewing an OAuth request and various OAuth settings

To troubleshoot OAuth requests, inspect the parameters provided by the client in different stages of an OAuth transaction, and then compare the parameter values against the corresponding settings defined in the PingFederate administrative console.

### About this task

A typical OAuth request looks like the following with the parameters that are submitted by a client. These are what you track as you go through the configuration during a troubleshooting task. Your requests could look very different depending on the specifics of your authorization server, resource server, and clients.

```
?client_id=client&response_type=code&redirect_uri=uri&scope=scope1 scope2
```

In this example request, the client is providing 4 parameters:

- client\_id
- response\_type
- redirect\_uri
- scope



#### Note:

There are other optional parameters that can be included in the request but are at this time not of interest to you in troubleshooting a typical request.

### Steps

1. Review OAuth request in the server log.

PingFederate logs requests and responses to the server log. The details vary based on the log level set in `<pf_install>/pingfederate/server/default/conf/log4j2.xml` file. The following example shows a client making an Authorization Code grant type, as indicated by the **response\_type** parameter of `code`.

```
2015-11-29 22:11:35,795 tid:aUBgyTMjPfuSFp5BYtsK6Cb2McM DEBUG
[org.sourceid.websso.servlet.ProtocolControllerServlet] ---REQUEST
(GET)/as/authorization.oauth2 from 127.0.0.1:
---PARAMETERS---
scope:
  list_users
response_type:
  code
client_id:
  pa_web_session_9
```

2. Check if the client is valid.
  - a. Go to **Applications # OAuth # Clients** to open the **Clients** window.
  - b. Look for the client by its **Client ID**.

#### Result:

If the client is not found, PingFederate denies the request, returns a 400 error to the client, and logs an Unknown or invalid client\_id message to the server log, similar to the following code.

```
2015-11-29 22:11:35,812 tid:aUBgyTMjPfuSFp5BYtsK6Cb2McM DEBUG
[org.sourceid.oauth20.handlers.HandleAuthorizationRequest]
Normal exception being handled during OAuth request processing:
org.sourceid.oauth20.handlers.AuthorizationRequestException: Unknown or
invalid client_id
```

3. Check if the `redirect_uri` parameter value is valid for the client.
  - a. Go to **Applications # OAuth # Clients** to open the **Clients** window.
  - b. Go to the **Clients** window.
  - c. Select the applicable client.
  - d. Compare the `redirect_uri` parameter value against the values defined in the **Redirect URIs** field.

Result:

If the request comes without a `redirect_uri` parameter and the **Redirect URIs** field contains multiple entries, PingFederate denies the request, returns a 400 error to the client, and logs an `Invalid redirect_uri` message to the server log, similar to the following code.

```
2015-11-29 22:23:59,858 tid:aUBgyTMjPfuSFp5BYtsK6Cb2McM DEBUG
[org.sourceid.oauth20.handlers.HandleAuthorizationRequest]
Normal exception being handled during OAuth request processing:
org.sourceid.oauth20.handlers.AuthorizationRequestException: Invalid
redirect_uri
```

If the request comes with a `redirect_uri` parameter value that does not match any **Redirect URIs** values defined for the client, PingFederate denies the request, returns a 400 error to the client, and logs an `Invalid redirect_uri` message to the server log.

4. Check if the `response_type` parameter value is authorized for the client.
  - a. Go to **Applications # OAuth # Clients** to open the **Clients** window.
  - b. Select the applicable client.
  - c. In the **Allowed Grant Types** field, verify the `response_type` is selected.

Result:

If the `response_type` value is not one of the allowable grant types, PingFederate denies the request, returns a 403 error to the client, and logs an `unauthorized_client` message with an error description to the server log, similar to the following code.

```
2015-11-29 22:25:51,212 tid:aUBgyTMjPfuSFp5BYtsK6Cb2McM DEBUG
[org.sourceid.saml20.bindings.LoggingInterceptor] Transported Response.
OutMessageContext:
  OutMessageContext
  entityId: pa_web_session_1 (null)
  virtualServerId: null
  Binding: oauth:authz
  params: {error=unauthorized_client, error_description=implicit grant
not allowed for this client}
  Endpoint: https://servapp.ext.den-ping.com/pa/oidc/
cb#error_description=implicit+grant+not+allowed+for+this
+client&error=unauthorized_client
  SignaturePolicy: BINDING_DEFAULT
```

5. Check if the scopes requested with the `scope` parameter are defined for the authorization server.
  - a. Go to **System # OAuth Settings # Authorization Server Settings**.
  - b. In the **Authorization Server Settings** window, compare the scopes requested against the values defined in the **Scope Value** or the **Scope Group Value** fields.

Result:

If the scopes requested are not defined, PingFederate denies the request, returns a 403 error to the client, and logs an `invalid_scope` message with an error description to the server log, similar to the following code.

```
2015-11-29 22:24:52,588 tid:aUBgyTMjPfuSFp5BYtsK6Cb2McM DEBUG
[org.sourceid.saml20.bindings.LoggingInterceptor] Transported Response.
OutMessageContext:
```

```

OutMessageContext
entityId: pa_web_session_1 (null)
virtualServerId: null
Binding: oauth:authz
params: {error=invalid_scope, error_description=The requested
scope(s) must be blank or a subset of the provided scopes.}
Endpoint: https://servapp.ext.den-ping.com/pa/oidc/cb?
error_description=The+requested+scope%28s%29+must+be+blank+or+a+subset+of
+the+provided+scopes.&error=invalid_scope#.
SignaturePolicy: BINDING_DEFAULT

```

6. Check if the scopes requested are valid for the client.
  - a. Go to **Applications # OAuth # Clients** to open the **Clients** window.
  - b. Select the applicable client.
  - c. If the client is limited to specific scopes, as indicated by the selection of the **Restrict Scopes** check box, verify the scopes requested are valid for the client.

Result:

If the scopes requested are not valid for the client, PingFederate denies the request, returns a 403 error to the client, and logs an `invalid_scope` message with an error description to the server log.

7. Review the authentication process.

Suppose this OAuth request uses an identity provider (IdP) adapter for authentication. Check the IdP adapter mapping and the runtime selection made by the user.

- a. Go to **Authentication # OAuth # IdP Adapter Grant Mapping**.
- b. Verify an entry exists for the IdP adapter involved.

Result:

If more than one option is available, authentication policies can be used to select an authentication source. If no authentication policy is defined or applicable, the user is prompted with a list of all available authentication sources. The user can also save the preferred authentication source for later in the form of a `pfidpaid` cookie.

If a selection was made and the authentication source is not defined for OAuth, an error is returned to the user.

8. Upon successful authentication, PingFederate presents to the user an authorization consent page or a redirection to a trusted web application that is responsible to prompt the user for authorization unless a bypass option is configured. Review the authorization approval settings.
  - a. Go to **System # OAuth Settings # Authorization Server Settings**.
  - b. Review the **Reuse Existing Persistent Access Grants for Grant Types** setting.

Result:

If the grant type is selected, the authorization consent page is bypassed for the same client, the same user and same, or lesser, scope.

- c. Review the **Consent User Interface** setting.

If PingFederate is configured to use an external consent user interface, verify that the associated settings are correctly configured and the web application is fulfilling its responsibilities.

- d. Go to **Applications # OAuth # Clients** to open the **Clients** window.
- e. Go to the **Clients** window.
- f. Select the applicable client.
- g. Review the **Bypass Authorization Approval** setting.

Result:

If the **Bypass Authorization Approval** check box is selected, the authorization consent page is bypassed as well.

9. Verify a mapping is configured.

When authorization is obtained, PingFederate maps attribute values from the authentication source into the persistent grants, the `USER_KEY`, `USER_NAME`, and extended attributes defined in the **Authorization Server Settings** window. This is the first stage of the two-stage OAuth attribute mapping process. In this example, because the user authenticates through an IdP adapter, check the IdP adapter mapping.

- a. Go to **Authentication # OAuth # IdP Adapter Grant Mapping**.
  - b. Verify an entry exists for the IdP adapter involved and review its configuration.
10. Review the request and the settings related to access token management.

Finally, PingFederate selects the applicable access token management (ATM) instance and fulfill the access token by mapping values from the persistent grants, the authentication source, or both. This is the second stage of the two-stage OAuth attribute mapping process.

At runtime, the OAuth authorization server uses the following rules to determine which ATM instances to use:

- a. limits the eligible ATM instances to those that are available in the context of the request. For most requests, these are instances that have an attribute mapping defined in the **Access Token Mapping** window. For OAuth Assertion Grant requests, it is the set of instances for which a mapping is defined in the IdP connection. If configured, the ACL can also limit which ATM instances are eligible.
  - b. If the request comes with an `access_token_manager_id` or `aud` parameter, uses the information to determine the applicable ATM instance.
  - c. If the request does not come with either parameter, for OAuth clients supporting the OpenID Connect protocol by including the `openid` scope value, uses the ATM instance specified by the OpenID Connect policy associated with the client. For resource server clients, you can optionally configure to use any eligible ATM instances for the purpose of token validation.
  - d. If the request comes with neither of the two parameters nor the `openid` scope, uses the default ATM instance of the client if configured, or the default ATM instance defined for the installation if eligible. For token validation requests, if resource server clients do not provide either the `access_token_manager_id` or `aud` parameter in their requests and the resource server clients have not been configured to validate against any eligible ATM instances, the same logic applies.
- a. Determine if the OAuth request is sent to the `/as/authorization.oauth2` authorization endpoint or the `/as/token.oauth2` token endpoint with an `access_token_manager_id` or `aud` parameter.
  - b. Go to **Applications # OAuth # Clients** to open the **Clients** window.
  - c. Select the applicable client.
  - d. Verify if a default access token is selected from the **Default Access Token Manager** list.
  - e. Go to **Applications # OAuth # Access Token Mapping**.
  - f. Review the attribute mapping configuration for the authentication source, if such mapping exists, or the `Default` mapping.

## Other runtime issues

Possible runtime issues and their solutions related to unexpected certificate expiration and `CrossModule` and `Network` error messages.

### Runtime issues and solutions

| Problem                           | Solution   |
|-----------------------------------|--|
| Certificates unexpectedly expire. | Verify that the server clocks are synchronized on both sides of the federation. You can configure PingFederate to notify administrators in advance of impending certificate expiration. For more information, see <a href="#">Runtime notifications</a> on page 935. |

| Problem   | Solution   |
|---|--|
| Receive <code>CrossModule</code> or <code>Network</code> error messages when <code>PingFederate</code> is deployed with a supported hardware security module (HSM). | Verify network connections to the HSMs are active and running. Also ensure the HSMs have not been unintentionally shut down. |

## Collecting support data

When Ping Identity Support is helping an administrator troubleshoot a problem, it might ask the administrator to use the collect support data (CSD) tool to compile information about your `PingFederate` installation. The CSD tool is available through the `pingfederate/bin` directory.

About this task

The tool collects the following information by default:

- `pingfederate/bin`
- `pingfederate/log` (the most recent files of each type within a size limit)
- `pingfederate/server/conf`(configuration files)
- `pingfederate/server/data` (not key files)

The tool collects the following environment details:

- files present and their sizes
- certificate data
- version data
- JVM details
- and so on

The tool also collects the following system details, depending on the operating system:

- Crontab
- `lscfg`
- `netstat`
- `uname`
- and so on

If Ping Identity Support needs more information about the `PingFederate` installation than the default configuration provides, Support might ask the administrator to add a data collector to the tool by modifying its `csd_configuration.yaml` file.

The tool consists of the following files in the `pingfederate` directory:

- `bin/collect-support-data.bat`
- `bin/collect-support-data.sh`
- `bin/csd-1.0.jar`
- `server/default/conf/collect-support-data/csd_configuration.yaml`



### Tip:

You can use other parameters with the `collect-support-data` tool, including:

```
--encrypt
```

Encrypts the CSD output.



```
--outputPath
```

Specifies a directory for the CSD package.

For additional information about these parameters and more, use the `--help` command.

### Steps

1. Using your PingFederate administrator account and a terminal, navigate to the `pingfederate/bin` directory.
2. Use one of the following commands to run the CSD tool, depending on your operating system:  
Choose from:

- On a Windows operating system, use `collect-support-data.bat`.
- On a Unix-based operating system, use `./collect-support-data.sh`.

Result: As the tool collects data, it displays its progress and any errors. When it finishes collecting data, the tool places the data in a zip file in the `bin` directory. The file name format is `support-data-ping- $\{hostname\}$ -r- $\{timestamp\}$ .zip`.

3. Review any errors that the tool displayed during the process or added to the log file `support-data-ping- $\{hostname\}$ -r.log`. If needed, resolve the errors and run the tool again.
4. Send the support data zip file to Ping Identity Support according to the instructions from Support.

## WS-Trust STS configuration

The PingFederate WS-Trust Security Token Service (STS) provides security-token validation and creation to extend single sign-on access to identity-enabled web services.

The section provides instructions for configuring the WS-Trust STS. For more information, see [Web services standards](#) on page 53.



### Note:

WS-Trust STS settings can also be configured through the PingFederate Administrative API platform. For more information, see [Accessing the API interactive documentation](#).

## Server settings

To use the PingFederate WS-Trust security token service (STS) for partner connections, enable and configure the WS-Trust protocol in your system server settings.

After you enable the protocol, you must identify the STS server with a unique federation identifier for both SAML 2.0 and SAML 1.1 tokens, unless these IDs are already established for the corresponding browser-based single sign-on protocols.

In addition, also within these server settings tasks, you have the option to require authentication globally for access to STS endpoints.

### Enabling the WS-Trust protocol

To use the PingFederate WS-Trust security token service (STS) for partner connections, enable the WS-Trust protocol.

#### About this task

Using the administrative console, configure your server settings to enable the WS-Trust protocol.

## Steps

1. Go to **System # Server # Protocol Settings**.
2. On the **Federation Info** tab, enter your SAML federation IDs unless these IDs are already established for the corresponding browser-based SSO protocols.



### Note:

Identifiers are required for both SAML 2.0 and SAML 1.x to enable the STS to issue either type of token when requested. If you have not established a federation ID for either of these protocols or do not expect to use one or the other, enter a placeholder in any format and reconfigure later.

## Configuring STS authentication

You can configure PingFederate to require that client applications provide credentials to access the STS.

### About this task

Although it is an optional configuration, configuring security token service (STS) authentication is recommended for identity provider (IdP) configurations that use the Username Token Processor. For other token processors and token generators, trust in the identity of the client is conveyed within the token itself and verified as part of processing. You can still configure authentication requirements to add another layer of security by limiting access to only authenticated clients.



### Note:

You can configure STS authentication to either apply globally to all token formats and for all IdP and service provider (SP) partner connections, or token-to-token mappings, using more fine grained controls, at the connection level through issuance criteria.

## Steps

1. Go to **System # Server # Protocol Settings**.
2. On the **WS-Trust STS Settings** tab, click **Configure WS-Trust STS Authentication** to open the **WS-Trust STS Settings** window.
3. On the **Authentication Methods** tab, select the **Require HTTP Basic Authentication** check box, the **Require Mutual SSL/TLS Authentication** check box, or both.

If both the **Require HTTP Basic Authentication** check box and the **Require Mutual SSL/TLS Authentication** check box are selected, all clients must provide credentials for both mechanisms.



### Important:

If you select the **Require Mutual SSL/TLS Authentication** check box, you must configure a secondary PingFederate HTTPS port `pf.secondary.https.port` in the `run.properties` file. For more information, see [Configuring PingFederate properties](#) on page 820.

4. If you select the **Require HTTP Basic Authentication** check box, manage user accounts on the **HTTP Basic Authentication** tab.
  - a. Click **Create User**.
  - b. In the **HTTP Basic Authentication**, enter a user name in the **username** field and a password in the **password** field.. Repeat to create additional user accounts for your client applications.
  - c. Click **Done**.

**Note:**

On the **HTTP Basic Authentication** tab, you can also delete user accounts and update their passwords.

5. If you select the **Require Mutual SSL/TLS Authentication** check box, on the **Mutual SSL Authentication** tab, click **Configure Mutual SSL Authentication**.
  - a. On the **Authentication Options** tab, you can select the **Restrict Access by Subject DN** check box and the **Restrict Access by Issuer Certificate** check box. Click **Next**.  
If both options are selected, the client certificate used for authentication to the STS endpoints must meet both sets of restrictions.
  - b. If you selected the **Restrict Access by Subject DN** check box, enter one or more subject DNs on the **Allowed Subject DNs** tab.

**Note:**

On the **Allowed Subject DNs** tab, you can edit or delete existing entries but you must keep at least one subject DN.

- c. Click **Next**.. When finished, click **Save**.
- d. If you selected the **Restrict Access by Issuer Certificate** check box, on the **Allowed Issuer Certificates** tab, from the **Issuer Certificate** list, select one or more client certificates.
- e. Click **Add**.  
If you have not yet imported the client certificate, click **Manage Certificates** to do so.

**Note:**

On the **Allowed Issuer Certificates** tab, you can remove existing entries but you must keep at least one issuer.

- f. On the **Summary** tab, review your mutual SSL/TLS authentication settings. Click **Done**.  
Result: This will take you back to the **WS-Trust STS Settings** window.
6. When you finish configuring WS-Trust STS settings, on the **Summary** tab, review the configuration. To keep your changes, click **Save**.

## Identity provider STS configuration

This section covers the identity provider (IdP) configuration for the PingFederate WS-Trust security token services (STS).

### Managing token processors

The PingFederate Security Token Service (STS) uses token processors to validate incoming tokens and token requests.

#### About this task

You must configure at least one processor in order to set up an STS connection or a token-to-token mapping.

For more information about WS-Trust, see [Web services standards](#) on page 53.

PingFederate comes bundled with the following token processors:

- JWT Token Processor
- Kerberos Token Processor
- OAuth Bear Token Processor
- SAML 1.1 Token Processor
- SAML 2.0 Token Processor
- Username Token Processor

You can deploy additional token translators from [Ping Identity website](#).

#### Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. In the **Token Processors** window, choose from the following options.

| Option  | Description  |
|---|--|
| <b>Configure a new instance</b>               | Click <b>Create New Instance</b>   |
| <b>Modify an existing instance</b>            | Click the name of instance in the <b>Instance Name</b> column              |
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |



#### Note:

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

#### Selecting a token processor type

Begin creating a token-processor instance by choosing the processor type.

About this task

#### Steps

1. Go to **AuthenticationToken ExchangeToken Processors**.

- To create a new instance, click **Create New Instance** to open a new **Create Token Processor Instance** configuration window and follow the following steps.



**Note:**

To select an existing token processor instance, select an instance in the **Instance Name** section.

- Click on the **Type** tab.
- Enter a name in the **Instance Name** field and ID in the **Instance ID** field.
- From the **Type** list, select the token-processor type.
- From the **Parent Instance** list, select a parent instance.

This is useful when you are creating an instance that is similar to an existing instance. The child instance inherits the configuration of its parent. In addition, you can override one or more settings during the rest of the setup. Select the **Override ...** check box and make the adjustments as needed in one or more subsequent windows.

- Click **Next**.

### Configuring a token processor instance

PingFederate configures multiple token processor instances. Select one that best fits your environment needs.

About this task

Depending on the selected token processor, the **Instance Configuration** tab presents you with different parameters.

Steps

- For configuring a specific token processor bundled with PingFederate, see one of the relevant following sections:
  - [Configuring a Username Token Processor instance](#) on page 1045
  - [Configuring a Kerberos Token Processor instance](#) on page 1046
  - [Configuring an OAuth Token Processor instance](#) on page 1046
  - [Configuring a JSON Web Token Processor instance](#) on page 1047
  - [Configuring a SAML Token Processor instance](#) on page 1047
- For information about add-on processors, see [Integration overview](#) on page 65.

### Configuring a Username Token Processor instance

The integrated Username Token Processor accepts and validates username security tokens.

Steps

- Go to **Authentication # Token Exchange # Token Processors** to open the **Token Processors** window.
- Select on an existing token processor instance by clicking its name in the **Instance Name** section, or create a new instance by clicking **Create New Instance**.

Result: This will open the **Create Token Processor Instance** window configuration.

3. On the **Instance Configuration** tab, configure the basics of this token processor instances.
  - a. If you have not yet defined the desired Password Credential Validator instance, click **Manage Password Credential Validators** to do so.
  - b. Click **Add a new row to 'Credential Validators'** to select a credential-authentication mechanism instance for this adapter instance.
  - c. From the **Password Credential Validator Instance** list, select a Password Credential Validator instance. Click **Update**.

Add as many validators as necessary. Use the up and down arrows to adjust the order in which you want to attempt credential authentication. If the first mechanism fails to validate the credentials, moves sequentially through the list until credential validation succeeds. If none of the Password Credential Validator instances can authenticate the user's credentials, and the challenge retries maximum has been reached, the process fails.

 **Note:**

If usernames overlap across multiple Password Credential Validator instances, this failover setup could lock out those accounts in their source locations.

- d. In the **Field Value** section, enter a value in the **Authentication Attempts**.

When the number of login failures reaches this threshold, the user is locked out for a period of time.

The default value is 3.

### Configuring a Kerberos Token Processor instance

The integrated Kerberos Token Processor accepts and validates Kerberos tokens through a configured Kerberos realm.

#### About this task

It supports authentication mechanism assurance from Active Directory (AD) domain service, making it possible to restrict access to users authenticating through specific mechanisms. For more information, see [Authentication mechanism assurance](#) on page 336.

#### Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. On the **Instance Configuration** tab, select the applicable domain from the **Domain/Realm Name** list. An AD domain or a Kerberos realm must be configured for use with the Kerberos Token Processor. If the domain you want does not appear, click **Manage Active Directory Domains/Kerberos Realms** to add it. For more information, see [Active Directory and Kerberos](#) on page 992.

 **Note:**

Kerberos tickets can be accepted from domains other than the domain configured in the token processor if there is a transient, two-way trust. This trust exists by default when domains are joined within a single server forest. For more information, see [Multiple-domain support](#) on page 993.

### Configuring an OAuth Token Processor instance

The PingFederate STS provides validation for OAuth 2.0 bearer tokens. To use the OAuth Token Processor, you must first configure an Access Token Management (ATM) instance.

#### About this task

For more information about PingFederate OAuth authorization server and access token management, see [About OAuth](#) on page 83 and [Access token management](#) on page 603.

## Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. On the **Instance Configuration** tab, configure the basics of the token processor instance.
  - a. In the **Access Token Manager** row, from the **Field Value** list, select an ATM instance.

If the desired ATM instance is not shown, click **Manage Access Token Manager**.

Result:

The token processor instance uses the selected ATM instance to validate the OAuth bearer access tokens.

- b. Optional: Select the **Scope Value as Single String** check box.

Result:

If selected, the scope value is returned as a single space-delimited set of string value. If it is not selected, scope values are returned as a multivalued attribute.

### Configuring a JSON Web Token Processor instance

The PingFederate security token services (STS) provides validation for JSON web tokens (JWTs).

## Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. On the **Instance Configuration** tab, enter the required information.

See the following table for information about each field.

#### JWT Token Processor instance field names and descriptions

| Field                    | Description   |
|--------------------------|---|
| <b>JWKS Endpoint URI</b> | The URI of the JWKS endpoint. A set of JSON Web Keys (JWK) are downloaded from this endpoint and used for JWT signature verification. |
| <b>Issuer</b>            | A unique identifier for the issuer of the JWT.  |
| <b>Expiry Tolerance</b>  | The amount of time, in seconds, to allow for clock skew between servers. Valid range is 0 to 3600.                                    |

### Configuring a SAML Token Processor instance

The integrated SAML (1.1 or 2.0) Token Processor accepts and validates SAML (1.1 or 2.0) security tokens. The PingFederate security token service (STS) validates digital signatures using all trusted certificate authorities (CAs) imported into PingFederate.

#### About this task

On the **Instance Configuration** tab, configure a SAML Token Processor instance.

You can restrict the signature verification process by subject distinguished names (DN), issuers, or both to limit the token requests accepted for this token processor instance.

You must indicate a unique identifier for the PingFederate STS. Token processor instances reject SAML tokens that do not contain the identifier in the **audience** element.

## Steps

- Go to **Authentication # Token Exchange # Token Processors**.

- On the **Instance Configuration** tab, configure the basics of the token processor instance.
  - a. In the **Audience** row, in the **field value** field, enter the URI that uniquely identifies your federation gateway for this SAML protocol.  
This is the federation ID for the STS for either SAML 1.1 or SAML 2.0 tokens, depending on which processor you are configuring.
  - b. Optional: Click **Add a new row to 'Valid Certificate Issuer DNs'** to enter one or more issuers.

 **Important:**

If issuer DNs are specified here, then only those issuers are considered valid for verifying incoming digital signatures. Otherwise, all trusted certificate authorities (CAs) are used to verify signatures.

- c. Optional: Click **Add a new row to 'Valid Certificate Subject DNs'** to enter one or more subject DNs.

 **Important:**

If subject DNs are specified here, then only those subject DNs are considered valid for verifying incoming digital signatures. Otherwise, all trusted certificate authorities (CAs) are used to verify signatures.

If you specify both issuer DNs and subject DNs, then the certificate used to validate signatures must match an entry in both lists.

If you provide no issuer DN and subject DN, then all certificates are treated as valid for purposes of verification.

### Extending a token processor contract

Token processors allow administrators to add to a built-in list of user attributes that the processor returns from an incoming token.

About this task

 **Note:**

The **Extended Contract** tab shows a different list of attributes under **Core Contract**, depending on the token processor selected.

Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. On the **Extended Contract** tab, in the **Extend the Contract** field, enter the name of the desired attribute. Click **Add**.

 **Important:**

For the OAuth Bearer Token Processor, added attributes must also be among those configured with the associated access token management instance.

Repeat these steps to add additional attributes.



### Setting attribute masking

Mask attribute values that PingFederate logs from a processor instance at runtime.

#### Steps

1. Go to **Authentication # Token Exchange # Token Processors**.
2. On the **Token Attributes** tab, in the **Mask Log Values** section, select the check box for the attribute whose value you want to mask in logs.



#### Note:

If OGNL expressions might be used to map derived values into outgoing tokens and you want those values masked in logs as well, select the **Mask All OGNL-expression Generated Log Values** check box under the list of attributes.

### Reviewing the token processor configuration

Review your token processor instance summary information.

#### About this task

On the **Summary** tab, review, amend, save, or discard the token processor configuration.

#### Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

### Managing STS request parameters

Configure PingFederate to act as a WS-Trust security token service (STS) by defining sets of Request for Security Token (RST) metadata parameters that can be used for mapping attributes into outgoing SAML security tokens.

#### About this task

After these request contracts are defined, you can make them available when configuring WS-Trust STS settings in the SP connections. For more information, see [Selecting a request contract](#) on page 1055.

To manage your request contracts:

#### Steps

- Go to **Authentication # Token Exchange # STS Request Parameters**  
Choose from:
  - To configure a new set of request parameters, click **Add New Request Contract**.
  - To modify an existing request contract, select it by its name in the **Contract Name** column.
- To review the usage of an existing request contract, in the **Action** section, click **Check Usage**.
- To remove an existing request contract or to cancel the removal request, in the **Action** section, click **Delete** or **Undelete**.

### Creating a request contract

Specify one or more parameters that will be included in request-security-tokens (RST) applicable to connection partners. You can make request contracts available for token-attribute mapping during partner-connection configuration.

#### About this task

Identify the contract and define parameters that will be available in token requests associated with this contract for partner connections.

#### Steps

1. Go to **Authentication # Token Exchange # STS Request Parameters**.  
Result: This will open the **STS Request Parameters** window configuration.
2. Click **Add New Request Contract**.  
Result:  
This will open the **Request Contract** configuration window.
3. Enter the contract name in the **Contract Name** field and the contract ID in the **Contract ID** field.



#### Note:

In the **Request Contract** configuration window, after you click **Done**, the **Contract Name** and **Contract ID** cannot be modified.

4. In the **Parameter Name** field, enter the parameter that will be included in the RSTs. Click **Add**.  
You must add at least one parameter. Repeat this step to add more parameters.



#### Note:

After the request is saved, you can add, modify, or remove parameters. You must keep at least one parameter.

5. Click **Done**.

### Configuring SP connections for STS

Configure a security token service (STS) connection to a service provider (SP) partner either in conjunction with browser-based single sign-on (SSO) or independently.

#### Steps

1. Go to **System # Server # Protocol Settings**.
2. On the **WS-Trust STS** tab, configure an STS connection.

### Configuring protocol settings for IdP STS

Specify the WS-Trust protocol details for web service clients related to this connection.

#### Steps

1. Go to **Applications # Integration # SP Connections**.
2. Click on an existing connection in the **SP Connection** column, or click **Create Connection** to configure a new SP connection to open the **SP Connection** configuration window.

- On the **WS-Trust STS** tab, click **Configure WS-Trust STS** to open the **WS-Trust STS** configuration window.

**Note:**

The **WS-Trust STS** tab is only available after you enable the **WS-Trust** role on the **Connection Type** tab. For more information, see [Configuring SP Connections for STS](#).

- On the **Protocol Settings** tab, enter a URL for your partner's web service in the **Partner Service Identifier** field. Click **Add**.

This identifier compares to the **AppliesTo** element in the Requests for Security Token (RST) messages and can be either a complete URL or a base URL for matching variable ports or paths.

Repeat this step to add additional identifiers.

- Select any of the following WS-Trust protocol setting options that are applicable to your use case.

| Option   | Description   |
|--|---|
| <b>OAuth Assertion Profiles</b>  | <p>When selected, four additional token-type requests become available based on these OAuth grant types:</p> <ul style="list-style-type: none"> <li>JWT Bearer Token grant type</li> <li>OAuth Access Token via JWT Bearer Token grant type</li> <li>SAML 2.0 Bearer Assertion grant type</li> <li>OAuth Access Token via SAML 2.0 Bearer Assertion grant type</li> </ul> <p>See <a href="#">STS OAuth integration</a> on page 83 for more information on the use of these token-type requests.</p>                               |
| <b>Default Token Type</b>  | <p>The default token type when a web service client (WSC) does not specify in the token request which token type the STS should issue. The choices are:</p> <ul style="list-style-type: none"> <li><b>SAML 2.0</b></li> <li><b>SAML 1.1</b></li> <li><b>SAML 1.1 for Office 365</b></li> </ul> <p>The default token type does not need to match the protocol selected for the browser-based SSO, if enabled, and does not apply to OAuth assertion profiles because those RST messages must contain the requested token type.</p> |
| <b>Generate Key for SAML Holder of Key Subject Confirmation Method</b> | <p>When selected, the STS generates a symmetric key to be used in conjunction with the "Holder of Key" (HoK) designation for the assertion's Subject Confirmation Method.</p> <p>For information about HoK assertions, see <a href="#">Web Services Security SAML Token Profile</a>.</p> <p>This option does not apply to OAuth assertion profiles.</p>   |

| Option                            | Description  |
|-----------------------------------|--|
| <b>Encrypt SAML 2.0 Assertion</b> | When selected, the STS encrypts the SAML 2.0 assertion. Applicable only to SAML 2.0 security token.<br><br>This option does not apply to OAuth assertion profiles. |

6. On the **Protocol Settings** tab, customize SAML messages and assertions for WS-Trust connections. Message customizations are OGNL expressions that allow you to customize the security token sent from PingFederate to the service provider (SP).
- Click **Show Advanced Customizations**.
  - From the **Message Type** list, select a type option and enter an expression. The message type is used to override the message type returned from the OGNL expression.

The following tables describe the relationship between message type and available variables, and the corresponding class or interface information in Java.

#### SP connections SAML 2.0 message types and expressions

| Message types    | Available variables and classes/interfaces in Javadoc   |
|------------------|---|
| AssertionType    | #AssertionType<br>org.sourceid.saml20.xmlbinding.assertion.AssertionType<br>#AssertionTypes<br>org.sourceid.saml20.xmlbinding.assertion.AssertionType[]<br>#Attributes<br>org.sourceid.util.log.AttributeMap  |
| ResponseDocument | #ResponseDocument<br>For a connection with WS-Trust v1.3, #ResponseDocument will be of type org.oasisOpen.docs.wsSx.wsTrust.x200512.RequestSecurityTokenResponseCollectionDocument<br>For a connection with WS-Trust v1.2, #ResponseDocument will be of type org.xmlsoap.schemas.ws.x2005.x02.trust.RequestSecurityTokenResponseDocument<br>#Attributes<br>org.sourceid.util.log.AttributeMap |

#### SP Connections SAML 1.x message types and expressions

| Message types | Available variables and classes/interfaces in Javadoc  |
|---------------|--|
| AssertionType | #AssertionType<br>org.sourceid.protocol.saml11.xml.AssertionType<br>#AssertionTypes<br>org.sourceid.protocol.saml11.xml.AssertionType[]<br>#Attributes<br>org.sourceid.util.log.AttributeMap |

| Message types    | Available variables and classes/interfaces in Javadoc  |
|------------------|--|
| ResponseDocument | <p>#ResponseDocument</p> <p>For a connection with WS-Trust v1.3, #ResponseDocument will be of type org.oasisOpen.docs.wsSx.wsTrust.x200512.RequestSecurityTokenResponseCollectionDocument</p> <p>For a connection with WS-Trust v1.2, #ResponseDocument will be of type org.xmlsoap.schemas.ws.x2005.x02.trust.RequestSecurityTokenResponseDocument</p> <p>#Attributes</p> <p>org.sourceid.util.log.AttributeMap</p> |

Example:

- Example of an **AssertionType** expression for SAML1.1.

```
#AssertionType.getAuthenticationStatementArray(0)
.getSubject().getNameIdentifier().setStringValue("JoeSAML2IDP"),
#AssertionType
```

- Example of a **ResponseDocument** expression for a connection with WS-Trust v1.3.

```
#RequestSecurityTokenResponseCollectionDocument.getRequestSecurityTokenResponseCollection()
.getRequestSecurityTokenResponseArray(0).setContext('context1'){code}
```

- Example of a **ResponseDocument** expression for a connection with WS-Trust v1.2.

```
#RequestSecurityTokenResponseDocument.getRequestSecurityTokenResponse().setContext('context1')
```

#### 7. ClickNext.

### Setting a token lifetime

Specify a token's timeframe of validity before and after issuance.

About this task

Standards require a window of time during which a security token is considered valid. Each token has a time-stamp XML element as well as elements indicating the allowable lifetime of the token, in minutes, before and after the token time stamp.

Steps

1. Go to **Applications # Integration # SP Connections**.
2. In the **WS-Trust STS** window, click the **Token Lifetime** tab.
3. Override the default values for the fields in the following table.

#### Token timeframe parameters and descriptions

| Field                 | Description  |
|-----------------------|--|
| <b>Minutes Before</b> | The amount of time before the SAML token was issued during which it is to be considered valid. The default value is 5. |
| <b>Minutes After</b>  | The amount of time after the SAML token was issued during which it is to be considered valid. The default value is 30. |

4. Click **Next**.

## Configuring token creation

The PingFederate security token service (STS) requires creating tokens to enable web services access to resources at your service provider (SP) partner's site.

### About this task

For the PingFederate STS to issue a security token in response to requests for partner services, you must indicate what user attributes are to be included in the token attribute contract. The attribute values sent in the token are then derived by mapping those available from the token processor you select. As with browser single sign-on (SSO), the mapping can be augmented using local data stores, variable or constant text, or expressions.

### Steps

- On the **Token Creation**, click **Configure Token Creation** to begin a token creation configuration.

#### *Defining an attribute contract for IdP STS*

During token creation configuration, define an attribute contract that the server sends in the security tokens issued in response to a web service client at your site.

### About this task

An attribute contract is the set of user attributes that a web service client at your site expects to receive in security tokens issued for this connection. You identify these attributes on the **Attribute Contract** tab. For more information, see [Attribute contracts](#) on page 101.

### Steps

1. Enter the attribute name in the **Extend the Contract** field. Attribute names are case-sensitive and must correspond to the attribute names, including claims, expected by the requesting web services client (WSC).

Result:



#### Tip:

The Format attribute associated with the **NameID** element in outgoing SAML tokens can be set by adding an attribute called **SAML\_NAME\_FORMAT**. The value of that attribute can then be mapped later. For more information, see [Configuring contract fulfillment for token creation](#) on page 1059.

For information about the **NameID** elements and applicable URI values, locate the SAML 2.0 specification at [www.oasis-open.org/standards](http://www.oasis-open.org/standards).



#### Tip:

You can add a special attribute, **SAML\_AUTHN\_CTX**, to indicate to the service provider (SP) the type of credentials used to authenticate to the identity provider (IdP) application-authentication context. Map a value for the authentication context on the attribute-mapping window later in the configuration, from any available attribute source, including the RST if a requested context is specified as a request parameter. For more information, see [Configuring contract fulfillment for token creation](#) on page 1059.

- Optional: For SAML 1.1 tokens, select a attribute namespace from the list.

This field appears only when the chosen default token type is **SAML 1.1** or **SAML 1.1 for Office 365** in the **WS-Trust STS # Protocol Settings** configuration.

Change the default namespace selection if you and your SP partner have agreed to a specific namespace.



**Note:**

You can customize name-format alternatives in the `custom-name-formats.xml` configuration file located in the `<pf_install>/pingfederate/server/default/data/config-store` directory. You must restart PingFederate to activate any changes made to this file.

For more information about attribute namespace, see [Attribute contracts](#) on page 101.

- Click **Add**.
- Repeat until all applicable attributes are defined.
- Click **Next**.

### Result

Use the **Edit**, **Update**, and **Cancel** workflow to make or undo a change to an item. Use the **Delete** and **Undelete** workflow to remove an item or cancel the removal request.

#### *Selecting a request contract*

Select a request contract to be used to map attribute values into the security token.

#### About this task

This optional setting allows you to use XML parameters contained in RSTs for token-attribute mapping. For more information, see [Managing STS request parameters](#) on page 1049. If you are not using request parameters, click **Next** to continue.



**Note:**

If you are editing an existing configuration, you can change the request contract or disable this optional setting. These changes might require additional configuration changes in subsequent tasks.

### Steps

- To use request parameters, select the **Request Contract** check box to access the **Request Contractlist**.
- Select a request contract from the **Request Contract** list.

If the contract you want is in the **Request Contract** list, click **Manage STS Request Parameters**.

When selected, you can choose the request contract as the attribute source in the **IdP Token Processor Mapping** configuration later in the setup.

- Click **Next**.

### Managing IdP token processor mappings

Identity provider (IdP) token processors are responsible for validating incoming security tokens as part of an STS operation. A configured and deployed token processor in PingFederate is known as a token processor instance. Map, edit, remove, or save a token processor instance.

#### About this task

You can map one or more token processor instances into an service provider (SP) connection to satisfy multiple session-management requirements where needed. The same token processor instances can be mapped in multiple SP connections.

When token processor instances are restricted to certain virtual server IDs, the allowed IDs are displayed in the **Virtual Server IDs** column.

#### Steps

1. In the **Token Creation** window, click the **IdP Token Processor Mapping** tab.
2. To map a token processor instance, click **Map New Token Processor Instance**.  
Choose from:
  - To edit the mapping configuration of a token process instance, open it by clicking on its name, select the setting that you want to reconfigure, and complete the change.
  - To remove a token processor instance or cancel the removal request, click **Delete** followed by **Save** or **Undelete**.
3. If you are creating a new connection and you are finished with mapping configuration, click **Done**.
4. If you are editing an existing configuration and want to keep your changes, click **Save**.

#### Selecting a token processor instance

Select an IdP token processor instance that can be used to authenticate users for a partner. Attributes returned by the token processor instance you choose for the token processor contract can be used to fulfill the attribute contract with your partner.

#### About this task

On the **Token Processor Instance** tab, choose an instance of a deployed token processor that suits your requirements for this connection.



#### Note:

If you are editing a currently mapped token processor instance, you can toggle the **Override Instance Settings** check box. Clearing it removes all previously overridden settings for this connection. Selecting it provides you the opportunity to customize token processor settings specifically for this connection.

#### Steps

1. From the **Token Processor Instance** list, select a token processor instance.



#### Note:

If you do not see the desired token processor instance, click **Manage Token Processor Instances** to create a new instance of any deployed token processor.



2. Select the **Override Instance Settings** check box if you want to customize one or more token processor settings for this connection alone.

 **Tip:**

Alternatively, you can create child token processor instances of a base token processor instance with overrides so that such customized settings can be applied to several connections. For more information, see [Hierarchical plugin configurations](#) on page 99.

**Result:**

When selected, the administrative console adds a new **Override Instance** tab.

### Overriding a token processor instance

Customize the token processor instance settings for overriding one or more token processor settings for a connection.

#### About this task

On the **Override Instance** tab, configure override token processor settings specifically for this connection.

 **Note:**

Any changes to the base token processor instance are propagated to a connection provided the same changes are not overridden for the connection.

### Steps

1. Click **Override Instance Settings**.
2. On the **Instance Configuration**, **Extended Contract**, and **Token Attributes** tabs, for each of the settings, select the **Override** check box and make your changes.

 **Note:**

If you are editing a currently mapped token processor instance, click **Override Instance Settings** to reconfigure any overridden settings for this connection. You can also remove all overridden settings on a per-tab basis by clearing the **Override** check box near the top of the window.

3. Click **Next**.
4. Click **Done** to close the **Override Instance Settings** window and continue with the rest of the **IdP Token Processor Mapping** window configuration.

### Restricting a token processor to certain virtual server IDs

Virtual server IDs provide more configuration flexibility in cases where you need to identify your server differently when connecting to a partner in one connection for multiple environments or in multiple connections where the partner also supports multiple federation IDs. When you multiplex one connection for multiple environments, you can restrict each token processor added to a WS-Trust STS SP connection or IdP connection.

#### About this task

When you multiplex one connection for multiple environments see , you can enforce authentication requirements by restricting a token processor to certain virtual server IDs on the **Virtual Server IDs** tab. By default, no restriction is imposed.

 **Note:**

If you are editing a currently mapped token processor instance, you can toggle the **Restrict Virtual Server IDs** setting. You can also change the allowed virtual server IDs.

### Steps

1. In the **IdP Token Processor Mapping** configuration window, go to the **Virtual Server IDs** tab.
2. Select the **Restrict Virtual Server IDs** check box.
3. Select one or more virtual server IDs that you want to allow for this token processor.

### Selecting an attribute retrieval method for token creation

For token creation, you can query local data stores to help fulfill the attribute contract in conjunction with attribute values supplied by the token processor you are using with PingFederate.

### About this task

The values supplied by the token processor are shown on the **Attribute Retrieval** tab, in the **Token Processor Contract** section.

To determine whether you need to look up additional values, compare the attribute contract against the token processor contract or the request contract, if configured. If the attribute contract requires more information, determine whether local data stores can supply it.



#### Note:

If you are editing a currently mapped token processor instance, you can change the mapping method, which may require additional configuration changes in subsequent tasks.

### Steps

1. Go to the **IdP Token Processor Mapping** window.
2. On the **Attribute Retrieval** tab, in the **Token Processor Contract** section, choose from the following options.  
Choose from:
  - Select the **Retrieve Additional Attributes from Data Stores to Fulfill the Attribute Contract** option if you want to configure one or more data stores to look up attribute for a single mapping.
  - Select the **Use only the Token Processor Contract Values in the Outgoing Token** option if you do not require data store query.
3. When finished, click **Next**.

### Configuring attribute sources and user lookup for token creation

Specify a series of local data stores from which data, along with the attributes supplied in the incoming token, will be used to fulfill the attribute contract.

### About this task

Attribute sources are specific data store or directory locations containing information that might be needed for the attribute contract. They are used to retrieve supplemental attributes. You can use more than one attribute source when mapping values to the attribute contract. The order matters and affects the queries differently. For example, if you plan on using the result of a query as an input to a subsequent query, stack your attribute sources accordingly.



#### Note:

If you are editing a currently mapped token processor instance, you can add, remove, or reorder attribute sources, which might require additional configuration changes in subsequent tasks.

### Steps

1. In the **IdP Token Processor Mapping** window, click the **Attribute Sources & User Lookup** tab.



#### Note:

The **Attribute Sources & User Lookup** tab is only visible if you selected the **Retrieve Additional Attributes from Data Stores to Fulfill the Attribute Contract** option on the **Attribute Retrieval** tab. For more information, see [Selecting an attribute retrieval method for token creation](#).

2. Click **Add Attribute Source**.  
Result: The **Attribute Sources & User Lookup** window configuration opens.
3. On the **Data Store** tab, choose a data store for PingFederate to look up attributes.
4. Enter a description in the **Attribute Source Description** field and a source ID in the **Attribute Source ID** field, if prompted, for the data store.
5. From the **Active Data Store** list, select a data store instance.



#### Tip:

If the data store you want is not shown in the **Active Data Store** list, click **Manage Data Stores** to review or add a data store instance.

6. Depending on the data store type, the rest of the setup varies as follows.

#### Data store types and their required tasks

| Data store type | Required tasks   |
|-----------------|--|
| JDBC            | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying database tables and columns</a> on page 399</li> <li>▪ <a href="#">Entering a database search filter</a> on page 400</li> </ul>  |
| LDAP            | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying directory properties and attributes</a> on page 401</li> <li>▪ <a href="#">Defining encoding for binary attributes</a> on page 403 (optional)</li> <li>▪ <a href="#">Entering a directory search filter</a> on page 404</li> </ul> |
| Other           | <ul style="list-style-type: none"> <li>▪ <a href="#">Specifying data source filters and fields</a> on page 405</li> </ul>  |

7. Repeat steps 2 - 6 as needed.
8. Click **Save** to exit the **Attribute Sources & User Lookup** window configuration.

#### Configuring contract fulfillment for token creation

Map values to the attributes defined for the contract. These are the values that are included in the SAML security tokens sent to the service provider (SP).

### Steps

In the **Token Creation | IdP Token Processor Mapping** window, on the **Attribute Contract Fulfillment** tab, for each attribute, select a source from the **Source** list and then choose or enter a value. You must map all target attributes.

- **Token**

When selected, the **Value** list is populated with attributes from the token processor instance. Select the desired attribute from the list. At runtime, the attribute value from the token processor instance is mapped to the value of the attribute in the SAML security token.

For example, to map the value of the Username Token Processor's **username** attribute as the value of the **TOKEN\_SUBJECT** attribute on the contract, select **Token** from the **Source** list and **username** from the **Value** list.

- **Context**

When selected, the **Value** list is populated with the available context of the transaction. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the SAML security token.



**Note:**

The **HTTP Request** and **STS SSL Client Certificate Chain** context values are retrieved as Java objects rather than text. For this reason, OGNL expressions are more appropriate to evaluate and return values, such as **Expression**.



**Note:**

When using the **STS Basic Authentication Username**, **STS SSL Client Certificate's Subject DN**, or **STS SSL Client Certificate Chain** contexts, ensure the associated authentication is enabled and configured on the **System # Server # Protocol Settings # WS-Trust STS Settings** tab.

- **Request**

When selected, the **Value** list populates with parameter values from the token request received from the web service client. This selection is available only if a request contract was selected earlier on the **Request Contract** tab. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the SAML security token.

- **LDAP, JDBC, or Other**

When selected, the **Value** list populates with attributes that you have selected in the **Attribute Source & User Lookup** window configuration. Select the desired attribute from the list. At runtime, the attribute value from the attribute source is mapped to the value of the attribute in the SAML security token.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under **Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

When selected, the text you enter is mapped to the value of the attribute in the single sign-on tokens at runtime. You can mix text with references to any of the values from the authentication source using the `${attribute}` syntax.

You can also enter values from your data store, when applicable, using the following syntax.

```
${ds.attr-source-id.attribute}
```

where `attr-source-id` is the attribute source ID value and `attribute` is any of the selected attributes in the attribute source configuration.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{` and `}` in the default value.



**Note:**

If you are editing a currently mapped token processor instance, you can update the mapping configuration, which might require additional configuration changes in subsequent tasks.

## Defining issuance criteria for token creation

### About this task

On the **Issuance Criteria** tab, define the criteria that must be satisfied in order for to process a request further. This token authorization feature provides the capability to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by adding a criterion. Choose the source that contains the attribute to be verified. Some sources, such as **Mapped Attributes**, are common to almost all use cases. Other sources, such as **JDBC**, depend on the type of configuration. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to be verified. Depending on the selected source, the available attributes or properties vary. Finally, specify the comparison method and the desired, compared-to, value.

If you define multiple criteria, all criteria must be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value depending on the chosen comparison method. The multi-value contains and multi-value does not contain comparison methods are intended for attributes that might contain multiple values. Such criterion is considered satisfied if one of the multiple values matches or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Important:**

When you multiplex one connection for multiple environments, consider using attribute mapping expressions to verify the virtual server ID in conjunction with other conditions, such as group membership information, to protect against unauthorized access. For more information, see [Multiple virtual server IDs](#) on page 115 and [Issuance criteria and multiple virtual server IDs](#) on page 229.



**Note:**


All criteria defined must be satisfied or evaluated as true for a request to move forward. As soon as one criterion fails, rejects the request and returns an error message.

### Steps


1. In the **Token Generator Mapping & User Lookup** configuration window, go to the **Issuance Criteria** tab.
2. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

### Attributes or properties and descriptions

| Source  | Description   |
|---|---|
| Context   | Select to evaluate properties returned from the context of the transaction at runtime.<br><br><div data-bbox="565 737 1472 940" style="border: 1px solid black; padding: 5px;">  <b>Note:</b><br/>           Because the <b>HTTP Request</b> and <b>STS SSL Client Certificate Chain</b> context values are retrieved as a Java object rather than text, use attribute mapping expressions to evaluate and return values.         </div> |
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.  |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.   |
| Token   | Select to evaluate attributes from the token processor instance.  |

3. Select the attribute to be evaluated under **Attribute Name**.

 **Note:**  
 To evaluate the **STS Basic Authentication Username**, **STS SSL Client Certificate Chain**, or **STS SSL Client Certificate's Subject DN** context value, ensure that the associated authentication is enabled and configured on **System # Server # Protocol Settings** to open the **WS-Trust STS Settings** window.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.



**Note:**

To evaluate the **STS SSL Client Certificate's Subject DN** context value, you must select one of the ... **DN** conditions. These methods normalize the DN before comparison to accommodate for different string representations that are still considered equivalent, such as case sensitivity or white space.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The **Error Result** field is used by the `faultstring` element for SOAP 1.1 and the **Reason/Text** element for SOAP 1.2. For more information on SOAP, see [Simple Object Access Protocol](#).

Using an error code in the **Error Result** field allows an application to process the code in a variety of ways, such as displaying an error message or e-mailing an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

9. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
- e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
- f. Optional: Repeat to add multiple criteria using attribute mapping expressions.

#### Reviewing the IdP token processor mapping

Review the identity provider (IdP) token processor mapping configuration to make and save changes as needed.

#### About this task

On the **Summary** tab, review, amend, save, or discard your configuration changes.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### Selecting a request error handling method

If you are using request parameters to fulfill the attribute contract and the parameter values are not supplied in the request token (RST) messages, you can choose whether to continue or abort the token-creation process.

#### About this task

On the **Error Handling** tab, select a request error handling method.

 **Note:**

On the **Request Contract** tab, you must select the **Request Contract** check box and configure a request contract for this connection for the **Error Handling** tab to appear after the **IdP Token Processor Mapping** tab.

#### Steps

1. Go to **Applications # Integrations # SP Connections** to choose the appropriate connection.
2. On the **WS-Trust STS** tab, click **Configure WS-Trust STS**.
3. On the **Token Creation** tab, click **Configure Token Creation**.



4. On the **Error Handling** tab, select one of the following options.  
Choose from:
  - To allow the STS transaction to continue with null attribute values sent in the generated token, select **Send User to SP Using Null Values for Attributes** .
  - To abort the STS transaction with null attribute values sent in the generated token, select **Abort the STS Transaction** .
5. Click **Next**.

#### *Reviewing the token creation configuration*

Review the token creation configuration to make changes as needed.

#### About this task

On the **Summary** tab, review, amend, save, or discard your token creation configuration changes.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### **Reviewing the IdP STS settings**

Review the identity provider (IdP) security token service (STS) settings to make and save changes as needed.

#### About this task

On the **Summary** tab, review, amend, save, or discard the IdP STS settings.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.



#### **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## Service provider STS configuration

This section covers the service provider (SP) configuration for security token service (STS).

### Managing token generators

The PingFederate security token service (STS) uses token generators to issue security tokens that can be consumed by web services at your site. You must configure at least one generator to set up an STS connection or a token-to-token mapping.

About this task

In the **Token Generators** window, create, modify, review, or remove a token generator instance.



#### Note:

PingFederate comes bundled with the SAML 1.1 Token Generator and SAML 2.0 Token Generator.

You can deploy additional token translators from [Ping Identity website](#).

For simplicity, this topic focuses on configuring an instance of the SAML 1.1 or 2.0 Token Generator. For information about add-on token generators, see [Integration overview](#) on page 65.

For more information about WS-Trust, see [Web services standards](#) on page 53.

Steps

1. Go to **Applications # Token Exchange # Token Generators**.
2. In the **Token Generators** window, choose from the following options.

| Option  | Description  |
|---|--|
| <b>Configure a new instance</b>               | Click <b>Create New Instance</b>   |
| <b>Modify an existing instance</b>            | Click the name of instance in the <b>Instance Name</b> column              |
| <b>View the usage of an existing instance</b> | Click <b>Check Usage</b> in the <b>Action</b> column on the instance's row |
| <b>Remove an existing instance</b>            | Click <b>Delete</b> in the <b>Action</b> column on the instance's row      |



#### Note:

By default, automatically checks multi-connection errors whenever you access this window. This verifies that configured connections are not adversely affected by changes made here.

If you experience noticeable delays in accessing this window, you can disable automatic connection validation. Go to **System # Server # General Settings**.

### Selecting a token generator type

Token generators issue tokens for security token service and OAuth token exchange use cases. Select instances of a token generator type to use in mapping and policy configuration.

About this task

The first step in creating a token-generator instance is choosing the generator type.

Steps

1. Go to **Applications # Token Exchange # Token Generators**.

2. Select an existing generator instance by clicking its name or click **Create New Instance** to open the **Create Token Generator Instance** window.
3. On the **Type** tab, enter a name in the **Instance Name** field and ID in the **Instance ID** field for the token generator instance.
4. From the **Type** list, select the token-generator type.
5. From the **Parent Instance** list, select an option.

This is useful when you are creating an instance that is similar to an existing instance. The child instance inherits the configuration of its parent. You have the option to override one or more settings during the rest of the setup. Select the **Override ...** check box and make the adjustments as needed in one or more subsequent tabs.

6. Click **Next**.

### Configuring a token generator instance

Configure the SAML token generator instance parameters depending on the use case requirements.

About this task

Depending on the selected token generator, the **Instance Configuration** tab presents you with different parameters.

Steps

1. Go to **Applications # Token Exchange # Token Generators**.
2. Select an existing generator instance by clicking its name or click **Create New Instance** to open the **Create Token Generator Instance** window.
3. On the **Instance Configuration** tab, configure the parameters for this instance type. For the integrated SAML 1.0 and 2.0 Token Generators, see the following table and specify parameters for generated SAML tokens.

### SAML token generator instance field names and descriptions

| Field                          | Instructions  |
|--------------------------------|---|
| Minutes Before                 | Enter a numerical value. This element in a SAML token allows for any server clock variability.  |
| Minutes After                  | Enter a numerical value. This element in a SAML token allows for any server clock variability.  |
| Issuer                         | Enter your SAML 2.0 entity ID or the SAML 1.x issuer as configured in the <b>System # Server # Protocol Settings</b> window.  |
| Signing Certificate            | Responses containing SAML tokens must be signed. Select a signing certificate from the list.<br><br>If you have not yet created or imported your certificate into PingFederate, click <b>Manage Signing Certificates</b> . For more information, see <a href="#">Manage digital signing certificates and decryption keys</a> on page 667. |
| Signing Algorithm              | Select the signing algorithm corresponding to the selected certificate. Choices include SHA1 for both RSA and DSA, RSA-SHA256, SHA384, and SHA512, as well as, ECDSA-SHA256, SHA384, and SHA512.  |
| Include Certificate in KeyInfo | If selected, the entire public certificate is included with the assertion. Otherwise, a short hash reference to the certificate is sent.  |
| Include Raw Key in KeyValue    | If selected, the raw key is included in the <b>KeyInfo</b> element as well.   |

| Field                            | Instructions  |
|----------------------------------|---|
| Audience                         | A unique identifier for the target web service, used for the <b>audience</b> element of the generated SAML token.   |
| Confirmation Method              | <p>Choose from among available methods:</p> <ul style="list-style-type: none"> <li>▪ <b>urn...cm:sender-vouches</b> Default option.</li> <li>▪ <b>urn...cm:bearer</b></li> <li>▪ <b>urn...cm:holder-of-key</b></li> </ul> <p>For more information, see <a href="#">WSS SAML Token Profile</a>.</p>  |
| Encryption Certificate           | <p>The web service provider's public certificate for encryption is required only if holder-of-key is selected as the confirmation method. Select a partner certificate from the list.</p> <p>If you have not yet imported the certificate from your partner, click <b>Manage Certificates</b> to do so. For more information, see <a href="#">Managing certificates from partners</a> on page 681.</p>  |
| Message Customization expression | <p>Click <b>Show Advanced Fields</b> to see this field.</p> <p>An OGNL expression to customize the assertion. The returned type from the expression must be an AssertionType, or the customization will be ignored.</p> <p>The available attributes are:</p> <ul style="list-style-type: none"> <li>▪ #AssertionType: org.sourceid.saml20.xmlbinding.assertion.AssertionType</li> <li>▪ #Attributes: org.sourceid.util.log.AttributeMap</li> </ul> <p>The following example is for SAML2. The line breaks are provided to improve readability.</p> <pre>#AssertionType   .getSubject()   .getNameID()   .setStringValue("JoeSAML2IDP"), #AssertionType</pre> <p>The following example is for SAML1.1.</p> <pre>#AssertionType   .getAuthenticationStatementArray(0)   .getSubject().getNameIdentifier()   .setStringValue("Joe123"), #AssertionType</pre> |

For information about add-on generators, see [Integration overview](#) on page 65.

4. Click **Next**.

### Extending a token generator contract

Token generators allow administrators to add to a built-in list of user attributes that the generator includes in the outgoing token—an extended generator-attribute contract.

About this task

The **Extended Contract** tab shows a different list of attributes in the **Core Contract** section, depending on the token generator selected.

### Steps

1. Go to **Applications # Token Exchange # Token Generators**.
2. Select an existing generator instance by clicking its name or click **Create New Instance** to open the **Create Token Generator Instance** window.
3. On the **Extended Contract** tab, in the **Extend the Contract** field, enter a name of the desired attribute. Click **Add**.

Repeat this step as needed to add another attribute.

4. Click **Next**.

### Reviewing the token generator configuration

Review, save, or make changes as needed to your token generator instance configuration.

### About this task

On the **Summary** tab, review, amend, save, or discard your token generator instance configuration.

### Steps

- To keep your changes, click **Save**.
- To amend your configuration, click the name of the corresponding tab and then follow the configuration wizard to complete the task.
- To discard your changes, click **Cancel**.

### Configuring IdP connections for STS

Configure a security token services (STS) connection to an identity provider (IdP) partner either in conjunction with browser-based single sign-on (SSO) or independently.

### Configuring protocol settings for SP STS

Configure the processing options for validating incoming SAML tokens in your identity provider (IdP) partner connection either in conjunction with browser-based single sign-on (SSO) or independently.

### About this task

Select whether the STS should validate incoming tokens only or validate and then generate other types of tokens.

### Steps

1. Go to **Authentication # Integration # IdP Connections**.
2. On the **WS-Trust STS** tab, click **Configure WS-Trust STS**.
3. On the **Protocol Settings** tab, from the **Request Processing Options** list, choose one of the following options:  
Choose from:
  - To only validate incoming SAML tokens, select **Validate Incoming SAML Token**.
  - To validate and then also generate local tokens to enable single sign-on (SSO) access to web services at your site, select **Validate Incoming SAML Token and Issue Local Token**.



#### Note:

If you choose to generate local tokens as well, you must set up at least one token generator.

### Configuring token generation

### About this task

Details of this configuration are handled under the Token Generation configuration.

## Steps

- Go to **Authentication # Integration # IdP Connections**.
- On the **WS-Trust STS** tab, click **Configure WS-Trust STS**.
- On the **Token Generation** tab, click **Configure Token Generation**.

Result: The **Token Generation** window opens.

### *Defining an attribute contract for SP STS*

An attribute contract is the set of user attributes expected in incoming SAML assertions. For more information, see [Attribute contracts](#) on page 101.

## About this task

On the **Attribute Contract** tab, identify the user attributes.

Optionally, you can mask the values of attributes, other than **SAML\_SUBJECT**, in logs that PingFederate writes when it receives security tokens.



### **Note:**

Use the **Edit**, **Update**, and **Cancel** workflows to make or undo a change to an item. Use the **Delete** and **Undelete** workflows to remove an item or cancel the removal request.

## Steps

1. Go to **Authentication # Integration # IdP Connections**.
2. On the **WS-Trust STS** tab, click **Configure WS-Trust STS**.
3. On the **Token Generation** tab, click **Configure Token Generation**.

Result: The **Token Generation** configuration window opens.

4. Click the **Attribute Contract** tab.
5. Enter the name in the **Extend the Contract** field.



### **Note:**

Attribute names are case-sensitive and must correspond to the attribute names expected by the requester.

6. Optional: Select the **Mask Values in Log** check box .
7. Click **Add**.
8. Repeat until all applicable attributes are defined.
9. Click **Next**.

### *Managing SP token generator mappings*

Token generators provide a mechanism through which PingFederate can generate a local token based upon an incoming SAML token, including mapping user attributes to be included in the generated token. A configured and deployed token generator in PingFederate is known as a token generator instance.

## About this task

In the **Token Generator Mapping & User Lookup** configuration window, manage service provider (SP) token generator mappings.

Map one or more token generator instances into an identity provider (IdP) connection to satisfy different token requirements by the web services at your site. The same token generator instances can be mapped in multiple connections.

When token generator instances are restricted to certain virtual server IDs, the allowed IDs are displayed under **Virtual Server IDs**.

#### Steps

1. Go to **Authentication # Integration # IdP Connections # WS-Trust STS**.
2. Click **Configure WS-Trust STS**.  
Result: The **WS-Trust STS** configuration window opens.
3. On the **Protocol Settings** tab, from the **Request Processing Options** list, select **Validate Incoming SAML Token and Local Issue Token**. Click **Next**.  
Result: This will add a **Token Generation** tab.
4. On the **Token Generation** tab, click **Configure Token Generation**.  
Result: The **Token Generation** configuration window opens.
5. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance** to open the **Token Generator Mapping & User Lookup** configuration window.  
Choose from:
  - To map a token generator instance, click **Map New Token Generator Instance**.
  - To edit the mapping configuration of a token generator instance, on the **Token Generator Instance** tab, click **Manage Token Generator** to open the **Token Generators** window. Click the token generator instance in the **Instance Name** section to open the configuration summary for this token generator instance. Select the setting that you want to reconfigure, and complete the change by clicking **Done**.
  - To remove a token generator instance or cancel the removal request, click **Delete** followed by **Save** or **Undelete**.
6. If you are creating a new connection and you are finished with mapping configuration, click **Done**. If you are editing an existing configuration and want to keep your changes, click **Save**.

#### Selecting a token generator instance

Select the token generator instance you would like to activate for incoming SAML messages from the service provider (SP) partner.

#### About this task



#### Note:

If you are editing a currently mapped token generator instance, you can toggle the **Override Instance Settings** setting. Clearing it removes all previously overridden settings for this connection. Selecting it provides you the opportunity to customize token processor settings specifically for this connection.

#### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance**.  
Result: The **Token Generator Mapping & User Lookup** configuration window opens.
2. On the **Token Generator Instance** tab, select an instance from the **Token Generator Instance**.



#### Note:

If you do not see the desired token generator instance, click **Manage Token Generator Instances** to create a new instance of any deployed token generator.

3. Select the **Override Instance Settings** check box to customize one or more token processor settings for this connection alone.

Result:

When selected, the administrative console adds a **Override Instance** tab and a its new set of sub tasks.

 **Tip:**

You can also create child token processor instances of a base token processor instance with overrides so that the customized settings can be applied to several connections. For more information, see [Hierarchical plugin configurations](#) on page 99.

4. Click **Next**.

#### Overriding a token generator instance

Make changes to the token generator instance to override it or to leave it as is and propagate it for a particular service provider connection.

About this task

Override token generator settings for a specific service provider connection.

 **Note:**

Any changes to the base token generator instance are propagated to a connection provided the same changes are not overridden for the connection.

#### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance**. .  
Result: The **Token Generator Mapping & User Lookup** configuration window opens.
2. On the **Override Instance** tab, select the **Override Instance Settings** check box.

 **Note:**

The override setting windows are functionally identical to those used for creating a new token generator instance. For more information, see [Managing token generators](#) on page 1066.

3. On each of the settings windows, select the **Override** check box, make your changes, and then click **Next**.
4. When you are finished, click **Done** to continue with the rest of the mapping configuration.

#### Restricting a token generator to certain virtual server IDs

Virtual server IDs provide more configuration flexibility in cases where you need to identify your server differently when connecting to a partner in one connection for multiple environments or in multiple connections where the partner also supports multiple federation IDs.

About this task

When you multiplex one connection for multiple environments, you can enforce integration requirements by restricting a token generator to certain virtual server IDs on the **Virtual Server IDs** tab. By default, no restriction is imposed. For more information, see .

 **Note:**



If you are editing a currently mapped token generator instance, you can toggle the **Restrict Virtual Server IDs** setting. You can also change the allowed virtual server IDs.

#### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance** to open the **Token Generator Mapping & User Lookup** configuration window.
2. Click the **Virtual Server IDs** tab.
3. Select the **Restrict Virtual Server IDs** check box.
4. Select one or more virtual server IDs that you want to allow for this token generator.

#### Selecting an attribute retrieval method for token generation

You can fulfill the token generator contract by using only the attributes from the incoming SAML token or by using these attributes to look up additional information from a local data store.

#### About this task

For token generation, you can query local data stores to help fulfill the token generator contract, in conjunction with attribute values supplied by the incoming token.

The values supplied by the token are shown in the **Attribute Contract** section on the **Attribute Retrieval** tab.

#### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance**.  
Result: The **Token Generator Mapping & User Lookup** configuration window opens.
2. On the **Attribute Retrieval** tab, select how you want to fulfill the token generator contract for an instance.  
Choose from:
  - If the incoming SAML token contains all the attributes that your application requires, select **Use only the attributes available in the incoming token**.
  - To set up a data store query, select **Use the incoming token to look up additional information** and then follow a series of sub tasks to complete the configuration.

For step-by-step instructions, see [Choosing a datastore](#) on page 398.



#### Note:

If you are editing a currently mapped token generator instance, you can change the mapping method, which might require additional configuration changes in subsequent tasks.

#### Configuring contract fulfillment for token generation

Fulfill your token generator contract requirements with values from the incoming SAML token, dynamic text, expressions, or from a data store lookup.

#### About this task

Map the values that the web services require to the attributes defined for the contract.

#### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance**.  
Result: The **Token Generator Mapping & User Lookup** configuration window opens.

2. On the **Token Generator Contract Fulfillment** tab, for each attribute, select a source from the **Source** list and then choose or enter a value. You must map all attributes.

- **Assertion**

When selected, the **Value** list populates with attributes from the incoming SAML token (assertion). Select the desired attribute from the list. At runtime, the attribute value from the assertion is mapped to the value of the attribute in the local token.

For example, to map the value of **TOKEN\_SUBJECT** from a SAML assertion as the value of the **subject** user identifier on the token generator contract, select **Assertion** from the **Source** list and **TOKEN\_SUBJECT** from the **Value** list.

- **Context**

When selected, the **Value** list populates with the available context of the transaction. Select the desired context from the list. At runtime, the context value is mapped to the value of the attribute in the local token.



**Note:**

Because the **HTTP Request** and **STS SSL Client Certificate Chain** context values are retrieved as Java objects rather than text, use OGNL expressions to evaluate and return values, see **Expression**.



**Note:**

When using the **STS Basic Authentication Username**, **STS SSL Client Certificate's Subject DN**, or **STS SSL Client Certificate Chain** contexts, ensure the associated authentication is enabled and configured on the **System # Server # Protocol Settings # WS-Trust STS Settings** tab.

- **LDAP, JDBC, or Other**

When selected, the **Value** list populates with attributes that you have selected from the data store. Select the desired attribute from the list. At runtime, the attribute value from the data store is mapped to the value of the attribute in the local token.

- **Expression**

When enabled, this option provides more complex mapping capabilities, such as transforming incoming values into different formats. Select **Expression** from the **Source** list, click **Edit** under

**Actions**, and compose your OGNL expressions. All variables available for text entries are also available for expressions. For more information, see **Text**.

Expressions are not enabled by default. For more information about enabling and editing OGNL expressions, see [Attribute mapping expressions](#) on page 225.

- **No Mapping**

Select this option to ignore the **Value** field.

- **Text**

When selected, the text you enter is used at runtime. You can mix text with references to any of the values from the SAML token, using the `${attribute}` syntax.

You can also enter values from your datastore, when applicable, using this syntax:

```
${ds.attribute}
```

where *attribute* is any of the attributes that you have selected from the data store.



**Tip:**

You can reference attribute values in the form of `${attributeName:-defaultValue}`. The default value is optional. When specified, it is used at runtime if the attribute value is not available. Do not use `{ and }` in the default value.



**Note:**

If you are editing a currently mapped token generator instance, you can update the mapping configuration, which might require additional configuration changes in subsequent tasks.

3. Click **Next**.

### Defining issuance criteria for token generation

PingFederate can evaluate various criteria to determine whether users are authorized to access service provider (SP) resources.

#### About this task

On the **Issuance Criteria** tab, define the criteria that must be satisfied in order for to process a request further. This token authorization feature provides the capability to conditionally approve or reject requests based on individual attributes.

Begin this optional configuration by adding a criterion. Choose the source that contains the attribute to be verified. Some sources, such as **Mapped Attributes**, are common to almost all use cases. Other sources, such as **JDBC**, depend on the type of configuration. Irrelevant sources are automatically hidden. After you select a source, choose the attribute to be verified. Depending on the selected source, the available attributes or properties vary. Finally, specify the comparison method and the desired, compared-to, value.

If you define multiple criteria, all criteria must be satisfied for to move a request to the next phase. A criterion is satisfied when the runtime value of the selected attribute matches or does not match the specified value depending on the chosen comparison method. The multi-value contains and multi-value does not contain comparison methods are intended for attributes that might contain multiple values. Such criterion is considered satisfied if one of the multiple values matches or does not match the specified value. Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions.



**Important:**

When you multiplex one connection for multiple environments, consider using attribute mapping expressions to verify the virtual server ID in conjunction with other conditions, such as group membership information, to protect against unauthorized access. For more information, see [Multiple virtual server IDs](#) on page 115 and [Issuance criteria and multiple virtual server IDs](#) on page 229.

 **Note:**


All criteria defined must be satisfied or evaluated as true for a request to move forward. As soon as one criterion fails, rejects the request and returns an error message.

### Steps

1. On the **Token Generator Mapping & User Lookup** tab, click **Map New Token Generator Instance**.  
Result: The **Token Generator Mapping & User Lookup** configuration window opens.
2. Click the **Issuance Criteria** tab.
3. In the **Source** list, select the attribute's source.

Depending on the selection, the **Attribute Name** list populates with associated attributes. See the following table for more information.

#### Source entries and descriptions

| Source  | Description  |
|---|--|
| Context   | Select to evaluate properties returned from the context of the transaction at runtime.<br><br> <b>Note:</b><br>Because the <b>HTTP Request</b> and <b>STS SSL Client Certificate Chain</b> context values are retrieved as a Java object rather than text, use attribute mapping expressions to evaluate and return values. |
| <b>JDBC, LDAP</b> , or other types of datastore (if configured) | Select to evaluate attributes returned from a data source.   |
| <b>Mapped Attributes</b>  | Select to evaluate the mapped attributes.  |
| Token   | Select to evaluate attributes from the incoming SAML token.  |

4. Select the attribute to be evaluated in the **Attribute Name** column.

 **Note:**

To evaluate the **STS Basic Authentication Username**, **STS SSL Client Certificate Chain**, or **STS SSL Client Certificate's Subject DN** context value, ensure that the associated authentication is enabled and configured on **System # Server # Protocol Settings** to open the **WS-Trust STS Settings** window.

- In the **Condition** list, select the comparison method.

Available methods:

- **equal to**
- **equal to (case insensitive)**
- **equal to DN**
- **not equal to**
- **not equal to (case insensitive)**
- **not equal to DN**
- **multi-value contains**
- **multi-value contains (case insensitive)**
- **multi-value contains DN**
- **multi-value does not contain**
- **multi-value does not contain (case insensitive)**
- **multi-value does not contain DN**



**Note:**

The first six conditions are intended for single-value attributes. Use one of the **multi-value ...** conditions for to validate whether one of the attribute values matches the specified value. When an attribute has multiple values, using a single-value condition causes the criteria to fail.



**Note:**

To evaluate the **STS SSL Client Certificate's Subject DN** context value, you must select one of the ... **DN** conditions. These methods normalize the DN before comparison to accommodate for different string representations that are still considered equivalent, such as case sensitivity or white space.

- In the **Value** field, enter the comparison value.



**Note:**

Values are compared verbatim. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions. For more information, see [Attribute mapping expressions](#) on page 225.

- In the **Error Result** field, enter a custom error message.

The **Error Result** field is used by the `faultstring` element for SOAP 1.1 and the **Reason/Text** element for SOAP 1.2. For more information on SOAP, see the World Wide Web Consortium's [Simple Object Access Protocol](#).

Using an error code in the **Error Result** field allows an application to process the code in a variety of ways, such as display an error message or e-mail an administrator.

To use localized descriptions, enter a unique alias in the **Error Result** field, such as `someIssuanceCriterionFailed`. Insert the same alias with the desired localized text in the applicable language resource files, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

If not defined, returns `ACCESS_DENIED` when the criterion fails at runtime.

- Click **Add**.
- Optional: Repeat to add more criteria.

10. If you require complex evaluations, including conditional criteria or partial matching, define them using attribute mapping expressions
  - . For more information, see [Attribute mapping expressions](#) on page 225.
  - a. Click **Show Advanced Criteria**.
  - b. In the **Expression** field, enter the required expressions.
  - c. Optional: In the **Error Result** field, enter an error code or message.

 **Note:**

If the expressions resolve to a string value instead of `true` or `false`, the returned value overrides the **Error Result** field value.

- d. Click **Add**.
  - e. Optional: Click **Test**, enter values in the applicable fields, and verify the results.
  - f. Optional: Repeat to add multiple criteria using attribute mapping expressions.
11. When finished, click **Next**.

#### Reviewing the SP token generator mapping

Review the service provider (SP) token generator mapping instance.

#### About this task

On the **Summary** tab, review, amend, save, or discard your changes.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

#### Reviewing the token generation configuration

Review the token generation configuration to make changes or save as needed.

#### About this task

On the **Summary** tab, review, amend, save, or discard your configuration.

#### Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

 **Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

### Reviewing the SP STS configuration

Review the service provider (SP) security token service (STS) configuration to make changes or save as needed.

About this task

On the **Summary** tab, review, amend, save, or discard your changes.

Steps

- To amend your configuration, click the corresponding tab title, then follow the configuration wizard to complete the task.
- To keep your changes, click **Done** and continue with the rest of the configuration.

**Tip:**

When editing an existing configuration, you can also click **Save** as soon as the administrative console offers the opportunity to do so.

- To discard your changes, click **Cancel**.

## PingFederate Performance Tuning Guide

---

This section shows you how to fine-tune a few simple application and system level settings to enable PingFederate to achieve maximum performance of the hardware chosen for your deployment.

The default configuration since PingFederate 10.2 is acceptable for most small size deployments. Mission-critical and high-transaction volume deployments might require additional tuning.

This guide addresses several areas of tuning such as logging, concurrency, memory, and Java-specific tuning options. It is not designed as a one-size-fits-all set of instructions to optimize PingFederate, but more as a checklist of suggestions for areas of the product that can be tuned to improve performance, and any tradeoffs associated with those changes. For ultimate reassurance that any fine-tuned settings will meet your expectations, performance testing in a lab environment is recommended.

### Logging

---

This section explains the logging practices of PingFederate and discusses minimizing the system's overall performance impact.

Logging tracks various aspects of the system's overall performance and requires a certain amount of system resources, which affects the system's overall performance. In particular, writing to the log files takes the greatest amount of resources. To minimize the performance impact, PingFederate uses the high-performance asynchronous logger from Log4j 2 for logging runtime and administrative events, including status and error messages used for troubleshooting. To preserve transactional integrity, audit information logs synchronously.

Although the bulk of logging is executed asynchronously, decreasing the amount of information written to log files always provides the best possible performance.

only records messages tagged with log level `INFO`, `WARN`, `ERROR`, and `FATAL` to the server log and the provisioner log. Messages with `DEBUG`, or `TRACE` tags, are not recorded to optimize performance. Console logging is also disabled for the same reason.

For troubleshooting purposes, you can adjust the log level to `DEBUG` in the `log4j2.xml` file and re-enable console logging.

**Important:**

When you no longer require debug messages and console logging, turn them off. On Windows, never highlight the console output because it might slow or stop from processing requests.

## Operating system tuning

---

This section contains tuning recommendations for your operating system.

The tuning recommendations provided here work best in preventing deployment issues in high capacity environments.

### Linux tuning

Follow these recommendations for your Linux environment to prevent deployment issues, to increase the performance and capacity of the networking stack, particularly TCP and the file descriptor usage, and to enable PingFederate to handle a high volume of concurrent requests.

#### Network/TCP tuning

For SystemV, add or modify the following entries in the `/etc/sysctl.conf` file.

For systemd, you can create a sysctl preload/configuration file in `/etc/sysctl.d` (for example, `99-sysctl.conf`) in which to add and modify the following entries.

```
##TCP Tuning##
# Controls the use of TCP syncookies (default is 1)
# and increase the number of outstanding syn requests allowed.
net.ipv4.tcp_syncookies=1
net.ipv4.tcp_max_syn_backlog=8192

# Increase number of incoming connections.
# somaxconn defines the number of request_sock structures allocated
# per each listen call.
# The queue is persistent through the life of the listen socket.
net.core.somaxconn=4096

# Increase number of incoming connections backlog queue.
# Sets the maximum number of packets, queued on the INPUT side,
# when the interface receives packets faster
# than kernel can process them.
net.core.netdev_max_backlog=65536

# increase system IP port limits
net.ipv4.ip_local_port_range=2048 65535

# Turn on window scaling which can enlarge the transfer window:
net.ipv4.tcp_window_scaling=1

# decrease TCP timeout
net.ipv4.tcp_fin_timeout=10

# Allow reuse of sockets in TIME_WAIT state for new connections
# (While this may increase performance, use with caution according
# to the kernel documentation. This setting should only be enabled
# after the system administrator reviews security considerations.)
net.ipv4.tcp_tw_reuse=1

# Increase the read and write buffer space allocatable
# (minimum size, initial size, and maximum size in bytes)
```



```
net.ipv4.tcp_rmem = 4096 65536 16777216
net.ipv4.tcp_wmem = 4096 65536 16777216

# The maximum number of packets which may be queued
# for each unresolved address by other network layers
net.ipv4.neigh.default.unres_qlen=100
net.ipv4.neigh.eth0.unres_qlen=100
net.ipv4.neigh.em1.unres_qlen=100

# Default Socket Receive and Write Buffer
net.core.rmem_default=8388608
net.core.wmem_default=8388608
#####
```

### Increase file descriptor limits

Add or modify the following lines in the `/etc/security/limits.conf` file where `pf_user` is the user account used to run the PingFederate java process or `*` for all user accounts.

```
pf_user soft nofile 10400
pf_user hard nofile 10400
```

## Windows tuning

Follow these recommendations for your Windows environment to prevent deployment issues, to increase the performance and the capacity of the networking stack, specifically the TCP socket, and to enable PingFederate to handle a high volume of concurrent requests.

### About this task

Use Command Prompt and a Registry Editor to edit the `cmd.exe` file and the `regedit.exe` file respectively.

### Steps

1. Edit the `jvm-memory.options` file with a time stamp.
  - a. Start the Command Prompt application `cmd.exe`.
  - b. Enter `netsh int ipv4 show dynamicportrange tcp` to view the ephemeral ports.
  - c. Enter `netsh int ipv4 set dynamicport tcp start=1025 num=64510` to increase the range of the ephemeral ports using administrative privileges.
  - d. Reboot the server.
  - e. Enter `netsh int ipv4 show dynamicportrange tcp` to confirm the updated port range.
2. Reduce socket `TIME_WAIT` delay.
  - a. Start the Registry Editor application `regedit.exe`.
  - b. Go to `HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\Tcpip\Parameters`.
  - c. Create a new `DWORD 32 bit` value and set the name as `TcpTimedWaitDelay`.
  - d. Set a decimal value of 30.
  - e. Reboot the server.

## Concurrency

---

This section describes how to configure PingFederate to support more concurrent requests to optimize your deployment.

The more requests processed in parallel, the more requests processed over all. Given the appropriate amount of hardware, processing  $N$  requests concurrently is typically faster than processing  $N$  requests serially.

In PingFederate, there are two main pools of threads that control the level of concurrent user requests: Acceptor Threads and Server Threads. Acceptor threads receive the HTTPS requests and pass those requests on to available server threads to be processed.

### Caveats

This topic serves as a guideline for optimizing the concurrency of your deployment. On a large system with multiple CPUs, or cores, a thread pool that is too small will under-utilize the available processor resources. A thread pool that is too large can cause the system to become flooded and unusable.

A good target for the CPU is between 60%-80% utilization when under nominal, standard user load. This way CPU resources are not under-utilized while still allowing room for occasional load spikes. The level of concurrency in PingFederate might need to be decreased, or even increased, depending on the system's configuration, the adapters in use, available memory, and other processes competing for resources. All deployments are different. This section serves as a guideline of where to start when tuning the server.

## Tuning the acceptor queue size

For optimal performance, particularly in larger deployments, PingFederate uses a non-blocking I/O model to process requests. You can tune the acceptor queue size parameters for your environment.

### About this task

If the request queue reaches its maximum size, additional requests will receive a connection refused error. If this occurs in your environment, you can increase the values of the acceptor queue size parameters `pf.admin.acceptQueueSize` and `pf.runtime.acceptQueueSize`. The `pf.admin.acceptQueueSize` parameter applies to the administrative console and the `pf.runtime.acceptQueueSize` parameter applies to the engine nodes.

### Steps

1. Stop PingFederate.
2. Open the `<pf_install>/pingfederate/bin/run.properties` file in an editor.



**Tip:**

Consider making a backup copy of this file.

3. Go to the following section and change the values of the `pf.admin.acceptQueueSize` and `pf.runtime.acceptQueueSize` parameters.

```
# HTTP Connector Queue Size Settings
# -----
# The following properties control the queue size of the HTTP connector.
#
# Please refer to the performance tuning guide for further tuning
# guidance.
pf.admin.acceptQueueSize=512
pf.runtime.acceptQueueSize=512
```

4. Save your changes and restart PingFederate.
5. For a clustered PingFederate environment, repeat the previous steps on each engine node.

## Tuning the server thread pool

When tuning the server thread pool, set the minimum and maximum number of threads to optimize PingFederate for your needs.

### About this task

Set the minimum and maximum numbers according to the expected user load:

- Set the minimum number of threads to between 75% and 100% of the number of requests you expect the system to handle most often.
- Set the maximum number of threads to between 25% and 50% higher than the minimum to handle load spikes.

Performance testing offers an alternative guideline. Testing shows that PingFederate performs well when the server thread pool has 25 to 50 server threads per available CPU core, assuming sufficient memory. For example, if your PingFederate system has one CPU with four cores, the total available cores is four. In that case, the minimum thread value would be 100 and the maximum thread value would be 200.



### Note:

This alternative guideline might not apply to larger systems. For example, if PingFederate is running on a system with 24 CPU cores, it doesn't make sense to size the thread pool at a minimum of 600 threads and a maximum of 1200 unless you expect to normally handle at least 800 concurrent requests.

For more information on managing memory for PingFederate, see [Memory](#) on page 1085.

### Steps

1. Stop PingFederate.
2. Edit the `<pf_install>/pingfederate/bin/run.properties` file.



### Tip:

Consider making a backup copy of this file.

3. Go to the following section, and change the thread number.

```
# HTTP Server Thread Pool Settings
# -----
# The following properties control the minimum and the maximum number of
# threads used to configure PingFederate thread pools.
#
# Please refer to the performance tuning guide for further tuning
# guidance.
pf.admin.threads.min=1
pf.admin.threads.max=10
pf.runtime.threads.min=10
pf.runtime.threads.max=200
```

4. Save your changes and restart PingFederate.
5. For a clustered PingFederate environment, repeat the previous steps on each engine node as needed.

## Configuring connection pools to datastores

Java Database Connectivity (JDBC) and LDAP datastores use connection pooling to improve the performance and efficiency of communicating with external systems. For optimal performance, a number of connections are required to handle most or all the requests in parallel.

### About this task

In the **Data & Credential Stores** window, set the minimum and maximum values for connection pools to JDBC and LDAP data stores.

Connection pools improve efficiency by maintaining persistent connections to the JDBC or LDAP server preventing the expense of creating the connection on demand. Connection pools also allow more control over the load placed on the back-end server. It might not be necessary to have a connection available for every concurrent request received by the server, but having too few available will cause requests to wait when accessing JDBC and LDAP resources.



**Important:**

Size the connection pool based on the capacity and limitation of the database or LDAP server. Sizing the connection pool beyond the capability of the back-end server could lead to PingFederate flooding the datastore without any performance improvement. For optimal performance, size connection pools large enough to handle between 50% and 100% of the number of concurrent requests the server is expected to encounter often. For more information on optimizing the connection pool, see [Best practices for tuning the JDBC connection pool](#) in the Ping Identity Knowledge Base.

### Steps

1. Choose from configuring connection pools to JDBC or LDAP datastores:

| Datastore type  | Configuration steps  |
|---|--|
| <p><b>Configuring connection pools to JDBC datastores</b></p> | <ol style="list-style-type: none"> <li>Go to <b>System # Data &amp; Credential Stores # Data Stores</b>, and select the applicable JDBC datastore.</li> <li>Go to <b>Database Config # Advanced</b>.</li> <li>On the <b>Advanced Database Options</b> window:                             <ol style="list-style-type: none"> <li>Set the <b>Minimum Pool Size</b> value to 50% of the <b>maxThreads</b> value.</li> <li>Set the <b>Maximum Pool Size</b> value to between 75% and 100% of the <b>maxThreads</b> value, subject to the capability of the back-end database server.</li> </ol> </li> </ol> <div data-bbox="971 1528 1471 1780" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Remember:</b><br/>The <b>maxThreads</b> value is defined in the <code>&lt;pf_install&gt;/pingfederate/etc/jetty-runtime.xml</code> file. For more information, see <a href="#">Tuning the server thread pool</a> on page 1083).</p> </div> |
| <p><b>Configuring connection pools to LDAP datastores</b></p> | <ol style="list-style-type: none"> <li>Go to <b>System # Data &amp; Credential Stores # Data Stores</b>, and select the applicable LDAP datastore.</li> </ol>  |

| Datastore type | Configuration steps  |
|----------------|--|
|                | <ul style="list-style-type: none"> <li>b. Go to the <b>LDAP Configuration # Advanced # Advanced LDAP Options</b>.</li> <li>c. Set the <b>Minimum Connections</b> value to 50% of the <code>maxThreads</code> value.</li> <li>d. Set the <b>Maximum Connections</b> value to between 75% and 100% of the <code>maxThreads</code> value, subject to the capability of the back-end database server.</li> </ul> |

2. For a clustered PingFederate environment, replicate the changes to all engine nodes on the **System # Server # Cluster Management** window.

## Snapshot isolation for high-volume transactions

Because deadlocks can occur in some tables in high-concurrency environments with contention for shared data, you can enable `READ_COMMITTED_SNAPSHOT` in SQL Server to improve the performance and scalability of applications with long-running transactions.

When snapshot isolation is enabled, each transaction reads data from a snapshot of the database taken at the start of the transaction rather than directly from the database itself.

Because there can be some overhead with snapshot isolation, evaluate and test this setting carefully before deploying in production environments. For more information on snapshot isolation and how to configure the option, see [Snapshot Isolation in SQL Server](#) in the Microsoft documentation.

## Memory

---

After the CPU, memory is the most important resource for sizing Java virtual machine (JVM) heap, managing garbage collection, and optimizing the overall performance of your PingFederate deployment.

The Concurrency section describes how to configure PingFederate to support more concurrent requests. This section highlights how supporting increasing concurrency requests can affect PingFederate's performance because these requests require an increase in memory. Because PingFederate is a Java application, it is important to consider how tuning affects, or is affected by, garbage collection. This section is not a guide to garbage collection theory or ergonomics.

### JVM heap

The most important tuning for the Java Virtual Machine (JVM) is the size of the heap memory, which ensures adequate memory is available to manage garbage collection and optimize overall performance.

If the demands require more memory than what is currently available, the JVM must grow the heap, if it can, or perform garbage collection to provide memory to allocate. Resizing the heap and garbage collecting can be an expensive processes and negatively impact performance. Sizing the heap to ensure an adequate amount of memory is available but still manageable to garbage collection is important in optimizing overall performance.

PingFederate attempts to optimize JVM heap and garbage collector settings based on available system resources at the time of installation and upgrade. Depending on your environment, you can override these settings at a later time.

#### Additional considerations

The JVM can grow the heap from the minimum heap variable value up to the maximum heap variable value. However, growing the heap is often an expensive exercise and requests memory from the operating system. In addition, the JVM must also reorganize the heap to account for the memory being added. To conserve memory in your deployment, set a lower value for the minimum heap than that of the maximum

heap to ensure you are not reserving unused memory. If you have enough memory that a certain amount is easily earmarked for the PingFederate server, adjust the size of the heap by setting the minimum heap and maximum heap to the same value. This allows the JVM to reserve its entire heap and decrease the amount of resizing that the JVM needs to perform if the amount of memory in use exceeds the value of the minimum heap.

## Garbage collectors

Although the Java virtual machine (JVM) configures itself for optimal performance for most situations, it is advantageous to configure it for a specific application.

This section explores additional tuning options to improve the PingFederate service in your deployment. In all cases, test these options to ensure that they do benefit your deployment before enabling them in a production environment.

### Parallel collector

By default, the server HotSpot JVM selects the parallel collector on machines with multiple CPUs or cores. On machines with a single CPU, the serial collector is used.

On machines with eight or more hardware threads, the parallel collector uses a fraction of them as the number of garbage collector threads; the fraction is roughly 5/8. If the number of hardware threads drops below 8, the number of garbage collector threads matches the number of hardware threads.

The number of garbage collector threads can be overridden by the `-XX:ParallelGCThreads=n` JVM option, where *n* is the desired number of garbage collector threads. It is generally recommended to leave `ParallelGCThreads` as the default. Specifically, setting to a value greater than the number of CPUs will not improve garbage collection performance as the GC threads will all contend for CPU time, causing the operating system to context switch between them. Setting to less than the number of CPUs can cause longer than necessary pause times because not all available CPU resources will be utilized.

The parallel collection is generational, so minor (young generation only) and major (entire heap) collections do occur. Because PingFederate uses a much larger proportion of short to medium lived objects, consider applying a young generation bias to the JVM heap, which will improve performance because the parallel scavenge copying collector used for the young generation is fast. For more information, see [Young generation bias](#) on page 1087.

### Concurrent mark sweep collector

The concurrent mark sweep (CMS) collector suits applications that prefer shorter garbage collection pauses, can afford to share CPU resources with the garbage collector, have a large set of long-lived objects in the tenured (or old) generation, and run on machines with multiple CPUs.

The CMS collection is generational, so minor, young generation only, and major, entire heap, collections occur. Because PingFederate uses a much larger proportion of short to medium lived objects, the CMS collector is not generally the best fit. However, if you use a JVM heap greater than 6 GB on larger machines with eight or more CPUs, the CMS collector can provide shorter pause time than the parallel collector in major collections. Applying a young generation bias to the JVM heap will improve performance when using the CMS collector because it employs the same parallel scavenge copying collector for the young generation as the parallel collector.

Enable the CMS collector using the `-XX:+UseConcMarkSweepGC` JVM option as needed.

### Garbage first collector

The garbage first (G1) collector is best for machines with multiple CPUs and a JVM heap of 6 GB or more. The G1 collector is designed to achieve high throughput while meeting its pause times goal for garbage collection.



**Important:**

When using the G1 Collector, it is best to remove any sizing options specific to the young generation. The G1 collector self-tunes by adjusting the size and nature of the various heap regions to meet the pause time goal. By setting a fixed amount of memory to be used for young generation regions, it limits its self-tuning options.

When applicable, you can enable the G1 collector using the `#XX:+UseG1GC` JVM option.

For more information about each garbage collector, see [Java Platform, Standard Edition HotSpot Virtual Machine Garbage Collection Tuning Guide](#) from Oracle.

## Young generation bias

An overview of the generation memory management model in Java and the processing model of PingFederate, how they create, collect, and manage objects, and how to optimize both for your deployment needs.

In the Java generational memory management model, the young generation creates new objects and the garbage collector gathers them when they are no longer used. For example, if the young generation creates a new object, and a reference is maintained, then the garbage collector moves that object to the old generation.



### Tip:

If you intend to use the garbage first (G1) collector, let the Java virtual machine (JVM) handle this aspect of the heap because specific settings can affect the performance of the G1 collector adversely.

For more information on fine-tuning memory and garbage collection settings and instructions, see [Fine-tuning JVM options](#) on page 1094.

The processing model of PingFederate is mostly geared towards short-lived transactions, such as single sign-on and token processing and not long-held, interactive, user sessions. Because most of the objects created are relatively short-lived, it does not make sense to promote short-lived objects to the old generation because they are not needed for long. When the young generation fills up, space must be made for new objects. To allow for more space, objects still in use in the young generation must be moved to the old generation. Moreover, those objects will become garbage and need to be collected from the old generation.

The old generation is typically more expensive to clean up than the young generation. The old generation is cleaned only during a full garbage collection, which happens when the JVM has almost reached the value of the maximum heap variable `-Xmx` and the entire heap must be cleaned. With multiple threads by default on systems with multiple cores, the young generation is garbage collected more often and so the pauses for collections are shorter.

By default, the JVM tends to size the generations biased to the old generation, giving it most of the space of the heap. This results in moving objects more frequently from the young generation into the old generation to make space for new objects, and more frequent full collections as the old generation fills up. By configuring the JVM to provide more memory to the young generation, it reduces the frequency of full, more costly, collections. You can either specify fixed values for the size of the young generation or modify the ratio of young generation to old generation.

To specify a fixed value for the young generation, use the `-XX:NewSize=` and `-XX:MaxNewSize=` arguments. These arguments are to the young generation what the minimum heap variable (`-Xms`) and the maximum heap variable (`-Xmx`) are to the entire heap. The `-XX:NewSize=` and `-XX:MaxNewSize=` arguments define the initial or minimum and the maximum sizes of the young generation. The same reasoning that applies to the minimum and maximum heap variables also applies when adjusting these values.

To specify a ratio between the old and new generation size, use the `-XX:NewRatio=` argument. For example, setting `-XX:NewRatio=3` means that the ratio between the young and old generation is 1:3. The size of the young generation is 25% of the total heap size.

In a mostly short-lived object environment, give 50 - 60% of the heap to the young generation. See the following table for examples.

### Setting the JVM options according to young generation sizing

| Young generation bias condition  | JVM options  |
|--|--|
| To fix a heap size of 2 GB with 50% the young generation bias using the <code>NewSize</code> argument  | <pre>-Xms2048m -Xmx-2048m -XX:NewSize=1024m -XX:MaxNewSize=1024m</pre> |
| To fix a heap size of 2 GB with 50% the young generation bias using the <code>NewRatio</code> argument | <pre>-Xms2048m -Xmx-2048m -XX:NewRatio=1</pre>                         |

## The memoryoptions utility

Where to find the `memoryoptions` utility in a PingFederate installation and how the utility's expected behavior differs in a Linux or Windows system.

PingFederate installation and upgrade tools use the `memoryoptions` utility to detect the available resources at the time of the installation or upgrade and record the recommended options for Java heap and the garbage collector in a configuration file. As needed, administrators can re-run the utility or manually edit the configuration file.

The `memoryoptions` utility, located in the `<pf_install>/pingfederate/bin` directory, comes in two variants:

- `memoryoptions.bat` for Windows
- `memoryoptions.sh` for Linux

The configuration file, `jvm-memory.options`, is located in the same `bin` directory.



#### Important:

You should not use the `memoryoptions` script when you deploy PingFederate inside of a container. Instead, you should edit the `jvm-memory.options` file directly. In containers, you should use the `InitialRAMPercentage` and `MaxRAMPercentage` JVM options to control the size of the heap.

## Installation and upgrade

When the installer is executed for Windows or a subsequent rerun of the `memoryoptions` utility, it creates a backup copy of the current `jvm-memory.options`, if any, detects available system resources at the time, and records the recommended options in the `jvm-memory.options` file. Changes made as a result of the execution of the utility or a manual edit are activated after a restart of .

Depending upon the selected tool and whether the `jvm-memory.options` file exists in the source installation, the expected behavior of the `memoryoptions` utility differs. In general, the `jvm-memory.options` file from the source installation is preserved without new recommended values.



**memoryoptions and installation**

When the PingFederate installer for Windows runs the **memoryoptions** utility tool or when changes are made from a manual edit, expect the following behaviors to the installation medium.

The PingFederate installer for Windows runs the **memoryoptions** utility in an attempt to optimize the Java virtual machine (JVM) heap and garbage collector options based on available system resources at the time of installation. As needed, administrators can rerun the utility or manually edit these options at a later time.

When the installer is executed for Windows or a subsequent rerun of the **memoryoptions** utility, it creates a backup copy of the current `jvm-memory.options`, if any, detects available system resources at the time, and records the recommended options in the `jvm-memory.options` file. Changes made as a result of the execution of the utility or a manual edit are activated after a restart of . See the following table for information regarding expected behaviors.

 **Important:**

You should not use the `memoryoptions` script when you deploy PingFederate inside of a container. Instead, you should edit the `jvm-memory.options` file directly. In containers, you should use the `InitialRAMPercentage` and `MaxRAMPercentage` JVM options to control the size of the heap.

**PingFederate installation mediums and their expected behaviors from the execution of the `memoryoptions` utility tool**

| Installation medium   | Expected behavior  |
|-----------------------|--|
| installer for Windows | <ul style="list-style-type: none"> <li>▪ The installer creates a new installation.</li> <li>▪ The installer runs the <b>memoryoptions</b> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and to record them in the <code>jvm-memory.options</code> file.</li> <li>▪ The installer configures to run as a service.</li> <li>▪ The recommended options are activated as the service starts.</li> </ul> |

| Installation medium                        | Expected behavior   |
|--|---|
| PingFederate product distribution ZIP file | <p>The default <code>jvm-memory.options</code> file becomes part of the new installation as program and default configuration files are extracted from the PingFederate product distribution <code>.zipfile</code>.</p> <p>PingFederate as a console application on Windows <i>or</i> as a console application, or a service on Linux</p> <ul style="list-style-type: none"> <li>▪ The JVM options set in the default <code>jvm-memory.options</code> file are activated as <code>starts</code>.</li> <li>▪ The default JVM options are conservative. For most deployment scenarios using various physical or virtual resources, run the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> <li>▪ As a result of the execution of the <code>memoryoptions</code> utility or a manual edit of the <code>jvm-memory.options</code> file, the JVM options are activated as <code>restarts</code>.</li> </ul> <p>as a service on Windows</p> <ul style="list-style-type: none"> <li>▪ When administrators run the service-installation program <code>install-service.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/win-x86-64</code> directory, to install the Windows service manually, the program runs the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> </ul> <p>The service-installation program then runs a helper utility <code>generate-wrapper-jvm-options.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/wrapper</code> directory, to read the JVM options from the <code>jvm-memory.options</code> file and create a resource file that the Windows service requires to configure its JVM options.</p> <ul style="list-style-type: none"> <li>▪ The recommended options are activated as the <code>service</code> starts.</li> </ul> |

### memoryoptions and upgrade

Upgrade paths behave differently when changes are executed based on the recommendations and execution of the `memoryoptions` utility tool.

Depending upon the selected tool and whether the `jvm-memory.options` file exists in the source installation, the expected behavior of the `memoryoptions` utility differs. In general, the `jvm-memory.options` file from the source installation is preserved without new recommended values. See the following table for information regarding expected behaviors.



#### Important:


You should not use the `memoryoptions` script when you deploy PingFederate inside of a container. Instead, you should edit the `jvm-memory.options` file directly. In containers, you should use the `InitialRAMPercentage` and `MaxRAMPercentage` JVM options to control the size of the heap.

## PingFederate upgrade paths and their expected behaviors from the execution of the `memoryoptions` utility tool

| Upgrade path  | Expected behavior when the <code>jvm-memory.options</code> file does not exist in the source installation  |
|---|--|
| installer for Windows                                     | <ul style="list-style-type: none"> <li>▪ The installer creates a new installation.</li> <li>▪ The installer runs the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and to record them in the <code>jvm-memory.options</code> file.</li> <li>▪ The installer configures to run as a service.</li> <li>▪ The recommended options are activated as the service starts.</li> </ul>   |
| PingFederate Upgrade Utility ( <code>upgrade.bat</code> ) | <p>The upgrade utility creates a new installation based on the source installation and the product distribution <code>.zip</code> file. The default <code>jvm-memory.options</code> file becomes part of the new installation as the upgrade utility extracts files from the product distribution <code>.zip</code> file.</p> <p>PingFederate as a console application on Windows</p> <ul style="list-style-type: none"> <li>▪ The JVM options set in the default <code>jvm-memory.options</code> file are activated as starts.</li> <li>▪ The default JVM options are conservative. For most deployment scenarios using various physical or virtual resources, run the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> <li>▪ As a result of the execution of the <code>memoryoptions</code> utility or a manual edit of the <code>jvm-memory.options</code> file, the JVM options are activated as restarts.</li> </ul> <p>as a service on Windows</p> <ul style="list-style-type: none"> <li>▪ When administrators run the service-installation program <code>install-service.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/win-x86-64</code> directory, to install the Windows service manually, the program runs the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> </ul> <p>The service-installation program then runs a helper utility <code>generate-wrapper-jvm-options.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/wrapper</code> directory, to read the JVM options from the <code>jvm-memory.options</code> file and create a resource file that the Windows service requires to configure its JVM options.</p> <ul style="list-style-type: none"> <li>▪ The recommended options are activated as the service starts.</li> </ul> |

| Upgrade path                              | Expected behavior when the <code>jvm-memory.options</code> file does not exist in the source installation  |
|---|--|
| PingFederate Upgrade Utility (upgrade.sh) | <ul style="list-style-type: none"> <li>▪ The upgrade utility creates a new installation based on the source installation and the product distribution <code>.zip</code> file. The default <code>jvm-memory.options</code> file becomes part of the new installation as the upgrade utility extracts files from the product distribution <code>.zip</code> file.</li> <li>▪ The JVM options set in the default <code>jvm-memory.options</code> file are activated as <code>starts</code>.</li> <li>▪ The default JVM options are conservative. For most deployment scenarios using various physical or virtual resources, run the <b>memoryoptions</b> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> <li>▪ As a result of the execution of the <b>memoryoptions</b> utility or a manual edit of the <code>jvm-memory.options</code> file, the JVM options are activated as <code>restarts</code>.</li> </ul> |

| Upgrade path                              | Expected behavior when the <code>jvm-memory.options</code> file exists in the source installation  |
|---|--|
| PingFederate installer for Windows        | <ul style="list-style-type: none"> <li>▪ The installer creates a new installation based on the source installation and copies the <code>jvm-memory.options</code> file from the source installation to the new installation.</li> <li>▪ At the end of the installation, the installer runs the PingFederate service-installation program, which runs a helper utility <code>generate-wrapper-jvm-options.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/wrapper</code> directory, to read the JVM options from the <code>jvm-memory.options</code> file and create a resource file that the Windows service requires to configure its JVM options.</li> <li>▪ The preserved Java virtual machine (JVM) options are activated as the PingFederate service starts.</li> </ul> |
| PingFederate Upgrade Utility (upgrade.sh) | <ul style="list-style-type: none"> <li>▪ The upgrade utility creates a new installation based on the source installation and copies the <code>jvm-memory.options</code> file from the source installation to the new installation.</li> <li>▪ The preserved JVM options are activated as the PingFederate service starts.</li> </ul>   |

| Upgrade path                               | Expected behavior when the <code>jvm-memory.options</code> file exists in the source installation  |
|--|--|
| PingFederate Upgrade Utility (upgrade.bat) | <p>The upgrade utility creates a new installation based on the source installation and copies the <code>jvm-memory.options</code> file from the source installation to the new installation.</p> <p>PingFederate as a console application on Windows</p> <p>The preserved JVM options are activated as the PingFederate service starts.</p> <p>PingFederate as a service on Windows</p> <ul style="list-style-type: none"> <li>When administrators run the service-installation program <code>install-service.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/win-x86-64</code> directory, to install the Windows service manually, the program runs the <code>memoryoptions</code> utility, which is designed to determine the recommended Java heap and garbage collector options based on the available resources and record them in the <code>jvm-memory.options</code> file.</li> </ul> <p>The service-installation program then runs a helper utility <code>generate-wrapper-jvm-options.bat</code>, located in the <code>&lt;pf_install&gt;/pingfederate/sbin/wrapper</code> directory, to read the JVM options from the <code>jvm-memory.options</code> file and create a resource file that the Windows service requires to configure its JVM options.</p> <ul style="list-style-type: none"> <li>The new recommended options are activated as the PingFederate service starts.</li> </ul> <div data-bbox="581 1056 1464 1228" style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>To restore the preserved JVM options from the source installation, see <a href="#">Restoring the preserved JVM</a>.</p> </div> |

### Restoring the preserved JVM options

When administrators run the PingFederate service-installation program `install-service.bat`, the upgrade utility creates a new installation based on the source installation and copies the `jvm-memory.options` file from the source installation to the new installation. You can edit the `jvm-memory.options` file with a time stamp to restore the preserved JVM options that exist in the `jvm-memory.options` file from the source installation.

#### About this task

Use the command prompt to edit the `jvm-memory.options` file with a time stamp.

#### Steps

1. Rename the current `jvm-memory.options` file. For example, `jvm-memory.options.backup`.
2. Look for the preserved `jvm-memory.options` file.

 **Note:**

The preserved file was renamed with a time stamp.

3. Remove the time stamp from the file name.

**Note:**

The `jvm-memory.options` is the file preserved from the source installation.

4. Open a command prompt and go to the `<pf_install>/pingfederate/sbin/wrapper` directory.
5. Run `generate-wrapper-jvm-options.bat`.

**Note:**

This helper utility reads the JVM options from the `jvm-memory.options` file and creates a resource file that the PingFederate Windows service requires to configure its JVM options.

6. Close the command prompt.  
The preserved file was renamed with a time stamp.
7. Restart the PingFederate Windows service.

**Result**

The preserved JVM options are activated as the PingFederate service starts.

**Fine-tuning JVM options**

Edit the JVM options `jvm-memory.options` file to customize minimum and maximum heap sizing, garbage collection, and generation specific sizing for your memory use and to optimize PingFederate's performance.

**About this task**

PingFederate reads java virtual machine (JVM) options from the `jvm-memory.options` file, located in the `<pf_install>/pingfederate/bin` directory. Any manual modifications or additions should be made in this file.

**Remember:**

Before making any edits to the file, consider the following:

- Make a backup copy prior to any manual edits.
- The empty lines and comments, indicated by a leading # character, are ignored.
- JVM options do not need a specific organization or order.

**Steps**

1. Edit the `<pf_install>/pingfederate/bin/jvm-memory.options` file.
2. To configure a specific heap size, edit the minimum `-Xms` and maximum `-Xmx` heap options.

The valid unit qualifiers are `k` for kilobytes, `m` for megabytes, and `g` for gigabytes. In other words, `-Xmx1536m` and `-Xmx1.5g` are equivalent.

**Example:**

For example, to fix the JVM heap size to 2 GB, configure the minimum and maximum options as follows.

```
-Xms2g
-Xmx2g
```

3. To override the number of garbage collection threads used by the parallel collector, add the `-XX:ParallelGCThreads=n` option, where *n* is the desired number of garbage collector threads.

Example:

For example, to configure the parallel collector to use four threads, add the following option to the configuration file.

```
-XX:ParallelGCThreads=4
```

4. To enable the concurrent mark sweep (CMS) collector, remove the `-XX:+UseParallelGC` option, or the options pertaining to another garbage collector, and replace it with the `-XX:+UseConcMarkSweepGC` option.
5. To enable the garbage first (G1) collector, remove the `-XX:+UseParallelGC` option, or the options pertaining to another garbage collector, and replace it with the `#XX:+UseG1GC` option.



**Note:**

If you enable the G1 collector, remove any sizing options specific to the young generation. Skip to [step 7](#).

6. To configure young generation-specific sizing options, edit the minimum `-XX:NewSize` and maximum `-XX:MaxNewSize` options for the young generation space.

Example:

For example, to fix the young generation bias to 1 GB, set the minimum and maximum options as follows.

```
-XX:NewSize=1024m
-XX:MaxNewSize=1024m
```

7. To remove young generation-specific sizing options completely, remove the aforementioned options or add a leading `#` character.
8. To add additional JVM options, insert the applicable options to the file.

Example:

For example, to enable the aggressive options flag, configure the file as follows.

```
...

# Enable the aggressive options flag
-XX:+AggressiveOpts
```

The comment is optional.

9. When finished, save your changes.
10. If PingFederate is configured to run as a service on a Windows server, follow these steps:
  - a. Open command prompt and go to the `<pf_install>/pingfederate/sbin/wrapper` directory.
  - b. Run `generate-wrapper-jvm-options.bat`.

Result:

This helper utility reads the JVM options from the `jvm-memory.options` file and creates a resource file that the PingFederate Windows service requires to configure its JVM options.
  - c. Close the command prompt.
11. Restart PingFederate.
12. For a clustered PingFederate environment, repeat these steps on each engine node as needed.

## Hardware security modules

---

When configuring PingFederate to use a hardware security module, be aware of the following performance impact considerations.

You can configure to use a hardware security module (HSM) for cryptographic material storage and operations. When configured, private keys and their corresponding certificate are stored on the HSM. Related signing and decryption operations are processed there for enhanced security.

For more information on supported configurations for secure material storing and processing, see [Supported hardware security modules](#) on page 177.

### Performance considerations

Configuring PingFederate to use an HSM for cryptographic material storage and operations can introduce an impact on performance. The level of impact depends on the performance of cryptographic functionality provided by the HSM and the network latency between PingFederate and the HSM. Consult your HSM vendor for performance tuning and optimization recommendations if you plan to use an HSM as part of your PingFederate deployment.

## Configuration at scale

---

You can configure PingFederate to improve the administrative-console experience for your scaling needs.

For deployments that have hundreds of connections or OAuth clients, or both, and observe noticeable delays in the administrative console, administrators can optionally configure PingFederate to create configuration archives during off-peak hours and disable automatic connection validation to improve the administrative-console experience.

## References

---

For more information on memory management and Hotspot Java virtual machine (JVM) arguments for garbage collection tuning, see the following resources.

### Memory management

For more information, see [Java Platform, Standard Edition HotSpot Virtual Machine Garbage Collection Tuning Guide](#) from Oracle.

### Hotspot JVM arguments

For more information, see [Java HotSpot VM Options](#) from Oracle.

## PingFederate Monitoring Guide

---

PingFederate provides a range of monitoring options, from simple heartbeat options for checking responsiveness to transaction response-time logging and resource-utilization metrics.

To help you gain insight into the health and performance of your PingFederate deployment, this guide provides the following information:

- [Liveliness and responsiveness](#) on page 1100 describes the heartbeat request endpoint and audit logs
- [Resource metrics](#) on page 1097 describes mechanisms for obtaining resource metrics including JMX



- [Monitoring](#) on page 1104 describes the key JVM performance metrics for evaluating the performance of PingFederate deployments
- [Thread pool](#) on page 1109 describes the MBeans tab and the recommended number of threads in the pool
- [Logging, reporting, and troubleshooting](#) on page 1110 describes the available logging, reporting, and troubleshooting features

## Resource metrics

---

PingFederate provides mechanisms for obtaining resource metrics including JMX and heartbeat endpoint.

PingFederate provides the following mechanisms for obtaining resource metrics:

- JMX - Ping recommends using JMX MBeans because this method provides a more comprehensive set of resource metric counters for analyzing performance. Several tools are available for collecting and analyzing data from JMX MBeans, including many security information and event management (SIEM) tools, like Splunk.
- Heartbeat endpoint - For information about enabling and customizing heartbeat message reporting, see [Liveliness and responsiveness](#) on page 1100.

[Monitoring](#) discusses the JConsole monitoring tool that is included with the Java SE platform. For more information about the Comprehensive JConsole, see [Troubleshoot with the JConsole Tool](#) in the Oracle JDK documentation and [The Java Monitoring and Management Console \(jconsole\)](#) in the OpenJDK documentation.

## Runtime monitoring using JMX

PingFederate supports runtime monitoring and reporting through Java Management Extensions (JMX). JMX technology represents a Java-centric approach to application management and monitoring.

JMX exposes instrumented code in the form of MBeans. Application management systems that support JMX technology, such as JConsole, can request runtime information from the PingFederate JMX server.



### Important:

Authentication is required for JMX-client access to PingFederate runtime data. For more information, see [Configuring service authentication](#) on page 698.



### Tip:

You can use HTTP requests at any time to verify the status of the PingFederate server. For more information, see [Customizing the heartbeat message](#) on page 907.

You can also supplement monitoring information by applying third-party analysis and reporting tools to the security audit log, in which PingFederate records fine-grain details, including response times and event types, for all server transactions. For more information, see [Security audit logging](#) on page 834.

PingFederate JMX server reports monitoring data for single sign-on (SSO) and single logout (SLO) transactions. In addition, numerous Jetty-standard MBeans are available to the PingFederate server's JMX clients.

### PingFederate MBeans

PingFederate provides MBeans for tracking server performance. The attributes exposed by these MBeans align with those available at the [heartbeat endpoint](#). Most statistics and counts are calculated over a period. You can configure the period's length in the file `com.pingidentity.monitoring.MonitoringService.xml`.

- `TOTAL_TRANSACTIONS`: The total number of SSO, SLO, and STS transactions processed since the server started. PingFederate resets this counter to zero after restart.
- `TOTAL_FAILED_TRANSACTIONS`: The total number of failed transactions since the server started. PingFederate resets this counter to zero after restart.
- `dataStores`: The request rate and response time statistics for data stores
- `httpRequests.admin`: The request rate and response time statistics for HTTP requests to the administrative console
- `httpRequests.engine`: The request rate and response time statistics for HTTP requests to PingFederate's runtime endpoints
- `stateMaps`: The current number of entries in various runtime state maps
- `transactions`: The counts of all transactions and failed transactions, including values for the previous period and accumulated totals since the server started

### Sample Jetty metrics

The following table describes examples of Jetty MBean metrics, available through JMX, that you might find useful to supplement the information that the PingFederate-specific MBeans provide.

| MBean  | Attributes   |
|--|--|
| <code>org.eclipse.jetty.io:connectionstatistics</code><br>For Jetty connectors including the primary and secondary PingFederate runtime server ports.  | <code>connectionsTotal</code> – Total number of TCP connections accepted by the server<br><code>connectionDuration*</code> – How long connections are kept open. Maximum, mean, and standard deviation are available<br><code>connections</code> – Current number of open connections. Maximum is also available ( <code>connectionsMax</code> )   |
| <code>org.eclipse.jetty.server.handler:statisticshandler</code>  | <code>requests</code> – Total number of requests received<br><code>requestsActive</code> – Number of requests currently being processed. Max is also available<br><code>requestTime</code> – Request duration. Maximum, mean, standard deviation, and total accumulated time are available<br><code>responses1xx</code> , <code>responses2xx</code> , <code>responses3xx</code> , ... – Total number of requests that returned HTTP status codes of 1xx, 2xx, 3xx, and so on |
| <code>org.eclipse.jetty.util.thread:queuedthreadpool</code><br>Two pools: one for the runtime server, with 200 maximum threads; one for the administrative console, with 20 maximum threads. | <code>idleThreads</code> – Number of idle threads currently available<br><code>threads</code> – Number of threads currently running, including both idle and active<br><code>minThreads</code> – Minimum number of threads in the pool<br><code>maxThreads</code> – Maximum number of threads in the pool<br><code>lowOnThreads</code> – A boolean flag indicating whether the pool is running low on threads  |
| <code>java.lang: Memory</code><br><code>java.lang: MemoryPool</code><br><code>java.lang: GarbageCollection</code><br><code>java.lang: OperatingSystem</code>                                 | Attributes measuring CPU usage and memory  |

## Advanced JMX configuration

PingFederate uses port 1099 for its JMX server. You can change the port and other Java Message Service (JMS) settings by modifying the `jmx-remote-config.xml` file in the `<pf_install>/pingfederate/server/default/conf` directory.



### Note:

When connecting to the JMX service using SSL, the default, ensure that the client trusts the PingFederate SSL server certificate presented. For more information, see [Manage SSL server certificates](#) on page 658.

## Connecting with JMX

You can connect to JMX using local and remote processes.

JConsole permits connections to local and remote Java processes. If your instance of PingFederate is running as a Windows Service, you must connect through the remote option. For more information on connecting to a local process, see [Connecting to a local process](#) on page 1099. For information on connecting to a remote process, see [Connecting to a remote process](#) on page 1100.

### Connecting to a local process

Unless you are running PingFederate as a Windows service, the easiest method by which to launch JConsole on the same machine as the server is to select **Local Process**.


#### About this task

For information about connecting to a remote process, see [Connecting to a remote process](#) on page 1100.

To connect to a local instance and start the monitoring process:

#### Steps

- From the **Local Process** list, select **org.pingidentity.RunPF** and then click **Connect**.



### Note:

If you are running the process locally, the system might prompt you to accept the connection as insecure.

### Connecting to a remote process

If PingFederate is running as a Windows Service, or if the `org.pingidentity.RunPF` class is unavailable in the Local Process list, use this procedure to establish a connection.

About this task

To enable remote JMX monitoring in PingFederate:

#### Steps

1. In the Administrative Console, go to the **Security # System Integration # Service Authentication** window.
2. Define the credentials that are required to connect to the PingFederate JMX service.
3. Restart PingFederate to enable the JMX Service.
4. If PingFederate is deployed in a clustered environment:
  - a. Replicate the configuration changes on each node in the cluster.
  - b. Restart each engine node.
5. After you enable the JMX service, connect to the remote JMX service by specifying the hostname and port 1099, or a service URL like the following:

```
service:jmx:rmi:///jndi/rmi://[hostname]:1099/jmxrmi
```

Because JMX uses SSL by default when communicating with a remote host, the client host must trust the PingFederate SSL certificate that is presented when a connection is established.

To disable the use of SSL for JMX, open the `/server/default/conf/jmx-remote-config.xml` file and set the `<item name="jmx.rmi.ssl">` property to `false`.



#### Note:

If the JMX client does not trust the JMX certificate, a `connection failed SSL` message appears.

6. If SSL is enabled in `jmx-remote-config.xml`, import the PingFederate SSL certificate to the client's trusted certificates.
7. If SSL is disabled, click **Insecure** to connect.

## Liveliness and responsiveness

---

One of the simpler methods for monitoring the performance of a PingFederate deployment involves determining whether the PingFederate Server is available and responsive. To help you identify the status of a server, PingFederate provides a heartbeat request endpoint.

#### Heartbeat endpoint

If the PingFederate server is running, the process of sending a request to the endpoint `/pf/heartbeat.ping` returns an HTTP 200 status. If the request times out or requires an extended amount of time to return, the server might be overloaded or experiencing other difficulties.

If a request requires more than two or three seconds to return, multiple factors in your PingFederate deployment might be responsible. We recommend that you develop a baseline for the desired response time by testing the heartbeat endpoint of your deployment at various times. This endpoint can be useful when load balancing a cluster of PingFederate instances. Some load balancers can alter the number of requests that are sent to a particular server based on the response code received, or the responsiveness of requests that are made to the heartbeat endpoint.

The output of the heartbeat endpoint can be modified to provide performance-related information, such as CPU and memory usage, and response times. The response metrics can help you make better auto-scaling decisions. The map size metrics can help you recognize performance issues.

The following example shows a report containing all the PingFederate server metrics available from the heartbeat endpoint.

```
{
  "items": [
    {
      "cpu.load": "77.31",
      "total.jvm.memory": "1045.955 MB",
      "free.jvm.memory": "486.56 MB",
      "used.jvm.memory": "559.395 MB",
      "total.physical.system.memory": "68.719 GB",
      "total.free.physical.system.memory": "15781.827 MB",
      "total.used.physical.system.memory": "52.938 GB",
      "number.of.cpus": "12",
      "response.statistics.count": "4074",
      "response.statistics.window.seconds": "10",
      "response.time.statistics.90.percentile": "450.883584",
      "response.time.statistics.mean": "112.82695139911635",
      "response.time.statistics.min": "0.0",
      "response.time.statistics.max": "7951.0",
      "response.concurrency.statistics.90.percentile": "49.2421875",
      "response.concurrency.statistics.mean": "45.562130177514796",
      "response.concurrency.statistics.min": "0.0",
      "response.concurrency.statistics.max": "51.0",
      "response.http.status.1xx": "0",
      "response.http.status.2xx": "3052",
      "response.http.status.3xx": "1017",
      "response.http.status.4xx": "0",
      "response.http.status.5xx": "0",
      "transaction.count": "2037",
      "transaction.errors": "0",
      "total.transactions": "4050",
      "total.failed.transactions": "0",
      "ds.JDBC.PFDefaultDS.request.count": "3945",
      "ds.JDBC.PFDefaultDS.response.time.90.percentile": "8.024064",
      "ds.JDBC.PFDefaultDS.response.time.mean": "2.2572877059569074",
      "ds.JDBC.PFDefaultDS.response.time.min": "0.0",
      "ds.JDBC.PFDefaultDS.response.time.max": "157.0",
      "engine.jetty.queued.thread.pool.utilized.threads": "52",
      "engine.jetty.queued.thread.pool.max.available.threads": "199",
      "engine.jetty.queued.thread.pool.utilization.rate":
      "0.2613065326633166",
      "engine.jetty.queued.thread.pool.queue.size": "0",
      "idp.session.registry.session.map.size": "2034",
      "sp.session.registry.session.map.size": "0",
      "session.state.attribute.map.size": "2034",
      "transaction.state.map.size": "0",
      "atm.default.token.map.size": "0"
    }
  ]
}
```

The following table describes all the PingFederate server metrics available from the heartbeat endpoint.



**Note:**

In the following table, for server metrics that end in `.90.percentile`, the current 90 value is determined by the `ServerPercentilesList` item in the `com.pingidentity.monitoring.MonitoringService.xml` file. 90 is the default value. For more information on how to edit this value, see step 4 in [Liveliness and responsiveness](#).

| Server metrics   | Description  |
|--|--|
| <code>cpu.load</code>                                      | Load on the PingFederate server's cores as a percentage of total capacity  |
| <code>total.jvm.memory</code>                              | Total memory of the JVM  |
| <code>free.jvm.memory</code>                               | Free memory of the JVM   |
| <code>used.jvm.memory</code>                               | Used memory of the JVM   |
| <code>total.physical.system.memory</code>                  | Total system memory  |
| <code>total.free.physical.system.memory</code>             | Free system memory   |
| <code>total.used.physical.system.memory</code>             | Used system memory   |
| <code>number.of.cpus</code>                                | Number of cores on the PingFederate server   |
| <code>response.statistics.count</code>                     | Number of items considered in the heartbeat report for the time and concurrency statistics   |
| <code>response.statistics.window.seconds</code>            | Time interval (in seconds) for the statistics report (this is an echo of the <code>StatisticsWindowSecs</code> parameter's value and provides context for the concurrency and time statistics) |
| <code>response.time.statistics.90.percentile</code>        | The 90th percentile response time in milliseconds during the statistics window (for example, if this value is 168, then 90% of the report samples had response times below 168 milliseconds)   |
| <code>response.time.statistics.max</code>                  | Longest time in milliseconds that the PingFederate server took to respond during the statistics window   |
| <code>response.time.statistics.mean</code>                 | Mean time in milliseconds that the PingFederate server took to respond during the statistics window  |
| <code>response.time.statistics.min</code>                  | Shortest time in milliseconds that the PingFederate server took to respond during the statistics window  |
| <code>response.concurrency.statistics.90.percentile</code> | The 90th percentile response concurrency during the statistics window (for example, if this value is 124, then 90% of the report samples had response concurrency values below 124)            |
| <code>response.concurrency.statistics.max</code>           | Maximum number of HTTP requests that the PingFederate server processed concurrently during the statistics window   |
| <code>response.concurrency.statistics.mean</code>          | Mean number of HTTP requests that the PingFederate server processed concurrently during the statistics window  |
| <code>response.concurrency.statistics.min</code>           | Minimum number of HTTP requests that the PingFederate server processed concurrently during the statistics window   |
| <code>response.http.status.1xx</code>                      | Number of 1xx HTTP response codes during the statistics window   |
| <code>response.http.status.2xx</code>                      | Number of 2xx HTTP response codes during the statistics window   |

| Server metrics   | Description   |
|--|---|
| <code>response.http.status.3xx</code>  | Number of 3xx HTTP response codes during the statistics window                                    |
| <code>response.http.status.4xx</code>  | Number of 4xx HTTP response codes during the statistics window                                    |
| <code>response.http.status.5xx</code>  | Number of 5xx HTTP response codes during the statistics window                                    |
| <code>transaction.count</code>   | Number of SSO, SLO, and STS transactions during the statistics window                             |
| <code>transaction.errors</code>  | Number of failed SSO, SLO, and STS transactions during the statistics window                      |
| <code>total.transactions</code>  | Total number of SSO, SLO, and STS transactions since the server started                           |
| <code>total.failed.transactions</code>   | Total number of failed SSO, SLO, and STS transactions since the server started                    |
| <code>ds.&lt;type&gt;.&lt;id&gt;.request.count</code>                            | Number of requests for the data store during the statistics window                                |
| <code>ds.&lt;type&gt;.&lt;id&gt;.response.time.90.percentile</code>              | The data store's 90th percentile response time in milliseconds during the statistics window       |
| <code>ds.&lt;type&gt;.&lt;id&gt;.response.time.mean</code>                       | The data store's mean response time in milliseconds during the statistics window                  |
| <code>ds.&lt;type&gt;.&lt;id&gt;.response.time.min</code>                        | The data store's minimum response time in milliseconds during the statistics window               |
| <code>ds.&lt;type&gt;.&lt;id&gt;.response.time.max</code>                        | The data store's maximum response time in milliseconds during the statistics window               |
| <code>&lt;admin engine&gt;.jetty.queued.thread.pool.utilized.threads</code>      | Number of threads in the Jetty thread pool that are currently in use                              |
| <code>&lt;admin engine&gt;.jetty.queued.thread.pool.max.available.threads</code> | Maximum number of threads in the Jetty thread pool  |
| <code>&lt;admin engine&gt;.jetty.queued.thread.pool.utilization.rate</code>      | The threads in the pool that are currently in use, as a fraction of the maximum available threads |
| <code>&lt;admin engine&gt;.jetty.queued.thread.pool.queue.size</code>            | Number of requests currently queued waiting to be handled by a thread in the pool                 |
| <code>idp.session.registry.session.map.size</code>                               | Number of identity provider sessions  |
| <code>sp.session.registry.session.map.size</code>                                | Number of service provider sessions   |
| <code>session.state.attribute.map.size</code>                                    | Number of items in the session state attribute map  |
| <code>transaction.state.map.size</code>  | Number of items in the SSO transaction state map  |
| <code>atm.&lt;atm&gt;.token.map.size</code>                                      | Number of tokens in the access token manager with the ID specified by <code>&lt;atm&gt;</code>    |

As indicated in the table, the values of some metrics are calculated over a configurable time window. The default statistics window is five minutes.

To customize the statistics window period, change the value of the `StatisticsWindowSecs` parameter in the `<pf_install>/pingfederate/server/default/data/config-store/com.pingidentity.monitoring.MonitoringService.xml` file. This file also lets you specify additional JMX MBean attributes that will be made available to the heartbeat page templates.

For more information, see [Customizing the heartbeat message](#) on page 907

### Response-time logging

By default, the audit logs record the processing time for each transaction. With audit logging enabled, you can identify the speed with which PingFederate processes the following transaction types:

- Single sign-on (SSO)
- OAuth
- Security token services (STS)

Depending on your logging configuration, audit logging might not log any transactions. For more information, see [Security audit logging](#) on page 834.

The following provides examples of the default audit log.

```
2019-11-10 13:24:57,493| tid:cYunBsgybiw_fiRnJjkAhbIXvzc|
AUTHN_SESSION_USED| | 127.0.0.1 | | ac_client| | localhost| IdP| success|
PdFormAdpt| | 17
```

```
2019-11-10 13:24:58,720| tid:cYunBsgybiw_fiRnJjkAhbIXvzc| OAuth|
5c60f022-1e9d-3fbe-9749-4b9ca5591356| 127.0.0.1 | | ac_client| OAuth20|
localhost| AS| success| PdFormAdpt| | 7
```

Processing times are shown at the end of the entry in milliseconds.

## Monitoring

---

This topic outlines the key JVM performance metrics for evaluating the performance of a PingFederate deployment.

After a connection is established, you can access the JConsole monitoring interface.

### Monitoring clustered PingFederate engines

JConsole can be connected to multiple processes. To monitor several instances of PingFederate after a connection is established, click **Connection # New Connection** and add the additional connection.


### Monitoring CPU utilization

The **Overview** tab provides a dashboard of the following performance and resource-utilization charts:

- Heap Memory Usage (cumulative memory that is used by all memory pools).
- Live Threads
- CPU Usage
- Classes (number of classes that are loaded)

This tab provides a high-level view of the JVM's performance metrics.





Use the **Overview** tab to visualize and collect CPU usage data. When your PingFederate deployment is subjected to its normal or expected load, the CPU utilization typically falls between 60 and 80%. If the system registers consistently at 80% or higher, additional CPU resources might be necessary to handle load spikes that occur during peak usage times.

### Monitoring memory utilization

The **Overview** tab shows only overall heap usage. To view additional details about memory utilization, click the **Memory** tab, which lets you analyze usage patterns in specific memory pools within the heap. This tab also provides information about the overall heap utilization profile.

### Old Generation space

Objects that survive a sufficient number of garbage-collection cycles are promoted to the Old Generation. To view the memory usage in the pool of such objects, click **Memory Pool # PS Old Gen** or **Memory Pool # G1 Old**, depending on the relevant garbage collection. PingFederate services mostly short-lived transactions, like SSO, STS, and OAuth requests and most of the created memory objects are required only for a short period of time.


Although PingFederate makes use of some memory objects that are medium to long lived, such as session data for authentication session, adapter sessions, or single logout functionality, most of the objects that are promoted to the Old Generation are likely to become garbage that requires cleaning up. If the younger generation, or *Eden space*, is not sized appropriately, objects are moved to and retained in the Old Generation before they are collected as garbage. If size limitations prevent the Old Generation from accumulating future garbage as well as longer-lived objects, then garbage-collection cycles occur more frequently.

The Old Generation space is the most important space to monitor. It is easy to identify if the heap is sized and proportioned appropriately for a specific load, based on its usage pattern. The following examples involve two Old Generation usage charts. In both examples, the same user load executes the same workflow. The size of the heap represents the only difference.

The most important space to monitor. It is easy to identify if the heap is sized andBecause the heap is sized adequately in the first example, memory in the Old Generation rises at a reasonably slow rate. Garbage collection frees around 60 to 75% of the space, and room is available to accommodate the future garbage of newly created objects that are moved from the Eden space, as well as the longer-term objects that remain in use. Although the space is 1 GB in size, the average full (PS MarkSweep or G1 Old Generation) collection time is approximately only 240 milliseconds (0.728 seconds for three collections).




When a heap is sized inadequately, the Old Generation runs out of space. In the following example, the amount of memory that becomes free with each garbage collection shrinks, due to the rate at which objects are promoted from the Eden space.




184 PS MarkSweep (full) collections require garbage collections more frequently, totaling 60 seconds, or an average of 326 milliseconds per collection.

### Entire heap space

If the heap is sized appropriately for the load that the system must handle, it fills up and is followed by an appreciable drop in usage as a full garbage collection occurs (such as a PS MarkSweep collection triggered by the Old Generation filling up). In this example, the heap rises steadily, with drops from minor collections until a PS MarkSweep collection occurs and collects approximately 70% of the heap.





When the heap is undersized, full collections that are performed more frequently return less memory. In the following example, the frequency of JMX data that the JConsole retrieves does not keep pace with the frequency of full collections. As a result, only a fraction of them occur.



## Eden space

Regardless of whether the heap is adequately sized or undersized, the usage pattern is nearly identical with the Eden space. This similarity can be due to the sampling frequency of the data-collection tool because the number of samples might be insufficient to show that, with an undersized heap, memory is consumed and subsequently freed with greater frequency. The behavior of garbage collection in the Eden space is such that when it fills, the space is completely emptied by moving live objects to the Survivor and Old Generation spaces. Under load, the pattern resembles a jagged sawtooth, as shown in the following examples of an adequately sized heap and an undersized heap.



### Increasing heap size

Because garbage collectors manage memory in the Java Runtime Environment, simply increasing the size of the heap is not always the appropriate solution. The following table outlines the total heap size recommendations for the available garbage collectors, based on available CPU resources. For more information about garbage collectors, see [Garbage collectors](#) on page 1086.

| Garbage Collector     | Minimum Recommended Number of CPUs | Recommended Heap Size |
|-----------------------|------------------------------------|-----------------------|
| Parallel              | 4                                  | 6 GB maximum          |
| Concurrent Mark Sweep | 12                                 | 4 - 6 GB minimum      |
| Garbage First (G1)    | 12                                 | 6 GB minimum          |


If additional memory is unavailable, or if increasing the size of the heap is inadvisable because of these recommendations, the load that is handled by this instance is probably too high. In such instances, consider adding additional resources to your deployment. To verify whether the load for the instance is too high, check the CPU utilization

To allow for the most efficient management of memory, set the minimum and maximum heap sizes to the maximum allowed values to avoid potentially expensive heap allocation resizing and divide it evenly between the young and old generations. If you are using the Garbage First collector, generational spaces are not specified through command line options because they are managed logically in real time. Even in such instances, we recommend setting the minimum and maximum heap sizes to the maximum allowed values. For more information about fine-tuning the JVM options in the `jvm-memory.options` file, see [Fine-tuning JVM options](#) on page 1094.

## Thread pool

The following topic describes the MBeans tab and the recommended number of threads in the pool.

The **MBeans** tab provides access to the JMX Managed Beans and their available attributes and operations. Of particular interest are the `queuedThreadPool` instances that are available within the `org.eclipse.jetty.util.thread` bean. For example, instance 0 represents the thread pool that handles runtime requests. When you click the **Attributes** item for instance 0, the current state of the thread pool is displayed.



The number of threads in the pool (the `threads` attribute) can be compared to the number of threads that are not currently in use (the `idleThreads` attribute). Ideally, a sufficient number of threads is available to handle load spikes that occur during peak usage times, while also limiting the number of idle threads that are running. If the thread pool is too small, requests might be blocked. If the thread pool is too large, memory might be used unnecessarily, and CPU contention might increase, limiting the processing effectiveness.

We recommend allowing for 10 to 25% more threads than are typically active while the system executes a normal or expected load. Because most of your users will not be active at the same time, set the minimum threads to 10% above the average number of active threads that are observed during monitoring.

We also recommend setting the maximum number of threads to 25% above the average number of active threads that are observed while monitoring under expected load conditions. Make certain to weigh this recommendation against the observed CPU utilization metrics and the suggestions in the [Performance Tuning Guide](#).

## Logging, reporting, and troubleshooting

---

This section provides an overview of the available logging, reporting, and troubleshooting features for PingFederate.

### PingFederate Logs

The `server.log` file represents the primary troubleshooting log. Along with an HTTP trace from the browser, which can be generated from a debugging application like Fiddler, this file is helpful for identifying issues that must be resolved. The following table identifies the available PingFederate logs and summarizes their purposes.

| Name                                | Purpose  |
|-------------------------------------|--|
| <code>admin.log</code>              | Records the actions that users of the Administrative Console perform.  |
| <code>admin-event-detail.log</code> | If detailed event logging is enabled, this log records detailed information about each applicable administrative-console event that users of the Administrative Console perform.                   |
| <code>admin-api.log</code>          | Records the actions that users of the administrative API perform.  |
| <code>runtime-api.log</code>        | Records the actions that API users perform by using the OAuth Client Management Service, the OAuth Access Grant Management Service, and the Session Revocation API.                                |
| <code>transaction.log</code>        | Records individual identity-federation runtime transactions at specified levels of detail.   |
| <code>audit.log</code>              | Records a selected, configurable subset of transaction log information plus additional details. Intended for security-audit and regulatory-compliance purposes.                                    |
| <code>provisioner-audit.log</code>  | Records outbound provisioning events intended for security-audit purposes.   |
| <code>provisioner.log</code>        | Records provisioning activity only. Useful when troubleshooting issues that relate to provisioning.  |
| <code>server.log</code>             | Records PingFederate runtime and administrative server activities. For more information about the primary troubleshooting log, see <a href="#">Creating an error-only server log</a> on page 1111. |
| <code>init.log</code>               | Records only Jetty messages that are generated prior to starting PingFederate.   |

## Creating an error-only server log

This section describes an approach for modifying your `log4j2.xml` file, which can be sent to a security information and event management (SIEM) tool, such as Splunk. You can configure alerts to send notifications when such events occur, or to improve the monitoring of these events.

### About this task

We recommend using the `server.log` file for error-level messages. Even when levels are down to a minimum, the server log generates large amounts of information in an active production environment. As an alternative, you can set up a specific log to log only `ERROR` and higher.

To change your `log4j2.xml` file to enable a separate log file:

### Steps

1. Create an appender.

The easiest way to create an appender is to copy an existing one as a base. In the following example, the `RollingFile` is the same one that the `server.log` file uses. Bold text identifies items that have been changed.

```
<!-- Error Only Main Log : A size based file rolling appender -->
<RollingFile name="FILEERR" fileName="${sys:pf.log.dir}/server.error.log"
    filePattern="${sys:pf.log.dir}/server.error.log.%i"
    ignoreExceptions="false">
  <PatternLayout>
    <!-- Uncomment this if you want to use UTF-8 encoding instead
    of system's default encoding.
    <charset>UTF-8</charset> -->
    <pattern>%d %X{trackingid} %-5p [%c] %m%n</pattern>
  </PatternLayout>
  <Policies>
    <SizeBasedTriggeringPolicy
      size="10000 KB" />
  </Policies>
  <DefaultRolloverStrategy max="5" />
</RollingFile>
```

2. At the end of your `log4j2.xml` file, set the appender that you created in the previous step for `AsyncRoot`.

```
<AsyncRoot level="INFO" includeLocation="false">
  <!-- <AppenderRef ref="CONSOLE" /> -->
  <AppenderRef ref="FILE" />
  <AppenderRef ref="FILEERR" level="ERROR" />
</AsyncRoot>
```

In this example, the `level` attribute indicates the level of messages that are sent to the log file.

3. Remove the attribute `additivity="false"` from all other loggers that contain a reference to the `File` appender.

```
Logger name="org.sourceid.saml20.util.SystemUtil" level="INFO"
  additivity="false">
  <!--<AppenderRef ref="CONSOLE" /> -->
  <AppenderRef ref="FILE" />
```

Becomes:

```
<Logger name="org.sourceid.saml20.util.SystemUtil" level="INFO" >
  <!--<AppenderRef ref="CONSOLE" /> -->
```

```
<AppenderRef ref="FILE" />
```

4. Make this change on all nodes within the cluster.



**Note:**

To expedite this step, we recommend creating a base file with the appropriate changes and copying it to all the nodes.

5. Restart PingFederate.

## Splunk dashboards and audit logs


Ping provides a free [Splunk for PingFederate](#) application that customers can use to create dashboards.

This application takes advantage of the [Writing audit logs for Splunk](#) on page 845 and [Outbound provisioning audit logging](#) on page 838, which can be enabled in `log4j2.xml` file.


Examples of Splunk dashboards

To help you review different events, the following dashboards are available from the top-level menu of the PingFederate app for Splunk:

- Account Manager
- Identity Provider
- Service Provider
- OAuth Server




Click a menu item to view its sub-menus, as the following example shows for **OAuth Server**.




The following image shows the **Identity Provider Access** sub-menu dashboard with examples from the security audit log entries.







After you select a sub-menu, an image like the following **OAuth Server Client Request** example is displayed while the dashboard waits for the search results.




After you click **Submit**, the dashboard displays the following search results for the client request.



To view additional results, scroll downward or select another page. The following **Client Request** page provides an example.



The following images provide additional examples of the **Service Provider Access** sub-menu dashboard.



## SDK Developer's Guide

The PingFederate SDK enables integration with identity providers (IdPs) and service providers (SPs). The SDK allows application developers and system administrators to build custom implementations for communicating authentication and security information between PingFederate and their enterprise environment.

Possible customizations

Extending PingFederate could include:

- Authentication adapters to integrate web applications or identity-management systems
- Authentication selectors to direct single sign-on (SSO) authentication to instances of authentication adapters based on specified conditions

- WS-Trust Security Token Service (STS) token translators, including token processors and token generators
- Custom data source drivers
- Password credential validators
- Identity store provisioners
- Notification publishers

The PingFederate Java SDK consists of several APIs, including:

- Adapter and STS token-translator interfaces
- Authentication selector interfaces
- Custom data source interfaces
- Password credential validator interfaces
- Identity store provisioner interfaces
- Notification publisher interface

These interfaces allow users to create their own custom PingFederate plugins to suit their organization's needs. This SDK provides a means to develop, compile, and deploy custom plugins to PingFederate. The package also contains example plugins for reference. These example plugin projects are located in the `<pf_install>/sdk/plugin-src` directory.

The PingFederate [Integration overview](#) on page 65 describes the pre-built authentication adapters Ping Identity provides for integrating web applications and identity-management systems with PingFederate. Review this document before building your own adapter to see if an available adapter fits your use case.



#### Important:

Custom components might not work the same way after upgrading PingFederate. When upgrading, ensure you thoroughly retest the behavior of customizations in a non-critical upgraded environment.

#### Adapter and STS token-translator interfaces

The adapter and token-translator APIs enable PingFederate integration with IdPs or SPs. Adapter token-translator APIs are configurable UI plugins that provide requisite runtime integration and allow you to render custom configuration windows.



#### Note:

Suitable adapter or token-translator implementations for your deployment might already exist. Before developing your own custom solution, see the Ping Identity [Downloads](#) website for available implementations.

#### Authentication selector interfaces

Authentication selectors provide a mechanism to choose among multiple authentication sources and to direct a user to use a particular adapter or IdP connections. For example, an authentication selector might map internal corporate users to use one adapter and map external non-corporate users to a different adapter. Authentication selectors are configurable UI plugins that allow you to render custom configuration windows.

#### Custom data source interfaces

The custom data source API is a set of Java interfaces that enable PingFederate to integrate with datastores not covered by existing Java Database Connectivity (JDBC) or LDAP drivers. This allows developers to retrieve attributes from their choice of data source during attribute fulfillment. Custom data source interfaces are configurable UI plugins that allow you to render custom configuration windows.

### Password credential validator interfaces

The password credential validator interfaces allow developers to define credential validators that verify a given username and password in various contexts throughout the system. For example, credential validators are used to configure OAuth Resource Owner authorization grants and the HTML Form Adapter.

### Identity store provisioner interfaces

Identity store provisioners provide a mechanism for provisioning and deprovisioning users to external user stores. For example, you can configure a custom identity store provisioner within an inbound provisioning IdP connection to provision users using the System for Cross-domain Identity Management (SCIM) protocol. Identity store provisioners are configurable UI plugins that allow you to render custom configuration windows.

### Notification publisher interface

PingFederate delivers messages to administrators and end users based on notification publisher settings. Developers can implement custom notification publishers using the `NotificationPublisherPlugin` interface.

### Additional documentation

- Javadocs provide detailed reference information for developers. The Javadocs are located in the `<pf_install>/pingfederate/sdk/doc` directory.
- The user guides for Java, .NET, and PHP integration kits show examples of SDK implementations.

## SDK directory structure

---

This topic describes the directory and build components that comprise the SDK.

The PingFederate SDK directory (`<pf_install>/pingfederate/sdk`) contains the following:

- `plugin-src/` — The directory where you place your custom plugin projects. This directory also contains example plugin implementations showing a wide range of functionality. You can use these examples to develop your own implementations.
- `doc/` — Contains the SDK Javadocs. Open `index.html` to get started.
- `lib/` — Contains libraries used for compiling and deploying custom components into PingFederate.
- `build.properties` — Contains properties used by the Ant build script, `build.xml`, to compile and deploy your custom components. Do not modify this file. If you need to override a property, use `build.local.properties`.
- `build.local.properties` — Allows you to specify which project you want to build and define properties specific to your environment. Use this file to declare the project you want to build.
- `build.xml` — The Ant build script used to compile, build, and deploy your component. This file should not need modification.

The Java SDK, along with Apache Ant, enables you to create directories for your project and use the build script to build, clean, or deploy it. For more information, see [Developing your own plugin](#) on page 1117.

## Developing your own plugin

---

You can set up a development environment within the SDK and use it to create a plugin.

### Before you begin

Ensure you have the Java SDK and Apache Ant installed.

### About this task

The Java SDK, along with Apache Ant, enables you to create directories for your project and use the build script to build, clean, or deploy it.

### Steps

1. Create a new project directory in the `<pf_install>/pingfederate/sdk/plugin-src` directory.
2. In the new project directory, create a subdirectory named `java`.  
This is where you place the Java source code for your implementation. Follow standard Java package and directory structure layout.
3. If your project depends on third-party libraries, create another subdirectory called `lib` and place the necessary `.jar` files in it.
4. Edit the `build.local.properties` file and set `target-plugin-name` to specify the name of the directory that contains your project.
5. Run the appropriate target to clean, build, or deploy your plugin.

To display a list of available build targets, run `ant` from `<pf_install>/pingfederate/sdk`.

```
[java] Main targets:
[java]
[java] clean-plugin Clean the plug-in build directory
[java] deploy-plugin Deploy the plug-in jar and libs to PingFederate
[java] jar-plugin Package the plug-in jar
[java]
[java] Default target: help
```



#### Note:

Because it packages the `.jar` files with additional metadata to make them discoverable by PingFederate, we recommend building the project with the `build.xml` file included in the SDK.

## Implementation guidelines

The following topics provide programming guidance for developing custom interfaces.

- [Shared plugin interfaces](#) on page 1119
- [Developing IdP adapters](#) on page 1120
- [Developing SP adapters](#) on page 1132
- [Developing token processors](#) on page 1133
- [Developing token generators](#) on page 1134
- [Developing authentication selectors](#) on page 1134
- [Developing data source connectors](#) on page 1135
- [Developing password credential validators](#) on page 1137
- [Developing identity store provisioners](#) on page 1137
- [Developing notification publishers](#) on page 1143
- [Building and deploying your project](#)

For more details about interfaces discussed here and additional functionality, see the SDK Javadocs.

## Shared plugin interfaces

Plugin implementations generally invoke methods categorized as either configurable or describable. This document describes these types of plugins and how they are used in PingFederate.

### Configurable plugin

Any custom plugin that requires UI settings is configurable and implements the `ConfigurablePlugin` interface. This ensures that PingFederate loads the plugin instance with the correct configuration settings.

All plugin types implement the `ConfigurablePlugin` interface and must define the following within the `ConfigurablePlugin` interface to enable configuration loading.

```
void configure(Configuration configuration)
```

During processing of a configurable plugin instance, PingFederate calls the `ConfigurablePlugin.configure()` method and passes a **Configuration** object. The **Configuration** object provides the plugin adapter instance configuration set by an administrator in the PingFederate UI.

The `SpAuthnAdapterExample.java` sample provided with the SDK shows how to use this method to initialize an adapter instance from a saved configuration. After your implementation loads the configuration values, the plugin instance can use them in other method calls.

### Describable plugin

Any plugin that requires configuration windows in the PingFederate administrative console is a describable plugin. Most plugins implement the `DescribablePlugin` interface to ensure that PingFederate renders the correct UI components based on the returned `PluginDescriptor`.

Adapter and custom data source plugins are special cases and do not implement the `DescribablePlugin` interface. However, they still return a plugin descriptor (`AuthnAdapterDescriptor` and `SourceDescriptor`) and are still describable plugins.

All describable plugins must define a UI descriptor. Use one of the following methods to implement a UI descriptor, depending on the type of plugin:

- For plugins using the `DescribablePlugin` interface

```
PluginDescriptor getPluginDescriptor()
```

- For adapter plugins

```
AuthnAdapterDescriptor getAdapterDescriptor()
```

- For custom data source plugins

```
SourceDescriptor getSourceDescriptor()
```

Describable plugins can return a subclass of `PluginDescriptor`, so the return type might differ between plugin implementations. Your plugin implementation populates `PluginDescriptor` with `FieldDescriptors`, `FieldValidators`, and `Actions` and is presented as a set of UI components in the PingFederate administrative console.



#### Tip:

Some plugin types offer concrete descriptor implementations for developers. The Javadocs and examples provided with the SDK show which descriptor classes are available for each plugin type. The examples

also show you how to use `FieldDescriptors`, `FieldValidators`, and `Actions` to define your plugin descriptor.

## Developing IdP adapters

Developers can use the PingFederate SDK to create identity provider (IdP) adapters.

IdP adapters facilitate integration with external authentication systems, allowing user attributes to be looked up and sessions to be terminated during logout. In addition to performing the primary authentication step, IdP adapters can also perform secondary authentication steps to confirm the user's identity. Administrators can configure IdP adapters in sign-on authentication policies and in policies for resetting or changing passwords.

The IdP authentication adapter interface

Developers can create an IdP adapter by implementing the `IdpAuthenticationAdapterV2` interface. Implementing this interface requires the following Java packages:

- `org.sourceid.saml20.adapter.idp.authn`
- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`

For each IdP adapter implementation, in addition to the methods described in [Shared plugin interfaces](#) on page 1119, you must define methods for:

- User attribute lookup
- Session termination

Looking up user attributes

PingFederate invokes the `lookupAuthN()` method of your IdP adapter to look up user attributes for a request, regardless of whether the request is for IdP- or SP-initiated single sign-on (SSO), an OAuth transaction, or direct IdP-to-SP adapter processing. PingFederate uses the same method to authenticate a user when the adapter is placed in a password reset or password change policy.

```
AuthnAdapterResponse lookupAuthN(
    HttpServletRequest req,
    HttpServletResponse resp,
    Map<String, Object> inParameters)
    throws AuthnAdapterException, IOException;
```



### Note:

The `IdpAuthenticationAdapterV2` interface provides an overloaded version of the `lookupAuthN()` method. The original `lookupAuthN()` method in the `IdpAuthenticationAdapter` interface is deprecated, so only use the method in the `IdpAuthenticationAdapterV2` interface.

The parameters for the `lookupAuthN()` method are `HttpServletRequest`, the `HttpServletResponse`, and the `inParameters` map. The `inParameters` map contains important information about the SSO transaction that an adapter can use. The parameter keys are defined and documented in the `IdpAuthenticationAdapterV2` interface.

If an adapter is able to identify the user without further interaction, it can immediately return an `AuthnAdapterResponse` containing the user attributes. If the adapter needs further interaction, it can write to the `HttpServletResponse` as appropriate and commit it. Immediately after invoking `lookupAuthN()`, PingFederate checks if the response has been committed. If it has been committed, PingFederate saves the state it needs and stops processing the current transaction. PingFederate continues processing the transaction when the browser returns to the transaction's resume path, at which



point `PingFederate` again invokes the `lookupAuthN()` method. This series of events will be repeated until the method returns without committing the response. When that happens, which could be during the first invocation, `PingFederate` continues transaction processing using the result of the method.

 **Note:**

If the response is committed, then `PingFederate` ignores the return value. It only uses the return value of an invocation that does not commit the response.


The return type of `lookupAuthN()` is `AuthnAdapterResponse`. When the adapter has completed its processing and returns a value, it must populate the `authnStatus` field of this object. If the `authnStatus` is `SUCCESS`, it must also provide the user attributes in the `attributeMap` field. There are several attribute keys with special meanings, which are defined and documented in the `IdpAuthenticationAdapterV2` interface.

Two basic styles of IdP adapter are common. In the first style, the adapter presents the user a form in which the user enters their credentials to authenticate themselves. Such adapters can use the `TemplateRendererUtil` class to render an HTML template in the user's browser. An example of such an adapter is `template-render-adapter-example`, which is in the `/sdk/plugin-src` directory of `PingFederate`. That example also shows how you can develop an interactive adapter that supports the `PingFederate` authentication API. For more information, see [Developing authentication API-capable adapters and selectors](#) on page 1123.

The second style of IdP adapter redirects the user to an external authentication system. After the user has been authenticated, the external system must redirect the user to the resume path for the SSO transaction. This path is provided to the adapter in the `inParameters` map using the key `IN_PARAMETER_NAME_RESUME_PATH`.

How the user attributes are returned to the adapter is up to the implementation. If the authentication system provides an API for retrieving user attributes, a reference to the attributes can be passed through a query parameter appended to the resume URL. Alternatively, if the authentication system shares a parent domain with `PingFederate`, a cookie can be used to communicate the user attributes.

The following diagram and numbered list show the request sequence for an adapter that redirects to an external authentication system.



IdP-initiated SSO sequence:

1. A user signs on to a local application or domain through an authentication mechanism such as an identity-management system.
2. The user requests access to a protected resource located in the service provider (SP) domain. The link or other mechanism invokes the `PingFederate` SSO service.
3. `PingFederate` invokes the designated adapter's lookup method, including the `resumePath` parameter.

4. The application server returns the session information and redirects the browser along with the returned information to the `resumePath` URL.
5. PingFederate generates a SAML assertion and sends the browser with the SAML assertion to the SP's SAML gateway.

### Managing session attributes

The PingFederate SDK allows adapters to track session attributes. These attributes are stored in memory and replicated across multiple cluster nodes. They are looked up using the attribute name and the `PF` cookie from the user's browser.

Session attributes can be global, spanning multiple SSO transactions, or be linked to a specific transaction. To avoid prompting the user again for credentials, an adapter could use a global session attribute containing the user attributes that were obtained when the user first signed on. A multi-factor authentication (MFA) adapter can use a transaction-scoped attribute to keep track of a one-time passcode that was sent to the user's mobile device. Use `SessionStateSupport` to keep track of global attributes and use `TransactionalStateSupport` to track attributes for the current transaction. It's important to remove transactional attributes when your adapter is finished processing and about to return a result from `lookupAuthN()`. This reduces heap usage and, more importantly, helps avoid subtle security issues.

PingFederate can maintain an authentication session on behalf of your adapter. If an authentication session is enabled for your adapter and user attributes were obtained through a previous call to `lookupAuthN()`, then PingFederate will avoid calling `lookupAuthN()` during subsequent SSO transactions, provided the session idle or maximum timeout has not been exceeded.

Generally, it's better to rely on the PingFederate authentication session capability, rather than implementing your own within your adapter. If you do implement an internal session capability, ensure this session is not used when the authentication policy for the transaction indicates that reauthentication is required. The policy for the transaction is passed in the `inParameters` map using the key `IN_PARAMETER_NAME_AUTHN_POLICY`.

### Designing adapters for use in password reset or password change policies

The HTML Form Adapter can invoke an authentication policy during password reset or password change operations. When your adapter is invoked as part of such a policy, `IN_PARAMETER_NAME_USERID` refers to the username the user entered at the start of the operation.



#### Important:

Consider the following when designing adapters that will be used in password reset or password change policies.

If your adapter can track an internal session, an existing session should not be used during a password reset or password change transaction. PingFederate will ensure the `reauthenticate` flag in the transaction policy (`IN_PARAMETER_NAME_AUTHN_POLICY` in the `inParameters` map) is set to `true`. When this flag is `true`, your adapter should ignore any existing session.

Session attributes that track the progress of the current authentication attempt should be stored using `TransactionalStateSupport` and must be removed when returning a success or failure result from `lookupAuthN()`. In particular, if your adapter tracks a session attribute indicating the authentication was successful (for example, to render a "Success" page to the user), you should store that attribute using `TransactionalStateSupport` and ensure it's removed before returning `AUTHN_STATUS.SUCCESS` from `lookupAuthN()`.

## Terminating sessions

During single logout (SLO) request processing, PingFederate invokes your IdP adapter's `logoutAuthN()` method to terminate a user's session. This method is invoked during IdP- or SP-initiated SLO requests.

```
boolean logoutAuthN(Map authnIdentifiers,
    HttpServletRequest req,
    HttpServletResponse resp,
    String resumePath)
    throws AuthnAdapterException, IOException
```

Like the `lookupAuthN()` method, the `logoutAuthN()` method has access to the `HttpServletRequest` and `HttpServletResponse` objects. The user attributes returned earlier from `lookupAuthN()` are also passed as the input parameter `authnIdentifiers`.

If your adapter maintains an internal session, it should remove associated session attributes during `logoutAuthN()`. If the adapter is associated with an external authentication system, it can redirect the browser to an endpoint used to terminate the session at the application. The `resumePath` parameter contains the URL to which the user is redirected to complete the SLO process.

## Developing authentication API-capable adapters and selectors

The PingFederate authentication API lets applications interact with authentication policies. Making an adapter or selector plugin API-capable means ensuring that an authentication application can invoke the plugin through this API.

API-capable plugins must handle JSON-based API requests. When a plugin is invoked through the authentication API endpoint, if it needs interaction from the user, the plugin sends a JSON-based response rather than rendering a template.

Adapter and selector plugins handle distinct kinds of requests and generate distinct kinds of responses. The main method you implement in adapters is `lookupAuthN()`. The main method you implement in selectors is `selectContext()`.

Developing an API-capable plugin requires a dependency on the PingFederate authentication API SDK JAR file, `pf-authn-api-sdk-version.jar`. In the PingFederate installation package, you can find the SDK JAR file in the `server/default/lib` directory. Documentation for the classes are in the Javadocs for the standard PingFederate SDK, under `sdk/doc/index.html` in the PingFederate install package.

### Authentication API states, actions, and models

To develop authentication API-capable adapters and selectors, you must understand the states, actions, and models of single sign-on (SSO) transactions through the PingFederate authentication API.

PingFederate assigns a flow ID to each SSO transaction that uses the authentication API. PingFederate uses the flow ID to determine a transaction's state.

As a user steps through an SSO transaction, the transaction is always in some state. The state includes a status field and other fields specific to that state. The class containing those other fields is the model for the state.

The API endpoint returns the following when the user's SSO transaction has reached the `USERNAME_PASSWORD_REQUIRED` state for the form adapter.

```
{
  "id": "PyH5g",
  "pluginTypeId": "7RmQNDWaOnBoudTufx2sEw",
  "status": "USERNAME_PASSWORD_REQUIRED",
  "showRememberMyUsername": false,
  "showThisIsMyDevice": false,
  "thisIsMyDeviceSelected": false,
  "showCaptcha": false,
  "rememberMyUsernameSelected": false,
  "_links": {
```

```

"self": {
  "href": "https://localhost:9031/pf-ws/authn/flows/PyH5g"
},
"checkUsernamePassword": {
  "href": "https://localhost:9031/pf-ws/authn/flows/PyH5g"
}
}
}
}

```

The model for this state is the class `UsernamePasswordRequired`. It includes fields such as `showThisIsMyDevice`, which help the API client know how to render the credential prompt to the user.

The API response also includes a list of available actions. In this case, the only action available is `checkUsernamePassword`. The API client can select this action by sending a POST request with the Content-Type of `application/vnd.pingidentity.checkUsernamePassword+json`. Each action has its own model containing the fields that the POST body can provide. For the `checkUsernamePassword` action, the model is `CheckUsernamePassword`.

The POST body can be as simple as the following.

```

{
  "username": "joe",
  "password": "2Federate"
}

```

After receiving this request, `PingFederate` calls the `lookupAuthN()` method of the form adapter. If the form adapter encounters an error while validating the credentials, it writes a JSON API error to the response. If the form adapter successfully validates the credentials, it returns `AUTHN_STATUS.SUCCESS` from its `lookupAuthN()` method. `PingFederate` then goes to the next step in the authentication policy. If the next step is an API-capable adapter, `PingFederate` calls `lookupAuthN()` on that adapter and the adapter determines its current state and writes it to the response, along with the available actions.



#### Note:

The `PingFederate` authentication API follows a different naming convention for actions than `PingOne`. `PingOne` names actions as *noun.verb*, such as `otp.check`. `PingFederate` uses *verbNoun*, such as `checkOtp`.

### Specification of the plugin API

The first step in adding API support to your plugin is to implement the `AuthnApiPlugin` interface.

The `AuthnApiPlugin` interface has two methods: `getApiSpec()` and `getApiPluginDescriptor()`. You only need to implement the `getApiSpec()` method. The API specification this method returns defines the states, models, and actions that your plugin exposes in the API.

The API specification is defined by the `*Spec` classes in the SDK. These include `AuthnStateSpec`, `AuthnActionSpec`, `AuthnErrorSpec`, and `AuthnErrorDetailSpec`. The information in these classes lets the `PingFederate` authentication API Explorer provide documentation for API client developers. That documentation describes your plugin's API and lets developers experiment with it.

You can access the API Explorer at `https://PingFederate_host:9031/pf-ws/authn/explorer`. To enable the API Explorer, go to the **Authentication API Applications** window and select the **Enable API Explorer** check box. An easy way to use the API Explorer is to create an authentication API application in `PingFederate` and set the URL for the application to the API Explorer's URL.



#### Note:

When defining models for states and actions, use the `@Schema` annotation to describe each field in the model and show whether the field is required.

The rest of this document primarily uses the `TemplateRenderAdapter` as an example. The source for this adapter is in the PingFederate installation package's `sdk/plugin-src/template-render-adapter-example` directory. This adapter is simple. It just prompts the user to enter their username and provide a set of string attributes. The administrator defines the list of attributes by extending the adapter contract. The attribute values are passed back in the `SubmitUserAttributes` model as a map. Representing field values using a map in the model is unusual. Usually a separate field in the model defines each allowed field, which provides better type safety in the code.

### State model example

The following is an example of a state model used by the `TemplateRenderAdapter`.

```
/**
 * This is the model for the USER_ATTRIBUTES_REQUIRED state. It defines the
 * fields that are returned to the API client in a GET response for this
 * state.
 */
public class UserAttributesRequired
{
    private List<String> attributeNames = new ArrayList<>();

    /**
     * Get the list of user attributes supported by this adapter instance.
     *
     * It is recommended to annotate each getter with the @Schema annotation
     * and provide a description. This description will be used in
     * generating API documentation.
     */
    @Schema(description="A list of user attribute names that are supported by
    this adapter instance.")
    public List<String> getAttributeNames()
    {
        return attributeNames;
    }

    /**
     * Set the list of user attributes supported by this adapter instance.
     */
    public void setAttributeNames(List<String> attributeNames)
    {
        this.attributeNames = attributeNames;
    }
}
```

### Action model example

The following is the model for the `submitUserAttributes` action.

```
/**
 * This is the model for the submitUserAttributes API action. It defines
 * the
 * fields that may be included in the POST body for this action.
 */
public class SubmitUserAttributes
{
    private String username;
    private Map<String, Object> userAttributes = new HashMap<>();

    /**
     * Get the username.
     */
}
```

```

*
* It is recommended to annotate each getter with the @Schema annotation
* and provide a description. The 'required' flag can also be specified.
This
* information will be used in generating API documentation.
*/
@Schema(description="The user's username.", required=true)
public String getUsername()
{
    return username;
}

/**
 * Set the username.
 */
public void setUsername(String username)
{
    this.username = username;
}

/**
 * Get the user attributes.
 */
@Schema(description="Additional user attributes, as name-value pairs.")
public Map<String, Object> getUserAttributes()
{
    return userAttributes;
}

/**
 * Set the user attributes.
 */
public void setUserAttributes(Map<String, Object> userAttributes)
{
    this.userAttributes = userAttributes;
}
}

```

### AuthnStateSpec and AuthnActionSpec objects

A fluent builder is provided for creating `AuthnStateSpec` and `AuthnActionSpec` objects.

Here is the definition of the `AuthnStateSpec` for the `USER_ATTRIBUTES_REQUIRED` state:

```

public final static AuthnStateSpec<UserAttributesRequired>
    USER_ATTRIBUTES_REQUIRED = new
    AuthnStateSpec.Builder<UserAttributesRequired>()
    .status("USER_ATTRIBUTES_REQUIRED")
    .description("The user's username and attributes are required.")
    .modelClass(UserAttributesRequired.class)
    .action(ActionSpec.SUBMIT_USER_ATTRIBUTES)
    .action(CommonActionSpec.CANCEL_AUTHENTICATION)
    .build();

```

Here is the specification for the `submitUserAttributes` action:

```

public final static AuthnActionSpec<SubmitUserAttributes>
    SUBMIT_USER_ATTRIBUTES = new
    AuthnActionSpec.Builder<SubmitUserAttributes>()
    .id("submitUserAttributes")
    .description("Submit the user's username and attributes.")
    .modelClass(SubmitUserAttributes.class)
    .error(CommonErrorSpec.VALIDATION_ERROR)
    .errorDetail(ErrorDetailSpec.INVALID_ATTRIBUTE_NAME)

```

```
.build();
```

### Error specifications

Action specifications can include a list of possible errors and error details. Each top-level error that an authentication API request returns can include one or more error detail objects underneath it.

Typically, in the API specification, your only top-level error will be

`CommonErrorSpec.VALIDATION_ERROR`. However, you can include error detail specifications that can appear under that top-level error.

The following is how the `TemplateRenderAdapter` defines the specification for the `INVALID_ATTRIBUTE_NAME` error detail.

```
public final static AuthnErrorDetailSpec INVALID_ATTRIBUTE_NAME = new
    AuthnErrorDetailSpec.Builder()
        .code("INVALID_ATTRIBUTE_NAME")
        .message("An invalid attribute name was provided.")
        .parentCode(CommonErrorSpec.VALIDATION_ERROR.getCode())
        .build();
```



#### Note:

The error detail specification must reference the error code of its parent top-level error. This ensures that the authentication API Explorer correctly represents the error information.

`INVALID_ATTRIBUTE_NAME` is an example of an error that would be useful for API client developers but not for end users.

For more information about defining user-facing errors, see [Error messages and localization](#).

### State model contents

The model for a state includes all the information an API client would need to build a form (not necessarily an HTML form) to show the user. A state model should not include the text for messages to display to the user.

Defining messages for users, and localizing them if needed, is the responsibility of the API client. One of the reasons we avoid including messages in state models is that those messages will often end up including semantic content that the API client needs to drive its code. Following the rule that models do not include messages helps ensure that our models include all the fields that an API client needs to provide the desired user experience.

Sometimes following this rule requires you to add more states. This is preferable to embedding the state information inside of a message because it makes it easier for an API client to handle that state in the desired way.

The one exception we have to this rule is around error messages. API errors include error message text, and in some cases, API clients will display the message text directly to users. This avoids every API client having to write its own messages for every user-facing error the API can generate. For more information, see [Error messages and localization](#).

### Non-interactive plugins

Some plugins, typically selectors, do not need to interact with the user to do their job. Making these plugins API-capable is straight-forward.

You still implement the `AuthnApiPlugin` interface, but you can just return null from the `getApiSpec()` method. And then you override the default implementation of `getApiPluginDescriptor()` and return an `AuthnApiPluginDescriptor` instance with the `interactive` flag set to `false`. As with many other classes in the SDK, there is an `AuthnApiPluginDescriptor.Builder` class to help in creating the descriptor.

When `interactive` is `false`, `PingFederate` knows that it never needs to redirect when it encounters your selector. If the request is occurring on the API endpoint, `PingFederate` can immediately call `selectContext()`. The same is true if the request is occurring on a front-channel endpoint, such as `/as/authorization.oauth2`.

If your selector does not implement `AuthnApiPlugin`, then `PingFederate` assumes that only a front-channel endpoint can call your selector. If `PingFederate` encounters your selector while executing an API request, `PingFederate` will send a `RESUME` response to the API client so that the user is redirected to `PingFederate`.

### Runtime behavior implementation

After you specify your plugin's API at least partially, you can start implementing the runtime behavior. Use the specification that you defined previously to implement the runtime functionality.

Follow this pattern in `lookupAuthN()`:

1. Check for the possible actions the adapter expects in the current state.
2. If an action is matched, then try to extract the expected model from the request and handle the action.
3. If an action is requested, but it does not match an action allowed for the current state, then return an `INVALID_ACTION_ID` error.
4. If no action is requested, render the response for the current state.

The `AuthnApiSupport` class provides much of the functionality for handling API requests and sending responses. The `TemplateRenderAdapter` stores a reference to this singleton in its `apiSupport` field.

```
private AuthnApiSupport apiSupport = AuthnApiSupport.getDefault();
```

### Checking for actions

The following code shows the preferred approach for checking for the `submitIdentifiers` action.

The adapter performs this check two ways, depending on whether the current request is from the API endpoint. The `TemplateRenderAdapter` uses a slightly different but equivalent method.

```
/**
 * Determine if the user chose "Submit".
 */
private boolean isSubmitAttributesRequest(HttpServletRequest req)
{
    if (apiSupport.isApiRequest(req))
    {
        return ActionSpec.SUBMIT_USER_ATTRIBUTES.isRequested(req);
    }
    return StringUtils.isNotBlank(req.getParameter("pf.submit"));
}
```

### Extracting models from requests

The next step extracts the model from the request. This step varies depending on whether the request is from the API endpoint. For an API request, call the `AuthnApiSupport.deserializeAsModel()` method. For a non-API request, you must build the model from the parameters in the request.

```
private SubmitUserAttributes getSubmittedAttributes(HttpServletRequest req)
    throws AuthnErrorException, AuthnAdapterException
{
    if (apiSupport.isApiRequest(req))
    {
        try
        {
            return apiSupport.deserializeAsModel(req, SubmitUserAttributes.class);
        }
        catch (IOException e)
        {

```



```

        throw new AuthnAdapterException(e);
    }
}
else
{
    SubmitUserAttributes result = new SubmitUserAttributes();
    result.setUsername(req.getParameter("username"));

    for (String key : extendedAttr)
    {
        result.getUserAttributes().put(key, req.getParameter(key));
    }
    return result;
}
}
}

```

The `deserializeAsModel()` method also does some validation on the incoming JSON. This includes checking for fields flagged as `required` in the model, using the `@Schema` annotation. If a validation error occurs during this step, the method throws an `AuthnErrorException`, which the adapter can convert to an API error response. For more information, see [Handling authentication error exceptions](#).

### Performing additional validation

The `deserializeAsModel()` method performs some basic validation on the submitted JSON. Your adapter probably needs to perform more validation and send an `AuthnError` to the API client if it finds any errors. Here is how the `TemplateRenderAdapter` validates the names of the provided user attributes:

```

private void validateSubmittedAttributes(HttpServletRequest req,
    SubmitUserAttributes submitted) throws AuthnErrorException
{
    if (apiSupport.isApiRequest(req))
    {
        List<AuthnErrorDetail> errorDetails = new ArrayList<>();
        for (String attrName : submitted.getUserAttributes().keySet())
        {
            if (!extendedAttr.contains(attrName))
            {
                errorDetails.add(ErrorDetailSpec.INVALID_ATTRIBUTE_NAME.makeInstanceBuilder()
                    .message("Invalid attribute name: " + attrName).build());
            }
        }
        if (!errorDetails.isEmpty())
        {
            AuthnError authnError = CommonErrorSpec.VALIDATION_ERROR.makeInstance();
            authnError.setDetails(errorDetails);
            throw new AuthnErrorException(authnError);
        }
    }
}
}

```

### Handling invalid action IDs

If a request from an API client includes an action ID that does not match any actions available in the current state, it is best practice to return an error to the client.

After checking all the possible actions, if none match and the request's action ID is not null, the adapter can throw an `AuthnErrorException`. The adapter catches this exception and writes an error to the API response.

```

if (apiSupport.getActionId(req) != null)
{

```

```
// An action ID was provided but it does not match one of those expected in
the current state.
throw new
AuthnErrorException(CommonErrorSpec.INVALID_ACTION_ID.makeInstance());
}
```

### Handling authentication error exceptions

If the `deserializeAsModel()` method detects an error while deserializing the model, it throws an `AuthnErrorException`. If the added validation checks in `validateSubmittedAttributes` detect an error, they also throw this exception.

The adapter should catch this exception and send an API error response using the method `AuthnApiSupport.writeErrorResponse()`.

```
try
{
...
}
catch (AuthnErrorException e)
{
// A validation error occurred while processing an API request, return an
error response to the API client
apiSupport.writeErrorResponse(req, resp, e.getValidationError());
authnAdapterResponse.setAuthnStatus(AUTHN_STATUS.IN_PROGRESS);
return authnAdapterResponse;
}
```

### Sending API responses

`AuthnApiSupport` provides several methods for writing API responses.

The following example shows how the `TemplateRenderAdapter` writes the response for the `USER_ATTRIBUTES_REQUIRED` state.

```
private void renderApiResponse(HttpServletRequest req, HttpServletResponse
resp, Map<String, Object> inParameters) throws AuthnAdapterException
{
UserAttributesRequired model = new UserAttributesRequired();
model.setAttributeNames(new ArrayList<>(extendedAttr));
AuthnState<UserAttributesRequired> authnState =
apiSupport.makeAuthnState(req, StateSpec.USER_ATTRIBUTES_REQUIRED, model);
try
{
apiSupport.writeAuthnStateResponse(req, resp, authnState);
}
catch (IOException e)
{
throw new AuthnAdapterException(e);
}
}
```

The `makeAuthnState()` method takes an `AuthnStateSpec` and an instance of the model for that state and builds an `AuthnState` object. The `AuthnState` object can then be further modified. For example, you could remove an action that is not currently applicable using the `removeAction()` method. Then you write the `AuthnState` object to the response using the `writeAuthnStateResponse()` method.

### Returning authentication statuses

As with non-API requests, when the adapter finishes, it returns `AUTHN_STATUS.SUCCESS` or `AUTHN_STATUS.FAILURE` from `lookupAuthN()`.

If the adapter has not yet finished and has written something to the response, it should return `AUTHN_STATUS.IN_PROGRESS`.

## Session state management

Session state management for authentication API adapters is no different than for regular adapters. The same mechanisms, such as `SessionStateSupport` and `TransactionalStateSupport`, are used to store and retrieve session attributes on behalf of a user.

It should not be necessary to store more state attributes just to support the authentication API. The same session attributes should cover both API and non-API requests.

You can also wrap an API-capable adapter in a `PingFederate`-managed authentication session. `PingFederate`-managed authentication sessions mean that many adapters no longer need to provide their own internal session tracking.

## Error messages and localization

Error messages are the one case where an API response could include user-facing text. The typical case is a validation error.

For validation errors, the adapter constructs an `AuthnError` with the code `VALIDATION_ERROR`, and then adds `AuthnErrorDetail` objects for each of the errors that occurred. The `userMessage` field of the `AuthnErrorDetail` object provides the user-facing text. Like states and actions, you can define errors up front using an `AuthnErrorSpec` or an `AuthnErrorDetailSpec`. Then an instance of the error is constructed from the specification on demand.

The following example shows how you can define the specification for an invalid OTP error.

```
public final static AuthnErrorDetailSpec INVALID_OTP = new
    AuthnErrorDetailSpec.Builder()
        .code("INVALID_OTP")
        .message("An invalid or expired OTP code was provided.")
        .userMessage("This code is invalid or has expired.")
        .parentCode(CommonErrorSpec.VALIDATION_ERROR.getCode())
        .build();
```

The following example shows how you can use that specification to send an error response to the API client.

```
AuthnErrorDetail errorDetail =
    ErrorDetailSpec.INVALID_OTP.makeInstanceBuilder().build();
AuthnError authnError =
    CommonErrorSpec.VALIDATION_ERROR.makeInstanceBuilder().detail(errorDetail).build();
apiSupport.writeErrorResponse(req, resp, authnError);
```

To localize the error message using a properties file for your adapter, you can use `LocaleUtil` and `LanguagePackMessages` from the standard `PingFederate` SDK.

```
LanguagePackMessages messages = new LanguagePackMessages("my-adapter-
messages", LocaleUtil.getUserLocale(req));
String errorMessage = messages.getMessage("invalid.otp.key", new String[]
{});
AuthnErrorDetail errorDetail =
    ErrorDetailSpec.INVALID_OTP.makeInstanceBuilder().userMessage(errorMessage).build();
AuthnError authnError =
    CommonErrorSpec.VALIDATION_ERROR.makeInstanceBuilder().detail(errorDetail).build();
apiSupport.writeErrorResponse(req, resp, authnError);
```

For more information about how `PingFederate` determines the user's locale at runtime, see [Locale overrides by cookies](#) on page 890.

Some errors reflect problems with API client programming rather than with end user input. If you think an error will not be shown to an end user, then you do not need to populate the `userMessage` field.

## Developing SP adapters

This topic describes how to create a service provider (SP) adapter, as well as the methods used during SP session creation, SP adapter session logout, and SP account linking.

### SP authentication adapter interface

Create service provider (SP) adapters by implementing the `SPAuthenticationAdapter` interface. Implementing this interface requires the following Java packages:

- `org.sourceid.saml20.adapter.sp.authn`
- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`

For each SP adapter implementation, in addition to the methods described in [Shared plugin interfaces](#) on page 1119, you must define:

- SP session creation
- SP adapter session logout
- SP account linking

### SP session creation

PingFederate invokes the `createAuthN()` method during the processing of a single sign-on (SSO) request to establish a security context in the external application for the user.

```
java.io.Serializable createAuthN(SsoContext ssoContext,
    javax.servlet.http.HttpServletRequest req,
    javax.servlet.http.HttpServletResponse resp,
    java.lang.String resumePath)
```

This method resembles the `IdpAuthenticationAdapter.lookupAuthN()` method in terms of the objects passed to it and its support for asynchronous requests using the `HttpServletResponse` and `resumePath` parameters. It also accepts an `SsoContext` object, which has access to information such as user attributes and the target destination URL.

### SP adapter session logout

PingFederate invokes the `logoutAuthN()` method during a single logout (SLO) request to terminate a user's session with the external application.

```
boolean logoutAuthN (java.io.Serializable authnBean,
    javax.servlet.http.HttpServletRequest req,
    javax.servlet.http.HttpServletResponse resp,
    java.lang.String resumePath)
    throws AuthnAdapterException, java.io.IOException
```

The `HttpServletResponse` and `resumePath` objects are available to support scenarios where the user's browser redirects to an additional service to clean up any remaining sessions.

### SP account linking

PingFederate invokes the `lookupLocalUserId()` method during an SSO request when the identity provider (IdP) connection uses account linking but no account link for this user is yet established.


```
java.lang.String lookupLocalUserId(
    javax.servlet.http.HttpServletRequest req,
    javax.servlet.http.HttpServletResponse resp,
    java.lang.String partnerIdpEntityId,
    java.lang.String resumePath)
```

```
throws AuthnAdapterException, java.io.IOException
```

After the account link is set, PingFederate maintains this information until the user defederates, which occurs when the user clicks a hyperlink redirecting them to the `/sp/defederate.ping` PingFederate endpoint.

The `HttpServletResponse` and `resumePath` objects are used to send the user to a local service where the user authenticates. After authentication, the user is redirected to the URL specified in the `resumePath` parameter and PingFederate completes the account link.

The following diagram illustrates a typical account-link sequence.



Use the `HttpServletRequest` to read a local session token. The `lookupLocalUserId()` method should return a local user identifier `String` object.

## Developing token processors

You can create a token processor by implementing the `TokenProcessor` interface.

The following Java packages are required for implementing the `TokenProcessor` interface:

- `org.sourceid.saml20.adapter.attribute`
- `org.sourceid.saml20.adapter.idp.authn`
- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`
- `org.sourceid.wstrust.model`
- `org.sourceid.wstrust.plugin`

- `org.sourceid.wstrust.plugin.process`
- `com.pingidentity.sdk`

For each token-processor implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must define the `TokenContext processToken(T token)` method.

PingFederate invokes the `processToken()` method when processing a security token service (STS) request to perform necessary operations for determining the validity of a token. The type parameter `T` must extend, at a minimum, the type `SecurityToken`. The type `BinarySecurityToken` is also available to represent custom security tokens that can be transported as Base64-encoded data.

## Developing token generators

You can create a token-generator implementation by using the `TokenGenerator` interface.

The following Java packages are required for implementing the `TokenGenerator` interface:

- `org.sourceid.saml20.adapter.sp.authn`
- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`
- `org.sourceid.wstrust.model`
- `org.sourceid.wstrust.plugin`
- `org.sourceid.wstrust.plugin.process`
- `com.pingidentity.sdk`

For each token-generator implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must define the `SecurityToken generateToken(TokenContext attributeContext)` method.

PingFederate invokes the `generateToken()` method when processing a security token service (STS) request to perform necessary operations for generation of a security token. The type `BinarySecurityToken` is available and you can use it to represent custom security tokens that can be transported as Base64-encoded data. The `TokenContext` contains subject data available for insertion into the generated security token.

## Developing authentication selectors

This topic describes aspects of authentication selectors within the context of PingFederate, including implementation, context selection, and callbacks.

### Authentication selector interface

Authentication selectors allow PingFederate to choose an appropriate authentication source, an identity provider (IdP) adapter or an IdP connection (for federation hub use cases), based on criteria defined in the authentication selector instance.

When creating an authentication selector, use the following primary Java packages:

- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`
- `com.pingidentity.sdk`

For each authentication selector implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must define the following:

- Context Selection
- Authentication selector callback

## Context selection

PingFederate calls the `selectContext()` method to determine which authentication source to select. The `mappedAuthnSourcesNames` contains the list of `AuthenticationSourceKeys` and names that are available for the selector to reference.

```
AuthenticationSelectorContext selectContext(HttpServletRequest req,
    HttpServletResponse resp,
    Map<AuthenticationSourceKey, String> mappedAuthnSourcesNames,
    Map<String, Object> extraParameters,
    String resumePath)
```

The `HttpServletRequest` can evaluate cookies, parameters, headers, and other request information to determine which authentication source to select. The `HttpServletResponse` also helps determine the appropriate authentication source to select if the authentication selector requires user interaction. If the `resp` object is written to, it is considered a committed response and returned to the user's browser. The `resumePath` is a relative URL used in conjunction with the `resp` object, such that the user's browser is sent to this URL to resume the single sign-on (SSO) work flow.

After an authentication source is selected, you can create an `AuthenticationSelectorContext` to denote which authentication source to use. You can reference the selected authentication source by its ID or by its context, which is a name that decouples authentication selectors from the configured IDs.

## Authentication selector callback

PingFederate calls the `callback()` method after authenticating against a selected source. The `callback()` method allows authentication selectors to update resulting attributes, set cookies, or perform other custom functions.

```
void callback(HttpServletRequest req,
    HttpServletResponse resp,
    Map authnIdentifiers,
    AuthenticationSourceKey authenticationSourceKey,
    AuthenticationSelectorContext authnSelectorContext);
```



### Note:

Writing content to the `resp` object in the `callback()` method is not supported, and doing so might result in unexpected behavior. Setting cookies is supported.

## Developing data source connectors

Use PingFederate to query various data sources or build data source connectors to process customized data sources.

PingFederate can query data sources for a variety of purposes using LDAP or Java Database Connectivity (JDBC) interfaces. Use the PingFederate SDK to build data source connectors to query additional data source types. Examples of other data sources include a web service, a flat file, or a different way of using a JDBC or LDAP connection than what is supplied by PingFederate.

The following are the primary Java packages used to build a custom data source:

- `com.pingidentity.sources`
- `com.pingidentity.sources.gui`

For each implementation described in [Shared plugin interfaces](#) on page 1119, you must define the following:

- Connection testing
- Available fields retrieval

- Data source query handling

#### Data source connection testing

```
boolean testConnection()
```

When associating a custom data source with an identity provider (IdP) or service provider (SP) connection, PingFederate tests connectivity to the data source by calling the `testConnection()` method. Your implementation of this method should perform the necessary steps to demonstrate a successful connection and return `true`, or return `false` if your implementation cannot communicate with the datastore. A `false` result prevents an administrator from continuing with the data source configuration.

#### Data source available fields retrieval

```
java.util.List<java.lang.String> getAvailableFields()
```

PingFederate calls the `getAvailableFields()` method to determine the available fields that can be returned from a query of this data source. These fields are displayed to the PingFederate administrator during the configuration of a data source lookup, and the administrator selects the attributes from the data source and maps them to the adapter or attribute contract. PingFederate requires at least one field returned from this method.

#### Data source query handling

```
java.util.Map<java.lang.String,java.lang.Object> retrieveValues(
    java.util.Collection<java.lang.String> attributeNamesToFill,
    SimpleFieldList filterConfiguration)
```

When processing a connection using a custom data source, PingFederate calls the `retrieveValues()` method to perform the actual query for user attributes. This method receives a list of attribute names populated with data. The method can also receive a `filterConfiguration` object populated with a list of fields. Each field contains a name/value pair determined at runtime and collectively used as the criteria for selecting a specific record. In most cases, the criteria are used to locate additional user attributes.

Create the filter criteria selections needed for this lookup by passing back a `CustomDataSourceDriverDescriptor`, an implementation of `SourceDescriptor`, from the `getSourceDescriptor()` method. A `CustomDataSourceDriverDescriptor` can include a `FilterFieldDataDescriptor` composed of a list of fields that can be used as the query criteria. This list of fields is displayed similarly to the other UI-descriptor display fields.



#### Note:

The `filterConfiguration` object is set and populated with a list of fields only if the data source was defined with a `CustomDataSourceDriverDescriptor`. If the `CustomDataSourceDriverDescriptor` was not used in the definition of the data source, the `filterConfiguration` object is set to null.



#### Important:

To pass runtime attribute values to the filter, an administrator must reference the attributes using the `${attribute name}` format when defining a filter in the PingFederate administrative console.

After all relevant attributes are retrieved from the data source, they must be returned as a map of name/value pairs, where the names correspond to the initial collection of attribute names passed into the method and the values are the attributes.



## Developing password credential validators

Password credential validators allow PingFederate administrators to define a centralized location for username/password validation, allowing PingFederate configurations to reference validator instances.

To implement a custom password credential validator, import the following Java packages:

- `org.sourceid.saml20.adapter.gui`
- `org.sourceid.saml20.adapter.conf`
- `org.sourceid.util.log`
- `com.pingidentity.sdk`
- `com.pingidentity.sdk.password`

For each implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must define the following method.

```
AttributeMap processPasswordCredential(String username,
    String password)
    throws PasswordValidationException
```

This method takes a username and password and verifies the credential against an external source. If the credentials are valid, it returns an `AttributeMap` containing at least one entry representing the principal. If the credentials are invalid, then it returns `null` or an empty map. If the plugin was unable to validate the credentials (for example, due to an offline host or network problems), it returns a `PasswordValidationException`.

To enable password changes in a password credential validator, implement the `com.pingidentity.sdk.password.ChangeablePasswordCredential` interface.

To enable password resets in a password credential validator, implement the `com.pingidentity.sdk.password.ResettablePasswordCredential` interface.



### Note:

Depending on your password management system, you might need additional system configuration to enable password changes. For example, you can change passwords in Active Directory only if LDAPS is enabled.

## Developing identity store provisioners

You can create an identity store provisioner by implementing either the `IdentityStoreProvisionerWithFiltering` or `IdentityStoreProvisioner` interface.

Both interfaces support provisioning and deprovisioning users and groups to an external user store. The `IdentityStoreProvisionerWithFiltering` interface supports list/query and filtering; the `IdentityStoreProvisioner` interface does not. For more information about list/query and filtering, see [3.2.2. List/Query Resources and 3.2.2.1. Filtering](#) in the SCIM specification.



### Note:

The `IdentityStoreUserProvisioner` interface is deprecated. Developers should implement either the `IdentityStoreProvisionerWithFiltering` or `IdentityStoreProvisioner` interfaces.

### **IdentityStoreProvisionerWithFiltering interface implementation**

Implement the `IdentityStoreProvisionerWithFiltering` interface to provision and deprovision users and groups to an external user store with list/query and filtering support.



### Note:

If you do not need to support list/query and filtering, you can implement the `IdentityStoreProvisioner` interface instead.

Implementing this interface requires the following Java packages:

- `com.pingidentity.sdk.provision`
- `com.pingidentity.sdk.provision.exception`
- `com.pingidentity.sdk.provision.users.request`
- `com.pingidentity.sdk.provision.users.response`
- `com.pingidentity.sdk.provision.groups.response`
- `com.pingidentity.sdk.provision.groups.request`



**Note:**

Group support is optional (see [Check for group provisioning support](#)).

For each identity store provisioner implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must implement the following:

- Create user
- Read user
- Read users (not applicable to the `IdentityStoreProvisioner` interface)
- Update user
- Delete user
- Check for group provisioning support
- Create group
- Read group
- Read groups (not applicable to the `IdentityStoreProvisioner` interface)
- Update group
- Delete group

### Create user

```
UserResponseContext createUser(CreateUserRequestContext createRequestCtx)
throws IdentityStoreException
```

invokes the `createUser()` method of your identity store provisioner in response to create-user requests made to services, such as inbound provisioning. This method creates the user in the user store managed by the identity store provisioner.

The `CreateUserRequestContext` contains all information needed to fulfill the request. If the user is successfully provisioned, the method returns a `UserResponseContext` containing the user attributes used to provision the user. The method throws an `IdentityStoreException` if an error occurred during the creation process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Read user

```
UserResponseContext readUser(ReadUserRequestContext readRequestCtx)
throws IdentityStoreException
```

invokes the `readUser()` method of your identity store provisioner in response to get-user requests made to services, such as inbound provisioning. This method retrieves user data from the user store managed by the identity store provisioner.

The `ReadUserRequestContext` contains all information needed to fulfill the request. If the user data is successfully retrieved, the method returns a `UserResponseContext` containing the user attributes for the user. The method throws an `IdentityStoreException` if an error occurred during the retrieval process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Read users

```
UsersResponseContext readUsers(ReadUsersRequestContext readRequestCtx)
throws IdentityStoreException
```

`PingFederate` invokes the `readUsers()` method of your identity store provisioner in response to list/query requests for user attributes made to `PingFederate` services, such as inbound provisioning. This method retrieves user data from the user store managed by the identity store provisioner.



#### Note:

The `readUsers` method applies only to the `IdentityStoreProvisionerWithFiltering` interface; it does not apply to the `IdentityStoreProvisioner` interface.

The `ReadUsersRequestContext` contains all information needed to fulfill the request. If the user data is successfully retrieved, the method returns a `UsersResponseContext` containing the user attributes satisfying the filter. If an error occurred during the retrieval process, the method returns an `IdentityStoreException`. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Update user

```
UserResponseContext updateUser(UpdateUserRequestContext updateRequestCtx)
throws IdentityStoreException
```

invokes the `updateUser()` method of your identity store provisioner in response to update-user requests made to services, such as inbound provisioning. This method updates the user in the user store managed by the identity store provisioner.

The `UpdateUserRequestContext` contains all information needed to fulfill the request. If the user data is successfully updated, the method returns a `UserResponseContext` containing the user's updated attributes. The method throws an `IdentityStoreException` if an error occurred during the update process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Delete user

```
void deleteUser(DeleteUserRequestContext deleteRequestCtx)
throws IdentityStoreException
```

invokes the `deleteUser()` method of your identity store provisioner in response to delete-user requests made to services, such as inbound provisioning. This method deprovisions the user in the user store managed by the identity store provisioner.

The `DeleteUserRequestContext` contains all information needed to fulfill the request. The method throws an `IdentityStoreException` if an error occurred during the deprovision process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.



#### Note:

The plugin implementation can choose not to permanently delete the resource, but must return a `NotFoundException` for all `readUser()`, `updateUser()`, and `deleteUser()` operations associated with the previously deleted ID. In addition, the plugin must not consider the deleted user in conflict calculation. For example, a `createUser()` request for a user with a previously deleted ID should not throw a `ConflictException`.

### Check for group provisioning support

```
boolean isGroupProvisioningSupported()
throws IdentityStoreException
```

Implement the `isGroupProvisioningSupported()` method to return true if group provisioning is supported by your identity store provisioner or false otherwise. The method throws an `IdentityStoreException` if an error occurred during the query process. See `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Create group

```
GroupResponseContext createGroup(CreateGroupRequestContext
createRequestCtx)
throws IdentityStoreException
```

`PingFederate` invokes the `createGroup()` method of your identity store provisioner in response to create-group requests made to `PingFederate` services, such as inbound provisioning. This method creates the group in the user store managed by the identity store provisioner if the `isGroupProvisioningSupported()` method returns true; otherwise, it should throw `NotImplementedException`.

The `CreateGroupRequestContext` contains all information needed to fulfill the request, such as group attributes. If the group is successfully provisioned, the method returns a `GroupResponseContext` containing the group attributes used to provision the group. The method throws an `IdentityStoreException` if an error occurred during the creation process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Read group

```
GroupResponseContext readGroup(ReadGroupRequestContext readRequestCtx)
throws IdentityStoreException
```

`PingFederate` invokes the `readGroup()` method of your identity store provisioner in response to get-group requests made to `PingFederate` services, such as inbound provisioning. This method retrieves group data from the user store managed by the identity store provisioner if the `isGroupProvisioningSupported()` returns true; otherwise, it should throw `NotImplementedException`.

The `ReadGroupRequestContext` contains all information needed to fulfill the request, such as group ID. If the group data is successfully retrieved, the method returns a `GroupResponseContext` containing the group attributes. The method throws an `IdentityStoreException` if an error occurred during the retrieval process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Read groups

```
GroupsResponseContext readGroups(ReadGroupsRequestContext readRequestCtx)
throws IdentityStoreException
```

PingFederate invokes the `readGroups()` method of your identity store provisioner in response to list/query requests for group attributes made to PingFederate services, such as inbound provisioning. This method retrieves group data from the user store managed by the identity store provisioner if the `isGroupProvisioningSupported()` returns true; otherwise, it should throw `NotImplementedException`.



#### Note:

The `readGroups` method applies only to the `IdentityStoreProvisionerWithFiltering` interface; it does not apply to the `IdentityStoreProvisioner` interface.

The `ReadGroupsRequestContext` will contain all information needed to fulfill the request (for example, a filter). If the group data was successfully retrieved, a `GroupsResponseContext` should be returned and contain the group attributes for the groups. An `IdentityStoreException` should be thrown if an error occurred during the retrieval process. See `com.pingidentity.sdk.provision.exception` package for different exceptions that can be thrown.

### Update group

```
GroupResponseContext updateGroup(UpdateGroupRequestContext
    updateRequestCtx)
throws IdentityStoreException
```

PingFederate invokes the `updateGroup()` method of your identity store provisioner in response to update-group requests made to PingFederate services, such as inbound provisioning. This method updates the group in the user store managed by the identity store provisioner if the `isGroupProvisioningSupported()` method returns true; otherwise, it should throw `NotImplementedException`.

The `UpdateGroupRequestContext` contains all information needed to fulfill the request, such as group attributes. If the group data is successfully updated, the method returns a `GroupResponseContext` containing the group's updated attributes. The method throws an `IdentityStoreException` if an error occurred during the update process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Delete group

```
void deleteGroup(DeleteGroupRequestContext deleteRequestCtx)
throws IdentityStoreException
```

PingFederate invokes the `deleteGroup()` method of your identity store provisioner in response to delete-group requests made to PingFederate services, such as inbound provisioning. This method deprovisions the group in the user store managed by the identity store provisioner if the `isGroupProvisioningSupported()` returns true; otherwise, it should throw `NotImplementedException`.

The `DeleteGroupRequestContext` contains all information needed to fulfill the request, such as a group ID. The method throws an `IdentityStoreException` if an error occurred during the deprovisioning process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

## IdentityStoreUserProvisioner interface implementation

The `IdentityStoreUserProvisioner` interface is deprecated, but you can still implement it to provision and deprovision users to an external user store.

The `IdentityStoreUserProvisioner` interface is deprecated. Developers can implement it to provision and deprovision users, but they should implement either the `IdentityStoreProvisionerWithFiltering` or `IdentityStoreProvisioner` interface.



### Note:

The `IdentityStoreUserProvisioner` interface does not provision or deprovision groups. For group support, see [IdentityStoreProvisionerWithFiltering interface implementation](#) on page 1137.

The following Java packages are required for implementing the interface:

- `com.pingidentity.sdk.provision`
- `com.pingidentity.sdk.provision.exception`
- `com.pingidentity.sdk.provision.users.request`
- `com.pingidentity.sdk.provision.users.response`

For each identity store provisioner implementation, in addition to the methods described under [Shared plugin interfaces](#) on page 1119, you must implement the following methods:

- Create user
- Read user
- Update user
- Delete user

### Create user

```
UserResponseContext createUser(CreateUserRequestContext createRequestCtx)
throws IdentityStoreException
```

invokes the `createUser()` method of your identity store provisioner in response to create-user requests made to services, such as inbound provisioning. This method creates the user in the user store managed by the identity store provisioner.

The `CreateUserRequestContext` contains all information needed to fulfill the request. If the user is successfully provisioned, the method returns a `UserResponseContext` containing the user attributes used to provision the user. The method throws an `IdentityStoreException` if an error occurred during the creation process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

### Read user

```
UserResponseContext readUser(ReadUserRequestContext readRequestCtx)
throws IdentityStoreException
```

invokes the `readUser()` method of your identity store provisioner in response to get-user requests made to services, such as inbound provisioning. This method retrieves user data from the user store managed by the identity store provisioner.

The `ReadUserRequestContext` contains all information needed to fulfill the request. If the user data is successfully retrieved, the method returns a `UserResponseContext` containing the user attributes for the user. The method throws an `IdentityStoreException` if an error occurred during the retrieval process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

## Update user

```
UserResponseContext updateUser(UpdateUserRequestContext updateRequestCtx)
throws IdentityStoreException
```

invokes the `updateUser()` method of your identity store provisioner in response to update-user requests made to services, such as inbound provisioning. This method updates the user in the user store managed by the identity store provisioner.

The `UpdateUserRequestContext` contains all information needed to fulfill the request. If the user data is successfully updated, the method returns a `UserResponseContext` containing the user's updated attributes. The method throws an `IdentityStoreException` if an error occurred during the update process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.

## Delete user

```
void deleteUser(DeleteUserRequestContext deleteRequestCtx)
throws IdentityStoreException
```

invokes the `deleteUser()` method of your identity store provisioner in response to delete-user requests made to services, such as inbound provisioning. This method deprovisions the user in the user store managed by the identity store provisioner.

The `DeleteUserRequestContext` contains all information needed to fulfill the request. The method throws an `IdentityStoreException` if an error occurred during the deprovision process. See the `com.pingidentity.sdk.provision.exception` package for exceptions that can be thrown.



### Note:

The plugin implementation can choose not to permanently delete the resource, but must return a `NotFoundException` for all `readUser()`, `updateUser()`, and `deleteUser()` operations associated with the previously deleted ID. In addition, the plugin must not consider the deleted user in conflict calculation. For example, a `createUser()` request for a user with a previously deleted ID should not throw a `ConflictException`.

## Developing notification publishers

To develop a notification publisher, implement the `NotificationPublisherPlugin` interface.

PingFederate administrators can define and manage notification publishers, as described in [Managing notification publisher instances](#) on page 1009. If those features do not meet your needs, you can develop a custom notification publisher using the PingFederate `NotificationPublisherPlugin` interface and the following Java packages:

- `com.pingidentity.sdk`
- `org.sourceid.saml20.adapter.conf`
- `org.sourceid.saml20.adapter.gui`

The `NotificationPublisherPlugin` interface, which extends the `Plugin` interface, defines the `publishNotification()` method.

For each implementation, define the `publishNotification()` method, in addition to the methods described in [Shared plugin interfaces](#) on page 1119. PingFederate invokes the `publishNotification()` method when publishing a notification. For example, you can configure PingFederate so that an account password change invokes the method.

```
PublishResult publishNotification(String eventType,
    Map<String, String> data,
```

```
Map<String, String> configuration)
```

The method returns the `PublishResult`, the status of the notification that the plugin instance sent.

For more information about the `NotificationPublisherPlugin` interface, see the SDK Javadocs. You can also see a sample implementation in `pingfederate/sdk/plugin-src`.

## Building and deploying with Ant

Use the Apache Ant build script to clean, build, package, and deploy projects within the PingFederate Java SDK.

About this task

The PingFederate Java SDK comes with an Apache Ant build script that simplifies building and deploying your projects.

Steps

1. Edit the `build.local.properties` file and set the `target-plugin.name` property to the name of your project subdirectory (see [Directory structure](#)).



### Note:

You can develop source code for multiple projects simultaneously, but you can build and deploy only one at a time. Change the value of the `target-plugin.name` property as needed to build and deploy other projects.

2. If your project depends on any third-party `.jar` files, place them into your project's `lib` directory. If the directory does not exist, create a new directory called `lib` directly under your project's directory. For example, `pingfederate/sdk/plugin-src/<subproject-name>/lib`.
3. On the command line in the `sdk` directory, use `ant` to clean, build, and package or to build, package, and deploy your project.

| Option  | Description                     |
|---|---------------------------------|
| Clean the project                                       | <code>ant clean-plugin</code>   |
| Compile the project                                     | <code>ant compile-plugin</code> |
| Compile the project and create a <code>.jar</code> file | <code>ant jar-plugin</code>     |



### Note:

The SDK creates a deployment descriptor in the `PF_INF` directory and places it in a `.jar` file. The descriptor tells PingFederate what plugin implementations are contained in the file, and the compiled class files and the deployment descriptor are placed in the `pingfederate/sdk/plugin-src/<subproject-name>/build/classes` directory. The `pf.plugins.<subproject-`



`<name>.jar` file is placed in the `pingfederate/sdk/plugin-src/<subproject-name>/build/jar` directory.

To compile the project, create a `.jar` file, and deploy the project to PingFederate, enter:

```
ant deploy-plugin
```

This build target performs the steps described above and deploys any `.jar` files found in the `lib` directory of your subproject.



**Note:**

To deploy your plugin manually to an installation of the PingFederate server, copy the `.jar` file and any third-party `.jar` files into the `/server/default/deploy/` directory of that PingFederate installation.

- Restart the PingFederate server.

## Building and deploying manually

Use a build utility to add directories, create deployment descriptors, and create a `.jar` file to build and deploy your plugins with PingFederate.

Before you begin

To compile your project, you must have the following directories on your classpath:

- `<pf_install>/pingfederate/server/default/lib`
- `<pf_install>/pingfederate/lib`
- `<pf_install>/pingfederate/sdk/lib`
- `<pf_install>/pingfederate/sdk/plugin-src/<subproject-name>/lib`

About this task

To build your project with another build utility, you must create the deployment descriptors for each of your plugins. The deployment descriptor files allow PingFederate to discover your plugins. Once this is complete, use the build tool to create a `.jar` file and deploy it within the appropriate directory.

Steps

- Add a new directory called `PF-INF` into your project. This directory must be at the root of your `.jar` file, similar to `META-INF`.
- In `PF-INF`, add an appropriate text file for each type of plugin you created:

| Plugin type                   | File name                      |
|-------------------------------|--------------------------------|
| IdP Adapter                   | idp-authn-adapters             |
| SP Adapter                    | sp-authn-adapters              |
| Custom Data Source            | custom-drivers                 |
| Token Processor               | token-processors               |
| Token Generator               | token-generators               |
| Authentication Selector       | authentication-selectors       |
| Password Credential Validator | password-credential-validators |

| Plugin type                | File name                   |
|----------------------------|-----------------------------|
| Identity Store Provisioner | identity-store-provisioners |
| CIBA Authenticator         | oob-auth-plugins            |
| Notification Publisher     | notification-sender         |

3. In each text file added, specify the fully-qualified class name of each plugin that implements the corresponding plugin interface. Place each class name on a separate line.
4. To create a `.jar`, archive the compiled class files along with the deployment descriptors using your build tool. The deployment descriptors must be in the `PF-INF` directory, located at the root of the `.jar` file.
5. To deploy your plugin, copy the `.jar` file and any third-party `.jar` files into the `<pf_install>/pingfederate/server/default/deploy` directory of the PingFederate installation.

## Log messages

You can use a typical logging pattern based on the Apache Commons logging framework to log messages from your adapter, token translator, or custom data source driver.

The service provider (SP) adapter contained in the directory `sdk/adapters-src/sp-adapter-example` shows how to use a logger for your adapter.

# Developer's Reference Guide

---

This section describes the PingFederate endpoints and APIs.

Use this developer's guide to learn how to develop authentication API-capable adapters and selectors with the following endpoints and APIs:

- [OAuth 2.0 endpoints](#) on page 1146
- [Web service interfaces and APIs](#) on page 1193
- [Application endpoints](#) on page 1249
- [Authentication API](#) on page 1273
- [Developing authentication API-capable adapters and selectors](#) on page 1123

## OAuth 2.0 endpoints

---

When developing OAuth-capable applications, developers must follow the OAuth 2.0 Authorization Framework and OpenID Connect specifications if applicable.

OAuth-capable applications must send requests to various OAuth endpoints to obtain authorization grants, access tokens, refresh tokens, and ID tokens if applicable. Additional endpoints exist for other purposes, including for clients to validate access and refresh tokens, for developers to submit client registrations using the OAuth 2.0 Dynamic Client Registration protocol, and for clients to retrieve OpenID Connect metadata.

Each endpoint extends from the runtime server at the base URL. If you configure virtual host names, the endpoints are also accessible at those locations.

Example

Example

If the base URL is `https://www.example.com:9031` and the configured virtual host names are `www.example.org` and `www.example.info`, the authorization and token endpoints are accessible at the following locations:

Authorization endpoint `/as/authorization.oauth2`

- `https://www.example.com:9031/as/authorization.oauth2`
- `https://www.example.org:9031/as/authorization.oauth2`
- `https://www.example.info:9031/as/authorization.oauth2`

Token endpoint `/as/token.oauth2`

- `https://www.example.com:9031/as/token.oauth2`
- `https://www.example.org:9031/as/token.oauth2`
- `https://www.example.info:9031/as/token.oauth2`

## Authorization endpoint

The OAuth authorization server (AS) uses the authorization endpoint to interact directly with resource owners, authenticate them, and obtain their authorizations.

[The OAuth 2.0 Authorization Framework](#) defines the authorization endpoint. Typically, an OAuth client makes an authorization request by directing a resource owner through an HTTP user-agent to the authorization endpoint. After the OAuth AS completes its interaction with the resource owner, the OAuth AS redirects the resource owner's user-agent back to the client's redirect URI with the response to the authorization request.



### Note:


This endpoint can be used in an OAuth Scope Authentication Selector configuration, which can affect the behavior of the endpoint. For example, the `idp` parameter might be enforced or overridden by policy determined by an instance of the OAuth Scope Authentication Selector.



This endpoint accepts the HTTP GET and POST methods.



Endpoint: `/as/authorization.oauth2`



When transmitting through the HTTP POST method, the required **Content-Type** value is `application/x-www-form-urlencoded`. The following table describes parameters for this endpoint.


| Parameter                            | Description  |
|--------------------------------------|--|
| <code>client_id</code><br>(Required) | The client identifier.   |
| <code>response_mode</code>           | When set to <code>form_post</code> , the authorization response is returned to the client in an auto-POST form, in accordance with <a href="#">the OAuth 2.0 Form Post Response Mode specification</a> . |

| Parameter             | Description   |
|-----------------------|---|
| <b>response_type</b>  | <p>A value of <code>code</code> results in the Authorization Code grant type while a value of <code>token</code> implies the Implicit grant type. Additionally, a value of <code>id_token</code> can be requested by implicit clients.</p> <p>To initiate a Hybrid Flow, multiple <code>response_type</code> values can be specified by space-separating them. When using the Hybrid Flow, some tokens are returned from the Authorization Endpoint and others are returned from the Token Endpoint. For information about multiple-valued response type combinations, see the description of the <code>restrictedResponseTypes</code> parameter in <a href="#">OAuth Client Management Service</a> on page 1201.</p> |
| <b>code_challenge</b> | <p>To reduce the risk of authorization code interception attack, supply a one-time string value to associate the authorization request with the token request. For more information, see <a href="#">Proof Key for Code Exchange (PKCE) by OAuth Public Clients</a>.</p> <p>Applicable only when <code>response_type</code> parameter value is <code>code</code>. Mandatory if the client is required to do so. For more information, see <b>Require Proof Key for Code Exchange (PKCE)</b> in <a href="#">Configuring OAuth clients</a> on page 566.</p>   |
|                       | <p> <b>Note:</b></p> <p>If used, the OAuth client must submit the corresponding code verifier when using the authorization code to obtain an access token. For more information, see <code>code_verifier</code> in <a href="#">OAuth grant type parameters</a> on page 1164.</p>   |

| Parameter                          | Description  |
|------------------------------------|--|
| <code>code_challenge_method</code> | <p>Applicable only when the <code>response_type</code> parameter value is <code>code</code> and a <code>code_challenge</code> parameter value is provided.</p> <p>This parameter indicates the transformation method used to derive the <code>code_challenge</code> parameter value from that of the <code>code_verifier</code> parameter. PingFederate OAuth AS supports two transformation methods:</p> <ul style="list-style-type: none"> <li>▪ <code>plain</code>, which indicates the <code>code_challenge</code> parameter value is that of the <code>code_verifier</code> parameter.</li> <li>▪ <code>S256</code>, which indicates the <code>code_challenge</code> parameter is derived from the <code>code_verifier</code> parameter value as follows</li> </ul> <p><code>code_challenge=Base64Url-encode(SHA256(ASCII(<code>code_verifier</code>)))</code>, where:</p> <ul style="list-style-type: none"> <li>▪ <code>ASCII(<code>code_verifier</code>)</code> denotes the octets of the ASCII representation of the <code>code_verifier</code> value.</li> <li>▪ <code>SHA256(octets)</code> denotes the SHA 256-bit hash of the octets.</li> <li>▪ <code>Base64Url-encode(octets)</code> denotes the base64url encoding of octets; the output is URL-safe.</li> </ul> <div data-bbox="574 810 1466 982" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>For detailed information about the transformation method, see <a href="#">Proof Key for Code Exchange (PKCE) by OAuth Public Clients</a>.</p> </div> <p>The <code>code_challenge_method</code> parameter value is case-sensitive. An error message is returned to the clients for any other values.</p> <p>Omitting the <code>code_challenge_method</code> parameter has the same effect as providing the <code>code_challenge_method</code> parameter with a value of <code>plain</code>.</p> |
| <code>redirect_uri</code>          | <p>The URI to which PingFederate redirects the resource owner's user-agent after an authorization is obtained.</p> <p>For OpenID Connect protocol compliance, clients that use the authorization code or implicit grant type must include this parameter in their authorization requests. It is also the default behavior in new PingFederate installations starting with version 9.1.4.</p> <p>For upgraded installations, this requirement remains true for clients that have been configured with more than one redirection URIs. For clients that have been configured with only one redirection URI, this requirement is waived to minimize the impact that it might impose on customers upgrading to version 9.1.4 or a subsequent release. As needed, it can be enabled at a later time.</p> <div data-bbox="524 1566 1466 1770" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If this parameter is used, the same parameter and value must also be used in subsequent token requests. For more information, see <a href="#">OAuth grant type parameters</a> on page 1164.</p> </div>  |

| Parameter                   | Description   |
|-----------------------------|---|
| <code>claims_locales</code> | <p>Specifies the end-user's preferred languages for claims being returned in a space-separated list, ordered by preference. The values must conform to the <a href="#">IETF BCP 47</a> guidelines.</p> <div data-bbox="521 317 1466 621" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>You can map the <code>claims_locales</code> value into the persistent grants (and therefore the access tokens, the ID tokens, or both) from an IdP adapter or an IdP connection by selecting <b>Context</b> under <b>Source</b> and <b>Requested Claims Locales</b> under <b>Value</b> in the <b>Contract Fulfillment</b> tab in the <b>IdP Adapter Mapping</b> configuration or the <b>OAuth Attribute Mapping</b> configuration in an IdP connection.</p> </div> |
| <code>login_hint</code>     | <p>Provides a hint to the PingFederate AS about the end user. For example, when an OAuth client includes a <code>login_hint</code> in its authorization request and the authentication source is an HTML Form Adapter instance, the username field in the login form is pre-populated with the <code>login_hint</code> parameter value.</p>   |
| <code>max_age</code>        | <p>Sets an allowable elapsed time in seconds since the end user last authenticated. If the elapsed time exceeds the value of <code>max_age</code>, PingFederate prompts the end user for authentication.</p> <div data-bbox="521 898 1466 1071" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>The HTML Form Adapter supports the <code>max_age</code> parameter by tracking the authentication time for each user.</p> </div>   |

| Parameter            | Description   |
|----------------------|---|
| <code>request</code> | <p>A single, self-contained parameter; a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>The <code>request</code> parameter is required if a client is configured to transmit request parameters in signed request objects. When PingFederate receives an authorization request, it verifies the digital signature of the signed request object based on the key obtained from the pre-configured JWKS URL or JWKS, and the selected request object signing algorithms. If the signature does not pass the verification process, the request fails.</p> <p>The <code>request</code> parameter is optional if a client is not configured to transmit request parameters in signed request objects but is configured with a JWKS URL or an actual JWKS. This flexibility allows the client to transmit request parameters in signed request objects for some requests and without the use of signed request objects for some other transactions. When PingFederate receives an authorization request with a signed request object, it verifies the digital signature of the signed request object based on the key obtained from the pre-configured JWKS URL or JWKS, and the selected request object signing algorithms. If the signature does not pass the verification process, the request fails.</p> <p>If a client is not configured to transmit request parameters in signed request objects and is not configured with a JWKS URL or an actual JWKS, PingFederate ignores the <code>request</code> parameter. When PingFederate receives an authorization request with a signed request object, it processes the authorization request and disregards the signed request object. As needed, develop a custom IdP adapter using the PingFederate SDK to extract the <code>request</code> parameter and its value from the HTTP request for further processing.</p> <p>PingFederate can decrypt encrypted request objects, which are described in the <a href="#">OpenID Connect 1.0 specification</a>. Request objects with asymmetric encryption must be encrypted using the public keys that PingFederate exposes at <code>/pf/JWKS</code>. Request objects with symmetric encryption need a key derived from the client's configured client secret and the client secret must be stored in a reversible format with, for example, symmetric encrypted ID tokens or hash-based message authentication code (HMAC) ID tokens. You can configure PingFederate to accept only request objects that are encrypted by enabling the <code>front-channel-encryption-required</code> setting in <code>jwt-request-object-options.xml</code>.</p> |
|                      | <p> <b>Note:</b></p> <p>If a client includes in an authorization request a request parameter other than <code>client_id</code>, as a parameter outside of the signed request object and a claim inside of the signed request object, always uses the claim value found inside the signed request object to process the request further.</p> <p>For the <code>client_id</code> request parameter, the values outside of the signed request object must match the claim values inside of the signed request object. If the values do not match, returns an error message to the client.</p> <p>If a request parameter is found only outside of the signed request object, ignores the request parameter and returns no error message.</p>  |
|                      | <p> <b>Tip:</b></p> <p>Per OAuth and OpenID Connect specifications, a client must always include in an authorization request the <code>client_id</code> parameter outside of the signed request object.</p>  |

| Parameter  | Description   |
|--|---|
| <code>request_uri</code>                                 | <p>This parameter indicates that the client is using the <a href="#">pushed authorization requests</a> (PAR) protocol to initiate an authorization flow. The client previously pushed an authorization request payload to the PAR endpoint of the AS. The payload can contain any of the parameters that usually comprise an authorization request and any additional parameters needed for client authentication. After the AS validated the request and saved the payload, it sent the <code>request_uri</code> parameter to the client to serve as a reference to the payload.</p> <p>Now the client is using the <code>request_uri</code> parameter to request an authorization code or token. The AS uses the value of the <code>request_uri</code> to look up the request payload and continue the authorization flow as usual. The AS accepts a particular request URI only once. For more information about PAR, see <a href="#">Pushed authorization requests endpoint</a> on page 1191.</p> |
| <code>scope</code>                                       | Expresses the scope of the access request as a list of space-separated, case-sensitive strings. For detailed information about scopes, see <a href="#">Scopes and scope management</a> on page 531.   |
| <code>state</code>                                       | An opaque value used by the client to maintain state between the request and callback. If included, the AS returns this parameter and the given value when redirecting the user agent back to the client.   |
| <code>ui_locales</code>                                  | Specifies the end-user's preferred languages for OAuth user interactions in a space-separated list, ordered by preference. The values must conform to the <a href="#">IETF BCP 47</a> guidelines.   |
| <code>idp</code> or <code>PartnerIdpId</code>            | A PingFederate OAuth AS parameter indicating the entity ID or the connection ID of the IdP with whom to initiate Browser SSO for user authentication.   |
| <code>pfidpadapterid</code> or <code>IdpAdapterId</code> | A PingFederate OAuth AS parameter indicating the IdP adapter instance ID of the adapter to use for user authentication.   |
|  | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This parameter might be overridden by policy based on authentication policies. For example, an OAuth Scope Authentication Selector instance could enforce the use of a given adapter instance based on client-requested scopes.</p> </div>  |
| <code>PolicyAction</code><br>(optional)                  | The HTML Form Adapter immediately returns the value of this parameter in the <code>policy.action</code> attribute, allowing the policy to bypass the adapter in favor of an alternative authentication source, provided a rule matching the action is configured. When this parameter is set to <code>identity.registration</code> and the adapter is followed by a local identity profile, the user is directed to the registration page for the profile.  |

If more than one source of authentication is configured in the system and no `pfidpadapterid` or `idp` parameter is provided, PingFederate provides users with an intermediate page asking them to choose among the available sources of authentication. The authentication results in a set of user attributes that must be mapped into the `USER_KEY` attribute for persistent grant storage and the `USER_NAME` attribute that displays on the user authorization page.

#### OpenID Connect parameters


The following table describes OpenID Connect parameters for this endpoint.



| Parameter            | Description  |
|----------------------|--|
| <b>acr_values</b>    | Specifies the Authentication Context Class Reference (acr) values for the AS to use when processing an Authentication Request. Express the values as a space-separated string, and list them in order of preference.   |
| <b>id_token_hint</b> | Includes an ID token as a hint to the PingFederate AS about the end user. If the authenticated user does not match the information stored in the ID token, the PingFederate AS rejects the authorization request and returns an error message.   |
| <b>nonce</b>         | Specifies a string value used to associate a client session with an ID token and to reduce replay attacks. The value passes through unmodified from an authorization request to the ID token.  |
| <b>prompt</b>        | Specifies whether the AS prompts the end user for reauthentication and consent. Expressed as a list of space-separated, case-sensitive ASCII string values. If included, the client can use this parameter to verify that the end user is still present for the current session or to bring attention to the request.<br><br>PingFederate supports values of <code>none</code> , <code>login</code> , and <code>consent</code> . |

#### OAuth access token management parameters

supports multiple access token management (ATM) instances. Clients can specify an ATM instance by providing the ATM ID (**access\_token\_manager\_id**) or a resource URI (**aud**) in their requests to the OAuth AS.

| Parameter                      | Description  |
|--------------------------------|--|
| <b>access_token_manager_id</b> | The <b>access_token_manager_id</b> value is the instance ID of the desired ATM instance. When specified, uses the desired ATM instance for the request if it is eligible; otherwise it aborts the request.<br><br><div data-bbox="522 1136 1472 1310" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b><br/>When the <b>access_token_manager_id</b> parameter is specified, ignores the <b>aud</b> parameter.</p> </div> |
| <b>aud</b>                     | The <b>aud</b> is the resource URI the client wants to access. The provided value is matched against resource URIs configured in access token management instances. When a match is found, uses the corresponding access token management instance for the request if it is eligible; otherwise it aborts the request.   |

A match can be an exact match or a partial match where the provided URI has the same scheme and authority parts and a more specific path contained within the path of the pre-configured resource URI. takes an exact match over a partial match. If there are multiple partial matches, takes the partial match where the provided URI matches more specifically against the pre-configured resource URI.

#### Example

##### A partial match

A resource URI of `https://app.example.local` is a partial match for the following provided URIs:

- `https://app.example.local/file1.ext`
- `https://app.example.local/path/file2.ext`

- `https://app.example.local/path/more`

### Example

An exact match is a better match than a partial match

| Access Token Management instances | Resource URIs (configured)  |
|-----------------------------------|---|
| ATM1                              | <ul style="list-style-type: none"> <li><code>https://localhost:9031/app1</code></li> <li><code>https://localhost:9031/app2/data</code></li> <li><code>https://app.example.local</code></li> </ul> |
| ATM2                              | <ul style="list-style-type: none"> <li><code>https://localhost:9031/app1/data</code></li> <li><code>https://localhost:9031/app2/data/get</code></li> </ul>  |

`https://localhost:9031/app1` (a resource URI pre-configured for ATM1) is a partial match for `https://localhost:9031/app1/data` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app1/data` (a resource URI pre-configured for ATM2) is an exact match against the provided URI.

### Example

A more specific partial match is a better match

Both `https://localhost:9031/app2/data` (a resource URI for ATM1) and `https://localhost:9031/app2/data/get` (a resource URI for ATM2) are partial matches for `https://localhost:9031/app2/data/get/sample` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app2/data/get` matches more specifically against the provided URI.

## Client-initiated backchannel authentication endpoint

A CIBA-capable client uses this endpoint to initiate a backchannel, out-of-band flow to authenticate the resource owners and obtain their authorizations.

The [OpenID Connect Client Initiated Backchannel Authentication Flow](#) defines the client-initiated backchannel authentication (CIBA) endpoint.






### Note:

This endpoint accepts only the HTTP POST method.

Endpoint: `/as/bc-auth.ciba`

The following table describes parameters for this endpoint. The required **Content-Type** value is `application/x-www-form-urlencoded`.

| Parameter   | Description  |
|---|--|
| <code>client_id</code><br>(Required)  | <p>The client identifier.</p> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>When sending request parameters of an authentication request with a signed request object, the client must include the <code>client_id</code> parameter and its value inside and outside of the <code>request</code> parameter value. Both <code>client_id</code> parameter values must match.</p> </div>   |
| <code>scope</code><br>(Required)  | <p>The scope of the access request. Expressed as a list of space-separated, case-sensitive strings.</p> <p>Scope values are globally defined on the <b>System # OAuth Settings # Scope Management</b> window. You can constrain scopes on a client-to-client basis.</p> <p>This parameter must include the <code>openid</code> scope value.</p>  |
| <code>client_notification_token</code>  | <p>A bearer token provided by the client that PingFederate must include when sending a ping callback message to the client's notification endpoint. This usage must conform to the syntax for bearer credentials as defined in section 2.1 of <a href="#">RFC 6750</a>.</p> <p>If the client is configured to use the poll delivery method, this parameter is required.</p>  |
| <code>id_token_hint</code> ,<br><code>login_hint_token</code> , or<br><code>login_hint</code> | <p>Per the CIBA specification, the client must include one and only one hint for the OpenID Provider to identify the user. The valid hint parameters are <code>id_token_hint</code>, <code>login_hint</code>, and <code>login_hint_token</code>.</p> <p><b><code>id_token_hint</code></b></p> <p>Use this parameter to include an ID token as a hint for PingFederate to identify the user. This ID token must be unencrypted. It must be a signed ID token.</p> <p><b><code>login_hint_token</code></b></p> <p>Use this parameter to include a JSON web token (JWT) as a hint for PingFederate to identify the user. The attributes of this token can vary from one use case to another. For more information how PingFederate uses the login hint token, see <a href="#">Configuring identity hint contract</a> on page 639.</p> <p><b><code>login_hint</code></b></p> <p>Use this parameter to provide a hint to PingFederate to identify the user. The value can contain an email address, phone number, account number, subject identifier, username, or any attribute that both sides agreed upon.</p> |
| <code>user_code</code>  | <p>A secret code that is known only to the user and verifiable by PingFederate through the use of a Password Credential Validator instance. The purpose of this code is to authorize the transmission of an authentication request to the user's authentication device.</p> <p>If the client record is configured to support user code and associated with a user code-enabled CIBA request policy, this parameter is required.</p>  |

| Parameter                     | Description   |
|-------------------------------|---|
| <code>binding_message</code>  | <p>An alphanumeric message intended to be made available on both the authentication device and the consumption device. The user can tie them together and decide whether to grant the authorization.</p> <p>When provided, the length of the message must range from 1 - 20 characters.</p>   |
| <code>requested_expiry</code> | <p>The requested expiration time of the request in seconds since the generation of the authentication request acknowledgment.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>PingFederate honors the requested expiration time only if the value is shorter than that of the <b>Transaction Lifetime</b> field found in the associated CIBA request policy.</p> </div>   |
| <code>request</code>          | <p>A single, self-contained parameter; a signed JWT whose claims represent the request parameters of the authentication request. The OpenID Connect specification calls this JWT a request object. The requirement of this parameter and the processing rules vary depending on whether the client is configured with the <b>Require CIBA Signed Requests</b> option.</p> <p>If the client is configured to transmit request parameters to the backchannel authentication endpoint in signed request objects, this parameter is required. In other words, the <b>Require CIBA Signed Requests</b> check box is selected in the configuration of the client. When PingFederate receives an authentication request with a signed request object, it verifies the digital signature of the signed request object based on the key obtained from the pre-configured JWKS URL (or JWKS) and the selected CIBA request object signing algorithm (or algorithms). If the signature does not pass the verification process, the request fails.</p> <p>If a client is not configured to transmit request parameters to the backchannel authentication endpoint in signed request objects, but it is configured with a JWKS URL or an actual JWKS, this parameter is optional. This flexibility allows the client to transmit request parameters in signed request objects for some requests and without the use of signed request objects for some other transactions. When PingFederate receives an authentication request with a signed request object, it verifies the digital signature of the signed request object based on the key obtained from the pre-configured JWKS URL (or JWKS) and the selected CIBA request object signing algorithms. If the signature does not pass the verification process, the request fails.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>If the client is not configured to transmit request parameters to the backchannel authentication endpoint in signed request objects, and not configured with a JWKS URL or an actual JWKS, an authentication request with a signed request object will always fail.</p> </div> |

#### Sample authentication request

```
POST /as/bc-auth.ciba HTTP/1.1
Content-Type: application/x-www-form-urlencoded
Host: www.example.com
```

```
client_id=myCibaApp&scope=openid&login_hint=joe@example.com
```

### Sample authentication request acknowledgements

- 200 - Success

```
HTTP/1.1 200 OK
...
{
  "auth_req_id":
  "HQnCGseUzWNRZEv8n3E8wIip9L3iwBdJAAect04BqdpEsFBGqfxRvoa_Q",
  "interval": 3,
  "expires_in": 120
}
```

- 400 - Bad Request

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "CIBA authentication requests MUST contain
the openid scope value.",
  "error": "invalid_scope"
}
```

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "Authentication request parameters (such
as binding_message) MUST NOT be present outside of the JWT when a
signed authentication request is used.",
  "error": "invalid_request"
}
```

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "Exactly one (not more, not less) of
the hint parameters (i.e. 'login_hint_token', 'id_token_hint' or
'login_hint') must be provided.",
  "error": "invalid_request"
}
```

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "User could not be sufficiently identified
to initiate out-of-band auth",
  "error": "unknown_user_id"
}
```

```
HTTP/1.1 400 Bad Request
...
{ "error": "invalid_user_code" }
```

```
HTTP/1.1 400 Bad Request
...
```

```
{ "error": "missing_user_code" }
```

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "Client is not configured to support user
code but a user_code was sent in the request.",
  "error": "invalid_request"
}
```

```
HTTP/1.1 400 Bad Request
...
{
  "error_description": "Policy is set to require a token for the
user hint but login_hint was sent.",
  "error": "invalid_request"
}
```

- **401 - Unauthorized**

```
HTTP/1.1 401 Unauthorized
...
{
  "error_description": "Invalid client or client credentials.",
  "error": "invalid_client"
}
```



- **500 - Server Error**

```
HTTP/1.1 500 Server Error
...
{
  "error_description": "Client is configured to support user code
but server policy doesn't have a PCV configured to do the user code
checking",
  "error": "server_error"
}
```

For more information about error responses, see section [13. Authentication Error Response](#) in the specification.


### OAuth client identification and authentication

The authentication requirement of this endpoint depends on the client authentication method configured for the clients.

| Authentication method | Parameters  |
|-----------------------|---|
| Client secret         | <p>Clients can present their client identifier and client secret using the HTTP Basic authentication scheme, where the client identifier is the username, and the client secret is the password.</p> <p>Clients can provide credentials using the request parameters <code>client_id</code> and <code>client_secret</code>.</p> <div data-bbox="521 401 1472 606" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>This is a sensitive parameter. To avoid recording it in web server logs, only pass in this parameter with the HTTP POST method in the message body, or through the HTTP Basic authentication scheme.</p> </div>   |
| Client certificate    | <p>Clients must present their client certificate for mutual TLS authentication. The issuer and the subject distinguished name (DN) of the client certificate must match values configured for the clients.</p>  |
| Private key JWT       | <p>Clients must include request parameters <code>client_assertion_type</code> and <code>client_assertion</code> in the message body of their requests.</p> <p><b>client_assertion_type</b></p> <p>The value describes the format of the assertion as defined by the authorization server. For the <code>private_key_jwt</code> client authentication method, the value is <code>urn:ietf:params:oauth:client-assertion-type:jwt-bearer</code>.</p> <p><b>client_assertion</b></p> <p>The value is the authentication token.</p> <p><b>Example</b></p> <pre data-bbox="537 1171 1472 1402">... client_assertion_type= urn%3Aietf%3Aparams%3Aoauth% 3Aclient-assertion-type%3Ajwt-bearer&amp; client_assertion= eyJhbGciOiJSUzI1NiIs...LbSWi1YO-TILOd4L7ZCg&amp; ...</pre> <div data-bbox="521 1413 1472 1591" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>For readability, line breaks are inserted and the authentication token is truncated.</p> </div> |
| None                  | <p>For more information about the <code>private_key_jwt</code> client authentication method, see <a href="#">Client Authentication and Using Assertions for Client Authentication</a>.</p> <p>Clients must pass in the <code>client_id</code> parameter in a query string or the message body to identify themselves.</p>   |

## OAuth access token management parameters

supports multiple access token management (ATM) instances. Clients can specify an ATM instance by providing the ATM ID (`access_token_manager_id`) or a resource URI (`aud`) in their requests to the OAuth AS.

| Parameter                            | Description  |
|--------------------------------------|--|
| <code>access_token_manager_id</code> | <p>The <code>access_token_manager_id</code> value is the instance ID of the desired ATM instance. When specified, uses the desired ATM instance for the request if it is eligible; otherwise it aborts the request.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>When the <code>access_token_manager_id</code> parameter is specified, ignores the <code>aud</code> parameter.</p> </div> |
| <code>aud</code>                     | <p>The <code>aud</code> is the resource URI the client wants to access. The provided value is matched against resource URIs configured in access token management instances. When a match is found, uses the corresponding access token management instance for the request if it is eligible; otherwise it aborts the request.</p>  |

A match can be an exact match or a partial match where the provided URI has the same scheme and authority parts and a more specific path contained within the path of the pre-configured resource URI. takes an exact match over a partial match. If there are multiple partial matches, takes the partial match where the provided URI matches more specifically against the pre-configured resource URI.

### Example

#### A partial match

A resource URI of `https://app.example.local` is a partial match for the following provided URIs:

- `https://app.example.local/file1.ext`
- `https://app.example.local/path/file2.ext`
- `https://app.example.local/path/more`

### Example

An exact match is a better match than a partial match

| Access Token Management instances | Resource URIs (configured)   |
|-----------------------------------|--|
| ATM1                              | <p><code>https://localhost:9031/app1</code></p> <p><code>https://localhost:9031/app2/data</code></p> <p><code>https://app.example.local</code></p> |
| ATM2                              | <p><code>https://localhost:9031/app1/data</code></p> <p><code>https://localhost:9031/app2/data/get</code></p>                                      |

`https://localhost:9031/app1` (a resource URI pre-configured for ATM1) is a partial match for `https://localhost:9031/app1/data` (the provided URI). However, chooses ATM2 because `https://`



`localhost:9031/app1/data` (a resource URI pre-configured for ATM2) is an exact match against the provided URI.

### Example

A more specific partial match is a better match

Both `https://localhost:9031/app2/data` (a resource URI for ATM1) and `https://localhost:9031/app2/data/get` (a resource URI for ATM2) are partial matches for `https://localhost:9031/app2/data/get/sample` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app2/data/get` matches more specifically against the provided URI.

## Token endpoint

The client presents its authorization grant to the token endpoint to obtain an access token and a refresh token when needed.

[The OAuth 2.0 Authorization Framework](#) defines the token endpoint. Because the authorization endpoint directly issues an access token, every authorization grant uses this endpoint except the Implicit grant type.



### Note:

This endpoint accepts only the HTTP POST method.

Endpoint: `/as/token.oauth2`

Parameters vary depending on the grant type. For more information, see [OAuth grant type parameters](#) on page 1164. The required **Content-Type** value is `application/x-www-form-urlencoded`.

Like other OAuth 2.0 endpoints, the token endpoint is accessible at the base URL and any configured virtual host names.



If the **Token Endpoint Base URL** field is configured on the **Authorization Server Settings** window (**System # OAuth Settings # Authorization Server Settings**) the token endpoint is also accessible at that location.

For example, if the base URL is `https://www.example.com:9031` and the **Token Endpoint Base URL** value is `https://www.example.local:9031`, the token endpoints are accessible at the following locations:

- `https://www.example.com:9031/as/token.oauth2`
- `https://www.example.local:9031/as/token.oauth2`


### OAuth client identification and authentication

The authentication requirement of this endpoint depends on the client authentication method configured for the clients.

| Authentication method | Parameters  |
|-----------------------|---|
| Client secret         | <p>Clients can present their client identifier and client secret using the HTTP Basic authentication scheme, where the client identifier is the username, and the client secret is the password.</p> <p>Clients can provide credentials using the request parameters <code>client_id</code> and <code>client_secret</code>.</p> <div data-bbox="521 401 1472 611" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>This is a sensitive parameter. To avoid recording it in web server logs, only pass in this parameter with the HTTP POST method in the message body, or through the HTTP Basic authentication scheme.</p> </div>   |
| Client certificate    | <p>Clients must present their client certificate for mutual TLS authentication. The issuer and the subject distinguished name (DN) of the client certificate must match values configured for the clients.</p>  |
| Private key JWT       | <p>Clients must include request parameters <code>client_assertion_type</code> and <code>client_assertion</code> in the message body of their requests.</p> <p><b>client_assertion_type</b></p> <p>The value describes the format of the assertion as defined by the authorization server. For the <code>private_key_jwt</code> client authentication method, the value is <code>urn:ietf:params:oauth:client-assertion-type:jwt-bearer</code>.</p> <p><b>client_assertion</b></p> <p>The value is the authentication token.</p> <p><b>Example</b></p> <pre data-bbox="537 1171 1472 1402"> ... client_assertion_type= urn%3Aietf%3Aparams%3Aoauth% 3Aclient-assertion-type%3Ajwt-bearer&amp; client_assertion= eyJhbGciOiJSUzI1NiIs...LbSWi1YO-TILOd4L7ZCg&amp; ... </pre> <div data-bbox="521 1413 1472 1591" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>For readability, line breaks are inserted and the authentication token is truncated.</p> </div> |
| None                  | <p>For more information about the <code>private_key_jwt</code> client authentication method, see <a href="#">Client Authentication and Using Assertions for Client Authentication</a>.</p> <p>Clients must pass in the <code>client_id</code> parameter in a query string or the message body to identify themselves.</p>   |

## OAuth access token management parameters

supports multiple access token management (ATM) instances. Clients can specify an ATM instance by providing the ATM ID (`access_token_manager_id`) or a resource URI (`aud`) in their requests to the OAuth AS.

| Parameter                            | Description  |
|--------------------------------------|--|
| <code>access_token_manager_id</code> | <p>The <code>access_token_manager_id</code> value is the instance ID of the desired ATM instance. When specified, uses the desired ATM instance for the request if it is eligible; otherwise it aborts the request.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When the <code>access_token_manager_id</code> parameter is specified, ignores the <code>aud</code> parameter.</p> </div> |
| <code>aud</code>                     | <p>The <code>aud</code> is the resource URI the client wants to access. The provided value is matched against resource URIs configured in access token management instances. When a match is found, uses the corresponding access token management instance for the request if it is eligible; otherwise it aborts the request.</p>  |

A match can be an exact match or a partial match where the provided URI has the same scheme and authority parts and a more specific path contained within the path of the pre-configured resource URI. takes an exact match over a partial match. If there are multiple partial matches, takes the partial match where the provided URI matches more specifically against the pre-configured resource URI.

### Example

#### A partial match

A resource URI of `https://app.example.local` is a partial match for the following provided URIs:

- `https://app.example.local/file1.ext`
- `https://app.example.local/path/file2.ext`
- `https://app.example.local/path/more`

### Example

An exact match is a better match than a partial match

| Access Token Management instances | Resource URIs (configured)   |
|-----------------------------------|--|
| ATM1                              | <p><code>https://localhost:9031/app1</code></p> <p><code>https://localhost:9031/app2/data</code></p> <p><code>https://app.example.local</code></p> |
| ATM2                              | <p><code>https://localhost:9031/app1/data</code></p> <p><code>https://localhost:9031/app2/data/get</code></p>                                      |

`https://localhost:9031/app1` (a resource URI pre-configured for ATM1) is a partial match for `https://localhost:9031/app1/data` (the provided URI). However, chooses ATM2 because `https://`

`localhost:9031/app1/data` (a resource URI pre-configured for ATM2) is an exact match against the provided URI.

### Example


A more specific partial match is a better match

Both `https://localhost:9031/app2/data` (a resource URI for ATM1) and `https://localhost:9031/app2/data/get` (a resource URI for ATM2) are partial matches for `https://localhost:9031/app2/data/get/sample` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app2/data/get` matches more specifically against the provided URI.

### OAuth grant type parameters

The `/as/token.oauth2` endpoint accepts other parameters which vary by the grant type presented.

These parameters include OAuth-defined standard parameters and parameters proprietary to PingFederate. The following parameter indicates the grant type of the access token request.

| Parameter                       | Description   |
|---------------------------------|---|
| <b>grant_type</b><br>(Required) | <p>Indicates the type of grant being presented in exchange for an access token and possibly a refresh token. The value is an extensibility mechanism of the OAuth 2.0 specification. PingFederate supports these values:</p> <ul style="list-style-type: none"> <li>▪ <code>authorization_code</code></li> <li>▪ <code>refresh_token</code></li> <li>▪ <code>password</code></li> <li>▪ <code>client_credentials</code></li> <li>▪ <code>urn:openid:params:grant-type:ciba</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:device_code</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:jwt-bearer</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:saml2-bearer</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:token-exchange</code></li> <li>▪ <code>urn:pingidentity.com:oauth2:grant_type:validate_bearer</code></li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The following sections define further parameters associated with each grant type.</p> </div> |

### Authorization code grant type


These parameters apply when the `grant_type` parameter for `/as/token.oauth2` is set to `authorization_code`.

| Parameter                 | Description  |
|---------------------------|--|
| <b>code</b><br>(Required) | The authorization code received from the authorization server during the redirect interaction at the authorization endpoint when the <code>response_type</code> parameter is <code>code</code> . |

| Parameter                        | Description  |
|----------------------------------|--|
| <code>code_verifier</code>       | <p>Required if the authorization request was sent with a <code>code_challenge</code> parameter to reduce the risk of code interception attack.</p> <p>If a <code>code_challenge_method</code> parameter value is provided in the request for the authorization code, PingFederate OAuth Authorization Server (AS) validates the <code>code_verifier</code> parameter value against that of the <code>code_challenge</code> value. If the validation returns no errors, PingFederate OAuth AS returns an access token; otherwise it returns an error to the client.</p> <p>For more information about the <code>code_challenge</code> parameter, the <code>code_challenge_method</code> parameter, and the support for the <a href="#">Proof Key for Code Exchange (PKCE) by OAuth Public Clients</a> specification (tools.ietf.org/html/rfc7636), see <a href="#">Authorization endpoint</a> on page 1147.</p> |
| <code>redirect_uri</code>        | <p>This parameter is required if the <code>redirect_uri</code> parameter was included in the authorization request that resulted in the issuance of the code. For more information, see <a href="#">Authorization endpoint</a> on page 1147). The value here must match the authorization-request value, if applicable.</p> <p>The parameter is also required for clients with multiple redirection URIs or one redirection URI that uses wildcards.</p> <p>The parameter is optional for clients with only one specific redirection URI.</p>  |
| <code>scope</code><br>(Optional) | <p>The scope of the access request expressed as a list of space-delimited, case-sensitive strings. The requested scope must be equal to or less than the scope originally authorized. If omitted, the scope is treated as equal to the scope originally authorized.</p> <p>Scopes can also be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531.</p>  |


#### Refresh token grant type

These parameters apply when the `grant_type` parameter for `/as/token.oauth2` is set to `refresh_token`.

| Parameter                                | Description   |
|--|---|
| <code>refresh_token</code><br>(Required) | <p>The refresh token issued to the client during a previous access token request.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.</p> </div>   |
| <code>scope</code>                       | <p>The scope of the access request expressed as a list of space-delimited, case-sensitive strings. The requested scope must be equal to or less than the scope originally granted. If omitted, the scope is treated as equal to the original set.</p> <p>Scopes can also be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531.</p> |

#### Resource owner password credentials grant type

These parameters apply when the `grant_type` parameter for `/as/token.oauth2` is set to `password`.

| Parameter                     | Description   |
|-------------------------------|---|
| <b>username</b><br>(Required) | The username, encoded as UTF-8.   |
| <b>password</b><br>(Required) | The password, encoded as UTF-8.<br><br><div style="border: 1px solid #ccc; padding: 5px;">  <b>Important:</b><br/>           To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.         </div>   |
| <b>scope</b>                  | The scope of the access request expressed as a list of space-delimited, case-sensitive strings. Scopes can also be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531.  |
| <b>validator_id</b>           | A PingFederate OAuth AS parameter indicating the instance ID of the password credential validator to check the username and password, and the associated attribute mapping into the <b>USER_KEY</b> of the persistent grant.<br><br>If multiple validator instances are configured and mapped and no <b>validator_id</b> parameter is provided, each instance will be tried sequentially until one succeeds or they all fail. |

When a token request triggers an `invalid_grant` error because the corresponding LDAP Username Password Credential Validator instance returns an authentication error, PingFederate includes the relevant message in the error response. See the following example.

```
{
  "error": "invalid_grant",
  "error_description": "We didn't recognize the username or password you
  entered. Please try again."
}
```

The error description varies based on the error condition that the LDAP Username PCV detects. OAuth-client developers can create custom experiences based on the error messages.

 **Tip:**

These customizable messages are stored in the message file, `pingfederate-messages.properties`, located in the `<pf_install>/pingfederate/server/default/conf/language-packs` directory.

You can localize these messages by using the localization framework for an international audience. For more information, see [Localizing messages for end users](#) on page 889.

The `client_id` parameter is not required when the **Allow unidentified clients to make resource owner password credentials grants** check box is selected in the **System # OAuth Settings # Authorization Server Settings** window.

#### Client credentials grant type

The following parameters applies when the `grant_type` parameter for `/as/token.oauth2` is set to `client_credentials`.

| Parameter    | Description  |
|--------------|--|
| <b>scope</b> | The scope of the access request expressed as a list of space-delimited, case-sensitive strings. Scopes can also be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531. |

#### Client-initiated backchannel authentication (CIBA)

The following parameter applies when the **grant\_type** parameter for `/as/token.oauth2` is set to `urn:openid:params:grant-type:ciba`.

| Parameter          | Description   |
|--------------------|---|
| <b>auth_req_id</b> | The unique identifier to identify the authentication request. |

#### Sample request

```
POST /as/token.oauth2 HTTP/1.1
Content-Type: application/x-www-form-urlencoded
Host: www.example.com
...

grant_type=urn%3Aopenid%3Aparams%3Agrant-type
%3Aciba&client_id=myCibaApp&auth_req_id=yQn...1Vw
```

The **auth\_req\_id** parameter value in the sample is truncated for readability.

#### Device authorization grant type


The following parameter applies when the **grant\_type** parameter for `/as/token.oauth2` is set to `urn:iETF:params:oauth:grant-type:device_code`.

The [OAuth 2.0 Device Authorization Grant](#) specification defines the process that allows a user to grant authorization to a device using a browser on a second device, such as a smart phone or a computer. For more information, see [Device authorization grant](#) on page 57.

| Parameter                        | Description   |
|----------------------------------|---|
| <b>device_code</b><br>(Required) | The device code found in the device authorization response. |

#### JWT Bearer Token grant type

These parameters apply when the **grant\_type** parameter for `/as/token.oauth2` is set to `urn:iETF:params:oauth:grant-type:jwt-bearer`.


| Parameter                      | Description  |
|--------------------------------|--|
| <b>assertion</b><br>(Required) | A JSON Web Token (JWT), as defined in <a href="#">RFC7523, section 2.1</a> .<br><br><div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.</p> </div> |

| Parameter          | Description   |
|--------------------|---|
| <code>scope</code> | The scope of the access request expressed as a list of space-delimited, case-sensitive strings. Scopes can be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531. |

The `client_id` parameter is not required when the **Allow unidentified clients to request extension grants** check box is selected in the **System # OAuth Settings # Authorization Server Settings** window.

#### SAML 2.0 Bearer Assertion grant type

The following parameters apply when the `grant_type` parameter for `/as/token.oauth2` is set to `urn:ietf:params:oauth:grant-type:saml2-bearer`.

| Parameter                            | Description   |
|--------------------------------------|---|
| <code>assertion</code><br>(Required) | A single SAML 2.0 assertion, which must be encoded using base64url. For more information, see <a href="#">RFC4648, section 5</a> .  |
|                                      |  <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.                 |
| <code>scope</code>                   | The scope of the access request expressed as a list of space-delimited, case-sensitive strings. Scopes can be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531. |

#### Note:




The `client_id` parameter is not required when the **Allow unidentified clients to request extension grants** check box is selected in the **System # OAuth Settings # Authorization Server Settings** window.

#### token exchange grant type

The following parameters apply when the `grant_type` parameter for `/as/token.oauth2` is set to `urn:ietf:params:oauth:grant-type:token_exchange`.


| Parameter             | Description   |
|-----------------------|---|
| <code>resource</code> | An absolute URI that indicates the target service or resource where the client will use the requested security token. This information lets the authorization server apply the appropriate policy for the target.<br><br>For example, the authorization server can ensure that the token it issues has the type, content, and encryption that the target requires. If the issued token will be used at multiple targets, multiple <code>resource</code> parameters can be used.   |
| <code>audience</code> | The logical name of the target where the client will use the requested security token. This serves a purpose like the <code>resource</code> parameter. To interpret the audience, the value must be something that both the client and the authorization server understand. The value must be unique within the authorization server. If the issued token will be used at multiple targets, multiple <code>audience</code> parameters can be used. When indicating multiple targets, <code>audience</code> and <code>resource</code> parameters can be used together. |



| Parameter                               | Description   |
|---|---|
| <b>scope</b>                            | The scope of the access request expressed as a list of space-delimited, case-sensitive strings. Scopes can also be constrained on a client-to-client basis. For more information, see <a href="#">Scopes and scope management</a> on page 531.    |
| <b>requested_token_type</b>             | An identifier for the type of the requested security token. If the requested type is not specified, the authorization server can determine which type is required by the target that the <b>resource</b> or <b>audience</b> parameter identifies. |
| <b>subject_token</b><br>(Required)      | A security token that represents the identity of the party on behalf of whom the request is being made. Typically, the subject of this token will be the subject of the security token issued in response to the request.                         |
|   |  <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.                         |
| <b>subject_token_type</b><br>(Required) | An identifier for the type of security token in the <b>subject_token</b> parameter.   |
| <b>actor_token</b>                      | A security token that represents the identity of the acting party. Typically, this will be the party that is authorized to use the requested security token and act on behalf of the subject.   |
|   |  <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.                        |
| <b>actor_token_type</b>                 | An identifier for the type of security token in the <b>actor_token</b> parameter.   |
|   |  <b>Important:</b><br>This parameter is required when the <b>actor_token</b> parameter is present in the request but must not be included otherwise.           |

#### Access token validation grant type

The following parameter applies when the **grant\_type** parameter for `/as/token.oauth2` is set to `urn:pingidentity.com:oauth2:grant_type:validate_bearer`.

| Parameter                  | Description   |
|----------------------------|---|
| <b>token</b><br>(Required) | The bearer access token to be validated.  |
|                            |  <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method. |

This validation grant type is a custom PingFederate OAuth extension that enables a resource server (RS) to communicate with the OAuth AS while leveraging the established communication and encoding patterns

from OAuth 2.0. This grant type allows an RS to verify with the OAuth AS on the validity of a bearer access token that it has received from a client making a protected-resources call.



**Tip:**

An RS client can also use the standard-based Introspection Endpoint at `/as/introspect.oauth2` to validate an access token or a refresh token.

Client authentication is not required. In other words, when creating a client for the sole purpose of validating access tokens, the **Client Secret** field is optional. For this grant type, the RS acts in the role of a client for the request/response exchange with the OAuth AS to make the validation call.

The response is a standard OAuth access-token response from the token endpoint with some extensions and minor semantic differences in the treatment of some of the parameters. The returned token is in a JSON structure with name-to-value elements or name-to-array elements.

The token type is `urn:pingidentity.com:oauth2:validated_token`, a URN indicating the token represents the attributes associated with the validated access token passed on the request. A `client_id` element is returned indicating the client identifier of the client to whom the grant was made. A `scope` element is returned, if the scope is greater than the default implied scope, indicating the approved scope of the grant. If the issuing access token management (ATM) instance is configured to expand scope groups, the response includes the corresponding sub scopes instead of the scope groups. The `expires_in` element indicates for how many more seconds the token is valid; the value can increase on subsequent validation calls if a token lifetime extension policy is in place.

Sample response when scope group expansion is disabled (the default)

```
{
  "access_token": {
    "Username": "joe",
    "OrgName": "Ping Identity Corporation"
  },
  "scope": "openid AAAGroup",
  "token_type": "urn:pingidentity.com:oauth2:validated_token",
  "expires_in": 7121,
  "client_id": "ac_oic_client"
}
```

**AAAGroup** is a scope group.

Sample response when scope group expansion is enabled

```
{
  "access_token": {
    "Username": "joe",
    "OrgName": "Ping Identity Corporation"
  },
  "scope": "openid AAA1 AAA2",
  "token_type": "urn:pingidentity.com:oauth2:validated_token",
  "expires_in": 7169,
  "client_id": "ac_oic_client"
}
```

**AAA1** and **AAA2** are the expanded outcome of **AAAGroup**.

Validate against all eligible ATM instances

If multiple ATM instances are eligible, the configuration of the RS client determines whether it must specify the desired ATM instance in its token validation requests. For more information, see .

After an ATM instance is chosen, considers the per-instance session validation settings and processes the validation request. For more information, see [Managing session validation settings](#) on page 612.

## Introspection endpoint

A resource server (RS) client uses the introspection endpoint to validate an access token or a refresh token prior to granting access to a protected-resources call.

The [OAuth 2.0 Token Introspection](#) documentation defines the introspection endpoint.



### Note:

This endpoint accepts only the HTTP POST method.

Endpoint: `/as/introspect.oauth2`

When transmitting through the HTTP POST method, the required **Content-Type** value is `application/x-www-form-urlencoded`. The RS acts in the role of a client for the request/response exchange with the PingFederate OAuth AS. The validation call is made using the following parameters.

| Parameter                  | Description   |
|----------------------------|---|
| <b>token</b><br>(Required) | The bearer access token or refresh token to be validated.<br><br><div data-bbox="527 913 576 955" data-label="Image"></div> <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method. |
| <b>token_type_hint</b>     | A hint about the type of token submitted for validation. PingFederate supports values of <code>access_token</code> and <code>refresh_token</code> .<br><br>Required only when validating a refresh token.   |

Client authentication is not required; when creating a client for the sole purpose of validating access tokens and refresh tokens, the **Client Secret** field is optional.

The response is in a JSON structure with a list of name-to-value elements. If a token is valid, the OAuth AS returns to the client a JSON object with the following elements:

- An `"active": true` element to indicate the token is valid. This is also the only element returned by the OAuth AS for a valid refresh token.
- A `client_id` element to indicate the client identifier of the client to whom the grant was made.
- A `scope` element, if the scope is greater than the default implied scope, indicating the approved scope of the grant. If you configured the issuing access token management (ATM) instance to expand scope groups, the response includes the corresponding sub scopes instead of the scope groups.
- An `exp` element indicates the token is valid until the number of seconds since January 1, 1970 UTC (epoch time).
- Other elements from the access token.

- For token introspection requests, if the `Accept HTTP` request header is present the value must be `application/token-introspection+jwt`

**Note:**

To receive the token introspection JSON response as a JSON Web Token (JWT), specify the `Accept HTTP` request header with the value `application/token-introspection+jwt`.

- For token introspection requests, if the `Content-Type` response header is present the value must be `application/token-introspection+jwt`

**Note:**

The response includes the `username` and subject (`sub`) elements only if they were mapped in the ATM instance.

A sample JSON response for a valid access token when a JWT header is present on token introspection requests

```
{
  "typ": "token-introspection+jwt",
  "alg": "RS256",
  "kid": "wG6D"
}
```

A sample JSON response for a valid access token. If the JWT `Accept` header is specified in the request, the JSON will be returned as a JSON web token (JWT).

```
{
  "iss": "https://as.example.com/",
  "aud": "https://rs.example.com/resource",
  "iat": 1514797892,
  "token_introspection": {
    "active": true,
    "iss": "https://as.example.com/",
    "aud": "https://rs.example.com/resource",
    "iat": 1514797822,
    "exp": 1514797942,
    "client_id": "paiB2goo0a",
    "scope": "read write dolphin",
    "sub": "Z5O3upPC88QrAjx00dis",
    "birthdate": "1982-02-01",
    "given_name": "John",
    "family_name": "Doe",
    "jti": "t1FoCCaZd4Xv4ORJUWVUeTZfsKhW30CQCrWDDjwXy6w"
  }
}
```

If a token is invalid, the OAuth AS returns `{"active": false}` to the client.

A sample response for a valid access token when scope group expansion is disabled (the default)

```
{
  "scope": "openid AAAGroup",
  "active": true,
  "OrgName": "Ping Identity Corporation",
  "token_type": "Bearer",
}
```

```
"exp": 1556823489,
"client_id": "ac_oic_client"
}
```

**AAAGroup** is a scope group.

A sample response for a valid access token when scope group expansion is enabled

```
{
  "scope": "openid AAA1 AAA2",
  "active": true,
  "OrgName": "Ping Identity Corporation",
  "token_type": "Bearer",
  "exp": 1556823764,
  "client_id": "ac_oic_client"
}
```

**AAA1** and **AAA2** are the expanded outcome of **AAAGroup**.

Response for a valid refresh token

```
{
  "active": true
  "exp": 1556823764
}
```

 **Note:**


If the refresh token is configured to never expire, the "exp" attribute will not be returned.


Response for an invalid token

```
{"active":false}
```

## OAuth client identification and authentication


The authentication requirement of this endpoint depends on the client authentication method configured for the clients.

| Authentication method | Parameters  |
|-----------------------|---|
| Client secret         | <p>Clients can present their client identifier and client secret using the HTTP Basic authentication scheme, where the client identifier is the username, and the client secret is the password.</p> <p>Clients can provide credentials using the request parameters <code>client_id</code> and <code>client_secret</code>.</p> <div data-bbox="532 1654 724 1701"> <p> <b>Important:</b></p> </div> <p>This is a sensitive parameter. To avoid recording it in web server logs, only pass in this parameter with the HTTP POST method in the message body, or through the HTTP Basic authentication scheme.</p> |

| Authentication method | Parameters   |
|-----------------------|--|
| Client certificate    | Clients must present their client certificate for mutual TLS authentication. The issuer and the subject distinguished name (DN) of the client certificate must match values configured for the clients.  |
| Private key JWT       | <p>Clients must include request parameters <code>client_assertion_type</code> and <code>client_assertion</code> in the message body of their requests.</p> <p><b>client_assertion_type</b></p> <p>The value describes the format of the assertion as defined by the authorization server. For the <code>private_key_jwt</code> client authentication method, the value is <code>urn:ietf:params:oauth:client-assertion-type:jwt-bearer</code>.</p> <p><b>client_assertion</b></p> <p>The value is the authentication token.</p> <p><b>Example</b></p> <pre>... client_assertion_type= urn%3Aietf%3Aparams%3Aoauth% 3Aclient-assertion-type%3Ajwt-bearer&amp; client_assertion= eyJhbGciOiJSUzI1NiIs...LbSWi1YO-TILOd4L7ZCg&amp; ...</pre> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>For readability, line breaks are inserted and the authentication token is truncated.</p> </div> <p>For more information about the <code>private_key_jwt</code> client authentication method, see <a href="#">Client Authentication and Using Assertions for Client Authentication</a>.</p> |
| None                  | Clients must pass in the <code>client_id</code> parameter in a query string or the message body to identify themselves.  |

#### OAuth access token management parameters

supports multiple access token management (ATM) instances. Clients can specify an ATM instance by providing the ATM ID (`access_token_manager_id`) or a resource URI (`aud`) in their requests to the OAuth AS.

| Parameter                            | Description  |
|--------------------------------------|--|
| <code>access_token_manager_id</code> | <p>The <code>access_token_manager_id</code> value is the instance ID of the desired ATM instance. When specified, uses the desired ATM instance for the request if it is eligible; otherwise it aborts the request.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When the <code>access_token_manager_id</code> parameter is specified, ignores the <code>aud</code> parameter.</p> </div> |

| Parameter  | Description  |
|------------|--|
| <b>aud</b> | The <b>aud</b> is the resource URI the client wants to access. The provided value is matched against resource URIs configured in access token management instances. When a match is found, uses the corresponding access token management instance for the request if it is eligible; otherwise it aborts the request. |

A match can be an exact match or a partial match where the provided URI has the same scheme and authority parts and a more specific path contained within the path of the pre-configured resource URI. takes an exact match over a partial match. If there are multiple partial matches, takes the partial match where the provided URI matches more specifically against the pre-configured resource URI.

#### Example

##### A partial match

A resource URI of `https://app.example.local` is a partial match for the following provided URIs:

- `https://app.example.local/file1.ext`
- `https://app.example.local/path/file2.ext`
- `https://app.example.local/path/more`

#### Example

An exact match is a better match than a partial match

| Access Token Management instances | Resource URIs (configured)  |
|-----------------------------------|---|
| ATM1                              | <code>https://localhost:9031/app1</code><br><code>https://localhost:9031/app2/data</code><br><code>https://app.example.local</code> |
| ATM2                              | <code>https://localhost:9031/app1/data</code><br><code>https://localhost:9031/app2/data/get</code>                                  |

`https://localhost:9031/app1` (a resource URI pre-configured for ATM1) is a partial match for `https://localhost:9031/app1/data` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app1/data` (a resource URI pre-configured for ATM2) is an exact match against the provided URI.

#### Example

A more specific partial match is a better match

Both `https://localhost:9031/app2/data` (a resource URI for ATM1) and `https://localhost:9031/app2/data/get` (a resource URI for ATM2) are partial matches for `https://localhost:9031/app2/data/get/sample` (the provided URI). However, chooses ATM2 because `https://localhost:9031/app2/data/get` matches more specifically against the provided URI.

Validate against all eligible ATM instances

If multiple ATM instances are eligible, the configuration of the RS client determines whether it must specify the desired ATM instance in its token validation requests. For more information, see .

After an ATM instance is chosen, considers the per-instance session validation settings and processes the validation request. For more information, see [Managing session validation settings](#) on page 612.

## Token revocation endpoint

The token revocation endpoint allows clients to notify the authorization server that a previously obtained refresh or access token is no longer needed. The revocation request invalidates the actual token and possibly other tokens based on the same authorization grant.

The [OAuth 2.0 Token Revocation](#) documentation defines the token revocation endpoint.



### Note:

This endpoint accepts only the HTTP POST method.

Endpoint: /as/revoke\_token.oauth2



### Important:

By default, Internally Managed Reference Tokens support direct access token revocation. JSON web token (JWT) access tokens can only be indirectly revoked if the associated refresh token is revoked, and the JWT's configuration field **Access Grant GUID Claim Name** is set for the given access token manager instance.

However, you can optionally enable direct revocation for self-contained JWT access tokens assigned to them by enabling JWT access token revocation in access token managers. When enabled, the JWTs require a **Client ID Claim Name** and a minimum **JWT ID Claim Length** of 22 alphanumeric characters. For more information, see [Configuring JSON token management](#) on page 606 and its description of the **Enable Token Revocation** check box.

When the authorization server revokes a refresh token, it also revokes the associated access grant and access tokens. When the authorization server revokes an access token, the associated access grant and refresh token remain untouched with the exception of the implicit grant type. If the **Reuse Existing Persistent Access Grants for GrantTypes** check box is selected in the **System # OAuth Settings # Authorization Server Settings** window, the implicit access grant will also be revoked with the access token.

The following table describes parameters for this endpoint. The required **Content-Type** value is `application/x-www-form-urlencoded` when transmitting through the HTTP POST method.



| Parameter                  | Description  |
|----------------------------|--|
| <b>token</b><br>(Required) | The token that the client wants to revoke.<br><br><div data-bbox="527 1564 574 1610" data-label="Image"></div> <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method. |

The following table describes parameters for this endpoint. The required **Content-Type** value is `application/x-www-form-urlencoded`.



## OAuth client identification and authentication

The authentication requirement of this endpoint depends on the client authentication method configured for the clients.

| Authentication method | Parameters   |
|-----------------------|--|
| Client secret         | <p>Clients can present their client identifier and client secret using the HTTP Basic authentication scheme, where the client identifier is the username, and the client secret is the password.</p> <p>Clients can provide credentials using the request parameters <code>client_id</code> and <code>client_secret</code>.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Important:</b></p> <p>This is a sensitive parameter. To avoid recording it in web server logs, only pass in this parameter with the HTTP POST method in the message body, or through the HTTP Basic authentication scheme.</p> </div>   |
| Client certificate    | <p>Clients must present their client certificate for mutual TLS authentication. The issuer and the subject distinguished name (DN) of the client certificate must match values configured for the clients.</p>   |
| Private key JWT       | <p>Clients must include request parameters <code>client_assertion_type</code> and <code>client_assertion</code> in the message body of their requests.</p> <p><b>client_assertion_type</b></p> <p>The value describes the format of the assertion as defined by the authorization server. For the <code>private_key_jwt</code> client authentication method, the value is <code>urn:ietf:params:oauth:client-assertion-type:jwt-bearer</code>.</p> <p><b>client_assertion</b></p> <p>The value is the authentication token.</p> <p><b>Example</b></p> <pre>... client_assertion_type= urn%3Aietf%3Aparams%3Aoauth% 3Aclient-assertion-type%3Ajwt-bearer&amp; client_assertion= eyJhbGciOiJSUzI1NiIs...LbSWi1YO-TILOd4L7ZCg&amp; ...</pre> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>For readability, line breaks are inserted and the authentication token is truncated.</p> </div> <p>For more information about the <code>private_key_jwt</code> client authentication method, see <a href="#">Client Authentication and Using Assertions for Client Authentication</a>.</p> |
| None                  | <p>Clients must pass in the <code>client_id</code> parameter in a query string or the message body to identify themselves.</p>   |

## Grant-management endpoint


Resource owners use the grant-management endpoint to view, and optionally revoke, the persistent access grants they have made.

Two grant-management endpoints are provided. One is for use with parameters. This endpoint is not part of the OAuth specification, but many OAuth providers offer a similar function.

Grants associated with the **USER\_KEY** of the authenticated user are displayed. The same attribute mappings from the authentication source to **USER\_KEY**, which are used for the authorization endpoint, are used here to look up the user's existing grants.

Endpoints: `/as/grants.oauth2` and `/as/oauth_access_grants.ping`

The following table describes the available parameters for the `/as/grants.oauth2` endpoint. Use only one of them as needed.

| Parameter                                     | Description  |
|---|--|
| <code>idp</code> or <code>PartnerIdpId</code> | Indicates the entity ID of the connection ID of the identity provider (IdP) with whom to initiate browser single sign-on (SSO) for user authentication.  |
| <code>pfidpadapterid</code>                   | Indicates the IdP adapter instance ID of the adapter to use for user authentication.   |
|   | <div style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>This parameter may be overridden by policy based on authentication selection configuration. For example, the OAuth Scope Authentication Selector could enforce the use of a given adapter based on client-requested scopes.</p> </div> |

If no recent user attributes are found for the session context, the user is redirected to `/as/oauth_access_grants.ping` to initiate the authentication process, which behaves in the same way as the authorization endpoint.

## Dynamic client registration endpoint

The client registration endpoint allows developers to dynamically register OAuth clients on a PingFederate authorization server.

The [OAuth 2.0 Dynamic Client Registration Protocol](#) defines this endpoint. Developers can send client registrations with the desired properties, such as client metadata, to this endpoint. If the requests are valid, PingFederate evaluates them and returns a response with a client ID and the registered client metadata values.

 **Note:**

This runtime endpoint is only active when the dynamic registration client is enabled and configured.

 **Important:**

As dynamic client registration can expose your server to unwanted client registrations, we recommend protecting by requiring an initial access token, configuring one or more client registration policies, and protecting access to the dynamic client registration endpoint.

You can configure access token requirement and client registration policies using the **System # OAuth Settings # Client Settings** window. To further protect against unauthorized access to the dynamic client

registration endpoint, consider using PingAccess or your choice of web access management solution to do so.



**Note:**

This endpoint accepts only the HTTP POST method.

Endpoint: /as/clients.oauth2

Both the request and the response follow the [OAuth 2.0 Dynamic Client Registration Protocol](#).

Example

Example 1

A developer wants to register a client that supports the authorization code flow, two redirection URIs, two scopes, and HTTP Basic as the client authentication method. In this example, PingFederate is not configured to require an initial access token.

Request

```
POST /as/clients.oauth2 HTTP/1.1
Content-Type: application/json
Accept: application/json
Host: sso.example.com

{
  "client_name": "Example Org Sample One",
  "redirect_uris": [
    "https://example.org/app1",
    "https://example.org/appM"
  ],
  "scope": "email phone",
  "grant_types": [
    "authorization_code"
  ]
}
```

Response

```
HTTP/1.1 201 Created
Date: Fri, 13 Oct 2017 12:34:56 GMT
Referrer-Policy: origin
Content-Type: application/json
Transfer-Encoding: chunked

{
  "client_id": "dc-F3JxcBlNctjk36J3Yi4yQK",
  "client_name": "Example Org Sample One",
  "redirect_uris": [
    "https://example.org/app1",
    "https://example.org/appM"
  ],
  "token_endpoint_auth_method": "client_secret_basic",
  "grant_types": [
    "authorization_code"
  ]
}
```

```

"client_secret": "fYhGUjnkjGp0UPQGaAfdcs",
"client_secret_expires_at": 0,
"scope": "phone email",
"validate_using_all_eligible_atms": false,
"refresh_token_rolling_policy": "server_default",
"persistent_grant_expiration_type": "server_default",
"grant_access_session_revocation_api": false
"grant_access_session_management_api": false
}

```

PingFederate returns 201 Created, the client ID, and other registered client metadata after creating the new client.

Additionally, when a registration request does not specify a client authentication method (`token_endpoint_auth_method`), PingFederate defaults to `client_secret_basic` per [OAuth 2.0 Dynamic Client Registration Protocol](#).

### Example

#### Example 2

A developer wants to register a client that supports the authorization code flow, refresh tokens, one redirection URI, one `profile` scope, and HTTP Basic as the client authentication method. In this example, PingFederate is not configured to require an initial access token. However, the `profile` scope is restricted. As a result, the registration request should fail.

#### Request

```

POST /as/clients.oauth2 HTTP/1.1
Content-Type: application/json
Accept: application/json
Host: www.example.com

{
  "client_name": "Example Org Sample Two",
  "redirect_uris": [
    "https://example.org/app2"
  ],
  "scope": "profile",
  "grant_types": [
    "authorization_code",
    "refresh_token"
  ]
}

```

#### Response

```

HTTP/1.1 400 Bad Request
Date: Fri, 13 Oct 2017 13:00:00 GMT
Referrer-Policy: origin
Content-Type: application/json
Transfer-Encoding: chunked
{
  "error": "invalid_client_metadata",
  "error_description": "The requested scope is invalid."
}

```

PingFederate returns 400 Bad Request and the relevant error message when a client registration fails.

## Example

### Example 3

A developer wants to register a client that supports the authorization code flow, two redirection URIs, two scopes, and HTTP Basic as the client authentication method. In this example, PingFederate is configured to require an initial access token.

#### Request

```
POST /as/clients.oauth2 HTTP/1.1
Content-Type: application/json
Accept: application/json
Authorization: Bearer
  eyJhbGciOiJSUzI1NiIsImtpZCI6ImxIn0.eyJzY29wZSI6WyJkQ1IiXSwiY2xpZW50X2lkX25hbWUiOi
  CHtcQ79Wefz2Sw5GOB5LfV9mWJ0n3vzJ93Ie7wbEAKalIFg53J-9e7s59MjA1igx6ybf1GMQ9QAjYobs-
  jM24arJZZgopEXvcx6IQpyU8U4AMTJ7tr9Lmody8P0QZOKcUDBTT5egv9vr5NuXcTUBfVPhGZ-3p5g5mwrn
  oDhmilbmiga4319YSFfx5-
  U3li9XPen3JZB2ukLbTFjjVIVLJIInbSR_IFTWP5Irg92aXlrIfm5MvBp8D1fOU6xYjbgjvw9QKNiFFVD7o
Host: www.example.com

{
  "client_name": "Example Org Sample Three",
  "redirect_uris": [
    "https://example.org/app3",
    "https://example.org/appN"
  ],
  "scope": "email phone",
  "grant_types": [
    "authorization_code"
  ]
}
```

#### Response

```
HTTP/1.1 201 Created
Date: Fri, 13 Oct 2017 15:30:00 GMT
Referrer-Policy: origin
Content-Type: application/json
Transfer-Encoding: chunked

{
  "client_id": "dc-rqUtii4vRXj5NMztkAeJ1S",
  "client_name": "Example Org Sample Three",
  "redirect_uris": [
    "https://example.org/app3",
    "https://example.org/appN"
  ],
  "token_endpoint_auth_method": "client_secret_basic",
  "grant_types": [
    "authorization_code"
  ],
  "client_secret": "p7MD0U11DNI9xRDc5kcOxs",
  "client_secret_expires_at": 0,
  "scope": "phone email",
  "validate_using_all_eligible_atms": false,
  "refresh_token_rolling_policy": "server_default",
  "persistent_grant_expiration_type": "server_default",
  "grant_access_session_revocation_api": false
  "grant_access_session_management_api": false
}
```

```
}

```

The registration request must include an **Authorization** HTTP header with a valid access token as its value.

If the authorization fails, PingFederate returns the following JSON payload in the response.

```
{
  "error": "invalid_access_token",
  "error_description": "Please provide a valid Access Token with the correct
scope"
}
```

## Device authorization endpoint

The device authorization endpoint allows a user to grant authorization to a device client using a browser on a second device, such as a smart phone or a computer.

The [OAuth 2.0 Device Authorization Grant](#) defines the device authorization endpoint. Based on the specification, the device sends a device authorization request to PingFederate, the authorization server (AS), at its device authorization endpoint.



### Note:

Per OAuth specifications, this endpoint accepts only the HTTP POST method.

Endpoint: `/as/device_authz.oauth2`

The required **Content-Type** value is `application/x-www-form-urlencoded`. The following table describes parameters for this endpoint.

| Parameter                        | Description  |
|----------------------------------|--|
| <code>client_id</code>           | A unique identifier the client provides to the resource server (RS) to identify itself. This identifier is included with every request the client makes  |
| <code>scope</code><br>(Optional) | The scope of the access request expressed as a list of space-delimited, case-sensitive strings.<br><br>Scopes can also be constrained on a client-to-client basis. For more information about scopes, see <a href="#">Scopes and scope management</a> on page 531. |

Both the request and the response follow the [OAuth 2.0 Device Authorization Grant](#).

### Example

#### Example request

```
POST /as/device_authz.oauth2 HTTP/1.1
Content-Type: application/x-www-form-urlencoded
Host: www.example.com
...
client_id=df_client
```

## Example

### Response codes and example responses

#### 200 - Success

```
HTTP/1.1 200 OK

...
{
  "user_code": "YYD6-CD4T",
  "device_code": "4EHsIngavzIPvvqMlFgQlseTCsH7EpU75f9yGvj60T",
  "interval": 5,
  "verification_uri_complete": "https://www.example.com/as/
user_authz.oauth2?user_code=YYD6-CD4T",
  "verification_uri": "https://www.example.com/as/user_authz.oauth2",
  "expires_in": 600
}
```

#### 400 - Bad Request

```
HTTP/1.1 400 Bad Request

...
{
  "error_description": "The requested scope(s) must be blank or a subset
of the provided scopes.",
  "error": "invalid_scope"
}
```



#### 401 - Unauthorized

```
HTTP/1.1 401 Unauthorized

...
{
  "error_description": "Invalid client or client credentials.",
  "error": "invalid_client"
}
```

### OAuth client identification and authentication

The authentication requirement of this endpoint depends on the client authentication method configured for the clients.

| Authentication method | Parameters  |
|-----------------------|---|
| Client secret         | <p>Clients can present their client identifier and client secret using the HTTP Basic authentication scheme, where the client identifier is the username, and the client secret is the password.</p> <p>Clients can provide credentials using the request parameters <code>client_id</code> and <code>client_secret</code>.</p> <div data-bbox="521 401 1472 606" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>This is a sensitive parameter. To avoid recording it in web server logs, only pass in this parameter with the HTTP POST method in the message body, or through the HTTP Basic authentication scheme.</p> </div>   |
| Client certificate    | <p>Clients must present their client certificate for mutual TLS authentication. The issuer and the subject distinguished name (DN) of the client certificate must match values configured for the clients.</p>  |
| Private key JWT       | <p>Clients must include request parameters <code>client_assertion_type</code> and <code>client_assertion</code> in the message body of their requests.</p> <p><b>client_assertion_type</b></p> <p>The value describes the format of the assertion as defined by the authorization server. For the <code>private_key_jwt</code> client authentication method, the value is <code>urn:ietf:params:oauth:client-assertion-type:jwt-bearer</code>.</p> <p><b>client_assertion</b></p> <p>The value is the authentication token.</p> <p><b>Example</b></p> <pre data-bbox="537 1171 1472 1402"> ... client_assertion_type= urn%3Aietf%3Aparams%3Aoauth% 3Aclient-assertion-type%3Ajwt-bearer&amp; client_assertion= eyJhbGciOiJSUzI1NiIs...LbSWi1YO-TILOd4L7ZCg&amp; ... </pre> <div data-bbox="521 1413 1472 1591" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>For readability, line breaks are inserted and the authentication token is truncated.</p> </div> |
| None                  | <p>For more information about the <code>private_key_jwt</code> client authentication method, see <a href="#">Client Authentication and Using Assertions for Client Authentication</a>.</p> <p>Clients must pass in the <code>client_id</code> parameter in a query string or the message body to identify themselves.</p>   |



## User authorization endpoint

The user authorization endpoint allows a user to grant authorization to a device client using a browser on a second device, such as a smart phone or a computer.

Based on the [OAuth 2.0 Device Authorization Grant](#) specification, the user goes to the user authorization endpoint of the PingFederate authorization server (AS) to complete the authorization process.



### Note:

This endpoint accepts the HTTP GET and POST methods.

Endpoint: `/as/user_authz.oauth2`

The following table describes parameter for this endpoint. The required **Content-Type** value is `application/x-www-form-urlencoded` when transmitting through the HTTP POST method.

| Parameter                            | Description                                |
|--------------------------------------|--|
| <code>user_code</code><br>(Optional) | This value represents the activation code. |

Both the request and the response follow the [OAuth 2.0 Device Authorization Grant](#).

### Example

#### Example request

```
POST /as/user_authz.oauth2 HTTP/1.1
Content-Type: application/x-www-form-urlencoded
Host: www.example.com
...
user_code=QQWP-TJ6B
```

### Subsequent responses

#### Phase 1: Activation code verification

If the verification request does not include an activation code, PingFederate returns the **Connect a device (user code prompt)** page, prompting the user to enter the activation code shown by the device.

If the verification request includes an activation code, PingFederate returns the **Connect a device (pre-populated user code prompt)** page, prompting the user to confirm the activation code from the verification request matches the activation code shown by the device. PingFederate skips this step if the **Bypass Activation Code Confirmation** option is enabled globally or individually for that invoking client.

PingFederate validates the activation code, prompts the user to enter another activation code if it is invalid, or moves to the next phase.

#### Phase 2: Authentication

PingFederate prompts the user to fulfill the authentication requirements based on OAuth grant mapping configurations and authentication policies.

If the user fulfills the authentication requirements, PingFederate moves to the next phase; otherwise it returns an error message to the user.

### Phase 3: Authorization

PingFederate returns the **Request for Approval** page, prompting the user to approve or deny the requested scopes. PingFederate skips this step if the **Bypass Authorization Approval** option is enabled globally or individually for that invoking client and the user has granted authorization for the requested scopes previously.

PingFederate returns the **Connect a device (result)** page to the user. The message reflects the authorization status.

If the user approves the requested scopes, the next time the device sends a device access token request to PingFederate at its token endpoint, PingFederate returns an access token to the device.

When an error occurs, PingFederate returns 400 Bad Request in response to the device access token request.

### Example

#### Examples of 400 Bad Request

```
HTTP/1.1 400 Bad Request
...
{"error_description":"Authorization request is
denied", "error":"access_denied"}
```

```
HTTP/1.1 400 Bad Request
...
{"error_description":"Device code not found, expired or
invalid", "error":"invalid_grant"}
```

```
HTTP/1.1 400 Bad Request
...
{"error_description":"The authorization request has
expired.", "error":"expired_token"}
```

## OpenID Provider configuration endpoint

The OpenID Provider (OP) configuration endpoint provides configuration information for the OAuth clients to interface with PingFederate using the OpenID Connect protocol.

This endpoint returns configuration information that is controlled by a template file and can be customized to suit multiple use cases simultaneously.

This public endpoint accepts HTTP GET requests without authentication.

Endpoint: /.well-known/openid-configuration

The following table describes the parameter for this endpoint.

| Parameter              | Description  |
|------------------------|--|
| <code>policy_id</code> | Indicates the OpenID Connect policy from which PingFederate derives the attributes to include under <code>claims_supported</code> in the response body.<br>If omitted, PingFederate includes the attributes based on the default policy. |

## Example

### Example response

```
$ curl -s https://localhost:9031/.well-known/openid-configuration|python -m
json.tool
{
  "authorization_endpoint": "https://localhost:9031/as/
authorization.oauth2",
  "backchannel_authentication_endpoint": "https://localhost:9031/as/bc-
auth.ciba",
  "backchannel_authentication_request_signing_alg_values_supported": [
    "RS256",
    "RS384",
    "RS512",
    "ES256",
    "ES384",
    "ES512",
    "PS256",
    "PS384",
    "PS512"
  ],
  "backchannel_token_delivery_modes_supported": [
    "poll",
    "ping"
  ],
  "backchannel_user_code_parameter_supported": true,
  "code_challenge_methods_supported": [
    "plain",
    "S256"
  ],
  "claim_types_supported": [
    "normal"
  ],
  "claims_parameter_supported": false,
  "claims_supported": [
    "address",
    "birthdate",
    "email",
    "email_verified",
    "family_name",
    "gender",
    "given_name",
    "locale",
    "middle_name",
    "name",
    "nickname",
    "phone_number",
    "phone_number_verified",
    "picture",
    "preferred_username",
    "profile",
    "sub",
    "updated_at",
    "website",
    "zoneinfo"
  ],
  "device_authorization_endpoint": "https://localhost:9031/as/
device_authz.oauth2",
  "grant_types_supported": [
    "implicit",
    "authorization_code",
```

```

    "refresh_token",
    "password",
    "client_credentials",
    "urn:pingidentity.com:oauth2:grant_type:validate_bearer",
    "urn:ietf:params:oauth:grant-type:jwt-bearer",
    "urn:ietf:params:oauth:grant-type:saml2-bearer",
    "urn:ietf:params:oauth:grant-type:device_code",
    "urn:openid:params:grant-type:ciba"
  ],
  "id_token_encryption_alg_values_supported": [
    "dir",
    "A128KW",
    "A192KW",
    "A256KW",
    "A128GCMKW",
    "A192GCMKW",
    "A256GCMKW",
    "ECDH-ES",
    "ECDH-ES+A128KW",
    "ECDH-ES+A192KW",
    "ECDH-ES+A256KW",
    "RSA-OAEP"
  ],
  "id_token_encryption_enc_values_supported": [
    "A128CBC-HS256",
    "A192CBC-HS384",
    "A256CBC-HS512",
    "A128GCM",
    "A192GCM",
    "A256GCM"
  ],
  "id_token_signing_alg_values_supported": [
    "none",
    "HS256",
    "HS384",
    "HS512",
    "RS256",
    "RS384",
    "RS512",
    "ES256",
    "ES384",
    "ES512",
    "PS256",
    "PS384",
    "PS512"
  ],
  "introspection_endpoint": "https://localhost:9031/as/introspect.oauth2",
  "issuer": "https://localhost:9031",
  "jwks_uri": "https://localhost:9031/pf/JWKS",
  "ping_end_session_endpoint": "https://localhost:9031/idp/startSLO.ping",
  "ping_revoked_sris_endpoint": "https://localhost:9031/pf-ws/rest/
sessionMgmt/revokedSris",
  "registration_endpoint": "https://localhost:9031/as/clients.oauth2",
  "request_object_signing_alg_values_supported": [
    "RS256",
    "RS384",
    "RS512",
    "ES256",
    "ES384",
    "ES512",
    "PS256",
    "PS384",
    "PS512"
  ],
],

```

```

"request_parameter_supported": true,
"request_uri_parameter_supported": false,
"response_modes_supported": [
  "fragment",
  "query",
  "form_post"
],
"response_types_supported": [
  "code",
  "token",
  "id_token",
  "code token",
  "code id_token",
  "token id_token",
  "code token id_token"
],
"revocation_endpoint": "https://localhost:9031/as/revoke_token.oauth2",
"scopes_supported": [
  "address",
  "phone",
  "edit",
  "openid",
  "profile",
  "admin",
  "email"
],
"subject_types_supported": [
  "public",
  "pairwise"
],
"token_endpoint": "https://www.example.com:9031/as/token.oauth2",
"token_endpoint_auth_methods_supported": [
  "client_secret_basic",
  "client_secret_post",
  "private_key_jwt"
],
"token_endpoint_auth_signing_alg_values_supported": [
  "RS256",
  "RS384",
  "RS512",
  "ES256",
  "ES384",
  "ES512",
  "PS256",
  "PS384",
  "PS512"
],
"userinfo_endpoint": "https://localhost:9031/idp/userinfo.openid"
}

```

## Notable metadata parameters

### CIBA user code support

The **backchannel\_user\_code\_parameter\_supported** parameter indicates whether the default CIBA request policy supports user codes, which are an optional feature in the CIBA specification.

In the previous example, because the **User Code PCV** field is configured with a Password Credential Validator instance in the default CIBA request policy, the value of the **backchannel\_user\_code\_parameter\_supported** parameter is `true`. For more information,

see [OpenID Connect Client Initiated Backchannel Authentication Flow](#) and [Defining a request policy](#) on page 638.

### Digital signature algorithms

The `backchannel_authentication_request_signing_alg_values_supported`, `id_token_signing_alg_values_supported`, `token_endpoint_auth_signing_alg_values_supported`, and `request_object_signing_alg_values_supported` parameters provide lists of supported algorithms to process digital signatures.

In this example, because PingFederate is integrated with a hardware security module (HSM) and configured to use static keys for OAuth and OpenID Connect, the endpoint includes additional RSASSA-PSS digital signature algorithms (PS256, PS384, and PS512) in its response. For more information on HSM integration and static keys, see [Supported hardware security modules](#) on page 177 and [Keys for OAuth and OpenID Connect](#) on page 675, respectively. Deploying PingFederate to run on a Java 8 or a Java 11 environment will have the same result.

### JWKS endpoint

The JWKS endpoint, `jwtks_uri`, returns a set of public keys for OAuth and OpenID Connect. Clients can use this information to verify the integrity of asymmetrically-signed ID tokens, JSON web tokens (JWTs) for client authentication, and OpenID Connect request objects.

### Scopes

The OP configuration endpoint returns all common static scopes and common scope groups but not exclusive static scopes, exclusive scope groups, common dynamic scopes, or exclusive dynamic scopes by default. The response can be customized by editing a template file to include or exclude individual scopes and scope groups.

### Token endpoint

The token endpoint, `token_endpoint`, is used by clients to obtain access tokens and refresh tokens if applicable.

In the previous example, because the **Token Endpoint Base URL** is set to `https://www.example.com:9031` in the **System # OAuth Settings # Authorization Server Settings** window, the `token_endpoint` value is set to `https://www.example.com:9031/as/token.oauth2`. For more information, see [Configuring authorization server settings](#) on page 519 and [Token endpoint](#) on page 1161.

## Userinfo endpoint

OAuth clients can present access tokens to the Userinfo endpoint to retrieve additional information about the resource owners.

You can customize the amount of information presented by the endpoint by using OpenID Connect policies. Information can include specification-defined attributes (standard attributes) and non-standard attributes. Scopes, authorized by the users, also determine the attributes to be returned.

This endpoint accepts HTTP GET requests without parameters. Clients must present valid access tokens for authentication.

### Example

Endpoint example: `/idp/userinfo.openid`

```
$ curl -s https://localhost:9031/idp/userinfo.openid -H 'Authorization:
Bearer eyJ...9-g'|python -m json.tool
{
  "email": "auser@example.com",
  "phone_number": "(555) 555-5555",
```

```

    "phone_number_verified": true,
    "sub": "joe"
  }

```

**Note:**

The self-contained access token in the **Authorization** HTTP header is truncated for readability.

If the access token presented is not valid, PingFederate returns 401 Unauthorized.

### Self-contained tokens

If clients using self-contained access tokens are expected to contact the UserInfo endpoint, consider the following implications.

#### Client ID Claim Name

This field's default value is `client_id`. When this field is configured with a value, PingFederate includes the client ID of the requesting client as a claim in the self-contained tokens. The claim name is the value of the **Client ID Claim Name** field.

If the field value is empty, will not include the client ID of the requesting client in the self-contained tokens. In this scenario, the access token manager (ATM) instance used by the default OpenID Connect policy must remain accessible to all clients, or clients using self-contained access tokens issued by this ATM instance will not be able to retrieve additional claims from the UserInfo endpoint. Instead, they receive an HTTP status code 401 Unauthorized from PingFederate. For more information, see [Defining access control](#) on page 616.

#### Scope Claim Name

This field's default value is `scope`. When this field is configured with a value, PingFederate includes the requested scopes as a claim in the self-contained tokens. The claim name is the value of the **Scope Claim Name** field.

If the field value is empty, PingFederate will not include any scope information in the self-contained token, and clients using self-contained access tokens issued by this ATM instance will not be able to retrieve additional claims from the UserInfo endpoint. Instead, they receive an HTTP status code 403 Forbidden from PingFederate.

## Pushed authorization requests endpoint

The PingFederate authorization server (AS) can provide a pushed authorization requests (PAR) endpoint `/as/par.oauth2`. OAuth 2.0 clients can use the PAR endpoint to securely *initiate* authorization flows.

When the PAR endpoint is enabled, a client can push an authorization request payload to the AS with a direct back-channel request. This is a more secure method of sending sensitive data, such as personally identifiable information, than sending it with a browser on the front channel. The payload contains parameters that are application/x-www-form-urlencoded formatted. The PAR endpoint can accept all parameters that usually comprise an authorization request and any additional parameters needed for client authentication. It also can accept signed requests.

**Note:**

The PAR endpoint only accepts the HTTP POST method.

After the AS validates the request and saves the payload, it returns the `request_uri` parameter to serve as a reference to the payload. The response also indicates the lifetime of the request URI. The default lifetime is 60 seconds.

### Sample request for a request\_uri to the PAR endpoint

```
POST /as/par.oauth2 HTTP/1.1
Host: as.example.com
Content-Type: application/x-www-form-urlencoded
Authorization: Basic czZCaGRSa3F0Mzo3RmpmcDBaQnIxS3REUmJuZlZkbU13

response_type=code
&client_id=s6BhdRkqt3
&state=af0ifjsldkj
&redirect_uri=https%3A%2F%2Fclient.example.org%2Fcb
```

### Sample response with a request\_uri from the PAR endpoint

```
HTTP/1.1 201 Created
Cache-Control: no-cache, no-store
Content-Type: application/json

{
  "expires_in": 60,
  "request_uri": "urn:example:bwc4JK-ESC0w8acc191e-Y1LTC2"
}
```

Subsequently, the client uses the front channel to request an authorization code or token, sending the **request\_uri** parameter to the AS authorization endpoint. The AS uses the request URI to look up the request payload and continue the authorization flow as usual. The AS accepts a particular request URI only once.

### Sample request for an authorization code or token to the authorization endpoint

```
GET /as/authorization.oauth2?client_id=s6BhdRkqt3
&request_uri=urn%3Aexample%3Abwc4JK-ESC0w8acc191e-Y1LTC2 HTTP/1.1
Host: as.example.com
```

To let OAuth clients use the PAR endpoint, you must enable PAR on the AS. Additionally, you can configure individual clients so that they must use the PAR endpoint to initiate authorization flows. For more information about PAR settings, see [Configuring authorization server settings](#) on page 519 and [Configuring OAuth clients](#) on page 566.

When PAR is enabled on the AS, the well-known endpoint `/.well-known/openid-configuration` includes these PAR parameters in responses:

- **pushed\_authorization\_request\_endpoint** contains the PAR endpoint
- **require\_pushed\_authorization\_requests** indicates whether the AS requires clients to use PAR

PingFederate can decrypt encrypted request objects, which are described in the [OpenID Connect 1.0 specification](#). Request objects with asymmetric encryption must be encrypted using the public keys that PingFederate exposes at `/pf/JWKS`. Request objects with symmetric encryption need a key derived from the client's configured client secret and the client secret must be stored in a reversible format with, for example, symmetric encrypted ID tokens or hash-based message authentication code (HMAC) ID tokens. You can configure PingFederate to accept only request objects that are encrypted by enabling the `front-channel-encryption-required` setting in `jwt-request-object-options.xml`.

For more information about the PAR protocol, see [OAuth 2.0 Pushed Authorization Requests](#) on the IETF website.



## OAuth Playground

Developers can install and use the PingFederate OAuth Playground to experiment with OAuth and OpenID Connect.

Before you begin

Before you can install the OAuth Playground, install the instance of PingFederate in which you will install the OAuth Playground.



### Note:

You should not install OAuth Playground in PingFederate production environments.

About this task

Acting as both a client and a resource server, the OAuth Playground simulates authorization requests, responses, and token validation. These features can help you integrate OAuth and OpenID Connect protocols into your applications.

To install the OAuth Playground, perform the following procedure. For more information, including the credentials needed for some OAuth grants, see the `ReadMeFirst` file in the OAuth Playground `.zip` file.

Steps

1. Get the OAuth Playground files:
  - a. In a browser, go to the [Developer Tools](#) page on the Ping Identity website.
  - b. Click the OAuth Playground **Download** button. If requested, log in to your Ping Identity account. Your browser downloads the OAuth Playground `.zip` file.
  - c. Extract the contents from the `.zip` file.
2. Install the OAuth Playground:
  - a. Copy the contents of the `/dist/deploy` directory to `/pingfederate/server/default/deploy` in PingFederate.
  - b. Merge the contents of the `/dist/conf` directory into `/pingfederate/server/default/conf` in PingFederate.
3. Configure the OAuth Playground:
  - a. Open the OAuth Playground by going to `https://<pf_host>:9031/OAuthPlayground` in a browser.
  - b. Click the **Setup** button. The Setup wizard appears.
  - c. Follow the wizard's instructions.



### Note:

The **Setup** button appears only the first time that you configure the OAuth Playground. To reconfigure the OAuth Playground, click **Settings** on the taskbar. On the **Settings** window, click the **Set Up Again** button. Then following the wizard's instructions.

## Web service interfaces and APIs

---

PingFederate provides two built-in, SOAP-accessible web services related to browser-based single sign-on (SSO).

These services can be used by client applications to manage partner connections and support integration of web applications, respectively.

Connection Management Service

 **Note:**

As of PingFederate 10.2, the Connection Management Service has been deprecated and will be removed in a future release.

The Connection Management Service enables creation and deletion of single connection configurations in PingFederate. This service can be used to migrate connections from one server environment to another, for example, from testing or staging to production, or to create new connections in a single server programmatically.

 **Tip:**

PingFederate provides a command-line utility that can be used to export and modify connections, as well as other administrative-console configurations, and then import them to target environments. For more information, see [Automating configuration migration](#) on page 861.

## SSO Directory Service

 **Note:**

As of PingFederate 10.2, the SSO Directory Service has been deprecated and will be removed in a future release.

The SSO Directory Service provides web application developers with information regarding partner connections and adapter instances.

 **Tip:**

Applications accessing the Connection Management Service must first authenticate themselves to the PingFederate server. SSO Directory Service authentication is optional by default, but might be required. For more information, see [Configuring service authentication](#) on page 698.

Additionally, PingFederate provides REST-based web services and APIs for a variety of administrative and runtime tasks.

## OAuth Client Management Service

A runtime API to manage OAuth client applications.

## OAuth Access Grant Management Service

A runtime API to retrieve and revoke persistent grants. This API is intended for administrators to manage grants per client or per user.

## OAuth Persistence Grant Management API

Another runtime API to retrieve and revoke persistent grants. This API is intended for the use case where clients can assume the responsibility of grant management, provided that the users authorize the clients to do so.

## Session Revocation API

A runtime API allowing clients supporting the OpenID Connect protocol to query revocation status of their sessions and add user sessions to the revocation list.

## Administrative API

An administrative API to manage various PingFederate settings.

## Connection Management Service

The Connection Management Service supports basic connection management capabilities and is accessible only on a PingFederate server running the administrative console.



### Note:

As of PingFederate 10.2, the Connection Management Service has been deprecated and will be removed in a future release.

The Connection Management Service is useful in a variety of circumstances. Consider the following use cases:

- Using the Connection Management Service as a utility, you can migrate changes to a partner connection through staging environments. For example, development, test, and production.
 

Using the Connection Management Service, you might need to make changes to URLs and keys to make the connection appropriate to the next environment.
- Using the Connection Management Service, an external application can update or delete connections programmatically, or create new ones using an exported connection XML file as a template.

You can find the WAR file for this service, `pf-mgmt-ws.war`, in the `<pf_install>/pingfederate/server/default/deploy2` directory.



### Note:

If you do not want to allow use of the service, do not deploy it: remove the WAR file from the `deploy2` directory.

The SOAP-accessible service endpoint is `pf-mgmt-ws/ws/ConnectionMigrationMgr`.

The web services Description Language (WSDL) document describing this service can be retrieved from `/pf-mgmt-ws/ws/ConnectionMigrationMgr?wsdl`.

### Exporting a connection

You can export a connection either manually, using the administrative console, or programmatically through a call to the Connection Management Service.

Whether you export a connection manually or programmatically, the exported XML complies with the standard SAML 2.0 metadata format, with extensions to capture PingFederate's proprietary configuration. Most connection configuration information is contained in the XML markup, with the exception of global configuration items such as adapter instances, datastores, and key pairs. Adapter instances and datastores are referenced by ID, and key pairs are referenced by the MD5 fingerprint of their X.509 certificate. Public certificates, such as the partner's signature verification certificate, are included completely (base-64 encoded).

#### Export manually

For information about using the administrative console to export connections, see [Accessing SP connections](#) on page 441 or [Accessing IdP connections](#) on page 725.

## Export via the Connection Management Service

The Connection Management Service exposes the following method for exporting connections.

```
public string getConnection( String entityId, String role,) throws
    IOException
```

The **entityId** parameter is the connection ID, which identifies the connection to be deleted. The **role** parameter is the connection role, the identity provider (IdP) or the service provider (SP).

### Code sample

The following example invokes this web service to export a connection.

```
Service service = new Service();
Call call = (Call)service.createCall();
call.setUsername("username");
call.setPassword("password");
call.setTargetEndpointAddress("https://localhost:9999/pf-mgmt-ws/ws/
ConnectionMigrationMgr");
call.setOperationName("getConnection");
Object result = call.invoke(new Object[] {"<entityId>", "SP"});
```

## Importing connections

Moving a connection from one PingFederate server to another requires care, as the target server must contain the global configuration items, such as datastores, key pairs, and adapter instances, that the connection references.

Changing the references in the XML file, either manually or programmatically, may be necessary to adjust the connection to the target PingFederate environment.

After the required changes are made to the XML file, developers can use the Connection Management Service to import the connection into a different instance of PingFederate.



### Tip:

Alternatively, you can import XML connection files through the PingFederate administrative console. For more information, see [Accessing SP connections](#) on page 441 or [Accessing IdP connections](#) on page 725. You can also import the connections into PingFederate manually by copying them into the `<pf_install>/pingfederate/server/default/ data/connection-deployer` directory.

PingFederate scans this directory periodically and imports connections automatically.



### CAUTION:

Manually importing a connection always overwrites an existing connection with the same ID. The web service provides a switch to disallow this behavior, if desired. For more information, see below.

The web service exposes the following method for importing connections.

```
public void saveConnection( String xml, boolean allowUpdate) throws
    IOException
```

The **xml** parameter is the complete representation of the connection retrieved by your application from an exported connection file, and optionally modified.

If **allowUpdate** is false, the web service can be used only to add a new connection. An error occurs if a connection already exists with the same connection ID and federation protocol in the XML. If **allowUpdate** is true and the connection already exists, it will be overwritten.

#### Sample code

The following example uses the Apache AXIS libraries to invoke this web service to create a new connection.

```
Service service = new Service();
    Call call = (Call) service.createCall();
    call.setUsername("username");
    call.setPassword("password");
    String addr = "https://localhost:9999/pf-mgmt-ws/ws/
ConnectionMigrationMgr";
    call.setTargetEndpointAddress(addr);
    call.setOperationName("saveConnection");
    String xml = "<EntityDescriptor entityID=\"some_entity_id\"
...
</EntityDescriptor>";
    boolean allowUpdate = false;
    call.invoke(new Object[]{xml, allowUpdate});
```

#### Deleting connections

You can invoke the web service to delete connections.

The web service exposes the following method for connection deletion.

```
public void deleteConnection( String entityId, String role) throws
    IOException
```

The **entityId** parameter is the connection ID, which identifies the connection to be deleted. The **role** parameter is the connection role, identity provider (IdP) or service provider (SP).

#### Code sample

The following example uses the Apache AXIS libraries to invoke this web service to delete a connection.

```
Service service = new Service();
Call call = (Call) service.createCall();
call.setUsername("username");
call.setPassword("password");
call.setTargetEndpointAddress(
    "https://localhost:9999/pf-mgmt-ws/ws/ConnectionMigrationMgr"
);
call.setOperationName("deleteConnection");
call.invoke(new Object[]{"entityid", "SP"});
```

#### Cluster configuration replication

A web service endpoint is available to replicate the administrative-console configuration to other nodes in a PingFederate cluster from the Connection Management Service.

The cluster configuration replication web service endpoint allows a client of this web service to create, update, or delete a connection, and then push the new configuration to the other cluster nodes.

The service endpoint is `/pf-mgmt-ws/ws/ConfigReplication`.

The WSDL document describing this service can be retrieved from `/pf-mgmt-ws/ws/ConfigReplication?wsdl`.

The web service exposes the following method: `public void replicateConfiguration();`

### Code sample

Below is example client code using the Apache AXIS libraries that invokes the configuration replication functionality.

```
Call call2 = (Call) service.createCall();
call2.setUsername("joe");
call2.setPassword("test");
String addr2 = "https://localhost:9999/pf-mgmt-ws/ws/ConfigReplication";
call2.setTargetEndpointAddress(addr2);
call2.setOperationName("replicateConfiguration");
call2.invoke(new Object[]{});
```

### Validation disclaimer

Use the administrative console whenever possible to reduce the risk to data integrity.

The import process is not subject to the same rigorous data validation performed by the administrative user interface. Although some checks are made, it is possible to create invalid connections using the connection-migration process. As the XML is complex and validation is limited, use the administrative console to create the initial XML connection instead of attempting to create an XML connection from scratch. That way, changes necessary to the exported connection's XML representation can be held to a minimum, reducing the risk of compromising data integrity.

## SSO Directory Service

PingFederate single sign-on (SSO) Directory Service allows applications to retrieve configuration data from a runtime PingFederate server. A PingFederate server in a cluster configured as an administrative console does not support this web service.



### Note:

As of PingFederate 10.2, the SSO Directory Service has been deprecated and will be removed in a future release.

The SSO Directory Service lets web applications avoid storing and maintaining the data locally. These applications can retrieve the following types of data:

- A list of identity provider (IdP) partners
- A list of service provider (SP) partners
- A list of IdP adapter instances
- A list of SP adapter instances

The SSO Directory Service provides useful information for integrating an application with a PingFederate server. It is a way for the application to dynamically determine which partners can be used for SSO. This means applications do not need to be modified when new partners are configured in PingFederate.

You can find the WAR file for this module, `pf-ws.war`, in the `pingfederate/server/default/deploy` directory.



### Note:

If you do not want to allow use of the service, remove the WAR file from the `deploy` directory.

The service endpoint is: `pf-ws/services/SSODirectoryService`.

You can retrieve the WSDL document describing this service from `/pf-ws/services/SSODirectoryService?wsdl`.

You can retrieve a list using any of the following methods:

- `getIdPList` returns a list of active IdP connections configured for SP-initiated SSO. The list contains each IdP's connection ID and connection name.
- `getSPList` returns a list of active SP connections configured for IdP-initiated SSO. The list contains each SP's connection ID and connection name.

**Note:**

For either IdP or SP lists, connection IDs are returned as values for the XML tag `<entityId>`. Connection Names are returned as values for the XML tag `<company>`. For more information see [SOAP request and response examples](#) on page 1200.

- `getAdapterInstanceList` returns a list of SP adapter instances containing an ID and name.
- `getIdpAdapterInstanceList` returns a list of IdP adapter instances containing an ID and name.

**Note:**

These methods do not require input parameters.

The service is also available over HTTP. The query string for retrieving any of the lists is `/pf-ws/services/SSODirectoryService?method=<method_name>`.

**Coding example**

When you integrate a web application with PingFederate, use the single sign-on (SSO) Directory Service to generate a connection or adapter list. The code needed to create any of the lists is similar.

The following Java code example retrieves an identity provider (IdP) list from the web service. The program calls the `getIdPList` method in the SSO Directory Service to retrieve an IdP list and print it to the console. This example uses the Apache Axis library and includes optional code for authentication to the PingFederate server. For more information see [Configuring service authentication](#) on page 698. HTTPS is recommended when including credentials.

```
import org.apache.axis.client.Call;
import org.apache.axis.client.Service;
import java.net.URL;
import javax.xml.namespace.QName;
import com.pingidentity.ws.SSOEntity;
public class SSODirectoryClientSample
{
    public static void main(String[] args) throws Exception
    {
        Service service = new Service();
        Call call = (Call) service.createCall();
        call.setUsername("username");
        call.setPassword("pass");
        URL serviceUrl = new URL(
            "https://localhost:9031/pf-ws/services/
            SSODirectoryService");
        QName qn = new QName("urn:BeanService", "SSOEntity");
        call.registerTypeMapping(SSOEntity.class, qn,
            new org.apache.axis.encoding.ser.BeanSerializerFactory(
                SSOEntity.class, qn),

            new org.apache.axis.encoding.ser.BeanDeserializerFactory(
                SSOEntity.class, qn));
        call.setTargetEndpointAddress( serviceUrl );
        call.setOperationName( new QName(
            "http://www.pingidentity.com/servicesSSODirectoryService",
            "getIdPList"));
        Object result = call.invoke( new Object[] { } );
    }
}
```

```

if (result instanceof SSOEntity[])
{
    SSOEntity[] idpArray = (SSOEntity[])result;
    for (SSOEntity idp : idpArray)
    {
        System.out.println(idp.getEntityId() + " " +
            idp.getCompany());
    }
}
else
{
    System.out.println("Received problem response from
        server: " + result);
}
}
}

```

## SOAP request and response examples

A client application must send a SOAP request to the PingFederate server specifying the requested web service and the specific method.

The following is a typical SOAP request for an identity provider (IdP) list using the single sign-on (SSO) Directory Service.

```

<?xml version="1.0" encoding="UTF-8"?>
<soapenv:Envelope
    xmlns:soapenv="http://schemas.xmlsoap.org/soap/envelope/"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
    <soapenv:Body>
        <ns1:getIDPList
            soapenv:encodingStyle=
                "http://schemas.xmlsoap.org/soap/encoding/"
            xmlns:ns1=
                "https://localhost:9031/ssodir/services/
                SSODirectoryService"/>
    </soapenv:Body>
</soapenv:Envelope>

```

The PingFederate server's web service returns a response containing the list you requested. The following is an example of a typical SOAP response for an IdP list.

```

<?xml version="1.0" encoding="UTF-8" ?>
<soapenv:Envelope xmlns:soapenv="http://schemas.xmlsoap.org/
    soap/envelope/"
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
    <soapenv:Body>
        <getIDPListResponse
            soapenv:encodingStyle=
                "http://schemas.xmlsoap.org/soap/encoding/">
            <getIDPListReturn
                soapenc:arrayType=
                    "ns1:IDP[2]" xsi:type="soapenc:Array"
                xmlns:ns1="urn:BeanService"
                xmlns:soapenc=
                    "http://schemas.xmlsoap.org/soap/encoding">
                <getIDPListReturn href="#id0" />
                <getIDPListReturn href="#id1" />
            </getIDPListReturn>
        </getIDPListResponse>
    <multiRef id="id0" soapenc:root="0"

```



```

soapenv:encodingStyle=
  "http://schemas.xmlsoap.org/soap/encoding/"
  xsi:type="ns2:IDP"
  xmlns:soapenc=
    "http://schemas.xmlsoap.org/soap/encoding/"
    xmlns:ns2="urn:BeanService">
  <company xsi:type="xsd:string">MegaMarket</company>
  <entityId xsi:type="xsd:string">www.megamarket.com
  </entityId>
</multiRef>
<multiRef id="idl" soapenc:root="0"
  soapenv:encodingStyle=
    "http://schemas.xmlsoap.org/soap/encoding/"
    xsi:type="ns3:IDP" xmlns:ns3="urn:BeanService"
  xmlns:soapenc=
    "http://schemas.xmlsoap.org/soap/encoding/">
  <company xsi:type="xsd:string">Ping</company>
  <entityId
    xsi:type="xsd:string">pingfederate3:default:entityId
  </entityId>
</multiRef>
</soapenv:Body>
</soapenv:Envelope>

```

## OAuth Client Management Service

PingFederate includes a REST-based web service for OAuth client management.

The OAuth client management service is provided primarily for organizations with many OAuth clients, for allowing programmatic management of OAuth clients, and as an alternative to using the administrative console, the administrative API, or dynamic client registration.

The [/pf-ws/rest/oauth/clients](#) and [/pf-ws/rest/oauth/clients/<clientId>](#) REST resources are URL path extensions of the PingFederate runtime endpoint:

- <https://www.example.com:9031/pf-ws/rest/oauth/clients>
- <https://www.example.com:9031/pf-ws/rest/oauth/clients/<clientId>>

### Important:

The OAuth Client Management Service requires client records to be stored on an external storage.

### Note:

Applications must authenticate to this web service using HTTP Basic authentication and credentials validated through an instance of a Password Credential Validator (PCV). The PCV instance, in turn, must be selected in the OAuth authorization server (AS) configuration.

### Tip:

The administrative API can also manage OAuth clients programmatically regardless of whether the client records are managed in XML files or in a database.

Endpoint: [/pf-ws/rest/oauth/clients](#)



This resource accepts the [POST](#), [PUT](#), and [GET](#) methods. The POST and PUT methods described in this section require parameter name/value pairs formatted in JSON.


## POST




Use the POST method to create a new client based on the parameters provided in the request. Parameters correspond to the fields on the **Client** window. The required **MIME** type is `application/json`.


## JSON Parameters

| Parameter                     | Description  |
|-------------------------------|--|
| <b>clientId</b><br>(Required) | A unique identifier the client provides to the resource server (RS) to identify itself. This identifier is included with every request the client makes. |
| <b>enabled</b>                | Specifies whether the client is enabled. The default value is <code>true</code> . A valid value is either <code>true</code> or <code>false</code> .      |
| <b>name</b><br>(Required)     | A descriptive name for the client instance. This name appears when the user is prompted for authorization.   |
| <b>description</b>            | A description of what the client application does. This description appears when the user is prompted for authorization.                                 |


| Parameter                    | Description   |
|------------------------------|---|
| <code>clientAuthnType</code> | <p>The authentication method that the client uses.</p> <ul style="list-style-type: none"> <li>Set to <code>none</code> if your use case does not require client authentication.</li> </ul> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>A value other than <code>none</code> is required for any of the following use cases:</p> <ul style="list-style-type: none"> <li>This client uses the <code>client_credentials</code> grant type. See the <code>grantTypes</code> parameter.</li> <li>This client signs its ID tokens using an HMAC signing algorithm. See the <code>idTokenSigningAlgorithm</code> parameter.</li> <li>This client can access the Session Revocation API endpoint. See the <code>grantAccessSessionRevocationApi</code> parameter.</li> <li>This client sends a <code>secret</code> parameter value.</li> </ul> </div> <ul style="list-style-type: none"> <li>Set to <code>SECRET</code> for HTTP Basic authentication.<br/>This authentication method requires the <code>secret</code> parameter.</li> <li>Set to <code>CLIENT_CERT</code> for mutual SSL/TLS authentication; recommended for client applications where security policies prohibit storing passwords.<br/>This authentication method requires the <code>clientCertIssuerDn</code> and <code>clientCertSubjectDn</code> parameters.</li> </ul> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <p> <b>Important:</b></p> <p>If you choose mutual SSL/TLS authentication, you must configure a secondary PingFederate HTTPS port. For more information, see the property <code>pf.secondary.https.port</code> in the table under <a href="#">Configuring PingFederate properties</a> on page 820.</p> </div> <ul style="list-style-type: none"> <li>Set to <code>PRIVATE_KEY_JWT</code> check box if the client authenticates through the <code>private_key_jwt</code> client authentication method, as defined in <a href="#">Client Authentication</a> in the OpenID Connect specification. For more information, see <a href="https://openid.net/specs/openid-connect-core-1_0.html#ClientAuthentication">openid.net/specs/openid-connect-core-1_0.html#ClientAuthentication</a>.</li> </ul> |
| <code>secret</code>          | <p>The client password or phrase.</p> <p>Required when the <code>clientAuthnType</code> parameter is set to <code>SECRET</code>.</p>  |

| Parameter                                      | Description  |
|--|--|
| <code>clientCertIssuerDN</code>                | <p>The issuer distinguished name (DN) of the client certificate.</p> <p>These are certificate authority (CA) certificates imported into PingFederate on the <b>Security # Certificate &amp; Key Management # Trusted CAs</b> window. Alternatively, it might be set to <code>Trust Any</code> to trust all the issuers found on the <b>Trusted CAs</b> window.</p> <p>Required when the <code>clientAuthnType</code> parameter is set to <code>CLIENT_CERT</code>.</p>   |
| <code>clientCertSubjectDN</code>               | <p>The subject DN of the client certificate.</p> <p>Required when the <code>clientAuthnType</code> parameter is set to <code>CLIENT_CERT</code>.</p>   |
| <code>tokenEndpointAuthSigningAlgorithm</code> | <p>The signing algorithm that the client must use to sign the JSON web tokens (JWT) for client authentication.</p> <p>Applicable only when the <code>clientAuthnType</code> parameter is provided with a value of <code>PRIVATE_KEY_JWT</code>.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>If this parameter is not provided, the client can use any of the supported signing algorithms.</p> |


| Parameter                      | Description   |
|--------------------------------|---|
| <b>enforceReplayPrevention</b> | <p>This field determines whether mandates a unique signed JWT from the client for each request when the client is configured to authenticate via the <code>private_key_jwt</code> client authentication method, to transmit request parameters using in signed request objects, or to do both.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <div data-bbox="618 432 1438 638" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>The underlying Assertion Replay Prevention Service is cluster-aware. For more information, see <a href="#">Assertion Replay Prevention Service</a> on page 204.</p> </div>   |
| <b>requireSignedRequests</b>   | <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <code>request</code>. The value of the <code>request</code> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <div data-bbox="618 919 1438 1457" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Note:</b></p> <p>If a client includes in an authorization request a request parameter other than <code>client_id</code>, as a parameter outside of the signed request object and a claim inside of the signed request object, always uses the claim value found inside the signed request object to process the request further.</p> <p>For the <code>client_id</code> request parameter, the values outside of the signed request object must match the claim values inside of the signed request object. If the values do not match, returns an error message to the client.</p> <p>If a request parameter is found only outside of the signed request object, ignores the request parameter and returns no error message.</p> </div> <div data-bbox="618 1457 1438 1667" style="border: 1px solid #ccc; padding: 5px;"> <p> <b>Tip:</b></p> <p>Per OAuth and OpenID Connect specifications, a client must always include in an authorization request the <code>client_id</code> parameter outside of the signed request object.</p> </div> |
|                                | <p>For more information about request objects, see <a href="#">JWT Secured Authorization Request (JAR) draft specification</a>.</p> <p>If this parameter is not provided, a value of <code>false</code> is assumed.</p>   |

| Parameter                     | Description  |
|-------------------------------|--|
| requestObjectSigningAlgorithm | <p data-bbox="638 205 1430 268">The signing algorithm that the client must use to sign its request objects for transmission of request parameters.</p> <p data-bbox="638 289 1430 352">Applicable only when the client might send its authorization requests using request objects.</p> <p data-bbox="638 373 1430 394">accepts the following values:</p> <ul data-bbox="654 415 1430 730" style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div data-bbox="673 745 1430 1081" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="682 766 722 808"> <b>Note:</b></p> <p data-bbox="682 829 1430 1050">RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p data-bbox="638 1102 1430 1155">If this parameter is not provided, the client can use any of the supported signing algorithms.</p> |


| Parameter                                   | Description  |
|---|--|
| <code>jwtksUrl</code> or <code>jwtks</code> | <p>The URL of the JSON Web Key Set (JWKS) or the actual JWKS from the client.</p> <p>If the client is configured to use the <code>private_key_jwt</code> client authentication method, to transmit request parameters in signed request objects, or to transmit CIBA request parameters in signed request objects, only one of the previous values is required for to verify the authenticity of the JWTs.</p> <p>Either value can be defined even if the client is not configured to use JWTs for authentication or transmission of request parameters. This flexibility allows the client to transmit request parameters in signed request objects for some requests and without the use of signed request objects for some other transactions. For information on runtime processing, see .</p> <p>If the client signs its JWTs using an RSASSA-PSS signing algorithm, must be deployed to run in a Java 8 or Java 11 runtime environment, or integrated with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> <p>If the client is configured to encrypt ID tokens using an asymmetric encryption algorithm, either the JWKS URL or the actual JWKS must be provided. See the <b>ID Token Key Management Encryption Algorithm</b> setting.</p> |
| <code>redirectUris</code>                   | URIs where the OAuth AS may redirect the resource owner's user agent after authorization is obtained. The authorization code and implicit grant types require at least one redirection URI.  |
| <code>logoUrl</code>                        | The location of the logo used on user-facing OAuth grant authorization and revocation pages. For best results with the installed HTML templates, the recommended size is 72 x 72 pixels.   |
| <code>bypassApprovalPage</code>             | <p>If set to <code>true</code>, resource-owner approval for client access is assumed, and no longer presents to the user an authorization consent page or redirects to a trusted web application that is responsible to prompt the user for authorization for this client.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided, a value of <code>false</code> is assumed.</p>   |

| Parameter               | Description  |
|-------------------------|--|
| <b>restrictScopes</b>   | <p>This setting controls whether all existing common scopes and scope groups, and those created in the future, or only the select few should be made available to the client.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>When set to <code>true</code>, PingFederate limits the client to a list of common scopes and scope groups as specified by the <b>restrictedScopes</b> parameter.</p> <p>When set to <code>false</code>, all existing common scopes and scope groups and those created in the future are available to the client.</p> <p>If this parameter is not provided, a value of <code>false</code> is assumed.</p> <div data-bbox="625 615 1438 982" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Depending on the configured dynamic scope patterns and whether they are defined as common or exclusive dynamic scopes, this setting and the <b>restrictedScopes</b> parameter value can impact the results of scope evaluation. The default scope, however, is always allowed for and available to all clients. For detailed information, see the Dynamic scope evaluation and per-client scope management section in <a href="#">Scopes and scope management</a> on page 531.</p> </div> |
| <b>restrictedScopes</b> | <p>Used in conjunction with the <b>restrictScopes</b> parameter value of <code>true</code> to limit this client to a list of common scopes or scope groups in addition to the default scope. The rest and any common scopes and scope groups created in the future become invalid for the client; that is, if the client tries to use such scope or scope group, it will receive an <code>invalid_scope</code> error message from PingFederate.</p>  |






| Parameter              | Description  |
|------------------------|--|
| <b>exclusiveScopes</b> | <p>This setting controls whether any exclusive scopes and scope groups should be made available to the client.</p> <p>As needed, provide this parameter with a list of exclusive scopes or scope groups that are intended for the client. The rest and any exclusive scopes and scope groups created in the future become invalid for the client. In other words, if the client tries to use such scope or scope group, it will receive an <code>invalid_scope</code> error message from PingFederate.</p> <p>If this parameter is not provided, no exclusive scopes or scope groups are available to the client.</p> <div data-bbox="625 583 1438 919" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Depending on the configured dynamic scope patterns and whether they are defined as common or exclusive dynamic scopes, this setting can impact the results of scope evaluation. The default scope, however, is always allowed for and available to all clients. For detailed information, see the Dynamic scope evaluation and per-client scope management section in <a href="#">Scopes and scope management</a> on page 531.</p> </div> |
| <b>grantTypes</b>      | <p>An array of one or more grant types, which a client can request. accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ <code>authorization_code</code></li> <li>▪ <code>implicit</code></li> <li>▪ <code>refresh_token</code></li> <li>▪ <code>client_credentials</code></li> <li>▪ <code>urn:ietf:params:oauth:grant-type:device_code</code></li> <li>▪ <code>urn:openid:params:grant-type:ciba</code></li> <li>▪ <code>password</code></li> <li>▪ <code>extension</code> (JWT Bearer Token or SAML 2.0 Bearer Assertion)</li> </ul> <p>For more information about each grant type, see <a href="#">Grant types</a>.</p>  |


| Parameter                           | Description  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
|-------------------------------------|--|---------------|-------------|------|--------------------|---------------|---------------------------------|---------------------|---------------------------------|------------|---------------------------------|----------|----------|----------------|----------|-------|----------|
| <b>restrictedResponseTypes</b>      | <p>An array of one or more response types, which a client can request.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ code</li> <li>▪ code id_token</li> <li>▪ code id_token token</li> <li>▪ code token</li> <li>▪ id_token</li> <li>▪ id_token token</li> <li>▪ token</li> </ul> <p>For more information about these response types, see Definitions of Multiple-Valued Response Type Combinations.</p> <p>If one or more response types are specified, the resulting client is only allowed to send one of the specified response types at runtime. Requests from this client with other response types will be rejected.</p> <p>Response type and grant type parameters must be provided in tandem because certain response types require one or more grant types, and vice versa. The following table provides a summary of their relationship.</p> <table border="1" style="margin-left: auto; margin-right: auto;"> <thead> <tr> <th>response type</th> <th>grant types</th> </tr> </thead> <tbody> <tr> <td>code</td> <td>authorization_code</td> </tr> <tr> <td>code id_token</td> <td>authorization_code and implicit</td> </tr> <tr> <td>code id_token token</td> <td>authorization_code and implicit</td> </tr> <tr> <td>code token</td> <td>authorization_code and implicit</td> </tr> <tr> <td>id_token</td> <td>implicit</td> </tr> <tr> <td>id_token token</td> <td>implicit</td> </tr> <tr> <td>token</td> <td>implicit</td> </tr> </tbody> </table> | response type | grant types | code | authorization_code | code id_token | authorization_code and implicit | code id_token token | authorization_code and implicit | code token | authorization_code and implicit | id_token | implicit | id_token token | implicit | token | implicit |
| response type                       | grant types  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code                                | authorization_code   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code id_token                       | authorization_code and implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code id_token token                 | authorization_code and implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| code token                          | authorization_code and implicit  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| id_token                            | implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| id_token token                      | implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| token                               | implicit   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| <b>defaultAccessTokenManager</b>    | <p>Determines the default Access Token Management (ATM) instance for this client.</p>  |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |
| <b>validateUsingAllEligibleAtms</b> | <p>Applicable only to resource server clients.</p> <p>If selected, this resource server client is not required to specify the additional <b>access_token_manager_id</b> or <b>aud</b> parameters to disambiguate the ATM instance in its token validation requests. When the resource server client does not specify the desired ATM instance, validates the access tokens against all eligible ATM instances. This simplifies interactions with PingAccess by avoiding the need to align resource URIs between PingAccess and .</p> <p>This check box is not selected by default.</p>   |               |             |      |                    |               |                                 |                     |                                 |            |                                 |          |          |                |          |       |          |


| Parameter                                      | Description   |
|--|---|
| <code>requireProofKeyForCodeExchange</code>    | <p>Applicable when the client is configured to support the <code>authorization_code</code> grant type.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>Determines whether the client must provide certain parameters to reduce the risk of authorization code interception attack. For more information, see the Proof Key for Code Exchange (PKCE) by OAuth Public Clients specification.</p> <p>When enabled, this client must include a one-time string value through the use of the <code>code_challenge</code> parameter in its authorization request. For more information, see <a href="#">Authorization endpoint</a> on page 1147. It must also submit the corresponding code verifier through the <code>code_verifier</code> parameter in its token request when exchanging an authorization code for an access token. For more information, see <a href="#">OAuth grant type parameters</a> on page 1164.</p> <p>If this parameter is not provided, the assumed value is <code>false</code>.</p> |
| <code>persistentGrantExpirationType</code>     | <p>Overrides the <b>Persistent Grant Max Lifetime</b> value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This setting can be overridden per grant-mapping configuration through the use of an extended persistent grant attribute <code>PERSISTENT_GRANT_LIFETIME</code>. The <code>PERSISTENT_GRANT_LIFETIME</code> attribute is defined in <b>System # OAuth Settings # Authorization Server Settings</b>. When this attribute is active, you can set the lifetime of persistent grants based on the outcome of attribute mapping expressions in individual grant-mapping configurations. For grant-mapping configurations that do not require this fine-grain control, you can configure them to use the default value.</p> </div>   |
| <code>persistentGrantExpirationTime</code>     | <p>An integer representing units of time for storage of persistent grants for this client.</p> <p>Required when the <code>persistentGrantExpirationType</code> parameter is provided with a value of <code>OVERRIDE_SERVER_DEFAULT</code>.</p>  |
| <code>persistentGrantExpirationTimeUnit</code> | <p>Units for the expiration time set by the <code>persistentGrantExpirationTime</code> parameter.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ h (hours)</li> <li>▪ d (days)</li> <li>▪ n (minutes)</li> </ul> <p>Required when the <code>persistentGrantExpirationType</code> parameter is provided with a value of <code>OVERRIDE_SERVER_DEFAULT</code>.</p>   |

| Parameter                                       | Description  |
|---|--|
| <code>persistentGrantIdleTimeoutType</code>     | <p>Overrides the <b>Persistent Grant Idle Timeout</b> field value set globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>SERVER_DEFAULT (the default): Use the global setting.</li> <li>NONE: Grants do not expire due to inactivity.</li> <li>OVERRIDE_SERVER_DEFAULT: Use in conjunction with the <code>persistentGrantIdleTimeout</code> and <code>persistentGrantIdleTimeoutUnit</code> parameters to set the idle timeout window.</li> </ul> <p>If an idle timeout value is configured, the idle timeout window slides when a persistent grant is updated. For more information, see .</p> <p>If you configure an idle timeout value, the idle timeout window slides when a persistent grant updates. When you have an idle timeout value configured without a maximum lifetime, persistent grants remain valid until they expire due to inactivity or until the grant storage revokes or removes them. When you have an idle timeout value configured with a maximum lifetime, persistent grants remain valid until they expire due to inactivity or lifetime expiration or until the grant storage removes them.</p> |
| <code>persistentGrantIdleTimeout</code>         | <p>An integer representing the inactivity timeout value for this client.</p> <p>Required when the <code>persistentGrantIdleTimeoutType</code> parameter is provided with a value of <code>OVERRIDE_SERVER_DEFAULT</code>.</p>  |
| <code>persistentGrantIdleTimeoutTimeUnit</code> | <p>Units of the inactivity timeout value set by the <code>persistentGrantIdleTimeout</code> parameter.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>h (hours)</li> <li>d (days)</li> <li>n (minutes)</li> </ul> <p>Required when the <code>persistentGrantIdleTimeoutType</code> parameter is provided with a value of <code>OVERRIDE_SERVER_DEFAULT</code>.</p>  |
| <code>refreshRolling</code>                     | <p>Overrides the <b>Roll Refresh Token Values</b> setting configured globally in <b>System # OAuth Settings # Authorization Server Settings</b>.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>Note that a value of <code>true</code> does not override the <b>Minimum Interval to Roll Refresh Tokens</b> value set on the <b>Authorization Server Settings</b> window.</p> <p>If this parameter is not provided, the <b>Roll Refresh Token Values</b> setting configured globally in the <b>System # OAuth Settings # Authorization Server Settings</b> window is used.</p>   |


| Parameter  | Description   |
|--|---|
| <code>refreshTokenRollingIntervalType</code>   | <p>When set to the default value, <code>SERVER_DEFAULT</code>, the client's minimum refresh token rolling interval comes from the global value in the <b>Minimum Interval to Roll Refresh Tokens</b> field on the <b>Authorization Server Settings</b> window.</p> <p>When set to <code>OVERRIDE_SERVER_DEFAULT</code>, the client's refresh token rolling interval comes from the value of the <code>refreshTokenRollingInterval</code> parameter.</p>   |
| <code>refreshTokenRollingInterval</code>   | <p>An integer from 0 to 8760 that represents the minimum number of hours that must pass before a new refresh token can be issued. This value overrides the global value in the <b>Minimum Interval to Roll Refresh Tokens</b> field on the <b>Authorization Server Settings</b> window when the <code>refreshTokenRollingIntervalType</code> parameter is set to <code>OVERRIDE_SERVER_DEFAULT</code>.</p> <p>Required when the <code>refreshTokenRollingIntervalType</code> parameter is set to <code>OVERRIDE_SERVER_DEFAULT</code>.</p>  |
| <code>refreshTokenRollingGracePeriod</code>  | <p>The amount of time in seconds that a rolled refresh token is still valid in the event that the client failed to receive an updated one during a roll.</p>  |
| <code>requirePushedAuthorizationRequests</code>  | <p>When set to <code>true</code>, the client must use the PAR endpoint <code>/as/par.oauth2</code> on the AS to initiate authorization flows. When set to <code>false</code>, the client can use the PAR endpoint. The default value is <code>false</code>.</p> <p>This parameter works in conjunction with the <b>PAR Status</b> setting on the AS. For example:</p> <ul style="list-style-type: none"> <li>▪ If PAR is <b>Enabled</b> on the AS and this parameter is set to <code>true</code>, then the client must use PAR</li> <li>▪ If PAR is <b>Enabled</b> on the AS but this parameter is set to <code>false</code>, then the client can use PAR</li> <li>▪ If PAR is <b>Required</b> on the AS but this parameter is set to <code>false</code>, then the client must use PAR</li> <li>▪ If PAR is <b>Disabled</b> on the AS and this parameter is set to <code>true</code>, then the client cannot access the AS</li> </ul> <p>Do not set this parameter to <code>true</code> if PAR is disabled on the AS.</p> <p>For more information about PAR, see <a href="#">Pushed authorization requests endpoint</a> on page 1191 and <a href="#">Configuring authorization server settings</a> on page 519.</p> |
| OpenID Connect client settings   |   |
| <p> <b>Note:</b><br/>The following parameters are only applicable when this client supports the OpenID Connect use cases.</p> |   |

| Parameter               | Description   |
|-------------------------|---|
| idTokenSigningAlgorithm | <p data-bbox="633 205 1430 268">The JSON Web Signature (JWS) algorithm required for the OpenID Connect ID tokens.</p> <p data-bbox="633 289 820 317">Allowed values:</p> <ul data-bbox="654 338 1268 793" style="list-style-type: none"> <li>▪ none - No signing algorithm</li> <li>▪ HS256 - HMAC using SHA-256</li> <li>▪ HS384 - HMAC using SHA-384</li> <li>▪ HS512 - HMAC using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div data-bbox="672 814 1438 1142" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="683 829 727 865"> <b>Note:</b></p> <p data-bbox="683 892 1430 1115">RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <div data-bbox="625 1163 1438 1365" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="636 1178 680 1213"> <b>Important:</b></p> <p data-bbox="636 1241 1438 1335">If static keys for OAuth and OpenID Connect are enabled, use either an RSA algorithm or an EC algorithm that has been configured with an active static key.</p> </div> |


| Parameter                                      | Description   |
|--|---|
| <code>idTokenEncryptionAlgorithm</code>        | <p>The algorithm used to encrypt or otherwise determine the value of the content encryption key.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ <code>dir</code> - Direct Encryption with symmetric key</li> <li>▪ <code>A128KW</code> - AES-128 Key Wrap</li> <li>▪ <code>A192KW</code> - AES-192 Key Wrap</li> <li>▪ <code>A256KW</code> - AES-256 Key Wrap</li> <li>▪ <code>A128GCMKW</code> - AES-GCM-128 key encryption</li> <li>▪ <code>A192GCMKW</code> - AES-GCM-192 key encryption</li> <li>▪ <code>A256GCMKW</code> - AES-GCM-256 key encryption</li> <li>▪ <code>ECDH-ES</code> - ECDH-ES</li> <li>▪ <code>ECDH-ES+A128KW</code> - ECDH-ES with AES-128 Key Wrap</li> <li>▪ <code>ECDH-ES+A192KW</code> - ECDH-ES with AES-192 Key Wrap</li> <li>▪ <code>ECDH-ES+A256KW</code> - ECDH-ES with AES-256 Key Wrap</li> <li>▪ <code>RSA-OAEP</code> - RSAES-OAEP</li> <li>▪ <code>RSA-OAEP-256</code> - RSAES OAEP using SHA-256 and MGF1 with SHA-256</li> </ul> |
| <code>idTokenContentEncryptionAlgorithm</code> | <p>The content encryption algorithm used to perform authenticated encryption on the plain text payload of the token.</p> <p>Required if an algorithm is provided through the <code>idTokenEncryptionAlgorithm</code> parameter.</p> <p>Allowed values:</p> <ul style="list-style-type: none"> <li>▪ <code>A128CBC-HS256</code> - Composite AES-CBC-128 HMAC-SHA-256</li> <li>▪ <code>A192CBC-HS384</code> - Composite AES-CBC-192 HMAC-SHA-384</li> <li>▪ <code>A256CBC-HS512</code> - Composite AES-CBC-256 HMAC-SHA-512</li> <li>▪ <code>AES-GCM-128</code> - A128GCM</li> <li>▪ <code>AES-GCM-192</code> - A192GCM</li> <li>▪ <code>AES-GCM-256</code> - A256GCM</li> </ul>  |
| <code>policyGroupId</code>                     | The desired Open ID Connect policy.   |
| <code>grantAccessSessionRevocationApi</code>   | <p>Set to <code>true</code> to allow this client to access the Session Revocation API for back-channel session query and revocation.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided, a value of <code>false</code> is assumed.</p> <div style="border: 1px solid black; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If clients are allowed to add sessions to the revocation list, you can enable the <b>Check session revocation status</b> option in the applicable Access Token Management instances for the token validation process to consider whether a session has been added to the revocation list. For more information, see <a href="#">Managing session validation settings</a> on page 612.</p> </div>  |

| Parameter   | Description   |
|---|---|
| <b>pairwiseUserType</b>   | Set to <code>true</code> to allow this client to use pairwise pseudonymous IDs. This parameter is set to <code>false</code> by default.   |
| <b>sectorIdentifierUri</b>  | Specify one HTTPS URL only. This parameter is applicable only if <b>pairwiseUserType</b> is set to <code>true</code> .  |
|  <b>Note:</b><br>If the <b>Track User Sessions for Logout</b> check box is selected in the <b>System # OAuth Settings # Authorization Server Settings</b> window, you can provide two additional parameters to enable asynchronous front-channel logout for this client. |   |
| <b>pingAccessLogoutCapable</b>  | <p>Set to <code>true</code>, sends logout requests through the browser to an OpenID Connect endpoint in PingAccess as part of the logout process.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided, a value of <code>false</code> is assumed.</p>                 |
| <b>logoutUris</b>   | A list of additional endpoints at the relying parties as needed. sends requests to these URIs through the browser as part of the logout process. The relying parties must return an image in their logout responses, otherwise returns an error message or redirects to the <b>InErrorResource</b> parameter value, if specified. |
| Device Authorization Grant client settings  |   |



| Parameter                     | Description   |
|-------------------------------|---|
| <b>deviceFlowSettingsType</b> | <p>This field controls whether to use global device authorization grant settings defined on the <b>System # OAuth Settings # Authorization Server Settings</b> window.</p> <p>Allowed values are <code>SERVER_DEFAULT</code> and <code>OVERRIDE_SERVER_DEFAULT</code>.</p> <p>Set to <code>OVERRIDE_SERVER_DEFAULT</code> and configure any of the following settings:</p> <p><b>userAuthzUrlOverride</b></p> <p>This field controls whether PingFederate should use a different URL, perhaps for ease of use or branding purposes, when formulating the verification URLs to be included in its device authorization responses. For more information, see <a href="#">Device authorization endpoint</a> on page 1182.</p> <p>For example, if this field is configured with a value of <code>https://www.example.org/welcome</code>, PingFederate returns <code>https://www.example.org/welcome</code> and <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> as the verification URIs. After processing the device authorization response, which includes the verification URIs, the device presents one of them to the user. The user is expected to browse to the presented verification URI on a second device.</p> <div data-bbox="672 989 1440 1255" style="border: 1px solid black; padding: 5px;"> <p> <b>Important:</b></p> <p>The target web server must redirect the browser to PingFederate at its user authorization endpoint. For more information, see <a href="#">User authorization endpoint</a> on page 1185. Moreover, it must also preserve the <code>user_code</code> parameter value, if provided.</p> </div> <p>For example, if the base URL of your PingFederate server is <code>https://www.example.com</code> and this field is configured with a value of <code>https://www.example.org/welcome</code>, the target web server must redirect as follows:</p> <ul style="list-style-type: none"> <li>▪ <code>https://www.example.org/welcome</code> to <code>https://www.example.com/as/user_authz.oauth2</code></li> <li>▪ <code>https://www.example.org/welcome?user_code=&lt;activationcode&gt;</code> to <code>https://www.example.com/as/user_authz.oauth2?user_code=&lt;activationcode&gt;</code></li> </ul> <p><b>pendingAuthzTimeoutOverride</b></p> <p>The lifetime of an activation code (the <code>user_code</code> parameter value) in seconds.</p> <p><b>devicePollingIntervalOverride</b></p> <p>The amount of time in seconds that the device waits between polling requests to the PingFederate token endpoint.</p> <p><b>bypassActivationCodeConfirmationOverride</b></p> <p>When PingFederate receives a verification request that includes an activation code (the <code>user_code</code> parameter value), it prompts the user to confirm the activation code.</p> <p>This field controls whether PingFederate should skip this confirmation step.</p> |

| Parameter  | Description   |
|--|---|
| Client-initiated backchannel authentication (CIBA) client settings |   |
| <b>cibaTokenDeliveryMode</b>                                       | <p>The token delivery method that the client supports. supports poll and ping.</p> <p>Set to <code>poll</code> if the client can check for the authorization results periodically at the token endpoint.</p> <p>Set to <code>ping</code> if the client prefers to wait for a ping callback message from as a signal that the authorization result is ready for pickup.</p> <p>If the CIBA grant type is enabled, this parameter is required; no value is assumed.</p>   |
| <b>cibaNotificationEndpoint</b>                                    | <p>The client's notification endpoint, to which sends its ping call back messages.</p> <p>Required only if <code>ping</code> is the configured token delivery method.</p>   |
| <b>cibaPollingInterval</b>   | <p>Specifies the number of seconds that the client must wait between its attempts to check for the authorization results at the token endpoint. When receives a token request within this time interval, it returns a <code>slow_down</code> error message to the client.</p> <p>A valid value ranges from 1 to 3600.</p> <p>If the CIBA grant type is enabled, this parameter is required; no value is assumed.</p>  |
| <b>cibaPolicyId</b>  | <p>Specifies the CIBA request policy associated with the client.</p> <p>uses CIBA request policies to determine various aspects of CIBA authentication request, such as the maximum lifetime of authentication requests, the validity of unsigned login hint tokens, and the mapping configuration of identity hints.</p> <p>Provide an existing CIBA policy</p> <p>If this parameter is not provided and the CIBA grant type is enabled, PingFederate associates the client with the CIBA request policy has been designated as the default CIBA request policy on the <b>Applications # OAuth # CIBA Request Policies</b> window.</p> |
| <b>cibaUserCodeSupported</b>                                       | <p>Indicates whether the client supports user code.</p> <p>The purpose of this code is to authorize the transmission of an authentication request to the user's authentication device.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided and the CIBA grant type is enabled, user code support is not enabled.</p> <p>When user code support is enabled, the associated CIBA request policy must also be user code enabled.</p>  |

| Parameter                                | Description   |
|--|---|
| <b>cibaRequireSignedRequests</b>         | <p>Determines whether the client must transmit request parameters in a single, self-contained parameter. The parameter name is <b>request</b>. The value of the <b>request</b> parameter is a signed JWT whose claims represent the request parameters of the authorization request. The OpenID Connect specification calls this JWT a request object.</p> <p>A valid value is either <code>true</code> or <code>false</code>.</p> <p>If this parameter is not provided and the CIBA grant type is enabled, CIBA signed requests are not required.</p> <p>If CIBA signed requests are required, the client must also be configured with either the JWKS URL or the actual JWKS from the client.</p>   |
| <b>cibaRequestObjectSigningAlgorithm</b> | <p>The signing algorithm that the client must use to sign its request objects for transmission of request parameters.</p> <p>accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <div style="border: 1px solid black; padding: 10px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>RSASSA-PSS signing algorithms require a Java 8 or Java 11 runtime environment, or an integration with a hardware security module (HSM) and a static-key configuration for OAuth and OpenID Connect. For more information on HSM integration and static keys, see <a href="#">Supported hardware security modules</a> on page 177 and <a href="#">Keys for OAuth and OpenID Connect</a> on page 675, respectively.</p> </div> <p>If this parameter is not provided and the CIBA grant type is enabled, the client can use any of the allowed signing algorithms.</p> |

Token introspection settings

| Parameter                                     | Description  |
|---|--|
| <code>introspectionSigningAlgorithm</code>    | <p>The JWS algorithm used to sign token introspection responses.</p> <p>This parameter is optional.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ none - No signing algorithm</li> <li>▪ HS256 - HMAC using SHA-256</li> <li>▪ HS384 - HMAC using SHA-384</li> <li>▪ HS512 - HMAC using SHA-512</li> <li>▪ ES256 - ECDSA using P256 Curve and SHA-256</li> <li>▪ ES384 - ECDSA using P384 Curve and SHA-384</li> <li>▪ ES512 - ECDSA using P521 Curve and SHA-512</li> <li>▪ RS256 - RSA using SHA-256</li> <li>▪ RS384 - RSA using SHA-384</li> <li>▪ RS512 - RSA using SHA-512</li> <li>▪ PS256 - RSASSA-PSS using SHA-256</li> <li>▪ PS384 - RSASSA-PSS using SHA-384</li> <li>▪ PS512 - RSASSA-PSS using SHA-512</li> </ul> <p>Default value is RS256.</p>  |
| <code>introspectionEncryptionAlgorithm</code> | <p>The JSON web encryption (JWE) encryption algorithm used to encrypt the content-encryption key of token introspection responses.</p> <p>This parameter is optional.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ dir - Direct Encryption with symmetric key</li> <li>▪ A128KW - AES-128 Key Wrap</li> <li>▪ A192KW - AES-192 Key Wrap</li> <li>▪ A256KW - AES-256 Key Wrap</li> <li>▪ A128GCMKW - AES-GCM-128 key encryption</li> <li>▪ A192GCMKW - AES-GCM-192 key encryption</li> <li>▪ A256GCMKW - AES-GCM-256 key encryption</li> <li>▪ ECDH-ES - ECDH-ES</li> <li>▪ ECDH-ES+A128KW - ECDH-ES with AES-128 Key Wrap</li> <li>▪ ECDH-ES+A192KW - ECDH-ES with AES-192 Key Wrap</li> <li>▪ ECDH-ES+A256KW - ECDH-ES with AES-256 Key Wrap</li> <li>▪ RSA-OAEP - RSAES-OAEP</li> <li>▪ RSA-OAEP-256 - RSAES OAEP using SHA-256 and MGF1 with SHA-256</li> </ul> <p>For asymmetric algorithms, a JWKS or the HTTPS URL of a JWKS endpoint is required.</p> <p>For symmetric algorithms, the reversible secret is required.</p> |

| Parameter   | Description   |
|---|---|
| <code>introspectionContentEncryptionAlgorithm</code>    | <p>The JWT content encryption algorithm for token introspection responses.</p> <p>This parameter's value must be set if the <code>introspectionEncryptionAlgorithm</code> parameter is set.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ A128CBC-HS256 - Composite AES-CBC-128 HMAC-SHA-256</li> <li>▪ A192CBC-HS384 - Composite AES-CBC-192 HMAC-SHA-384</li> <li>▪ A256CBC-HS512 - Composite AES-CBC-256 HMAC-SHA-512</li> <li>▪ AES-GCM-128 - A128GCM</li> <li>▪ AES-GCM-192 - A192GCM</li> <li>▪ AES-GCM-256 - A256GCM</li> </ul>   |
| <code>requireJwtSecuredAuthorizationResponseMode</code> | <p>JWT secured authorization response mode (JARM) settings</p> <p>When enabled, the client must use JARM. The client's authorization requests must include one of the following authorization response mode values:</p> <ul style="list-style-type: none"> <li>▪ <code>jwt</code>: <ul style="list-style-type: none"> <li>▪ query JWT response in the case of the authorization code grant</li> <li>▪ fragment JWT response in the case of the implicit grant</li> </ul> </li> <li>▪ <code>query.jwt</code>: <ul style="list-style-type: none"> <li>▪ JWT response in the case of the authorization code grant</li> <li>▪ Failure in the case of the implicit grant unless the response is an encrypted JWT based on the client settings</li> </ul> </li> <li>▪ <code>fragment.jwt</code>: fragment JWT response</li> <li>▪ <code>form_post.jwt</code>: auto form-post JWT response</li> </ul> <p>JARM is a mechanism to enhance the security of the standard authorization response. It adds support for signing and encryption, sender authentication, and audience restriction. It also offers protection from replay, credential leakage, and mix-up attacks. JARM can be combined with any response type. For more information, see the <a href="#">JARM specification</a>.</p> <p>A valid value is either <code>true</code> or <code>false</code>. The default value is <code>false</code>.</p> |

| Parameter   | Description  |
|---|--|
| <code>authorizationResponseSigningAlgorithm</code>    | <p>The JWKS algorithm that PingFederate uses to sign JARM authorization responses.</p> <p>This parameter is optional.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ <code>none</code> - No signing algorithm</li> <li>▪ <code>HS256</code> - HMAC using SHA-256</li> <li>▪ <code>HS384</code> - HMAC using SHA-384</li> <li>▪ <code>HS512</code> - HMAC using SHA-512</li> <li>▪ <code>ES256</code> - ECDSA using P256 Curve and SHA-256</li> <li>▪ <code>ES384</code> - ECDSA using P384 Curve and SHA-384</li> <li>▪ <code>ES512</code> - ECDSA using P521 Curve and SHA-512</li> <li>▪ <code>RS256</code> - RSA using SHA-256</li> <li>▪ <code>RS384</code> - RSA using SHA-384</li> <li>▪ <code>RS512</code> - RSA using SHA-512</li> <li>▪ <code>PS256</code> - RSASSA-PSS using SHA-256</li> <li>▪ <code>PS384</code> - RSASSA-PSS using SHA-384</li> <li>▪ <code>PS512</code> - RSASSA-PSS using SHA-512</li> </ul> <p>Default value is <code>RS256</code>.</p>  |
| <code>authorizationResponseEncryptionAlgorithm</code> | <p>The JWE encryption algorithm used to encrypt the content-encryption key of JARM authorization responses.</p> <p>This parameter is optional.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ <code>dir</code> - Direct Encryption with symmetric key</li> <li>▪ <code>A128KW</code> - AES-128 Key Wrap</li> <li>▪ <code>A192KW</code> - AES-192 Key Wrap</li> <li>▪ <code>A256KW</code> - AES-256 Key Wrap</li> <li>▪ <code>A128GCMKW</code> - AES-GCM-128 key encryption</li> <li>▪ <code>A192GCMKW</code> - AES-GCM-192 key encryption</li> <li>▪ <code>A256GCMKW</code> - AES-GCM-256 key encryption</li> <li>▪ <code>ECDH-ES</code> - ECDH-ES</li> <li>▪ <code>ECDH-ES+A128KW</code> - ECDH-ES with AES-128 Key Wrap</li> <li>▪ <code>ECDH-ES+A192KW</code> - ECDH-ES with AES-192 Key Wrap</li> <li>▪ <code>ECDH-ES+A256KW</code> - ECDH-ES with AES-256 Key Wrap</li> <li>▪ <code>RSA-OAEP</code> - RSAES-OAEP</li> <li>▪ <code>RSA-OAEP-256</code> - RSAES OAEP using SHA-256 and MGF1 with SHA-256</li> </ul> <p>For asymmetric algorithms, a JWKS or the HTTPS URL of a JWKS endpoint is required.</p> <p>For symmetric algorithms, the reversible secret is required.</p> |

| Parameter  | Description  |
|--|--|
| <b>authorizationResponseContentEncryptionAlgorithm</b> | <p>The JWE content encryption algorithm for JARM authorization responses.</p> <p>This parameter's value must be set if the <b>authorizationResponseEncryptionAlgorithm</b> parameter is set.</p> <p>This parameter's value must be null if the <b>authorizationResponseEncryptionAlgorithm</b> parameter is not set.</p> <p>PingFederate accepts the following values:</p> <ul style="list-style-type: none"> <li>▪ AES_128_CBC_HMAC_SHA_256</li> <li>▪ AES_192_CBC_HMAC_SHA_384</li> <li>▪ AES_256_CBC_HMAC_SHA_512</li> <li>▪ AES_128_GCM</li> <li>▪ AES_192_GCM</li> <li>▪ AES_256_GCM</li> </ul>   |
| <b>extendedParameters</b>                              | <p>Provide values for extended client metadata fields.</p> <pre> {   ...,   "extendedParams": {     "entry": [       {         "key": "ContactName",         "value": {           "elements": "J. Smith"         }       },       {         "key": "ContactNumbers",         "value": {           "elements": [             "555-123-4567",             "555-987-6543"           ]         }       }     ]   } }, ... } </pre> <p>This sample request provides a value for a single-valued client metadata field, <b>ContactName</b>, and multiple values for a multivalued client metadata field, <b>ContactNumbers</b>.</p> <p>Extended client metadata fields are defined on the <b>System # Server # Extended Properties</b> window.</p> |

Sample JSON

```
{
```

```

"client": [
  {
    "secret":
"L1u508MfeZYTvr03kcpa6ezysNEspFEtzxSAIEOTl18AuNd2pnNqjkRdOXzfTFXc",
    "clientId": "SampleClient",
    "description": "This is a sample client.",
    "grantTypes": [
      "refresh_token",
      "authorization_code"
    ],
    "name": "Sample Client",
    "redirectUris": [
      "https://www.example.com/redirect1",
      "https://www.example.com/redirect2"
    ]
  }
]
}

```

#### Return codes

- 200 – Success
- 400 – Failed To Create Client
 

The response contains details as to why the client creation failed.
- 401 – Invalid Credentials
 

The user does not exist or is not authorized to create a client.
- 500 – Internal Server Error
 

An unknown error has occurred.

#### PUT

Updates client details for a specified client.

##### Note:

You cannot update a client ID value. You can delete the client record and create a new one with a new client ID value.

#### JSON Parameters

The same parameters described for [POST](#) apply for PUT with one addition: **forceSecretChange**.

Use this parameter, set to `true`, in conjunction with the **secret** parameter to change a client pass phrase.

A valid value is either `true` or `false`.

If this parameter is not provided, a value of `false` is assumed.

##### Note:

If the **secret** parameter is used without a **forceSecretChange** parameter value of `true`, the **secret** value is ignored.



## Sample JSON

```
{
  "client": [
    {
      "secret":
"L1lu508MfeZYTvrR03kcpa6ezysNEspFEtzxSAIEOT118AuNd2pnNgjkRdOXzfTFXc",
      "forceSecretChange": "true",
      "clientId": "SampleClient",
      "description": "This is a sample client.",
      "grantTypes": [
        "refresh_token",
        "authorization_code"
      ],
      "name": "Sample Client",
      "redirectUris": [
        "https://www.example.com/redirectOne",
        "https://www.example.com/redirectTwo"
      ]
    }
  ]
}
```

### Return codes

- 200 – Success  
The body contains a list of updated clients.
- 400 – Failed To Update Client  
The response contains details as to why the client could not be updated.
- 401 – Invalid Credentials  
The user does not exist or is not authorized to update a client.
- 500 – Internal Server Error  
An unknown error has occurred.

## GET

Retrieves details for all OAuth clients.

### JSON Parameters

None.

### Return codes

- 200 – Success  
The body contains JSON data for all clients.



#### Note:

The parameter **refreshRolling** is not returned if the AS global setting is set for a client (the default).

- 400 – Failed To Retrieve Clients  
The response contains details as to why clients could not be retrieved.

- 401 – Invalid Credentials  
The user does not exist or is not authorized.
- 500 – Internal Server Error  
An unknown error has occurred.

Endpoint: `/pf-ws/rest/oauth/clients/<clientId>`

This resource accepts the [GET](#) and [DELETE](#) methods.

## GET

Retrieves details for the specified client ID.

### JSON Parameters

None.

### Return codes

- 200 – Success  
JSON client parameters are included.



#### Note:

The parameter **refreshRolling** is not returned if the AS global setting is set for a client, the default setting.

- 400 – Failed To Retrieve Client  
The response contains details as to why client could not be retrieved.
- 401 – Invalid Credentials  
The user does not exist or is not authorized.
- 500 – Internal Server Error  
An unknown error has occurred.

## DELETE

Deletes records for the specified client ID.

### JSON Parameters

None.

### Return codes

- 200 – Success
- 400 – Failed To Delete Client  
The response contains details as to why client could not be deleted.
- 401 – Invalid Credentials  
The user does not exist or is not authorized.
- 405 – Method Not Allowed  
The client ID was not specified.

- 500 – Internal Server Error  
An unknown error has occurred.

### Logging

records the actions performed through this endpoint in the `runtime-api.log` file. While the events themselves are not configurable, you can adjust the `log4j2.xml` configuration settings to alter the format and desired level of detail surrounding each event.

Each log entry contains information relating to the event, including:

- Time the event occurred on the server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of the above fields is separated by a vertical pipe (|) for ease of parsing.

## OAuth Access Grant Management Service

PingFederate includes a REST-based web service to manage OAuth persistent grants administratively.

The OAuth access grant management service enables retrieval and revocation of persistent grants and their associated extended attribute names and values, if any, on a per-client or per-resource owner basis.



### Important:

Client records must be stored in an external client data store.



### Note:

Applications must authenticate to this web service using HTTP Basic authentication and credentials validated through an instance of a Password Credential Validator (PCV). The PCV instance, in turn, must be selected in the OAuth authorization server (AS) configuration.

### Endpoints

#### Manage by client



```
/pf-ws/rest/oauth/clients/<clientId>/grants[/<grantId>]
```

#### Manage by user (based on the USER\_KEY value)

```
/pf-ws/rest/oauth/users/<userKey>/grants[/<grantId>]
```

Both REST resources accept the GET, for retrieval methods, and DELETE, for revocation methods. The results are formatted in JSON.

### Parameters

| Parameter                    | Description  |
|------------------------------|--|
| <b>clientId</b>              | The client ID for which to retrieve or revoke grants.<br>Required to manage grants for a specific client.  |
| <b>userKey</b>               | The <b>USER_KEY</b> value for which to retrieve or revoke grants.<br>Required to manage grants for a specific resource owner.<br><br><div data-bbox="574 422 1451 659" style="border: 1px solid black; padding: 5px;"> <p> <b>Tip:</b></p> <p>The <b>USER_KEY</b> value varies, depending on its fulfillment based on the mapping configuration defined in the <b>IdP Adapter Grant Mapping</b>, <b>Authentication Policy Contract Mapping</b>, or <b>Resource Owner Credentials Grant Mapping</b> tabs.</p> </div>   |
| <b>grantId</b><br>(Optional) | The persistent grant identifier for which to retrieve or revoke a specific grant.<br><br>The value corresponds to the value of the <b>id</b> field found in the JSON array of grants returned from a previous <code>GET /oauth/clients/&lt;clientId&gt;/grants</code> or <code>GET /oauth/users/&lt;userKey&gt;/grants</code> request.<br><br><div data-bbox="574 905 1451 1079" style="border: 1px solid black; padding: 5px;"> <p> <b>Note:</b></p> <p>If this parameter is not specified, the request applies to all grants for the client or user.</p> </div> |

### Cross Site Request Forgery Protection

Both endpoints require the **X-XSRF-HEADER** HTTP Header with any value to prevent cross site request forgery.

#### Example 1

##### Sample request

A request to retrieve all grants for client with an ID value of `ac_client`. Note that this client is configured with **Allowed Grant Types** values of **Authorization Code** and **Refresh Token**.

```
GET /pf-ws/rest/oauth/clients/ac_client/grants HTTP/1.1
Host: localhost:9031
Authorization: Basic YWRtaW46MkZlZGVyYXRl
X-XSRF-HEADER: PingFederate
```

##### Sample response

```
{
  "items": [
    {
      "id": "ixqWL3k9ZnPxjTaphcFLrVqwdrtvc6tV",
      "userKey": "asmith",
      "grantType": "AUTHORIZATION_CODE",
      "scopes": [],
    }
  ]
}
```

```

    "clientId": "ac_client",
    "issued": "2019-03-15T20:00:27.343Z",
    "updated": "2019-03-15T20:00:27.343Z",
    "grantAttributes": [
      {
        "name": "pgeaAttrMulti",
        "values": [
          "CN=group1,OU=Resources,DC=example,DC=local",
          "CN=group2,OU=Resources,DC=example,DC=local"
        ]
      },
      {
        "name": "pgeaAttrSingle",
        "values": [
          "asmith@example.local"
        ]
      }
    ]
  }
]
}

```

## Example 2

### Sample request

A request to retrieve all grants for client with an ID value of `im_client`. This client is configured with an **Allowed Grant Types** value of **Implicit**, and PingFederate is configured to reuse existing persistent access grants for the implicit grant type on the **System # OAuth Settings # Authorization Server Settings** window.

```

GET /pf-ws/rest/oauth/clients/im_client/grants HTTP/1.1
Host: localhost:9031
Authorization: Basic YWRtaW46MkZlZGVyYXRl
X-XSRF-HEADER: PingFederate

```

### Sample response

```

{
  "items": [
    {
      "id": "G7fv0HVALkplTl1Hdw109DYz1LNPXXIt",
      "userKey": "asmith",
      "grantType": "IMPLICIT",
      "scopes": [],
      "clientId": "im_client",
      "issued": "2019-03-15T18:20:39.652Z",
      "updated": "2019-03-15T18:20:39.652Z"
    }
  ]
}

```

For more information about persistent grants and their relationship with various grant types, see [Transient grants and persistent grants](#) on page 88.

Return codes

- 200 – Success
- 204 – Success with no content returned  
Returned when revoking a persistent grant.
- 401 – Invalid Credentials  
The user does not exist, the password is incorrect, or the user account is locked.
- 404 – Not Found  
Returned when the requested persistent grant or client is not found.
- 500 – Internal Server Error  
An unknown error has occurred.

### Logging

records the actions performed through this endpoint in the `runtime-api.log` file. While the events themselves are not configurable, you can adjust the `log4j2.xml` configuration settings to alter the format and desired level of detail surrounding each event.

Each log entry contains information relating to the event, including:

- Time the event occurred on the server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of the above fields is separated by a vertical pipe (|) for ease of parsing.

## OAuth Persistent Grant Management API

This REST-based runtime API facilitates the use case where clients can assume the responsibility of grant management if the users authorize the clients to do so.

In this scenario, a client prompts the user to approve a specific scope for managing persistent grants on the user's behalf. If the user approves, the client requests an access token with such scope from PingFederate. As long as the access token remains valid, the client can retrieve and revoke persistent grants and their associated extended attribute names and values, if any, for that user.

The activation of the Persistent Grant Management API requires two settings: the scope required to perform this task and the Access Token Management instance under which the access tokens issued can be used by clients to manage persistent grants. You can find both settings from the System tab on the **System # OAuth Settings # Authorization Server Settings** window. Additionally, clients that are capable of managing grants on their users' behalf must be configured to use the selected Access Token Management instance in their client records.



#### Note:

To use this runtime API, clients must authenticate by presenting a valid access token with the required scope. The token is presented as a bearer token through the HTTP Bearer authentication scheme.



#### Tip:

Not all OAuth use cases involve persistent grants. For more information, see [Transient grants and persistent grants](#) on page 88.

Endpoint: `/pf-ws/rest/oauth/grants/<grantId>`

This REST resource accepts the GET for retrieval methods, and DELETE for revocation methods. The results are formatted in JSON.

Parameter

| Parameter            | Description   |
|----------------------|---|
| <code>grantId</code> | The persistent grant identifier to retrieve or revoke a specific grant.<br>The value corresponds to the value of the <code>id</code> field found in the JSON array of grants returned by a previous GET request from this endpoint. |

Cross Site Request Forgery Protection

This endpoint requires the **X-XSRF-HEADER** HTTP Header with any value to prevent cross-site request forgery.

Sample request

A request to retrieve all grants.

```
GET /pf-ws/rest/oauth/grants/ HTTP/1.1
Host: localhost:9031
Authorization: Bearer eyJhbG...IKqMfg
X-XSRF-HEADER: PingFederate
```

In this example, the client prompted the resource owner (Joe) to authorize it to manage persistent grants on his behalf. Joe agreed and approved the requested `adminscope`. The client then obtained an access token with the scope from PingFederate. The issued access token is a self-contained JSON web token (JWT).

This sample request illustrates a GET request from the client. The client wants to retrieve a list of grants associated with Joe by presenting the access token to the Persistent Grant Management API for authentication. The access token is truncated for readability.

Sample response

```
{
  "items": [
    {
      "id": "5a4nszZOppgo9RfRtrVXNY0Eq5ka1YZ6",
      "userKey": "joe",
      "grantType": "RESOURCE_OWNER_CREDENTIALS",
      "scopes": [
        "phone"
      ],
      "clientId": "ro_client",
      "issued": "2018-12-15T00:54:30.190Z",
      "updated": "2018-12-15T00:54:30.190Z"
    },
    {
      "id": "PTfURLoaXC97JXU6uilaORSkFQoMOLyV",
      "userKey": "joe",
      "grantType": "AUTHORIZATION_CODE",
```

```

    "scopes": [
      "openid",
      "profile",
      "admin"
    ],
    "clientId": "ac_oic_client",
    "issued": "2018-12-15T18:29:26.018Z",
    "updated": "2018-12-15T18:29:26.018Z"
  },
  {
    "id": "k1oFbxujlGHbfEBfVqDj0aID1lFBzghX",
    "userKey": "joe",
    "grantType": "AUTHORIZATION_CODE",
    "scopes": [
      "openid",
      "email",
      "phone"
    ],
    "clientId": "ac_oic_client",
    "issued": "2018-12-15T19:03:29.439Z",
    "updated": "2018-12-15T19:03:29.439Z"
  },
  {
    "id": "EhzZYggNuFT9EWpw9p21SYCddwAPFAKR",
    "userKey": "joe",
    "grantType": "IMPLICIT",
    "scopes": [
      "openid",
      "profile"
    ],
    "clientId": "im_oic_client",
    "issued": "2018-12-15T19:04:05.044Z",
    "updated": "2018-12-15T19:04:05.044Z"
  }
]
}

```

In this example, PingFederate returned four persistent grants associated with the resource owner from three clients.

#### Return codes

- 200 – Success
- 204 – Success with no content returned  
Returned when revoking a persistent grant.
- 401 – Invalid Credentials  
The access token is invalid (including the lack of the required scope) or missing.
- 404 – Not Found  
Returned when the requested persistent grant is not found or a grant ID is missing.
- 500 – Internal Server Error  
An unknown error has occurred.

#### Logging

records the actions performed through this endpoint in the `runtime-api.log` file. While the events themselves are not configurable, you can adjust the `log4j2.xml` configuration settings to alter the format and desired level of detail surrounding each event.



Each log entry contains information relating to the event, including:

- Time the event occurred on the server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of the above fields is separated by a vertical pipe (|) for ease of parsing.

## Session Management API by session identifiers

The runtime session management API lets OAuth clients get information about user sessions, extend sessions, revoke sessions, and delete sessions. Knowing the remaining lifetime of a valid session could, for example, let an application prompt the user to extend the session.

An OAuth client can take the pi.sri session identifier from its access token and send it to the session management API in an HTTP GET request. An OAuth client can also send the pi.sri to the session management API in an HTTP POST request to extend or revoke the sessions. The API returns information in JSON format about each session associated with the pi.sri, including:

- Last activity time
- Idle and maximum timeout time
- Authentication source that created the session
- Context data
  - IP address
  - User agent



### Note:

The API response body includes only sessions that were configured with the authentication sessions capability described in [Configuring authentication sessions](#) on page 295.

The session management API works with sessions stored in persistent storage and across clustered nodes. For this API, the runtime APIs audit log only records session revoke events.



### Important:

OAuth clients must authenticate to the API using their configured client authentication method.

To configure PingFederate so that an OAuth client can use the session management API:

- Allow the client to access the session management API, as described in [Configuring OAuth clients](#) on page 566.
- Configure the client's access token manager instance to include a pi.sri in access tokens, as described in [Managing session validation settings](#) on page 612.

## Session management API by session identifiers endpoints

The session management API by session identifiers has three endpoints, which all require the `sri` parameter.

The OpenID Provider configuration endpoint `/.well-known/openid-configuration` provides configuration information for OAuth clients to access the session management API endpoints. For more information, see [OpenID Provider configuration endpoint](#) on page 1186.

The session management API endpoints return several response codes, including:

- 200 OK: The request was successfully processed.
- 400 Bad request: The format of the SRI is invalid.

Endpoint `/pf-ws/rest/sessionMgmt/sessions/{sri}`

Use HTTP GET requests to get information about all sessions associated with the pi.sri specified by the `sri` parameter.

Here is a sample GET request from a client to the `/pf-ws/rest/sessionMgmt/sessions/{sri}` endpoint:

```
GET /pf-ws/rest/sessionMgmt/sessions/qzTEiEroxdzAufjYKQawm72lcBE..4RbA
HTTP/1.1
Host: www.example.com
X-XSRF-Header: PingFederate
Authorization: Basic YWNfY2xpZW50OmdPWdh0NEQ...h3ZjI=
Cookie: PF=K60mOoBlTvWcD4frFzcKF5
```

After receiving a successful request, the endpoint returns a response like one of the following samples, depending on whether the status is `HAS_VALID_SESSIONS`, `NO_VALID_SESSIONS`, or `SESSION_REVOKED`:

- ```
{
  "sri": "qzTEiEroxdzAufjYKQawm72lcBE..4RbA",
  "status": "HAS_VALID_SESSIONS",
  "lastActivityTime": "2020-06-10T17:25:00.461Z",
  "authnSessions": [ // This section can include multiple sessions
    {
      "authnSource": {
        "sourceType": "IDP_CONN",
        "id": "L07d8fse7dslShd6d_20HA8jp6",
        "entityId": "Amazon_Africa_A" // Only for IDP_CONN
      },
      "sourceType": "IDP_CONN",
      "id": "ba5a3d97afee5ef9450b710ff932680e3579dc7f",
      "creationTime": "2020-06-10T17:25:00.454Z",
      "idleTimeout": "2020-06-10T18:25:00.461Z",
      "maxTimeout": "2020-06-11T01:25:00.461Z"
    },
    {
      "authnSource": {
        "sourceType": "ADAPTER",
        "id": "HtmlFormAdapter",
        "adapterType": "HTML Form IdP Adapter" // Only for
      },
      "sourceType": "ADAPTER",
      "id": "7cbef5022be8d841f14a95ace8987cbb34c77a21",
      "creationTime": "2020-06-10T17:25:00.454Z",
      "idleTimeout": "2020-06-10T18:25:00.461Z",
      "maxTimeout": "2020-06-11T01:25:00.461Z"
    }
  ],
  "contextData": {
    "ipAddress": "127.0.0.1",
    "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X
10_15_7) AppleWebKit/537.36 (KHTML, like Gecko) Chrome/94.0.4606.81
Safari/537.36"
  }
}
```

- ```

}

```
- ```

{
  "sri": "qzTEiEroxdzAufjYKQawm72lcBE..4RbA",
  "status": "NO_VALID_SESSIONS",
}

```
  - ```

{
  "sri": "qzTEiEroxdzAufjYKQawm72lcBE..4RbA",
  "status": "SESSION_REVOKED",
}

```

Endpoint `/pf-ws/rest/sessionMgmt/sessions/{sri}/extend`

Use HTTP POST requests to extend the `idleTimeout` value of all sessions associated with the `pi.sri` specified by the `sri` parameter.

Here is a sample POST request from a client to the `/pf-ws/rest/sessionMgmt/sessions/{sri}/extend` endpoint:

```

POST /pf-ws/rest/sessionMgmt/sessions/qzTEiEroxdzAufjYKQawm72lcBE..4RbA/
extend HTTP/1.1
Host: www.example.com
X-XSRF-Header: PingFederate
Authorization: Basic YWNfY2xpZW50OmdPwDh0NEQ...h3ZjI=
Cookie: PF=K60mOoBlTvWcD4frFzcKF5

```

After receiving a successful request, the endpoint returns a response like the following sample:

```

{
  "sri": "Y9tTHRVD7s55Vn2hrrVxWgRD44..aHbY.tEXnpsf6V1YGT3OWMNWxZjp2m",
  "status": "HAS_VALID_SESSIONS",
  "lastActivityTime": "2021-10-14T18:29:00.195Z",
  "authnSessions": [
    {
      "authnSource": {
        "sourceType": "ADAPTER",
        "id": "CIAMHtml",
        "adapterType": "HTML Form IdP Adapter"
      },
      "id": "8e95ab8600d71a6091af61d54b75ddefb9270c2c",
      "creationTime": "2021-10-14T18:28:47.205Z",
      "idleTimeout": "2021-10-14T19:29:00.195Z",
      "maxTimeout": "2021-10-15T02:28:47.205Z"
    }
  ]
  "contextData": {
    "ipAddress": "127.0.0.1",
    "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X 10_15_7)
AppleWebKit/537.36 (KHTML, like Gecko) Chrome/94.0.4606.81 Safari/537.36"
  }
}

```

Endpoint `/pf-ws/rest/sessionMgmt/sessions/{sri}/revoke`

Use HTTP POST requests to revoke all sessions associated with the `pi.sri` specified by the `sri` parameter.

Here is a sample POST request from a client to the `/pf-ws/rest/sessionMgmt/sessions/{sri}/revoke` endpoint:

```
POST /pf-ws/rest/sessionMgmt/sessions/qzTEiEroxdzAufjYKQawm72lcBE..4RbA/
revoke HTTP/1.1
Host: www.example.com
X-XSRF-Header: PingFederate
Authorization: Basic YWNfY2xpZW50OmdPWDh0NEQ...h3ZjI=
Cookie: PF=K60mOoBlTvWcD4frFzcKF5
```

After receiving a successful request, the endpoint returns a response like the following sample:

```
{
  "sri": "qzTEiEroxdzAufjYKQawm72lcBE..4RbA",
  "status": "SESSION_REVOKED",
}
```

Endpoint `/pf-ws/rest/sessionMgmt/sessions/{sri}/authnSessions/{id}`

Use HTTP DELETE requests to remove an authentication session with the specified `id` parameter from the sessions associated with the `pi.sri` specified by the `sri` parameter.

Here is a sample DELETE request from a client to the `/pf-ws/rest/sessionMgmt/sessions/{sri}/authnSessions/{id}` endpoint:

```
DELETE /pf-ws/rest/sessionMgmt/sessions/qzTEiEroxdzAufjYKQawm72lcBE..4RbA/
authnSessions/ba5a3d97afee5ef9450b710ff932680e3579dc7f HTTP/1.1
Host: www.example.com
X-XSRF-Header: PingFederate
Authorization: Basic YWNfY2xpZW50OmdPWDh0NEQ...h3ZjI=
Cookie: PF=K60mOoBlTvWcD4frFzcKF5
```

After receiving a successful request, the endpoint returns an HTTP status of 204 No Content.

## Session Management API by user identifiers

OAuth applications can send a user identifier to the Session Management API endpoint to query or revoke authentication sessions belonging to the end-user.



### Note:

- **Allow Access to Session Management API** must be enabled on an OAuth client to allow the client to access this session management API by user identifier.
- Adapters must be configured with a Unique User Key Attribute, as described in [Setting pseudonym and masking options](#) on page 423.
- The `user_key` specified in the session management API request must match the value of the Unique User Key Attribute determined at runtime.
- This API is different than the other session management APIs in that it only returns currently valid sessions (status = HAS\_VALID\_SESSIONS). Revoked sessions (SESSION\_REVOKED) or users without any sessions (NO\_VALID\_SESSIONS) will not be seen from this API.
- The `user_key` parameter needs to be URL encoded (`@` is encoded as `%40`) since the value appears as a query parameter in the URL.

Applications can query or revoke user sessions based on user identifiers. The bulk revocation capability provides a convenient way to expire server-side authentication sessions on a per-user basis if needed. When revoked and without valid credentials, such end-users will not be able to fulfill authentication requirements and access protected resources.

An OAuth client needs to obtain a user identifier and send it to the session management API in an HTTP GET or POST request. If the client is configured to obtain an access token, an ID token, or a User Info response, it could potentially get the user identifier that way. However, if the client is not configured to obtain one of these items, or if none of them delivers the applicable user identifier, the client can still use this endpoint by sending a user identifier. For example, an application for the help desk to query or revoke all authentication sessions for a given user falls into this category. In this example, the developer will build an application to prompt the help desk staff to provide a user identifier, which becomes the **user\_key** parameter value, send a GET or POST request to the session management API endpoint, and display the result of the request.

The API returns information in JSON format about each session associated with the user, such as:

- SRI
- Status
- Last activity time
- Authentication sessions
  - Authentication Source
  - ID of the per-authentication source session information
  - Creation time
  - Idle and maximum timeout
- Context data
  - IP address
  - User agent



**Note:**

The API response body includes only sessions that were configured with the authentication sessions capability described in [Configuring authentication sessions](#) on page 295.

An OAuth client can also send the user identifier to the session management API in an HTTP POST request to revoke the sessions.

The session management API works with sessions stored in persistent storage and across clustered nodes. For this API, the runtime API's audit log only records session revoke events.



**Important:**

OAuth clients must authenticate to the API using their configured client authentication method.

To configure PingFederate so that an OAuth client can use the session management API, allow the client to access the session management API, as described in [Configuring OAuth clients](#) on page 566

#### Session management API by user identifier endpoints

The session management API by user identifiers has one endpoint, which requires the **user\_key** parameter.

The OpenID Provider configuration endpoint `/.well-known/openid-configuration` provides configuration information for OAuth clients to access the session management API endpoints. For more information, see [OpenID Provider configuration endpoint](#) on page 1186.

Endpoint `/pf-ws/rest/sessionMgmt/users/{user_key}`

Use HTTP GET requests to get information about all sessions associated with the user specified by the **user\_key** parameter.

**Sample request:**

```
GET /pf-ws/rest/sessionMgmt/users/john%40test.com-east HTTP/1.1
```

**Sample response**

```
{
  "sri": "qzTEiEroxdzAufjYKQawm72lcBE..4RbA",
  "status": "HAS_VALID_SESSIONS",
  "lastActivityTime": "2020-06-10T17:25:00.461Z",
  "authnSessions": [ // This section can include multiple sessions
    {
      "authnSource": {
        "sourceType": "IDP_CONN",
        "id": "L07d8fse7ds1Shd6d_20HA8jP6",
        "entityId": "Amazon_Africa_A" // Only for IDP_CONN
      },
      sourceType sessions
    },
    {
      "id": "ba5a3d97afee5ef9450b710ff932680e3579dc7f",
      "creationTime": "2020-06-10T17:25:00.454Z",
      "idleTimeout": "2020-06-10T18:25:00.461Z",
      "maxTimeout": "2020-06-11T01:25:00.461Z"
    },
    {
      "authnSource": {
        "sourceType": "ADAPTER",
        "id": "HtmlFormAdapter",
        "adapterType": "HTML Form IdP Adapter" // Only for ADAPTER
      },
      sourceType sessions
    },
    {
      "id": "7cbef5022be8d841f14a95ace8987cbb34c77a21",
      "creationTime": "2020-06-10T17:25:00.454Z",
      "idleTimeout": "2020-06-10T18:25:00.461Z",
      "maxTimeout": "2020-06-11T01:25:00.461Z"
    }
  ],
  "contextData": {
    "ipAddress": "127.0.0.1",
    "userAgent": "Mozilla/5.0 (Macintosh; Intel Mac OS X 10_15_7)
AppleWebKit/537.36 (KHTML, like Gecko) Chrome/94.0.4606.81 Safari/537.36"
  }
}
```

**Endpoint /pf-ws/rest/sessionMgmt/users/{user\_key}/revoke**

Use HTTP POST requests to revoke all PingFederate runtime authentication sessions that are associated with the given user identifier **user\_key**. After running this request, any revoked sessions will be logged with an event as "SRI\_REVOKED" in the audit log.

**Sample request:**

```
POST /pf-ws/rest/sessionMgmt/users/john%40test.com-east/revoke HTTP/1.1
Host: www.example.com
X-XSRF-Header: PingFederate
Authorization: Basic YWNfyY2xpZW50OmdPwDh0NEQ...h3ZjI=
Cookie: PF=K60mOoBlTvWcD4frFzcKF5
```

**Return codes:**

- 200 OK: The request was successfully processed
- 503 Service Unavailable: An error occurred while deleting stored sessions

**Note:**

You can optionally use the endpoints described in [Session Management API by session identifiers](#) on page 1233 if needed.

## Session Revocation API endpoint

PingFederate includes a REST-based web service for back-channel session revocation.

This service enables OAuth clients to add sessions to the revocation list or to query their revocation status. This endpoint is not part of the OAuth specification. You must select the **Allow Access to Session Revocation API** check box in the configuration for the applicable clients. This endpoint is a URL path extension of the PingFederate runtime endpoint. For example, <https://www.example.com:9031/pf-ws/rest/sessionMgmt/revokedSris>.

**Important:**

OAuth clients must authenticate to the web service using their configured client authentication method. For more information about OAuth client authentication methods, see [Configuring OAuth clients](#) on page 566.

**Note:**

If clients are allowed to add sessions to the revocation list, you can enable the **Check session revocation status** option in the applicable Access Token Management instances for the token validation process to consider whether a session has been added to the revocation list. For more information, see [Managing session validation settings](#) on page 612.

Endpoint: `/pf-ws/rest/sessionMgmt/revokedSris`

This resource accepts the [POST](#) and [GET](#) methods. It also requires the **X-XSRF-HEADER** HTTP header with any value to prevent cross site request forgery.

**Note:**

The POST method described in this section requires the element name/value pair formatted in JSON.

**Tip:**

You can find information about the Session Revocation API endpoint in the OpenID Provider Configuration endpoint metadata: `ping_revoked_sris_endpoint`.

### POST

A POST request adds a session to the revocation list based on its session identifier, `id`, in the POST data. The ID value corresponds to that of the `pi.sri` element in the ID token. The required **Content-Type** is `application/json`.

#### Sample request

A POST request to add a session with a session identifier of abc123 to the revocation list.

```
POST /pf-ws/rest/sessionMgmt/revokedSris
Host: localhost:9031
```

```
Authorization: Basic
YWNfb2ljX2NsaWVudDphYmMxMjNERUZnaGlqa2xtbm9wNDU2N3JzdHV2d3h5elpZWVdVVDg5MTBTU1
X-XSRF-HEADER: PingFederate
Content-Type: application/json

{"id": "abc123"}
```

#### Return codes

- 201 – Created
  - The session is added to the revocation list.
- 400 – Bad Request
  - The **x-xsrf-header** HTTP header is not found in the HTTP POST request.
- 401 – Unauthorized
  - The response contains details as to why the attempt failed.
- 415 – Unsupported Media Type
  - The **Content-Type: application/json** HTTP header is not found in the HTTP POST request.
- 500 – Internal Server Error
  - An unknown error has occurred.

#### GET

A GET request sends a query for the revocation status for a session with its session identifier, `id`, appended to the endpoint. The ID value corresponds to that of `pi.sri` in the ID token.

#### Sample request

A GET request to query the revocation status for a session with a session identifier of `abc123`.

```
GET /pf-ws/rest/sessionMgmt/revokedSris/abc123
Host: localhost:9031
Authorization: Basic
YWNfb2ljX2NsaWVudDphYmMxMjNERUZnaGlqa2xtbm9wNDU2N3JzdHV2d3h5elpZWVdVVDg5MTBTU1
X-XSRF-HEADER: PingFederate
```

If PingFederate authentication sessions are enabled, querying a valid session also extends the session lifetime by the time value specified in the global **Idle Timeout** field or the idle timeout override for the authentication source associated with the session. The latter takes precedence. For externally stored authentication sessions, this operation is optimized to only send updates to the external storage when the remaining idle timeout window is less than 75%.

Alternatively, include the optional **updateActivityTime** query parameter and set the value to `false` in the request to query the status of a session without extending its lifetime.

#### Example

```
GET /pf-ws/rest/sessionMgmt/revokedSris/abc123?updateActivityTime=false
Host: localhost:9031
Authorization: Basic
YWNfb2ljX2NsaWVudDphYmMxMjNERUZnaGlqa2xtbm9wNDU2N3JzdHV2d3h5elpZWVdVVDg5MTBTU1FQT25tbG
X-XSRF-HEADER: PingFederate
```

#### Return codes



- 200 – OK
  - `{"id": "abc123"}` is found in the revocation list.
- 400 – Bad Request
  - The **X-XSRF-HEADER** HTTP header is not found in the HTTP POST request.
- 401 – Unauthorized
  - The response contains details as to why the attempt failed.
- 404 – Not Found
  - `{"resultId": "session_mgmt_sri_not_revoked", "message": "The SRI has not been revoked."}` if the session is not found in the revocation list. If PingFederate is configured to manage authentication sessions and the request does not come with the `updateActivityTime=false` query parameter, the session is extended as well.
- 500 – Internal Server Error
  - An unknown error has occurred.

### Logging

records the actions performed through this endpoint in the `runtime-api.log` file. While the events themselves are not configurable, you can adjust the `log4j2.xml` configuration settings to alter the format and desired level of detail surrounding each event.

Each log entry contains information relating to the event, including:

- Time the event occurred on the server
- Administrator username performing the action
- Authentication method
- Client IP
- HTTP method
- REST endpoint
- HTTP status code

Each of the above fields is separated by a vertical pipe (|) for ease of parsing.

### PingFederate administrative API

PingFederate includes a REST-based API for administrative functions. The administrative API provides a programmatic way to make configuration changes to PingFederate as an alternative to using the administrative console.

The configuration changes that you can make through the administrative API include, but are not limited to:

- Adapters and connections
- Authentication policy contracts
- Cluster management
- Data stores and password credential validators
- Keys and certificates
- License management
- Local administrative account management
- OAuth settings
- Server settings

For a complete list, see [Accessing the API interactive documentation](#) on page 1248. For known limitations, see Release notes.

## Initial setup using the administrative API

After installing PingFederate you can make four unauthenticated administrative API requests to perform the following tasks:

1. A GET request to `/license/agreement` to retrieve a URL to the license agreement.
2. A PUT request to `/license/agreement` to accept the license agreement.
3. A PUT request to `/license` to import a license file.
4. A POST request to `/administrativeAccounts` to create the first local administrative account, for native authentication.

You must assign the User Admin administrative role, `USER_ADMINISTRATOR`, to the first local administrative account. Other administrative roles are optional at this point. For more information, see the interactive documentation for the administrative API [Accessing the API interactive documentation](#) on page 1248.

After the first local administrative account is created, you can make other authenticated administrative API requests to configure various components in PingFederate.

## Authentication and authorization

Similar to the administrative console, access to the administrative API is protected after initial setup. The administrative API supports various authentication and authorization options. For more information, see [Configure access to the administrative API](#).

## Concurrent access

The administrative API supports concurrent access. When concurrent API calls are made to modify the same API resource, such as the IdP adapter instance or the SP connection, PingFederate processes the last request made.

## Logging

PingFederate records actions performed through the administrative API in the `admin-api.log` file. Information includes the time of the event, the action performed, the authentication method, and other fields. For more information, see [Administrative API audit log](#).

## Configure access to the administrative API

Similar to the administrative console, access to the administrative API after initial setup might be protected by several authentication and authorization schemes.

Access to the administrative API after initial setup is protected by one of the following authentication and authorization schemes:

- Native authentication, against local administrative accounts
- LDAP authentication
- RADIUS authentication
- Mutual TLS client certificate-based authentication
- OAuth 2.0 authorization


For new installations, native authentication is the default.

For upgrades, if the authentication or authorization method of the administrative API was not previously set, such as when upgrading from PingFederate 7.3 or an earlier version, the Upgrade Utility sets the value to that of the administrative console. Otherwise, it preserves the previously set value, such as when upgrading from PingFederate 8.0 to a future release.

The authentication or authorization method for the administrative API can change at a later time to any of the choices, regardless of which authentication or authorization method is chosen for the administrative console.

Besides authentication and authorization, PingFederate also provides role-based access control, as shown in the following table. The roles assigned to the accounts affect the results of the API calls.

### User Access Control

| Account type  | Administrative role | Access privileges  |
|---|---------------------|--|
| Admin   | User Admin          | Create users, deactivate users, change or reset passwords, and install replacement license keys.   |
| Admin   | Admin               | Configure partner connections and most system settings, except the management of local accounts and the handling of local keys and certificates. |
| Admin   | Expression Admin    | Map user attributes by using the expression language, Object-Graph Navigation Language (OGNL).   |
| <div style="border: 1px solid black; padding: 10px;"> <p> <b>Important:</b></p> <p>Only Administrative users who have both the Admin role and the Expression Admin role:</p> <ul style="list-style-type: none"> <li>▪ Can be granted the User Admin role. This restriction prevents non-Expression Admin users from granting themselves the Expression Admin Role.</li> <li>▪ Can be granted write access to the file system or directory where is installed. This restriction prevents a non-Expression Admin user from placing a <code>data.zip</code> file containing expressions into the <code>&lt;pf_install&gt;/pingfederate/server/default/deploy</code> directory, which would introduce expressions into .</li> </ul> </div> |                     |  |
| Admin   | Crypto Admin        | Manage local keys and certificates.  |
| Auditor   | Not applicable      | View-only permissions for all administrative functions. When the <b>Auditor</b> role is assigned, no other administrative roles can be set.      |

#### Note:

All four administrative roles are required to access and make changes through the following services:

- The `/bulk`, `/configArchive`, and `/configStore` administrative API endpoints
- The **Configuration Archive** window, accessed from **System # Server**, in the administrative console
- The **Connection Management** configuration item on the **Service Authentication** window, accessed from **Security # System Integration**

### Enabling native authentication for the administrative API

When the administrative API is protected by native authentication, access to the administrative API is restricted to the users defined in the **Account Management** window.

#### About this task

The API calls must be authenticated by valid credentials over HTTP Basic authentication; otherwise, the administrative API returns an error message. The roles assigned to the users affect the results of the API calls.

## Steps

1. Verify the `pf.admin.api.authentication` value in `<pf_install>/pingfederate/bin/run.properties` is set to `native`. Update as needed and restart PingFederate to activate this change.



### Note:

In a clustered PingFederate environment, you only need to modify `run.properties` on the console node.

2. Sign on to the administrative console with an account that has the User Admin role.



### Important:

When the administrative console is protected by an alternative console authentication, such as certificate-based, LDAP, or RADIUS authentication, most user-management functions are handled outside the scope of the PingFederate administrative console. Therefore, the administrative console disables the functionality of the **System # Server # Administrative Accounts** window unless the logged-on administrator has been granted User Admin permissions.

To create or manage users in this scenario, add at least one external account to the role setting `userAdmin` in the configuration file for the respective authentication method. When the administrator logs on to the administrative console, the **Administrative Accounts** window becomes available to create or manage users for the purposes of accessing the administrative API.

For more information about the alternative console authentication and the respective configuration, see [Alternative console authentication](#) on page 848.

3. On the **Administrative Accounts** window, create or manage users as needed, and assign various PingFederate administrative roles as indicated by the PingFederate User Access Control table. For more information, see [Configure access to the administrative API](#) on page 1242.



### Note:

When assigning roles, remember that all users defined in the **Administrative Accounts** window can access the administrative API and the administrative console.

## Enabling LDAP authentication

When the administrative API is protected by LDAP authentication, the API calls must be authenticated by valid LDAP credentials over HTTP Basic authentication; otherwise, the administrative API returns an error message.

### About this task

The LDAP authentication setup, including role assignment, is available through `<pf_install>/pingfederate/bin/ldap.properties`. The roles assigned to the LDAP accounts affect the results of the API calls.



### Note:

When you configure LDAP authentication, PingFederate does not lock out accounts based upon the number of failed sign-on attempts. The LDAP server is responsible for preventing access and is enforced according to its password lockout settings.

## Steps

1. Verify the `pf.admin.api.authentication` value in `<pf_install>/pingfederate/bin/run.properties` is set to LDAP. Update as needed.
2. In the `<pf_install>/pingfederate/bin/ldap.properties` file, change property values as needed for your network configuration. For instructions and additional information, see the comments in the file.

### Important:

Remember to assign LDAP users or designated LDAP groups, or both, to at least one of the PingFederate administrative roles, as indicated in the properties file. For information about permissions attached to the PingFederate roles, see the PingFederate User Access Control table in [Configure access to the administrative API](#) on page 1242.

### Note:

When you assign roles, remember that all LDAP accounts specified in `ldap.properties` can access the administrative API and the administrative console.

### Tip:

You can also use this configuration file in conjunction with RADIUS authentication to determine permissions dynamically with an LDAP connection.

3. Restart PingFederate.

### Note:

In a clustered PingFederate environment, you only need to modify `run.properties` and `ldap.properties` on the console node.

## Enabling RADIUS authentication

The RADIUS protocol provides a common approach for implementing strong authentication in a client-server configuration.

### About this task

The RADIUS authentication setup is available through configuration files in the `<pf_install>/pingfederate/bin` directory. The administrative API supports the protocol scenario for one-step authentication, for example, appending a one time password (OTP) after the password.

When RADIUS authentication is protecting the administrative API, the API calls must be authenticated by valid credentials over HTTP Basic authentication. Otherwise, the administrative API returns an error message. The roles assigned to the accounts affect the results of the API calls.

### Note:

When you configure RADIUS authentication, PingFederate does not lock out accounts based upon the number of failed logon attempts. Instead, responsibility for preventing access is delegated to the RADIUS server and enforced according to its password lockout settings.

### Note:

The `NAS-IP-Address` attribute is added to all Access-Request packets sent to the RADIUS server. The value is copied from the `pf.engine.bind.address` property in `run.properties`. Only IPv4 addresses are supported.

### Steps

1. Verify the `pf.admin.api.authentication` value in `<pf_install>/pingfederate/bin/run.properties` is set to `RADIUS`. Update as needed.
2. In the `<pf_install>/pingfederate/bin/radius.properties` file, change property values as needed for your network configuration. For instructions and additional information, see the comments in the file.

#### Important:

Assign RADIUS users or designated RADIUS groups, or both, to at least one of the PingFederate administrative roles as indicated in the properties file. Alternatively, you can set the `use.ldap.roles` property to `true` and use the LDAP properties file, which is also in the `bin` directory, to map LDAP group-based permissions to PingFederate roles. For more information about permissions attached to the PingFederate roles, see the PingFederate User Access Control table in [Configure access to the administrative API](#) on page 1242.

#### Note:

When assigning roles, remember that all accounts specified in `radius.properties` can access the administrative API and the administrative console.

3. Restart PingFederate.

#### Note:

In a clustered PingFederate environment, you only need to modify `run.properties` and `radius.properties` on the console node.

### Enabling certificate-based authentication

When client-certificate authentication is enabled, the API calls must be authenticated by X.509 client certificates; otherwise, the administrative API returns an error message.

#### About this task

In addition to X.509 client certificate authentication, the corresponding root certificate authority (CA) certificates must either be contained in the Java runtime or be imported into the PingFederate's Trusted CA store. For more information, see [Manage trusted certificate authorities](#) on page 657.

The rest of the certificate-based authentication setup, including specifying the Issuer DN of the root CA certificates and the applicable roles of the client certificates, is available through `<pf_install>/pingfederate/bin/cert_auth.properties`. The roles assigned to the certificates affect the results of the API calls.

### Steps

1. Sign on to the administrative console with an account that has the role `Crypto Admin`.

2. Ensure the client-certificate's root CA and any intermediate CA certificates are contained in the trusted store, either for the Java runtime, or PingFederate, or both.

 **Note:**

To import a certificate, click **Trusted CAs** in the Certificate Management section under Server Configuration.

 **Tip:**

Click the Serial number and copy the Issuer distinguished name (DN) to use in a couple steps later.

3. Verify the `pf.admin.api.authentication` value in `<pf_install>/pingfederate/bin/run.properties` is set to `cert`. Update as needed.
4. In the `<pf_install>/pingfederate/bin/cert_auth.properties` file, enter the Issuer DN for the client certificate as a value for the property: `rootca.issuer.<x>`, where `<x>` is a sequential number starting at 1. For more information, see the properties file.

 **Important:**

The configuration values are case-sensitive.

If you copied the Issuer DN a couple steps earlier, paste this value.

5. Repeat the previous step for any additional CAs as needed.
6. Enter the certificate's Subject DN for the applicable PingFederate permission roles, as described in the properties file. For information about permissions attached to the PingFederate roles, see the PingFederate User Access Control table in [Configure access to the administrative API](#) on page 1242.

 **Important:**

The configuration values are case-sensitive.

 **Note:**

When assigning roles, keep in mind that all client certificates specified in `cert_auth.properties` can be used to access the administrative API and the administrative console.

7. Repeat the previous step for all client certificates as needed.
8. Restart PingFederate.

 **Note:**

In a clustered PingFederate environment, you only need to modify `run.properties` and `cert_auth.properties` on the console node.

### Enabling OAuth 2.0 authorization

PingFederate clients can gain access to the administrative API endpoint by providing an OAuth 2.0 access token. The `<pf_install>/pingfederate/bin/oauth2.properties` file contains settings that allow you to configure information required to interact with the authorization server as a client.

#### Steps

1. Set the `pf.admin.api.authentication` value in `<pf_install>/pingfederate/bin/run.properties` to `OAuth2`.
2. In the `<pf_install>/pingfederate/bin/oauth2.properties` file, change property values as needed. For instructions and additional information, see the comments in the file.



#### Important:

Remember to assign at least one of the PingFederate administrative roles, as indicated in the properties file. For information about permissions attached to the PingFederate roles, see the PingFederate User Access Control table in [Configure access to the administrative API](#) on page 1242.

3. Restart PingFederate.



#### Note:

In a clustered PingFederate environment, you only need to modify `run.properties` and `oauth2.properties` on the console node.

### Accessing the API interactive documentation

PingFederate ships with interactive documentation for both developers and non-developers to explore the API endpoints, view documentation for the API, and experiment with API calls.

#### About this task

In general, you can make API calls from an interactive user interface, custom applications, or from command line tools such as cURL. The endpoint is only available at the administrative port, as defined by the `pf.admin.https.port` property in `<pf_install>/pingfederate/bin/run.properties`.



#### Important:

For enhanced API security, you must include `X-XSRF-Header: PingFederate` in all requests and use the `application/json` content type for PUT and POST requests.

To access the administrative API documentation, follow these steps:

#### Steps

1. Start PingFederate.
2. Start a web browser.



3. Browse to the following URL: `https://<pf_host>:9999/pf-admin-api/api-docs/`

**Note:**

`<pf_host>` is the network address of your PingFederate server. It can be an IP address, a host name, or a fully qualified domain name. It must be reachable from your computer.

9999 is the default value of the `pf.admin.https.port` property in the `run.properties` file.

**Tip:**

The administrative API is also documented in the OpenAPI Specification, previously known as the Swagger Specification. Click on the `/pf-admin-api/v1/swagger.json` URL on the Administrative API Documentation page to access the contents.

4. To test an administrative API, follow these steps:
  - a. Select a section of the administrative API you would like to explore; for example, **/dataStores**.
  - b. Expand the method you want to use; for example, **GET /dataStores**.
  - c. Enter required parameters, if any. For more information, see **Operation Models** underneath the selected API endpoint.
  - d. Click **Try it out**.

**Note:**

You might be prompted to sign on using administrative credentials over HTTP Basic authentication. The role assigned to the respective administrative accounts affects the access to the requested API.

Result:

If the request completes successfully, the administrative API returns the **Request URL**, the **Response Body**, the **Response Code**, and the **Response Headers**.

## Application endpoints

---

Application endpoints provide a means, through standard HTTP, by which external applications can communicate with the PingFederate server.

The single sign-on (SSO) and single log-out (SLO) endpoints for an identity provider (IdP) and a service provider (SP) include optional parameters which you can use to specify error pages that users see in the event of an SSO or SLO failure. By default, PingFederate provides templates for these and other errors or conditions. For more information, see [Customizable user-facing pages](#) on page 869.

SP endpoints also include those available for system for cross-domain identity management (SCIM) inbound provisioning. For more information, see [Provisioning for SPs](#) on page 107.

For either SP or IdP servers, PingFederate provides a maintenance endpoint for administrators to verify that the server is running. Endpoints applicable to both server roles include those needed for adapter-to-adapter mapping and retrieval of WS-Trust metadata. For more information, see [Adapter-to-adapter mappings](#) on page 408 and [WSC and WSP support](#) on page 82.

PingFederate provides a favorite icon for all application endpoints. For more information, see [Customizing the favicon for application and protocol endpoints](#) on page 908.

## IdP endpoints

The following sections describe PingFederate identity provider (IdP) endpoints, including the case-sensitive query parameters that each accepts or requires. These endpoints accept either the HTTP GET or POST methods.

Begin each URL with the fully-qualified server name and port number of your PingFederate IdP server, for example, `https://www.example.com:9031/idp/startSSO.ping`.



### Important:

When using the parameters **TargetResource** or **TARGET** with their own query parameters included, the parameter value must be URL-encoded. Any other parameters that contain restricted characters, such as many SAML URNs, also must be URL-encoded. For information about URL encoding, see third party resources such as HTML URL-encoding Reference. Parameters are case-sensitive.

You can customize and localize user-facing templates.



`/idp/startSSO.ping`

This is the path used to initiate an unsolicited IdP-initiated single sign-on (SSO) transaction during which a SAML response containing an assertion is sent to a service provider (SP). Typically, a systems integrator or developer creates one or more links to this endpoint in the IdP application or portal to allow users to initiate SSO to various SPs.

For information about allowing applications to retrieve configuration data from the PingFederate server over SOAP, see [Web service interfaces and APIs](#) on page 1193.

The following table shows the HTTP parameters for this endpoint.

| Parameter  | Description  |
|--|--|
| <b>PartnerSpId</b> or <b>PARTNER</b>                 | The federation ID of the SP to whom the SAML response containing an assertion should be issued. This ID value is case-sensitive.<br><br>One of these parameters is required unless the federation ID can be derived from <b>TargetResource</b> or <b>TARGET</b> .  |
| <b>TargetResource</b> or <b>TARGET</b><br>(optional) | For SAML 2.0, the value of either parameter is passed to the SP as the <b>RelayState</b> element of a SAML response message. This is the PingFederate implementation of the SAML 2.0 indicator for a desired resource at the SP during IdP-initiated SSO.<br><br>For SAML 1.x, the value is sent to the SP as a parameter named <b>TARGET</b> .<br><br>The parameter value must be URL-encoded.  |
| <b>InErrorResource</b><br>(optional)                 | Indicates where the user is redirected after an unsuccessful SSO. If this parameter is not included in the request, PingFederate redirects the user to the SSO error landing page hosted within PingFederate.  |
| <b>Binding</b><br>(optional)                         | Indicates the binding to be used; allowed values are URIs defined in the SAML specifications. For example, the SAML 2.0 applicable URIs are: <ul style="list-style-type: none"> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Artifact</code></li> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Post</code></li> </ul> When the parameter is not used, the default ACS URL configured for the SP-partner connection is used unless an ACS index is specified using the <b>ACSIdx</b> parameter. |

| Parameter                                       | Description  |
|---|--|
| <b>ACSIIdx</b><br>(optional - SAML 2.0)         | Specifies the index number of partner's ACS. For more information, see <a href="#">Setting Assertion Consumer Service URLs (SAML)</a> on page 472. Takes precedence over the <b>Binding</b> parameter if both are specified. If neither the binding nor index is specified in the call, the default ACS is used.   |
| <b>IdpAdapterId</b><br>(optional)               | Allows an application to call out what IdP adapter to use for authentication in a configuration with multiple IdP adapters. <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This parameter might be overridden by policy based on authentication policies. For example, a CIDR Authentication Selector instance could enforce the use of a given adapter instance based on whether a user is on or off the network. For more information, see <a href="#">Authentication policies</a> on page 231.</p> </div>  |
| <b>ChangePassword</b>                           | If a request includes this parameter with a value of <code>true</code> and invokes an HTML Form Adapter instance, the user is redirected to the <b>Change Password</b> template and prompted to update the network password. <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>To use this parameter, the <b>Allow Password Changes</b> check box must be selected in the adapter configuration of the invoked HTML Form Adapter instance. For more information, see <a href="#">Configuring an HTML Form Adapter instance</a> on page 306.</p> </div> |
| <b>RequestedFormat</b><br>(optional - SAML 2.0) | Allows control over the <b>NameId</b> format.  |
| <b>vsid</b><br>(optional)                       | Specifies the virtual server ID.<br><br>When absent, PingFederate uses the default virtual server ID, if specified, for the connection or the SAML federation ID defined in <b>Server Settings</b> . For more information, see <a href="#">Identifying the SP</a> on page 449 and <a href="#">Specifying federation information</a> on page 910.   |
| <b>PolicyAction</b><br>(optional)               | The HTML Form Adapter immediately returns the value of this parameter in the <code>policy.action</code> attribute, allowing the policy to bypass the adapter in favor of an alternative authentication source, provided a rule matching the action is configured. When this parameter is set to <code>identity.registration</code> and the adapter is followed by a local identity profile, the user is directed to the registration page for the profile.   |

/idp/startSLO.ping

This is the path used to start an IdP-initiated SLO (under SAML 2.0) or an OpenID Connect logout. For more information see [Asynchronous Front-Channel Logout](#) on page 650. Typically, a systems integrator or developer creates one or more links to this endpoint in the protected resources of their IdP application or portal to allow users to end their sessions at various SPs. This endpoint uses the local PingFederate session to determine which SPs have been issued an SSO assertion and sends them a SAML logout request.

PingFederate sends SLO requests in the following sequence, which prioritizes synchronous logouts:

1. IdP adapters

2. SAML IdP partners
3. SP adapters
4. SAML SP partners
5. WS-Fed and OIDC partners in parallel


The **LogoutType** parameter lets you customize the SLO process. For example, you can change the SLO process so that it does not prioritize synchronous logouts.

To start with asynchronous logouts, you could chain the logouts. Start with `/idp/startSLO.ping?LogoutType=AsyncOnly`. Set the **TargetResource** to `/idp/startSLO.ping?LogoutType=SyncOnly`. In this case, you would also need to add the `/idp/startSLO.ping` endpoint as an allowed redirect for SLO on the **Redirect Validation** window.

To perform asynchronous and synchronous logouts in parallel, you could create a page with two iframes. One iframe points to `/idp/startSLO.ping?LogoutType=AsyncOnly` and the other points to `/idp/startSLO.ping?LogoutType=SyncOnly`.

The following table describes the HTTP parameters for this endpoint.

| Parameter                               | Description   |
|---|---|
| <b>TargetResource</b><br>(optional)     | Indicates where the user is redirected after a successful SLO. If this parameter is not included in the request, PingFederate uses as a default the URL for a successful SLO as entered on the <b>IdP Default URL</b> window.<br><br>The parameter value must be URL-encoded.   |
| <b>InErrorResource</b><br>(optional)    | Indicates where the user is redirected after an unsuccessful SLO. If this parameter is not included in the request, PingFederate redirects the user to the SLO error landing page hosted within PingFederate.   |
| <b>Binding</b><br>(optional - SAML 2.0) | Indicates the binding to use. The allowed values are URIs defined in the SAML specifications. The SAML 2.0 applicable URIs are: <ul style="list-style-type: none"> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Artifact</code></li> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST</code></li> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect</code></li> <li>▪ <code>urn:oasis:names:tc:SAML:2.0:bindings:SOAP</code></li> </ul> When the parameter is not used, the first SLO Service URL configured for the SP-partner connection is used. For more information, see <a href="#">Specifying SLO service URLs (SAML 2.0)</a> on page 476. |

| Parameter                       | Description   |
|---------------------------------|---|
| <b>LogoutType</b><br>(optional) | <p>Controls which kinds of adapters and partners PingFederate will send SLO requests to. The allowed values are:</p> <ul style="list-style-type: none"> <li>▪ <b>All</b> (the default value) logs out all adapters and partners in the default sequence</li> <li>▪ <b>SyncOnly</b> logs out only SAML partners and adapters in series</li> <li>▪ <b>AsyncOnly</b> logs out only WS-Fed and OIDC partners in parallel</li> </ul> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When WS-Fed partner logout entries exist, <code>LogoutType=AsyncOnly</code> might still cause the log out of all partners and adapters. The reason is that WS-Fed logout requests to a partner might reflect back to PingFederate. For example, a <code>wsignout1.0</code> request to an IdP reflects back to PingFederate as a <code>wsignoutcleanup1.0</code> request. When PingFederate receives the signout request, there is no context connecting it to the original request. As a result, PingFederate performs a full SLO.</p> </div> |

`/idp/writecdc.ping`

This endpoint is used for SAML 2.0 IdP Discovery. This is the path used when the IdP wants to write to the common domain cookie (CDC) held within the user's browser. The information written to the cookie indicates from which IdP this user has authenticated.


The following table shows the one HTTP query parameter for this endpoint.

| Parameter                           | Description  |
|-------------------------------------|--|
| <b>TargetResource</b><br>(optional) | <p>Indicates where the user is redirected after successful IdP Discovery. If this parameter is not included in the request, PingFederate redirects the user to the referrer in the HTTP header. If there is no <b>TargetResource</b> or referrer, the call to this endpoint will fail.</p> <p>The parameter value must be URL-encoded.</p> |

`/pf/idprofile.ping`

This endpoint is used for profile management. When profile management is enabled for customer identities, authenticated users can review and modify the local identity fields that have been configured to be shown on the profile management page, connect or disconnect third-party identity providers, also known as Social Connections to the end users on the profile management page, and delete their local identities if the option to do so has been enabled. Each local identity profile has its own profile management URL.


The following table shows the one HTTP query parameter for this endpoint.

| Parameter                     | Description  |
|-------------------------------|--|
| <b>LocalIdentityProfileId</b> | Indicates which profile management page that PingFederate should serve to the authenticated users based on the ID of the local identity profile.   |
|                               |  <b>Tip:</b><br>You can copy the profile management URL for a given local identity profile on its configuration summary window. |

/pf/id/verification.ping

This endpoint is used for email ownership verification. When email ownership verification is enabled for customer identities, authenticated users can request additional email-verification notifications by accessing this endpoint.


The following table shows the one HTTP query parameter for this endpoint.

| Parameter                     | Description   |
|-------------------------------|---|
| <b>LocalIdentityProfileId</b> | Indicates the local identity profile from which the authenticated users, who are requesting additional email-verification notifications, originate.   |
|                               |  <b>Tip:</b><br>You can copy the email ownership verification endpoint for a given local identity profile on its configuration summary window. |

/ext/pwdchange/Identify

The Change Password endpoint allows users to change their password through an HTML Form Adapter instance without submitting SSO requests. This endpoint requires one parameter, **AdapterId**; the parameter value is the identifier of the HTML Form Adapter instance that has been configured with such capability. For example, if the fully-qualified name of your PingFederate environment and the adapter ID are `www.example.com` and `HTMLFormSimplePCV` respectively, the resulting URL is `https://www.example.com/ext/pwdchange/Identify?AdapterId=HTMLFormSimplePCV`.


The following table shows the one additional HTTP query parameter for this endpoint.

| Parameter             | Description  |
|-----------------------|--|
| <b>TargetResource</b> | Indicates the desired destination after users have successfully change their network password.   |
|                       |  <b>Note:</b><br>When target resource validation is enabled for this endpoint, as indicated by the <b>SLO and Other</b> check box on the <b>Security # System Integration # Redirect Validation # Local Redirect Validation</b> tab, PingFederate honors the URL only if the parameter value satisfies the configured requirement on the <b>Local Redirect Validation</b> tab. If the validation fails, PingFederate displays the default success or error message.<br><br>For more information, see <a href="#">Configuring redirect validation</a> on page 694. |

`/ext/pwdreset/Identify`

The Account Recovery endpoint allows users to reset their password or unlock their account through an HTML Form Adapter instance without submitting SSO requests. This endpoint requires one parameter, **AdapterId**; the parameter value is the identifier of the HTML Form Adapter instance that has been configured with such capabilities. For example, if the fully-qualified name of your PingFederate environment and the adapter ID is `www.example.com` and `HTMLFormSimplePCV` respectively, the resulting URL is `https://www.example.com/ext/pwdreset/Identify?AdapterId=HTMLFormSimplePCV`.


The following table shows the one additional HTTP query parameter for this endpoint.

| Parameter             | Description  |
|-----------------------|--|
| <b>TargetResource</b> | <p>Indicates the desired destination after users have successfully reset their network password or unlocked their account.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When target resource validation is enabled for this endpoint, as indicated by the <b>SLO and Other</b> check box on the <b>Security # System Integration # Redirect Validation # Local Redirect Validation</b> tab, PingFederate honors the URL only if the parameter value satisfies the configured requirement on the <b>Local Redirect Validation</b> tab. If the validation fails, PingFederate displays the default success or error message.</p> <p>For more information, see <a href="#">Configuring redirect validation</a> on page 694.</p> </div> |

`/ext/idrecovery/Recover`

The Username Recovery endpoint allows users to recover their username through an HTML Form Adapter instance without submitting SSO requests. This endpoint requires one parameter, **AdapterId**; the parameter value is the identifier of the HTML Form Adapter instance that has been configured with such capabilities. For example, if the fully-qualified name of your PingFederate environment and the adapter ID is `www.example.com` and `HTMLFormSimplePCV` respectively, the resulting URL is `https://www.example.com/ext/idrecovery/Recover?AdapterId=HTMLFormSimplePCV`.

The following table shows the one additional HTTP query parameter for this endpoint.

| Parameter             | Description  |
|-----------------------|--|
| <b>TargetResource</b> | <p>Indicates the desired destination after users have successfully recovered their username.</p> <div style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When target resource validation is enabled for this endpoint, as indicated by the <b>SLO and Other</b> check box on the <b>Security # System Integration # Redirect Validation # Local Redirect Validation</b> tab, PingFederate honors the URL only if the parameter value satisfies the configured requirement on the <b>Local Redirect Validation</b> tab. If the validation fails, PingFederate displays the default success or error message.</p> <p>For more information, see <a href="#">Configuring redirect validation</a> on page 694.</p> </div> |

## SP endpoints

PingFederate provides configuration options for a variety of endpoints.

The following sections describe the PingFederate service provider (SP) endpoints for SP services and system for cross-domain identity management (SCIM) inbound provisioning.

### SP services

The following sections describe PingFederate service provider (SP) endpoints, including the query parameters that each accepts or requires. These endpoints accept either the HTTP GET or POST methods.

Begin each URL with the fully-qualified server name and port number of your PingFederate SP server; for example, <https://www.example.com:9031/sp/startSSO.ping>.



#### Important:

When using the parameters **TargetResource** or **TARGET** with their own query parameters included, the parameter value must be URL-encoded. Any other parameters that contain restricted characters, such as many SAML URNs, also must be URL-encoded. For information about URL encoding, see third party resources such as [HTML URL-encoding Reference](#). Parameters are case-sensitive.

[/sp/startSSO.ping](#)

This is the path used to initiate SP-initiated single sign-on (SSO). In this scenario, the SP issues an SSO request to the identity provider (IdP) asking for an SSO authentication response. Typically, a systems integrator or developer creates links to this endpoint in SP applications to allow users to access various protected resources through SSO using the IdP as an authentication authority.

For information about allowing applications to retrieve configuration data from the PingFederate server over SOAP, see [Web service interfaces and APIs](#) on page 1193.

The following table shows the HTTP parameters for this endpoint.



#### Note:

Some parameters described below can have multiple values. Specify these values by using multiple independent query string parameters of the same name.

| Parameter                      | Description  |
|--------------------------------|--|
| <b>PartnerIdpId</b>            | <p>The federation ID of the IdP that authenticates the user and issues an assertion. This ID is case-sensitive.</p> <p>Required if more than one IdP connection is configured and <b>Domain</b> is not used, and SP authentication policies are turned off.</p> <p>Not required if SP authentication policies are turned on.</p>   |
| <b>SpSessionAuthnAdapterId</b> | <p>The explicit SP adapter instance ID indicating the adapter to use to create an authenticated session or security context.</p> <p>Optional if SP authentication policies are turned off.</p> <p>Required if SP authentication policies are turned on unless the PingFederate SP server can determine the applicable SP adapter instance based on the target URL mapping configuration and the <b>TargetResource</b> or <b>TARGET</b> value at runtime.</p> |



| Parameter  | Description   |
|--|---|
| <b>TargetResource</b> or <b>TARGET</b>                       | <p>This parameter indicates the target applications where a successful SSO redirects the end-user.</p> <p>The parameter value must be URL-encoded.</p> <p>When this parameter is not provided in the URL, you can specify a default target resource in the administrative console, either for all IdP connections, for individual connections, or both. For more information, see <a href="#">Configuring default URLs</a> on page 719 and <a href="#">Configuring default target URLs</a> on page 758.</p>                               |
| <b>InErrorResource</b><br>(optional)                         | <p>This parameter indicates where an unsuccessful SSO redirects the end-user. If this parameter is not included in the request, PingFederate redirects the user to the single log-out (SLO) error landing page hosted within PingFederate. For more information, see <a href="#">Customizable user-facing pages</a> on page 869.</p>  |
| <b>Binding</b><br>(optional)                                 | <p>Indicates the binding to use; allowed values are URIs defined in the SAML specifications. For example, the SAML 2.0 applicable URIs are</p> <pre>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Artifact urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect</pre> <p>When the parameter is not used for SAML 2.0, the first SSO Service URL configured for the IdP-partner connection is used. For more information, see <a href="#">Specifying SSO service URLs (SAML)</a> on page 749.</p> |
| <b>AllowCreate</b><br>(optional - SAML 2.0)                  | <p>Controls the value of the <b>AllowCreate</b> attribute of the <b>NameIDPolicy</b> element in the AuthnRequest. The default is <code>true</code>.</p>   |
| <b>AuthenticatingIdpId</b><br>(optional - SAML 2.0)          | <p>This parameter indicates the preferred IdP for authenticating the user through an IdP proxy, such as PingOne for Enterprise. The parameter specifies the value of the <b>ProviderID</b> attribute in the <b>Scoping/IDPList/IDPEntry</b> element in the AuthnRequest. For more information, see section 3.4.1.3.1 of the OASIS SAML document <a href="#">saml-core-2.0-os.pdf</a>.</p> <p>You can specify multiple values to build a preferred list.</p>   |
| <b>ForceAuthn</b><br>(optional - SAML 2.0 or OpenID Connect) | <p>For SAML 2.0, this parameter controls the attribute of the same name in the AuthnRequest.</p> <p>For OpenID Connect, a value of <code>true</code> sets the <b>prompt</b> parameter in the authentication request to <code>login</code>. For more information about the authentication request and its parameter, see the <a href="#">OpenID Connect specification</a>.</p> <p>The default is <code>false</code>.</p>   |
| <b>IsPassive</b><br>(optional - SAML 2.0 or OpenID Connect)  | <p>For SAML 2.0, this parameter controls the attribute of the same name in the AuthnRequest.</p> <p>For OpenID Connect, a value of <code>true</code> sets the <b>prompt</b> parameter in the authentication request to <code>none</code>.</p> <p>The default is <code>false</code>.</p>   |
| <b>RequestedACSIIdx</b><br>(optional - SAML 2.0)             | <p>The index number of your site's Assertion Consumer Service, where you want the assertion to be sent.</p>   |

| Parameter   | Description   |
|---|---|
| <b>RequestedAcsUrl</b><br>(optional - SAML 2.0)                     | The URL of your site's Assertion Consumer Service, where you want the assertion to be sent.   |
| <b>RequestedAuthnCtx</b><br>(optional - SAML 2.0 or OpenID Connect) | For SAML 2.0, this parameter indicates the requested authentication context of the assertion; allowed values include URIs defined in the SAML specifications. For more information, see the OASIS SAML document <a href="#">saml-authn-context-2.0-os.pdf</a> .<br><br>For OpenID Connect, the specified value becomes the <code>acr_values</code> parameter value in the authentication request.<br><br>You can specify multiple values to build a preferred list. |
| <b>RequestedAuthnDeclReq</b><br>(optional - SAML 2.0)               | An alternative to <b>RequestedAuthnCtx</b> above, indicating the requested authentication context of the assertion by declaring any URI reference. For more information see section 2.7.2.2 of the OASIS SAML document <a href="#">saml-core-2.0-os.pdf</a> .<br><br>You can specify multiple values to build a preferred list.   |
| <b>RequestedBinding</b><br>(optional - SAML 2.0)                    | Indicates the binding requested for the response containing the assertion; allowed values are URIs defined in the SAML specifications.  |
| <b>RequestedFormat</b><br>(optional - SAML 2.0)                     | Specifies the value for the Format attribute in the <b>NameIDPolicy</b> element of the AuthnRequest. If not specified, the AuthnRequest does not include the attribute.   |
| <b>RequestedSPNameQualifier</b><br>(optional - SAML 2.0)            | Indicates that the IdP should return the given name qualifier as part of the assertion used primarily to identify SP affiliations. For more information, see <a href="#">SP affiliations</a> on page 515.   |
| <b>vsid</b><br>(optional)   | Specify the virtual server ID.<br><br>When absent, PingFederate uses the default virtual server ID (if specified) for the connection or the SAML federation ID defined in <b>Server Settings</b> . For more information, see <a href="#">Identifying the partner</a> on page 731 and <a href="#">Specifying federation information</a> on page 910.   |
| <b>PolicyAction</b><br>(optional)                                   | The HTML Form Adapter immediately returns the value of this parameter in the <code>policy.action</code> attribute, allowing the policy to bypass the adapter in favor of an alternative authentication source, provided a rule matching the action is configured. When this parameter is set to <code>identity.registration</code> and the adapter is followed by a local identity profile, the user is directed to the registration page for the profile.          |

If **SpSessionAuthnAdapterId** specifies an adapter, then that adapter is used to create an authenticated session for SP-initiated SSO. If there is no **SpSessionAuthnAdapterId**, the ultimate destination of the user after SSO, either the **TargetResource** or the default SSO success URL, is used along with the mappings defined in the administrative console on the **Map URLs to Adapter Instances** window. For more information, see [Configuring target URL mapping](#) on page 715.

Note that adapter selection for SP-initiated SSO is similar to that for IdP-initiated SSO except that, because the adapter ID depends on the SAML deployment, PingFederate cannot expect it from an IdP. Therefore, it uses only the URL mapping for adapter selection for SSO.

/sp/startSLO.ping

This is the path used to initiate SP-initiated SLO. Typically, a systems integrator or developer creates one or more links to this endpoint in the protected resources of their SP application, which allows users to end a session by sending a logout request to the IdP that authenticated the session.

Note that the IdP might send additional logout request messages to other SPs when it receives a logout request from a PingFederate server acting as an SP.

The following table shows the HTTP parameters for this endpoint.

| Parameter                               | Description   |
|---|---|
| <b>TargetResource</b><br>(optional)     | Indicates where a successful SLO redirects the user. If the request does not include this parameter, PingFederate uses the URL for a successful SLO as a default, as entered on the <b>SP Default URLs</b> window.<br><br>Note that the parameter value must be URL-encoded.  |
| <b>Binding</b><br>(optional - SAML 2.0) | Indicates the binding to use; allowed values are URIs defined in the SAML specifications. The SAML 2.0 applicable URIs are<br><br><pre>urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Artifact urn:oasis:names:tc:SAML:2.0:bindings:HTTP-POST urn:oasis:names:tc:SAML:2.0:bindings:HTTP-Redirect urn:oasis:names:tc:SAML:2.0:bindings:SOAP</pre><br>When the parameter is not used, the first SLO Service URL configured for the IdP-partner connection is used. For more information, see <a href="#">Specifying SLO service URLs (SAML 2.0)</a> on page 476. |
| <b>InErrorResource</b><br>(optional)    | Indicates where an unsuccessful SLO redirects the user. If the request does not include this parameter, PingFederate redirects the user to the SLO error landing page hosted within PingFederate. For more information, see <a href="#">Customizable user-facing pages</a> on page 869.   |

/sp/defederate.ping

This path terminates an account link created during SSO. Account linking provides a means for subject identification on the SP side. On the SP side, only users create and terminate links. The link contains the name identifier from the IdP, the IdP's federation ID, the adapter instance ID, and the local user identifier.

There are no HTTP parameters for this endpoint.

You can unlink a user session only if it was established during SSO using an existing account link on the SP side. If more than one SP session was established through account linking on the same PingFederate session, this endpoint will terminate each of those links. A local logout is also performed for any link that is terminated.

/sp/cdcstartSSO.ping

This endpoint is used for IdP-Discovery implementations. For more information, see [Standard IdP Discovery](#) on page 50 . This endpoint is similar to `/sp/startSSO.ping` and accepts the same parameters, with the exception of `PartnerIdpId` and `vsid`. Instead of this parameter, the server attempts to use the common domain cookie to determine the IdP.

/sp/startAttributeQuery.ping

This endpoint initiates an Attribute Query with a SAML 2.0 IdP. For more information, see [Attribute Query and XASP](#) on page 49 .

The following table shows the HTTP parameters for this endpoint.

**Note:**

Some parameters described below can have multiple values. Specify these values by using multiple independent query string parameters of the same name.

| Parameter  | Description  |
|--|--|
| <b>Subject</b>   | Uniquely identifies the user to the IdP. When user authenticates with an X.509 certificate, this is the Subject DN, which must be URL-encoded.   |
| <b>Issuer</b><br>(optional)                              | The IssuerDN from the user's X.509 certificate, when X.509 attribute sharing profile (XASP) is used, which uniquely identifies the entity that issued the user's certificate. The parameter must be URL-encoded.   |
|  | <b>Note:</b><br>When specified this parameter overrides the <b>Subject</b> parameter.  |
| <b>PartnerIdpId</b><br>(except for XASP)                 | Used to identify the specific IdP partner to which the attribute query should be sent. Without this parameter, the Subject and Issuer are used to determine the correct IdP.   |
|  | <b>Note:</b><br>For XASP, this parameter overrides both the <b>Subject</b> and <b>Issuer</b> parameters.   |
| <b>Format</b><br>(required for XASP, otherwise optional) | Identifies the name-identifier format of the <b>Subject</b> query parameter. If included, the value must be one of the SAML 2.0 Name Identifier Format URIs. For more information, see section 8.3 of the <a href="#">SAML specifications</a> .          |
|  | <b>Note:</b><br>For XASP, this parameter must be set to<br><code>urn:oasis:names:tc:SAML:1.1:nameid-format:X509SubjectName</code><br>If not specified, the parameter defaults to<br><code>urn:oasis:names:tc:SAML:1.1:nameid-format:unspecified</code> . |
|  | The parameter must be URL-encoded.   |
| <b>AppId</b>   | The unique identifier of the initiating application.   |
| <b>SharedSecret</b>                                      | Used to authenticate the initiating application. Both the <b>AppId</b> and <b>SharedSecret</b> values must match those defined on the <b>Security # System Integration # Service Authentication</b> window.  |
|  | <b>Important:</b><br>To avoid recording this parameter in web server logs, only pass it in the message body using the HTTP POST method.  |

| Parameter                              | Description   |
|--|---|
| <b>RequestedAttrName</b><br>(optional) | A name of a user attribute requested from the IdP. For each desired user attribute, include this parameter. If this parameter is not present, then the IdP returns all allowable user attributes.<br><br>You can specify multiple values to build a preferred list.   |
| <b>vsid</b><br>(optional)              | Specify the virtual server ID.<br><br>When absent, PingFederate uses the default virtual server ID, if specified, for the connection or the SAML federation ID defined in <b>Server Settings</b> . For more information, see <a href="#">Identifying the partner</a> on page 731 and <a href="#">Specifying federation information</a> on page 910. |

### SCIM inbound provisioning endpoints

PingFederate supports system for cross-domain identity management (SCIM) inbound provisioning and provides four endpoints.

The four endpoints are:

- /pf-scim/v1/Users
- /pf-scim/v1/Groups
- /pf-scim/v1/Schemas
- /pf-scim/v1/ServiceProviderConfigs

These endpoints are defined in the following SCIM 1.1 specifications:

- [SCIM Core Schema](#)
- [SCIM Specification](#)

Begin each endpoint with the fully-qualified server name and port number of your PingFederate server, for example: `https://pingidentity.com:9031/pf-scim/v1/Users`.

/pf-scim/v1/Users





The users endpoint is where client applications make HTTP requests to create, retrieve, update, and delete or deactivate users. This REST-based endpoint accepts POST, GET, PUT, and DELETE methods, as described in the following table.



#### Note:

HTTP requests must be made using either Basic or client-certificate application authentication. JSON is currently the only supported format for the HTTP message body.

| HTTP method | Description  |
|-------------|--|
| POST        | <p data-bbox="540 212 808 239">/pf-scim/v1/Users</p> <ul data-bbox="558 260 1458 478" style="list-style-type: none"><li data-bbox="558 260 1458 317">▪ Sends user attributes in JSON format—defined in the SCIM Core Schema—to create a new user.</li><li data-bbox="558 327 1458 478">▪ A successful response is indicated by an HTTP 201 status code and a message body containing the user record that has been added to the target datastore. The user ID is set as the <code>id</code> attribute in the JSON response, and the full URL to reference the user is in the HTTP response Location header.</li></ul> <p data-bbox="540 501 1458 684">For an existing user, you can also use the POST method to either update or delete or disable a user record by appending the user ID to the path in the format of <code>/pf-scim/v1/Users/<i>user_id</i></code> and setting the request header <code>x-HTTP-Method-Override</code> value to PUT or DELETE, respectively. For more information, see the PUT and DELETE method descriptions at the end of this topic.</p> |

| HTTP method | Description   |
|-------------|---|
| GET         | <p data-bbox="537 212 808 237"><code>/pf-scim/v1/Users</code></p> <ul data-bbox="558 260 1455 352" style="list-style-type: none"> <li>▪ Retrieves all user records.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of all users and their attributes.</li> </ul> <p data-bbox="537 375 938 401"><code>/pf-scim/v1/Users/user_id</code></p> <ul data-bbox="558 424 1435 516" style="list-style-type: none"> <li>▪ Retrieves the user record of a specific user.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and the requested user record.</li> </ul> <p data-bbox="537 539 1143 564"><code>/pf-scim/v1/Users?attributes=attribute</code></p> <ul data-bbox="558 588 1455 680" style="list-style-type: none"> <li>▪ Retrieves the specific attribute from all users.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of the desired attribute from all users.</li> </ul> <div data-bbox="574 695 1469 869" style="border: 1px solid black; padding: 5px;"> <p data-bbox="586 716 711 758"> <b>Note:</b></p> <p data-bbox="586 779 1325 842">For more information, see <a href="#">3.2.2 List/Query Resources</a> in SCIM Specification.</p> </div> <p data-bbox="537 892 1032 917"><code>/pf-scim/v1/Users?filter=filter</code></p> <ul data-bbox="558 940 1455 1033" style="list-style-type: none"> <li>▪ Retrieves resources based on the filter.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of resources matching the filter.</li> </ul> <div data-bbox="574 1050 1469 1188" style="border: 1px solid black; padding: 5px;"> <p data-bbox="586 1071 711 1113"> <b>Note:</b></p> <p data-bbox="586 1134 1349 1159">For more information, see <a href="#">3.2.2.1 Filtering</a> in SCIM Specification.</p> </div> <p data-bbox="537 1211 1409 1270"><code>/pf-scim/v1/Users?sortBy=attribute&amp;sortOrder=ascending descending</code></p> <ul data-bbox="558 1293 1442 1512" style="list-style-type: none"> <li>▪ Retrieves all user records and sorts them based on a specific attribute in ascending or descending order.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a sorted result set. Depending on the implementation of the target datastore, the target datastore might not return the user records that do not contain a value for that specific attribute as indicated by the <b>sortBy</b> parameter in the request.</li> </ul> <div data-bbox="574 1528 1469 1667" style="border: 1px solid black; padding: 5px;"> <p data-bbox="586 1549 711 1591"> <b>Note:</b></p> <p data-bbox="586 1612 1341 1638">For more information, see <a href="#">3.2.2.2 Sorting</a> in SCIM Specification.</p> </div> <p data-bbox="537 1690 1170 1715"><code>/pf-scim/v1/Users?startIndex=x[&amp;count=y]</code></p> <ul data-bbox="558 1738 1463 1892" style="list-style-type: none"> <li>▪ Retrieves the user records starting with a specific index number, a positive integer <code>x</code>. If the optional <code>count</code> parameter is included, with a positive integer <code>y</code>, the endpoint limits the number of user records in the result set.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a limited set of user records.</li> </ul> <div data-bbox="574 1908 1469 2047" style="border: 1px solid black; padding: 5px;"> <p data-bbox="586 1929 711 1971"> <b>Note:</b></p> <p data-bbox="586 1992 1382 2018">For more information, see <a href="#">3.2.2.3 Pagination</a> in SCIM Specification.</p> </div> |

| HTTP method | Description   |
|-------------|---|
| PUT         | <p><code>/pf-scim/v1/Users/user_id</code></p> <ul style="list-style-type: none"> <li>Updates user attributes for the specified user, using JSON in the body of the HTTP request. Attributes not included in the request are set to a default value in the datastore.</li> <li>A successful PUT operation returns an HTTP 200 status code and the entire updated user record within the response body.</li> </ul>  |
| DELETE      | <p><code>/pf-scim/v1/Users/user_id</code></p> <ul style="list-style-type: none"> <li>Deletes or disables the user record for the specified user. Note that whether a user is deleted or disabled is determined by the selection of the <b>SCIM DELETE message behavior</b> option on the <b>Delete/Disable Users</b> tab in the applicable identity provider (IdP) connection.</li> <li>A successful response is indicated by an HTTP 200 status code.</li> </ul> |

**Note:**

For a list of HTTP error codes that might be returned, see [3.9 HTTP Response Codes](#) in SCIM Specification.

`/pf-scim/v1/Groups`

The groups endpoint is where client applications make HTTP requests to create, retrieve, update, and delete groups.

**Note:**

Inbound provisioning for groups is a per-connection, optional feature. To enable group provisioning, select the **User and Group Support** option on the **Connection Type** tab when configuring the applicable IdP connection.





This REST-based endpoint accepts POST, GET, PUT, and DELETE methods, as described in the following table.

**Note:**

HTTP requests must be made using either Basic or client-certificate application authentication. JSON is currently the only supported format for the HTTP message body.



| HTTP method | Description  |
|-------------|--|
| POST        | <p data-bbox="540 212 824 239">/pf-scim/v1/Groups</p> <ul data-bbox="558 260 1425 485" style="list-style-type: none"><li data-bbox="558 260 1370 321">▪ Sends group attributes in JSON format—defined in the SCIM Core Schema—to create a new group.</li><li data-bbox="558 327 1425 485">▪ A successful response is indicated by an HTTP 201 status code and a message body containing the group record that has been added to the target datastore. The group ID is set as the <code>id</code> attribute in the JSON response, and the full URL to reference the group is in the HTTP response Location header.</li></ul> <p data-bbox="540 506 1442 688">For an existing group, you can also use the POST method to either update or delete the group by appending the group ID to the path, in the format of <code>/pf-scim/v1/Groups/group_id</code>, and setting the request header <code>x-HTTP-Method-Override</code> value to PUT or DELETE, respectively. For more information, see the PUT and DELETE method descriptions at the end of this topic.</p> |

| HTTP method | Description  |
|-------------|--|
| GET         | <p data-bbox="537 212 824 239"><code>/pf-scim/v1/Groups</code></p> <ul data-bbox="558 258 1455 352" style="list-style-type: none"> <li>▪ Retrieves all group records.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of all groups and their attributes.</li> </ul> <p data-bbox="537 373 971 401"><code>/pf-scim/v1/Groups/group_id</code></p> <ul data-bbox="558 420 1435 514" style="list-style-type: none"> <li>▪ Retrieve the group record of a specific group.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and the requested group record.</li> </ul> <p data-bbox="537 535 1159 562"><code>/pf-scim/v1/Groups?attributes=attribute</code></p> <ul data-bbox="558 581 1455 676" style="list-style-type: none"> <li>▪ Retrieves the specific attribute from all groups.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of the desired attribute from all groups.</li> </ul> <div data-bbox="574 695 1472 869" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="586 716 711 758"> <b>Note:</b></p> <p data-bbox="586 779 1321 835">For more information, see <a href="#">3.2.2 List/Query Resources</a> in SCIM Specification.</p> </div> <p data-bbox="537 890 1049 917"><code>/pf-scim/v1/Groups?filter=filter</code></p> <ul data-bbox="558 936 1455 1031" style="list-style-type: none"> <li>▪ Retrieves resources based on the filter.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a list of resources matching the filter.</li> </ul> <div data-bbox="574 1050 1472 1188" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="586 1071 711 1113"> <b>Note:</b></p> <p data-bbox="586 1134 1349 1161">For more information, see <a href="#">3.2.2.1 Filtering</a> in SCIM Specification.</p> </div> <p data-bbox="537 1209 1425 1266"><code>/pf-scim/v1/Groups?sortBy=attribute&amp;sortOrder=ascending descending</code></p> <ul data-bbox="558 1287 1455 1507" style="list-style-type: none"> <li>▪ Retrieves all group records and sorts them based on a specific attribute in ascending or descending order.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a sorted result set. Depending on the implementation of the target datastore, the target datastore might not return the group records that do not contain a value for that specific attribute as indicated by the <b>sortBy</b> parameter in the request.</li> </ul> <div data-bbox="574 1528 1472 1667" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="586 1549 711 1591"> <b>Note:</b></p> <p data-bbox="586 1612 1338 1640">For more information, see <a href="#">3.2.2.2 Sorting</a> in SCIM Specification.</p> </div> <p data-bbox="537 1688 1187 1715"><code>/pf-scim/v1/Groups?startIndex=x[&amp;count=y]</code></p> <ul data-bbox="558 1734 1414 1923" style="list-style-type: none"> <li>▪ Retrieves the group records starting with a specific index number, a positive integer <code>x</code>. If the optional <code>count</code> parameter is included, with a positive integer <code>y</code>, the endpoint limits the number of user records in the result set.</li> <li>▪ A successful response is indicated by an HTTP 200 status code and a limited set of group records.</li> </ul> <div data-bbox="574 1944 1472 2083" style="border: 1px solid black; padding: 5px; margin-top: 10px;"> <p data-bbox="586 1965 711 2007"> <b>Note:</b></p> <p data-bbox="586 2028 1382 2055">For more information, see <a href="#">3.2.2.3 Pagination</a> in SCIM Specification.</p> </div> |

| HTTP method | Description   |
|-------------|---|
| PUT         | <p><code>/pf-scim/v1/Groups/group_id</code></p> <ul style="list-style-type: none"> <li>Updates group attributes for the specified group, using JSON in the body of the HTTP request. Attributes not included in the request are set to a default value in the datastore.</li> <li>A successful PUT operation returns an HTTP 200 status code and the entire updated group record within the response body.</li> </ul> |
| DELETE      | <p><code>/pf-scim/v1/Groups/group_id</code></p> <ul style="list-style-type: none"> <li>Deletes the group record for the specified group.</li> <li>A successful response is indicated by an HTTP 200 status code.</li> </ul>   |

**Note:**

For a list of HTTP error codes that might be returned, see [3.9 HTTP Response Codes](#) in SCIM Specification.

### `/pf-scim/v1/Schemas`

The schemas endpoint is where a client can retrieve a resource's schema. This REST-based endpoint accepts GET method as described in the following table.

**Note:**

HTTP requests must be made using either Basic or client-certificate application authentication. JSON is currently the only supported format for the HTTP message body.

| HTTP method | Description   |
|-------------|---|
| GET         | <p>Retrieves the resource's schema for an IdP connection based on the authentication information.</p> <p>A successful response is indicated by an HTTP 200 status code and the results in the message body.</p> |

**Example**

```
$ curl -u basicUser 'https://localhost:9031/pf-scim/v1/Schemas' | python -m
json.tool
{
  "attributes": [
    {
      "caseExact": false,
      "description": "Unique identifier for the SCIM resource as
defined by the Service Provider. Each representation of the resource MUST
include a non-empty id value. This identifier MUST be unique across the
Service Provider's entire set of resources. It MUST be a stable, non-
reassignable identifier that does not change when the same resource is
returned in subsequent requests. The value of the id attribute is always
issued by the Service Provider and MUST never be specified by the Service
Consumer. REQUIRED.",
      "multiValued": false,
      "name": "id",
      "readOnly": true,
```

```

        "required": true,
        "schema": "urn:scim:schemas:core:1.0",
        "type": "string"
    },
    ...
],
"description": "Core User",
"endpoint": "/Users",
"id": "urn:scim:schemas:core:1.0:User",
"name": "User",
"schema": "urn:scim:schemas:core:1.0"
}

```

### /pf-scim/v1/ServiceProviderConfigs

This service provider (SP) configuration endpoint is where developers can retrieve detailed information on the PingFederate SCIM 1.1 implementation. When you enable inbound provisioning for an SP PingFederate server, an HTTP GET request to this endpoint returns a JSON response outlining SCIM 1.1 compliance details.



#### Note:

The `/pf-scim/v1/ServiceProviderConfigs` endpoint does not require authentication. JSON is currently the only supported format for the HTTP message body.

### Example

```

$ curl https://localhost:9031/pf-scim/v1/ServiceProviderConfigs
{
  "schemas": ["urn:scim:schemas:core:1.0"],
  ...
  "patch": {
    "supported": false
  },
  "bulk": {
    "supported": false
  },
  "filter": {
    "supported": true
  },
  "changePassword" : {
    "supported": true
  },
  "sort": {
    "supported": false
  },
  "etag": {
    "supported": false
  },
  "xmlDataFormat": {
    "supported": false
  },
  "authenticationSchemes": [
    {
      "name": "HTTP Basic",
      "description": "Authentication using HTTP Basic",
      ...
      "type": "httpbasic"
    },
    {

```

```

    "name": "TLS Client Certificate",
    "description": "Authentication via TLS Client Certificate",
    ...
    "type": "tls"
  }
]
}

```

## System-services endpoints

System-services endpoints generally apply to the PingFederate server, whether used as an identity provider (IdP), service provider (SP), or both. Parameters are case-sensitive.

/pf/heartbeat.ping

This endpoint returns an HTTP status code of 200 and a message body of **OK** if the PingFederate runtime server is up and functional. You can customize the message by modifying a PingFederate property and a Velocity template file. For more information, see [Customizing the heartbeat message](#) on page 907.



### Note:

If a GET request receives a connection error or an HTTP status code other than 200, the server associated with the endpoint is down or malfunctioning.

Load balancers can use this endpoint to determine the status of PingFederate independently of checks used to determine the status of the supporting hardware.

You can also configure the server to provide regular status information to a network-management utility. For more information, see [Runtime reporting](#).

/pf/adapter2adapter.ping

This endpoint initiates direct IdP-to-SP adapter mapping, when that feature is configured in the **Adapter-to-Adapter Mappings** window. For more information, see [Adapter-to-adapter mappings](#) on page 408.




### Note:

To prevent users from circumventing the SP authentication policies, this endpoint becomes inactive when SP authentication policies are enabled but IdP authentication policies are disabled. Administrators can configure SP authentication policies for the internal users to re-enable access to protected resources.

For information, see [Configuring SP authentication policies for internal users](#) on page 282.

The following table shows the HTTP parameters for this endpoint.

| Parameter                            | Description  |
|--------------------------------------|--|
| <b>TargetResource</b><br>(optional)  | Indicates where the user is redirected after a successful SSO. If this parameter is not included in the request, PingFederate redirects the user to a default location if one is specified in the <b>Applications # Integration # SP Default URLs</b> window.  |
| <b>InErrorResource</b><br>(optional) | Indicates where the user is redirected if the SSO is unsuccessful. If this parameter is not included in the request, PingFederate redirects the user to the SSO error landing page hosted within PingFederate. For more information, see <a href="#">Customizable user-facing pages</a> on page 869. |

| Parameter                                    | Description  |
|--|--|
| <b>IdpAdapterId</b><br>(optional)            | Indicates the IdP adapter instance to use for authentication if more than one IdP adapter is configured in adapter-to-adapter mappings.  |
| <b>SpSessionAuthnAdapterId</b><br>(optional) | Indicates the SP adapter instance to be used. If not provided and more than one SP adapter instance is configured with adapter-to-adapter mapping, PingFederate selects one based on entries defined in the <b>Applications # Integration # Target URL Mapping</b> window. For more information, see <a href="#">Configuring target URL mapping</a> on page 715.   |
| <b>ChangePassword</b>                        | If a request includes this parameter with a value of <code>true</code> and invokes an HTML Form Adapter instance, the user is redirected to the <b>Change Password</b> template and prompted to update the network password.   |
|  |  <b>Note:</b><br>To use this parameter, the <b>Allow Password Changes</b> check box must be selected in the adapter configuration of the invoked HTML Form Adapter instance. For more information, see <a href="#">Configuring an HTML Form Adapter instance</a> on page 306.   |
| <b>PolicyAction</b><br>(optional)            | The HTML Form Adapter immediately returns the value of this parameter in the <code>policy.action</code> attribute, allowing the policy to bypass the adapter in favor of an alternative authentication source, provided a rule matching the action is configured. When this parameter is set to <code>identity.registration</code> and the adapter is followed by a local identity profile, the user is directed to the registration page for the profile. |

/pf/sts.wst

This endpoint initiates direct security token service (STS) token-to-token exchange and token validation from an IdP token processor to an SP token generator, when that feature is configured in the **Token Translator Mappings** window. For more information, see [Token translator mappings](#) on page 414.

The following table shows the HTTP parameters for this endpoint.

| Parameter               | Description   |
|-------------------------|---|
| <b>TokenProcessorId</b> | Indicates the IdP token processor to use in the mapping. Required when multiple IdP token processors are configured in token-to-token mappings. |
| <b>TokenGeneratorId</b> | Indicates the SP token generator to use in the mapping. Required when multiple SP token generators are configured in token-to-token mappings.   |



**Important:**

If mutual SSL/TLS is used for authentication, you must configure a secondary PingFederate listening port used by partners or STS clients for the relevant endpoints—`*.ssaml*` and `*.wst`. For more information, see [Configuring PingFederate properties](#) on page 820.

/pf/sts\_mex.ping

This endpoint returns STS metadata for use in expediting configuration of web-service applications.

The following table shows the HTTP parameters for this endpoint.

| Parameter                 | Description  |
|---------------------------|--|
| <b>PartnerSpId</b>        | The connection ID of the SP to whom the SAML token will be issued. This parameter determines the connection for which metadata will be generated.  |
| <b>PartnerIdpId</b>       | The connection ID of the IdP issuing the SAML token to be consumed by PingFederate. This parameter determines the connection for which the metadata will be generated.   |
| <b>vsid</b><br>(optional) | Specify the virtual server ID.<br>If absent, PingFederate uses the default virtual server ID (if specified) for the connection or the federation ID defined on the <b>System # Server # Protocol Settings # Federation Info</b> tab. |

**Note:**

If your partner fails to retrieve metadata when sending both the **PartnerSpId** or the **PartnerIdpId**, and the **vsid** query parameters, perhaps it is only capable of sending one query parameter in such requests. An alternative metadata exchange endpoint that includes the virtual server ID information should resolve the issue.

For more information, see [Constructing an alternative metadata exchange endpoint](#) on page 1272.

/pf/federation\_metadata.ping

This endpoint returns SAML and WS-Federation metadata.

The following table shows the HTTP parameters for this endpoint.

| Parameter                 | Description   |
|---------------------------|---|
| <b>PartnerSpId</b>        | The connection ID of the SP to whom the assertions or tokens are issued. This parameter determines the connection for which metadata is generated.  |
| <b>PartnerIdpId</b>       | The connection ID of the IdP issuing the assertions or tokens to be consumed by PingFederate. This parameter determines the connection for which the metadata is generated.   |
| <b>vsid</b><br>(optional) | Specify the virtual server ID.<br>If absent, generates the metadata based on the connection's default virtual server ID, if two or more virtual server IDs are defined, or the federation ID defined on the <b>System # Server # Protocol Settings # Federation Info</b> tab. |

**Note:**

If your partner fails to retrieve metadata when sending both the **PartnerSpId** or the **PartnerIdpId**, and the **vsid** query parameters, perhaps it is only capable of sending one query parameter in such requests. An alternative metadata exchange endpoint that includes the virtual server ID information should resolve the issue.

For more information, see [Constructing an alternative metadata exchange endpoint](#) on page 1272.

## Constructing an alternative metadata exchange endpoint

You can embed virtual server ID information into a security token service (STS) metadata exchange endpoint or a SAML and WS-Federation metadata exchange endpoint.

### About this task

This process is useful for scenarios where partners prefer to retrieve metadata by sending one query parameter such as `asPartnerSpId` or `PartnerIdpId`, instead of two query parameters such as `asPartnerSpId` or `PartnerIdpId` and `vsid`.

### Steps

1. Construct a JSON object containing a key-value pair of the virtual server ID by using the following format.

```
{"vsid": "<VirtualServerIdValue>"}
```

Example:

For example, if the virtual server ID is `Engineering`, the JSON object is

```
{"vsid": "Engineering"}
```

2. Base64url-encode the JSON object.

Example:

For example, if the JSON object is `{"vsid": "Engineering"}`, the base64url-encoded value is `eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ`.

For more information about base64url, see [tools.ietf.org/html/rfc4648](https://tools.ietf.org/html/rfc4648).

3. Insert the base64url-encoded value prefixed with a forward slash into the metadata exchange endpoints, described as follows:

Federation metadata endpoint (`/pf/federation_metadata.ping`)

Between `/pf` and `/federation_metadata.ping`.

STS metadata endpoint (`/pf/sts_mex.ping`)

Between `/pf` and `/sts_mex.ping`.

Example:

For example, if the base64url-encoded value is `eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ`, the metadata exchange endpoints embedding with the virtual server ID are:

Federation metadata endpoint

```
/pf/eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ/federation_metadata.ping
```

Example: `https://idp.example.com:9031/pf/eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ/federation_metadata.ping?PartnerSpId=sp.example.org`

STS metadata endpoint

```
/pf/eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ/sts_mex.ping
```

Example: `https://idp.example.com:9031/pf/eyJ2c2lkIjoiRW5naW5lZXJpbmcfQ/sts_mex.ping?PartnerSpId=sp.example.org`



## Authentication API

The PingFederate authentication API is a JSON-based API that enables end-user interactions, such as credential prompts, to be handled by an external web application. This API does so by providing access to the current state of the flow as an end user steps through a PingFederate authentication policy.

Authentication flows are initiated through browser-based single sign-on (SSO) application endpoints, such as `/idp/startSSO.ping`, or a protocol request, such as an OpenID Connect authentication request received at the authorization endpoint: `/as/authorization.oauth2`. As PingFederate runs the configured authentication policy, if it encounters an API-capable adapter or selector, and an authentication application is configured for the policy, PingFederate redirects to the authentication application's URL, passing the ID of the flow in the `flowId` query parameter.

The authentication application can then retrieve the current state of the flow by issuing a **GET** request to the `/pf-ws/authn/flows/{flowId}` endpoint. The `_links` field in the response lists the available authentication actions that can be performed from the current state. To invoke an action, the authentication application sends a **POST** request to the `/pf-ws/authn/flows/{flowId}` endpoint.

The API client can choose authentication actions using either an `action` query parameter or a custom content type. The `action` query parameter should be used when your networks block custom content types, and is specified using the following format:

```
/pf-ws/authn/flows/<flowId>?action=<actionID>
```

For example, to check username and password, pass the `checkUsernamePassword` action ID through the query parameter as follows:

```
/pf-ws/authn/flows/<flowId>?action=checkUsernamePassword
```

For the custom content type, the action ID is specified using the Content-Type HTTP request header in the following format:

```
application/vnd.pingidentity.<actionId>+json
```

For example, to indicate a username and password check from the HTML Form Adapter, specify the following:

```
application/vnd.pingidentity.checkUsernamePassword+json
```

When the application invokes an action, PingFederate responds either with the next state for the flow or an error.

When the user completes the authentication policy steps successfully, the authentication API returns a `RESUME` status to the authentication application. This status indicates that the API client should redirect the user's browser to the `resumeUrl` specified in the response. PingFederate will then be responsible for the final step in the flow, such as passing a SAML assertion to a partner. A `RESUME` status will also be sent if PingFederate encounters an identity provider (IdP) connection in the policy tree, or an IdP adapter or selector that is not API-capable. When the API client redirects the user, PingFederate will take the steps needed to invoke the authentication source.

If the user has interacted with an authentication application and the flow terminates with an error, the API client will receive a `FAILED` status from the API.



### Note:

To avoid issues with third-party cookies in some browsers, you should give the authentication application the same parent domain as the PingFederate authentication API URL that the application accesses. This could be a common domain of PingFederate's base URL or one of PingFederate's defined virtual hosts.

## Key concepts

### Flow

The SSO transaction invoking the authentication API.

### States

The available states (if any) for a given API-enabled adapter or selector.

### Current state

Indicates what the adapter or selector is ready to do next.

### Actions

The available actions (if any) for a given state.

## Session management

The authentication API endpoint has the same domain as PingFederate's other application endpoints and shares the PingFederate session cookies with those endpoints. This ensures that session data created by API applications can be retrieved when the user interacts with PingFederate's other endpoints and vice versa.



### Note:

Because the authentication API relies on the PingFederate session cookies, only browser-based web applications can currently make use of the API. Server-side web applications are not supported.

In order for PingFederate to manage session cookies correctly, the Javascript-written authentication application must set the `withCredentials` flag on the XMLHttpRequest object to `true`.

To protect against cross-site request forgeries, API clients are also required to include an X-XSRF-Header HTTP request header with each request, for example: `X-XSRF-Header: PingFederate`. This custom header ensures that browsers enforce cross-origin resource sharing (CORS) policies when API requests are sent. This header can have any value.

## Authentication API Explorer

PingFederate includes an API Explorer, which allows you to view the states, actions, and models available for the various API-capable adapters and selectors included in your PingFederate environment. The endpoint for the Authentication API Explorer is `/pf-ws/authn/explorer`.

You can download a Postman collection file from **Authentication # Integration # Authentication API Applications**. The file contains information converted from the Explorer into a Postman collection. You can then import the collection file into the Postman application. The collection file provides every possible action of every state in every plugin deployed in the PingFederate instance. It contains:

- All API-capable plugins, both adapters and selectors, with all of their states and actions
- Pre-populated body containing information about required information types and parameters
- Headers for API calls, both X-XSRF-Header and Content-Type

For more information, see [Exploring the authentication API](#) on page 1275.

## JavaScript widget for the PingFederate authentication API

The JavaScript Widget for the PingFederate authentication API is a customizable JavaScript library that provides the capabilities of the HTML Form Adapter and Identifier First Adapter through the authentication API:

- User Login
- Trouble Signing in
- Trouble with Username
- Password Reset

The widget is a ready-to-use drop-in bundle with CSS and customizable templates. This alternative to the PingFederate templates provides a sign-in experience as a single page application. For more information, go to [JavaScript Widget for the PingFederate Authentication API](#).

## Exploring the authentication API

The **Authentication API Applications** window includes an Authentication API Explorer that lets you view the states, actions, and models available for the various API-capable adapters and selectors included in your PingFederate environment.

### Steps

1. Enable the authentication API and Authentication API Explorer.
  - a. Go to **Authentication # Integration # Authentication API Applications**.
  - b. Select the **Enable Authentication API** check box.
  - c. Select the **Enable API Explorer** check box.
2. Configure an authentication application for the Authentication API Explorer.
  - a. Go to **Authentication # Integration # Authentication API Applications**.
  - b. Click **Add Authentication Application**.
  - c. In the **Authentication Application** window, configure each field as described in the following table.

| Field                             | Description  |
|-----------------------------------|--|
| <b>Name</b>                       | A name of the authentication application, such as <code>Authentication API Explorer</code> .   |
| <b>Description</b>                | An optional description of the authentication application, such as <code>Explore the authentication API!</code>  |
| <b>URL</b>                        | <p>A combination of the PingFederate base URL and the application path / <code>pf-ws/authn/explorer</code>.</p> <p>For example, if the base URL is <code>https://localhost:9031</code>, enter: <code>https://localhost:9031/pf-ws/authn/explorer</code>.</p> <p>You can find your PingFederate base URL at <b>System # Server # Protocol Settings # Federation Info</b>.</p> |
| <b>Additional Allowed Origins</b> | <p>Any additional allowed origins. For more information, see <a href="#">Configuring authentication applications</a> on page 434.</p> <p>If you are using a PingFederate base URL of <code>https://localhost:9031</code> for testing purposes, you can skip this field.</p>  |

- d. In the **Authentication Application** window, click **Save**.
- e. In the **Authentication API Applications** window, click **Save**.

3. In the Authentication API Explorer, view the available states, actions, and models for any API-capable adapter or selector in your PingFederate environment:
  - a. Go to the URL of the Authentication API Explorer, such as <https://localhost:9031/pf-ws/authn/explorer>
  - b. In the **Authentication Adapter/Selector** list, select an authentication adapter or selector.

Result:

The Authentication API Explorer displays a list of states. You can then inspect the following items for any given state:

- The state purpose
- The state data model (if any)
- The available action of actions (if any)
- The action data model (if any) for a given action
- The errors (if any) for a given action

The developers of your web applications use this information to create the desired authentication experience.

4. Explore the authentication API through a request without an authentication policy:
  - a. Configure a use case to use an instance of the HTML Form Adapter for authentication.

For example, you can create an SP connection that uses an instance of the HTML Form Adapter for authentication. For more information, see [Configuring a sample use case](#) on page 248.

- b. Go to **Authentication # Integration # Authentication API Applications**.
- c. In the **Default Authentication Application** list, select the authentication application that represents the Authentication API Explorer. Click **Save**.
- d. Initiate a request supported by the use case.

Result:

When PingFederate receives your request, it determines from your use case that it should invoke the HTML Form Adapter. Because the HTML Form Adapter is API-enabled and you have configured the Authentication API Explorer to be the default authentication application, instead of returning the **Sign On** page (from the HTML Form Adapter), PingFederate redirects the browser to the Authentication API Explorer with a `flowId` query parameter, such as <https://localhost:9031/pf-ws/authn/explorer?flowId=Tt9n7>.

The Authentication API Explorer opens and pre-populates the **Flow ID** field with the flow ID value generated by PingFederate.

- e. In the Authentication API Explorer, click **Get** next to the pre-populated flow ID value.

Result:

The Authentication API Explorer displays a JSON response as the result of the GET request. This response contains information that the web application requires to proceed further. For instance, the `status` parameter value indicates the current state of the request. Because the sample request invokes the HTML Form Adapter, the current state should be `USERNAME_PASSWORD_REQUIRED`.

At the end of the result is a hyperlink to the current state. In this example, when you select the current state link, the Authentication API Explorer jumps to the **USERNAME\_PASSWORD\_REQUIRED** state and expands its contents for further review.

From this point, you can review the state data model and move the request further by selecting the appropriate action and action data, if it's required.

5. Explore the authentication API through a request with an authentication policy:
  - a. Go to **Authentication # Integration # Authentication API Applications**.
  - b. In the **Default Authentication Application** list, select **Select**.  
Result:  
No application is designated as the default authentication application.
  - c. Define an authentication policy to use the Authentication API Explorer:
    1. Go to **Authentication # Policies # Policies**, and click **Add Policy**.
    2. Enter a policy name and optionally a description.
    3. In the **Authentication Application** list, select the authentication application that represents the Authentication API Explorer.
    4. Select the HTML Form Adapter instance that has been mapped to the use case you configured in step **4a**.  
For both the **Fail** and **Success** policy paths, select **Done**.
    5. Click **Done**.
    6. Select the **IdP Authentication Policies** check box.
    7. Click **Save**.
  - d. Initiate a request supported by the use case you configured in step **4a**.
  - e. Use the Authentication API Explorer to learn more about the authentication API.
6. Generate and configure a Postman collection JSON file.
  - a. Go to the **Authentication API Explorer**.
  - b. Click **What is the PingFederate Authentication API?** to expand the top panel
  - c. Click the **Postman Collection** button.  
Result: The **Authentication API Explorer** downloads the Postman collection file.
  - d. Open the Postman application, and import the file.
  - e. In Postman, manually configure the following:
    - The `flowid` collection variable. When PingFederate receives a request, it generates a `flowid`, such as `Tt9n7`, and displays it in the **Flow ID** field on the **Authentication API Explorer** page.
    - The `baseUrl` collection variable. This is the base URL of your Authentication API Explorer, such as `https://localhost:9031`.
    - The PingFederate cookie.

You must also modify the body, if one exists, to ensure that API calls work correctly.

## Mobile application authentication through REST APIs

In PingFederate, you can configure mobile applications to authenticate through REST APIs as OAuth clients without needing to handle HTTP redirections. When authentication is complete, the applications receive an OAuth authorization code, or an access token and possibly an OpenID Connect (OIDC) ID token.

Single-page web applications can also use redirectless mode if administrators configure them in PingFederate as authentication applications. For more information, see [Configuring authentication applications](#) on page 434. Web-based authentication applications must be highly trusted.

Administrators can allow an OAuth client to initiate authorization directly through the authentication API:

1. Go to the client's configuration in the **Client** window.
2. Select the **Allow Authentication API Redirectless Mode** check box.

When enabling this feature, consider the following:

- Redirection URLs are optional, but without a redirection URL, browser-based OAuth flows do not work.

- This flow does not support the user-facing scope consent page, **Request for Approval**.

**Note:**

Enabling this feature automatically enables the **Bypass Authorization Approval** feature and **Restrict Common Scopes** feature.

- The application must manage the PF cookie and, if persistent authentication sessions are configured, the PF.PERSISTENT cookie.

To authenticate with this method, an OAuth client makes two or more API requests:

1. The OAuth client initiates authentication by calling the OAuth 2.0 authorization endpoint `/as/authorization.oauth2` to get a flow ID and other information it needs for the next request. The client must specify the `pi.flow` response mode in this call. See the first request sample below.

**Note:**


If a valid authentication session already exists when the OAuth client makes the first request, the client will receive a response with a token. In this case, the client does not need to make the next request.

2. The client calls the authentication API flow endpoint `/pf-ws/authn/flows/{flow_id}` to get the token. See the [Second request sample](#) below.

**Note:**

In some cases, depending on the configuration of the authentication policy, the client must make more than two requests to get a token.

### Mobile application authentication through REST APIs



### First request sample

```
GET /as/authorization.oauth2?
client_id=im_client&response_type=token&response_mode=pi.flow HTTP/1.1
Host: www.example.com:9031
```

### Sample response 1 to the first request

If a valid authentication session does not already exist, the OAuth client receives a response that provides the information the client needs for the next request (see the second request sample).

```
{
  "id": "PyH5g", // Flow ID
  "pluginTypeId": "7RmQNDWaOnBoudTufx2sEw",
  "status": "USERNAME_PASSWORD_REQUIRED",
  "showRememberMyUsername": false,
  "showThisIsMyDevice": false,
  "thisIsMyDeviceSelected": false,
  "showCaptcha": false,
  "rememberMyUsernameSelected": false,
  "_links": {
    "self": {
      "href": "https://www.example.com:9031/pf-ws/authn/flows/
PyH5g"
    },
    "checkUsernamePassword": {
      "href": "https://www.example.com:9031/pf-ws/authn/flows/
PyH5g"
    }
  }
}
```

```
}
}
```

The `self` link in the response shows that the second request must call the `pf-ws/authn/flows` endpoint instead of the authorization endpoint. The value of the `id` field is the ID of the flow that was created. The client must append the flow ID to the `pf-ws/authn/flows` endpoint for subsequent API requests.

#### Sample response 2 to the first request

If a valid authentication session already exists, the OAuth client receives a response with a token, so the client does not need to make the second request.

```
{
  "id": "PyH5g", // Flow ID
  "pluginTypeId": "7RmQNDWaOnBoudTufx2sEw",
  "status": "COMPLETED",
  "authorizeResponse": {
    "access_token": "000144Qlv9eqpBk03ngAd7M35Gaj41Mgisk",
    "token_type": "Bearer"
  },
  "_links": {
    "self": {
      "href": "https://www.example.com:9031/pf-ws/authn/flows/PyH5g"
    }
  }
}
```

#### Second request sample

```
POST /pf-ws/authn/flows/PyH5g HTTP/1.1
Host: www.example.com:9031
X-XSRF-Header: PingFederate
Content-Type: application/vnd.pingidentity.checkUsernamePassword+json
Cookie: PF=8PgutwFizNS7EoaiB0qVsa
```

```
{
  "username": "joe",
  "password": "Password1"
}
```

#### Sample response to the second request

```
{
  "id": "PyH5g",
  "pluginTypeId": "7RmQNDWaOnBoudTufx2sEw",
  "status": "COMPLETED",
  "authorizeResponse": {
    "access_token": "000144Qlv9eqpBk03ngAd7M35Gaj41Mgisk",
    "token_type": "Bearer"
  },
  "_links": {
    "self": {
      "href": "https://www.example.com:9031/pf-ws/authn/flows/PyH5g"
    }
  }
}
```



## Device authorization through mobile applications

In addition to initiating a regular OAuth authorization flow, mobile applications and single-page web applications can use the authentication API to initiate and complete the user authorization side of the OAuth *device authorization* flow.

There are a few differences between this case and the non-device case:

- You don't need to select **Allow Authentication API Redirectless Mode** on the **Client** window for the OAuth device client because the mobile or single-page web application doesn't receive tokens at the end of the flow.
- For the same reason, in the case of web applications, you don't need to enable **Allow Redirectless Mode** on the **Authentication Application** window when configuring the authentication API application.
- The initial request is made to the user authorization endpoint `/as/user_authz.oauth2` rather than `/as/authorization.oauth2`. As with the non-device flow, you must specify `pi.flow` for the `response_mode`. Optionally, the initial request can also provide the `user_code`. This endpoint doesn't need any other parameters.
- At the end of the flow, the `OAuthDeviceCompleted` state is returned to the API client. This response doesn't include an authorization code or tokens.

As with the non-device flow, you must select **Bypass Authorization Approval** on the **Client** window for the device client because the PingFederate authentication API does not yet support the OAuth consent approval step.

The models and actions for the `OAuthDeviceUserCodeRequired`, `OAuthDeviceUserCodeConfirmationRequired`, and `OAuthDeviceCompleted` states are documented in the *Authentication API Explorer* under the PingFederate Core adapter.

# Index

## A

Assertions [35](#)  
attribute sources  
    custom [952](#)

## C

certificates  
    revocation of [682](#)  
CIAM [108](#)  
Customer IAM [108](#)

## D

directory service  
    SOAP example [1200](#)

## E

Exchange admin center [403](#)

## I

installation  
    federation server [130](#)

## O

Office 365  
    Outlook web app [403](#)  
OpenID Connect [64](#)

## S

SSO [1198](#)  
SSO directory service [1198](#)

## U

uninstalling [136](#)

## W

web services  
    SSO Directory [1198](#)